

Run-Time Library (RTL) :
Reference guide.

Free Pascal version 3.2.4:
Reference guide for RTL units.
Document version 3.2.4
February 2022

Michaël Van Canneyt

Contents

0.1	Overview	140
1	Reference for unit 'BaseUnix'	141
1.1	Used units	141
1.2	Overview	141
1.3	Constants, types and variables	141
1.3.1	Constants	141
1.3.2	Types	166
1.4	Procedures and functions	179
1.4.1	CreateShellArgV	179
1.4.2	FpAccess	179
1.4.3	FpAlarm	180
1.4.4	FpChdir	181
1.4.5	FpChmod	181
1.4.6	FpChown	182
1.4.7	FpClose	183
1.4.8	FpClosedir	184
1.4.9	FpDup	184
1.4.10	FpDup2	185
1.4.11	FpExecv	186
1.4.12	FpExecve	187
1.4.13	FpExit	188
1.4.14	FpFcntl	188
1.4.15	fpdffillset	189
1.4.16	fpFD_CLR	189
1.4.17	fpFD_ISSET	189
1.4.18	fpFD_SET	189
1.4.19	fpFD_ZERO	190
1.4.20	FpFork	190
1.4.21	FPFStat	190
1.4.22	FpFtruncate	191

1.4.23	FpGetcwd	192
1.4.24	FpGetegid	192
1.4.25	FpGetEnv	192
1.4.26	fpgeterno	193
1.4.27	FpGeteuid	193
1.4.28	FpGetgid	194
1.4.29	FpGetgroups	194
1.4.30	FpGetpggrp	194
1.4.31	FpGetpid	195
1.4.32	FpGetppid	195
1.4.33	fpGetPriority	196
1.4.34	FpGetRLimit	196
1.4.35	FpGetsid	196
1.4.36	FpGetuid	197
1.4.37	FpIOCtl	197
1.4.38	FpKill	198
1.4.39	FpLink	198
1.4.40	FpLseek	199
1.4.41	fpLstat	200
1.4.42	FpMkdir	201
1.4.43	FpMkfifo	202
1.4.44	Fp mmap	202
1.4.45	Fp mprotect	203
1.4.46	Fp munmap	204
1.4.47	FpNanoSleep	204
1.4.48	fpNice	205
1.4.49	FpOpen	206
1.4.50	FpOpendir	207
1.4.51	FpPause	208
1.4.52	FpPipe	208
1.4.53	FpPoll	209
1.4.54	FppRead	209
1.4.55	FppWrite	210
1.4.56	FpRead	210
1.4.57	FpReaddir	211
1.4.58	fpReadLink	211
1.4.59	FpReadV	213
1.4.60	FpRename	213
1.4.61	FpRmdir	214
1.4.62	fpSelect	214

1.4.63	fpseterno	215
1.4.64	FpSetgid	216
1.4.65	fpSetPriority	216
1.4.66	FpSetRLimit	216
1.4.67	FpSetsid	217
1.4.68	fpsettimeofday	217
1.4.69	FpSetuid	217
1.4.70	FPSigaction	218
1.4.71	FpSigAddSet	219
1.4.72	FpSigDelSet	219
1.4.73	FpsigEmptySet	219
1.4.74	FpSigFillSet	220
1.4.75	FpSigIsMember	220
1.4.76	FpSignal	220
1.4.77	FpSigPending	221
1.4.78	FpSigProcMask	221
1.4.79	FpSigSuspend	222
1.4.80	FpSigTimedWait	222
1.4.81	FpSleep	222
1.4.82	FpStat	223
1.4.83	fpSymlink	224
1.4.84	fpS_ISBLK	225
1.4.85	fpS_ISCHR	225
1.4.86	fpS_ISDIR	226
1.4.87	fpS_ISFIFO	226
1.4.88	fpS_ISLNK	226
1.4.89	fpS_ISREG	227
1.4.90	fpS_ISSOCK	227
1.4.91	fpTime	227
1.4.92	FpTimes	228
1.4.93	FpUmask	228
1.4.94	FpUname	229
1.4.95	FpUnlink	229
1.4.96	FpUtime	229
1.4.97	FpWait	230
1.4.98	FpWaitPid	231
1.4.99	FpWrite	231
1.4.100	FpWriteV	232
1.4.101	FreeShellArgV	232
1.4.102	wexitStatus	232

1.4.103	wifexited	232
1.4.104	wifsignaled	233
1.4.105	wstopsig	233
1.4.106	wtermSIG	233
1.5	Dir	233
1.6	Dirent	234
1.7	FLock	234
1.8	iovec	234
1.9	pollfd	234
1.10	sigactionrec	235
1.11	Stat	235
1.12	tfpreg	235
1.13	tfpstate	236
1.14	tfpxreg	236
1.15	tfpx_sw_bytes	237
1.16	timezone	237
1.17	tms	237
1.18	TRLimit	237
1.19	tsigaltstack	238
1.20	TSigContext	238
1.21	tsiginfo	239
1.22	TUcontext	240
1.23	txmmreg	240
1.24	UTimBuf	240
1.25	UtsName	241
2	Reference for unit 'Character'	242
2.1	Used units	242
2.2	Overview	242
2.3	Constants, types and variables	242
2.3.1	Types	242
2.4	Procedures and functions	244
2.4.1	ConvertFromUtf32	244
2.4.2	ConvertToUtf32	245
2.4.3	GetNumericValue	245
2.4.4	GetUnicodeCategory	245
2.4.5	IsControl	246
2.4.6	IsDigit	246
2.4.7	IsHighSurrogate	246
2.4.8	IsLetter	246

2.4.9	IsLetterOrDigit	247
2.4.10	IsLower	247
2.4.11	IsLowSurrogate	247
2.4.12	IsNumber	247
2.4.13	IsPunctuation	248
2.4.14	IsSeparator	248
2.4.15	IsSurrogate	248
2.4.16	IsSurrogatePair	248
2.4.17	IsSymbol	249
2.4.18	IsUpper	249
2.4.19	IsWhiteSpace	249
2.4.20	ToLower	249
2.4.21	ToUpper	250
2.5	TCharacter	250
2.5.1	Description	250
2.5.2	Method overview	250
2.5.3	TCharacter.Create	250
2.5.4	TCharacter.ConvertFromUtf32	251
2.5.5	TCharacter.ConvertToUtf32	251
2.5.6	TCharacter.GetNumericValue	252
2.5.7	TCharacter.GetUnicodeCategory	252
2.5.8	TCharacter.IsControl	252
2.5.9	TCharacter.IsDigit	253
2.5.10	TCharacter.IsSurrogate	253
2.5.11	TCharacter.IsHighSurrogate	254
2.5.12	TCharacter.IsLowSurrogate	254
2.5.13	TCharacter.IsSurrogatePair	254
2.5.14	TCharacter.IsLetter	255
2.5.15	TCharacter.IsLetterOrDigit	255
2.5.16	TCharacter.IsLower	256
2.5.17	TCharacter.IsNumber	256
2.5.18	TCharacter.IsPunctuation	257
2.5.19	TCharacter.IsSeparator	257
2.5.20	TCharacter.IsSymbol	257
2.5.21	TCharacter.IsUpper	258
2.5.22	TCharacter.IsWhiteSpace	258
2.5.23	TCharacter.ToLower	259
2.5.24	TCharacter.ToUpper	259

3 Reference for unit 'charset'

260

3.1	Used units	260
3.2	Overview	260
3.3	Constants, types and variables	260
3.3.1	Constants	260
3.3.2	Types	260
3.4	Procedures and functions	261
3.4.1	getascii	261
3.4.2	getmap	262
3.4.3	getunicode	262
3.4.4	loadbinaryunicodemapping	262
3.4.5	loadunicodemapping	263
3.4.6	mappingavailable	263
3.4.7	registerbinarymapping	263
3.4.8	registermapping	264
3.5	reversecharmapping	264
3.6	TSerializedMapHeader	264
3.7	tunicodecharmapping	264
3.8	tunicodemap	265
4	Reference for unit 'Classes'	266
4.1	Used units	266
4.2	Overview	266
4.3	Constants, types and variables	266
4.3.1	Constants	266
4.3.2	Types	269
4.3.3	Variables	286
4.4	Procedures and functions	287
4.4.1	ActivateClassGroup	287
4.4.2	BeginGlobalLoading	288
4.4.3	BinToHex	288
4.4.4	Bounds	288
4.4.5	CheckSynchronize	288
4.4.6	ClassGroupOf	289
4.4.7	CollectionsEqual	289
4.4.8	EndGlobalLoading	289
4.4.9	ExtractStrings	289
4.4.10	FindClass	290
4.4.11	FindGlobalComponent	290
4.4.12	FindIdentToInt	290
4.4.13	FindIntToIdent	291

4.4.14	FindNestedComponent	291
4.4.15	GetClass	291
4.4.16	GetFixupInstanceNames	291
4.4.17	GetFixupReferenceNames	292
4.4.18	GlobalFixupReferences	292
4.4.19	GroupDescendentsWith	292
4.4.20	HexToBin	292
4.4.21	IdentToInt	293
4.4.22	InitComponentRes	293
4.4.23	InitInheritedComponent	293
4.4.24	IntToIdent	293
4.4.25	InvalidPoint	294
4.4.26	LineStart	294
4.4.27	NotifyGlobalLoading	294
4.4.28	ObjectBinaryToText	294
4.4.29	ObjectResourceToText	295
4.4.30	ObjectTextToBinary	295
4.4.31	ObjectTextToResource	295
4.4.32	Point	295
4.4.33	PointsEqual	295
4.4.34	ReadComponentRes	296
4.4.35	ReadComponentResEx	296
4.4.36	ReadComponentResFile	296
4.4.37	Rect	297
4.4.38	RedirectFixupReferences	297
4.4.39	RegisterClass	297
4.4.40	RegisterClassAlias	297
4.4.41	RegisterClasses	298
4.4.42	RegisterComponents	298
4.4.43	RegisterFindGlobalComponentProc	298
4.4.44	RegisterInitComponentHandler	298
4.4.45	RegisterIntegerConsts	299
4.4.46	RegisterNoIcon	299
4.4.47	RegisterNonActiveX	299
4.4.48	RemoveFixupReferences	300
4.4.49	RemoveFixups	300
4.4.50	SmallPoint	300
4.4.51	StartClassGroup	300
4.4.52	UnRegisterClass	301
4.4.53	UnRegisterClasses	301

4.4.54	UnregisterFindGlobalComponentProc	301
4.4.55	UnRegisterModuleClasses	301
4.4.56	WriteComponentResFile	302
4.5	TIdentMapEntry	302
4.6	TStringItem	302
4.7	EBitsError	302
4.7.1	Description	302
4.8	EClassNotFound	302
4.8.1	Description	302
4.9	EComponentError	303
4.9.1	Description	303
4.10	EFCreateError	303
4.10.1	Description	303
4.11	EFileError	303
4.11.1	Description	303
4.12	EFOpenError	303
4.12.1	Description	303
4.13	EInvalidImage	303
4.13.1	Description	303
4.14	EInvalidOperation	304
4.14.1	Description	304
4.15	EListError	304
4.15.1	Description	304
4.16	EMethodNotFound	304
4.16.1	Description	304
4.17	EObserver	304
4.17.1	Description	304
4.18	EOutOfResources	304
4.18.1	Description	304
4.19	EParseError	305
4.19.1	Description	305
4.20	EReadError	305
4.20.1	Description	305
4.21	EResNotFound	305
4.21.1	Description	305
4.22	EStreamError	305
4.22.1	Description	305
4.23	EStringListError	306
4.23.1	Description	306
4.24	EThread	306

4.24.1	Description	306
4.25	EThreadDestroyCalled	306
4.25.1	Description	306
4.26	EThreadExternalException	306
4.26.1	Description	306
4.27	EWriteError	306
4.27.1	Description	306
4.28	IDesignerNotify	307
4.28.1	Description	307
4.28.2	Method overview	307
4.28.3	IDesignerNotify.Modified	307
4.28.4	IDesignerNotify.Notification	307
4.29	IFPObserved	307
4.29.1	Description	307
4.29.2	Method overview	308
4.29.3	IFPObserved.FPOAttachObserver	308
4.29.4	IFPObserved.FPODetachObserver	308
4.29.5	IFPObserved.FPONotifyObservers	308
4.30	IFPObserver	309
4.30.1	Description	309
4.30.2	Method overview	309
4.30.3	IFPObserver.FPOObservedChanged	309
4.31	IInterfaceComponentReference	309
4.31.1	Description	309
4.31.2	Method overview	310
4.31.3	IInterfaceComponentReference.GetComponent	310
4.32	IInterfaceList	310
4.32.1	Description	310
4.32.2	Method overview	310
4.32.3	Property overview	311
4.32.4	IInterfaceList.Get	311
4.32.5	IInterfaceList.GetCapacity	311
4.32.6	IInterfaceList.GetCount	311
4.32.7	IInterfaceList.Put	311
4.32.8	IInterfaceList.SetCapacity	312
4.32.9	IInterfaceList.SetCount	312
4.32.10	IInterfaceList.Clear	312
4.32.11	IInterfaceList.Delete	312
4.32.12	IInterfaceList.Exchange	313
4.32.13	IInterfaceList.First	313

4.32.14	IInterfaceList.IndexOf	313
4.32.15	IInterfaceList.Add	313
4.32.16	IInterfaceList.Insert	313
4.32.17	IInterfaceList.Last	314
4.32.18	IInterfaceList.Remove	314
4.32.19	IInterfaceList.Lock	314
4.32.20	IInterfaceList.Unlock	314
4.32.21	IInterfaceList.Capacity	314
4.32.22	IInterfaceList.Count	315
4.32.23	IInterfaceList.Items	315
4.33	IStreamPersist	315
4.33.1	Description	315
4.33.2	Method overview	315
4.33.3	IStreamPersist.LoadFromStream	316
4.33.4	IStreamPersist.SaveToStream	316
4.34	IStringsAdapter	316
4.34.1	Description	316
4.34.2	Method overview	316
4.34.3	IStringsAdapter.ReferenceStrings	316
4.34.4	IStringsAdapter.ReleaseStrings	316
4.35	IVCLComObject	317
4.35.1	Description	317
4.35.2	Method overview	317
4.35.3	IVCLComObject.GetTypeInfoCount	317
4.35.4	IVCLComObject.GetTypeInfo	317
4.35.5	IVCLComObject.GetIDsOfNames	318
4.35.6	IVCLComObject.Invoke	318
4.35.7	IVCLComObject.SafeCallException	318
4.35.8	IVCLComObject.FreeOnRelease	318
4.36	TAbstractObjectReader	319
4.36.1	Description	319
4.36.2	Method overview	319
4.36.3	TAbstractObjectReader.FlushBuffer	319
4.36.4	TAbstractObjectReader.NextValue	320
4.36.5	TAbstractObjectReader.ReadValue	320
4.36.6	TAbstractObjectReader.BeginRootComponent	320
4.36.7	TAbstractObjectReader.BeginComponent	320
4.36.8	TAbstractObjectReader.BeginProperty	321
4.36.9	TAbstractObjectReader.Read	321
4.36.10	TAbstractObjectReader.ReadBinary	321

4.36.11	TAbstractObjectReader.ReadFloat	322
4.36.12	TAbstractObjectReader.ReadSingle	322
4.36.13	TAbstractObjectReader.ReadDate	322
4.36.14	TAbstractObjectReader.ReadCurrency	323
4.36.15	TAbstractObjectReader.ReadIdent	323
4.36.16	TAbstractObjectReader.ReadInt8	323
4.36.17	TAbstractObjectReader.ReadInt16	324
4.36.18	TAbstractObjectReader.ReadInt32	324
4.36.19	TAbstractObjectReader.ReadInt64	324
4.36.20	TAbstractObjectReader.ReadSet	325
4.36.21	TAbstractObjectReader.ReadSignature	325
4.36.22	TAbstractObjectReader.ReadStr	325
4.36.23	TAbstractObjectReader.ReadString	326
4.36.24	TAbstractObjectReader.ReadWideString	326
4.36.25	TAbstractObjectReader.ReadUnicodeString	326
4.36.26	TAbstractObjectReader.SkipComponent	326
4.36.27	TAbstractObjectReader.SkipValue	327
4.37	TAbstractObjectWriter	327
4.37.1	Description	327
4.37.2	Method overview	327
4.37.3	TAbstractObjectWriter.BeginCollection	327
4.37.4	TAbstractObjectWriter.BeginComponent	328
4.37.5	TAbstractObjectWriter.WriteSignature	328
4.37.6	TAbstractObjectWriter.BeginList	328
4.37.7	TAbstractObjectWriter.EndList	328
4.37.8	TAbstractObjectWriter.BeginProperty	328
4.37.9	TAbstractObjectWriter.EndProperty	329
4.37.10	TAbstractObjectWriter.FlushBuffer	329
4.37.11	TAbstractObjectWriter.Write	329
4.37.12	TAbstractObjectWriter.WriteBinary	329
4.37.13	TAbstractObjectWriter.WriteBoolean	329
4.37.14	TAbstractObjectWriter.WriteFloat	330
4.37.15	TAbstractObjectWriter.WriteSingle	330
4.37.16	TAbstractObjectWriter.WriteDate	330
4.37.17	TAbstractObjectWriter.WriteCurrency	330
4.37.18	TAbstractObjectWriter.WriteIdent	330
4.37.19	TAbstractObjectWriter.WriteInteger	331
4.37.20	TAbstractObjectWriter.WriteUInt64	331
4.37.21	TAbstractObjectWriter.WriteVariant	331
4.37.22	TAbstractObjectWriter.WriteMethodName	331

4.37.23	TAbstractObjectWriter.WriteSet	331
4.37.24	TAbstractObjectWriter.WriteString	332
4.37.25	TAbstractObjectWriter.WriteWideString	332
4.37.26	TAbstractObjectWriter.WriteUnicodeString	332
4.38	TBasicAction	332
4.38.1	Description	332
4.38.2	Method overview	333
4.38.3	Property overview	333
4.38.4	TBasicAction.Create	333
4.38.5	TBasicAction.Destroy	333
4.38.6	TBasicAction.HandlesTarget	333
4.38.7	TBasicAction.UpdateTarget	334
4.38.8	TBasicAction.ExecuteTarget	334
4.38.9	TBasicAction.Execute	334
4.38.10	TBasicAction.RegisterChanges	335
4.38.11	TBasicAction.UnRegisterChanges	335
4.38.12	TBasicAction.Update	335
4.38.13	TBasicAction.ActionComponent	335
4.38.14	TBasicAction.OnExecute	336
4.38.15	TBasicAction.OnUpdate	336
4.39	TBasicActionLink	336
4.39.1	Description	336
4.39.2	Method overview	336
4.39.3	Property overview	337
4.39.4	TBasicActionLink.Create	337
4.39.5	TBasicActionLink.Destroy	337
4.39.6	TBasicActionLink.Execute	337
4.39.7	TBasicActionLink.Update	338
4.39.8	TBasicActionLink.Action	338
4.39.9	TBasicActionLink.OnChange	338
4.40	TBinaryObjectReader	338
4.40.1	Description	338
4.40.2	Method overview	339
4.40.3	TBinaryObjectReader.Create	339
4.40.4	TBinaryObjectReader.Destroy	339
4.40.5	TBinaryObjectReader.NextValue	340
4.40.6	TBinaryObjectReader.ReadValue	340
4.40.7	TBinaryObjectReader.BeginRootComponent	340
4.40.8	TBinaryObjectReader.BeginComponent	340
4.40.9	TBinaryObjectReader.BeginProperty	341

4.40.10	TBinaryObjectReader.Read	341
4.40.11	TBinaryObjectReader.ReadBinary	341
4.40.12	TBinaryObjectReader.ReadFloat	341
4.40.13	TBinaryObjectReader.ReadSingle	341
4.40.14	TBinaryObjectReader.ReadDate	342
4.40.15	TBinaryObjectReader.ReadCurrency	342
4.40.16	TBinaryObjectReader.ReadIdent	342
4.40.17	TBinaryObjectReader.ReadInt8	342
4.40.18	TBinaryObjectReader.ReadInt16	342
4.40.19	TBinaryObjectReader.ReadInt32	343
4.40.20	TBinaryObjectReader.ReadInt64	343
4.40.21	TBinaryObjectReader.ReadSet	343
4.40.22	TBinaryObjectReader.ReadSignature	343
4.40.23	TBinaryObjectReader.ReadStr	344
4.40.24	TBinaryObjectReader.ReadString	344
4.40.25	TBinaryObjectReader.ReadWideString	344
4.40.26	TBinaryObjectReader.ReadUnicodeString	344
4.40.27	TBinaryObjectReader.SkipComponent	345
4.40.28	TBinaryObjectReader.SkipValue	345
4.41	TBinaryObjectWriter	345
4.41.1	Description	345
4.41.2	Method overview	346
4.41.3	TBinaryObjectWriter.Create	346
4.41.4	TBinaryObjectWriter.Destroy	346
4.41.5	TBinaryObjectWriter.WriteSignature	346
4.41.6	TBinaryObjectWriter.FlushBuffer	347
4.41.7	TBinaryObjectWriter.BeginCollection	347
4.41.8	TBinaryObjectWriter.BeginComponent	347
4.41.9	TBinaryObjectWriter.BeginList	347
4.41.10	TBinaryObjectWriter.EndList	347
4.41.11	TBinaryObjectWriter.BeginProperty	348
4.41.12	TBinaryObjectWriter.EndProperty	348
4.41.13	TBinaryObjectWriter.Write	348
4.41.14	TBinaryObjectWriter.WriteBinary	348
4.41.15	TBinaryObjectWriter.WriteBoolean	348
4.41.16	TBinaryObjectWriter.WriteFloat	348
4.41.17	TBinaryObjectWriter.WriteSingle	349
4.41.18	TBinaryObjectWriter.WriteDate	349
4.41.19	TBinaryObjectWriter.WriteCurrency	349
4.41.20	TBinaryObjectWriter.WriteIdent	349

4.41.21	TBinaryObjectWriter.WriteInteger	349
4.41.22	TBinaryObjectWriter.WriteUInt64	349
4.41.23	TBinaryObjectWriter.WriteMethodName	350
4.41.24	TBinaryObjectWriter.WriteSet	350
4.41.25	TBinaryObjectWriter.WriteString	350
4.41.26	TBinaryObjectWriter.WriteString	350
4.41.27	TBinaryObjectWriter.WriteString	350
4.41.28	TBinaryObjectWriter.WriteString	350
4.41.29	TBinaryObjectWriter.WriteString	351
4.42	TBits	351
4.42.1	Description	351
4.42.2	Method overview	351
4.42.3	Property overview	351
4.42.4	TBits.Create	352
4.42.5	TBits.Destroy	352
4.42.6	TBits.GetFSize	352
4.42.7	TBits.SetOn	352
4.42.8	TBits.Clear	353
4.42.9	TBits.Clearall	353
4.42.10	TBits.CopyBits	353
4.42.11	TBits.AndBits	353
4.42.12	TBits.OrBits	354
4.42.13	TBits.XorBits	354
4.42.14	TBits.NotBits	354
4.42.15	TBits.Get	355
4.42.16	TBits.Grow	355
4.42.17	TBits.Equals	355
4.42.18	TBits.SetIndex	355
4.42.19	TBits.FindFirstBit	356
4.42.20	TBits.FindNextBit	356
4.42.21	TBits.FindPrevBit	356
4.42.22	TBits.OpenBit	357
4.42.23	TBits.Bits	357
4.42.24	TBits.Size	357
4.43	TBytesStream	357
4.43.1	Description	357
4.43.2	Method overview	358
4.43.3	Property overview	358
4.43.4	TBytesStream.Create	358
4.43.5	TBytesStream.Bytes	358

4.44	TCollection	358
4.44.1	Description	358
4.44.2	Method overview	359
4.44.3	Property overview	359
4.44.4	TCollection.Create	359
4.44.5	TCollection.Destroy	359
4.44.6	TCollection.Owner	360
4.44.7	TCollection.Add	360
4.44.8	TCollection.Assign	360
4.44.9	TCollection.BeginUpdate	360
4.44.10	TCollection.Clear	361
4.44.11	TCollection.EndUpdate	361
4.44.12	TCollection.Delete	361
4.44.13	TCollection.GetEnumerator	362
4.44.14	TCollection.GetNamePath	362
4.44.15	TCollection.Insert	362
4.44.16	TCollection.FindItemID	362
4.44.17	TCollection.Exchange	363
4.44.18	TCollection.Move	363
4.44.19	TCollection.Sort	363
4.44.20	TCollection.Count	364
4.44.21	TCollection.ItemClass	364
4.44.22	TCollection.Items	364
4.45	TCollectionEnumerator	365
4.45.1	Description	365
4.45.2	Method overview	365
4.45.3	Property overview	365
4.45.4	TCollectionEnumerator.Create	365
4.45.5	TCollectionEnumerator.GetCurrent	365
4.45.6	TCollectionEnumerator.MoveNext	365
4.45.7	TCollectionEnumerator.Current	366
4.46	TCollectionItem	366
4.46.1	Description	366
4.46.2	Method overview	366
4.46.3	Property overview	366
4.46.4	TCollectionItem.Create	367
4.46.5	TCollectionItem.Destroy	367
4.46.6	TCollectionItem.GetNamePath	367
4.46.7	TCollectionItem.Collection	367
4.46.8	TCollectionItem.ID	368

4.46.9	TCollectionItem.Index	368
4.46.10	TCollectionItem.DisplayName	368
4.47	TComponent	369
4.47.1	Description	369
4.47.2	Interfaces overview	369
4.47.3	Method overview	369
4.47.4	Property overview	370
4.47.5	TComponent.Notification	370
4.47.6	TComponent.WriteState	370
4.47.7	TComponent.Create	371
4.47.8	TComponent.Destroy	371
4.47.9	TComponent.BeforeDestruction	371
4.47.10	TComponent.DestroyComponents	371
4.47.11	TComponent.Destroying	372
4.47.12	TComponent.ExecuteAction	372
4.47.13	TComponent.FindComponent	372
4.47.14	TComponent.FreeNotification	372
4.47.15	TComponent.RemoveFreeNotification	373
4.47.16	TComponent.FreeOnRelease	373
4.47.17	TComponent.GetEnumerator	373
4.47.18	TComponent.GetNamePath	373
4.47.19	TComponent.GetParentComponent	373
4.47.20	TComponent.HasParent	374
4.47.21	TComponent.InsertComponent	374
4.47.22	TComponent.RemoveComponent	374
4.47.23	TComponent.SafeCallException	374
4.47.24	TComponent.SetSubComponent	375
4.47.25	TComponent.UpdateAction	375
4.47.26	TComponent.IsImplementorOf	375
4.47.27	TComponent.ReferenceInterface	375
4.47.28	TComponent.ComObject	376
4.47.29	TComponent.Components	376
4.47.30	TComponent.ComponentCount	376
4.47.31	TComponent.ComponentIndex	376
4.47.32	TComponent.ComponentState	377
4.47.33	TComponent.ComponentStyle	377
4.47.34	TComponent.DesignInfo	377
4.47.35	TComponent.Owner	378
4.47.36	TComponent.VCLComObject	378
4.47.37	TComponent.Name	378

4.47.38	TComponent.Tag	378
4.48	TComponentEnumerator	379
4.48.1	Description	379
4.48.2	Method overview	379
4.48.3	Property overview	379
4.48.4	TComponentEnumerator.Create	379
4.48.5	TComponentEnumerator.GetCurrent	379
4.48.6	TComponentEnumerator.MoveNext	380
4.48.7	TComponentEnumerator.Current	380
4.49	TCustomMemoryStream	380
4.49.1	Description	380
4.49.2	Method overview	380
4.49.3	Property overview	381
4.49.4	TCustomMemoryStream.Read	381
4.49.5	TCustomMemoryStream.Seek	381
4.49.6	TCustomMemoryStream.SaveToStream	381
4.49.7	TCustomMemoryStream.SaveToFile	382
4.49.8	TCustomMemoryStream.Memory	382
4.50	TDataModule	382
4.50.1	Description	382
4.50.2	Method overview	383
4.50.3	Property overview	383
4.50.4	TDataModule.Create	383
4.50.5	TDataModule.CreateNew	383
4.50.6	TDataModule.Destroy	384
4.50.7	TDataModule.AfterConstruction	384
4.50.8	TDataModule.BeforeDestruction	384
4.50.9	TDataModule.DesignOffset	384
4.50.10	TDataModule.DesignSize	385
4.50.11	TDataModule.DesignPPI	385
4.50.12	TDataModule.OnCreate	385
4.50.13	TDataModule.OnDestroy	385
4.50.14	TDataModule.OldCreateOrder	386
4.51	TFile	386
4.51.1	Description	386
4.51.2	Method overview	386
4.51.3	Property overview	386
4.51.4	TFile.DefineProperty	386
4.51.5	TFile.DefineBinaryProperty	387
4.51.6	TFile.FlushBuffer	387

4.51.7	TFile.Root	387
4.51.8	TFile.LookupRoot	387
4.51.9	TFile.Ancestor	388
4.51.10	TFile.IgnoreChildren	388
4.52	TFileStream	388
4.52.1	Description	388
4.52.2	Method overview	388
4.52.3	Property overview	388
4.52.4	TFileStream.Create	389
4.52.5	TFileStream.Destroy	389
4.52.6	TFileStream.FileName	390
4.53	TFPList	390
4.53.1	Description	390
4.53.2	Method overview	390
4.53.3	Property overview	391
4.53.4	TFPList.Destroy	391
4.53.5	TFPList.AddList	391
4.53.6	TFPList.Add	391
4.53.7	TFPList.Clear	391
4.53.8	TFPList.Delete	392
4.53.9	TFPList.Error	392
4.53.10	TFPList.Exchange	392
4.53.11	TFPList.Expand	392
4.53.12	TFPList.Extract	393
4.53.13	TFPList.First	393
4.53.14	TFPList.GetEnumerator	393
4.53.15	TFPList.IndexOf	393
4.53.16	TFPList.IndexOfItem	394
4.53.17	TFPList.Insert	394
4.53.18	TFPList.Last	394
4.53.19	TFPList.Move	394
4.53.20	TFPList.Assign	395
4.53.21	TFPList.Remove	395
4.53.22	TFPList.Pack	395
4.53.23	TFPList.Sort	395
4.53.24	TFPList.ForEachCall	396
4.53.25	TFPList.Capacity	396
4.53.26	TFPList.Count	396
4.53.27	TFPList.Items	397
4.53.28	TFPList.List	397

4.54	TFPListEnumerator	397
4.54.1	Description	397
4.54.2	Method overview	397
4.54.3	Property overview	397
4.54.4	TFPListEnumerator.Create	397
4.54.5	TFPListEnumerator.GetCurrent	398
4.54.6	TFPListEnumerator.MoveNext	398
4.54.7	TFPListEnumerator.Current	398
4.55	THandleStream	399
4.55.1	Description	399
4.55.2	Method overview	399
4.55.3	Property overview	399
4.55.4	THandleStream.Create	399
4.55.5	THandleStream.Read	399
4.55.6	THandleStream.Write	400
4.55.7	THandleStream.Seek	400
4.55.8	THandleStream.Handle	400
4.56	TInterfacedPersistent	401
4.56.1	Description	401
4.56.2	Interfaces overview	401
4.56.3	Method overview	401
4.56.4	TInterfacedPersistent.QueryInterface	401
4.56.5	TInterfacedPersistent.AfterConstruction	401
4.57	TInterfaceList	401
4.57.1	Description	401
4.57.2	Interfaces overview	402
4.57.3	Method overview	402
4.57.4	Property overview	402
4.57.5	TInterfaceList.Create	402
4.57.6	TInterfaceList.Destroy	402
4.57.7	TInterfaceList.Clear	403
4.57.8	TInterfaceList.Delete	403
4.57.9	TInterfaceList.Exchange	403
4.57.10	TInterfaceList.First	403
4.57.11	TInterfaceList.GetEnumerator	404
4.57.12	TInterfaceList.IndexOf	404
4.57.13	TInterfaceList.Add	404
4.57.14	TInterfaceList.Insert	404
4.57.15	TInterfaceList.Last	405
4.57.16	TInterfaceList.Remove	405

4.57.17	TInterfaceList.Lock	405
4.57.18	TInterfaceList.Unlock	405
4.57.19	TInterfaceList.Expand	406
4.57.20	TInterfaceList.Capacity	406
4.57.21	TInterfaceList.Count	406
4.57.22	TInterfaceList.Items	406
4.58	TInterfaceListEnumerator	407
4.58.1	Description	407
4.58.2	Method overview	407
4.58.3	Property overview	407
4.58.4	TInterfaceListEnumerator.Create	407
4.58.5	TInterfaceListEnumerator.GetCurrent	407
4.58.6	TInterfaceListEnumerator.MoveNext	408
4.58.7	TInterfaceListEnumerator.Current	408
4.59	TList	408
4.59.1	Description	408
4.59.2	Interfaces overview	408
4.59.3	Method overview	409
4.59.4	Property overview	409
4.59.5	TList.Create	409
4.59.6	TList.Destroy	409
4.59.7	TList.FPOAttachObserver	410
4.59.8	TList.FPODetachObserver	410
4.59.9	TList.FPONotifyObservers	410
4.59.10	TList.AddList	411
4.59.11	TList.Add	411
4.59.12	TList.Clear	411
4.59.13	TList.Delete	411
4.59.14	TList.Error	412
4.59.15	TList.Exchange	412
4.59.16	TList.Expand	412
4.59.17	TList.Extract	412
4.59.18	TList.First	413
4.59.19	TList.GetEnumerator	413
4.59.20	TList.IndexOf	413
4.59.21	TList.Insert	413
4.59.22	TList.Last	414
4.59.23	TList.Move	414
4.59.24	TList.Assign	414
4.59.25	TList.Remove	414

4.59.26	TList.Pack	415
4.59.27	TList.Sort	415
4.59.28	TList.Capacity	415
4.59.29	TList.Count	416
4.59.30	TList.Items	416
4.59.31	TList.List	416
4.60	TListEnumerator	416
4.60.1	Description	416
4.60.2	Method overview	416
4.60.3	Property overview	417
4.60.4	TListEnumerator.Create	417
4.60.5	TListEnumerator.GetCurrent	417
4.60.6	TListEnumerator.MoveNext	417
4.60.7	TListEnumerator.Current	417
4.61	TMemoryStream	418
4.61.1	Description	418
4.61.2	Method overview	418
4.61.3	TMemoryStream.Destroy	418
4.61.4	TMemoryStream.Clear	418
4.61.5	TMemoryStream.LoadFromStream	418
4.61.6	TMemoryStream.LoadFromFile	419
4.61.7	TMemoryStream.SetSize	419
4.61.8	TMemoryStream.Write	419
4.62	TOwnedCollection	420
4.62.1	Description	420
4.62.2	Method overview	420
4.62.3	TOwnedCollection.Create	420
4.63	TOwnerStream	420
4.63.1	Description	420
4.63.2	Method overview	421
4.63.3	Property overview	421
4.63.4	TOwnerStream.Create	421
4.63.5	TOwnerStream.Destroy	421
4.63.6	TOwnerStream.Source	421
4.63.7	TOwnerStream.SourceOwner	422
4.64	TParser	422
4.64.1	Description	422
4.64.2	Method overview	422
4.64.3	Property overview	423
4.64.4	TParser.Create	423

4.64.5	TParser.Destroy	423
4.64.6	TParser.CheckToken	423
4.64.7	TParser.CheckTokenSymbol	423
4.64.8	TParser.Error	424
4.64.9	TParser.ErrorFmt	424
4.64.10	TParser.ErrorStr	424
4.64.11	TParser.HexToBinary	424
4.64.12	TParser.NextToken	425
4.64.13	TParser.SourcePos	425
4.64.14	TParser.TokenComponentIdent	425
4.64.15	TParser.TokenFloat	426
4.64.16	TParser.TokenInt	426
4.64.17	TParser.TokenString	426
4.64.18	TParser.TokenWideString	427
4.64.19	TParser.TokenSymbolIs	427
4.64.20	TParser.FloatType	427
4.64.21	TParser.SourceLine	428
4.64.22	TParser.Token	428
4.65	TPersistent	428
4.65.1	Description	428
4.65.2	Interfaces overview	429
4.65.3	Method overview	429
4.65.4	TPersistent.Destroy	429
4.65.5	TPersistent.Assign	429
4.65.6	TPersistent.FPOAttachObserver	430
4.65.7	TPersistent.FPODetachObserver	430
4.65.8	TPersistent.FPONotifyObservers	430
4.65.9	TPersistent.GetNamePath	430
4.66	TProxyStream	431
4.66.1	Description	431
4.66.2	Method overview	431
4.66.3	TProxyStream.Create	431
4.66.4	TProxyStream.Read	431
4.66.5	TProxyStream.Write	431
4.66.6	TProxyStream.Seek	431
4.66.7	TProxyStream.Check	432
4.67	TRawByteStringStream	432
4.67.1	Description	432
4.67.2	Method overview	432
4.67.3	TRawByteStringStream.Create	432

4.67.4	TRawByteStringStream.DataString	432
4.67.5	TRawByteStringStream.ReadString	433
4.67.6	TRawByteStringStream.WriteString	433
4.68	TReader	433
4.68.1	Description	433
4.68.2	Method overview	434
4.68.3	Property overview	435
4.68.4	TReader.Create	435
4.68.5	TReader.Destroy	435
4.68.6	TReader.FlushBuffer	435
4.68.7	TReader.BeginReferences	436
4.68.8	TReader.CheckValue	436
4.68.9	TReader.DefineProperty	436
4.68.10	TReader.DefineBinaryProperty	436
4.68.11	TReader.EndOfList	436
4.68.12	TReader.EndReferences	437
4.68.13	TReader.FixupReferences	437
4.68.14	TReader.NextValue	437
4.68.15	TReader.Read	437
4.68.16	TReader.ReadBoolean	437
4.68.17	TReader.ReadChar	438
4.68.18	TReader.ReadWideChar	438
4.68.19	TReader.ReadUnicodeChar	438
4.68.20	TReader.ReadCollection	438
4.68.21	TReader.ReadComponent	438
4.68.22	TReader.ReadComponents	439
4.68.23	TReader.ReadFloat	439
4.68.24	TReader.ReadSingle	439
4.68.25	TReader.ReadDate	439
4.68.26	TReader.ReadCurrency	439
4.68.27	TReader.ReadIdent	440
4.68.28	TReader.ReadInteger	440
4.68.29	TReader.ReadInt64	440
4.68.30	TReader.ReadSet	440
4.68.31	TReader.ReadListBegin	440
4.68.32	TReader.ReadListEnd	441
4.68.33	TReader.ReadRootComponent	441
4.68.34	TReader.ReadVariant	441
4.68.35	TReader.ReadSignature	441
4.68.36	TReader.ReadString	441

4.68.37	TReader.ReadWideString	442
4.68.38	TReader.ReadUnicodeString	442
4.68.39	TReader.ReadValue	442
4.68.40	TReader.CopyValue	442
4.68.41	TReader.Driver	442
4.68.42	TReader.Owner	443
4.68.43	TReader.Parent	443
4.68.44	TReader.OnError	443
4.68.45	TReader.OnPropertyNotFound	443
4.68.46	TReader.OnFindMethod	444
4.68.47	TReader.OnSetMethodProperty	444
4.68.48	TReader.OnSetName	444
4.68.49	TReader.OnReferenceName	444
4.68.50	TReader.OnAncestorNotFound	444
4.68.51	TReader.OnCreateComponent	445
4.68.52	TReader.OnFindComponentClass	445
4.68.53	TReader.OnReadStringProperty	445
4.69	TRecall	445
4.69.1	Description	445
4.69.2	Method overview	446
4.69.3	Property overview	446
4.69.4	TRecall.Create	446
4.69.5	TRecall.Destroy	446
4.69.6	TRecall.Store	446
4.69.7	TRecall.Forget	447
4.69.8	TRecall.Reference	447
4.70	TResourceStream	447
4.70.1	Description	447
4.70.2	Method overview	447
4.70.3	TResourceStream.Create	448
4.70.4	TResourceStream.CreateFromID	448
4.70.5	TResourceStream.Destroy	448
4.71	TStream	448
4.71.1	Description	448
4.71.2	Method overview	449
4.71.3	Property overview	449
4.71.4	TStream.Read	449
4.71.5	TStream.Write	450
4.71.6	TStream.Seek	450
4.71.7	TStream.ReadBuffer	451

4.71.8	TStream.WriteBuffer	451
4.71.9	TStream.CopyFrom	452
4.71.10	TStream.ReadComponent	452
4.71.11	TStream.ReadComponentRes	452
4.71.12	TStream.WriteComponent	453
4.71.13	TStream.WriteComponentRes	453
4.71.14	TStream.WriteDescendent	453
4.71.15	TStream.WriteDescendentRes	453
4.71.16	TStream.WriteResourceHeader	454
4.71.17	TStream.FixupResourceHeader	454
4.71.18	TStream.ReadResHeader	454
4.71.19	TStream.ReadByte	454
4.71.20	TStream.ReadWord	455
4.71.21	TStream.ReadDWord	455
4.71.22	TStream.ReadQWord	455
4.71.23	TStream.ReadAnsiString	456
4.71.24	TStream.WriteByte	456
4.71.25	TStream.WriteWord	456
4.71.26	TStream.WriteDWord	456
4.71.27	TStream.WriteQWord	457
4.71.28	TStream.WriteAnsiString	457
4.71.29	TStream.Position	457
4.71.30	TStream.Size	458
4.72	TStreamAdapter	458
4.72.1	Description	458
4.72.2	Interfaces overview	458
4.72.3	Method overview	458
4.72.4	Property overview	459
4.72.5	TStreamAdapter.Create	459
4.72.6	TStreamAdapter.Destroy	459
4.72.7	TStreamAdapter.Read	459
4.72.8	TStreamAdapter.Write	459
4.72.9	TStreamAdapter.Seek	460
4.72.10	TStreamAdapter.SetSize	460
4.72.11	TStreamAdapter.CopyTo	460
4.72.12	TStreamAdapter.Commit	461
4.72.13	TStreamAdapter.Revert	461
4.72.14	TStreamAdapter.LockRegion	461
4.72.15	TStreamAdapter.UnlockRegion	461
4.72.16	TStreamAdapter.Stat	462

4.72.17	TStreamAdapter.Clone	462
4.72.18	TStreamAdapter.Stream	462
4.72.19	TStreamAdapter.StreamOwnership	462
4.73	TStringList	463
4.73.1	Description	463
4.73.2	Method overview	463
4.73.3	Property overview	463
4.73.4	TStringList.Destroy	463
4.73.5	TStringList.Add	464
4.73.6	TStringList.Clear	464
4.73.7	TStringList.Delete	464
4.73.8	TStringList.Exchange	464
4.73.9	TStringList.Find	465
4.73.10	TStringList.IndexOf	465
4.73.11	TStringList.Insert	465
4.73.12	TStringList.Sort	465
4.73.13	TStringList.CustomSort	466
4.73.14	TStringList.Duplicates	466
4.73.15	TStringList.Sorted	466
4.73.16	TStringList.CaseSensitive	467
4.73.17	TStringList.OnChange	467
4.73.18	TStringList.OnChanging	467
4.73.19	TStringList.OwnsObjects	468
4.73.20	TStringList.SortStyle	468
4.74	TStrings	468
4.74.1	Description	468
4.74.2	Method overview	469
4.74.3	Property overview	470
4.74.4	TStrings.Create	470
4.74.5	TStrings.Destroy	471
4.74.6	TStrings.ToObjectArray	471
4.74.7	TStrings.ToStringArray	471
4.74.8	TStrings.Add	472
4.74.9	TStrings.AddObject	472
4.74.10	TStrings.AddPair	472
4.74.11	TStrings.AddStrings	473
4.74.12	TStrings.SetStrings	473
4.74.13	TStrings.AddText	473
4.74.14	TStrings.AddCommaText	473
4.74.15	TStrings.AddDelimitedtext	474

4.74.16	TStrings.Append	474
4.74.17	TStrings.Assign	474
4.74.18	TStrings.BeginUpdate	475
4.74.19	TStrings.Clear	475
4.74.20	TStrings.Delete	475
4.74.21	TStrings.EndUpdate	476
4.74.22	TStrings.Equals	476
4.74.23	TStrings.Exchange	476
4.74.24	TStrings.ExtractName	477
4.74.25	TStrings.Filter	477
4.74.26	TStrings.Fill	477
4.74.27	TStrings.ForEach	477
4.74.28	TStrings.GetEnumerator	478
4.74.29	TStrings.GetNameValue	478
4.74.30	TStrings.GetText	478
4.74.31	TStrings.IndexOf	478
4.74.32	TStrings.IndexOfName	479
4.74.33	TStrings.IndexOfObject	479
4.74.34	TStrings.Insert	479
4.74.35	TStrings.InsertObject	480
4.74.36	TStrings.LastIndexOf	480
4.74.37	TStrings.LoadFromFile	480
4.74.38	TStrings.LoadFromStream	481
4.74.39	TStrings.Map	481
4.74.40	TStrings.Move	481
4.74.41	TStrings.Pop	482
4.74.42	TStrings.Reduce	482
4.74.43	TStrings.Reverse	482
4.74.44	TStrings.SaveToFile	483
4.74.45	TStrings.SaveToStream	483
4.74.46	TStrings.Shift	483
4.74.47	TStrings.Slice	484
4.74.48	TStrings.SetText	484
4.74.49	TStrings.AlwaysQuote	484
4.74.50	TStrings.Capacity	484
4.74.51	TStrings.CommaText	485
4.74.52	TStrings.Count	485
4.74.53	TStrings.DefaultEncoding	486
4.74.54	TStrings.DelimitedText	486
4.74.55	TStrings.Delimiter	487

4.74.56	TStrings.Encoding	487
4.74.57	TStrings.LineBreak	487
4.74.58	TStrings.MissingNameValueSeparatorAction	487
4.74.59	TStrings.Names	488
4.74.60	TStrings.NameValueSeparator	488
4.74.61	TStrings.Objects	488
4.74.62	TStrings.Options	489
4.74.63	TStrings.QuoteChar	489
4.74.64	TStrings.SkipLastLineBreak	489
4.74.65	TStrings.TrailingLineBreak	489
4.74.66	TStrings.StrictDelimiter	490
4.74.67	TStrings.Strings	490
4.74.68	TStrings.StringsAdapter	490
4.74.69	TStrings.Text	491
4.74.70	TStrings.TextLineBreakStyle	491
4.74.71	TStrings.UseLocale	491
4.74.72	TStrings.ValueFromIndex	492
4.74.73	TStrings.Values	492
4.74.74	TStrings.WriteBOM	492
4.75	TStringsEnumerator	493
4.75.1	Description	493
4.75.2	Method overview	493
4.75.3	Property overview	493
4.75.4	TStringsEnumerator.Create	493
4.75.5	TStringsEnumerator.GetCurrent	493
4.75.6	TStringsEnumerator.MoveNext	493
4.75.7	TStringsEnumerator.Current	494
4.76	TStringStream	494
4.76.1	Description	494
4.76.2	Method overview	494
4.76.3	Property overview	495
4.76.4	TStringStream.Create	495
4.76.5	TStringStream.CreateRaw	495
4.76.6	TStringStream.Destroy	495
4.76.7	TStringStream.ReadUnicodeString	496
4.76.8	TStringStream.WriteUnicodeString	496
4.76.9	TStringStream.ReadAnsiString	496
4.76.10	TStringStream.WriteAnsiString	496
4.76.11	TStringStream.ReadString	497
4.76.12	TStringStream.WriteString	497

4.76.13	TStringStream.DataString	497
4.76.14	TStringStream.UnicodeDataString	497
4.76.15	TStringStream.OwnsEncoding	498
4.76.16	TStringStream.Encoding	498
4.77	TTextObjectWriter	498
4.77.1	Description	498
4.78	TThread	498
4.78.1	Description	498
4.78.2	Method overview	499
4.78.3	Property overview	499
4.78.4	TThread.Execute	499
4.78.5	TThread.Synchronize	500
4.78.6	TThread.Queue	500
4.78.7	TThread.Create	500
4.78.8	TThread.Destroy	500
4.78.9	TThread.CreateAnonymousThread	501
4.78.10	TThread.NameThreadForDebugging	501
4.78.11	TThread.SetReturnValue	501
4.78.12	TThread.CheckTerminated	501
4.78.13	TThread.RemoveQueuedEvents	502
4.78.14	TThread.SpinWait	502
4.78.15	TThread.Sleep	502
4.78.16	TThread.Yield	503
4.78.17	TThread.GetSystemTimes	503
4.78.18	TThread.GetTickCount	503
4.78.19	TThread.GetTickCount64	503
4.78.20	TThread.ExecuteInThread	504
4.78.21	TThread.AfterConstruction	508
4.78.22	TThread.Start	508
4.78.23	TThread.Resume	509
4.78.24	TThread.Suspend	509
4.78.25	TThread.Terminate	509
4.78.26	TThread.WaitFor	509
4.78.27	TThread.CurrentThread	510
4.78.28	TThread.ProcessorCount	510
4.78.29	TThread.IsSingleProcessor	510
4.78.30	TThread.FreeOnTerminate	511
4.78.31	TThread.Handle	511
4.78.32	TThread.ExternalThread	511
4.78.33	TThread.Priority	511

4.78.34	TThread.Suspended	512
4.78.35	TThread.Finished	512
4.78.36	TThread.ThreadID	512
4.78.37	TThread.OnTerminate	512
4.78.38	TThread.FatalException	513
4.79	TThreadList	513
4.79.1	Description	513
4.79.2	Method overview	513
4.79.3	Property overview	513
4.79.4	TThreadList.Create	513
4.79.5	TThreadList.Destroy	514
4.79.6	TThreadList.Add	514
4.79.7	TThreadList.Clear	514
4.79.8	TThreadList.LockList	514
4.79.9	TThreadList.Remove	515
4.79.10	TThreadList.UnlockList	515
4.79.11	TThreadList.Duplicates	515
4.80	TWriter	515
4.80.1	Description	515
4.80.2	Method overview	516
4.80.3	Property overview	516
4.80.4	TWriter.Create	516
4.80.5	TWriter.Destroy	517
4.80.6	TWriter.FlushBuffer	517
4.80.7	TWriter.DefineProperty	517
4.80.8	TWriter.DefineBinaryProperty	517
4.80.9	TWriter.Write	517
4.80.10	TWriter.WriteBoolean	518
4.80.11	TWriter.WriteCollection	518
4.80.12	TWriter.WriteComponent	518
4.80.13	TWriter.WriteChar	518
4.80.14	TWriter.WriteWideChar	518
4.80.15	TWriter.WriteDescendent	519
4.80.16	TWriter.WriteFloat	519
4.80.17	TWriter.WriteSingle	519
4.80.18	TWriter.WriteDate	519
4.80.19	TWriter.WriteCurrency	519
4.80.20	TWriter.WriteIdent	520
4.80.21	TWriter.WriteInteger	520
4.80.22	TWriter.WriteSet	520

4.80.23	TWriter.WriteListBegin	520
4.80.24	TWriter.WriteListEnd	520
4.80.25	TWriter.WriteSignature	521
4.80.26	TWriter.WriteRootComponent	521
4.80.27	TWriter.WriteString	521
4.80.28	TWriter.WriteWideString	521
4.80.29	TWriter.WriteUnicodeString	521
4.80.30	TWriter.WriteVariant	522
4.80.31	TWriter.RootAncestor	522
4.80.32	TWriter.OnFindAncestor	522
4.80.33	TWriter.OnWriteMethodProperty	522
4.80.34	TWriter.OnWriteStringProperty	523
4.80.35	TWriter.Driver	523
4.80.36	TWriter.PropertyPath	523
5	Reference for unit 'clocale'	524
5.1	Used units	524
5.2	Overview	524
6	Reference for unit 'cmem'	525
6.1	Used units	525
6.2	Overview	525
6.3	Constants, types and variables	525
6.3.1	Constants	525
6.4	Procedures and functions	525
6.4.1	CAlloc	525
6.4.2	Free	526
6.4.3	Malloc	526
6.4.4	ReAlloc	526
7	Reference for unit 'collation_de'	527
7.1	Used units	527
7.2	Overview	527
8	Reference for unit 'collation_es'	528
8.1	Used units	528
8.2	Overview	528
9	Reference for unit 'collation_fr_ca'	529
9.1	Used units	529
9.2	Overview	529

10 Reference for unit 'collation_ja'	530
10.1 Used units	530
10.2 Overview	530
11 Reference for unit 'collation_ko'	531
11.1 Used units	531
11.2 Overview	531
12 Reference for unit 'collation_ru'	532
12.1 Used units	532
12.2 Overview	532
13 Reference for unit 'collation_sv'	533
13.1 Used units	533
13.2 Overview	533
14 Reference for unit 'collation_zh'	534
14.1 Used units	534
14.2 Overview	534
15 Reference for unit 'cp1250'	535
15.1 Used units	535
15.2 Overview	535
16 Reference for unit 'cp1251'	536
16.1 Used units	536
16.2 Overview	536
17 Reference for unit 'cp1252'	537
17.1 Used units	537
17.2 Overview	537
18 Reference for unit 'cp1253'	538
18.1 Used units	538
18.2 Overview	538
19 Reference for unit 'cp1254'	539
19.1 Used units	539
19.2 Overview	539
20 Reference for unit 'cp1255'	540
20.1 Used units	540
20.2 Overview	540

21 Reference for unit 'cp1256'	541
21.1 Used units	541
21.2 Overview	541
22 Reference for unit 'cp1257'	542
22.1 Used units	542
22.2 Overview	542
23 Reference for unit 'cp1258'	543
23.1 Used units	543
23.2 Overview	543
24 Reference for unit 'cp437'	544
24.1 Used units	544
24.2 Overview	544
25 Reference for unit 'cp646'	545
25.1 Used units	545
25.2 Overview	545
26 Reference for unit 'cp850'	546
26.1 Used units	546
26.2 Overview	546
27 Reference for unit 'cp852'	547
27.1 Used units	547
27.2 Overview	547
28 Reference for unit 'cp856'	548
28.1 Used units	548
28.2 Overview	548
29 Reference for unit 'cp866'	549
29.1 Used units	549
29.2 Overview	549
30 Reference for unit 'cp874'	550
30.1 Used units	550
30.2 Overview	550
31 Reference for unit 'cp8859_1'	551
31.1 Used units	551
31.2 Overview	551

32 Reference for unit 'cp8859_2'	552
32.1 Used units	552
32.2 Overview	552
33 Reference for unit 'cp8859_5'	553
33.1 Used units	553
33.2 Overview	553
34 Reference for unit 'cp895'	554
34.1 Used units	554
34.2 Overview	554
35 Reference for unit 'cp932'	555
35.1 Used units	555
35.2 Overview	555
36 Reference for unit 'cp936'	556
36.1 Used units	556
36.2 Overview	556
37 Reference for unit 'cp949'	557
37.1 Used units	557
37.2 Overview	557
38 Reference for unit 'cp950'	558
38.1 Used units	558
38.2 Overview	558
39 Reference for unit 'cpall'	559
39.1 Used units	560
39.2 Overview	561
40 Reference for unit 'Crt'	562
40.1 Used units	562
40.2 Overview	562
40.3 Constants, types and variables	563
40.3.1 Constants	563
40.3.2 Types	565
40.3.3 Variables	565
40.4 Procedures and functions	566
40.4.1 AssignCrt	566
40.4.2 ClrEol	567
40.4.3 ClrScr	568

40.4.4	cursorbig	568
40.4.5	cursoroff	568
40.4.6	cursoron	569
40.4.7	Delay	569
40.4.8	DelLine	569
40.4.9	GotoXY	570
40.4.10	HighVideo	571
40.4.11	InsLine	571
40.4.12	KeyPressed	572
40.4.13	LowVideo	572
40.4.14	NormVideo	573
40.4.15	NoSound	573
40.4.16	ReadKey	573
40.4.17	Sound	574
40.4.18	TextBackground	574
40.4.19	TextColor	575
40.4.20	TextMode	576
40.4.21	WhereX	576
40.4.22	WhereY	576
40.4.23	Window	577
40.5	TCharAttr	577
41	Reference for unit 'cthreads'	579
41.1	Used units	579
41.2	Overview	579
41.3	Procedures and functions	580
41.3.1	SetCThreadManager	580
42	Reference for unit 'ctypes'	581
42.1	Used units	581
42.2	Overview	581
42.3	Constants, types and variables	581
42.3.1	Types	581
43	Reference for unit 'cwstring'	587
43.1	Used units	587
43.2	Overview	587
43.3	Procedures and functions	587
43.3.1	SetCWidestringManager	587
44	Reference for unit 'DateUtils'	589

44.1	Used units	589
44.2	Overview	589
44.3	Constants, types and variables	589
44.3.1	Constants	589
44.4	Procedures and functions	592
44.4.1	CompareDate	592
44.4.2	CompareDateTime	593
44.4.3	CompareTime	594
44.4.4	DateInRange	595
44.4.5	DateOf	595
44.4.6	DateTimeInRange	596
44.4.7	DateTimeToDosDateTime	596
44.4.8	DateTimeToJulianDate	597
44.4.9	DateTimeToMac	597
44.4.10	DateTimeToModifiedJulianDate	597
44.4.11	DateTimeToUnix	597
44.4.12	DateToISO8601	598
44.4.13	DayOf	598
44.4.14	DayOfTheMonth	599
44.4.15	DayOfTheWeek	599
44.4.16	DayOfTheYear	599
44.4.17	DaysBetween	600
44.4.18	DaysInAMonth	601
44.4.19	DaysInAYear	601
44.4.20	DaysInMonth	602
44.4.21	DaysInYear	602
44.4.22	DaySpan	603
44.4.23	DecodeDateDay	603
44.4.24	DecodeDateMonthWeek	604
44.4.25	DecodeDateTime	605
44.4.26	DecodeDateWeek	605
44.4.27	DecodeDayOfWeekInMonth	606
44.4.28	DosDateTimeToDateTime	606
44.4.29	EncodeDateDay	607
44.4.30	EncodeDateMonthWeek	607
44.4.31	EncodeDateTime	607
44.4.32	EncodeDateWeek	608
44.4.33	EncodeDayOfWeekInMonth	608
44.4.34	EncodeTimeInterval	608
44.4.35	EndOfADay	609

44.4.36	EndOfAMonth	609
44.4.37	EndOfAWeek	610
44.4.38	EndOfAYear	611
44.4.39	EndOfTheDay	611
44.4.40	EndOfTheMonth	612
44.4.41	EndOfTheWeek	612
44.4.42	EndOfTheYear	613
44.4.43	HourOf	613
44.4.44	HourOfTheDay	614
44.4.45	HourOfTheMonth	614
44.4.46	HourOfTheWeek	614
44.4.47	HourOfTheYear	615
44.4.48	HoursBetween	615
44.4.49	HourSpan	616
44.4.50	IncDay	617
44.4.51	IncHour	617
44.4.52	IncMilliSecond	618
44.4.53	IncMinute	618
44.4.54	IncSecond	619
44.4.55	IncWeek	619
44.4.56	IncYear	620
44.4.57	InvalidDateDayError	620
44.4.58	InvalidDateMonthWeekError	621
44.4.59	InvalidDateTimeError	621
44.4.60	InvalidDateWeekError	621
44.4.61	InvalidDayOfWeekInMonthError	622
44.4.62	IsInLeapYear	622
44.4.63	ISO8601ToDate	623
44.4.64	ISO8601ToDateDef	623
44.4.65	IsPM	624
44.4.66	IsSameDay	624
44.4.67	IsSameMonth	625
44.4.68	IsToday	625
44.4.69	IsValidDate	626
44.4.70	IsValidDateDay	626
44.4.71	IsValidDateMonthWeek	627
44.4.72	IsValidDateTime	628
44.4.73	IsValidDateWeek	629
44.4.74	IsValidTime	629
44.4.75	JulianDateToDateTime	630

44.4.76	LocalTimeToUniversal	630
44.4.77	MacTimeStampToUnix	630
44.4.78	MacToDateTime	630
44.4.79	MilliSecondOf	631
44.4.80	MilliSecondOfTheDay	631
44.4.81	MilliSecondOfTheHour	631
44.4.82	MilliSecondOfTheMinute	632
44.4.83	MilliSecondOfTheMonth	632
44.4.84	MilliSecondOfTheSecond	632
44.4.85	MilliSecondOfTheWeek	633
44.4.86	MilliSecondOfTheYear	633
44.4.87	MilliSecondsBetween	633
44.4.88	MilliSecondSpan	634
44.4.89	MinuteOf	635
44.4.90	MinuteOfTheDay	635
44.4.91	MinuteOfTheHour	635
44.4.92	MinuteOfTheMonth	636
44.4.93	MinuteOfTheWeek	636
44.4.94	MinuteOfTheYear	637
44.4.95	MinutesBetween	637
44.4.96	MinuteSpan	638
44.4.97	ModifiedJulianDateToDateTime	639
44.4.98	MonthOf	639
44.4.99	MonthOfTheYear	639
44.4.100	MonthsBetween	640
44.4.101	MonthSpan	640
44.4.102	NthDayOfWeek	641
44.4.103	PeriodBetween	642
44.4.104	PreviousDayOfWeek	642
44.4.105	RecodeDate	643
44.4.106	RecodeDateTime	643
44.4.107	RecodeDay	644
44.4.108	RecodeHour	645
44.4.109	RecodeMilliSecond	645
44.4.110	RecodeMinute	646
44.4.111	RecodeMonth	647
44.4.112	RecodeSecond	647
44.4.113	RecodeTime	648
44.4.114	RecodeYear	649
44.4.115	SameDate	649

44.4.116	SameDateTime	650
44.4.117	SameTime	651
44.4.118	ScanDateTime	652
44.4.119	SecondOf	652
44.4.120	SecondOfTheDay	653
44.4.121	SecondOfTheHour	653
44.4.122	SecondOfTheMinute	653
44.4.123	SecondOfTheMonth	654
44.4.124	SecondOfTheWeek	654
44.4.125	SecondOfTheYear	654
44.4.126	SecondsBetween	655
44.4.127	SecondSpan	655
44.4.128	StartOfADay	656
44.4.129	StartOfAMonth	657
44.4.130	StartOfAWeek	658
44.4.131	StartOfAYear	658
44.4.132	StartOfTheDay	659
44.4.133	StartOfTheMonth	659
44.4.134	StartOfTheWeek	660
44.4.135	StartOfTheYear	660
44.4.136	TimeInRange	661
44.4.137	TimeOf	661
44.4.138	Today	662
44.4.139	Tomorrow	662
44.4.140	TryEncodeDateDay	662
44.4.141	TryEncodeDateMonthWeek	663
44.4.142	TryEncodeDateTime	664
44.4.143	TryEncodeDateWeek	665
44.4.144	TryEncodeDayOfWeekInMonth	665
44.4.145	TryEncodeTimeInterval	666
44.4.146	TryISO8601ToDate	666
44.4.147	TryISOStrToDate	667
44.4.148	TryISOStrToDateTime	667
44.4.149	TryISOStrToTime	668
44.4.150	TryISOTZStrToTZOffset	669
44.4.151	TryJulianDateToDateTime	669
44.4.152	TryModifiedJulianDateToDateTime	669
44.4.153	TryRecodeDateTime	670
44.4.154	UniversalTimeToLocal	671
44.4.155	UnixTimeStampToMac	671

44.4.156	UnixToDateTime	671
44.4.157	WeekOf	671
44.4.158	WeekOfTheMonth	672
44.4.159	WeekOfTheYear	672
44.4.160	WeeksBetween	673
44.4.161	WeeksInAYear	674
44.4.162	WeeksInYear	675
44.4.163	WeekSpan	675
44.4.164	WithinPastDays	676
44.4.165	WithinPastHours	677
44.4.166	WithinPastMilliSeconds	678
44.4.167	WithinPastMinutes	679
44.4.168	WithinPastMonths	680
44.4.169	WithinPastSeconds	681
44.4.170	WithinPastWeeks	682
44.4.171	WithinPastYears	683
44.4.172	YearOf	684
44.4.173	YearsBetween	684
44.4.174	YearSpan	685
44.4.175	Yesterday	686
45	Reference for unit 'Dos'	688
45.1	Used units	688
45.2	Overview	688
45.3	System information	688
45.4	Process handling	689
45.5	Directory and disk handling	689
45.6	File handling	690
45.7	File open mode constants.	690
45.8	File attributes	690
45.9	Constants, types and variables	691
45.9.1	Constants	691
45.9.2	Types	692
45.9.3	Variables	694
45.10	Procedures and functions	694
45.10.1	AddDisk	694
45.10.2	DiskFree	695
45.10.3	DiskSize	696
45.10.4	DosExitCode	696
45.10.5	DosVersion	697

45.10.6	DTToUnixDate	697
45.10.7	EnvCount	698
45.10.8	EnvStr	698
45.10.9	Exec	699
45.10.10	FExpand	699
45.10.11	FindClose	699
45.10.12	FindFirst	700
45.10.13	FindNext	701
45.10.14	FSearch	701
45.10.15	FSplit	702
45.10.16	GetCBreak	702
45.10.17	GetDate	703
45.10.18	GetEnv	703
45.10.19	GetFAttr	704
45.10.20	GetFTime	705
45.10.21	GetIntVec	705
45.10.22	GetLongName	706
45.10.23	GetMsCount	706
45.10.24	GetShortName	706
45.10.25	GetTime	707
45.10.26	GetVerify	707
45.10.27	Intr	708
45.10.28	Keep	708
45.10.29	MSDos	708
45.10.30	PackTime	709
45.10.31	SetCBreak	709
45.10.32	SetDate	710
45.10.33	SetFAttr	710
45.10.34	SetFTime	711
45.10.35	SetIntVec	711
45.10.36	SetTime	711
45.10.37	SetVerify	711
45.10.38	SwapVectors	712
45.10.39	UnixDateToDt	712
45.10.40	UnpackTime	712
45.10.41	weekday	713
45.11	DateTime	713
45.12	SearchRec	713

46 Reference for unit 'dxeload'**715**

46.1	Used units	715
46.2	Overview	715
46.3	Procedures and functions	715
46.3.1	dxload	715
47	Reference for unit 'dynlibs'	716
47.1	Used units	716
47.2	Overview	716
47.3	Constants, types and variables	716
47.3.1	Constants	716
47.3.2	Types	716
47.4	Procedures and functions	717
47.4.1	FreeLibrary	717
47.4.2	GetLoadErrorStr	717
47.4.3	GetProcAddress	717
47.4.4	GetProcedureAddress	718
47.4.5	LoadLibrary	718
47.4.6	SafeLoadLibrary	718
47.4.7	UnloadLibrary	719
48	Reference for unit 'emu387'	720
48.1	Used units	720
48.2	Overview	720
48.3	Procedures and functions	720
48.3.1	npxsetup	720
49	Reference for unit 'errors'	722
49.1	Used units	722
49.2	Overview	722
49.3	Constants, types and variables	722
49.3.1	Constants	722
49.4	Procedures and functions	723
49.4.1	PError	723
49.4.2	StrError	724
50	Reference for unit 'exeinfo'	725
50.1	Used units	725
50.2	Overview	725
50.3	Constants, types and variables	725
50.3.1	Types	725
50.4	Procedures and functions	725

50.4.1	CloseExeFile	725
50.4.2	FindExeSection	726
50.4.3	GetModuleByAddr	726
50.4.4	OpenExeFile	726
50.4.5	ReadDebugLink	727
50.5	TExeFile	727
51	Reference for unit 'fgl'	728
51.1	Used units	728
51.2	Overview	728
51.3	Constants, types and variables	728
51.3.1	Constants	728
51.3.2	Types	728
51.4	EListError	729
51.4.1	Description	729
51.5	TFPGInterfacedObjectList	729
51.5.1	Description	729
51.5.2	Method overview	729
51.5.3	Property overview	729
51.5.4	TFPGInterfacedObjectList.Create	730
51.5.5	TFPGInterfacedObjectList.Add	730
51.5.6	TFPGInterfacedObjectList.Extract	730
51.5.7	TFPGInterfacedObjectList.GetEnumerator	730
51.5.8	TFPGInterfacedObjectList.IndexOf	731
51.5.9	TFPGInterfacedObjectList.Insert	731
51.5.10	TFPGInterfacedObjectList.Assign	731
51.5.11	TFPGInterfacedObjectList.AddList	731
51.5.12	TFPGInterfacedObjectList.Remove	732
51.5.13	TFPGInterfacedObjectList.Sort	732
51.5.14	TFPGInterfacedObjectList.First	732
51.5.15	TFPGInterfacedObjectList.Last	733
51.5.16	TFPGInterfacedObjectList.Items	733
51.5.17	TFPGInterfacedObjectList.List	733
51.6	TFPGList	733
51.6.1	Description	733
51.6.2	Method overview	734
51.6.3	Property overview	734
51.6.4	TFPGList.Create	734
51.6.5	TFPGList.ItemIsManaged	734
51.6.6	TFPGList.Add	734

51.6.7	TFPGList.Extract	735
51.6.8	TFPGList.GetEnumerator	735
51.6.9	TFPGList.IndexOf	735
51.6.10	TFPGList.Insert	735
51.6.11	TFPGList.Assign	736
51.6.12	TFPGList.AddList	736
51.6.13	TFPGList.Remove	736
51.6.14	TFPGList.Sort	736
51.6.15	TFPGList.First	737
51.6.16	TFPGList.Last	737
51.6.17	TFPGList.Items	737
51.6.18	TFPGList.List	737
51.7	TFPGListEnumerator	738
51.7.1	Description	738
51.7.2	Method overview	738
51.7.3	Property overview	738
51.7.4	TFPGListEnumerator.Create	738
51.7.5	TFPGListEnumerator.MoveNext	738
51.7.6	TFPGListEnumerator.Current	738
51.8	TFPGMap	739
51.8.1	Description	739
51.8.2	Method overview	739
51.8.3	Property overview	739
51.8.4	TFPGMap.Create	739
51.8.5	TFPGMap.Add	740
51.8.6	TFPGMap.Find	740
51.8.7	TFPGMap.TryGetData	740
51.8.8	TFPGMap.AddOrSetData	740
51.8.9	TFPGMap.IndexOf	741
51.8.10	TFPGMap.IndexOfData	741
51.8.11	TFPGMap.InsertKey	741
51.8.12	TFPGMap.InsertKeyData	741
51.8.13	TFPGMap.Remove	742
51.8.14	TFPGMap.Keys	742
51.8.15	TFPGMap.Data	742
51.8.16	TFPGMap.KeyData	743
51.8.17	TFPGMap.OnCompare	743
51.8.18	TFPGMap.OnKeyCompare	743
51.8.19	TFPGMap.OnDataCompare	744
51.9	TFPGMapInterfacedObjectData	744

51.9.1	Description	744
51.9.2	Method overview	744
51.9.3	Property overview	745
51.9.4	TFPGMapInterfacedObjectData.Create	745
51.9.5	TFPGMapInterfacedObjectData.Add	745
51.9.6	TFPGMapInterfacedObjectData.Find	745
51.9.7	TFPGMapInterfacedObjectData.TryGetData	746
51.9.8	TFPGMapInterfacedObjectData.AddOrSetData	746
51.9.9	TFPGMapInterfacedObjectData.IndexOf	746
51.9.10	TFPGMapInterfacedObjectData.IndexOfData	746
51.9.11	TFPGMapInterfacedObjectData.InsertKey	747
51.9.12	TFPGMapInterfacedObjectData.InsertKeyData	747
51.9.13	TFPGMapInterfacedObjectData.Remove	747
51.9.14	TFPGMapInterfacedObjectData.Keys	747
51.9.15	TFPGMapInterfacedObjectData.Data	748
51.9.16	TFPGMapInterfacedObjectData.KeyData	748
51.9.17	TFPGMapInterfacedObjectData.OnCompare	748
51.9.18	TFPGMapInterfacedObjectData.OnKeyCompare	749
51.9.19	TFPGMapInterfacedObjectData.OnDataCompare	749
51.10	TFPGMapObject	749
51.10.1	Description	749
51.10.2	Method overview	750
51.10.3	Property overview	750
51.10.4	TFPGMapObject.Create	750
51.10.5	TFPGMapObject.Add	750
51.10.6	TFPGMapObject.Find	751
51.10.7	TFPGMapObject.TryGetData	751
51.10.8	TFPGMapObject.AddOrSetData	751
51.10.9	TFPGMapObject.IndexOf	751
51.10.10	TFPGMapObject.IndexOfData	752
51.10.11	TFPGMapObject.InsertKey	752
51.10.12	TFPGMapObject.InsertKeyData	752
51.10.13	TFPGMapObject.Remove	752
51.10.14	TFPGMapObject.Keys	753
51.10.15	TFPGMapObject.Data	753
51.10.16	TFPGMapObject.KeyData	753
51.10.17	TFPGMapObject.OnCompare	754
51.10.18	TFPGMapObject.OnKeyCompare	754
51.10.19	TFPGMapObject.OnDataCompare	754
51.11	TFPGObjectList	755

51.11.1	Description	755
51.11.2	Method overview	755
51.11.3	Property overview	755
51.11.4	TFPGObjectList.Create	755
51.11.5	TFPGObjectList.Add	755
51.11.6	TFPGObjectList.Extract	756
51.11.7	TFPGObjectList.GetEnumerator	756
51.11.8	TFPGObjectList.IndexOf	756
51.11.9	TFPGObjectList.Insert	757
51.11.10	TFPGObjectList.AddList	757
51.11.11	TFPGObjectList.Assign	757
51.11.12	TFPGObjectList.Remove	757
51.11.13	TFPGObjectList.Sort	758
51.11.14	TFPGObjectList.First	758
51.11.15	TFPGObjectList.Last	758
51.11.16	TFPGObjectList.Items	758
51.11.17	TFPGObjectList.List	759
51.11.18	TFPGObjectList.FreeObjects	759
51.12	TFPSList	759
51.12.1	Description	759
51.12.2	Method overview	760
51.12.3	Property overview	760
51.12.4	TFPSList.Create	760
51.12.5	TFPSList.Destroy	760
51.12.6	TFPSList.ItemIsManaged	761
51.12.7	TFPSList.Add	761
51.12.8	TFPSList.Clear	761
51.12.9	TFPSList.Delete	761
51.12.10	TFPSList.DeleteRange	762
51.12.11	TFPSList.Error	762
51.12.12	TFPSList.Exchange	762
51.12.13	TFPSList.Expand	762
51.12.14	TFPSList.Extract	763
51.12.15	TFPSList.IndexOf	763
51.12.16	TFPSList.Insert	763
51.12.17	TFPSList.Move	764
51.12.18	TFPSList.Assign	764
51.12.19	TFPSList.AddList	764
51.12.20	TFPSList.Remove	764
51.12.21	TFPSList.Pack	765

51.12.22	TFPSList.Sort	765
51.12.23	TFPSList.Capacity	765
51.12.24	TFPSList.Count	766
51.12.25	TFPSList.Items	766
51.12.26	TFPSList.ItemSize	766
51.12.27	TFPSList.List	766
51.12.28	TFPSList.First	767
51.12.29	TFPSList.Last	767
51.13	TFPSMap	767
51.13.1	Description	767
51.13.2	Method overview	767
51.13.3	Property overview	768
51.13.4	TFPSMap.Create	768
51.13.5	TFPSMap.Add	768
51.13.6	TFPSMap.Find	768
51.13.7	TFPSMap.IndexOf	769
51.13.8	TFPSMap.IndexOfData	769
51.13.9	TFPSMap.Insert	769
51.13.10	TFPSMap.InsertKey	770
51.13.11	TFPSMap.InsertKeyData	770
51.13.12	TFPSMap.Remove	770
51.13.13	TFPSMap.Sort	770
51.13.14	TFPSMap.Duplicates	771
51.13.15	TFPSMap.KeySize	771
51.13.16	TFPSMap.DataSize	771
51.13.17	TFPSMap.Keys	772
51.13.18	TFPSMap.Data	772
51.13.19	TFPSMap.KeyData	772
51.13.20	TFPSMap.Sorted	772
51.13.21	TFPSMap.OnPtrCompare	773
51.13.22	TFPSMap.OnKeyPtrCompare	773
51.13.23	TFPSMap.OnDataPtrCompare	773
52	Reference for unit 'fpwiderstring'	774
52.1	Used units	774
52.2	Overview	774
52.3	Constants, types and variables	775
52.3.1	Variables	775
52.4	Procedures and functions	775
52.4.1	GetActiveCollation	775

52.4.2	SetActiveCollation	775
53	Reference for unit 'getopts'	776
53.1	Used units	776
53.2	Overview	776
53.3	Constants, types and variables	776
53.3.1	Constants	776
53.3.2	Types	777
53.3.3	Variables	777
53.4	Procedures and functions	777
53.4.1	GetLongOpts	777
53.4.2	GetOpt	778
53.5	TOption	780
53.5.1	Method overview	781
53.5.2	TOption.SetOption	781
54	Reference for unit 'go32'	782
54.1	Used units	782
54.2	Overview	782
54.3	Real mode callbacks	782
54.4	Executing software interrupts	783
54.5	Software interrupts	786
54.6	Hardware interrupts	786
54.7	Disabling interrupts	788
54.8	Creating your own interrupt handlers	788
54.9	Protected mode interrupts vs. Real mode interrupts	789
54.10	Handling interrupts with DPMI	789
54.11	Interrupt redirection	789
54.12	Processor access	789
54.13	I/O port access	789
54.14	dos memory access	789
54.15	FPC specialities	790
54.16	Selectors and descriptors	790
54.17	What is DPMI	790
54.18	Constants, types and variables	790
54.18.1	Constants	790
54.18.2	Types	793
54.18.3	Variables	795
54.19	Procedures and functions	795
54.19.1	allocate_ldt_descriptors	795
54.19.2	allocate_memory_block	798

54.19.3	copyfromdos	799
54.19.4	copytodos	799
54.19.5	create_code_segment_alias_descriptor	800
54.19.6	disable	800
54.19.7	dpmi_dosmemfillchar	800
54.19.8	dpmi_dosmemfillword	801
54.19.9	dpmi_dosmemget	801
54.19.10	dpmi_dosmemmove	801
54.19.11	dpmi_dosmemput	801
54.19.12	enable	802
54.19.13	free_ldt_descriptor	802
54.19.14	free_linear_addr_mapping	802
54.19.15	free_memory_block	802
54.19.16	free_rm_callback	803
54.19.17	get_cs	803
54.19.18	get_descriptor_access_right	803
54.19.19	get_dpmi_version	804
54.19.20	get_ds	804
54.19.21	get_exception_handler	804
54.19.22	get_linear_addr	805
54.19.23	get_meminfo	805
54.19.24	get_next_selector_increment_value	806
54.19.25	get_page_attributes	807
54.19.26	get_page_size	807
54.19.27	get_pm_exception_handler	807
54.19.28	get_pm_interrupt	807
54.19.29	get_rm_callback	808
54.19.30	get_rm_interrupt	812
54.19.31	get_run_mode	813
54.19.32	get_segment_base_address	814
54.19.33	get_segment_limit	814
54.19.34	get_ss	814
54.19.35	global_dos_alloc	815
54.19.36	global_dos_free	817
54.19.37	inportb	818
54.19.38	inportl	818
54.19.39	inportw	818
54.19.40	lock_code	819
54.19.41	lock_data	819
54.19.42	lock_linear_region	819

54.19.43	map_device_in_memory_block	820
54.19.44	outportb	820
54.19.45	outportl	821
54.19.46	outportw	821
54.19.47	realintr	821
54.19.48	request_linear_region	822
54.19.49	segment_to_descriptor	823
54.19.50	seg_fillchar	823
54.19.51	seg_fillword	824
54.19.52	seg_move	825
54.19.53	set_descriptor_access_right	825
54.19.54	set_exception_handler	825
54.19.55	set_page_attributes	826
54.19.56	set_pm_exception_handler	826
54.19.57	set_pm_interrupt	826
54.19.58	set_rm_interrupt	828
54.19.59	set_segment_base_address	828
54.19.60	set_segment_limit	828
54.19.61	tb_offset	829
54.19.62	tb_segment	829
54.19.63	tb_size	829
54.19.64	transfer_buffer	830
54.19.65	unlock_code	830
54.19.66	unlock_data	830
54.19.67	unlock_linear_region	831
54.20	tdpmiversioninfo	831
54.21	tmeminfo	832
54.22	tseginfo	832
55	Reference for unit 'gpm'	833
55.1	Used units	833
55.2	Overview	833
55.3	Constants, types and variables	833
55.3.1	Constants	833
55.3.2	Types	835
55.3.3	Variables	836
55.4	Procedures and functions	837
55.4.1	Gpm_AnyDouble	837
55.4.2	Gpm_AnySingle	837
55.4.3	Gpm_AnyTriple	837

55.4.4	gpm_close	838
55.4.5	gpm_fitvalues	838
55.4.6	gpm_fitvaluesM	838
55.4.7	gpm_getevent	839
55.4.8	gpm_getsnapshot	840
55.4.9	gpm_lowerroi	840
55.4.10	gpm_open	840
55.4.11	gpm_poproi	841
55.4.12	gpm_pushroi	841
55.4.13	gpm_raiseroi	841
55.4.14	gpm_repeat	842
55.4.15	Gpm_StrictDouble	842
55.4.16	Gpm_StrictSingle	842
55.4.17	Gpm_StrictTriple	842
55.5	Tgpm_connect	843
55.6	Tgpm_event	843
55.7	Tgpm_roi	843
56	Reference for unit 'Graph'	845
56.1	Used units	845
56.2	Overview	845
56.3	Categorized functions: Text and font handling	845
56.4	Categorized functions: Filled drawings	846
56.5	Categorized functions: Drawing primitives	846
56.6	Categorized functions: Color management	847
56.7	Categorized functions: Screen management	847
56.8	Categorized functions: Initialization	848
56.9	Target specific issues: Linux	848
56.10	Target specific issues: DOS	849
56.11	A word about mode selection	849
56.12	Requirements	854
56.13	Constants, types and variables	854
56.13.1	Constants	854
56.13.2	Types	871
56.13.3	Variables	874
56.14	Procedures and functions	877
56.14.1	Arc	877
56.14.2	Bar	877
56.14.3	Bar3D	877
56.14.4	ClearDevice	878

56.14.5	Closegraph	878
56.14.6	DetectGraph	878
56.14.7	DrawPoly	878
56.14.8	Ellipse	879
56.14.9	FillEllipse	879
56.14.10	FillPoly	879
56.14.11	FloodFill	879
56.14.12	GetArcCoords	880
56.14.13	GetAspectRatio	880
56.14.14	GetColor	880
56.14.15	GetDefaultPalette	880
56.14.16	GetDirectVideo	881
56.14.17	GetDriverName	881
56.14.18	GetFillPattern	881
56.14.19	GetFillSettings	881
56.14.20	GetGraphMode	882
56.14.21	GetLineSettings	882
56.14.22	GetMaxColor	882
56.14.23	GetMaxMode	882
56.14.24	GetMaxX	883
56.14.25	GetMaxY	883
56.14.26	GetModeName	883
56.14.27	GetModeRange	883
56.14.28	GetPalette	884
56.14.29	GetPaletteSize	884
56.14.30	GetTextSettings	884
56.14.31	GetViewSettings	884
56.14.32	GetX	885
56.14.33	GetY	885
56.14.34	GraphDefaults	885
56.14.35	GraphErrorMsg	885
56.14.36	GraphResult	886
56.14.37	InitGraph	886
56.14.38	InstallUserDriver	887
56.14.39	InstallUserFont	887
56.14.40	LineRel	887
56.14.41	LineTo	888
56.14.42	MoveRel	888
56.14.43	MoveTo	888
56.14.44	OutText	888

56.14.45	PieSlice	889
56.14.46	queryadapterinfo	889
56.14.47	Rectangle	889
56.14.48	RegisterBGIDriver	889
56.14.49	RegisterBGIfont	890
56.14.50	RestoreCrtMode	890
56.14.51	Sector	890
56.14.52	SetAspectRatio	890
56.14.53	SetColor	891
56.14.54	SetDirectVideo	891
56.14.55	SetFillPattern	891
56.14.56	SetFillStyle	891
56.14.57	SetGraphMode	892
56.14.58	SetLineStyle	892
56.14.59	SetPalette	893
56.14.60	SetTextJustify	893
56.14.61	SetTextStyle	893
56.14.62	SetUserCharSize	894
56.14.63	SetViewPort	894
56.14.64	SetWriteMode	895
56.14.65	SetWriteModeEx	895
56.14.66	TextHeight	895
56.14.67	TextWidth	895
56.15	ArcCoordsType	896
56.16	FillSettingsType	896
56.17	LineSettingsType	896
56.18	PaletteType	896
56.19	PointType	896
56.20	RGBRec	897
56.21	TextSettingsType	897
56.22	TModeInfo	897
56.23	TResolutionRec	898
56.24	ViewPortType	898
57	Reference for unit 'heaptrc'	900
57.1	Used units	900
57.2	Overview	900
57.3	Controlling HeapTrc with environment variables	900
57.4	HeapTrc Usage	901
57.5	Constants, types and variables	902

57.5.1	Constants	902
57.5.2	Types	904
57.6	Procedures and functions	904
57.6.1	CheckPointer	904
57.6.2	DumpHeap	904
57.6.3	SetHeapExtraInfo	904
57.6.4	SetHeapTraceOutput	906
58	Reference for unit 'ipc'	907
58.1	Used units	907
58.2	Overview	907
58.3	Constants, types and variables	907
58.3.1	Constants	907
58.3.2	Types	910
58.4	Procedures and functions	911
58.4.1	ftok	911
58.4.2	msgctl	912
58.4.3	msgget	914
58.4.4	msgrcv	915
58.4.5	msgsnd	915
58.4.6	semctl	916
58.4.7	semget	921
58.4.8	semop	921
58.4.9	semtimedop	922
58.4.10	shmat	922
58.4.11	shmctl	923
58.4.12	shmdt	925
58.4.13	shmget	925
58.5	TIPC_Perm	926
58.6	TMSG	926
58.7	TMSGbuf	926
58.8	TMSGinfo	926
58.9	TMSQid_ds	927
58.10	TSEMbuf	927
58.11	TSEMid_ds	927
58.12	TSEMinfo	928
58.13	TShmid_ds	928
58.14	TSHMinfo	929
58.15	TSHM_info	929
59	Reference for unit 'keyboard'	930

59.1	Used units	930
59.2	Overview	930
59.3	Unix specific notes	930
59.4	Writing a keyboard driver	932
59.5	Keyboard scan codes	935
59.6	Constants, types and variables	937
59.6.1	Constants	937
59.6.2	Types	942
59.7	Procedures and functions	942
59.7.1	DoneKeyboard	942
59.7.2	FunctionKeyName	943
59.7.3	GetKeyboardDriver	943
59.7.4	GetKeyEvent	944
59.7.5	GetKeyEventChar	944
59.7.6	GetKeyEventCode	945
59.7.7	GetKeyEventFlags	946
59.7.8	GetKeyEventShiftState	946
59.7.9	GetKeyEventUniCode	947
59.7.10	InitKeyboard	947
59.7.11	IsFunctionKey	947
59.7.12	KeyEventToString	948
59.7.13	KeyPressed	948
59.7.14	PollKeyEvent	949
59.7.15	PollShiftStateEvent	949
59.7.16	PutKeyEvent	950
59.7.17	SetKeyboardDriver	951
59.7.18	ShiftStateToString	951
59.7.19	TranslateKeyEvent	952
59.7.20	TranslateKeyEventUniCode	952
59.8	TKeyboardDriver	952
59.9	TKeyRecord	953
59.10	TTreeElement	953
60	Reference for unit 'lineinfo'	955
60.1	Used units	955
60.2	Overview	955
60.3	Constants, types and variables	955
60.3.1	Types	955
60.3.2	Variables	955
60.4	Procedures and functions	956

60.4.1	CloseStabs	956
60.4.2	GetLineInfo	956
60.4.3	StabBackTraceStr	956
61	Reference for unit 'Linux'	957
61.1	Used units	957
61.2	Overview	957
61.3	Constants, types and variables	957
61.3.1	Constants	957
61.3.2	Types	972
61.4	Procedures and functions	973
61.4.1	capget	973
61.4.2	capset	974
61.4.3	clock_getres	974
61.4.4	clock_gettime	974
61.4.5	clock_settime	974
61.4.6	clone	975
61.4.7	epoll_create	975
61.4.8	epoll_ctl	976
61.4.9	epoll_wait	976
61.4.10	fdatasync	977
61.4.11	futex	977
61.4.12	futex_op	978
61.4.13	inotify_add_watch	978
61.4.14	inotify_init	979
61.4.15	inotify_init1	979
61.4.16	inotify_rm_watch	979
61.4.17	modify_ldt	979
61.4.18	sched_yield	980
61.4.19	setregid	980
61.4.20	setreuid	980
61.4.21	sync_file_range	980
61.4.22	Sysinfo	981
61.5	EPoll_Event	982
61.6	inotify_event	982
61.7	TSysInfo	982
61.8	user_cap_data	983
61.9	user_cap_header	983
61.10	user_desc	983
62	Reference for unit 'Infodwrf'	984

62.1	Used units	984
62.2	Overview	984
62.3	Constants, types and variables	984
62.3.1	Types	984
62.3.2	Variables	984
62.4	Procedures and functions	985
62.4.1	CloseDwarf	985
62.4.2	DwarfBackTraceStr	985
62.4.3	GetLineInfo	985
63	Reference for unit 'Math'	986
63.1	Used units	986
63.2	Overview	986
63.3	Cash flow functions	986
63.4	Geometrical functions	987
63.5	Statistical functions	987
63.6	Number converting	988
63.7	Exponential and logarithmic functions	988
63.8	Hyperbolic functions	988
63.9	Trigonometric functions	989
63.10	Angle unit conversion	989
63.11	Min/max determination	989
63.12	Constants, types and variables	990
63.12.1	Constants	990
63.12.2	Types	991
63.13	Procedures and functions	992
63.13.1	ArcCos	992
63.13.2	ArcCosH	992
63.13.3	ArCosH	993
63.13.4	ArcSin	993
63.13.5	ArcSinH	994
63.13.6	ArcTan2	994
63.13.7	ArcTanH	995
63.13.8	ArSinH	995
63.13.9	ArTanH	995
63.13.10	Ceil	996
63.13.11	Ceil64	996
63.13.12	ClearExceptions	997
63.13.13	CompareValue	997
63.13.14	Cosecant	997

63.13.15 CosH	998
63.13.16 Cot	998
63.13.17 Cotan	998
63.13.18 Csc	999
63.13.19 CycleToRad	999
63.13.20 DegNormalize	1000
63.13.21 DegToGrad	1000
63.13.22 DegToRad	1000
63.13.23 DivMod	1001
63.13.24 EnsureRange	1001
63.13.25 Floor	1001
63.13.26 Floor64	1002
63.13.27 FMod	1002
63.13.28 Frexp	1003
63.13.29 FutureValue	1003
63.13.30 GetExceptionMask	1004
63.13.31 GetPrecisionMode	1004
63.13.32 GetRoundMode	1004
63.13.33 GradToDeg	1004
63.13.34 GradToRad	1005
63.13.35 Hypot	1005
63.13.36 IfThen	1006
63.13.37 InRange	1006
63.13.38 InterestRate	1006
63.13.39 IntPower	1007
63.13.40 IsInfinite	1007
63.13.41 IsNan	1007
63.13.42 IsZero	1008
63.13.43 Ldexp	1008
63.13.44 LnXP1	1009
63.13.45 Log10	1009
63.13.46 Log2	1010
63.13.47 LogN	1010
63.13.48 Max	1011
63.13.49 MaxIntValue	1011
63.13.50 MaxValue	1012
63.13.51 Mean	1013
63.13.52 MeanAndStdDev	1014
63.13.53 Min	1015
63.13.54 MinIntValue	1015

63.13.55	MinValue	1016
63.13.56	modulus(Float,Float):Float	1017
63.13.57	MomentSkewKurtosis	1017
63.13.58	Norm	1019
63.13.59	NumberOfPeriods	1019
63.13.60	Payment	1020
63.13.61	PopnStdDev	1020
63.13.62	PopnVariance	1021
63.13.63	Power	1022
63.13.64	power(Float,Float):Float	1022
63.13.65	power(Int64,Int64):Int64	1022
63.13.66	PresentValue	1023
63.13.67	RadToCycle	1023
63.13.68	RadToDeg	1023
63.13.69	RadToGrad	1024
63.13.70	RandG	1024
63.13.71	RandomFrom	1025
63.13.72	RandomRange	1025
63.13.73	RoundTo	1026
63.13.74	SameValue	1026
63.13.75	Sec	1026
63.13.76	Secant	1027
63.13.77	SetExceptionMask	1027
63.13.78	SetPrecisionMode	1027
63.13.79	SetRoundMode	1027
63.13.80	Sign	1028
63.13.81	SimpleRoundTo	1028
63.13.82	SinCos	1028
63.13.83	SinH	1029
63.13.84	StdDev	1029
63.13.85	Sum	1030
63.13.86	SumInt	1031
63.13.87	SumOfSquares	1031
63.13.88	SumsAndSquares	1032
63.13.89	Tan	1033
63.13.90	TanH	1034
63.13.91	TotalVariance	1034
63.13.92	Variance	1035
63.14	EInvalidArgument	1037
63.14.1	Description	1037

64 Reference for unit 'matrix'	1038
64.1 Used units	1038
64.2 Overview	1038
64.3 Constants, types and variables	1039
64.3.1 Types	1039
64.4 Procedures and functions	1041
64.4.1 add(Tmatrix2_double,Double):Tmatrix2_double	1041
64.4.2 add(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double	1041
64.4.3 add(Tmatrix2_extended,extended):Tmatrix2_extended	1042
64.4.4 add(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended	1042
64.4.5 add(Tmatrix2_single,single):Tmatrix2_single	1042
64.4.6 add(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single	1042
64.4.7 add(Tmatrix3_double,Double):Tmatrix3_double	1042
64.4.8 add(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double	1043
64.4.9 add(Tmatrix3_extended,extended):Tmatrix3_extended	1043
64.4.10 add(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended	1043
64.4.11 add(Tmatrix3_single,single):Tmatrix3_single	1043
64.4.12 add(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single	1043
64.4.13 add(Tmatrix4_double,Double):Tmatrix4_double	1044
64.4.14 add(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double	1044
64.4.15 add(Tmatrix4_extended,extended):Tmatrix4_extended	1044
64.4.16 add(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended	1044
64.4.17 add(Tmatrix4_single,single):Tmatrix4_single	1044
64.4.18 add(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single	1045
64.4.19 add(Tvector2_double,Double):Tvector2_double	1045
64.4.20 add(Tvector2_double,Tvector2_double):Tvector2_double	1045
64.4.21 add(Tvector2_extended,extended):Tvector2_extended	1045
64.4.22 add(Tvector2_extended,Tvector2_extended):Tvector2_extended	1045
64.4.23 add(Tvector2_single,single):Tvector2_single	1046
64.4.24 add(Tvector2_single,Tvector2_single):Tvector2_single	1046
64.4.25 add(Tvector3_double,Double):Tvector3_double	1046
64.4.26 add(Tvector3_double,Tvector3_double):Tvector3_double	1046
64.4.27 add(Tvector3_extended,extended):Tvector3_extended	1046
64.4.28 add(Tvector3_extended,Tvector3_extended):Tvector3_extended	1047
64.4.29 add(Tvector3_single,single):Tvector3_single	1047
64.4.30 add(Tvector3_single,Tvector3_single):Tvector3_single	1047
64.4.31 add(Tvector4_double,Double):Tvector4_double	1047
64.4.32 add(Tvector4_double,Tvector4_double):Tvector4_double	1047
64.4.33 add(Tvector4_extended,extended):Tvector4_extended	1048
64.4.34 add(Tvector4_extended,Tvector4_extended):Tvector4_extended	1048

64.4.35	add(Tvector4_single,single):Tvector4_single	1048
64.4.36	add(Tvector4_single,Tvector4_single):Tvector4_single	1048
64.4.37	assign(Tmatrix2_double):Tmatrix2_extended	1048
64.4.38	assign(Tmatrix2_double):Tmatrix2_single	1049
64.4.39	assign(Tmatrix2_double):Tmatrix3_double	1049
64.4.40	assign(Tmatrix2_double):Tmatrix3_extended	1049
64.4.41	assign(Tmatrix2_double):Tmatrix3_single	1049
64.4.42	assign(Tmatrix2_double):Tmatrix4_double	1049
64.4.43	assign(Tmatrix2_double):Tmatrix4_extended	1050
64.4.44	assign(Tmatrix2_double):Tmatrix4_single	1050
64.4.45	assign(Tmatrix2_extended):Tmatrix2_double	1050
64.4.46	assign(Tmatrix2_extended):Tmatrix2_single	1050
64.4.47	assign(Tmatrix2_extended):Tmatrix3_double	1051
64.4.48	assign(Tmatrix2_extended):Tmatrix3_extended	1051
64.4.49	assign(Tmatrix2_extended):Tmatrix3_single	1051
64.4.50	assign(Tmatrix2_extended):Tmatrix4_double	1051
64.4.51	assign(Tmatrix2_extended):Tmatrix4_extended	1052
64.4.52	assign(Tmatrix2_extended):Tmatrix4_single	1052
64.4.53	assign(Tmatrix2_single):Tmatrix2_double	1052
64.4.54	assign(Tmatrix2_single):Tmatrix2_extended	1052
64.4.55	assign(Tmatrix2_single):Tmatrix3_double	1052
64.4.56	assign(Tmatrix2_single):Tmatrix3_extended	1053
64.4.57	assign(Tmatrix2_single):Tmatrix3_single	1053
64.4.58	assign(Tmatrix2_single):Tmatrix4_double	1053
64.4.59	assign(Tmatrix2_single):Tmatrix4_extended	1053
64.4.60	assign(Tmatrix2_single):Tmatrix4_single	1053
64.4.61	assign(Tmatrix3_double):Tmatrix2_double	1054
64.4.62	assign(Tmatrix3_double):Tmatrix2_extended	1054
64.4.63	assign(Tmatrix3_double):Tmatrix2_single	1054
64.4.64	assign(Tmatrix3_double):Tmatrix3_extended	1054
64.4.65	assign(Tmatrix3_double):Tmatrix3_single	1054
64.4.66	assign(Tmatrix3_double):Tmatrix4_double	1055
64.4.67	assign(Tmatrix3_double):Tmatrix4_extended	1055
64.4.68	assign(Tmatrix3_double):Tmatrix4_single	1055
64.4.69	assign(Tmatrix3_extended):Tmatrix2_double	1055
64.4.70	assign(Tmatrix3_extended):Tmatrix2_extended	1056
64.4.71	assign(Tmatrix3_extended):Tmatrix2_single	1056
64.4.72	assign(Tmatrix3_extended):Tmatrix3_double	1056
64.4.73	assign(Tmatrix3_extended):Tmatrix3_single	1056
64.4.74	assign(Tmatrix3_extended):Tmatrix4_double	1057

64.4.75	assign(Tmatrix3_extended):Tmatrix4_extended	1057
64.4.76	assign(Tmatrix3_extended):Tmatrix4_single	1057
64.4.77	assign(Tmatrix3_single):Tmatrix2_double	1057
64.4.78	assign(Tmatrix3_single):Tmatrix2_extended	1057
64.4.79	assign(Tmatrix3_single):Tmatrix2_single	1058
64.4.80	assign(Tmatrix3_single):Tmatrix3_double	1058
64.4.81	assign(Tmatrix3_single):Tmatrix3_extended	1058
64.4.82	assign(Tmatrix3_single):Tmatrix4_double	1058
64.4.83	assign(Tmatrix3_single):Tmatrix4_extended	1059
64.4.84	assign(Tmatrix3_single):Tmatrix4_single	1059
64.4.85	assign(Tmatrix4_double):Tmatrix2_double	1059
64.4.86	assign(Tmatrix4_double):Tmatrix2_extended	1059
64.4.87	assign(Tmatrix4_double):Tmatrix2_single	1059
64.4.88	assign(Tmatrix4_double):Tmatrix3_double	1060
64.4.89	assign(Tmatrix4_double):Tmatrix3_extended	1060
64.4.90	assign(Tmatrix4_double):Tmatrix3_single	1060
64.4.91	assign(Tmatrix4_double):Tmatrix4_extended	1060
64.4.92	assign(Tmatrix4_double):Tmatrix4_single	1060
64.4.93	assign(Tmatrix4_extended):Tmatrix2_double	1061
64.4.94	assign(Tmatrix4_extended):Tmatrix2_extended	1061
64.4.95	assign(Tmatrix4_extended):Tmatrix2_single	1061
64.4.96	assign(Tmatrix4_extended):Tmatrix3_double	1061
64.4.97	assign(Tmatrix4_extended):Tmatrix3_extended	1062
64.4.98	assign(Tmatrix4_extended):Tmatrix3_single	1062
64.4.99	assign(Tmatrix4_extended):Tmatrix4_double	1062
64.4.100	assign(Tmatrix4_extended):Tmatrix4_single	1062
64.4.101	assign(Tmatrix4_single):Tmatrix2_double	1062
64.4.102	assign(Tmatrix4_single):Tmatrix2_extended	1063
64.4.103	assign(Tmatrix4_single):Tmatrix2_single	1063
64.4.104	assign(Tmatrix4_single):Tmatrix3_double	1063
64.4.105	assign(Tmatrix4_single):Tmatrix3_extended	1063
64.4.106	assign(Tmatrix4_single):Tmatrix3_single	1064
64.4.107	assign(Tmatrix4_single):Tmatrix4_double	1064
64.4.108	assign(Tmatrix4_single):Tmatrix4_extended	1064
64.4.109	assign(Tvector2_double):Tvector2_extended	1064
64.4.110	assign(Tvector2_double):Tvector2_single	1064
64.4.111	assign(Tvector2_double):Tvector3_double	1065
64.4.112	assign(Tvector2_double):Tvector3_extended	1065
64.4.113	assign(Tvector2_double):Tvector3_single	1065
64.4.114	assign(Tvector2_double):Tvector4_double	1065

64.4.115	assign(Tvector2_double):Tvector4_extended	1065
64.4.116	assign(Tvector2_double):Tvector4_single	1066
64.4.117	assign(Tvector2_extended):Tvector2_double	1066
64.4.118	assign(Tvector2_extended):Tvector2_single	1066
64.4.119	assign(Tvector2_extended):Tvector3_double	1066
64.4.120	assign(Tvector2_extended):Tvector3_extended	1067
64.4.121	assign(Tvector2_extended):Tvector3_single	1067
64.4.122	assign(Tvector2_extended):Tvector4_double	1067
64.4.123	assign(Tvector2_extended):Tvector4_extended	1067
64.4.124	assign(Tvector2_extended):Tvector4_single	1068
64.4.125	assign(Tvector2_single):Tvector2_double	1068
64.4.126	assign(Tvector2_single):Tvector2_extended	1068
64.4.127	assign(Tvector2_single):Tvector3_double	1068
64.4.128	assign(Tvector2_single):Tvector3_extended	1068
64.4.129	assign(Tvector2_single):Tvector3_single	1069
64.4.130	assign(Tvector2_single):Tvector4_double	1069
64.4.131	assign(Tvector2_single):Tvector4_extended	1069
64.4.132	assign(Tvector2_single):Tvector4_single	1069
64.4.133	assign(Tvector3_double):Tvector2_double	1070
64.4.134	assign(Tvector3_double):Tvector2_extended	1070
64.4.135	assign(Tvector3_double):Tvector2_single	1070
64.4.136	assign(Tvector3_double):Tvector3_extended	1070
64.4.137	assign(Tvector3_double):Tvector3_single	1070
64.4.138	assign(Tvector3_double):Tvector4_double	1071
64.4.139	assign(Tvector3_double):Tvector4_extended	1071
64.4.140	assign(Tvector3_double):Tvector4_single	1071
64.4.141	assign(Tvector3_extended):Tvector2_double	1071
64.4.142	assign(Tvector3_extended):Tvector2_extended	1072
64.4.143	assign(Tvector3_extended):Tvector2_single	1072
64.4.144	assign(Tvector3_extended):Tvector3_double	1072
64.4.145	assign(Tvector3_extended):Tvector3_single	1072
64.4.146	assign(Tvector3_extended):Tvector4_double	1073
64.4.147	assign(Tvector3_extended):Tvector4_extended	1073
64.4.148	assign(Tvector3_extended):Tvector4_single	1073
64.4.149	assign(Tvector3_single):Tvector2_double	1073
64.4.150	assign(Tvector3_single):Tvector2_extended	1073
64.4.151	assign(Tvector3_single):Tvector2_single	1074
64.4.152	assign(Tvector3_single):Tvector3_double	1074
64.4.153	assign(Tvector3_single):Tvector3_extended	1074
64.4.154	assign(Tvector3_single):Tvector4_double	1074

64.4.155	assign(Tvector3_single):Tvector4_extended	1075
64.4.156	assign(Tvector3_single):Tvector4_single	1075
64.4.157	assign(Tvector4_double):Tvector2_double	1075
64.4.158	assign(Tvector4_double):Tvector2_extended	1075
64.4.159	assign(Tvector4_double):Tvector2_single	1075
64.4.160	assign(Tvector4_double):Tvector3_double	1076
64.4.161	assign(Tvector4_double):Tvector3_extended	1076
64.4.162	assign(Tvector4_double):Tvector3_single	1076
64.4.163	assign(Tvector4_double):Tvector4_extended	1076
64.4.164	assign(Tvector4_double):Tvector4_single	1077
64.4.165	assign(Tvector4_extended):Tvector2_double	1077
64.4.166	assign(Tvector4_extended):Tvector2_extended	1077
64.4.167	assign(Tvector4_extended):Tvector2_single	1077
64.4.168	assign(Tvector4_extended):Tvector3_double	1078
64.4.169	assign(Tvector4_extended):Tvector3_extended	1078
64.4.170	assign(Tvector4_extended):Tvector3_single	1078
64.4.171	assign(Tvector4_extended):Tvector4_double	1078
64.4.172	assign(Tvector4_extended):Tvector4_single	1079
64.4.173	assign(Tvector4_single):Tvector2_double	1079
64.4.174	assign(Tvector4_single):Tvector2_extended	1079
64.4.175	assign(Tvector4_single):Tvector2_single	1079
64.4.176	assign(Tvector4_single):Tvector3_double	1080
64.4.177	assign(Tvector4_single):Tvector3_extended	1080
64.4.178	assign(Tvector4_single):Tvector3_single	1080
64.4.179	assign(Tvector4_single):Tvector4_double	1080
64.4.180	assign(Tvector4_single):Tvector4_extended	1080
64.4.181	divide(Tmatrix2_double,Double):Tmatrix2_double	1081
64.4.182	divide(Tmatrix2_extended,extended):Tmatrix2_extended	1081
64.4.183	divide(Tmatrix2_single,single):Tmatrix2_single	1081
64.4.184	divide(Tmatrix3_double,Double):Tmatrix3_double	1081
64.4.185	divide(Tmatrix3_extended,extended):Tmatrix3_extended	1081
64.4.186	divide(Tmatrix3_single,single):Tmatrix3_single	1082
64.4.187	divide(Tmatrix4_double,Double):Tmatrix4_double	1082
64.4.188	divide(Tmatrix4_extended,extended):Tmatrix4_extended	1082
64.4.189	divide(Tmatrix4_single,single):Tmatrix4_single	1082
64.4.190	divide(Tvector2_double,Double):Tvector2_double	1082
64.4.191	divide(Tvector2_extended,extended):Tvector2_extended	1083
64.4.192	divide(Tvector2_single,single):Tvector2_single	1083
64.4.193	divide(Tvector3_double,Double):Tvector3_double	1083
64.4.194	divide(Tvector3_extended,extended):Tvector3_extended	1083

64.4.195	<code>divide(Tvector3_single,single):Tvector3_single</code>	1083
64.4.196	<code>divide(Tvector4_double,Double):Tvector4_double</code>	1084
64.4.197	<code>divide(Tvector4_extended,extended):Tvector4_extended</code>	1084
64.4.198	<code>divide(Tvector4_single,single):Tvector4_single</code>	1084
64.4.199	<code>multiply(Tmatrix2_double,Double):Tmatrix2_double</code>	1084
64.4.200	<code>multiply(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double</code>	1084
64.4.201	<code>multiply(Tmatrix2_double,Tvector2_double):Tvector2_double</code>	1085
64.4.202	<code>multiply(Tmatrix2_extended,extended):Tmatrix2_extended</code>	1085
64.4.203	<code>multiply(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended</code>	1085
64.4.204	<code>multiply(Tmatrix2_extended,Tvector2_extended):Tvector2_extended</code>	1085
64.4.205	<code>multiply(Tmatrix2_single,single):Tmatrix2_single</code>	1086
64.4.206	<code>multiply(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single</code>	1086
64.4.207	<code>multiply(Tmatrix2_single,Tvector2_single):Tvector2_single</code>	1086
64.4.208	<code>multiply(Tmatrix3_double,Double):Tmatrix3_double</code>	1086
64.4.209	<code>multiply(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double</code>	1086
64.4.210	<code>multiply(Tmatrix3_double,Tvector3_double):Tvector3_double</code>	1087
64.4.211	<code>multiply(Tmatrix3_extended,extended):Tmatrix3_extended</code>	1087
64.4.212	<code>multiply(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended</code>	1087
64.4.213	<code>multiply(Tmatrix3_extended,Tvector3_extended):Tvector3_extended</code>	1087
64.4.214	<code>multiply(Tmatrix3_single,single):Tmatrix3_single</code>	1088
64.4.215	<code>multiply(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single</code>	1088
64.4.216	<code>multiply(Tmatrix3_single,Tvector3_single):Tvector3_single</code>	1088
64.4.217	<code>multiply(Tmatrix4_double,Double):Tmatrix4_double</code>	1088
64.4.218	<code>multiply(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double</code>	1088
64.4.219	<code>multiply(Tmatrix4_double,Tvector4_double):Tvector4_double</code>	1089
64.4.220	<code>multiply(Tmatrix4_extended,extended):Tmatrix4_extended</code>	1089
64.4.221	<code>multiply(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended</code>	1089
64.4.222	<code>multiply(Tmatrix4_extended,Tvector4_extended):Tvector4_extended</code>	1089
64.4.223	<code>multiply(Tmatrix4_single,single):Tmatrix4_single</code>	1090
64.4.224	<code>multiply(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single</code>	1090
64.4.225	<code>multiply(Tmatrix4_single,Tvector4_single):Tvector4_single</code>	1090
64.4.226	<code>multiply(Tvector2_double,Double):Tvector2_double</code>	1090
64.4.227	<code>multiply(Tvector2_double,Tvector2_double):Tvector2_double</code>	1090
64.4.228	<code>multiply(Tvector2_extended,extended):Tvector2_extended</code>	1091
64.4.229	<code>multiply(Tvector2_extended,Tvector2_extended):Tvector2_extended</code>	1091
64.4.230	<code>multiply(Tvector2_single,single):Tvector2_single</code>	1091
64.4.231	<code>multiply(Tvector2_single,Tvector2_single):Tvector2_single</code>	1091
64.4.232	<code>multiply(Tvector3_double,Double):Tvector3_double</code>	1091
64.4.233	<code>multiply(Tvector3_double,Tvector3_double):Tvector3_double</code>	1092
64.4.234	<code>multiply(Tvector3_extended,extended):Tvector3_extended</code>	1092

64.4.235	multiply(Tvector3_extended,Tvector3_extended):Tvector3_extended . . .	1092
64.4.236	multiply(Tvector3_single,single):Tvector3_single	1092
64.4.237	multiply(Tvector3_single,Tvector3_single):Tvector3_single	1092
64.4.238	multiply(Tvector4_double,Double):Tvector4_double	1093
64.4.239	multiply(Tvector4_double,Tvector4_double):Tvector4_double	1093
64.4.240	multiply(Tvector4_extended,extended):Tvector4_extended	1093
64.4.241	multiply(Tvector4_extended,Tvector4_extended):Tvector4_extended . . .	1093
64.4.242	multiply(Tvector4_single,single):Tvector4_single	1093
64.4.243	multiply(Tvector4_single,Tvector4_single):Tvector4_single	1094
64.4.244	negative(Tmatrix2_double):Tmatrix2_double	1094
64.4.245	negative(Tmatrix2_extended):Tmatrix2_extended	1094
64.4.246	negative(Tmatrix2_single):Tmatrix2_single	1094
64.4.247	negative(Tmatrix3_double):Tmatrix3_double	1094
64.4.248	negative(Tmatrix3_extended):Tmatrix3_extended	1094
64.4.249	negative(Tmatrix3_single):Tmatrix3_single	1095
64.4.250	negative(Tmatrix4_double):Tmatrix4_double	1095
64.4.251	negative(Tmatrix4_extended):Tmatrix4_extended	1095
64.4.252	negative(Tmatrix4_single):Tmatrix4_single	1095
64.4.253	negative(Tvector2_double):Tvector2_double	1095
64.4.254	negative(Tvector2_extended):Tvector2_extended	1095
64.4.255	negative(Tvector2_single):Tvector2_single	1096
64.4.256	negative(Tvector3_double):Tvector3_double	1096
64.4.257	negative(Tvector3_extended):Tvector3_extended	1096
64.4.258	negative(Tvector3_single):Tvector3_single	1096
64.4.259	negative(Tvector4_double):Tvector4_double	1096
64.4.260	negative(Tvector4_extended):Tvector4_extended	1097
64.4.261	negative(Tvector4_single):Tvector4_single	1097
64.4.262	power(Tvector2_double,Tvector2_double):Double	1097
64.4.263	power(Tvector2_extended,Tvector2_extended):extended	1097
64.4.264	power(Tvector2_single,Tvector2_single):single	1097
64.4.265	power(Tvector3_double,Tvector3_double):Double	1098
64.4.266	power(Tvector3_extended,Tvector3_extended):extended	1098
64.4.267	power(Tvector3_single,Tvector3_single):single	1098
64.4.268	power(Tvector4_double,Tvector4_double):Double	1098
64.4.269	power(Tvector4_extended,Tvector4_extended):extended	1098
64.4.270	power(Tvector4_single,Tvector4_single):single	1099
64.4.271	subtract(Tmatrix2_double,Double):Tmatrix2_double	1099
64.4.272	subtract(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double	1099
64.4.273	subtract(Tmatrix2_extended,extended):Tmatrix2_extended	1099
64.4.274	subtract(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended . .	1099

64.4.275	subtract(Tmatrix2_single,single):Tmatrix2_single	1100
64.4.276	subtract(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single	1100
64.4.277	subtract(Tmatrix3_double,Double):Tmatrix3_double	1100
64.4.278	subtract(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double	1100
64.4.279	subtract(Tmatrix3_extended,extended):Tmatrix3_extended	1100
64.4.280	subtract(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended	1101
64.4.281	subtract(Tmatrix3_single,single):Tmatrix3_single	1101
64.4.282	subtract(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single	1101
64.4.283	subtract(Tmatrix4_double,Double):Tmatrix4_double	1101
64.4.284	subtract(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double	1101
64.4.285	subtract(Tmatrix4_extended,extended):Tmatrix4_extended	1102
64.4.286	subtract(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended	1102
64.4.287	subtract(Tmatrix4_single,single):Tmatrix4_single	1102
64.4.288	subtract(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single	1102
64.4.289	subtract(Tvector2_double,Double):Tvector2_double	1102
64.4.290	subtract(Tvector2_double,Tvector2_double):Tvector2_double	1103
64.4.291	subtract(Tvector2_extended,extended):Tvector2_extended	1103
64.4.292	subtract(Tvector2_extended,Tvector2_extended):Tvector2_extended	1103
64.4.293	subtract(Tvector2_single,single):Tvector2_single	1103
64.4.294	subtract(Tvector2_single,Tvector2_single):Tvector2_single	1103
64.4.295	subtract(Tvector3_double,Double):Tvector3_double	1104
64.4.296	subtract(Tvector3_double,Tvector3_double):Tvector3_double	1104
64.4.297	subtract(Tvector3_extended,extended):Tvector3_extended	1104
64.4.298	subtract(Tvector3_extended,Tvector3_extended):Tvector3_extended	1104
64.4.299	subtract(Tvector3_single,single):Tvector3_single	1104
64.4.300	subtract(Tvector3_single,Tvector3_single):Tvector3_single	1105
64.4.301	subtract(Tvector4_double,Double):Tvector4_double	1105
64.4.302	subtract(Tvector4_double,Tvector4_double):Tvector4_double	1105
64.4.303	subtract(Tvector4_extended,extended):Tvector4_extended	1105
64.4.304	subtract(Tvector4_extended,Tvector4_extended):Tvector4_extended	1105
64.4.305	subtract(Tvector4_single,single):Tvector4_single	1106
64.4.306	subtract(Tvector4_single,Tvector4_single):Tvector4_single	1106
64.4.307	symmetricaldifference(Tvector3_double,Tvector3_double):Tvector3_double	1106
64.4.308	symmetricaldifference(Tvector3_extended,Tvector3_extended):Tvector3_extended	1106
64.4.309	symmetricaldifference(Tvector3_single,Tvector3_single):Tvector3_single	1107
64.5	Tmatrix2_double	1107
64.5.1	Description	1107
64.5.2	Method overview	1107
64.5.3	Tmatrix2_double.init_zero	1107
64.5.4	Tmatrix2_double.init_identity	1107

64.5.5	Tmatrix2_double.init	1108
64.5.6	Tmatrix2_double.get_column	1108
64.5.7	Tmatrix2_double.get_row	1108
64.5.8	Tmatrix2_double.set_column	1108
64.5.9	Tmatrix2_double.set_row	1108
64.5.10	Tmatrix2_double.determinant	1108
64.5.11	Tmatrix2_double.inverse	1109
64.5.12	Tmatrix2_double.transpose	1109
64.6	Tmatrix2_extended	1109
64.6.1	Description	1109
64.6.2	Method overview	1109
64.6.3	Tmatrix2_extended.init_zero	1109
64.6.4	Tmatrix2_extended.init_identity	1110
64.6.5	Tmatrix2_extended.init	1110
64.6.6	Tmatrix2_extended.get_column	1110
64.6.7	Tmatrix2_extended.get_row	1110
64.6.8	Tmatrix2_extended.set_column	1110
64.6.9	Tmatrix2_extended.set_row	1110
64.6.10	Tmatrix2_extended.determinant	1111
64.6.11	Tmatrix2_extended.inverse	1111
64.6.12	Tmatrix2_extended.transpose	1111
64.7	Tmatrix2_single	1111
64.7.1	Description	1111
64.7.2	Method overview	1111
64.7.3	Tmatrix2_single.init_zero	1112
64.7.4	Tmatrix2_single.init_identity	1112
64.7.5	Tmatrix2_single.init	1112
64.7.6	Tmatrix2_single.get_column	1112
64.7.7	Tmatrix2_single.get_row	1112
64.7.8	Tmatrix2_single.set_column	1112
64.7.9	Tmatrix2_single.set_row	1113
64.7.10	Tmatrix2_single.determinant	1113
64.7.11	Tmatrix2_single.inverse	1113
64.7.12	Tmatrix2_single.transpose	1113
64.8	Tmatrix3_double	1113
64.8.1	Description	1113
64.8.2	Method overview	1114
64.8.3	Tmatrix3_double.init_zero	1114
64.8.4	Tmatrix3_double.init_identity	1114
64.8.5	Tmatrix3_double.init	1114

64.8.6	Tmatrix3_double.get_column	1114
64.8.7	Tmatrix3_double.get_row	1115
64.8.8	Tmatrix3_double.set_column	1115
64.8.9	Tmatrix3_double.set_row	1115
64.8.10	Tmatrix3_double.determinant	1115
64.8.11	Tmatrix3_double.inverse	1115
64.8.12	Tmatrix3_double.transpose	1115
64.9	Tmatrix3_extended	1116
64.9.1	Description	1116
64.9.2	Method overview	1116
64.9.3	Tmatrix3_extended.init_zero	1116
64.9.4	Tmatrix3_extended.init_identity	1116
64.9.5	Tmatrix3_extended.init	1116
64.9.6	Tmatrix3_extended.get_column	1117
64.9.7	Tmatrix3_extended.get_row	1117
64.9.8	Tmatrix3_extended.set_column	1117
64.9.9	Tmatrix3_extended.set_row	1117
64.9.10	Tmatrix3_extended.determinant	1117
64.9.11	Tmatrix3_extended.inverse	1117
64.9.12	Tmatrix3_extended.transpose	1118
64.10	Tmatrix3_single	1118
64.10.1	Description	1118
64.10.2	Method overview	1118
64.10.3	Tmatrix3_single.init_zero	1118
64.10.4	Tmatrix3_single.init_identity	1118
64.10.5	Tmatrix3_single.init	1119
64.10.6	Tmatrix3_single.get_column	1119
64.10.7	Tmatrix3_single.get_row	1119
64.10.8	Tmatrix3_single.set_column	1119
64.10.9	Tmatrix3_single.set_row	1119
64.10.10	Tmatrix3_single.determinant	1120
64.10.11	Tmatrix3_single.inverse	1120
64.10.12	Tmatrix3_single.transpose	1120
64.11	Tmatrix4_double	1120
64.11.1	Description	1120
64.11.2	Method overview	1120
64.11.3	Tmatrix4_double.init_zero	1121
64.11.4	Tmatrix4_double.init_identity	1121
64.11.5	Tmatrix4_double.init	1121
64.11.6	Tmatrix4_double.get_column	1121

64.11.7	Tmatrix4_double.get_row	1121
64.11.8	Tmatrix4_double.set_column	1122
64.11.9	Tmatrix4_double.set_row	1122
64.11.10	Tmatrix4_double.determinant	1122
64.11.11	Tmatrix4_double.inverse	1122
64.11.12	Tmatrix4_double.transpose	1122
64.12	Tmatrix4_extended	1123
64.12.1	Description	1123
64.12.2	Method overview	1123
64.12.3	Tmatrix4_extended.init_zero	1123
64.12.4	Tmatrix4_extended.init_identity	1123
64.12.5	Tmatrix4_extended.init	1123
64.12.6	Tmatrix4_extended.get_column	1124
64.12.7	Tmatrix4_extended.get_row	1124
64.12.8	Tmatrix4_extended.set_column	1124
64.12.9	Tmatrix4_extended.set_row	1124
64.12.10	Tmatrix4_extended.determinant	1124
64.12.11	Tmatrix4_extended.inverse	1125
64.12.12	Tmatrix4_extended.transpose	1125
64.13	Tmatrix4_single	1125
64.13.1	Description	1125
64.13.2	Method overview	1125
64.13.3	Tmatrix4_single.init_zero	1125
64.13.4	Tmatrix4_single.init_identity	1126
64.13.5	Tmatrix4_single.init	1126
64.13.6	Tmatrix4_single.get_column	1126
64.13.7	Tmatrix4_single.get_row	1126
64.13.8	Tmatrix4_single.set_column	1126
64.13.9	Tmatrix4_single.set_row	1127
64.13.10	Tmatrix4_single.determinant	1127
64.13.11	Tmatrix4_single.inverse	1127
64.13.12	Tmatrix4_single.transpose	1127
64.14	Tvector2_double	1127
64.14.1	Description	1127
64.14.2	Method overview	1128
64.14.3	Tvector2_double.init_zero	1128
64.14.4	Tvector2_double.init_one	1128
64.14.5	Tvector2_double.init	1128
64.14.6	Tvector2_double.length	1128
64.14.7	Tvector2_double.squared_length	1128

64.15	Tvector2_extended	1129
64.15.1	Description	1129
64.15.2	Method overview	1129
64.15.3	Tvector2_extended.init_zero	1129
64.15.4	Tvector2_extended.init_one	1129
64.15.5	Tvector2_extended.init	1129
64.15.6	Tvector2_extended.length	1129
64.15.7	Tvector2_extended.squared_length	1130
64.16	Tvector2_single	1130
64.16.1	Description	1130
64.16.2	Method overview	1130
64.16.3	Tvector2_single.init_zero	1130
64.16.4	Tvector2_single.init_one	1130
64.16.5	Tvector2_single.init	1130
64.16.6	Tvector2_single.length	1131
64.16.7	Tvector2_single.squared_length	1131
64.17	Tvector3_double	1131
64.17.1	Description	1131
64.17.2	Method overview	1131
64.17.3	Tvector3_double.init_zero	1131
64.17.4	Tvector3_double.init_one	1131
64.17.5	Tvector3_double.init	1132
64.17.6	Tvector3_double.length	1132
64.17.7	Tvector3_double.squared_length	1132
64.18	Tvector3_extended	1132
64.18.1	Description	1132
64.18.2	Method overview	1132
64.18.3	Tvector3_extended.init_zero	1132
64.18.4	Tvector3_extended.init_one	1133
64.18.5	Tvector3_extended.init	1133
64.18.6	Tvector3_extended.length	1133
64.18.7	Tvector3_extended.squared_length	1133
64.19	Tvector3_single	1133
64.19.1	Description	1133
64.19.2	Method overview	1133
64.19.3	Tvector3_single.init_zero	1134
64.19.4	Tvector3_single.init_one	1134
64.19.5	Tvector3_single.init	1134
64.19.6	Tvector3_single.length	1134
64.19.7	Tvector3_single.squared_length	1134

64.20	Tvector4_double	1134
64.20.1	Description	1134
64.20.2	Method overview	1135
64.20.3	Tvector4_double.init_zero	1135
64.20.4	Tvector4_double.init_one	1135
64.20.5	Tvector4_double.init	1135
64.20.6	Tvector4_double.length	1135
64.20.7	Tvector4_double.squared_length	1135
64.21	Tvector4_extended	1136
64.21.1	Description	1136
64.21.2	Method overview	1136
64.21.3	Tvector4_extended.init_zero	1136
64.21.4	Tvector4_extended.init_one	1136
64.21.5	Tvector4_extended.init	1136
64.21.6	Tvector4_extended.length	1136
64.21.7	Tvector4_extended.squared_length	1137
64.22	Tvector4_single	1137
64.22.1	Description	1137
64.22.2	Method overview	1137
64.22.3	Tvector4_single.init_zero	1137
64.22.4	Tvector4_single.init_one	1137
64.22.5	Tvector4_single.init	1137
64.22.6	Tvector4_single.length	1138
64.22.7	Tvector4_single.squared_length	1138
65	Reference for unit 'mmx'	1139
65.1	Used units	1139
65.2	Overview	1139
65.3	Constants, types and variables	1139
65.3.1	Constants	1139
65.3.2	Types	1140
65.4	Procedures and functions	1141
65.4.1	emms	1141
65.4.2	femms	1142
66	Reference for unit 'Mouse'	1143
66.1	Used units	1143
66.2	Overview	1143
66.3	Writing a custom mouse driver	1143
66.4	Constants, types and variables	1145
66.4.1	Constants	1145

66.4.2	Types	1146
66.4.3	Variables	1147
66.5	Procedures and functions	1147
66.5.1	DetectMouse	1147
66.5.2	DoneMouse	1148
66.5.3	GetMouseButtons	1148
66.5.4	GetMouseDriver	1149
66.5.5	GetMouseEvent	1149
66.5.6	GetMouseX	1149
66.5.7	GetMouseY	1150
66.5.8	HideMouse	1150
66.5.9	InitMouse	1151
66.5.10	PollMouseEvent	1151
66.5.11	PutMouseEvent	1152
66.5.12	SetMouseDriver	1152
66.5.13	SetMouseXY	1152
66.5.14	ShowMouse	1153
66.6	TMouseDriver	1153
66.7	TMouseEvent	1154
67	Reference for unit 'Objects'	1155
67.1	Used units	1155
67.2	Overview	1155
67.3	Constants, types and variables	1155
67.3.1	Constants	1155
67.3.2	Types	1158
67.3.3	Variables	1160
67.4	Procedures and functions	1160
67.4.1	Abstract	1160
67.4.2	CallPointerConstructor	1161
67.4.3	CallPointerLocal	1161
67.4.4	CallPointerMethod	1161
67.4.5	CallPointerMethodLocal	1162
67.4.6	CallVoidConstructor	1162
67.4.7	CallVoidLocal	1162
67.4.8	CallVoidMethod	1163
67.4.9	CallVoidMethodLocal	1163
67.4.10	DisposeStr	1163
67.4.11	LongDiv	1163
67.4.12	LongMul	1164

67.4.13	NewStr	1164
67.4.14	RegisterObjects	1165
67.4.15	RegisterType	1165
67.4.16	SetStr	1167
67.5	LongRec	1167
67.6	PtrRec	1167
67.7	TStreamRec	1167
67.8	TStrIndexRec	1168
67.9	WordRec	1168
67.10	TBufStream	1168
67.10.1	Description	1168
67.10.2	Method overview	1169
67.10.3	TBufStream.Init	1169
67.10.4	TBufStream.Done	1169
67.10.5	TBufStream.Close	1170
67.10.6	TBufStream.Flush	1170
67.10.7	TBufStream.Truncate	1171
67.10.8	TBufStream.Seek	1171
67.10.9	TBufStream.Open	1171
67.10.10	TBufStream.Read	1172
67.10.11	TBufStream.Write	1172
67.11	TCollection	1172
67.11.1	Description	1172
67.11.2	Method overview	1173
67.11.3	TCollection.Init	1173
67.11.4	TCollection.Load	1173
67.11.5	TCollection.Done	1174
67.11.6	TCollection.At	1174
67.11.7	TCollection.IndexOf	1175
67.11.8	TCollection.GetItem	1176
67.11.9	TCollection.LastThat	1176
67.11.10	TCollection.FirstThat	1177
67.11.11	TCollection.Pack	1178
67.11.12	TCollection.FreeAll	1179
67.11.13	TCollection.DeleteAll	1180
67.11.14	TCollection.Free	1180
67.11.15	TCollection.Insert	1181
67.11.16	TCollection.Delete	1181
67.11.17	TCollection.AtFree	1182
67.11.18	TCollection.FreeItem	1183

67.11.19	TCollection.AtDelete	1183
67.11.20	TCollection.ForEach	1184
67.11.21	TCollection.SetLimit	1185
67.11.22	TCollection.Error	1185
67.11.23	TCollection.AtPut	1185
67.11.24	TCollection.AtInsert	1186
67.11.25	TCollection.Store	1187
67.11.26	TCollection.PutItem	1187
67.12	TDosStream	1187
67.12.1	Description	1187
67.12.2	Method overview	1187
67.12.3	TDosStream.Init	1188
67.12.4	TDosStream.Done	1188
67.12.5	TDosStream.Close	1188
67.12.6	TDosStream.Truncate	1189
67.12.7	TDosStream.Seek	1189
67.12.8	TDosStream.Open	1190
67.12.9	TDosStream.Read	1191
67.12.10	TDosStream.Write	1191
67.13	TMemoryStream	1192
67.13.1	Description	1192
67.13.2	Method overview	1192
67.13.3	TMemoryStream.Init	1192
67.13.4	TMemoryStream.Done	1192
67.13.5	TMemoryStream.Truncate	1193
67.13.6	TMemoryStream.Read	1193
67.13.7	TMemoryStream.Write	1194
67.14	TObject	1194
67.14.1	Description	1194
67.14.2	Method overview	1194
67.14.3	TObject.Init	1194
67.14.4	TObject.Free	1195
67.14.5	TObject.Is_Object	1195
67.14.6	TObject.Done	1195
67.15	TPoint	1196
67.15.1	Description	1196
67.16	TRect	1196
67.16.1	Description	1196
67.16.2	Method overview	1196
67.16.3	TRect.Empty	1196

67.16.4	TRect.Equals	1197
67.16.5	TRect.Contains	1198
67.16.6	TRect.Copy	1198
67.16.7	TRect.Union	1199
67.16.8	TRect.Intersect	1199
67.16.9	TRect.Move	1200
67.16.10	TRect.Grow	1201
67.16.11	TRect.Assign	1201
67.17	TResourceCollection	1202
67.17.1	Description	1202
67.17.2	Method overview	1202
67.17.3	TResourceCollection.KeyOf	1202
67.17.4	TResourceCollection.GetItem	1203
67.17.5	TResourceCollection.FreeItem	1203
67.17.6	TResourceCollection.PutItem	1203
67.18	TResourceFile	1203
67.18.1	Description	1203
67.18.2	Method overview	1204
67.18.3	TResourceFile.Init	1204
67.18.4	TResourceFile.Done	1204
67.18.5	TResourceFile.Count	1204
67.18.6	TResourceFile.KeyAt	1205
67.18.7	TResourceFile.Get	1205
67.18.8	TResourceFile.SwitchTo	1205
67.18.9	TResourceFile.Flush	1205
67.18.10	TResourceFile.Delete	1206
67.18.11	TResourceFile.Put	1206
67.19	TSortedCollection	1206
67.19.1	Description	1206
67.19.2	Method overview	1207
67.19.3	TSortedCollection.Init	1207
67.19.4	TSortedCollection.Load	1207
67.19.5	TSortedCollection.KeyOf	1207
67.19.6	TSortedCollection.IndexOf	1208
67.19.7	TSortedCollection.Compare	1208
67.19.8	TSortedCollection.Search	1209
67.19.9	TSortedCollection.Insert	1210
67.19.10	TSortedCollection.Store	1211
67.20	TStrCollection	1212
67.20.1	Description	1212

67.20.2	Method overview	1212
67.20.3	TStrCollection.Compare	1212
67.20.4	TStrCollection.GetItem	1213
67.20.5	TStrCollection.FreeItem	1213
67.20.6	TStrCollection.PutItem	1213
67.21	TStream	1214
67.21.1	Description	1214
67.21.2	Method overview	1214
67.21.3	TStream.Init	1214
67.21.4	TStream.Get	1214
67.21.5	TStream.StrRead	1215
67.21.6	TStream.GetPos	1216
67.21.7	TStream.GetSize	1216
67.21.8	TStream.ReadStr	1217
67.21.9	TStream.Open	1218
67.21.10	TStream.Close	1218
67.21.11	TStream.Reset	1218
67.21.12	TStream.Flush	1219
67.21.13	TStream.Truncate	1219
67.21.14	TStream.Put	1219
67.21.15	TStream.StrWrite	1220
67.21.16	TStream.WriteStr	1220
67.21.17	TStream.Seek	1220
67.21.18	TStream.Error	1220
67.21.19	TStream.Read	1221
67.21.20	TStream.Write	1221
67.21.21	TStream.CopyFrom	1222
67.22	TStringCollection	1222
67.22.1	Description	1222
67.22.2	Method overview	1223
67.22.3	TStringCollection.GetItem	1223
67.22.4	TStringCollection.Compare	1223
67.22.5	TStringCollection.FreeItem	1224
67.22.6	TStringCollection.PutItem	1224
67.23	TStringList	1224
67.23.1	Description	1224
67.23.2	Method overview	1225
67.23.3	TStringList.Load	1225
67.23.4	TStringList.Done	1225
67.23.5	TStringList.Get	1225

67.24	TStrListMaker	1226
67.24.1	Description	1226
67.24.2	Method overview	1226
67.24.3	TStrListMaker.Init	1226
67.24.4	TStrListMaker.Done	1226
67.24.5	TStrListMaker.Put	1226
67.24.6	TStrListMaker.Store	1227
67.25	TUnSortedStrCollection	1227
67.25.1	Description	1227
67.25.2	Method overview	1227
67.25.3	TUnSortedStrCollection.Insert	1227
68	Reference for unit 'objpas'	1229
68.1	Used units	1229
68.2	Overview	1229
68.3	Constants, types and variables	1229
68.3.1	Constants	1229
68.3.2	Types	1229
69	Reference for unit 'ports'	1231
69.1	Used units	1231
69.2	Overview	1231
69.3	Constants, types and variables	1231
69.3.1	Variables	1231
69.4	tport	1232
69.4.1	Description	1232
69.4.2	Property overview	1232
69.4.3	tport.pp	1232
69.5	tportl	1233
69.5.1	Description	1233
69.5.2	Property overview	1233
69.5.3	tportl.pp	1233
69.6	tportw	1233
69.6.1	Description	1233
69.6.2	Property overview	1233
69.6.3	tportw.pp	1233
70	Reference for unit 'printer'	1234
70.1	Used units	1234
70.2	Overview	1234
70.3	Constants, types and variables	1234

70.3.1	Variables	1234
70.4	Procedures and functions	1234
70.4.1	AssignLst	1234
70.4.2	InitPrinter	1235
70.4.3	IsLstAvailable	1235
71	Reference for unit 'sharemem'	1236
71.1	Used units	1236
71.2	Overview	1236
72	Reference for unit 'Sockets'	1237
72.1	Used units	1237
72.2	Overview	1237
72.3	Constants, types and variables	1237
72.3.1	Constants	1237
72.3.2	Types	1264
72.4	Procedures and functions	1268
72.4.1	Accept	1268
72.4.2	Bind	1269
72.4.3	CloseSocket	1269
72.4.4	Connect	1270
72.4.5	fpaccept	1272
72.4.6	fpbind	1273
72.4.7	fpconnect	1273
72.4.8	fpgetpeername	1275
72.4.9	fpgetsockname	1276
72.4.10	fpgetsockopt	1276
72.4.11	fplisten	1277
72.4.12	fprecv	1277
72.4.13	fprecvfrom	1278
72.4.14	fpsend	1278
72.4.15	fpsendto	1278
72.4.16	fpsetsockopt	1279
72.4.17	fpshutdown	1279
72.4.18	fpsocket	1280
72.4.19	fpsocketpair	1280
72.4.20	HostAddrToStr	1280
72.4.21	HostAddrToStr6	1281
72.4.22	HostToNet	1281
72.4.23	htonl	1281
72.4.24	htons	1281

72.4.25	NetAddrToStr	1282
72.4.26	NetAddrToStr6	1282
72.4.27	NetToHost	1282
72.4.28	NToHl	1282
72.4.29	NToHs	1283
72.4.30	ShortHostToNet	1283
72.4.31	ShortNetToHost	1283
72.4.32	Sock2File	1283
72.4.33	Sock2Text	1284
72.4.34	socketerror	1284
72.4.35	Str2UnixSockAddr	1284
72.4.36	StrToHostAddr	1284
72.4.37	StrToHostAddr6	1285
72.4.38	StrToNetAddr	1285
72.4.39	StrToNetAddr6	1285
72.4.40	TryStrToHostAddr	1285
72.4.41	TryStrToHostAddr6	1286
72.5	linger	1286
72.6	sockaddr_in	1286
72.7	sockaddr_in6	1286
72.8	sockaddr_un	1287
72.9	TUnixSockAddr	1287
72.10	ucred	1287
73	Reference for unit 'Strings'	1288
73.1	Used units	1288
73.2	Overview	1288
73.3	Procedures and functions	1288
73.3.1	stralloc	1288
73.3.2	strcat	1288
73.3.3	strcomp	1289
73.3.4	strcopy	1289
73.3.5	strdispose	1290
73.3.6	strecopy	1291
73.3.7	strend	1291
73.3.8	stricomp	1292
73.3.9	stripos	1292
73.3.10	striscan	1293
73.3.11	strlcat	1293
73.3.12	strlcomp	1294

73.3.13	strcpy	1294
73.3.14	strlen	1295
73.3.15	strlcomp	1295
73.3.16	strlower	1296
73.3.17	strmove	1296
73.3.18	strnew	1297
73.3.19	strpas	1298
73.3.20	strpcopy	1298
73.3.21	strpos	1299
73.3.22	strriscan	1299
73.3.23	strrscan	1300
73.3.24	strscan	1300
73.3.25	strupper	1300

74 Reference for unit 'StrUtils' 1301

74.1	Used units	1301
74.2	Constants, types and variables	1301
74.2.1	Resource strings	1301
74.2.2	Constants	1301
74.2.3	Types	1302
74.3	Procedures and functions	1304
74.3.1	AddChar	1304
74.3.2	AddCharR	1304
74.3.3	AnsiContainsStr	1304
74.3.4	AnsiContainsText	1305
74.3.5	AnsiEndsStr	1305
74.3.6	AnsiEndsText	1305
74.3.7	AnsiIndexStr	1305
74.3.8	AnsiIndexText	1306
74.3.9	AnsiLeftStr	1306
74.3.10	AnsiMatchStr	1306
74.3.11	AnsiMatchText	1307
74.3.12	AnsiMidStr	1307
74.3.13	AnsiProperCase	1307
74.3.14	AnsiReplaceStr	1307
74.3.15	AnsiReplaceText	1308
74.3.16	AnsiResemblesText	1308
74.3.17	AnsiReverseString	1308
74.3.18	AnsiRightStr	1309
74.3.19	AnsiStartsStr	1309

74.3.20	AnsiStartsText	1309
74.3.21	BinToHex	1309
74.3.22	ContainsStr	1310
74.3.23	ContainsText	1310
74.3.24	Copy2Space	1311
74.3.25	Copy2SpaceDel	1311
74.3.26	Copy2Symb	1311
74.3.27	Copy2SymbDel	1312
74.3.28	Dec2Numb	1312
74.3.29	DecodeSoundexInt	1312
74.3.30	DecodeSoundexWord	1312
74.3.31	DelChars	1313
74.3.32	DelSpace	1313
74.3.33	DelSpace1	1313
74.3.34	DupeString	1313
74.3.35	EndsStr	1314
74.3.36	EndsText	1314
74.3.37	ExtractDelimited	1314
74.3.38	ExtractSubstr	1315
74.3.39	ExtractWord	1315
74.3.40	ExtractWordPos	1315
74.3.41	FindMatchesBoyerMooreCaseInsensitive	1316
74.3.42	FindMatchesBoyerMooreCaseSensitive	1316
74.3.43	FindPart	1317
74.3.44	GetCmdLineArg	1317
74.3.45	Hex2Dec	1318
74.3.46	Hex2Dec64	1318
74.3.47	HexToBin	1318
74.3.48	IfThen	1318
74.3.49	in(string.):Boolean	1319
74.3.50	in(UnicodeString.):Boolean	1319
74.3.51	IndexStr	1319
74.3.52	IndexText	1319
74.3.53	IntToBin	1320
74.3.54	IntToRoman	1320
74.3.55	IsEmptyStr	1320
74.3.56	IsWild	1320
74.3.57	IsWordPresent	1321
74.3.58	LeftBStr	1321
74.3.59	LeftStr	1321

74.3.60	MatchStr	1322
74.3.61	MatchText	1322
74.3.62	MidBStr	1322
74.3.63	MidStr	1323
74.3.64	NaturalCompareText	1323
74.3.65	NPos	1323
74.3.66	Numb2Dec	1324
74.3.67	Numb2USA	1324
74.3.68	PadCenter	1324
74.3.69	PadLeft	1324
74.3.70	PadRight	1325
74.3.71	PosEx	1325
74.3.72	PosSet	1325
74.3.73	PosSetEx	1326
74.3.74	RandomFrom	1326
74.3.75	Removeleadingchars	1326
74.3.76	RemovePadChars	1327
74.3.77	RemoveTrailingChars	1327
74.3.78	ReplaceStr	1327
74.3.79	ReplaceText	1327
74.3.80	ResemblesText	1328
74.3.81	ReverseString	1328
74.3.82	RightBStr	1328
74.3.83	RightStr	1328
74.3.84	RomanToInt	1329
74.3.85	RomanToIntDef	1329
74.3.86	RPos	1329
74.3.87	RPosEx	1330
74.3.88	SearchBuf	1330
74.3.89	Soundex	1331
74.3.90	SoundexCompare	1331
74.3.91	SoundexInt	1331
74.3.92	SoundexProc	1332
74.3.93	SoundexSimilar	1332
74.3.94	SoundexWord	1332
74.3.95	SplitCommandLine	1333
74.3.96	SplitString	1333
74.3.97	StartsStr	1333
74.3.98	StartsText	1334
74.3.99	StringReplace	1334

74.3.100	StringsReplace	1334
74.3.101	StuffString	1335
74.3.102	Tab2Space	1335
74.3.103	TrimLeftSet	1336
74.3.104	TrimRightSet	1336
74.3.105	TrimSet	1336
74.3.106	TryRomanToInt	1336
74.3.107	WordCount	1337
74.3.108	WordPosition	1337
74.3.109	XorDecode	1337
74.3.110	XorEncode	1338
74.3.111	XorString	1338
75	Reference for unit 'System'	1339
75.1	Overview	1339
75.2	Unicode and codepage support	1339
75.3	Miscellaneous functions	1340
75.4	Operating System functions	1341
75.5	String handling	1341
75.6	Mathematical routines	1342
75.7	Memory management functions	1343
75.8	File handling functions	1343
75.9	Run-Time Error behaviour	1344
75.10	Constants, types and variables	1344
75.10.1	Constants	1344
75.10.2	Types	1372
75.10.3	Variables	1417
75.11	Procedures and functions	1422
75.11.1	Abs	1422
75.11.2	AbstractError	1423
75.11.3	AcquireExceptionObject	1423
75.11.4	add(variant,variant):variant	1423
75.11.5	AddExitProc	1423
75.11.6	Addr	1424
75.11.7	Align	1424
75.11.8	AllocMem	1425
75.11.9	AnsiToUtf8	1425
75.11.10	Append	1425
75.11.11	ArcTan	1426
75.11.12	ArrayStringToPPchar	1426

75.11.13	Assert	1427
75.11.14	Assign	1427
75.11.15	assign(Comp):olevariant	1428
75.11.16	assign(Comp):variant	1428
75.11.17	assign(extended):olevariant	1428
75.11.18	assign(extended):variant	1428
75.11.19	assign(NativeInt):variant	1428
75.11.20	assign(NativeUInt):variant	1429
75.11.21	assign(olevariant):Comp	1429
75.11.22	assign(olevariant):extended	1429
75.11.23	assign(olevariant):Real	1429
75.11.24	assign(olevariant):single	1429
75.11.25	assign(olevariant):UnicodeString	1429
75.11.26	assign(Real):olevariant	1429
75.11.27	assign(Real):variant	1430
75.11.28	assign(Real48):extended	1430
75.11.29	assign(single):olevariant	1430
75.11.30	assign(single):variant	1430
75.11.31	assign(UCS4String):variant	1430
75.11.32	assign(UnicodeString):olevariant	1430
75.11.33	assign(UnicodeString):variant	1431
75.11.34	assign(UTF8String):variant	1431
75.11.35	assign(variant):Comp	1431
75.11.36	assign(variant):extended	1431
75.11.37	assign(variant):NativeInt	1431
75.11.38	assign(variant):NativeUInt	1431
75.11.39	assign(variant):Real	1431
75.11.40	assign(variant):single	1432
75.11.41	assign(variant):unicodestring	1432
75.11.42	assign(variant):UTF8String	1432
75.11.43	Assigned	1432
75.11.44	BasicEventCreate	1433
75.11.45	BasicEventDestroy	1433
75.11.46	BasicEventResetEvent	1433
75.11.47	BasicEventSetEvent	1433
75.11.48	BasicEventWaitFor	1433
75.11.49	BeginThread	1434
75.11.50	BEToN	1434
75.11.51	BinStr	1434
75.11.52	BlockRead	1435

75.11.53 BlockWrite	1436
75.11.54 Break	1436
75.11.55 BsfByte	1438
75.11.56 BsfDWord	1438
75.11.57 BsfQWord	1438
75.11.58 BsfWord	1439
75.11.59 BsrByte	1439
75.11.60 BsrDWord	1439
75.11.61 BsrQWord	1440
75.11.62 BsrWord	1440
75.11.63 CaptureBacktrace	1440
75.11.64 ChDir	1440
75.11.65 Chr	1441
75.11.66 Close	1441
75.11.67 CloseThread	1442
75.11.68 CompareByte	1442
75.11.69 CompareChar	1443
75.11.70 CompareChar0	1445
75.11.71 CompareDWord	1445
75.11.72 CompareWord	1446
75.11.73 Concat	1447
75.11.74 Continue	1448
75.11.75 Copy	1449
75.11.76 CopyArray	1450
75.11.77 Cos	1450
75.11.78 CSeg	1451
75.11.79 Dec	1451
75.11.80 Default	1452
75.11.81 DefaultAnsi2UnicodeMove	1452
75.11.82 DefaultAnsi2WideMove	1453
75.11.83 DefaultUnicode2AnsiMove	1453
75.11.84 Delete	1453
75.11.85 Dispose	1454
75.11.86 divide(variant,variant):variant	1455
75.11.87 DoneCriticalSection	1455
75.11.88 DoneThread	1455
75.11.89 DSeg	1456
75.11.90 DumpExceptionBacktrace	1456
75.11.91 Dump_Stack	1456
75.11.92 DynArrayBounds	1457

75.11.93 DynArrayClear	1457
75.11.94 DynArrayDim	1457
75.11.95 DynArrayIndex	1457
75.11.96 DynArraySetLength	1458
75.11.97 DynArraySize	1458
75.11.98 EmptyMethod	1458
75.11.99 EndThread	1458
75.11.100EnterCriticalSection	1459
75.11.101EnumResourceLanguages	1459
75.11.102EnumResourceNames	1460
75.11.103EnumResourceTypes	1460
75.11.104EOF	1460
75.11.105EOLn	1461
75.11.106equal(variant,variant):Boolean	1462
75.11.107Erase	1462
75.11.108Error	1463
75.11.109Exclude	1463
75.11.110Exit	1464
75.11.111Exp	1466
75.11.112Fail	1466
75.11.113FilePos	1467
75.11.114FileSize	1468
75.11.115FillByte	1468
75.11.116FillChar	1469
75.11.117FillDWord	1470
75.11.118FillWord	1470
75.11.119Finalize	1471
75.11.120FinalizeArray	1471
75.11.121FindResource	1471
75.11.122FindResourceEx	1472
75.11.123float_raise	1473
75.11.124Flush	1473
75.11.125FlushThread	1474
75.11.126FMADouble	1474
75.11.127FMAExtended	1474
75.11.128FMASingle	1474
75.11.129FPower10	1474
75.11.130Frac	1474
75.11.131FreeLibrary	1475
75.11.132Freemem	1475

75.11.133Freememory	1476
75.11.134FreeResource	1476
75.11.135Get8087CW	1476
75.11.136GetCPUCount	1476
75.11.137GetCurrentThreadId	1477
75.11.138GetDir	1477
75.11.139GetDynLibsManager	1477
75.11.140GetFPCHeapStatus	1478
75.11.141GetHeapStatus	1478
75.11.142GetLoadErrorStr	1478
75.11.143GetMem	1478
75.11.144GetMemory	1479
75.11.145GetMemoryManager	1479
75.11.146GetMXCSR	1479
75.11.147GetProcAddress	1479
75.11.148GetProcedureAddress	1479
75.11.149GetProcessID	1480
75.11.150GetResourceManager	1480
75.11.151GetSSECSR	1480
75.11.152GetTextCodePage	1480
75.11.153GetThreadID	1481
75.11.154GetThreadManager	1481
75.11.155GetTypeKind	1481
75.11.156GetUnicodeStringManager	1481
75.11.157GetVariantManager	1482
75.11.158GetWideStringManager	1482
75.11.159get_caller_addr	1482
75.11.160get_caller_frame	1483
75.11.161get_caller_stackinfo	1483
75.11.162get_cmdline	1483
75.11.163get_frame	1483
75.11.164Get_pc_addr	1484
75.11.165greaterthan(variant,variant):Boolean	1484
75.11.166greaterthanorequal(variant,variant):Boolean	1484
75.11.167Halt	1484
75.11.168HexStr	1485
75.11.169Hi	1485
75.11.170High	1486
75.11.171HINSTANCE	1488
75.11.172Inc	1488

75.11.173Include	1489
75.11.174IndexByte	1489
75.11.175IndexChar	1490
75.11.176IndexChar0	1491
75.11.177IndexDWord	1491
75.11.178IndexQWord	1492
75.11.179Indexword	1492
75.11.180InitCriticalSection	1493
75.11.181Initialize	1493
75.11.182InitializeArray	1495
75.11.183InitThread	1495
75.11.184InitThreadVars	1495
75.11.185Insert	1496
75.11.186Int	1496
75.11.187intdivide(variant,variant):variant	1497
75.11.188InterlockedCompareExchange	1497
75.11.189InterlockedCompareExchange64	1498
75.11.190InterlockedCompareExchangePointer	1498
75.11.191InterlockedDecrement	1498
75.11.192InterlockedDecrement64	1498
75.11.193InterlockedExchange	1498
75.11.194InterlockedExchange64	1499
75.11.195InterlockedExchangeAdd	1499
75.11.196InterlockedExchangeAdd64	1499
75.11.197InterlockedIncrement	1500
75.11.198InterlockedIncrement64	1500
75.11.199IOResult	1500
75.11.200IsDynArrayRectangular	1501
75.11.201IsMemoryManagerSet	1502
75.11.202Is_IntResource	1502
75.11.203KillThread	1502
75.11.204LeaveCriticalSection	1502
75.11.205leftshift(variant,variant):variant	1503
75.11.206Length	1503
75.11.207lessthan(variant,variant):Boolean	1504
75.11.208lessthanorequal(variant,variant):Boolean	1504
75.11.209LEtoN	1504
75.11.210Ln	1505
75.11.211Lo	1505
75.11.212LoadLibrary	1506

75.11.213LoadResource	1506
75.11.214LockResource	1507
75.11.215logicaland(variant,variant):variant	1507
75.11.216logicalnot(variant):variant	1507
75.11.217logicalor(variant,variant):variant	1507
75.11.218logicalxor(variant,variant):variant	1508
75.11.219longjmp	1508
75.11.220Low	1508
75.11.221LowerCase	1509
75.11.222MakeLangID	1509
75.11.223MemSize	1510
75.11.224MkDir	1510
75.11.225modulus(variant,variant):variant	1510
75.11.226Move	1510
75.11.227MoveChar0	1511
75.11.228multiply(variant,variant):variant	1512
75.11.229negative(variant):variant	1512
75.11.230New	1512
75.11.231NtoBE	1513
75.11.232NtoLE	1513
75.11.233Null	1513
75.11.234OctStr	1513
75.11.235Odd	1514
75.11.236Ofs	1514
75.11.237Ord	1515
75.11.238Pack	1516
75.11.239ParamCount	1516
75.11.240ParamStr	1517
75.11.241Pi	1517
75.11.242PopCnt	1518
75.11.243Pos	1518
75.11.244power(variant,variant):variant	1519
75.11.245Pred	1519
75.11.246Prefetch	1520
75.11.247Ptr	1520
75.11.248RaiseList	1521
75.11.249Random	1521
75.11.250Randomize	1522
75.11.251Read	1522
75.11.252ReadBarrier	1523

75.11.253ReadDependencyBarrier	1523
75.11.254ReadLn	1523
75.11.255ReadStr	1524
75.11.256ReadWriteBarrier	1524
75.11.257Real2Double	1525
75.11.258ReAllocMem	1525
75.11.259ReAllocMemory	1526
75.11.260ReleaseExceptionObject	1526
75.11.261Rename	1526
75.11.262Reset	1527
75.11.263ResumeThread	1528
75.11.264Rewrite	1528
75.11.265Rightshift(variant,variant):variant	1529
75.11.266Rmdir	1529
75.11.267RolByte	1530
75.11.268RolDWord	1530
75.11.269RolQWord	1530
75.11.270RolWord	1531
75.11.271RorByte	1531
75.11.272RorDWord	1531
75.11.273RorQWord	1531
75.11.274RorWord	1532
75.11.275Round	1532
75.11.276RTLEventCreate	1532
75.11.277RTLEventDestroy	1533
75.11.278RTLEventResetEvent	1533
75.11.279RTLEventSetEvent	1533
75.11.280RTLEventWaitFor	1534
75.11.281RunError	1534
75.11.282SafeLoadLibrary	1534
75.11.283SarInt64	1535
75.11.284SarLongint	1535
75.11.285SarShortint	1535
75.11.286SarSmallint	1535
75.11.287Seek	1536
75.11.288SeekEOF	1536
75.11.289SeekEOLn	1537
75.11.290Seg	1538
75.11.291Set8087CW	1538
75.11.292SetCodePage	1538

75.11.293SetDynLibsManager	1539
75.11.294Setjmp	1539
75.11.295SetLength	1540
75.11.296SetMemoryManager	1541
75.11.297SetMultiByteConversionCodePage	1541
75.11.298SetMultiByteFileSystemCodePage	1541
75.11.299SetMultiByteRTLFileSystemCodePage	1542
75.11.300SetMXCSR	1542
75.11.301SetResourceManager	1542
75.11.302SetSSECSR	1542
75.11.303SetString	1543
75.11.304SetTextBuf	1543
75.11.305SetTextCodePage	1544
75.11.306SetTextLineEnding	1544
75.11.307SetThreadDebugName	1545
75.11.308SetThreadManager	1545
75.11.309SetUnicodeStringManager	1545
75.11.310SetVariantManager	1546
75.11.311SetWideStringManager	1546
75.11.312ShortCompareText	1546
75.11.313Sin	1547
75.11.314SizeOf	1547
75.11.315SizeofResource	1548
75.11.316Slice	1548
75.11.317Space	1548
75.11.318SPtr	1549
75.11.319Sqr	1549
75.11.320Sqrt	1550
75.11.321SSeg	1550
75.11.322StackTop	1550
75.11.323Str	1551
75.11.324StringCodePage	1552
75.11.325StringElementSize	1553
75.11.326StringOfChar	1553
75.11.327StringRefCount	1553
75.11.328StringToPPChar	1554
75.11.329StringToUnicodeChar	1554
75.11.330StringToWideChar	1554
75.11.331StrLen	1555
75.11.332StrPas	1555

75.11.333subtract(variant,variant):variant	1555
75.11.334Succ	1555
75.11.335SuspendThread	1556
75.11.336Swap	1556
75.11.337SwapEndian	1557
75.11.338SysAllocMem	1557
75.11.339SysAssert	1557
75.11.340SysBacktraceStr	1558
75.11.341SysFlushStdIO	1558
75.11.342SysFreemem	1558
75.11.343SysFreememSize	1558
75.11.344SysGetFPCHeapStatus	1558
75.11.345SysGetHeapStatus	1559
75.11.346SysGetmem	1559
75.11.347SysInitExceptions	1559
75.11.348SysInitFPU	1559
75.11.349SysInitStdIO	1560
75.11.350SysMemSize	1560
75.11.351SysReAllocMem	1560
75.11.352SysResetFPU	1560
75.11.353SysSetCtrlBreakHandler	1560
75.11.354SysTryResizeMem	1561
75.11.355ThreadGetPriority	1561
75.11.356ThreadSetPriority	1561
75.11.357ThreadSwitch	1561
75.11.358ToSingleByteFileSystemEncodedFileName	1562
75.11.359Trunc	1562
75.11.360Truncate	1562
75.11.361TryEnterCriticalSection	1563
75.11.362TypeInfo	1563
75.11.363TypeOf	1564
75.11.364UCS4StringToUnicodeString	1564
75.11.365UCS4StringToWideString	1564
75.11.366Unassigned	1564
75.11.367UnicodeCharLenToString	1564
75.11.368UnicodeCharLenToStrVar	1565
75.11.369UnicodeCharToString	1565
75.11.370UnicodeCharToStrVar	1565
75.11.371UnicodeStringToUCS4String	1566
75.11.372UnicodeToUtf8	1566

75.11.373UniqueString	1566
75.11.374UnloadLibrary	1566
75.11.375UnlockResource	1567
75.11.376UnPack	1567
75.11.377UpCase	1567
75.11.378Utf8CodePointLen	1568
75.11.379UTF8Decode	1568
75.11.380UTF8Encode	1569
75.11.381Utf8ToAnsi	1569
75.11.382UTF8ToString	1569
75.11.383Utf8ToUnicode	1570
75.11.384Val	1570
75.11.385VarArrayGet	1571
75.11.386VarArrayPut	1571
75.11.387VarArrayRedim	1572
75.11.388VarCast	1572
75.11.389WaitForThreadTerminate	1572
75.11.390WideCharLenToString	1572
75.11.391WideCharLenToStrVar	1573
75.11.392WideCharToString	1573
75.11.393WideCharToStrVar	1573
75.11.394WideStringToUCS4String	1574
75.11.395Write	1574
75.11.396WriteBarrier	1575
75.11.397WriteLn	1575
75.11.398WriteStr	1576
75.12 TDoubleRec	1576
75.12.1 Method overview	1577
75.12.2 Property overview	1578
75.12.3 TDoubleRec.Mantissa	1578
75.12.4 TDoubleRec.Fraction	1578
75.12.5 TDoubleRec.Exponent	1578
75.12.6 TDoubleRec.SpecialType	1578
75.12.7 TDoubleRec.BuildUp	1579
75.12.8 TDoubleRec.Sign	1579
75.12.9 TDoubleRec.Exp	1579
75.12.10 TDoubleRec.Frac	1579
75.13 TExtended80Rec	1580
75.13.1 Method overview	1581
75.13.2 Property overview	1581

75.13.3	TExtended80Rec.Mantissa	1581
75.13.4	TExtended80Rec.Fraction	1581
75.13.5	TExtended80Rec.Exponent	1581
75.13.6	TExtended80Rec.SpecialType	1582
75.13.7	TExtended80Rec.BuildUp	1582
75.13.8	TExtended80Rec.Sign	1582
75.13.9	TExtended80Rec.Exp	1582
75.14	tinterfaceentry	1582
75.14.1	Property overview	1583
75.14.2	tinterfaceentry.IID	1583
75.14.3	tinterfaceentry.IIDStr	1583
75.15	TSingleRec	1583
75.15.1	Method overview	1584
75.15.2	Property overview	1585
75.15.3	TSingleRec.Mantissa	1585
75.15.4	TSingleRec.Fraction	1585
75.15.5	TSingleRec.Exponent	1585
75.15.6	TSingleRec.SpecialType	1585
75.15.7	TSingleRec.BuildUp	1586
75.15.8	TSingleRec.Sign	1586
75.15.9	TSingleRec.Exp	1586
75.15.10	TSingleRec.Frac	1586
75.16	TVmt	1586
75.16.1	Property overview	1587
75.16.2	TVmt.vParent	1587
75.17	IDispatch	1588
75.17.1	Description	1588
75.17.2	Method overview	1588
75.17.3	IDispatch.GetTypeInfoCount	1588
75.17.4	IDispatch.GetTypeInfo	1588
75.17.5	IDispatch.GetIDsOfNames	1588
75.17.6	IDispatch.Invoke	1588
75.18	IEnumerable	1589
75.18.1	Description	1589
75.18.2	Method overview	1589
75.18.3	IEnumerable.GetEnumerator	1589
75.19	IEnumerator	1589
75.19.1	Description	1589
75.19.2	Method overview	1590
75.19.3	Property overview	1590

75.19.4	IEnumerator.GetCurrent	1590
75.19.5	IEnumerator.MoveNext	1590
75.19.6	IEnumerator.Reset	1591
75.19.7	IEnumerator.Current	1591
75.20	IInvokable	1591
75.20.1	Description	1591
75.21	IUnknown	1591
75.21.1	Description	1591
75.21.2	Method overview	1591
75.21.3	IUnknown.QueryInterface	1592
75.21.4	IUnknown._AddRef	1592
75.21.5	IUnknown._Release	1592
75.22	TAggregatedObject	1592
75.22.1	Description	1592
75.22.2	Method overview	1592
75.22.3	Property overview	1592
75.22.4	TAggregatedObject.Create	1593
75.22.5	TAggregatedObject.Controller	1593
75.23	TContainedObject	1593
75.23.1	Description	1593
75.23.2	Interfaces overview	1593
75.24	TInterfacedObject	1593
75.24.1	Description	1593
75.24.2	Interfaces overview	1594
75.24.3	Method overview	1594
75.24.4	Property overview	1594
75.24.5	TInterfacedObject.destroy	1594
75.24.6	TInterfacedObject.AfterConstruction	1594
75.24.7	TInterfacedObject.BeforeDestruction	1594
75.24.8	TInterfacedObject.NewInstance	1595
75.24.9	TInterfacedObject.RefCount	1595
75.25	TObject	1595
75.25.1	Description	1595
75.25.2	Method overview	1596
75.25.3	TObject.Create	1596
75.25.4	TObject.Destroy	1597
75.25.5	TObject.newinstance	1597
75.25.6	TObject.FreeInstance	1597
75.25.7	TObject.SafeCallException	1598
75.25.8	TObject.DefaultHandler	1598

75.25.9	TObject.Free	1598
75.25.10	TObject.InitInstance	1598
75.25.11	TObject.CleanupInstance	1599
75.25.12	TObject.ClassType	1599
75.25.13	TObject.ClassInfo	1599
75.25.14	TObject.ClassName	1599
75.25.15	TObject.ClassNameIs	1600
75.25.16	TObject.ClassParent	1600
75.25.17	TObject.InstanceSize	1600
75.25.18	TObject.InheritsFrom	1600
75.25.19	TObject.StringMessageTable	1601
75.25.20	TObject.MethodAddress	1601
75.25.21	TObject.MethodName	1601
75.25.22	TObject.FieldAddress	1601
75.25.23	TObject.AfterConstruction	1602
75.25.24	TObject.BeforeDestruction	1602
75.25.25	TObject.DefaultHandlerStr	1602
75.25.26	TObject.Dispatch	1602
75.25.27	TObject.DispatchStr	1603
75.25.28	TObject.GetInterface	1603
75.25.29	TObject.GetInterfaceByStr	1603
75.25.30	TObject.GetInterfaceWeak	1604
75.25.31	TObject.GetInterfaceEntry	1604
75.25.32	TObject.GetInterfaceEntryByStr	1604
75.25.33	TObject.GetInterfaceTable	1604
75.25.34	TObject.UnitName	1605
75.25.35	TObject.QualifiedClassName	1605
75.25.36	TObject.Equals	1605
75.25.37	TObject.GetHashCode	1605
75.25.38	TObject.ToString	1606
76	Reference for unit 'System.UITypes'	1607
76.1	Used units	1607
76.2	Constants, types and variables	1607
76.2.1	Constants	1607
76.2.2	Types	1608
76.3	TColorRec	1609
76.3.1	Method overview	1614
76.3.2	TColorRec.assign(TColor):TColorRec	1614
76.3.3	TColorRec.assign(TColorRec):TColor	1614

77 Reference for unit 'sysutils'	1615
77.1 Used units	1615
77.2 Overview	1615
77.3 Type Helpers for basic types	1615
77.4 Localization support	1616
77.5 Unicode and codepage awareness	1616
77.6 Miscellaneous conversion routines	1617
77.7 Date/time routines	1618
77.8 File Name handling routines	1618
77.9 File input/output routines	1619
77.10 PChar related functions	1620
77.11 Date and time formatting characters	1621
77.12 Formatting strings	1622
77.13 String functions	1622
77.14 Constants, types and variables	1623
77.14.1 Constants	1623
77.14.2 Types	1630
77.14.3 Variables	1643
77.15 Procedures and functions	1648
77.15.1 AbandonSignalHandler	1648
77.15.2 Abort	1648
77.15.3 AddDisk	1648
77.15.4 AddTerminateProc	1649
77.15.5 AdjustLineBreaks	1649
77.15.6 AnsiCompareFileName	1649
77.15.7 AnsiCompareStr	1650
77.15.8 AnsiCompareText	1651
77.15.9 AnsiDequotedStr	1652
77.15.10 AnsiExtractQuotedStr	1652
77.15.11 AnsiLastChar	1653
77.15.12 AnsiLowerCase	1653
77.15.13 AnsiLowerCaseFileName	1654
77.15.14 AnsiPos	1654
77.15.15 AnsiQuotedStr	1654
77.15.16 AnsiSameStr	1655
77.15.17 AnsiSameText	1655
77.15.18 AnsiStrComp	1655
77.15.19 AnsiStrIComp	1656
77.15.20 AnsiStrLastChar	1657
77.15.21 AnsiStrLComp	1658

77.15.22	AnsiStrLIComp	1658
77.15.23	AnsiStrLower	1659
77.15.24	AnsiStrPos	1660
77.15.25	AnsiStrRScan	1660
77.15.26	AnsiStrScan	1660
77.15.27	AnsiStrUpper	1661
77.15.28	AnsiUpperCase	1661
77.15.29	AnsiUpperCaseFileName	1662
77.15.30	AppendStr	1662
77.15.31	ApplicationName	1663
77.15.32	AssignStr	1663
77.15.33	BCDToInt	1664
77.15.34	Beep	1664
77.15.35	BoolToStr	1665
77.15.36	ByteLength	1665
77.15.37	BytesOf	1665
77.15.38	ByteToCharIndex	1665
77.15.39	ByteToCharLen	1666
77.15.40	ByteType	1666
77.15.41	CallTerminateProcs	1666
77.15.42	ChangeFileExt	1667
77.15.43	CharInSet	1667
77.15.44	CharToByteLen	1667
77.15.45	CheckOSError	1667
77.15.46	CodePageNameToCodePage	1668
77.15.47	CodePageToCodePageName	1668
77.15.48	CompareMem	1668
77.15.49	CompareMemRange	1668
77.15.50	CompareStr	1669
77.15.51	CompareText	1670
77.15.52	ComposeDateTime	1671
77.15.53	ConcatPaths	1671
77.15.54	CreateDir	1671
77.15.55	CreateGUID	1672
77.15.56	CurrentYear	1672
77.15.57	CurrToStr	1673
77.15.58	CurrToStrF	1673
77.15.59	Date	1673
77.15.60	DateTimeToFileDate	1674
77.15.61	DateTimeToStr	1674

77.15.62	DateTimeToString	1675
77.15.63	DateTimeToSystemTime	1676
77.15.64	DateTimeToTimeStamp	1677
77.15.65	DateToStr	1677
77.15.66	DayOfWeek	1678
77.15.67	DecodeDate	1679
77.15.68	DecodeDateFully	1679
77.15.69	DecodeTime	1679
77.15.70	DeleteFile	1680
77.15.71	DirectoryExists	1681
77.15.72	DiskFree	1681
77.15.73	DiskSize	1682
77.15.74	DisposeStr	1682
77.15.75	DoDirSeparators	1682
77.15.76	EncodeDate	1683
77.15.77	EncodeTime	1684
77.15.78	ExceptAddr	1684
77.15.79	ExceptFrameCount	1685
77.15.80	ExceptFrames	1685
77.15.81	ExceptionErrorMessage	1685
77.15.82	ExceptObject	1685
77.15.83	ExcludeLeadingPathDelimiter	1686
77.15.84	ExcludeTrailingBackslash	1686
77.15.85	ExcludeTrailingPathDelimiter	1686
77.15.86	ExecuteProcess	1687
77.15.87	ExeSearch	1687
77.15.88	ExpandFileName	1688
77.15.89	ExpandFileNameCase	1688
77.15.90	ExpandUNCFileName	1689
77.15.91	ExtractFileDir	1690
77.15.92	ExtractFileDrive	1691
77.15.93	ExtractFileExt	1691
77.15.94	ExtractFileName	1691
77.15.95	ExtractFilePath	1692
77.15.96	ExtractRelativePath	1692
77.15.97	ExtractShortPathName	1693
77.15.98	FileAge	1693
77.15.99	FileClose	1694
77.15.100	FileCreate	1694
77.15.101	FileDateToDateTime	1696

77.15.102FileExists	1696
77.15.103FileFlush	1697
77.15.104FileGetAttr	1697
77.15.105FileGetDate	1698
77.15.106FileGetSymLinkTarget	1699
77.15.107FileIsReadOnly	1699
77.15.108FileOpen	1700
77.15.109FileRead	1701
77.15.110FileSearch	1701
77.15.111FileSeek	1702
77.15.112FileSetAttr	1703
77.15.113FileSetDate	1703
77.15.114FileTruncate	1704
77.15.115FileWrite	1704
77.15.116FindClose	1705
77.15.117FindCmdLineSwitch	1705
77.15.118FindFirst	1705
77.15.119FindNext	1707
77.15.120FloattoCurr	1707
77.15.121FloatToDateTime	1707
77.15.122FloatToDecimal	1708
77.15.123FloatToStr	1708
77.15.124FloatToStrF	1709
77.15.125FloatToText	1711
77.15.126FloatToTextFmt	1712
77.15.127FmtStr	1713
77.15.128ForceDirectories	1713
77.15.129Format	1714
77.15.130FormatBuf	1720
77.15.131FormatCurr	1721
77.15.132FormatDateTime	1721
77.15.133FormatFloat	1722
77.15.134FreeAndNil	1723
77.15.135FreeMemAndNil	1724
77.15.136GetAppConfigDir	1724
77.15.137GetAppConfigFile	1725
77.15.138GetCurrentDir	1725
77.15.139GetDirs	1726
77.15.140GetDriveIDFromLetter	1727
77.15.141GetEnvironmentString	1727

77.15.142GetEnvironmentVariable	1727
77.15.143GetEnvironmentVariableCount	1727
77.15.144GetFileAsString	1728
77.15.145GetFileContents	1728
77.15.146GetFileHandle	1729
77.15.147GetLastOSError	1729
77.15.148GetLocalTime	1729
77.15.149GetLocalTimeOffset	1729
77.15.150GetModuleName	1730
77.15.151GetTempDir	1730
77.15.152GetTempFileName	1730
77.15.153GetTickCount	1731
77.15.154GetTickCount64	1731
77.15.155GetUserDir	1731
77.15.156GuidCase	1732
77.15.157GUIDToString	1732
77.15.158HashName	1732
77.15.159HookSignal	1732
77.15.160IncAMonth	1733
77.15.161IncludeLeadingPathDelimiter	1733
77.15.162IncludeTrailingBackslash	1733
77.15.163IncludeTrailingPathDelimiter	1734
77.15.164IncMonth	1734
77.15.165InquireSignal	1735
77.15.166IntToHex	1735
77.15.167IntToStr	1736
77.15.168IsDelimiter	1736
77.15.169IsEqualGUID	1737
77.15.170IsLeadChar	1737
77.15.171IsLeapYear	1737
77.15.172IsPathDelimiter	1738
77.15.173IsValidIdent	1738
77.15.174LastDelimiter	1739
77.15.175LeftStr	1739
77.15.176LoadStr	1740
77.15.177LowerCase	1740
77.15.178MsecsToTimeStamp	1741
77.15.179NewStr	1741
77.15.180Now	1742
77.15.181OutOfMemoryError	1742

77.15.182QuotedStr	1742
77.15.183RaiseLastError	1743
77.15.184RemoveDir	1743
77.15.185RenameFile	1743
77.15.186ReplaceDate	1744
77.15.187ReplaceTime	1744
77.15.188RightStr	1745
77.15.189SafeLoadLibrary	1745
77.15.190SameFileName	1745
77.15.191SameStr	1746
77.15.192SameText	1746
77.15.193SetCurrentDir	1746
77.15.194SetDirSeparators	1747
77.15.195ShowException	1747
77.15.196Sleep	1747
77.15.197SScanf	1748
77.15.198StrAlloc	1749
77.15.199StrBufSize	1749
77.15.200StrByteType	1750
77.15.201strcat	1750
77.15.202StrCharLength	1750
77.15.203strcomp	1751
77.15.204StrCopy	1751
77.15.205StrDispose	1752
77.15.206strecopy	1752
77.15.207strend	1753
77.15.208StrFmt	1753
77.15.209stricomp	1754
77.15.210StringOf	1754
77.15.211StringReplace	1755
77.15.212StringToGUID	1755
77.15.213strlcat	1755
77.15.214strlcomp	1756
77.15.215StrLCopy	1757
77.15.216StrLen	1757
77.15.217StrLFmt	1758
77.15.218strlicomp	1759
77.15.219strlower	1759
77.15.220StrMove	1760
77.15.221strnew	1760

77.15.222StrNextChar	1761
77.15.223StrPas	1761
77.15.224StrPCopy	1761
77.15.225StrPLCopy	1762
77.15.226strpos	1762
77.15.227strscan	1762
77.15.228StrScan	1763
77.15.229StrToBool	1763
77.15.230StrToBoolDef	1764
77.15.231StrToCurr	1764
77.15.232StrToCurrDef	1764
77.15.233StrToDate	1764
77.15.234StrToDateDef	1765
77.15.235StrToDateTime	1766
77.15.236StrToDateTimeDef	1767
77.15.237StrToDWord	1767
77.15.238StrToDWordDef	1767
77.15.239StrToFloat	1768
77.15.240StrToFloatDef	1769
77.15.241StrToInt	1769
77.15.242StrToInt64	1770
77.15.243StrToInt64Def	1770
77.15.244StrToIntDef	1770
77.15.245StrToQWord	1771
77.15.246StrToQWordDef	1771
77.15.247StrToTime	1771
77.15.248StrToTimeDef	1772
77.15.249StrToUInt	1773
77.15.250StrToUInt64	1773
77.15.251StrToUInt64Def	1773
77.15.252StrToUIntDef	1774
77.15.253strupper	1774
77.15.254Supports	1774
77.15.255SysErrorMessage	1775
77.15.256SystemTimeToDateTime	1775
77.15.257TextToFloat	1776
77.15.258Time	1777
77.15.259TimeStampToDateTime	1777
77.15.260TimeStampToMsecs	1778
77.15.261TimeToStr	1778

77.15.262Trim	1779
77.15.263TrimLeft	1779
77.15.264TrimRight	1780
77.15.265TryEncodeDate	1781
77.15.266TryEncodeTime	1781
77.15.267TryFloatToCurr	1781
77.15.268TryStringToGUID	1782
77.15.269TryStrToBool	1782
77.15.270TryStrToCurr	1782
77.15.271TryStrToDate	1783
77.15.272TryStrToDateTime	1783
77.15.273TryStrToDWord	1784
77.15.274TryStrToFloat	1784
77.15.275TryStrToInt	1784
77.15.276TryStrToInt64	1785
77.15.277TryStrToQWord	1785
77.15.278TryStrToTime	1785
77.15.279TryStrToUInt	1786
77.15.280TryStrToUInt64	1786
77.15.281UIntToStr	1786
77.15.282UnhookSignal	1786
77.15.283UnicodeCompareStr	1787
77.15.284UnicodeCompareText	1787
77.15.285UnicodeFmtStr	1787
77.15.286UnicodeFormat	1788
77.15.287UnicodeFormatBuf	1788
77.15.288UnicodeLowerCase	1788
77.15.289UnicodeSameStr	1789
77.15.290UnicodeSameText	1789
77.15.291UnicodeStringReplace	1789
77.15.292UnicodeUpperCase	1790
77.15.293UpperCase	1790
77.15.294VendorName	1790
77.15.295WideBytesOf	1791
77.15.296WideCompareStr	1791
77.15.297WideCompareText	1791
77.15.298WideFmtStr	1792
77.15.299WideFormat	1792
77.15.300WideFormatBuf	1792
77.15.301WideLowerCase	1793

77.15.302WideSameStr	1793
77.15.303WideSameText	1793
77.15.304WideStrAlloc	1793
77.15.305WideStringOf	1794
77.15.306WideStringReplace	1794
77.15.307WideUpperCase	1794
77.15.308WrapText	1795
77.16 TRawbyteSearchRec	1795
77.16.1 Property overview	1795
77.16.2 TRawbyteSearchRec.TimeStamp	1796
77.17 TRawbyteSymLinkRec	1796
77.17.1 Property overview	1796
77.17.2 TRawbyteSymLinkRec.TimeStamp	1796
77.18 TUnicodeSearchRec	1797
77.18.1 Property overview	1797
77.18.2 TUnicodeSearchRec.TimeStamp	1797
77.19 TUnicodeSymLinkRec	1797
77.19.1 Property overview	1798
77.19.2 TUnicodeSymLinkRec.TimeStamp	1798
77.20 EAbort	1798
77.20.1 Description	1798
77.21 EAbstractError	1798
77.21.1 Description	1798
77.22 EAccessViolation	1799
77.22.1 Description	1799
77.23 EArgumentException	1799
77.23.1 Description	1799
77.24 EArgumentNilException	1799
77.24.1 Description	1799
77.25 EArgumentOutOfRangeException	1799
77.25.1 Description	1799
77.26 EAssertionFailed	1799
77.26.1 Description	1799
77.27 EBusError	1800
77.27.1 Description	1800
77.28 EControlC	1800
77.28.1 Description	1800
77.29 EConvertError	1800
77.29.1 Description	1800
77.30 EDirectoryNotFoundException	1800

77.30.1	Description	1800
77.31	EDivByZero	1800
77.31.1	Description	1800
77.32	EEncodingError	1800
77.32.1	Description	1800
77.33	EExternal	1801
77.33.1	Description	1801
77.34	EExternalException	1801
77.34.1	Description	1801
77.35	EFileNotFoundException	1801
77.35.1	Description	1801
77.36	EFormatError	1801
77.36.1	Description	1801
77.37	EHeapMemoryError	1801
77.37.1	Description	1801
77.37.2	Method overview	1801
77.37.3	EHeapMemoryError.FreeInstance	1802
77.38	EInOutError	1802
77.38.1	Description	1802
77.39	EIntError	1802
77.39.1	Description	1802
77.40	EIntfCastError	1802
77.40.1	Description	1802
77.41	EIntOverflow	1802
77.41.1	Description	1802
77.42	EInvalidCast	1802
77.42.1	Description	1802
77.43	EInvalidContainer	1803
77.43.1	Description	1803
77.44	EInvalidInsert	1803
77.44.1	Description	1803
77.45	EInvalidOp	1803
77.45.1	Description	1803
77.46	EInvalidOpException	1803
77.46.1	Description	1803
77.47	EInvalidPointer	1803
77.47.1	Description	1803
77.48	EMathError	1803
77.48.1	Description	1803
77.49	ENoConstructException	1803

77.49.1	Description	1803
77.50	ENoDynLibsSupport	1804
77.50.1	Description	1804
77.51	ENoThreadSupport	1804
77.51.1	Description	1804
77.52	ENotImplemented	1804
77.52.1	Description	1804
77.53	ENotSupportedException	1804
77.53.1	Description	1804
77.54	ENoWideStringSupport	1804
77.54.1	Description	1804
77.55	EObjectCheck	1804
77.55.1	Description	1804
77.56	EOSError	1805
77.56.1	Description	1805
77.57	EOutOfMemory	1805
77.57.1	Description	1805
77.58	EOverflow	1805
77.58.1	Description	1805
77.59	EPackageError	1805
77.59.1	Description	1805
77.60	EPathNotFoundException	1805
77.60.1	Description	1805
77.61	EPathTooLongException	1806
77.61.1	Description	1806
77.62	EPrivilege	1806
77.62.1	Description	1806
77.63	EProgrammerNotFound	1806
77.63.1	Description	1806
77.64	EPropReadOnly	1806
77.64.1	Description	1806
77.65	EPropWriteOnly	1806
77.65.1	Description	1806
77.66	ERangeError	1806
77.66.1	Description	1806
77.67	ESafecallException	1807
77.67.1	Description	1807
77.68	ESigQuit	1807
77.68.1	Description	1807
77.69	EStackOverflow	1807

77.69.1	Description	1807
77.70	EThreadError	1807
77.71	EUnderflow	1807
77.71.1	Description	1807
77.72	EVariantError	1807
77.72.1	Description	1807
77.72.2	Method overview	1807
77.72.3	EVariantError.CreateCode	1807
77.73	Exception	1808
77.73.1	Description	1808
77.73.2	Method overview	1808
77.73.3	Property overview	1808
77.73.4	Exception.Create	1808
77.73.5	Exception.CreateFmt	1809
77.73.6	Exception.CreateRes	1809
77.73.7	Exception.CreateResFmt	1809
77.73.8	Exception.CreateHelp	1809
77.73.9	Exception.CreateFmtHelp	1810
77.73.10	Exception.CreateResHelp	1810
77.73.11	Exception.CreateResFmtHelp	1810
77.73.12	Exception.ToString	1810
77.73.13	Exception.HelpContext	1811
77.73.14	Exception.Message	1811
77.74	EZeroDivide	1811
77.74.1	Description	1811
77.75	IReadWriteSync	1811
77.75.1	Description	1811
77.75.2	Method overview	1811
77.75.3	IReadWriteSync.BeginRead	1812
77.75.4	IReadWriteSync.EndRead	1812
77.75.5	IReadWriteSync.BeginWrite	1812
77.75.6	IReadWriteSync.EndWrite	1812
77.76	TAnsiStringBuilder	1813
77.76.1	Description	1813
77.76.2	Method overview	1813
77.76.3	Property overview	1813
77.76.4	TAnsiStringBuilder.Create	1813
77.76.5	TAnsiStringBuilder.Append	1814
77.76.6	TAnsiStringBuilder.AppendFormat	1815
77.76.7	TAnsiStringBuilder.AppendLine	1815

77.76.8	TAnsiStringBuilder.Clear	1815
77.76.9	TAnsiStringBuilder.CopyTo	1815
77.76.10	TAnsiStringBuilder.EnsureCapacity	1816
77.76.11	TAnsiStringBuilder.Equals	1816
77.76.12	TAnsiStringBuilder.Insert	1816
77.76.13	TAnsiStringBuilder.Remove	1817
77.76.14	TAnsiStringBuilder.Replace	1817
77.76.15	TAnsiStringBuilder.ToString	1818
77.76.16	TAnsiStringBuilder.Chars	1818
77.76.17	TAnsiStringBuilder.Length	1819
77.76.18	TAnsiStringBuilder.Capacity	1819
77.76.19	TAnsiStringBuilder.MaxCapacity	1819
77.77	TBigEndianUnicodeEncoding	1819
77.77.1	Description	1819
77.77.2	Method overview	1820
77.77.3	TBigEndianUnicodeEncoding.Clone	1820
77.77.4	TBigEndianUnicodeEncoding.GetPreamble	1820
77.78	TBooleanHelper	1820
77.78.1	Description	1820
77.78.2	Method overview	1820
77.78.3	TBooleanHelper.Parse	1821
77.78.4	TBooleanHelper.Size	1821
77.78.5	TBooleanHelper.ToString	1821
77.78.6	TBooleanHelper.TryParse	1821
77.78.7	TBooleanHelper.ToInteger	1822
77.79	TByteBoolHelper	1822
77.79.1	Description	1822
77.79.2	Method overview	1822
77.79.3	TByteBoolHelper.Parse	1822
77.79.4	TByteBoolHelper.Size	1822
77.79.5	TByteBoolHelper.ToString	1823
77.79.6	TByteBoolHelper.TryParse	1823
77.79.7	TByteBoolHelper.ToInteger	1823
77.80	TByteHelper	1824
77.80.1	Description	1824
77.80.2	Method overview	1824
77.80.3	TByteHelper.Parse	1824
77.80.4	TByteHelper.Size	1824
77.80.5	TByteHelper.ToString	1825
77.80.6	TByteHelper.TryParse	1825

77.80.7	TByteHelper.ToBoolean	1825
77.80.8	TByteHelper.ToDouble	1825
77.80.9	TByteHelper.ToExtended	1826
77.80.10	TByteHelper.ToBinString	1826
77.80.11	TByteHelper.ToHexString	1826
77.80.12	TByteHelper.ToSingle	1826
77.80.13	TByteHelper.SetBit	1827
77.80.14	TByteHelper.ClearBit	1827
77.80.15	TByteHelper.ToggleBit	1827
77.80.16	TByteHelper.TestBit	1827
77.81	TCardinalHelper	1828
77.81.1	Description	1828
77.81.2	Method overview	1828
77.81.3	TCardinalHelper.Parse	1828
77.81.4	TCardinalHelper.Size	1828
77.81.5	TCardinalHelper.ToString	1829
77.81.6	TCardinalHelper.TryParse	1829
77.81.7	TCardinalHelper.ToBoolean	1829
77.81.8	TCardinalHelper.ToDouble	1829
77.81.9	TCardinalHelper.ToExtended	1830
77.81.10	TCardinalHelper.ToBinString	1830
77.81.11	TCardinalHelper.ToHexString	1830
77.81.12	TCardinalHelper.ToSingle	1830
77.81.13	TCardinalHelper.SetBit	1831
77.81.14	TCardinalHelper.ClearBit	1831
77.81.15	TCardinalHelper.ToggleBit	1831
77.81.16	TCardinalHelper.TestBit	1831
77.82	TDoubleHelper	1832
77.82.1	Description	1832
77.82.2	Method overview	1832
77.82.3	Property overview	1832
77.82.4	TDoubleHelper.IsInfinity	1832
77.82.5	TDoubleHelper.IsNan	1833
77.82.6	TDoubleHelper.IsNegativeInfinity	1833
77.82.7	TDoubleHelper.IsPositiveInfinity	1833
77.82.8	TDoubleHelper.Parse	1833
77.82.9	TDoubleHelper.Size	1834
77.82.10	TDoubleHelper.ToString	1834
77.82.11	TDoubleHelper.TryParse	1835
77.82.12	TDoubleHelper.BuildUp	1835

77.82.13	TDoubleHelper.Exponent	1835
77.82.14	TDoubleHelper.Fraction	1836
77.82.15	TDoubleHelper.Mantissa	1836
77.82.16	TDoubleHelper.SpecialType	1836
77.82.17	TDoubleHelper.Bytes	1836
77.82.18	TDoubleHelper.Words	1837
77.82.19	TDoubleHelper.Sign	1837
77.82.20	TDoubleHelper.Exp	1837
77.82.21	TDoubleHelper.Frac	1837
77.83	TEncoding	1838
77.83.1	Description	1838
77.83.2	Method overview	1838
77.83.3	Property overview	1838
77.83.4	TEncoding.Clone	1838
77.83.5	TEncoding.Convert	1839
77.83.6	TEncoding.IsStandardEncoding	1839
77.83.7	TEncoding.GetBufferEncoding	1839
77.83.8	TEncoding.GetEncoding	1840
77.83.9	TEncoding.GetMaxByteCount	1840
77.83.10	TEncoding.GetMaxCharCount	1840
77.83.11	TEncoding.GetPreamble	1841
77.83.12	TEncoding.GetString	1841
77.83.13	TEncoding.CodePage	1841
77.83.14	TEncoding.EncodingName	1842
77.83.15	TEncoding.IsSingleByte	1842
77.83.16	TEncoding.ANSI	1842
77.83.17	TEncoding.ASCII	1842
77.83.18	TEncoding.BigEndianUnicode	1843
77.83.19	TEncoding.Default	1843
77.83.20	TEncoding.SystemEncoding	1843
77.83.21	TEncoding.Unicode	1843
77.83.22	TEncoding.UTF7	1844
77.83.23	TEncoding.UTF8	1844
77.84	TExtendedHelper	1844
77.84.1	Description	1844
77.84.2	Method overview	1845
77.84.3	Property overview	1845
77.84.4	TExtendedHelper.ToString	1845
77.84.5	TExtendedHelper.Parse	1846
77.84.6	TExtendedHelper.TryParse	1846

77.84.7	TExtendedHelper.IsNan	1847
77.84.8	TExtendedHelper.IsInfinity	1847
77.84.9	TExtendedHelper.IsNegativeInfinity	1847
77.84.10	TExtendedHelper.IsPositiveInfinity	1847
77.84.11	TExtendedHelper.Size	1848
77.84.12	TExtendedHelper.BuildUp	1848
77.84.13	TExtendedHelper.Exponent	1848
77.84.14	TExtendedHelper.Fraction	1848
77.84.15	TExtendedHelper.Mantissa	1849
77.84.16	TExtendedHelper.SpecialType	1849
77.84.17	TExtendedHelper.Bytes	1849
77.84.18	TExtendedHelper.Words	1849
77.84.19	TExtendedHelper.Sign	1850
77.84.20	TExtendedHelper.Exp	1850
77.84.21	TExtendedHelper.Frac	1850
77.85	TGuidHelper	1850
77.85.1	Description	1850
77.85.2	Method overview	1851
77.85.3	TGuidHelper.Create	1851
77.85.4	TGuidHelper.NewGuid	1851
77.85.5	TGuidHelper.ToByteArray	1852
77.85.6	TGuidHelper.ToString	1852
77.86	TInt64Helper	1852
77.86.1	Description	1852
77.86.2	Method overview	1853
77.86.3	TInt64Helper.Parse	1853
77.86.4	TInt64Helper.Size	1853
77.86.5	TInt64Helper.ToString	1853
77.86.6	TInt64Helper.TryParse	1854
77.86.7	TInt64Helper.ToBoolean	1854
77.86.8	TInt64Helper.ToDouble	1854
77.86.9	TInt64Helper.ToExtended	1854
77.86.10	TInt64Helper.ToBinString	1855
77.86.11	TInt64Helper.ToHexString	1855
77.86.12	TInt64Helper.ToSingle	1855
77.86.13	TInt64Helper.SetBit	1855
77.86.14	TInt64Helper.ClearBit	1856
77.86.15	TInt64Helper.ToggleBit	1856
77.86.16	TInt64Helper.TestBit	1856
77.87	TIntegerHelper	1856

77.87.1	Description	1856
77.87.2	Method overview	1857
77.87.3	TIntegerHelper.Size	1857
77.87.4	TIntegerHelper.ToString	1857
77.87.5	TIntegerHelper.Parse	1857
77.87.6	TIntegerHelper.TryParse	1858
77.87.7	TIntegerHelper.ToBoolean	1858
77.87.8	TIntegerHelper.ToDouble	1858
77.87.9	TIntegerHelper.ToExtended	1859
77.87.10	TIntegerHelper.ToBinString	1859
77.87.11	TIntegerHelper.ToHexString	1859
77.87.12	TIntegerHelper.ToSingle	1859
77.87.13	TIntegerHelper.SetBit	1860
77.87.14	TIntegerHelper.ClearBit	1860
77.87.15	TIntegerHelper.ToggleBit	1860
77.87.16	TIntegerHelper.TestBit	1860
77.88	TLongBoolHelper	1861
77.88.1	Description	1861
77.88.2	Method overview	1861
77.88.3	TLongBoolHelper.Parse	1861
77.88.4	TLongBoolHelper.Size	1861
77.88.5	TLongBoolHelper.ToString	1861
77.88.6	TLongBoolHelper.TryToParse	1862
77.88.7	TLongBoolHelper.ToInteger	1862
77.89	TMBCSEncoding	1862
77.89.1	Description	1862
77.89.2	Method overview	1863
77.89.3	TMBCSEncoding.Create	1863
77.89.4	TMBCSEncoding.Clone	1863
77.89.5	TMBCSEncoding.GetMaxByteCount	1863
77.89.6	TMBCSEncoding.GetMaxCharCount	1864
77.89.7	TMBCSEncoding.GetPreamble	1864
77.90	TMREWException	1864
77.90.1	Description	1864
77.91	TMultiReadExclusiveWriteSynchronizer	1864
77.91.1	Description	1864
77.91.2	Interfaces overview	1864
77.91.3	Method overview	1865
77.91.4	Property overview	1865
77.91.5	TMultiReadExclusiveWriteSynchronizer.Create	1865

77.91.6	TMultiReadExclusiveWriteSynchronizer.Destroy	1865
77.91.7	TMultiReadExclusiveWriteSynchronizer.Beginwrite	1865
77.91.8	TMultiReadExclusiveWriteSynchronizer.Endwrite	1866
77.91.9	TMultiReadExclusiveWriteSynchronizer.Beginread	1866
77.91.10	TMultiReadExclusiveWriteSynchronizer.Endread	1866
77.91.11	TMultiReadExclusiveWriteSynchronizer.RevisionLevel	1866
77.91.12	TMultiReadExclusiveWriteSynchronizer.WriterThreadID	1867
77.92	TNativeIntHelper	1867
77.92.1	Description	1867
77.92.2	Method overview	1867
77.92.3	TNativeIntHelper.Parse	1867
77.92.4	TNativeIntHelper.Size	1868
77.92.5	TNativeIntHelper.ToString	1868
77.92.6	TNativeIntHelper.TryParse	1868
77.92.7	TNativeIntHelper.ToBoolean	1868
77.92.8	TNativeIntHelper.ToDouble	1869
77.92.9	TNativeIntHelper.ToExtended	1869
77.92.10	TNativeIntHelper.ToBinString	1869
77.92.11	TNativeIntHelper.ToHexString	1869
77.92.12	TNativeIntHelper.ToSingle	1870
77.92.13	TNativeIntHelper.SetBit	1870
77.92.14	TNativeIntHelper.ClearBit	1870
77.92.15	TNativeIntHelper.ToggleBit	1870
77.92.16	TNativeIntHelper.TestBit	1871
77.93	TNativeUIntHelper	1871
77.93.1	Description	1871
77.93.2	Method overview	1871
77.93.3	TNativeUIntHelper.Parse	1871
77.93.4	TNativeUIntHelper.Size	1872
77.93.5	TNativeUIntHelper.ToString	1872
77.93.6	TNativeUIntHelper.TryParse	1872
77.93.7	TNativeUIntHelper.ToBoolean	1873
77.93.8	TNativeUIntHelper.ToDouble	1873
77.93.9	TNativeUIntHelper.ToExtended	1873
77.93.10	TNativeUIntHelper.ToBinString	1873
77.93.11	TNativeUIntHelper.ToHexString	1873
77.93.12	TNativeUIntHelper.ToSingle	1874
77.93.13	TNativeUIntHelper.SetBit	1874
77.93.14	TNativeUIntHelper.ClearBit	1874
77.93.15	TNativeUIntHelper.ToggleBit	1874

77.93.16	TNativeUIntHelper.TestBit	1875
77.94	TQWordHelper	1875
77.94.1	Description	1875
77.94.2	Method overview	1875
77.94.3	TQWordHelper.Parse	1875
77.94.4	TQWordHelper.Size	1876
77.94.5	TQWordHelper.ToString	1876
77.94.6	TQWordHelper.TryParse	1876
77.94.7	TQWordHelper.ToBoolean	1877
77.94.8	TQWordHelper.ToDouble	1877
77.94.9	TQWordHelper.ToExtended	1877
77.94.10	TQWordHelper.ToBinString	1877
77.94.11	TQWordHelper.ToHexString	1878
77.94.12	TQWordHelper.ToSingle	1878
77.94.13	TQWordHelper.SetBit	1878
77.94.14	TQWordHelper.ClearBit	1878
77.94.15	TQWordHelper.ToggleBit	1879
77.94.16	TQWordHelper.TestBit	1879
77.95	TShortIntHelper	1879
77.95.1	Description	1879
77.95.2	Method overview	1880
77.95.3	TShortIntHelper.Parse	1880
77.95.4	TShortIntHelper.Size	1880
77.95.5	TShortIntHelper.ToString	1880
77.95.6	TShortIntHelper.TryParse	1881
77.95.7	TShortIntHelper.ToBoolean	1881
77.95.8	TShortIntHelper.ToDouble	1881
77.95.9	TShortIntHelper.ToExtended	1881
77.95.10	TShortIntHelper.ToBinString	1882
77.95.11	TShortIntHelper.ToHexString	1882
77.95.12	TShortIntHelper.ToSingle	1882
77.95.13	TShortIntHelper.SetBit	1882
77.95.14	TShortIntHelper.ClearBit	1883
77.95.15	TShortIntHelper.ToggleBit	1883
77.95.16	TShortIntHelper.TestBit	1883
77.96	TSimpleRWSync	1883
77.96.1	Description	1883
77.96.2	Interfaces overview	1884
77.96.3	Method overview	1884
77.96.4	TSimpleRWSync.Create	1884

77.96.5	TSimpleRWSync.Destroy	1884
77.96.6	TSimpleRWSync.Beginwrite	1884
77.96.7	TSimpleRWSync.Endwrite	1885
77.96.8	TSimpleRWSync.Beginread	1885
77.96.9	TSimpleRWSync.Endread	1885
77.97	TSingleHelper	1885
77.97.1	Description	1885
77.97.2	Method overview	1886
77.97.3	Property overview	1886
77.97.4	TSingleHelper.IsNan	1886
77.97.5	TSingleHelper.IsInfinity	1886
77.97.6	TSingleHelper.IsNegativeInfinity	1887
77.97.7	TSingleHelper.IsPositiveInfinity	1887
77.97.8	TSingleHelper.Parse	1887
77.97.9	TSingleHelper.Size	1888
77.97.10	TSingleHelper.ToString	1888
77.97.11	TSingleHelper.TryParse	1889
77.97.12	TSingleHelper.BuildUp	1889
77.97.13	TSingleHelper.Exponent	1889
77.97.14	TSingleHelper.Fraction	1889
77.97.15	TSingleHelper.Mantissa	1890
77.97.16	TSingleHelper.SpecialType	1890
77.97.17	TSingleHelper.Bytes	1890
77.97.18	TSingleHelper.Words	1890
77.97.19	TSingleHelper.Sign	1891
77.97.20	TSingleHelper.Exp	1891
77.97.21	TSingleHelper.Frac	1891
77.98	TSmallIntHelper	1891
77.98.1	Description	1891
77.98.2	Method overview	1892
77.98.3	TSmallIntHelper.Parse	1892
77.98.4	TSmallIntHelper.Size	1892
77.98.5	TSmallIntHelper.ToString	1892
77.98.6	TSmallIntHelper.TryParse	1893
77.98.7	TSmallIntHelper.ToBoolean	1893
77.98.8	TSmallIntHelper.ToBinString	1893
77.98.9	TSmallIntHelper.ToHexString	1893
77.98.10	TSmallIntHelper.ToSingle	1894
77.98.11	TSmallIntHelper.ToDouble	1894
77.98.12	TSmallIntHelper.ToExtended	1894

77.98.13	TSmallIntHelper.SetBit	1894
77.98.14	TSmallIntHelper.ClearBit	1895
77.98.15	TSmallIntHelper.ToggleBit	1895
77.98.16	TSmallIntHelper.TestBit	1895
77.99	TStringHelper	1895
77.99.1	Description	1895
77.99.2	Method overview	1897
77.99.3	Property overview	1898
77.99.4	TStringHelper.Compare	1898
77.99.5	TStringHelper.CompareOrdinal	1899
77.99.6	TStringHelper.CompareText	1899
77.99.7	TStringHelper.Copy	1899
77.99.8	TStringHelper.Create	1900
77.99.9	TStringHelper.EndsWith	1900
77.99.10	TStringHelper.Equals	1900
77.99.11	TStringHelper.Format	1901
77.99.12	TStringHelper.IsNullOrEmpty	1901
77.99.13	TStringHelper.IsNullOrEmptyOrWhiteSpace	1901
77.99.14	TStringHelper.Join	1901
77.99.15	TStringHelper.LowerCase	1902
77.99.16	TStringHelper.Parse	1902
77.99.17	TStringHelper.ToBoolean	1902
77.99.18	TStringHelper.ToDouble	1903
77.99.19	TStringHelper.ToExtended	1903
77.99.20	TStringHelper.ToInt64	1903
77.99.21	TStringHelper.ToInteger	1904
77.99.22	TStringHelper.ToSingle	1904
77.99.23	TStringHelper.UpperCase	1904
77.99.24	TStringHelper.CompareTo	1905
77.99.25	TStringHelper.Contains	1905
77.99.26	TStringHelper.CopyTo	1905
77.99.27	TStringHelper.CountChar	1905
77.99.28	TStringHelper.DeQuotedString	1906
77.99.29	TStringHelper.EndsWith	1906
77.99.30	TStringHelper.GetHashCode	1906
77.99.31	TStringHelper.IndexOf	1906
77.99.32	TStringHelper.IndexOfUnQuoted	1907
77.99.33	TStringHelper.IndexOfAny	1907
77.99.34	TStringHelper.IndexOfAnyUnquoted	1908
77.99.35	TStringHelper.Insert	1908

77.99.36	TStringHelper.IsDelimiter	1909
77.99.37	TStringHelper.IsEmpty	1909
77.99.38	TStringHelper.LastDelimiter	1909
77.99.39	TStringHelper.LastIndexOf	1909
77.99.40	TStringHelper.LastIndexOfAny	1910
77.99.41	TStringHelper.PadLeft	1910
77.99.42	TStringHelper.PadRight	1911
77.99.43	TStringHelper.QuotedString	1911
77.99.44	TStringHelper.Remove	1911
77.99.45	TStringHelper.Replace	1912
77.99.46	TStringHelper.Split	1912
77.99.47	TStringHelper.StartsWith	1913
77.99.48	TStringHelper.Substring	1913
77.99.49	TStringHelper.ToCharArray	1914
77.99.50	TStringHelper.ToLower	1914
77.99.51	TStringHelper.ToLowerInvariant	1914
77.99.52	TStringHelper.ToUpper	1914
77.99.53	TStringHelper.ToUpperInvariant	1915
77.99.54	TStringHelper.Trim	1915
77.99.55	TStringHelper.TrimLeft	1915
77.99.56	TStringHelper.TrimRight	1915
77.99.57	TStringHelper.TrimEnd	1916
77.99.58	TStringHelper.TrimStart	1916
77.99.59	TStringHelper.Chars	1916
77.99.60	TStringHelper.Length	1916
77.100	TUnicodeEncoding	1916
77.100.1	Description	1916
77.100.2	Method overview	1917
77.100.3	TUnicodeEncoding.Create	1917
77.100.4	TUnicodeEncoding.Clone	1917
77.100.5	TUnicodeEncoding.GetMaxByteCount	1917
77.100.6	TUnicodeEncoding.GetMaxCharCount	1917
77.100.7	TUnicodeEncoding.GetPreamble	1918
77.101	TUnicodeStringBuilder	1918
77.101.1	Description	1918
77.101.2	Method overview	1918
77.101.3	Property overview	1918
77.101.4	TUnicodeStringBuilder.Create	1918
77.101.5	TUnicodeStringBuilder.Append	1919
77.101.6	TUnicodeStringBuilder.AppendFormat	1920

77.101.7	TUnicodeStringBuilder.AppendLine	1920
77.101.8	TUnicodeStringBuilder.Clear	1920
77.101.9	TUnicodeStringBuilder.CopyTo	1921
77.101.10	TUnicodeStringBuilder.EnsureCapacity	1921
77.101.11	TUnicodeStringBuilder.Equals	1921
77.101.12	TUnicodeStringBuilder.Insert	1921
77.101.13	TUnicodeStringBuilder.Remove	1922
77.101.14	TUnicodeStringBuilder.Replace	1923
77.101.15	TUnicodeStringBuilder.ToString	1923
77.101.16	TUnicodeStringBuilder.Chars	1923
77.101.17	TUnicodeStringBuilder.Length	1924
77.101.18	TUnicodeStringBuilder.Capacity	1924
77.101.19	TUnicodeStringBuilder.MaxCapacity	1924
77.102	TUTF7Encoding	1925
77.102.1	Description	1925
77.102.2	Method overview	1925
77.102.3	TUTF7Encoding.Create	1925
77.102.4	TUTF7Encoding.Clone	1925
77.102.5	TUTF7Encoding.GetMaxByteCount	1925
77.102.6	TUTF7Encoding.GetMaxCharCount	1926
77.103	TUTF8Encoding	1926
77.103.1	Description	1926
77.103.2	Method overview	1926
77.103.3	TUTF8Encoding.Create	1926
77.103.4	TUTF8Encoding.Clone	1926
77.103.5	TUTF8Encoding.GetMaxByteCount	1927
77.103.6	TUTF8Encoding.GetMaxCharCount	1927
77.103.7	TUTF8Encoding.GetPreamble	1927
77.104	TWordBoolHelper	1927
77.104.1	Description	1927
77.104.2	Method overview	1928
77.104.3	TWordBoolHelper.Parse	1928
77.104.4	TWordBoolHelper.Size	1928
77.104.5	TWordBoolHelper.ToString	1928
77.104.6	TWordBoolHelper.TryToParse	1929
77.104.7	TWordBoolHelper.ToInteger	1929
77.105	TWordHelper	1929
77.105.1	Description	1929
77.105.2	Method overview	1929
77.105.3	TWordHelper.Parse	1930

77.105.4	TWordHelper.Size	1930
77.105.5	TWordHelper.ToString	1930
77.105.6	TWordHelper.TryParse	1930
77.105.7	TWordHelper.ToBoolean	1931
77.105.8	TWordHelper.ToDouble	1931
77.105.9	TWordHelper.ToExtended	1931
77.105.10	TWordHelper.ToBinString	1931
77.105.11	TWordHelper.ToHexString	1932
77.105.12	TWordHelper.ToSingle	1932
77.105.13	TWordHelper.SetBit	1932
77.105.14	TWordHelper.ClearBit	1932
77.105.15	TWordHelper.ToggleBit	1933
77.105.16	TWordHelper.TestBit	1933
78	Reference for unit 'Types'	1934
78.1	Used units	1934
78.2	Overview	1934
78.3	Constants, types and variables	1934
78.3.1	Constants	1934
78.3.2	Types	1939
78.4	Procedures and functions	1945
78.4.1	Bounds	1945
78.4.2	CenterPoint	1946
78.4.3	EqualRect	1946
78.4.4	InflateRect	1946
78.4.5	IntersectRect	1946
78.4.6	IsRectEmpty	1947
78.4.7	OffsetRect	1947
78.4.8	Point	1947
78.4.9	PtInRect	1947
78.4.10	Rect	1948
78.4.11	Size	1948
78.4.12	UnionRect	1948
78.5	TPoint	1948
78.5.1	Method overview	1950
78.5.2	TPoint.Zero	1950
78.5.3	TPoint.Add	1950
78.5.4	TPoint.Distance	1950
78.5.5	TPoint.IsZero	1950
78.5.6	TPoint.Subtract	1950

78.5.7	TPoint.SetLocation	1950
78.5.8	TPoint.Offset	1951
78.5.9	TPoint.PointInCircle	1951
78.5.10	TPoint.equal(TPoint,TPoint):Boolean	1951
78.5.11	TPoint.notequal(TPoint,TPoint):Boolean	1951
78.5.12	TPoint.add(TPoint,TPoint):TPoint	1951
78.5.13	TPoint.subtract(TPoint,TPoint):TPoint	1951
78.5.14	TPoint.assign(TSmallPoint):TPoint	1951
78.5.15	TPoint.explicit(TPoint):TSmallPoint	1951
78.6	TPointF	1952
78.6.1	Method overview	1953
78.6.2	TPointF.Add	1953
78.6.3	TPointF.Distance	1953
78.6.4	TPointF.DotProduct	1953
78.6.5	TPointF.IsZero	1953
78.6.6	TPointF.Subtract	1954
78.6.7	TPointF.SetLocation	1954
78.6.8	TPointF.Offset	1954
78.6.9	TPointF.Scale	1954
78.6.10	TPointF.Ceiling	1954
78.6.11	TPointF.Truncate	1954
78.6.12	TPointF.Floor	1954
78.6.13	TPointF.Round	1954
78.6.14	TPointF.Length	1955
78.6.15	TPointF.Create	1955
78.6.16	TPointF.equal(TPointF,TPointF):Boolean	1955
78.6.17	TPointF.notequal(TPointF,TPointF):Boolean	1955
78.6.18	TPointF.add(TPointF,TPointF):TPointF	1955
78.6.19	TPointF.subtract(TPointF,TPointF):TPointF	1955
78.6.20	TPointF.negative(TPointF):TPointF	1955
78.6.21	TPointF.multiply(TPointF,TPointF):Single	1955
78.6.22	TPointF.multiply(TPointF,single):TPointF	1956
78.6.23	TPointF.multiply(single,TPointF):TPointF	1956
78.7	TRect	1956
78.7.1	Method overview	1957
78.7.2	Property overview	1958
78.7.3	TRect.Create	1958
78.7.4	TRect.equal(TRect,TRect):Boolean	1958
78.7.5	TRect.notequal(TRect,TRect):Boolean	1958
78.7.6	TRect.add(TRect,TRect):TRect	1958

78.7.7	TRect.multiply(TRect,TRect):TRect	1958
78.7.8	TRect.Empty	1958
78.7.9	TRect.NormalizeRect	1958
78.7.10	TRect.IsEmpty	1959
78.7.11	TRect.Contains	1959
78.7.12	TRect.IntersectsWith	1959
78.7.13	TRect.Intersect	1959
78.7.14	TRect.Union	1959
78.7.15	TRect.Offset	1959
78.7.16	TRect.SetLocation	1959
78.7.17	TRect.Inflate	1959
78.7.18	TRect.CenterPoint	1960
78.7.19	TRect.SplitRect	1960
78.7.20	TRect.Height	1960
78.7.21	TRect.Width	1960
78.7.22	TRect.Size	1960
78.7.23	TRect.Location	1960
78.8	TRectF	1960
78.8.1	Method overview	1961
78.8.2	Property overview	1961
78.8.3	TRectF.Union	1961
78.8.4	TRectF.Offset	1961
78.8.5	TRectF.Width	1962
78.8.6	TRectF.Height	1962
78.9	TSize	1962
78.9.1	Method overview	1963
78.9.2	Property overview	1963
78.9.3	TSize.Add	1963
78.9.4	TSize.Distance	1963
78.9.5	TSize.IsZero	1963
78.9.6	TSize.Subtract	1963
78.9.7	TSize.equal(TSize,TSize):Boolean	1963
78.9.8	TSize.notequal(TSize,TSize):Boolean	1963
78.9.9	TSize.add(TSize,TSize):TSize	1964
78.9.10	TSize.subtract(TSize,TSize):TSize	1964
78.9.11	TSize.Width	1964
78.9.12	TSize.Height	1964
78.10	IClassFactory	1964
78.10.1	Description	1964
78.10.2	Method overview	1964

78.10.3	IClassFactory.CreateInstance	1964
78.10.4	IClassFactory.LockServer	1965
78.11	ISequentialStream	1965
78.11.1	Description	1965
78.11.2	Method overview	1965
78.11.3	ISequentialStream.Read	1965
78.11.4	ISequentialStream.Write	1965
78.12	IStream	1965
78.12.1	Description	1965
78.12.2	Method overview	1966
78.12.3	IStream.Seek	1966
78.12.4	IStream.SetSize	1966
78.12.5	IStream.CopyTo	1966
78.12.6	IStream.Commit	1967
78.12.7	IStream.Revert	1967
78.12.8	IStream.LockRegion	1967
78.12.9	IStream.UnlockRegion	1967
78.12.10	IStream.Stat	1968
78.12.11	IStream.Clone	1968
78.13	TBitConverter	1968
78.13.1	Method overview	1968
78.13.2	TBitConverter.UnsafeFrom	1968
78.13.3	TBitConverter.From	1968
78.13.4	TBitConverter.UnsafeInTo	1969
78.13.5	TBitConverter.InTo	1969
79	Reference for unit 'TypeInfo'	1970
79.1	Used units	1970
79.2	Overview	1970
79.3	Auxiliary functions	1970
79.4	Getting or setting property values	1971
79.5	Examining published property information	1971
79.6	Constants, types and variables	1972
79.6.1	Constants	1972
79.6.2	Types	1975
79.7	Procedures and functions	1983
79.7.1	AddEnumElementAliases	1983
79.7.2	AlignPTypeInfo	1983
79.7.3	AlignTParamFlags	1984
79.7.4	AlignTypeData	1984

79.7.5	DerefTypeInfoPtr	1984
79.7.6	FindPropInfo	1984
79.7.7	GetDynArrayProp	1985
79.7.8	GetEnumeratedAliasValue	1986
79.7.9	GetEnumName	1986
79.7.10	GetEnumNameCount	1987
79.7.11	GetEnumProp	1987
79.7.12	GetEnumValue	1988
79.7.13	GetFloatProp	1988
79.7.14	GetInt64Prop	1989
79.7.15	GetInterfaceProp	1990
79.7.16	GetMethodProp	1990
79.7.17	GetObjectProp	1992
79.7.18	GetObjectPropClass	1993
79.7.19	GetOrdProp	1994
79.7.20	GetPropInfo	1995
79.7.21	GetPropInfos	1995
79.7.22	GetPropList	1996
79.7.23	GetPropValue	1997
79.7.24	GetRawByteStrProp	1998
79.7.25	GetRawInterfaceProp	1998
79.7.26	GetSetProp	1998
79.7.27	GetStrProp	2000
79.7.28	GetTypeData	2001
79.7.29	GetUnicodeStrProp	2001
79.7.30	GetVariantProp	2001
79.7.31	GetWideStrProp	2002
79.7.32	IsPublishedProp	2002
79.7.33	IsReadableProp	2003
79.7.34	IsStoredProp	2003
79.7.35	IsWriteableProp	2004
79.7.36	PropIsType	2004
79.7.37	PropType	2005
79.7.38	RemoveEnumElementAliases	2006
79.7.39	SetDynArrayProp	2006
79.7.40	SetEnumProp	2007
79.7.41	SetFloatProp	2007
79.7.42	SetInt64Prop	2007
79.7.43	SetInterfaceProp	2008
79.7.44	SetMethodProp	2008

79.7.45	SetObjectProp	2009
79.7.46	SetOrdProp	2009
79.7.47	SetPropValue	2010
79.7.48	SetRawByteStrProp	2010
79.7.49	SetRawInterfaceProp	2010
79.7.50	SetSetProp	2011
79.7.51	SetStrProp	2011
79.7.52	SetToString	2011
79.7.53	SetUnicodeStrProp	2012
79.7.54	SetVariantProp	2013
79.7.55	SetWideStrProp	2013
79.7.56	StringToSet	2013
79.8	TArrayTypeData	2014
79.8.1	Property overview	2014
79.8.2	TArrayTypeData.ElType	2015
79.8.3	TArrayTypeData.Dims	2015
79.9	TClassData	2015
79.9.1	Property overview	2015
79.9.2	TClassData.UnitName	2015
79.9.3	TClassData.PropertyTable	2016
79.10	TInterfaceData	2016
79.10.1	Property overview	2016
79.10.2	TInterfaceData.UnitName	2017
79.10.3	TInterfaceData.PropertyTable	2017
79.10.4	TInterfaceData.MethodTable	2017
79.11	TInterfaceRawData	2017
79.11.1	Property overview	2018
79.11.2	TInterfaceRawData.UnitName	2018
79.11.3	TInterfaceRawData.IIDStr	2018
79.11.4	TInterfaceRawData.PropertyTable	2018
79.11.5	TInterfaceRawData.MethodTable	2019
79.12	TIntfMethodEntry	2019
79.12.1	Property overview	2020
79.12.2	TIntfMethodEntry.Name	2020
79.12.3	TIntfMethodEntry.Param	2020
79.12.4	TIntfMethodEntry.ResultLocs	2020
79.12.5	TIntfMethodEntry.Tail	2021
79.12.6	TIntfMethodEntry.Next	2021
79.13	TIntfMethodTable	2021
79.13.1	Property overview	2021

79.13.2	TIntfMethodTable.Method	2022
79.14	TManagedField	2022
79.14.1	Property overview	2022
79.14.2	TManagedField.TypeRef	2022
79.15	TParameterLocation	2022
79.15.1	Property overview	2023
79.15.2	TParameterLocation.Reference	2023
79.15.3	TParameterLocation.RegType	2024
79.15.4	TParameterLocation.ShiftVal	2024
79.16	TParameterLocations	2024
79.16.1	Property overview	2024
79.16.2	TParameterLocations.Location	2025
79.16.3	TParameterLocations.Tail	2025
79.17	TProcedureParam	2025
79.17.1	Property overview	2025
79.17.2	TProcedureParam.ParamType	2026
79.17.3	TProcedureParam.Flags	2026
79.18	TProcedureSignature	2026
79.18.1	Method overview	2026
79.18.2	Property overview	2026
79.18.3	TProcedureSignature.GetParam	2027
79.18.4	TProcedureSignature.ResultType	2027
79.19	TPropData	2027
79.19.1	Property overview	2027
79.19.2	TPropData.Prop	2028
79.19.3	TPropData.Tail	2028
79.20	TPropInfo	2028
79.20.1	Property overview	2029
79.20.2	TPropInfo.PropType	2029
79.20.3	TPropInfo.Tail	2029
79.20.4	TPropInfo.Next	2029
79.21	TTypeData	2030
79.21.1	Property overview	2045
79.21.2	TTypeData.BaseType	2045
79.21.3	TTypeData.CompType	2045
79.21.4	TTypeData.ParentInfo	2045
79.21.5	TTypeData.RecInitData	2046
79.21.6	TTypeData.HelperParent	2046
79.21.7	TTypeData.ExtendedInfo	2046
79.21.8	TTypeData.IntfParent	2046

79.21.9	TTypeData.RawIntfParent	2047
79.21.10	TTypeData.IIDStr	2047
79.21.11	TTypeData.ElType2	2047
79.21.12	TTypeData.ElType	2047
79.21.13	TTypeData.InstanceType	2047
79.21.14	TTypeData.RefType	2047
79.22	TVmtFieldEntry	2048
79.22.1	Property overview	2048
79.22.2	TVmtFieldEntry.Tail	2048
79.22.3	TVmtFieldEntry.Next	2048
79.23	TVmtFieldTable	2049
79.23.1	Property overview	2049
79.23.2	TVmtFieldTable.Field	2049
79.24	TVmtMethodParam	2049
79.24.1	Property overview	2050
79.24.2	TVmtMethodParam.Name	2050
79.24.3	TVmtMethodParam.Tail	2050
79.24.4	TVmtMethodParam.Next	2050
79.25	TVmtMethodTable	2051
79.25.1	Property overview	2051
79.25.2	TVmtMethodTable.Entry	2051
79.26	EPropertyConvertError	2051
79.26.1	Description	2051
79.27	EPropertyError	2051
79.27.1	Description	2051
80	Reference for unit 'unicodedata'	2052
80.1	Used units	2052
80.2	Overview	2052
80.3	Constants, types and variables	2053
80.3.1	Resource strings	2053
80.3.2	Constants	2053
80.3.3	Types	2057
80.4	Procedures and functions	2059
80.4.1	AddAliasCollation	2059
80.4.2	BytesToName	2059
80.4.3	BytesToString	2059
80.4.4	CanonicalOrder	2059
80.4.5	CompareSortKey	2060
80.4.6	ComputeSortKey	2060

80.4.7	FilterString	2061
80.4.8	FindCollation	2061
80.4.9	FreeCollation	2061
80.4.10	FromUCS4	2061
80.4.11	GetCollationCount	2062
80.4.12	GetProps	2062
80.4.13	GetPropUCA	2062
80.4.14	IncrementalCompareString	2062
80.4.15	LoadCollation	2063
80.4.16	NormalizeNFD	2064
80.4.17	PrepareCollation	2064
80.4.18	RegisterCollation	2064
80.4.19	ToUCS4	2065
80.4.20	UnicodeIsHighSurrogate	2065
80.4.21	UnicodeIsLowSurrogate	2065
80.4.22	UnicodeIsSurrogatePair	2066
80.4.23	UnicodeToLower	2066
80.4.24	UnicodeToUpper	2066
80.4.25	UnregisterCollation	2067
80.4.26	UnregisterCollations	2067
80.5	TCollationTable	2067
80.5.1	Method overview	2068
80.5.2	Property overview	2068
80.5.3	TCollationTable.NormalizeName	2068
80.5.4	TCollationTable.Clear	2068
80.5.5	TCollationTable.IndexOf	2068
80.5.6	TCollationTable.Find	2068
80.5.7	TCollationTable.Add	2069
80.5.8	TCollationTable.Remove	2069
80.5.9	TCollationTable.Item	2069
80.5.10	TCollationTable.Count	2069
80.5.11	TCollationTable.Capacity	2069
80.6	TUCA_DataBook	2069
80.6.1	Method overview	2070
80.6.2	TUCA_DataBook.IsVariable	2070
80.7	TUCA_PropItemContextRec	2070
80.7.1	Method overview	2071
80.7.2	TUCA_PropItemContextRec.GetCodePoints	2071
80.7.3	TUCA_PropItemContextRec.GetWeights	2071
80.8	TUCA_PropItemContextTreeNodeRec	2071

80.8.1	Method overview	2071
80.8.2	TUCA_PropItemContextTreeNodeRec.GetLeftNode	2071
80.8.3	TUCA_PropItemContextTreeNodeRec.GetRightNode	2072
80.9	TUCA_PropItemContextTreeRec	2072
80.9.1	Method overview	2072
80.9.2	Property overview	2072
80.9.3	TUCA_PropItemContextTreeRec.GetData	2072
80.9.4	TUCA_PropItemContextTreeRec.Find	2072
80.9.5	TUCA_PropItemContextTreeRec.Data	2073
80.10	TUCA_PropItemRec	2073
80.10.1	Method overview	2074
80.10.2	Property overview	2074
80.10.3	TUCA_PropItemRec.HasCodePoint	2074
80.10.4	TUCA_PropItemRec.IsValid	2074
80.10.5	TUCA_PropItemRec.GetWeightArray	2074
80.10.6	TUCA_PropItemRec.GetSelfOnlySize	2074
80.10.7	TUCA_PropItemRec.GetContextual	2075
80.10.8	TUCA_PropItemRec.GetContext	2075
80.10.9	TUCA_PropItemRec.IsDeleted	2075
80.10.10	TUCA_PropItemRec.IsWeightCompress_1	2075
80.10.11	TUCA_PropItemRec.IsWeightCompress_2	2075
80.10.12	TUCA_PropItemRec.CodePoint	2075
80.10.13	TUCA_PropItemRec.Contextual	2076
80.11	TUC_Prop	2076
80.11.1	Property overview	2076
80.11.2	TUC_Prop.Category	2077
80.11.3	TUC_Prop.WhiteSpace	2077
80.11.4	TUC_Prop.HangulSyllable	2077
80.11.5	TUC_Prop.NumericValue	2077
80.12	TUInt24Rec	2077
80.12.1	Method overview	2081
80.12.2	TUInt24Rec.implicit(TUInt24Rec):Cardinal	2082
80.12.3	TUInt24Rec.implicit(TUInt24Rec):LongInt	2082
80.12.4	TUInt24Rec.implicit(TUInt24Rec):Word	2082
80.12.5	TUInt24Rec.implicit(TUInt24Rec):Byte	2082
80.12.6	TUInt24Rec.implicit(Cardinal):TUInt24Rec	2083
80.12.7	TUInt24Rec.equal(TUInt24Rec,TUInt24Rec):Boolean	2083
80.12.8	TUInt24Rec.equal(TUInt24Rec,Cardinal):Boolean	2083
80.12.9	TUInt24Rec.equal(Cardinal,TUInt24Rec):Boolean	2083
80.12.10	TUInt24Rec.equal(TUInt24Rec,LongInt):Boolean	2083

80.12.11	TUInt24Rec.equal(LongInt,TUInt24Rec):Boolean	2084
80.12.12	TUInt24Rec.equal(TUInt24Rec,Word):Boolean	2084
80.12.13	TUInt24Rec.equal(Word,TUInt24Rec):Boolean	2084
80.12.14	TUInt24Rec.equal(TUInt24Rec,Byte):Boolean	2084
80.12.15	TUInt24Rec.equal(Byte,TUInt24Rec):Boolean	2084
80.12.16	TUInt24Rec.notequal(TUInt24Rec,TUInt24Rec):Boolean	2084
80.12.17	TUInt24Rec.notequal(TUInt24Rec,Cardinal):Boolean	2085
80.12.18	TUInt24Rec.notequal(Cardinal,TUInt24Rec):Boolean	2085
80.12.19	TUInt24Rec.greaterthan(TUInt24Rec,TUInt24Rec):Boolean	2085
80.12.20	TUInt24Rec.greaterthan(TUInt24Rec,Cardinal):Boolean	2085
80.12.21	TUInt24Rec.greaterthan(Cardinal,TUInt24Rec):Boolean	2085
80.12.22	TUInt24Rec.greaterthanorequal(TUInt24Rec,TUInt24Rec):Boolean	2086
80.12.23	TUInt24Rec.greaterthanorequal(TUInt24Rec,Cardinal):Boolean	2086
80.12.24	TUInt24Rec.greaterthanorequal(Cardinal,TUInt24Rec):Boolean	2086
80.12.25	TUInt24Rec.less than(TUInt24Rec,TUInt24Rec):Boolean	2086
80.12.26	TUInt24Rec.less than(TUInt24Rec,Cardinal):Boolean	2086
80.12.27	TUInt24Rec.less than(Cardinal,TUInt24Rec):Boolean	2087
80.12.28	TUInt24Rec.less thanorequal(TUInt24Rec,TUInt24Rec):Boolean	2087
80.12.29	TUInt24Rec.less thanorequal(TUInt24Rec,Cardinal):Boolean	2087
80.12.30	TUInt24Rec.less thanorequal(Cardinal,TUInt24Rec):Boolean	2087
81	Reference for unit 'unicodeducet'	2088
81.1	Used units	2088
81.2	Overview	2088
82	Reference for unit 'Unix'	2089
82.1	Used units	2089
82.2	Constants, types and variables	2089
82.2.1	Constants	2089
82.2.2	Types	2095
82.2.3	Variables	2104
82.3	Procedures and functions	2105
82.3.1	AssignPipe	2105
82.3.2	AssignStream	2106
82.3.3	FpExecL	2107
82.3.4	FpExecLE	2108
82.3.5	FpExecLP	2109
82.3.6	FpExecLPE	2110
82.3.7	FpExecV	2110
82.3.8	FpExecVP	2111
82.3.9	FpExecVPE	2112

82.3.10	fpFlock	2113
82.3.11	fpfStatFS	2113
82.3.12	fpfsync	2113
82.3.13	fpgettimeofday	2114
82.3.14	fpStatFS	2114
82.3.15	fpSystem	2114
82.3.16	FSearch	2115
82.3.17	GetDomainName	2116
82.3.18	GetHostName	2116
82.3.19	GetLocalTimezone	2117
82.3.20	GetTimezoneFile	2117
82.3.21	PClose	2117
82.3.22	POpen	2118
82.3.23	ReadTimezoneFile	2119
82.3.24	ReReadLocalTime	2119
82.3.25	SeekDir	2119
82.3.26	TellDir	2120
82.3.27	WaitProcess	2120
82.3.28	WIFSTOPPED	2120
82.3.29	W_EXITCODE	2121
82.3.30	W_STOPCODE	2121
83	Reference for unit 'unixcp'	2122
83.1	Used units	2122
83.2	Overview	2122
83.3	Constants, types and variables	2122
83.3.1	Constants	2122
83.3.2	Types	2125
83.4	Procedures and functions	2125
83.4.1	GetCodepageByName	2125
83.4.2	GetCodepageData	2126
83.4.3	GetSystemCodepage	2126
83.5	TUnixCpData	2126
84	Reference for unit 'unixtype'	2127
84.1	Used units	2127
84.2	Overview	2127
84.3	Constants, types and variables	2127
84.3.1	Constants	2127
84.3.2	Types	2129
84.4	mbstate_t	2139

84.5	pthread_attr_t	2139
84.6	pthread_condattr_t	2139
84.7	pthread_cond_t	2140
84.8	pthread_mutexattr_t	2140
84.9	pthread_rwlockattr_t	2140
84.10	sched_param	2140
84.11	sem_t	2140
84.12	timespec	2141
84.13	timeval	2141
84.14	TStatfs	2141
84.15	_pthread_fastlock	2142
85	Reference for unit 'unixutil'	2143
85.1	Used units	2143
85.2	Overview	2143
85.3	Constants, types and variables	2143
85.3.1	Variables	2143
85.4	Procedures and functions	2143
85.4.1	ArrayStringToPPchar	2143
85.4.2	EpochToLocal	2144
85.4.3	GregorianToJulian	2144
85.4.4	JulianToGregorian	2145
85.4.5	LocalToEpoch	2145
85.4.6	StringToPPChar	2145
86	Reference for unit 'Variants'	2147
86.1	Used units	2147
86.2	Overview	2147
86.3	Constants, types and variables	2147
86.3.1	Constants	2147
86.3.2	Types	2148
86.3.3	Variables	2150
86.4	Procedures and functions	2152
86.4.1	DynArrayFromVariant	2152
86.4.2	DynArrayToVariant	2152
86.4.3	FindCustomVariantType	2152
86.4.4	FindVarData	2153
86.4.5	GetPropValue	2153
86.4.6	GetVariantProp	2153
86.4.7	HandleConversionException	2154
86.4.8	Null	2154

86.4.9	SetClearVarToEmptyParam	2154
86.4.10	SetPropValue	2154
86.4.11	SetVariantProp	2155
86.4.12	Unassigned	2155
86.4.13	VarArrayAsPSafeArray	2155
86.4.14	VarArrayCreate	2155
86.4.15	VarArrayCreateError	2156
86.4.16	VarArrayDimCount	2156
86.4.17	VarArrayHighBound	2157
86.4.18	VarArrayLock	2157
86.4.19	VarArrayLockedError	2157
86.4.20	VarArrayLowBound	2158
86.4.21	VarArrayOf	2158
86.4.22	VarArrayRef	2158
86.4.23	VarArrayUnlock	2158
86.4.24	VarAsError	2159
86.4.25	VarAsType	2159
86.4.26	VarBadIndexError	2159
86.4.27	VarBadTypeError	2159
86.4.28	VarCastError	2160
86.4.29	VarCastErrorOle	2160
86.4.30	VarCheckEmpty	2160
86.4.31	VarClear	2160
86.4.32	VarCompareValue	2161
86.4.33	VarCopyNoInd	2161
86.4.34	VarEnsureRange	2161
86.4.35	VarFromDateTime	2161
86.4.36	VarInRange	2162
86.4.37	VarInvalidArgError	2162
86.4.38	VarInvalidNullOp	2162
86.4.39	VarInvalidOp	2162
86.4.40	VarIsArray	2163
86.4.41	VarIsBool	2163
86.4.42	VarIsByRef	2163
86.4.43	VarIsClear	2163
86.4.44	VarIsCustom	2164
86.4.45	VarIsEmpty	2164
86.4.46	VarIsEmptyParam	2164
86.4.47	VarIsError	2164
86.4.48	VarIsFloat	2165

86.4.49	VarIsNull	2165
86.4.50	VarIsNumeric	2165
86.4.51	VarIsOrdinal	2165
86.4.52	VarIsStr	2166
86.4.53	VarIsType	2166
86.4.54	VarNotImplError	2166
86.4.55	VarOutOfMemoryError	2166
86.4.56	VarOverflowError	2167
86.4.57	VarRangeCheckError	2167
86.4.58	VarResultCheck	2167
86.4.59	VarSameValue	2167
86.4.60	VarSupports	2168
86.4.61	VarToDateTime	2168
86.4.62	VarToStr	2168
86.4.63	VarToStrDef	2168
86.4.64	VarToUnicodeStr	2169
86.4.65	VarToUnicodeStrDef	2169
86.4.66	VarToWideStr	2169
86.4.67	VarToWideStrDef	2169
86.4.68	VarType	2170
86.4.69	VarTypeAsText	2170
86.4.70	VarTypeDeRef	2170
86.4.71	VarTypeIsValidArrayType	2170
86.4.72	VarTypeIsValidElementType	2171
86.4.73	VarUnexpectedError	2171
86.5	EVariantArrayCreateError	2171
86.5.1	Description	2171
86.6	EVariantArrayLockedError	2171
86.6.1	Description	2171
86.7	EVariantBadIndexError	2172
86.7.1	Description	2172
86.8	EVariantBadVarTypeError	2172
86.8.1	Description	2172
86.9	EVariantDispatchError	2172
86.9.1	Description	2172
86.10	EVariantInvalidArgError	2172
86.10.1	Description	2172
86.11	EVariantInvalidNullOpError	2172
86.11.1	Description	2172
86.12	EVariantInvalidOpError	2172

86.12.1	Description	2172
86.13	EVariantNotAnArrayError	2173
86.13.1	Description	2173
86.14	EVariantNotImplError	2173
86.14.1	Description	2173
86.15	EVariantOutOfMemoryError	2173
86.15.1	Description	2173
86.16	EVariantOverflowError	2173
86.16.1	Description	2173
86.17	EVariantParamNotFound	2173
86.17.1	Description	2173
86.18	EVariantRangeCheckError	2173
86.18.1	Description	2173
86.19	EVariantTypeCastError	2174
86.19.1	Description	2174
86.20	EVariantUnexpectedError	2174
86.20.1	Description	2174
86.21	IVarInstanceReference	2174
86.21.1	Description	2174
86.21.2	Method overview	2174
86.21.3	IVarInstanceReference.GetInstance	2174
86.22	IVarInvokeable	2175
86.22.1	Description	2175
86.22.2	Method overview	2175
86.22.3	IVarInvokeable.DoFunction	2175
86.22.4	IVarInvokeable.DoProcedure	2175
86.22.5	IVarInvokeable.GetProperty	2176
86.22.6	IVarInvokeable.SetProperty	2176
86.23	TCustomVariantType	2176
86.23.1	Description	2176
86.23.2	Interfaces overview	2177
86.23.3	Method overview	2177
86.23.4	Property overview	2177
86.23.5	TCustomVariantType.Create	2177
86.23.6	TCustomVariantType.Destroy	2177
86.23.7	TCustomVariantType.IsClear	2178
86.23.8	TCustomVariantType.Cast	2178
86.23.9	TCustomVariantType.CastTo	2178
86.23.10	TCustomVariantType.CastToOle	2178
86.23.11	TCustomVariantType.Clear	2179

86.23.12	TCustomVariantType.Copy	2179
86.23.13	TCustomVariantType.BinaryOp	2179
86.23.14	TCustomVariantType.UnaryOp	2180
86.23.15	TCustomVariantType.CompareOp	2180
86.23.16	TCustomVariantType.Compare	2180
86.23.17	TCustomVariantType.VarType	2181
86.24	TInvokeableVariantType	2181
86.24.1	Description	2181
86.24.2	Interfaces overview	2181
86.24.3	Method overview	2181
86.24.4	TInvokeableVariantType.DoFunction	2181
86.24.5	TInvokeableVariantType.DoProcedure	2182
86.24.6	TInvokeableVariantType.GetProperty	2182
86.24.7	TInvokeableVariantType.SetProperty	2182
86.25	TPublishableVariantType	2183
86.25.1	Description	2183
86.25.2	Interfaces overview	2183
86.25.3	Method overview	2183
86.25.4	TPublishableVariantType.GetProperty	2183
86.25.5	TPublishableVariantType.SetProperty	2183
87	Reference for unit 'video'	2184
87.1	Used units	2184
87.2	Overview	2184
87.3	Examples utility unit	2185
87.4	Writing a custom video driver	2186
87.5	Constants, types and variables	2189
87.5.1	Constants	2189
87.5.2	Types	2193
87.5.3	Variables	2194
87.6	Procedures and functions	2195
87.6.1	ClearScreen	2195
87.6.2	DefaultErrorHandler	2196
87.6.3	DoneVideo	2196
87.6.4	GetCapabilities	2196
87.6.5	GetCursorType	2197
87.6.6	GetLockScreenCount	2198
87.6.7	GetVideoDriver	2199
87.6.8	GetVideoMode	2199
87.6.9	GetVideoModeCount	2200

87.6.10	GetVideoModeData	2201
87.6.11	InitVideo	2201
87.6.12	LockScreenUpdate	2202
87.6.13	SetCursorPos	2202
87.6.14	SetCursorType	2203
87.6.15	SetVideoDriver	2204
87.6.16	SetVideoMode	2204
87.6.17	UnlockScreenUpdate	2204
87.6.18	UpdateScreen	2205
87.7	TVideoDriver	2205
87.8	TVideoMode	2206
88	Reference for unit 'WinCRT'	2207
88.1	Used units	2207
88.2	Overview	2207
88.3	Constants, types and variables	2207
88.3.1	Variables	2207
88.4	Procedures and functions	2207
88.4.1	delay	2207
88.4.2	keypressed	2208
88.4.3	nosound	2208
88.4.4	readkey	2208
88.4.5	sound	2208
88.4.6	textmode	2209
89	Reference for unit 'WinDirs'	2210
89.1	Used units	2210
89.2	Overview	2210
89.3	Constants, types and variables	2210
89.3.1	Constants	2210
89.4	Procedures and functions	2224
89.4.1	ConvertCSIDLtoFOLDERID	2224
89.4.2	ConvertFOLDERIDtoCSIDL	2224
89.4.3	GetWindowsSpecialDir	2224
89.4.4	GetWindowsSpecialDirUnicode	2224
89.4.5	GetWindowsSystemDirectory	2224
89.4.6	GetWindowsSystemDirectoryUnicode	2225
90	Reference for unit 'x86'	2226
90.1	Used units	2226
90.2	Overview	2226

90.3	Procedures and functions	2226
90.3.1	fpIOperm	2226
90.3.2	fpIoPL	2227
90.3.3	ReadPort	2227
90.3.4	ReadPortB	2227
90.3.5	ReadPortL	2228
90.3.6	ReadPortW	2228
90.3.7	WritePort	2228
90.3.8	WritePortB	2229
90.3.9	WritePortL	2229
90.3.10	WritePortW	2229

About this guide

This document describes all constants, types, variables, functions and procedures as they are declared in the units that come standard with the Free Pascal Run-Time library (RTL).

Throughout this document, we will refer to functions, types and variables with `typewriter` font. Functions and procedures have their own subsections, and for each function or procedure we have the following topics:

Declaration The exact declaration of the function.

Description What does the procedure exactly do ?

Errors What errors can occur.

See Also Cross references to other related functions/commands.

0.1 Overview

The Run-Time Library is the basis of all Free Pascal programs. It contains the basic units that most programs will use, and are made available on all platforms supported by Free pascal (well, more or less).

There are units for compatibility with the Turbo Pascal Run-Time library, and there are units for compatibility with Delphi.

On top of these two sets, there are also a series of units to handle keyboard/mouse and text screens in a cross-platform way.

Other units include platform specific units that implement the specifics of a platform, these are usually needed to support the Turbo Pascal or Delphi units.

Units that fall outside the above outline do not belong in the RTL, but should be included in the packages, or in the FCL.

Chapter 1

Reference for unit 'BaseUnix'

1.1 Used units

Table 1.1: Used units by unit 'BaseUnix'

Name	Page
System	1339
unixtype	2127

1.2 Overview

The BaseUnix unit was implemented by Marco Van de Voort. It contains basic Unix functionality. It supersedes the Linux unit of version 1.0.X of the compiler, but only implements a cleaned up, portable subset of that unit.

For porting FPC to new Unix-like platforms, it should be sufficient to implement the functionality in this unit for the new platform.

1.3 Constants, types and variables

1.3.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`AT_EMPTY_PATH = $1000`

Create link to old directly if path is empty

`AT_FDCWD = - 100`

Flag for various *at calls to indicate current working directory

`AT_NO_AUTOMOUNT = $800`

Do not auto mount filesystem if the base dir is a mount point.

AT_RECURSIVE = \$8000

Recurse subdirectories when applying changes

AT_REMOVEDIR = \$200

Unlink at: specify rmdir behaviour

AT_STATX_DONT_SYNC = \$4000

Do not synchronize the attributes with the server (if any)

AT_STATX_FORCE_SYNC = \$2000

Force the attributes to be synchronized with the server (if any)

AT_STATX_SYNC_AS_STAT = \$0000

Behave as fpStat

AT_STATX_SYNC_TYPE = \$6000

Type of synchronisation required from statx

AT_SYMLINK_FOLLOW = \$400

Dereference symbolic links

AT_SYMLINK_NOFOLLOW = \$100

Do not dereference symbolic links.

BITSINWORD = 8 * sizeof(cuLong)

Number of bits in a word.

clone_flags_fork = \$01200011

Request fork behaviour for clone call

ESysE2BIG = 7

System error: Argument list too long

ESysEACCES = 13

System error: Permission denied

ESysEADDRINUSE = 98

System error: Address already in use

ESysEADDRNOTAVAIL = 99

System error: Cannot assign requested address

ESysEADV = 68

System error: Advertise error

ESysEAFNOSUPPORT = 97

System error: Address family not supported by protocol

ESysEAGAIN = 11

System error: Try again

ESysEALREADY = 114

System error: Operation already in progress

ESysEBADE = 52

System error: Invalid exchange

ESysEBADF = 9

System error: Bad file number

ESysEBADFD = 77

System error: File descriptor in bad state

ESysEBADMSG = 74

System error: Not a data message

ESysEBADR = 53

System error: Invalid request descriptor

ESysEBADRQC = 56

System error: Invalid request code

ESysEBADSLT = 57

System error: Invalid slot

ESysEBFONT = 59

System error: Bad font file format

ESysEBUSY = 16

System error: Device or resource busy

ESysECANCELED = 125

Operation canceled

ESysECHILD = 10

System error: No child processes

ESysECHRNG = 44

System error: Channel number out of range

ESysECOMM = 70

System error: Communication error on send

ESysECONNABORTED = 103

System error: Software caused connection abort

ESysECONNREFUSED = 111

System error: Connection refused

ESysECONNRESET = 104

System error: Connection reset by peer

ESysEDEADLK = 35

System error: Resource deadlock would occur

ESysEDEADLOCK = ESysEDEADLK

System error: File locking deadlock error

ESysEDESTADDRREQ = 89

System error: Destination address required

ESysEDOM = 33

System error: Math argument out of domain of func

ESysEDOTDOT = 73

System error: RFS specific error

ESysEDQUOT = 122

System error: Quota exceeded

ESysEEXIST = 17

System error: File exists

ESysEFAULT = 14

System error: Bad address

ESysEFBIG = 27

System error: File too large

ESysEHOSTDOWN = 112

System error: Host is down

ESysEHOSTUNREACH = 113

System error: No route to host

ESysEIDRM = 43

System error: Identifier removed

ESysEILSEQ = 84

System error: Illegal byte sequence

ESysEINPROGRESS = 115

System error: Operation now in progress

ESysEINTR = 4

System error: Interrupted system call

ESysEINVAL = 22

System error: Invalid argument

ESysEIO = 5

System error: I/O error

ESysEISCONN = 106

System error: Transport endpoint is already connected

ESysEISDIR = 21

System error: Is a directory

ESysEISNAM = 120

System error: Is a named type file

ESysEKEYEXPIRED = 127

Key has expired (Linux kernel module)

ESysEKEYREJECTED = 129

Key was rejected by service (Linux kernel module)

ESysEKEYREVOKED = 128

Key has been revoked (Linux kernel module)

ESysEL2HLT = 51

System error: Level 2 halted

ESysEL2NSYNC = 45

System error: Level 2 not synchronized

ESysEL3HLT = 46

System error: Level 3 halted

ESysEL3RST = 47

System error: Level 3 reset

ESysELIBACC = 79

System error: Can not access a needed shared library

ESysELIBBAD = 80

System error: Accessing a corrupted shared library

ESysELIBEXEC = 83

System error: Cannot exec a shared library directly

ESysELIBMAX = 82

System error: Attempting to link in too many shared libraries

ESysELIBSCN = 81

System error: .lib section in a.out corrupted

ESysELNRNG = 48

System error: Link number out of range

ESysELOOP = 40

System error: Too many symbolic links encountered

ESysEMEDIUMTYPE = 124

Wrong medium type

ESysEMFILE = 24

System error: Too many open files

ESysEMLINK = 31

System error: Too many links

ESysEMSGSIZE = 90

System error: Message too long

ESysEMULTIHOP = 72

System error: Multihop attempted

ESysENAMETOOLONG = 36

System error: File name too long

ESysENAVAIL = 119

System error: No XENIX semaphores available

ESysENETDOWN = 100

System error: Network is down

ESysENETRESET = 102

System error: Network dropped connection because of reset

ESysENETUNREACH = 101

System error: Network is unreachable

ESysENFILE = 23

System error: File table overflow

ESysENOANO = 55

System error: No anode

ESysENOBUFFS = 105

System error: No buffer space available

ESysENOC SI = 50

System error: No CSI structure available

ESysENODATA = 61

System error: No data available

ESysENODEV = 19

System error: No such device

ESysENOENT = 2

System error: No such file or directory

ESysENOEXEC = 8

System error: Exec format error

ESysENOKEY = 126

Required key not available (Linux kernel module)

ESysENOLCK = 37

System error: No record locks available

ESysENOLINK = 67

System error: Link has been severed

ESysENOMEDIUM = 123

No medium present

ESysENOMEM = 12

System error: Out of memory

ESysENOMSG = 42

System error: No message of desired type

ESysENONET = 64

System error: Machine is not on the network

ESysENOPKG = 65

System error: Package not installed

ESysENOPROTOOPT = 92

System error: Protocol not available

ESysENOSPC = 28

System error: No space left on device

ESysENOSR = 63

System error: Out of streams resources

ESysENOSTR = 60

System error: Device not a stream

ESysENOSYS = 38

System error: Function not implemented

ESysENOTBLK = 15

System error: Block device required

ESysENOTCONN = 107

System error: Transport endpoint is not connected

ESysENOTDIR = 20

System error: Not a directory

ESysENOTEMPTY = 39

System error: Directory not empty

ESysENOTNAM = 118

System error: Not a XENIX named type file

ESysENOTRECOVERABLE = 131

State not recoverable (mutexes)

ESysENOTSOCK = 88

System error: Socket operation on non-socket

ESysENOTTY = 25

System error: Not a typewriter

ESysENOTUNIQ = 76

System error: Name not unique on network

ESysENXIO = 6

System error: No such device or address

ESysEOPNOTSUPP = 95

System error: Operation not supported on transport endpoint

ESysEOVERFLOW = 75

System error: Value too large for defined data type

ESysEOWNERDEAD = 130

Owner died (mutexes)

ESysEPERM = 1

System error: Operation not permitted.

ESysEPFNOSUPPORT = 96

System error: Protocol family not supported

ESysEPIPE = 32

System error: Broken pipe

ESysEPROTO = 71

System error: Protocol error

ESysEPROTONOSUPPORT = 93

System error: Protocol not supported

ESysEPROTOTYPE = 91

System error: Protocol wrong type for socket

ESysERANGE = 34

System error: Math result not representable

ESysEREMCHG = 78

System error: Remote address changed

ESysEREMOTE = 66

System error: Object is remote

ESysEREMOTEIO = 121

System error: Remote I/O error

ESysERESTART = 85

System error: Interrupted system call should be restarted

ESysERFKILL = 132

Operation not possible due to RF-Kill (wireless)

ESysEROFS = 30

System error: Read-only file system

ESysESHUTDOWN = 108

System error: Cannot send after transport endpoint shutdown

ESysESOCKTNOSUPPORT = 94

System error: Socket type not supported

ESysESPIPE = 29

System error: Illegal seek

ESysESRCH = 3

System error: No such process

ESysESRMNT = 69

System error: Srmount error

ESysESTALE = 116

System error: Stale NFS file handle

ESysESTRPIPE = 86

System error: Streams pipe error

ESysETIME = 62

System error: Timer expired

ESysETIMEDOUT = 110

System error: Connection timed out

ESysETOOMANYREFS = 109

System error: Too many references: cannot splice

ESysETXTBSY = 26

System error: Text (code segment) file busy

ESysEUCLEAN = 117

System error: Structure needs cleaning

ESysEUNATCH = 49

System error: Protocol driver not attached

ESysEUSERS = 87

System error: Too many users

ESysEWOULDBLOCK = ESysEAGAIN

System error: Operation would block

ESysEXDEV = 18

System error: Cross-device link

ESysEXFULL = 54

System error: Exchange full

FD_MAXFDSET = 1024

Maximum elements in a TFDSet (176) array.

FPE_FLTDIV = 3

Value signalling floating point divide by zero in case of SIGFPE signal

FPE_FLTINV = 7

Value signalling floating point invalid operation in case of SIGFPE signal

FPE_FLTOVF = 4

Value signalling floating point overflow in case of SIGFPE signal

FPE_FLTRES = 6

Value signalling floating point inexact result in case of SIGFPE signal

FPE_FLTSUB = 8

Value signalling floating point subscript out of range in case of SIGFPE signal

FPE_FLTUND = 5

Value signalling floating point underflow in case of SIGFPE signal

FPE_INTDIV = 1

Value signalling integer divide in case of SIGFPE signal

FPE_INTOVF = 2

Value signalling integer overflow in case of SIGFPE signal

F_GetFd = 1

fpFCntl (188) command: Get close-on-exec flag

F_GetFl = 3

fpFCntl (188) command: Get file descriptor flags

F_GetLk = 5

fpFCntl (188) command: Get lock

F_GetOwn = 9

fpFCntl (188) command: get owner of file descriptor events

F_OK = 0

`fpAccess (179)` call test: file exists.

`F_SetFd = 2`

`fpFCntl (188)` command: Set close-on-exec flag

`F_SetFl = 4`

`fpFCntl (188)` command: Set file descriptor flags

`F_SetLk = 6`

`fpFCntl (188)` command: Set lock

`F_SetLkW = 7`

`fpFCntl (188)` command: Test lock

`F_SetOwn = 8`

`fpFCntl (188)` command: Set owner of file descriptor events

`ln2bitmask = 1 shl ln2bitsinword - 1`

Last bit in word.

`ln2bitsinword = 6`

Power of 2 number of bits in word.

`MAP_ANON = MAP_ANONYMOUS`

Anonymous memory mapping (data private to application)

`MAP_ANONYMOUS = $20`

`FpMMap (202)` map type: Don't use a file

`MAP_DENYWRITE = $800`

`FpMMap (202)` option: Ignored.

`MAP_EXECUTABLE = $1000`

`FpMMap (202)` option: Ignored.

`MAP_FAILED = pointer(- 1)`

Memory mapping failed error code

`MAP_FIXED = $10`

FpMMap (202) map type: Interpret addr exactly

MAP_GROWSDOWN = \$100

FpMMap (202) option: Memory grows downward (like a stack)

MAP_LOCKED = \$2000

FpMMap (202) option: lock the pages in memory.

MAP_NORESERVE = \$4000

FpMMap (202) option: Do not reserve swap pages for this memory.

MAP_PRIVATE = \$2

FpMMap (202) map type: Changes are private

MAP_SHARED = \$1

FpMMap (202) map type: Share changes

MAP_TYPE = \$f

FpMMap (202) map type: Bitmask for type of mapping

NAME_MAX = UnixType.NAME_MAX

Maximum filename length.

O_APPEND = \$400

fpOpen (206) file open mode: Append to file

O_CREAT = \$40

fpOpen (206) file open mode: Create if file does not yet exist.

O_DIRECT = \$4000

fpOpen (206) file open mode: Minimize caching effects

O_DIRECTORY = \$10000

fpOpen (206) file open mode: File must be directory.

O_EXCL = \$80

fpOpen (206) file open mode: Open exclusively

O_LARGEFILE = \$8000

fpOpen (206) file open mode: Open for 64-bit I/O

`O_NDELAY = O_NONBLOCK`

fpOpen (206) file open mode: Alias for `O_NonBlock (156)`

`O_NOCTTY = $100`

fpOpen (206) file open mode: No TTY control.

`O_NOFOLLOW = $20000`

fpOpen (206) file open mode: Fail if file is symbolic link.

`O_NONBLOCK = $800`

fpOpen (206) file open mode: Open in non-blocking mode

`O_RDONLY = 0`

fpOpen (206) file open mode: Read only

`O_RDWR = 2`

fpOpen (206) file open mode: Read/Write

`O_SYNC = $1000`

fpOpen (206) file open mode: Write to disc at once

`O_TRUNC = $200`

fpOpen (206) file open mode: Truncate file to length 0

`O_WRONLY = 1`

fpOpen (206) file open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`POLLERR = $0008`

Error condition on output file descriptor

`POLLHUP = $0010`

Hang up

`POLLIN = $0001`

Data is available for reading

POLLNVAL = \$0020

Invalid request, file descriptor not open.

POLLOUT = \$0004

Writing data will not block the write call

POLLPRI = \$0002

Urgent data is available for reading.

POLLRDBAND = \$0080

Priority data ready for reading.

POLLRDNORM = \$0040

Same as POLLIN.

POLLWRBAND = \$0200

Priority data may be written.

POLLWRNORM = \$0100

Equivalent to POLLOUT.

PRIO_PGRP = UnixType.PRIO_PGRP

Easy access alias for unixtype.PRIO_PGRP ([2128](#))

PRIO_PROCESS = UnixType.PRIO_PROCESS

Easy access alias for unixtype.PRIO_PROCESS ([2128](#))

PRIO_USER = UnixType.PRIO_USER

Easy access alias for unixtype.PRIO_USER ([2128](#))

PROT_EXEC = \$4

FpMMap ([202](#)) memory access: page can be executed

PROT_NONE = \$0

FpMMap ([202](#)) memory access: page can not be accessed

PROT_READ = \$1

FpMMap (202) memory access: page can be read

PROT_WRITE = 2

FpMMap (202) memory access: page can be written

RLIMIT_AS = 9

RLimit request address space limit

RLIMIT_CORE = 4

RLimit request max core file size

RLIMIT_CPU = 0

RLimit request CPU time in ms

RLIMIT_DATA = 2

RLimit request max data size

RLIMIT_FSIZE = 1

Rlimit request maximum file size

RLIMIT_LOCKS = 10

RLimit request maximum file locks held

RLIMIT_MEMLOCK = 8

RLimit request max locked-in-memory address space

RLIMIT_NOFILE = 7

RLimit request max number of open files

RLIMIT_NPROC = 6

RLimit request max number of processes

RLIMIT_RSS = 5

RLimit request max resident set size

RLIMIT_STACK = 3

RLimit request max stack size

R_OK = 4

fpAccess (179) call test: read allowed

SA_INTERRUPT = \$20000000

Sigaction options: ?

SA_NOCLDSTOP = 1

Sigaction options: Do not receive notification when child processes stop

SA_NOCLDWAIT = 2

Sigaction options: ?

SA_NODEFER = \$40000000

Sigaction options: Do not mask signal in its own signal handler

SA_NOMASK = SA_NODEFER

Sigaction options: Do not prevent the signal from being received when it is handled.

SA_ONESHOT = SA_RESETHAND

Sigaction options: Restore the signal action to the default state.

SA_ONSTACK = \$08000000

SA_ONSTACK is used in the fpsigaction (218) to indicate the signal handler must be called on an alternate signal stack provided by sigaltstack(2) If an alternate stack is not available, the default stack will be used.

SA_RESETHAND = \$80000000

Sigaction options: Restore signal action to default state when signal handler exits.

SA_RESTART = \$10000000

Sigaction options: Provide behaviour compatible with BSD signal semantics

SA_RESTORER = \$04000000

Signal restorer handler

SA_SIGINFO = 4

Sigaction options: The signal handler takes 3 arguments, not one.

SEEK_CUR = 1

fpLSeek (199) option: Set position relative to current position.

SEEK_END = 2

fpLSeek (199) option: Set position relative to end of file.

SEEK_SET = 0

fpLSeek (199) option: Set absolute position.

SIGABRT = 6

Signal: ABRT (Abort)

SIGALRM = 14

Signal: ALRM (Alarm clock)

SIGBUS = 7

Signal: BUS (bus error)

SIGCHLD = 17

Signal: CHLD (child status changed)

SIGCONT = 18

Signal: CONT (Continue)

SIGFPE = 8

Signal: FPE (Floating point error)

SIGHUP = 1

Signal: HUP (Hangup)

SIGILL = 4

Signal: ILL (Illegal instruction)

SIGINT = 2

Signal: INT (Interrupt)

SIGIO = 29

Signal: IO (I/O operation possible)

SIGIOT = 6

Signal: IOT (IOT trap)

SIGKILL = 9

Signal: KILL (unblockable)

SIGPIPE = 13

Signal: PIPE (Broken pipe)

SIGPOLL = SIGIO

Signal: POLL (Pollable event)

SIGPROF = 27

Signal: PROF (Profiling alarm)

SIGPWR = 30

Signal: PWR (power failure restart)

SIGQUIT = 3

Signal: QUIT

SIGSEGV = 11

Signal: SEGV (Segmentation violation)

SIGSTKFLT = 16

Signal: STKFLT (Stack Fault)

SIGSTOP = 19

Signal: STOP (Stop, unblockable)

SIGTERM = 15

Signal: TERM (Terminate)

SIGTRAP = 5

Signal: TRAP (Trace trap)

SIGTSTP = 20

Signal: TSTP (keyboard stop)

SIGTTIN = 21

Signal: TTIN (Terminal input, background)

SIGTTOU = 22

Signal: TTOU (Terminal output, background)

SIGUNUSED = 31

Signal: Unused

SIGURG = 23

Signal: URG (Socket urgent condition)

SIGUSR1 = 10

Signal: USR1 (User-defined signal 1)

SIGUSR2 = 12

Signal: USR2 (User-defined signal 2)

SIGVTALRM = 26

Signal: VTALRM (Virtual alarm clock)

SIGWINCH = 28

Signal: WINCH (Window/Terminal size change)

SIGXCPU = 24

Signal: XCPU (CPU limit exceeded)

SIGXFSZ = 25

Signal: XFSZ (File size limit exceeded)

SIG_BLOCK = 0

Sigprocmask flags: Add signals to the set of blocked signals.

SIG_DFL = 0

Signal handler: Default signal handler

SIG_ERR = - 1

Signal handler: error

SIG_IGN = 1

Signal handler: Ignore signal

`SIG_MAXSIG = UnixType.SIG_MAXSIG`

Maximum system signal number.

`SIG_SETMASK = 2`

Sigprocmask flags: Set of blocked signals is given.

`SIG_UNBLOCK = 1`

Sigprocmask flags: Remove signals from the set set of blocked signals.

`SI_PAD_SIZE = 128 div sizeof(longint) - 3`

Signal information pad size.

`SYS_NMLN = UnixType.SYS_NMLN`

Max system name length.

`S_IFBLK = 24576`

File (`#rtl.baseunix.stat (235)` record) mode: Block device

`S_IFCHR = 8192`

File (`#rtl.baseunix.stat (235)` record) mode: Character device

`S_IFDIR = 16384`

File (`#rtl.baseunix.stat (235)` record) mode: Directory

`S_IFIFO = 4096`

File (`#rtl.baseunix.stat (235)` record) mode: FIFO

`S_IFLNK = 40960`

File (`#rtl.baseunix.stat (235)` record) mode: Link

`S_IFMT = 61440`

File (`#rtl.baseunix.stat (235)` record) mode: File type bit mask

`S_IFREG = 32768`

File (`#rtl.baseunix.stat (235)` record) mode: Regular file

`S_IFSOCK = 49152`

File (`#rtl.baseunix.stat (235)` record) mode: Socket

S_IRGRP = %0000100000

Mode flag: Read by group.

S_IROTH = %00000000100

Mode flag: Read by others.

S_IRUSR = %0100000000

Mode flag: Read by owner.

S_IRWXG = S_IRGRP or S_IWGRP or S_IXGRP

Mode flag: Read, write, execute by groups.

S_IRWXO = S_IROTH or S_IWOTH or S_IXOTH

Mode flag: Read, write, execute by others.

S_IRWXU = S_IRUSR or S_IWUSR or S_IXUSR

Mode flag: Read, write, execute by user.

S_ISGID = &2000

Mode flag: Set Group ID on execution.

S_ISUID = &4000

Mode flag: Set user ID on execution.

S_ISVTX = &1000

Mode flag: Set sticky bit.

S_IWGRP = %0000010000

Mode flag: Write by group.

S_IWOTH = %0000000010

Mode flag: Write by others.

S_IWUSR = %0010000000

Mode flag: Write by owner.

S_IXGRP = %0000001000

Mode flag: Execute by group.

S_IXOTH = %0000000001

Mode flag: Execute by others.

S_IXUSR = %0001000000

Mode flag: Execute by owner.

UTSNAME_DOMAIN_LENGTH = UTSNAME_LENGTH

Max length of utsname (241) domain name.

UTSNAME_LENGTH = SYS_NMLN

Max length of utsname (241) system name, release, version, machine.

UTSNAME_NODENAME_LENGTH = UTSNAME_LENGTH

Max length of utsname (241) node name.

WNOHANG = 1

#rtl.baseunix.fpWaitpid (231) option: Do not wait for processes to terminate.

wordsinfdset = FD_MAXFDSET div BITSINWORD

Number of words in a TFDSet (176) array

wordsinsigset = SIG_MAXSIG div BITSINWORD

Number of words in a signal set.

WUNTRACED = 2

#rtl.baseunix.fpWaitpid (231) option: Also report children which were stopped but not yet reported

W_OK = 2

fpAccess (179) call test: write allowed

X_OK = 1

fpAccess (179) call test: execute allowed

_STAT_VER = _STAT_VER_LINUX

Stat version number

_STAT_VER_KERNEL = 0

Current version of stat record

_STAT_VER_LINUX = 1

Version of Linux stat record

1.3.2 Types

`Blkcnt64_t = cuint64`

64-bit block count

`Blkcnt_t = cuint`

Block count type.

`Blksize_t = cuint`

Block size type.

`cbool = UnixType.cbool`

Boolean type

`cchar = UnixType.cchar`

Alias for `#rtl.UnixType.cchar` ([2129](#))

`cdouble = UnixType.cdouble`

Double precision real format.

`cfloat = UnixType.cfloat`

Floating-point real format

`cint = UnixType.cint`

C type: integer (natural size)

`cint16 = UnixType.cint16`

C type: 16 bits sized, signed integer.

`cint32 = UnixType.cint32`

C type: 32 bits sized, signed integer.

`cint64 = UnixType.cint64`

C type: 64 bits sized, signed integer.

`cint8 = UnixType.cint8`

C type: 8 bits sized, signed integer.

`clock_t = UnixType.clock_t`

Clock ticks type

`clong = UnixType.clong`

C type: long signed integer (double sized)

`clonglong = UnixType.clonglong`

C type: 64-bit (double long) signed integer.

`coff_t = UnixType.TOff`

Character offset type

`cschar = UnixType.cschar`

Signed character type

`cshort = UnixType.cshort`

C type: short signed integer (half sized)

`csigned = UnixType.csigned`

`csigned` is an alias for `cint` ([166](#)).

`csint = UnixType.csint`

Signed integer

`csize_t = UnixType.size_t`

Character size type

`cslong = UnixType.cslong`

The size is CPU dependent.

`cslonglong = UnixType.cslonglong`

`cslonglong` is an alias for `clonglong` ([167](#)).

`csshort = UnixType.csshort`

Short signed integer type

`cuchar = UnixType.cuchar`

Alias for `#rtl.UnixType.cuchar` ([2130](#))

`cuint = UnixType.cuint`

C type: unsigned integer (natural size)

```
cuint16 = UnixType.cuint16
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = UnixType.cuint32
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = UnixType.cuint64
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = UnixType.cuint8
```

C type: 8 bits sized, unsigned integer.

```
culong = UnixType.culong
```

C type: long unsigned integer (double sized)

```
culonglong = UnixType.culonglong
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = UnixType.cunsigned
```

Alias for `#rtl.unixtype.cunsigned` ([2131](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
kernel_gid_t = cuint
```

`kernel_gid_t` may differ from the `libc` type used to describe group IDs.

```
kernel_loff_t = clonglong
```

Long kernel offset type

`kernel_mode_t = cuint`

`kernel_mode_t` may differ from the `libc` type used to describe file modes.

`kernel_off_t = clong`

Kernel offset type

`kernel_uid_t = cuint`

`kernel_uid_t` may differ from the `libc` type used to describe user IDs.

`mode_t = UnixType.mode_t`

Inode mode type.

`nlink_t = UnixType.nlink_t`

Number of links type.

`off_t = UnixType.off_t`

Offset type.

`PBlkCnt = ^Blkcnt_t`

pointer to `TBlkCnt` (176) type.

`PBlkSize = ^Blksize_t`

Pointer to `TBlkSize` (176) type.

`pcbool = UnixType.pcbbool`

Pointer to boolean type `cbool` (166)

`pcchar = UnixType.pcchar`

Alias for `#rtl.UnixType.pcchar` (2132)

`pcdouble = UnixType.pcdouble`

Pointer to `cdouble` (166) type.

`pcfloat = UnixType.pcfloating`

Pointer to `cfloat` (166) type.

`pcint = UnixType.pcint`

Pointer to cInt (166) type.

```
pcint16 = UnixType.pcint16
```

Pointer to 16-bit signed integer type

```
pcint32 = UnixType.pcint32
```

Pointer to signed 32-bit integer type

```
pcint64 = UnixType.pcint64
```

Pointer to signed 64-bit integer type

```
pcint8 = UnixType.pcint8
```

Pointer to 8-bits signed integer type

```
pClock = UnixType.pClock
```

Pointer to TClock (176) type.

```
pclong = UnixType.pclong
```

Pointer to cLong (167) type.

```
pclonglong = UnixType.pclonglong
```

Pointer to longlong type.

```
pcschar = UnixType.pcschar
```

Pointer to character type cchar (167).

```
pcshort = UnixType.pcsshort
```

Pointer to cShort (167) type.

```
pcsigned = UnixType.pcsigned
```

Pointer to signed integer type csigned (167).

```
pcsint = UnixType.pcsint
```

Pointer to signed integer type csint (167)

```
pcsize_t = UnixType.psize_t
```

Pointer to csize_t

```
pcslong = UnixType.pcslong
```

Pointer to the signed long cslong (167)

```
pcslonglong = UnixType.pcslonglong
```

Pointer to Signed longlong type cslonglong (167)

```
pcssshort = UnixType.pcssshort
```

Pointer to short signed integer type csshort (167)

```
pcuchar = UnixType.pcuchar
```

Alias for #rtl.UnixType.pcuchar (2133)

```
pcuint = UnixType.pcuint
```

Pointer to cUInt (168) type.

```
pcuint16 = UnixType.pcuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = UnixType.pcuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = UnixType.pcuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = UnixType.pcuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = UnixType.pculong
```

Pointer to cuLong (168) type.

```
pculonglong = UnixType.pculonglong
```

Unsigned longlong type

```
pcunsigned = UnixType.pcunsigned
```

Alias for #rtl.unixtype.pcunsigned (2134)

```
pcushort = UnixType.pcushort
```

Pointer to cuShort (168) type.

```
pDev = UnixType.pDev
```

Pointer to TDev (176) type.

```
pDir = ^Dir
```

Pointer to TDir (176) record

```
pDirent = ^Dirent
```

Pointer to TDirent (176) record.

```
pFDSet = ^TFDSet
```

Pointer to TFDSet (176) type.

```
pFilDes = ^TFilDes
```

Pointer to TFilDes (176) type.

```
pfpstate = ^tfpstate
```

Pointer to tfpstate (236) record.

```
pGid = UnixType.pGid
```

Pointer to TGid (176) type.

```
pGrpArr = ^TGrpArr
```

Pointer to TGrpArr (176) array.

```
pid_t = UnixType.pid_t
```

Process ID type.

```
pIno = UnixType.pIno
```

Pointer to TIno (177) type.

```
piovec = ^tiovec
```

pointer to a iovec (234) record

```
pMode = UnixType.pMode
```

Pointer to TMode (177) type.

```
pnLink = UnixType.pnLink
```

Pointer to TnLink (177) type.

```
pOff = UnixType.pOff
```

Pointer to TOff (177) type.

```
pPid = UnixType.pPid
```

Pointer to TPid (177) type.

```
ppollfd = ^pollfd
```

Pointer to tpollfd.

```
PRLimit = ^TRLimit
```

Pointer to TRLimit (238) record

```
psigactionrec = ^sigactionrec
```

Pointer to SigActionRec (235) record type.

```
PSigContext = ^TSigContext
```

Pointer to #rtl.baseunix.TSigContext (239) record type.

```
psiginfo = ^tsiginfo
```

Pointer to #rtl.baseunix.TSigInfo (240) record type.

```
psigset = ^tsigset
```

Pointer to SigSet (175) type.

```
pSize = UnixType.pSize
```

Pointer to TSize (178) type.

```
pSize_t = UnixType.pSize_t
```

Pointer to Size_t

```
pSocklen = UnixType.pSocklen
```

Pointer to TSockLen (178) type.

```
psSize = UnixType.psSize
```

Pointer to TsSize (178) type

```
PStat = ^Stat
```

Pointer to TStat (178) type.

```
pstatfs = UnixType.PStatFs
```

This is an alias for the type defined in the `#rtl.unixtype` (2127) unit.

```
pthread_cond_t = UnixType.pthread_cond_t
```

Thread conditional variable type.

```
pthread_mutex_t = UnixType.pthread_mutex_t
```

Thread mutex type.

```
pthread_t = UnixType.pthread_t
```

POSIX thread type.

```
pTime = UnixType.pTime
```

Pointer to `TTime` (178) type.

```
ptimespec = UnixType.ptimespec
```

Pointer to `timespec` (176) type.

```
ptimeval = UnixType.ptimeval
```

Pointer to `timeval` (176) type.

```
ptimezone = ^timezone
```

Pointer to `TimeZone` (237) record.

```
ptime_t = UnixType.ptime_t
```

Pointer to `time_t` (177) type.

```
PTms = ^tms
```

Pointer to `TTms` (178) type.

```
Pucontext = ^Tucontext
```

Pointer to `TUContext` (240) type.

```
pUId = UnixType.pUId
```

Pointer to `TUId` (178) type.

```
pUtimBuf = ^UTimBuf
```

Pointer to `TUTimBuf` (178) type.

```
PUtsName = ^TUTsName
```

Pointer to TUnitsName (178) type.

```
rlim_t = culong
```

rlim_t is used as the type for the various fields in the TRLimit (238) record.

```
sigactionhandler = sigactionhandler_t
```

When installing a signal handler, the actual signal handler must be of type SigActionHandler.

```
sigactionhandler_t = procedure(signal: LongInt; info: psiginfo;
    context: PSigContext)
```

Standard signal action handler prototype

```
signalhandler = signalhandler_t
```

Simple signal handler prototype

```
signalhandler_t = procedure(signal: LongInt)
```

Standard signal handler prototype

```
sigrestorerhandler = sigrestorerhandler_t
```

Alias for sigrestorerhandler_t (175) type.

```
sigrestorerhandler_t = procedure
```

Standard signal action restorer prototype

```
sigset = sigset_t
```

Signal set type

```
sigset_t = Array[0..wordsinsigset-1] of culong
```

Signal set type

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

TBlkCnt = Blkcnt_t

Alias for Blkcnt_t (166) type.

TBlkSize = Blksize_t

Alias for blksize_t (166) type.

TClock = UnixType.TClock

Alias for clock_t (167) type.

TDev = UnixType.TDev

Alias for dev_t (168) type.

TDIr = Dir

Alias for Dir (233) type.

TDirent = Dirent

Alias for Dirent (234) type.

TFDSet = Array[0..(FD_MAXFDSETdivBITSINWORD)-1] of TFDSetEl

File descriptor set for fpSelect (214) call.

TFDSetEl = culong

Type alias for an element of the TFDSet

TFilDes = Array[0..1] of cint

Array of file descriptors as used in fpPipe (208) call.

TGid = UnixType.TGid

Alias for gid_t (168) type.

TGrpArr = Array[0..0] of TGid

Array of gid_t (168) IDs

timespec = UnixType.timespec

Short time specification type.

timeval = UnixType.timeval

Time specification type.

`time_t = UnixType.time_t`

Time span type

`TIno = UnixType.TIno`

Alias for `ino_t` (168) type.

`TIOCtlRequest = UnixType.TIOCtlRequest`

Easy access alias for `unixtype.TIOCtlRequest` (2137)

`tiovec = iovec`

Alias for the `iovec` (234) record type.

`TMode = UnixType.TMode`

Alias for `mode_t` (169) type.

`TnLink = UnixType.TnLink`

Alias for `nlink_t` (169) type.

`TOff = UnixType.TOff`

Alias for `off_t` (169) type.

`TPid = UnixType.TPid`

Alias for `pid_t` (172) type.

`tpollfd = pollfd`

Alias for `pollfd` type

`tsigactionhandler = sigactionhandler_t`

Alias for `sigactionhandler_t` (175) type.

`tsignalhandler = signalhandler_t`

Alias for `signalhandler_t` (175) type.

`tsigrestorerhandler = sigrestorerhandler_t`

Alias for `sigrestorerhandler_t` (175) type.

`tsigset = sigset_t`

Alias for `SigSet` (175) type.

`TSize = UnixType.TSize`

Alias for `size_t` (175) type

`TSocklen = UnixType.TSocklen`

Alias for `socklen_t` (175) type.

`TsSize = UnixType.TsSize`

Alias for `ssize_t` (175) type

`TStat = Stat`

Alias for `Stat` (235) type.

`tstatfs = UnixType.TStatFs`

Record describing a file system in the `unix.fstatfs` (141) call.

`TTime = UnixType.TTime`

Alias for `TTime` (178) type.

`Ttimespec = UnixType.Ttimespec`

Alias for `TimeSpec` (176) type.

`TTimeVal = UnixType.TTimeVal`

Alias for `timeval` (176) type.

`TTimeZone = timezone`

Alias for `TimeZone` (237) record.

`TTms = tms`

Alias for `Tms` (237) record type.

`TUid = UnixType.TUid`

Alias for `uid_t` (178) type.

`TUtimBuf = UtimBuf`

Alias for `UtimBuf` (240) type.

`TUtsName = UtsName`

Alias for `UtsName` (241) type.

`uid_t = UnixType.uid_t`

User ID type

1.4 Procedures and functions

1.4.1 CreateShellArgV

Synopsis: Create a null-terminated array of strings from a command-line string

Declaration: `function CreateShellArgV(const prog: string) : PPChar`
`function CreateShellArgV(const prog: RawByteString) : PPChar`

Visibility: default

Description: `CreateShellArgV` creates a command-line string for executing a shell command using 'sh -c'. The result is a null-terminated array of null-terminated strings suitable for use in `fpExecv` (186) and friends.

Errors: If no more memory is available, a heap error may occur.

See also: `fpExecv` (186), `FreeShellArgV` (232)

1.4.2 FpAccess

Synopsis: Check file access

Declaration: `function FpAccess(pathname: PChar; aMode: cint) : cint`
`function FpAccess(const pathname: RawByteString; aMode: cint) : cint`

Visibility: default

Description: `FpAccess` tests user's access rights on the specified file. Mode is a mask existing of one or more of the following:

R_OKUser has read rights.

W_OKUser has write rights.

X_OKUser has execute rights.

F_OKFile exists.

The test is done with the real user ID, instead of the effective user ID. If the user has the requested rights, zero is returned. If access is denied, or an error occurred, a nonzero value is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

sys_eaccessThe requested access is denied, either to the file or one of the directories in its path.

sys_einvalMode was incorrect.

sys_enoentA directory component in `Path` doesn't exist or is a dangling symbolic link.

sys_enotdirA directory component in `Path` is not a directory.

sys_enomemInsufficient kernel memory.

sys_eloop`Path` has a circular symbolic link.

See also: `FpChown` (182), `FpChmod` (181)

Listing: `./examples/bunixex/ex26.pp`

Program Example26;

{ Program to demonstrate the Access function. }

Uses BaseUnix;

```
begin
  if fpAccess ( '/etc/passwd',W_OK)=0 then
    begin
      Writeln ( 'Better check your system. ');
      Writeln ( 'I can write to the /etc/passwd file ! ');
    end;
  end.
end.
```

1.4.3 FpAlarm

Synopsis: Schedule an alarm signal to be delivered

Declaration: `function FpAlarm(seconds: cuint) : cuint`

Visibility: default

Description: `FpAlarm` schedules an alarm signal to be delivered to your process in `Seconds` seconds. When `Seconds` seconds have elapsed, the system will send a `SIGALRM` signal to the current process. If `Seconds` is zero, then no new alarm will be set. Whatever the value of `Seconds`, any previous alarm is cancelled.

The function returns the number of seconds till the previously scheduled alarm was due to be delivered, or zero if there was none. A negative value indicates an error.

See also: [fpSigAction \(218\)](#), [fpPause \(208\)](#)

Listing: `./examples/bunixex/ex59.pp`

Program Example59;

{ Program to demonstrate the Alarm function. }

Uses BaseUnix;

Procedure AlarmHandler(Sig : cint); cdecl;

```
begin
  Writeln ( 'Got to alarm handler ');
end;

begin
  Writeln ( 'Setting alarm handler ');
  fpSignal(SIGALRM, SignalHandler (@AlarmHandler));
  Writeln ( 'Scheduling Alarm in 10 seconds ');
  fpAlarm(10);
  Writeln ( 'Pausing ');
  fpPause;
  Writeln ( 'Pause returned ');
end.
```

1.4.4 FpChdir

Synopsis: Change current working directory.

Declaration: `function FpChdir(path: PChar) : cint`
`function FpChdir(const path: RawByteString) : cint`

Visibility: default

Description: `fpChDir` sets the current working directory to `Path`.

It returns zero if the call was successful, -1 on error.

Note: There exist a portable alternative to `fpChDir`: `system.chdir`. Please use `fpChDir` only if you are writing Unix specific code. `System.chdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([193](#)).

See also: `fpGetCwd` ([192](#))

1.4.5 FpChmod

Synopsis: Change file permission bits

Declaration: `function FpChmod(path: PChar; Mode: TMode) : cint`
`function FpChmod(const path: RawByteString; Mode: TMode) : cint`

Visibility: default

Description: `fpChmod` sets the `Mode` bits of the file in `Path` to `Mode`. `Mode` can be specified by 'or'-ing the following values:

S_ISUIDSet user ID on execution.

S_ISGIDSet Group ID on execution.

S_ISVTXSet sticky bit.

S_IRUSRRead by owner.

S_IWUSRWrite by owner.

S_IXUSRExecute by owner.

S_IRGRPRead by group.

S_IWGRPWrite by group.

S_IXGRPExecute by group.

S_IROTHRead by others.

S_IWOTHWrite by others.

S_IXOTHExecute by others.

S_IRWXORead, write, execute by others.

S_IRWXGRead, write, execute by groups.

S_IRWXURead, write, execute by user.

If the function is successful, zero is returned. A nonzero return value indicates an error.

Errors: The following error codes are returned:

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in `Path` has no search (=execute) permission.

sys_enoentA directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe file is on a read-only file system.

sys_eloop`Path` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `fpChown` ([182](#)), `fpAccess` ([179](#))

Listing: `./examples/bunixex/ex23.pp`

Program `Example23`;

{ Program to demonstrate the Chmod function. }

Uses `BaseUnix`, `Unix`;

Var `F` : `Text`;

begin

```

  { Create a file }
  Assign (f, 'testex21');
  Rewrite (F);
  Writeln (f, '#!/bin/sh');
  Writeln (f, 'echo Some text for this file');
  Close (F);
  fpChmod ('testex21', &777);
  { File is now executable }
  fpexecl ('./testex21', []);

```

end.

1.4.6 FpChown

Synopsis: Change owner of file

Declaration: `function FpChown(path: PChar; owner: TUid; group: TGid) : cint`
`function FpChown(const path: RawByteString; owner: TUid; group: TGid)`
`: cint`

Visibility: `default`

Description: `fpChown` sets the User ID and Group ID of the file in `Path` to `Owner,Group`.

The function returns zero if the call was successful, a nonzero return value indicates an error.

Errors: The following error codes are returned:

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in `Path` has no search (=execute) permission.

sys_enoentA directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomemInsufficient kernel memory.

sys_erofs The file is on a read-only file system.

sys_eloop Path has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `fpChmod` ([181](#)), `fpAccess` ([179](#))

Listing: `./examples/bunixex/ex24.pp`

Program Example24;

{ Program to demonstrate the Chown function. }

Uses BaseUnix;

Var UID : TUid;
 GID : TGid;
 F : Text;

begin

```

  Writeln ('This will only work if you are root. ');
  Write ('Enter a UID : '); readln (UID);
  Write ('Enter a GID : '); readln (GID);
  Assign (f, 'test.txt');
  Rewrite (f);
  Writeln (f, 'The owner of this file should become : ');
  Writeln (f, 'UID : ', UID);
  Writeln (f, 'GID : ', GID);
  Close (F);
  if fpChown ('test.txt', UID, GID) <> 0 then
    if fpgeterrno = ESysEPerm then
      Writeln ('You are not root !')
    else
      Writeln ('Chmod failed with exit code : ', fpgeterrno)
    else
      Writeln ('Changed owner successfully !');
end.
```

1.4.7 FpClose

Synopsis: Close file descriptor

Declaration: `function FpClose(fd: cint) : cint`

Visibility: default

Description: `FpClose` closes a file with file descriptor `Fd`. The function returns zero if the file was closed successfully, a nonzero return value indicates an error.

For an example, see `FpOpen` ([206](#)).

Errors: Extended error information can be retrieved using `fpGetErrno` ([193](#)).

See also: `FpOpen` ([206](#)), `FpRead` ([210](#)), `FpWrite` ([231](#)), `FpFTruncate` ([191](#)), `FpLSeek` ([199](#))

1.4.8 FpClosedir

Synopsis: Close directory file descriptor

Declaration: `function FpClosedir(var dirp: Dir) : cint`

Visibility: default

Description: `FpCloseDir` closes the directory pointed to by `dirp`. It returns zero if the directory was closed successfully, -1 otherwise.

For an example, see `fpOpenDir` (207).

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

See also: `FpOpenDir` (207), `FpReadDir` (211)

1.4.9 FpDup

Synopsis: Duplicate a file handle

Declaration: `function FpDup(fildes: cint) : cint`
`function FpDup(var oldfile: text; var newfile: text) : cint`
`function FpDup(var oldfile: File; var newfile: File) : cint`

Visibility: default

Description: `FpDup` returns a file descriptor that is a duplicate of the file descriptor `fildes`.

The second and third forms make `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in case it is a Text file or untyped file. Due to the buffering mechanism of Pascal, these calls do not have the same functionality as the `dup` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the file position in both files.

The function returns a negative value in case of an error, a positive value is a file handle, and indicates success.

Errors: A negative value can be one of the following error codes:

`sys_ebadf` `OldFile` hasn't been assigned.

`sys_emfile` Maximum number of open files for the process is reached.

See also: `fpDup2` (185)

Listing: `./examples/bunixex/ex31.pp`

```

program Example31 ;

  { Program to demonstrate the Dup function. }

uses baseunix ;

var f : text ;

begin
  if fpdup (output,f)=-1 then
    Writeln ('Dup Failed !');
    writeln ('This is written to stdout.');
```

```

    writeln (f, 'This is written to the dup file , and flushed');flush(f);
    writeln
end.

```

1.4.10 FpDup2

Synopsis: Duplicate one file handle to another

Declaration: `function FpDup2(fildes: cint; fildes2: cint) : cint`
`function FpDup2(var oldfile: text; var newfile: text) : cint`
`function FpDup2(var oldfile: File; var newfile: File) : cint`

Visibility: default

Description: Makes `fildes2` or `NewFile` an exact copy of `fildes` or `OldFile`, after having flushed the buffer of `OldFile` in the case of text or untyped files.

After a call to `fdup2`, the 2 file descriptors point to the same physical device (a file, socket, or a terminal).

`NewFile` can be an assigned file. If `newfile` or `fildes` was open, it is closed first. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup2` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the file position in both files.

The function returns the new file descriptor number, on error -1 is returned, and the error can be retrieved with `fpgeterrno` ([193](#))

Errors: In case of error, the following error codes can be reported:

`sys_ebadfOldFile` (or `fildes`) hasn't been assigned.

`sys_emfile`Maximum number of open files for the process is reached.

See also: `fpDup` ([184](#))

Listing: `./examples/bunixex/ex32.pp`

```

program Example32;

{ Program to demonstrate the FpDup2 function. }

uses BaseUnix;

var f : text;
    i : longint;

begin
    Assign (f, 'text.txt');
    Rewrite (F);
    For i:=1 to 10 do writeln (F, 'Line : ', i);
    if fpdup2 (output, f)=-1 then
        Writeln ('Dup2 Failed !');
    writeln ('This is written to stdout. ');
    writeln (f, 'This is written to the dup file , and flushed');
    flush(f);
    writeln;
    { Remove file. Comment this if you want to check flushing.}

```

```
    fpUnlink ( 'text.txt' );
end.
```

1.4.11 FpExecv

Synopsis: Execute process

Declaration: `function FpExecv(path: PChar; argv: PPChar) : cint`
`function FpExecv(const path: RawByteString; argv: PPChar) : cint`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execv` does not return.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` ([193](#))

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted .

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `fpExecve` ([187](#)), `fpFork` ([190](#))

Listing: `./examples/bunixex/ex8.pp`

Program Example8;

{ Program to demonstrate the Execv function. }

Uses Unix, strings;

Const Arg0 : PChar = '/bin/lS';
Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

```
    GetMem (PP, 3*SizeOf(Pchar));
    PP[0]:= Arg0;
    PP[1]:= Arg1;
    PP[3]:= Nil;
    { Execute '/bin/lS -l', with current environment }
    fpExecv ('/bin/lS',pp);
```

end.

1.4.12 FpExecve

Synopsis: Execute process using environment

Declaration: `function FpExecve(path: PChar; argv: PPChar; envp: PPChar) : cint`
`function FpExecve(const path: RawByteString; argv: PPChar; envp: PPChar)`
`: cint`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`, and the environment in `envp`. They are pointers to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. On success, `execve` does not return.

Errors: Extended error information can be retrieved with `fpGetErrno` (193), and includes the following:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted .

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `fpExecv` (186), `fpFork` (190)

Listing: `./examples/bunixex/ex7.pp`

Program Example7;

{ Program to demonstrate the Execve function. }

Uses BaseUnix, strings;

Const Arg0 : PChar = '/bin/lS';
 Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

GetMem (PP, 3 * **SizeOf**(Pchar));
 PP[0] := Arg0;
 PP[1] := Arg1;
 PP[3] := **Nil**;
{ Execute '/bin/lS -l', with current environment }
{ Env is defined in system.inc }
 fpExecVe ('/bin/lS', pp, envp);

end.

1.4.13 FpExit

Synopsis: Exit the current process

Declaration: `procedure FpExit (Status: cint)`

Visibility: default

Description: `FpExit` exits the currently running process, and report `Status` as the exit status.

Remark If this call is executed, the normal unit finalization code will not be executed. This may lead to unexpected errors and stray files on your system. It is therefore recommended to use the `Halt` call instead.

Errors: None.

See also: `FpFork` ([190](#)), `FpExecve` ([187](#))

1.4.14 FpFcntl

Synopsis: File control operations.

Declaration: `function FpFcntl(fildes: cint; cmd: cint) : cint`
`function FpFcntl(fildes: cint; cmd: cint; arg: cint) : cint`
`function FpFcntl(fildes: cint; cmd: cint; var arg: FLock) : cint`

Visibility: default

Description: Read/set a file's attributes. `Fildes` a valid file descriptor. `Cmd` specifies what to do, and is one of the following:

F_GetFdRead the `close_on_exec` flag. If the low-order bit is 0, then the file will remain open across `execve` calls.

F_GetFlRead the descriptor's flags.

F_GetOwnGet the Process ID of the owner of a socket.

F_SetFdSet the `close_on_exec` flag of `fildes`. (only the least significant bit is used).

F_GetLkReturn the `flock` record that prevents this process from obtaining the lock, or set the `l_type` field of the lock of there is no obstruction. `Arg` is the `flock` record.

F_SetLkSet the lock or clear it (depending on `l_type` in the `flock` structure). if the lock is held by another process, an error occurs.

F_GetLkwSame as for **F_Setlk**, but wait until the lock is released.

F_SetOwnSet the Process or process group that owns a socket.

The function returns 0 if successful, -1 otherwise.

Errors: On error, -1 is returned. Use `fpGetErrno` ([193](#)) for extended error information.

sys_ebadf`Fd` has a bad file descriptor.

sys_eagain or sys_eaccessFor , if the lock is held by another process.

1.4.15 **fpfdfillset**

Synopsis: Set all file descriptors in the set.

Declaration: `function fpfdfillset(var nset: TFDSet) : cint`

Visibility: default

Description: `fpfdfillset` sets all file descriptors in `nset`.

See also: `FpSelect` (214), `FpFD_ZERO` (190), `FpFD_IsSet` (189), `FpFD_Clr` (189), `FpFD_Set` (189)

1.4.16 **fpFD_CLR**

Synopsis: Clears a file descriptor in a set

Declaration: `function fpFD_CLR(fdno: cint; var nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Clr` clears file descriptor `fdno` in file descriptor set `nset`.

For an example, see `FpSelect` (214).

Errors: None.

See also: `FpSelect` (214), `FpFD_ZERO` (190), `FpFD_Set` (189), `FpFD_IsSet` (189)

1.4.17 **fpFD_ISSET**

Synopsis: Check whether a file descriptor is set

Declaration: `function fpFD_ISSET(fdno: cint; const nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Set` Checks whether file descriptor `fdNo` in file descriptor set `fds` is set. It returns zero if the descriptor is not set, 1 if it is set. If the number of the file descriptor it wrong, -1 is returned.

For an example, see `FpSelect` (214).

Errors: If an invalid file descriptor number is passed, -1 is returned.

See also: `FpSelect` (214), `FpFD_ZERO` (190), `FpFD_Clr` (189), `FpFD_Set` (189)

1.4.18 **fpFD_SET**

Synopsis: Set a file descriptor in a set

Declaration: `function fpFD_SET(fdno: cint; var nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Set` sets file descriptor `fdno` in file descriptor set `nset`.

For an example, see `FpSelect` (214).

Errors: None.

See also: `FpSelect` (214), `FpFD_ZERO` (190), `FpFD_Clr` (189), `FpFD_IsSet` (189)

1.4.19 fpFD_ZERO

Synopsis: Clear all file descriptors in set

Declaration: `function fpFD_ZERO(out nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_ZERO` clears all the file descriptors in the file descriptor set `nset`.

For an example, see `FpSelect` (214).

Errors: None.

See also: `FpSelect` (214), `FpFD_Clr` (189), `FpFD_Set` (189), `FpFD_IsSet` (189)

1.4.20 FpFork

Synopsis: Create child process

Declaration: `function FpFork : TPid`

Visibility: default

Description: `FpFork` creates a child process which is a copy of the parent process. `FpFork` returns the process ID in the parent process, and zero in the child's process. (you can get the parent's PID with `fpGetPPid` (195)).

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagainNot enough memory to create child process.

See also: `fpExecve` (187), `#rtl.linux.Clone` (975)

1.4.21 FPFStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpFStat(fd: cint; var sb: Stat) : cint`
`function FPFStat(var F: Text; var Info: Stat) : Boolean`
`function FPFStat(var F: File; var Info: Stat) : Boolean`

Visibility: default

Description: `FpFStat` gets information about the file specified in one of the following:

Fda valid file descriptor.

Fan opened text file or untyped file.

and stores it in `Info`, which is of type `stat` (235). The function returns zero if the call was successful, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

sys_enoent`Path` does not exist.

See also: `FpStat` (223), `FpLStat` (200)

Listing: `./examples/bunixex/ex28.pp`

```

program example28;

{ Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
    { Make a file }
    assign (f, 'test.fil');
    rewrite (f);
    for i:=1 to 10 do writeln (f, 'Testline # ', i);
    close (f);
    { Do the call on made file. }
    if fpstat ('test.fil', info) <= 0 then
        begin
            writeln ('Fstat failed. Errno : ', fpgeterrno);
            halt (1);
        end;
    writeln;
    writeln ('Result of fstat on file ''test.fil''.');
    writeln ('Inode   : ', info.st_ino);
    writeln ('Mode    : ', info.st_mode);
    writeln ('nlink   : ', info.st_nlink);
    writeln ('uid     : ', info.st_uid);
    writeln ('gid     : ', info.st_gid);
    writeln ('rdev    : ', info.st_rdev);
    writeln ('Size    : ', info.st_size);
    writeln ('Blksize : ', info.st_blksize);
    writeln ('Blocks  : ', info.st_blocks);
    writeln ('atime   : ', info.st_atime);
    writeln ('mtime   : ', info.st_mtime);
    writeln ('ctime   : ', info.st_ctime);
    { Remove file }
    erase (f);
end.

```

1.4.22 FpFtruncate

Synopsis: Truncate file on certain size.

Declaration: `function FpFtruncate(fd: cint; flength: TOff) : cint`

Visibility: default

Description: `FpFtruncate` sets the length of a file in `fd` on `flength` bytes, where `flength` must be less than or equal to the current length of the file in `fd`.

The function returns zero if the call was successful, a nonzero return value indicates that an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` ([193](#)).

See also: `FpOpen` ([206](#)), `FpClose` ([183](#)), `FpRead` ([210](#)), `FpWrite` ([231](#)), `FpLSeek` ([199](#))

1.4.23 FpGetcwd

Synopsis: Retrieve the current working directory.

Declaration: `function FpGetcwd(path: PChar; siz: TSize) : PChar`
`function FpGetcwd : RawByteString`

Visibility: default

Description: `fpgetCWD` returns the current working directory of the running process. It is returned in `Path`, which points to a memory location of at least `siz` bytes.

If the function is successful, a pointer to `Path` is returned, or a string with the result. On error `Nil` or an empty string are returned.

Errors: On error `Nil` or an empty string are returned.

See also: `FpGetPID` ([195](#)), `FpGetUID` ([197](#))

1.4.24 FpGetegid

Synopsis: Return effective group ID

Declaration: `function FpGetegid : TGid`

Visibility: default

Description: `FpGetegid` returns the effective group ID of the currently running process.

Errors: None.

See also: `FpGetGid` ([194](#)), `FpGetUid` ([197](#)), `FpGetEUid` ([193](#)), `FpGetPid` ([195](#)), `FpGetPPid` ([195](#)), `fpSetUID` ([217](#)), `FpSetGid` ([216](#))

Listing: `./examples/bunixex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses `BaseUnix;`

begin

`writeln ('Group Id = ',fpgetgid, ' Effective group Id = ',fpgetegid);`
end.

1.4.25 FpGetEnv

Synopsis: Return value of environment variable.

Declaration: `function FpGetEnv(name: PChar) : PChar`
`function FpGetEnv(name: string) : PChar`

Visibility: default

Description: `FPGetEnv` returns the value of the environment variable in `Name`. If the variable is not defined, `nil` is returned. The value of the environment variable may be the empty string. A `PChar` is returned to accommodate for strings longer than 255 bytes, `TERMCAP` and `LS_COLORS`, for instance.

Errors: None.

Listing: ./examples/bunixex/ex41.pp

```

Program Example41;

{ Program to demonstrate the GetEnv function. }

Uses BaseUnix;

begin
  WriteLn ( 'Path is : ',fpGetenv( 'PATH' ));
end.

```

1.4.26 fpgeterrno

Synopsis: Retrieve extended error information.

Declaration: `function fpgeterrno : LongInt`

Visibility: default

Description: `fpgeterrno` returns extended information on the latest error. It is set by all functions that communicate with the kernel or C library.

Errors: None.

See also: `fpseterrno` ([215](#))

1.4.27 FpGeteuid

Synopsis: Return effective user ID

Declaration: `function FpGeteuid : TUid`

Visibility: default

Description: `FpGeteuid` returns the effective user ID of the currently running process.

Errors: None.

See also: `FpGetUid` ([197](#)), `FpGetGid` ([194](#)), `FpGetEGid` ([192](#)), `FpGetPid` ([195](#)), `FpGetPPid` ([195](#)), `fpSetUID` ([217](#)), `FpSetGid` ([216](#))

Listing: ./examples/bunixex/ex17.pp

```

Program Example17;

{ Program to demonstrate the GetUid and GetEUid functions. }

Uses BaseUnix;

begin
  writeLn ( 'User Id = ',fpgetuid, ' Effective user Id = ',fpgeteuid);
end.

```

1.4.28 FpGetgid

Synopsis: Return real group ID

Declaration: `function FpGetgid : TGid`

Visibility: default

Description: `FpGetgid` returns the real group ID of the currently running process.

Errors: None.

See also: `FpGetEGid` (192), `FpGetUid` (197), `FpGetEUid` (193), `FpGetPid` (195), `FpGetPPid` (195), `fpSetUID` (217), `FpSetGid` (216)

Listing: `./examples/bunixex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses `BaseUnix;`

begin

`writeln ('Group Id = ',fpgetgid , ' Effective group Id = ',fpgetegid);`
end.

1.4.29 FpGetgroups

Synopsis: Get the list of supplementary groups.

Declaration: `function FpGetgroups(gidsetsize: cint; var grouplist: TGrpArr) : cint`

Visibility: default

Description: `FpGetgroups` returns up to `gidsetsize` groups in `GroupList`

If the function is successful, then number of groups that were stored is returned. On error, -1 is returned.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` (193)

See also: `FpGetpgrp` (194), `FpGetGID` (194), `FpGetEGID` (192)

1.4.30 FpGetpgrp

Synopsis: Get process group ID

Declaration: `function FpGetpgrp : TPid`

Visibility: default

Description: `FpGetpgrp` returns the process group ID of the current process.

Errors: None.

See also: `fpGetPID` (195), `fpGetPPID` (195), `FpGetGID` (194), `FpGetUID` (197)

1.4.31 FpGetpid

Synopsis: Return current process ID

Declaration: `function FpGetpid : TPid`

Visibility: default

Description: `FpGetpid` returns the process ID of the currently running process.

Note: There exist a portable alternative to `fpGetpid`: `system.GetProcessID`. Please use `fpGetpid` only if you are writing Unix specific code. `System.GetProcessID` will work on all operating systems.

Errors: None.

See also: `FpGetPPid` ([195](#))

Listing: `./examples/bunixex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the GetPid, GetPPid function. }

Uses `BaseUnix;`

begin

`WriteLn ('Process Id = ',fpgetpid , ' Parent process Id = ',fpgetppid);`
end.

1.4.32 FpGetppid

Synopsis: Return parent process ID

Declaration: `function FpGetppid : TPid`

Visibility: default

Description: `FpGetppid` returns the Process ID of the parent process.

Errors: None.

See also: `FpGetPid` ([195](#))

Listing: `./examples/bunixex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the GetPid, GetPPid function. }

Uses `BaseUnix;`

begin

`WriteLn ('Process Id = ',fpgetpid , ' Parent process Id = ',fpgetppid);`
end.

1.4.33 fpGetPriority

Synopsis: Return process priority

Declaration: `function fpGetPriority(Which: cint; Who: cint) : cint`

Visibility: default

Description: GetPriority returns the priority with which a process is running. Which process(es) is determined by the Which and Who variables. Which can be one of the predefined Prio_Process, Prio_PGrp, Prio_User, in which case Who is the process ID, Process group ID or User ID, respectively.

For an example, see FpNice (205).

Errors: Error information is returned solely by the FpGetErrno (193) function: a priority can be a positive or negative value.

sys_esrchNo process found using which and who.

sys_einvalWhich was not one of Prio_Process, Prio_Grp or Prio_User.

See also: FpSetPriority (216), FpNice (205)

1.4.34 FpGetRLimit

Synopsis: Get process resource limits

Declaration: `function FpGetRLimit(resource: cint; rlim: PRLimit) : cint`

Visibility: default

Description: FpGetRLimit gets the resource limits for the current process: resource determines the resource of which the kernel should return the limits (one of the many RLIMIT_* constants). rlim should point to a TRLimit (238) record and on success will contain the resource limits.

The function returns zero if the resource limits were correctly returned.

Errors: On error, -1 is returned and fpgeterrno (193) can be used to retrieve the error code.

See also: FpSetRLimit (216)

1.4.35 FpGetsid

Synopsis: Get current session ID

Declaration: `function FpGetsid(pid: TPid) : TPid`

Visibility: default

Description: FpGetsid returns the session ID of the process pid. The return value is the session ID of the process. (it equals the PID of the session leader). The process pid must be in the same session as the current process.

Errors: On error, -1 is returned, and extended error information can be obtained with fpGetErrno.

See also: FpGetpgid (194), FpGetpid (195), FpGetPpid (195)

1.4.36 FpGetuid

Synopsis: Return current user ID

Declaration: `function FpGetuid : TUid`

Visibility: default

Description: `FpGetuid` returns the real user ID of the currently running process.

Errors: None.

See also: `FpGetGid` ([194](#)), `FpGetEUid` ([193](#)), `FpGetEGid` ([192](#)), `FpGetPid` ([195](#)), `FpGetPPid` ([195](#)), `fpSetUID` ([217](#))

Listing: `./examples/bunixex/ex17.pp`

Program `Example17;`

{ Program to demonstrate the GetUid and GetEUid functions. }

Uses `BaseUnix;`

begin

`writeln ('User Id = ',fpgetuid,' Effective user Id = ',fpgeteuid);`
end.

1.4.37 FpIOctl

Synopsis: General kernel IOCTL call.

Declaration: `function FpIOctl(Handle: cint; Ndx: TIOctlRequest; Data: Pointer) : cint`

Visibility: default

Description: This is a general interface to the Unix/ Linux `ioctl` call. It performs various operations on the file descriptor `Handle`. `Ndx` describes the operation to perform. `Data` points to data needed for the `Ndx` function. The structure of this data is function-dependent, so we don't elaborate on this here. For more information on this, see various manual pages under Linux.

Errors: Extended error information can be retrieved using `fpGetErrno` ([193](#)).

Listing: `./examples/bunixex/ex54.pp`

Program `Example54;`

uses `BaseUnix,Termio;`

{ Program to demonstrate the IOCtl function. }

var

`tios : Termios;`

begin

{ \$ifdef FreeBSD }

`fpIOctl(1,TIOCGETA,@tios); // these constants are very OS dependant.`

// see the tcgetattr example for a better way

{ \$endif }

`WriteLn('Input Flags : $',hexstr(tios.c_iflag,8));`

```

    WriteLn('Output Flags : $',hexstr(tios.c_oflag,8));
    WriteLn('Line Flags   : $',hexstr(tios.c_lflag,8));
    WriteLn('Control Flags: $',hexstr(tios.c_cflag,8));
end.

```

1.4.38 FpKill

Synopsis: Send a signal to a process

Declaration: `function FpKill(pid: TPid; sig: cint) : cint`

Visibility: default

Description: `fpKill` sends a signal `Sig` to a process or process group. If `Pid`>0 then the signal is sent to `Pid`, if it equals -1, then the signal is sent to all processes except process 1. If `Pid`<-1 then the signal is sent to process group -`Pid`.

The return value is zero, except in case three, where the return value is the number of processes to which the signal was sent.

Errors: Extended error information can be retrieved using `fpGetErrno` ([193](#)):

sys_einvalAn invalid signal is sent.

sys_esrchThe `Pid` or process group don't exist.

sys_epermThe effective userid of the current process doesn't math the one of process `Pid`.

See also: `FpSigAction` ([218](#)), `FpSignal` ([220](#))

1.4.39 FpLink

Synopsis: Create a hard link to a file

Declaration: `function FpLink(existing: PChar; newone: PChar) : cint`
`function FpLink(const existing: RawByteString;`
`const newone: RawByteString) : cint`

Visibility: default

Description: `fpLink` makes `NewOne` point to the same file as `Existing`. The two files then have the same inode number. This is known as a 'hard' link. The function returns zero if the call was successful, and returns a non-zero value if the call failed.

Errors: The following error codes are returned:

sys_exdev`Existing` and `NewOne` are not on the same file system.

sys_epermThe file system containing `Existing` and `NewOne` doesn't support linking files.

sys_eaccessWrite access for the directory containing `NewOne` is disallowed, or one of the directories in `Existing` or `NewOne` has no search (=execute) permission.

sys_enoentA directory entry in `Existing` or `NewOne` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdirA directory entry in `Existing` or `NewOne` is nor a directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe files are on a read-only file system.

sys_eexist NewOne already exists.

sys_emlink Existing has reached maximal link count.

sys_eloop existing or NewOne has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

sys_enospc The device containing NewOne has no room for another entry.

sys_eperm Existing points to . or .. of a directory.

See also: [fpSymLink \(224\)](#), [fpUnLink \(229\)](#)

Listing: ./examples/bunixex/ex21.pp

Program Example21;

{ Program to demonstrate the Link and UnLink functions. }

Uses BaseUnix;

Var F : Text;

 S : **String**;

begin

 Assign (F, 'test.txt');

Rewrite (F);

Writeln (F, 'This is written to test.txt');

 Close(f);

{ new.txt and test.txt are now the same file }

if fpLink ('test.txt', 'new.txt') <> 0 **then**

writeln ('Error when linking !');

{ Removing test.txt still leaves new.txt }

If fpUnlink ('test.txt') <> 0 **then**

Writeln ('Error when unlinking !');

 Assign (f, 'new.txt');

Reset (F);

While not EOF(f) **do**

begin

Readln(F,S);

Writeln ('> ',s);

end;

 Close (f);

{ Remove new.txt also }

If not FPUntlink ('new.txt') <> 0 **then**

Writeln ('Error when unlinking !');

end.

1.4.40 FpLseek

Synopsis: Set file pointer position.

Declaration: function FpLseek(fd: cint; offset: TOff; whence: cint) : TOff

Visibility: default

Description: FpLseek sets the current file position of file fd to Offset, starting from Whence, which can be one of the following:

Seek_SetOffset is the absolute position in the file.

Seek_CurOffset is relative to the current position.

Seek_endOffset is relative to the end of the file.

The function returns the new file position, or -1 of an error occurred.

For an example, see [FpOpen \(206\)](#).

Errors: Extended error information can be retrieved using [fpGetErrno \(193\)](#).

See also: [FpOpen \(206\)](#), [FpWrite \(231\)](#), [FpClose \(183\)](#), [FpRead \(210\)](#), [FpFTruncate \(191\)](#)

1.4.41 **fpLstat**

Synopsis: Return information about symbolic link. Do not follow the link

Declaration: `function fpLstat(path: PChar; Info: PStat) : cint`
`function fpLstat(const path: RawByteString; Info: PStat) : cint`
`function fpLstat(path: PChar; var Info: Stat) : cint`
`function fpLstat(const Filename: RawByteString; var Info: Stat) : cint`

Visibility: default

Description: `FpLstat` gets information about the link specified in `Path` (or `FileName`, and stores it in `Info`, which points to a record of type `TStat`. Contrary to [FpFstat \(190\)](#), it stores information about the link, not about the file the link points to. The function returns zero if the call was successful, a nonzero return value indicates failure. failed.

Errors: Extended error information is returned by the [FpGetErrno \(193\)](#) function.

`sys_enoentPath` does not exist.

See also: [FpFStat \(190\)](#), [#rtl.unixtype.TStatFS \(2141\)](#)

Listing: `./examples/unixex/ex29.pp`

```
program example29;

{ Program to demonstrate the LStat function. }

uses BaseUnix, Unix;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ', i);
  close (f);
  { Do the call on made file. }
  if fpstat ('test.fil', info) <> 0 then
    begin
      writeln('Fstat failed. Errno : ', fpgeterrno);
      halt (1);
    end;
  writeln;
```

```

writeln ('Result of stat on file ''test.fil''.');
writeln ('Inode   : ',info.st_ino);
writeln ('Mode    : ',info.st_mode);
writeln ('nlink   : ',info.st_nlink);
writeln ('uid     : ',info.st_uid);
writeln ('gid     : ',info.st_gid);
writeln ('rdev    : ',info.st_rdev);
writeln ('Size    : ',info.st_size);
writeln ('Blksize  : ',info.st_blksize);
writeln ('Blocks  : ',info.st_blocks);
writeln ('atime   : ',info.st_atime);
writeln ('mtime   : ',info.st_mtime);
writeln ('ctime   : ',info.st_ctime);

If fpSymLink ('test.fil','test.lnk')<>0 then
  writeln ('Link failed ! Errno : ',fpgeterrno);

if fplstat ('test.lnk',@info)<>0 then
  begin
    writeln('LStat failed. Errno : ',fpgeterrno);
    halt (1);
  end;
writeln;
writeln ('Result of fstat on file ''test.lnk''.');
writeln ('Inode   : ',info.st_ino);
writeln ('Mode    : ',info.st_mode);
writeln ('nlink   : ',info.st_nlink);
writeln ('uid     : ',info.st_uid);
writeln ('gid     : ',info.st_gid);
writeln ('rdev    : ',info.st_rdev);
writeln ('Size    : ',info.st_size);
writeln ('Blksize  : ',info.st_blksize);
writeln ('Blocks  : ',info.st_blocks);
writeln ('atime   : ',info.st_atime);
writeln ('mtime   : ',info.st_mtime);
writeln ('ctime   : ',info.st_ctime);
{ Remove file and link }
erase (f);
fpunlink ('test.lnk');
end.

```

1.4.42 FpMkdir

Synopsis: Create a new directory

Declaration: `function FpMkdir(path: PChar; Mode: TMode) : cint`
`function FpMkdir(const path: RawByteString; Mode: TMode) : cint`

Visibility: default

Description: `FpMkDir` creates a new directory `Path`, and sets the new directory's mode to `Mode`. `Path` can be an absolute path or a relative path. Note that only the last element of the directory will be created, higher level directories must already exist, and must be writeable by the current user.

On success, 0 is returned. if the function fails, -1 is returned.

Note: There exist a portable alternative to `fpMkDir`: `system.mkdir`. Please use `fpMkDir` only if you are writing Unix specific code. `System.mkdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([193](#)).

See also: `fpGetCWD` ([192](#)), `fpChDir` ([181](#))

1.4.43 FpMkfifo

Synopsis: Create FIFO (named pipe) in file system

Declaration: `function FpMkfifo(path: PChar; Mode: TMode) : cint`
`function FpMkfifo(const path: RawByteString; Mode: TMode) : cint`

Visibility: default

Description: `fpMkFifo` creates named a named pipe in the file system, with name `Path` and mode `Mode`.

The function returns zero if the command was successful, and nonzero if it failed.

Errors: The error codes include:

sys_enfileToo many file descriptors for this process.

sys_enfileThe system file table is full.

1.4.44 Fpmmmap

Synopsis: Create memory map of a file

Declaration: `function Fpmmmap(start: pointer; len: size_t; prot: cint; flags: cint; fd: cint; offst: off_t) : pointer`

Visibility: default

Description: `FpMMap` maps or unmaps files or devices into memory. The different arguments determine what and how the file is mapped:

adrAddress where to mmap the device. This address is a hint, and may not be followed.

lenSize (in bytes) of area to be mapped.

protProtection of mapped memory. This is a OR-ed combination of the following constants:

PROT_EXECThe memory can be executed.

PROT_READThe memory can be read.

PROT_WRITEThe memory can be written.

PROT_NONEThe memory can not be accessed.

flagsContains some options for the mmap call. It is an OR-ed combination of the following constants:

MAP_FIXEDDo not map at another address than the given address. If the address cannot be used, `MMap` will fail.

MAP_SHAREDShare this map with other processes that map this object.

MAP_PRIVATECreate a private map with copy-on-write semantics.

MAP_ANONYMOUS`fd` does not have to be a file descriptor.

One of the options `MAP_SHARED` and `MAP_PRIVATE` must be present, but not both at the same time.

fdFile descriptor from which to map.

offOffset to be used in file descriptor `fd`.

The function returns a pointer to the mapped memory, or a -1 in case of an error.

Errors: On error, -1 is returned and extended error information is returned by the FpGetErrno (193) function.

Sys_EBADFfd is not a valid file descriptor and MAP_ANONYMOUS was not specified.

Sys_EACCESSMAP_PRIVATE was specified, but fd is not open for reading. Or MAP_SHARED was asked and PROT_WRITE is set, fd is not open for writing

Sys_EINVALOne of the record fields Start, length or offset is invalid.

Sys_ETXTBUSYMAP_DENYWRITE was set but the object specified by fd is open for writing.

Sys_EAGAINfd is locked, or too much memory is locked.

Sys_ENOMEMNot enough memory for this operation.

See also: FpMUnMap (204)

Listing: ./examples/unixex/ex66.pp

Program Example66;

{ Program to demonstrate the MMap function. }

Uses BaseUnix, Unix;

Var S : String;
 fd : cint;
 Len : longint;
 // args : tmmargs;
 P : PChar;

begin

 s:= 'This is the string';
 Len:=Length(S);
 fd:=fpOpen('testfile.txt',O_wrOnly or o_creat);
 If fd=-1 then
 Halt(1);
 If fpWrite(fd,S[1],Len)=-1 then
 Halt(2);
 fpClose(fd);
 fd:=fpOpen('testfile.txt',O_rdOnly);
 if fd=-1 then
 Halt(3);
 P:=Pchar(fpmmmap(nil, len+1, PROT_READ or PROT_WRITE, MAP_PRIVATE, fd, 0));

 If longint(P)=-1 then
 Halt(4);
 Writeln('Read in memory : ',P);
 fpclose(fd);
 if fpMUnMap(P,Len)<>0 Then
 Halt(fpgeterrno);

end.

1.4.45 Fpmprotect

Synopsis: Set memory protection

Declaration: function Fpmprotect(start: pointer; len: size_t; prot: cint) : cint

Visibility: default

Description: `fpmprotect` sets memory protection on a certain block of memory. The memory block to protect starts at `adr` and has size `len`. The `prot` argument specifies the kind of protection to apply, and is a bit-wise OR-ed combination of the following:

PROT_NONE Memory cannot be accessed

PROT_READ Memory can be read

PROT_WRITE Memory can be written

PROT_EXEC Memory can be executed

PROT_SEM Memory can be used for atomic operations

PROT_SA Memory must have strong access order (powerPC only).

1.4.46 Fpmunmap

Synopsis: Unmap previously mapped memory block

Declaration: `function Fpmunmap(start: pointer; len: size_t) : cint`

Visibility: default

Description: `FpMUnMap` unmaps the memory block of size `Len`, pointed to by `Adr`, which was previously allocated with `FpMMap` (202).

The function returns `True` if successful, `False` otherwise.

For an example, see `FpMMap` (202).

Errors: In case of error the function returns a nonzero value, extended error information is returned by the `FpGetErrno` (193) function. See `FpMMap` (202) for possible error values.

See also: `FpMMap` (202)

1.4.47 FpNanoSleep

Synopsis: Suspend process for a short time

Declaration: `function FpNanoSleep(req: ptimespec; rem: ptimespec) : cint`

Visibility: default

Description: `FpNanoSleep` suspends the process till a time period as specified in `req` has passed. Then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and `rem` will contain the remaining time till the end of the intended period. In this case the return value will be -1, and `ErrNo` will be set to `EINTR`.

If the function returns without error, the return value is zero.

Errors: If an error occurred or the call was interrupted, -1 is returned. Extended error information can be retrieved using `fpGetErrno` (193).

See also: `FpPause` (208), `FpAlarm` (180)

Listing: `./examples/bunixex/ex72.pp`

```

program example72;

{ Program to demonstrate the NanoSleep function. }

uses BaseUnix;

Var
    Req, Rem : TimeSpec;
    Res : Longint;

begin
    With Req do
        begin
            tv_sec:=10;
            tv_nsec:=100;
        end;
    Write( 'NanoSleep returned : ');
    Flush( Output );
    Res:=( fpNanoSleep (@Req,@rem));
    WriteLn( res );
    If (res<>0) then
        With rem do
            begin
                WriteLn( 'Remaining seconds      : ',tv_sec );
                WriteLn( 'Remaining nanoseconds : ',tv_nsec );
            end;
end.

```

1.4.48 fpNice

Synopsis: Set process priority

Declaration: `function fpNice(N: cint) : cint`

Visibility: default

Description: `Nice` adds `-N` to the priority of the running process. The lower the priority numerically, the less the process is favored. Only the superuser can specify a negative `N`, i.e. increase the rate at which the process is run.

If the function is successful, zero is returned. On error, a nonzero value is returned.

Errors: Extended error information is returned by the `FpGetErrno` ([193](#)) function.

sys_epermA non-superuser tried to specify a negative `N`, i.e. do a priority increase.

See also: `FpGetPriority` ([196](#)), `FpSetPriority` ([216](#))

Listing: `./examples/unixex/ex15.pp`

```

Program Example15;

{ Program to demonstrate the Nice and Get/SetPriority functions. }

Uses BaseUnix, Unix;

begin

```

```

writeln ('Setting priority to 5');
fpsetpriority (prio_process,fpgetpid,5);
writeln ('New priority = ',fpgetpriority (prio_process,fpgetpid));
writeln ('Doing nice 10');
fpnice (10);
writeln ('New Priority = ',fpgetpriority (prio_process,fpgetpid));
end.

```

1.4.49 FpOpen

Synopsis: Open file and return file descriptor

Declaration: `function FpOpen(path: PChar; flags: cint; Mode: TMode) : cint`
`function FpOpen(path: PChar; flags: cint) : cint`
`function FpOpen(const path: RawByteString; flags: cint) : cint`
`function FpOpen(const path: RawByteString; flags: cint; Mode: TMode)`
`: cint`
`function FpOpen(path: ShortString; flags: cint) : cint`
`function FpOpen(path: ShortString; flags: cint; Mode: TMode) : cint`

Visibility: default

Description: `FpOpen` opens a file in `Path` with flags `flags` and mode `Mode` One of the following:

O_RdOnlyFile is opened Read-only

O_WrOnlyFile is opened Write-only

O_RdWrFile is opened Read-Write

The flags may be OR-ed with one of the following constants:

O_CreatFile is created if it doesn't exist.

O_ExclIf the file is opened with `O_Creat` and it already exists, the call will fail.

O_NoCttyIf the file is a terminal device, it will NOT become the process' controlling terminal.

O_TruncIf the file exists, it will be truncated.

O_Appendthe file is opened in append mode. *Before each write*, the file pointer is positioned at the end of the file.

O_NonBlockThe file is opened in non-blocking mode. No operation on the file descriptor will cause the calling process to wait till.

O_NDelayIdem as `O_NonBlock`

O_SyncThe file is opened for synchronous IO. Any write operation on the file will not return until the data is physically written to disk.

O_NoFollowif the file is a symbolic link, the open fails. (Linux 2.1.126 and higher only)

O_Directoryif the file is not a directory, the open fails. (Linux 2.1.126 and higher only)

`Path` can be of type `PChar` or `String`. The optional `mode` argument specifies the permissions to set when opening the file. This is modified by the `umask` setting. The real permissions are `Mode` and not `umask`. The return value of the function is the file descriptor, or a negative value if there was an error.

Errors: Extended error information can be retrieved using `fpGetErrno` ([193](#)).

See also: `FpClose` ([183](#)), `FpRead` ([210](#)), `FpWrite` ([231](#)), `FpFTruncate` ([191](#)), `FpLSeek` ([199](#))

Listing: ./examples/bunixex/ex19.pp

Program Example19;

{ Program to demonstrate the fpOpen, fpwrite and fpClose functions. }

Uses BaseUnix;

Const Line : **String**[80] = 'This is easy writing !';

Var FD : CInt;

begin

FD:=fpOpen ('Test.dat',O_WrOnly or O_Creat);

if FD>0 **then**

begin

if **length**(Line)<>fpwrite (FD,Line[1],**Length**(Line)) **then**

WriteLn ('Error when writing to file !');

fpClose(FD);

end;

end.

1.4.50 FpOpendir

Synopsis: Open a directory for reading

Declaration: function FpOpendir(dirname: PChar) : pDir
 function FpOpendir(const dirname: RawByteString) : pDir
 function FpOpendir(dirname: ShortString) : pDir

Visibility: default

Description: FpOpenDir opens the directory DirName, and returns a pdir pointer to a Dir (233) record, which can be used to read the directory structure. If the directory cannot be opened, nil is returned.

Errors: Extended error information can be retrieved using fpGetErrno (193).

See also: FpCloseDir (184), FpReadDir (211)

Listing: ./examples/bunixex/ex35.pp

Program Example35;

*{ Program to demonstrate the
 OpenDir, ReadDir, SeekDir and TellDir functions. }*

Uses BaseUnix;

Var TheDir : PDir;
 ADirent : PDirent;
 Entry : Longint;

begin

TheDir:=fpOpenDir(' ./ ');

Repeat

// Entry:=fpTellDir(TheDir);

ADirent:=fpReadDir (TheDir^);

If ADirent<>Nil **then**

```

    With ADirent^ do
    begin
        Writeln ('Entry No : ', Entry);
        Writeln ('Inode   : ', d_fileno);
//      Writeln ('Offset  : ', d_off);
        Writeln ('Reclen  : ', d_reclen);
        Writeln ('Name    : ', pchar(@d_name[0]));
    end;
    Until ADirent=Nil;
  Repeat
    Write ('Entry No. you would like to see again (-1 to stop): ');
    ReadLn (Entry);
    If Entry<>-1 then
    begin
//      fpSeekDir (TheDir, Entry);           // not implemented for various platforms
        ADirent:=fpReadDir (TheDir^);
        If ADirent<>Nil then
        With ADirent^ do
        begin
            Writeln ('Entry No : ', Entry);
            Writeln ('Inode   : ', d_fileno);
//          Writeln ('Offset  : ', d_off);
            Writeln ('Reclen  : ', d_reclen);
            Writeln ('Name    : ', pchar(@d_name[0]));
        end;
    end;
  Until Entry=-1;
  fpCloseDir (TheDir^);
end.

```

1.4.51 FpPause

Synopsis: Wait for a signal to arrive

Declaration: `function FpPause : cint`

Visibility: default

Description: `FpPause` puts the process to sleep and waits until the application receives a signal. If a signal handler is installed for the received signal, the handler will be called and after that pause will return control to the process.

For an example, see `fpAlarm` ([180](#)).

1.4.52 FpPipe

Synopsis: Create a set of pipe file handlers

Declaration: `function FpPipe(var fildes: TFilDes) : cint`

Visibility: default

Description: `FpPipe` creates a pipe, i.e. two file objects, one for input, one for output. The file handles are returned in the array `fildes`. The input handle is in the 0-th element of the array, the output handle is in the 1-st element.

The function returns zero if everything went successfully, a nonzero return value indicates an error.

Errors: In case the function fails, the following return values are possible:

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

See also: `#rtl.unix.POpen` (2118), `fpMkFifo` (202)

Listing: `./examples/bunixex/ex36.pp`

Program `Example36`;

{ Program to demonstrate the AssignPipe function. }

Uses `BaseUnix, Unix`;

Var `pipi, pipo : Text;`
`s : String`;

```
begin
  Writeln ('Assigning Pipes. ');
  If assignpipe(pipi, pipo) <> 0 then
    Writeln('Error assigning pipes !', fpgeterrno);
  Writeln ('Writing to pipe, and flushing. ');
  Writeln (pipo, 'This is a textstring '); close(pipo);
  Writeln ('Reading from pipe. ');
  While not eof(pipi) do
    begin
      Readln (pipi, s);
      Writeln ('Read from pipe : ', s);
    end;
  close (pipi);
  writeln ('Closed pipes. ');
  writeln
end.
```

1.4.53 FpPoll

Synopsis: Poll a file descriptor for events.

Declaration: `function FpPoll(fds: ppollfd; nfds: cuint; timeout: clong) : cint`

Visibility: `default`

Description: `fpPoll` waits for events on file descriptors. `fds` points to an array of `tpollfd` records, each of these records describes a file descriptor on which to wait for events. The number of file descriptors is given by `nfds`. `>timeout` specifies the maximum time (in milliseconds) to wait for events.

On timeout, the result value is 0. If an event occurred on some descriptors, then the return value is the number of descriptors on which an event (or error) occurred. The `revents` field of the `tpollfd` records will contain the events for the file descriptor it described.

See also: `tpollfd` (177)

1.4.54 FppRead

Synopsis: Positional read: read from file descriptor at a certain position.

Declaration: `function FpPRead(fd: cint; buf: PChar; nbytes: TSize; offset: TOff) : TsSize`
`function FppRead(fd: cint; var buf; nbytes: TSize; offset: TOff) : TsSize`

Visibility: default

Description: `FpPRead` reads `nbytes` bytes from file descriptor `fd` into buffer `buf` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually read, or -1 on error.

Errors: On error, -1 is returned.

See also: `FpReadV` (213), `FpPWrite` (210)

1.4.55 FppWrite

Synopsis: Positional write: write to file descriptor at a certain position.

Declaration: `function FpPWrite(fd: cint; buf: PChar; nbytes: TSize; offset: TOff) : TsSize`
`function FppWrite(fd: cint; const buf; nbytes: TSize; offset: TOff) : TsSize`

Visibility: default

Description: `FppWrite` writes `nbytes` bytes from buffer `buf` into file descriptor `fd` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually written, or -1 on error.

Errors: On error, -1 is returned.

See also: `FpPRead` (209), `FpWriteV` (232)

1.4.56 FpRead

Synopsis: Read data from file descriptor

Declaration: `function FpRead(fd: cint; buf: PChar; nbytes: TSize) : TsSize`
`function FpRead(fd: cint; var buf; nbytes: TSize) : TsSize`

Visibility: default

Description: `FpdRead` reads at most `nbytes` bytes from the file descriptor `fd`, and stores them in `buf`.

The function returns the number of bytes actually read, or -1 if an error occurred. No checking on the length of `buf` is done.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

See also: `FpOpen` (206), `FpClose` (183), `FpWrite` (231), `FpFTruncate` (191), `FpLSeek` (199)

Listing: `./examples/bunixex/ex20.pp`

```

Program Example20;

{ Program to demonstrate the fdRead and fdTruncate functions. }

Uses BaseUnix;

Const Data : string[10] = '1234567890';

Var FD : cint;
    I : longint;

begin
    FD:=fpOpen('test.dat',o_wronly or o_creat,&666);
    if fd>0 then
        begin
            { Fill file with data }
            for I:=1 to 10 do
                if fpWrite (FD,Data[I],10)<>10 then
                    begin
                        writeln ('Error when writing !');
                        halt(1);
                    end;
                fpClose(FD);
                FD:=fpOpen('test.dat',o_rdonly);
                { Read data again }
                if FD>0 then
                    begin
                        For I:=1 to 5 do
                            if fpRead (FD,Data[I],10)<>10 then
                                begin
                                    Writeln ('Error when Reading !');
                                    Halt(2);
                                end;
                            fpClose(FD);
                            { Truncating file at 60 bytes }
                            { For truncating , file must be open or write }
                            FD:=fpOpen('test.dat',o_wronly,&666);
                            if FD>0 then
                                begin
                                    if fpfTruncate(FD,60)<>0 then
                                        Writeln('Error when truncating !');
                                    fpClose (FD);
                                end;
                            end;
                        end;
                    end;
                end;
            end.

```

1.4.57 FpReaddir

Synopsis: Read entry from directory

Declaration: `function FpReaddir(var dirp: Dir) : pDirent`

Visibility: default

Description: `FpReadDir` reads the next entry in the directory pointed to by `dirp`. It returns a `pdirent` pointer to a `dirent` (234) record describing the entry. If the next entry can't be read, `Nil` is returned.

For an example, see `FpOpenDir` (207).

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

See also: `FpCloseDir` (184), `FpOpenDir` (207)

1.4.58 `fpReadLink`

Synopsis: Read destination of symbolic link

Declaration: `function fpReadLink(name: PChar; linkname: PChar; maxlen: size_t) : cint`
`function fpReadLink(const Name: RawByteString) : RawByteString`

Visibility: default

Description: `FpReadLink` returns the file the symbolic link name is pointing to. The first form of this function accepts a buffer `linkname` of length `maxlen` where the filename will be stored. It returns the actual number of characters stored in the buffer.

The second form of the function returns simply the name of the file.

Errors: On error, the first form of the function returns -1; the second one returns an empty string. Extended error information is returned by the `FpGetErrno` (193) function.

SYS_ENOTDIRA part of the path in `Name` is not a directory.

SYS_EINVAL`maxlen` is not positive, or the file is not a symbolic link.

SYS_ENAMETOOLONGA pathname, or a component of a pathname, was too long.

SYS_ENOENTthe link name does not exist.

SYS_EACCESNo permission to search a directory in the path

SYS_ELOOPToo many symbolic links were encountered in translating the pathname.

SYS_EIOAn I/O error occurred while reading from the file system.

SYS_EFAULTThe buffer is not part of the process's memory space.

SYS_ENOMEMNot enough kernel memory was available.

See also: `FpSymLink` (224)

Listing: `./examples/unixex/ex62.pp`

Program `Example62`;

{ Program to demonstrate the ReadLink function. }

Uses `BaseUnix`, `Unix`;

Var `F` : `Text`;
`S` : **String**;

begin
`Assign (F, 'test.txt');`
`Rewrite (F);`
`Writeln (F, 'This is written to test.txt');`
`Close(f);`
{ new.txt and test.txt are now the same file }
`if fpSymLink ('test.txt', 'new.txt') <> 0 then`
`writeln ('Error when symlinking !');`
`S:=fpReadLink('new.txt');`

```

If S='' then
  Writeln ('Error reading link !')
Else
  Writeln ('Link points to : ',S);
{ Now remove links }
If fpUnlink ('new.txt')<>0 then
  Writeln ('Error when unlinking !');
If fpUnlink ('test.txt')<>0 then
  Writeln ('Error when unlinking !');
end.

```

1.4.59 FpReadV

Synopsis: Vector read: Read into multiple buffers

Declaration: `function FpReadV(fd: cint; const iov: piovec; iovcnt: cint) : TsSize`

Visibility: default

Description: `FpReadV` reads data from file descriptor `fd` and writes it into `iovcnt` buffers described by the `tiovec` (177) buffers pointed to by `iov`. It works like `fpRead` (210) only on multiple buffers.

Errors: On error, -1 is returned.

See also: `FpWriteV` (232), `FpPWrite` (210), `FpPRead` (209)

1.4.60 FpRename

Synopsis: Rename file

Declaration: `function FpRename(old: PChar; newpath: PChar) : cint`
`function FpRename(const old: RawByteString;`
`const newpath: RawByteString) : cint`

Visibility: default

Description: `FpRename` renames the file `Old` to `NewPath`. `NewPath` can be in a different directory than `Old`, but it cannot be on another partition (device). Any existing file on the new location will be replaced.

If the operation fails, then the `Old` file will be preserved.

The function returns zero on success, a nonzero value indicates failure.

Note: There exist a portable alternative to `fpRename`: `system.rename`. Please use `fpRename` only if you are writing Unix specific code. `System.rename` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

`sys_eisdir``NewPath` exists and is a directory, but `Old` is not a directory.

`sys_exdev``NewPath` and `Old` are on different devices.

`sys_enotempty` or `sys_eexist``NewPath` is an existing, non-empty directory.

`sys_ebusy``Old` or `NewPath` is a directory and is in use by another process.

`sys_einval``NewPath` is part of `Old`.

`sys_emlink``OldPath` or `NewPath` already have the maximum amount of links pointing to them.

`sys_enotdir`part of `Old` or `NewPath` is not directory.

`sys_efault`For the `pchar` case: One of the pointers points to an invalid address.

sys_eaccess access is denied when attempting to move the file.

sys_enametoolong Either Old or NewPath is too long.

sys_enoent a directory component in Old or NewPath didn't exist.

sys_enomem not enough kernel memory.

sys_erofs NewPath or Old is on a read-only file system.

sys_eloop too many symbolic links were encountered trying to expand Old or NewPath

sys_enospc the file system has no room for the new directory entry.

See also: [FpUnLink \(229\)](#)

1.4.61 FpRmdir

Synopsis: Remove a directory.

Declaration: `function FpRmdir(path: PChar) : cint`
`function FpRmdir(const path: RawByteString) : cint`

Visibility: default

Description: `FpRmdir` removes the directory `Path` from the system. The directory must be empty for this call to succeed, and the user must have the necessary permissions in the parent directory. Only the last component of the directory is removed, i.e. higher-lying directories are not removed.

On success, zero is returned. A nonzero return value indicates failure.

Note: There exist a portable alternative to `fpRmdir`: `system.rmdir`. Please use `fpRmdir` only if you are writing Unix specific code. `System.rmdir` will work on all operating systems.

Errors: Extended error information can be retrieved using [fpGetErrno \(193\)](#).

1.4.62 fpSelect

Synopsis: Wait for events on file descriptors

Declaration: `function FPSelect(N: cint; readfds: pFDSet; writefds: pFDSet;`
`exceptfds: pFDSet; TimeOut: ptimeval) : cint`
`function fpSelect(N: cint; readfds: pFDSet; writefds: pFDSet;`
`exceptfds: pFDSet; TimeOut: cint) : cint`
`function fpSelect(var T: Text; TimeOut: ptimeval) : cint`
`function fpSelect(var T: Text; TimeOut: time_t) : cint`

Visibility: default

Description: `FpSelect` checks one of the file descriptors in the `FDSet`s to see if the following I/O operation on the file descriptors will block.

`readfds`, `writefds` and `exceptfds` are pointers to arrays of 256 bits. If you want a file descriptor to be checked, you set the corresponding element in the array to 1. The other elements in the array must be set to zero. Three arrays are passed : The entries in `readfds` are checked to see if the following read operation will block. The entries in `writefds` are checked to see if the following write operation will block, while entries in `exceptfds` are checked to see if an exception occurred on them.

You can use the functions [fpFD_ZERO \(190\)](#), [fpFD_Clr \(189\)](#), [fpFD_Set \(189\)](#) or [fpFD_IsSet \(189\)](#) to manipulate the individual elements of a set.

The pointers can be `Nil`.

N is the value of the largest file descriptor in one of the sets, + 1. In other words, it is the position of the last bit which is set in the array of bits.

TimeOut can be used to set a time limit. If TimeOut can be two types :

1. TimeOut is of type `ptimeval` and contains a zero time, the call returns immediately. If TimeOut is `Nil`, the kernel will wait forever, or until a status changed.
2. TimeOut is of type `cint`. If it is -1, this has the same effect as a Timeout of type `PTime` which is `Nil`. Otherwise, TimeOut contains a time in milliseconds.

When the TimeOut is reached, or one of the file descriptors has changed, the `Select` call returns. On return, it will have modified the entries in the array which have actually changed, and it returns the number of entries that have been changed. If the timeout was reached, and no descriptor changed, zero is returned; The arrays of indexes are undefined after that. On error, -1 is returned.

The variant with the text file will execute the `FpSelect` call on the file descriptor associated with the text file `T`

Errors: On error, the function returns -1. Extended error information can be retrieved using `fpGetErrno` (193).

SYS_EBADF An invalid descriptor was specified in one of the sets.

SYS_EINTRA non blocked signal was caught.

SYS_EINVAL N is negative or too big.

SYS_ENOMEM `Select` was unable to allocate memory for its internal tables.

See also: `fpFD_ZERO` (190), `fpFD_Clr` (189), `fpFD_Set` (189), `fpFD_IsSet` (189)

Listing: `./examples/bunixex/ex33.pp`

Program Example33;

{ Program to demonstrate the Select function. }

Uses BaseUnix;

Var FDS : Tfdset;

begin

```

    fpfd_zero(FDS);
    fpfd_set(0,FDS);
    Writeln ('Press the <ENTER> to continue the program. ');
    { Wait until File descriptor 0 (=Input) changes }
    fpSelect (1,@FDS,nil ,nil ,nil );
    { Get rid of <ENTER> in buffer }
    readln;
    Writeln ('Press <ENTER> key in less than 2 seconds... ');
    Fpfd_zero(FDS);
    FpFd_set (0,FDS);
    if fpSelect (1,@FDS,nil ,nil ,2000)>0 then
        Writeln ('Thank you !')
        { FD_ISSET(0,FDS) would be true here. }
    else
        Writeln ('Too late !');

```

end.

1.4.63 fpseterrno

Synopsis: Set extended error information.

Declaration: `procedure fpseterrno(err: LongInt)`

Visibility: default

Description: `fpseterrno` sets the extended information on the latest error. It is called by all functions that communicate with the kernel or C library.

Unless a direct kernel call is performed, there should never be any need to call this function.

See also: `fpgeterrno` ([193](#))

1.4.64 FpSetgid

Synopsis: Set the current group ID

Declaration: `function FpSetgid(gid: TGid) : cint`

Visibility: default

Description: `fpSetUID` sets the group ID of the current process. This call will only work if it is executed as root, or the program is setgid root.

On success, zero is returned, on error -1 is returned.

Errors: Extended error information can be retrieved with `fpGetErrNo` ([193](#)).

See also: `FpSetUid` ([217](#)), `FpGetGid` ([194](#)), `FpGetUid` ([197](#)), `FpGetEUid` ([193](#)), `FpGetEGid` ([192](#)), `FpGetPid` ([195](#)), `FpGetPPid` ([195](#))

1.4.65 fpSetPriority

Synopsis: Set process priority

Declaration: `function fpSetPriority(Which: cint; Who: cint; What: cint) : cint`

Visibility: default

Description: `fpSetPriority` sets the priority with which a process is running. Which process(es) is determined by the `Which` and `Who` variables. Which can be one of the predefined constants:

Prio_Process`Who` is interpreted as process ID

Prio_PGrp`Who` is interpreted as process group ID

Prio_User`Who` is interpreted as user ID

`Prio` is a value in the range -20 to 20.

For an example, see `FpNice` ([205](#)).

The function returns zero on success, -1 on failure

Errors: Extended error information is returned by the `FpGetErrno` ([193](#)) function.

sys_esrchNo process found using `which` and `who`.

sys_einval`Which` was not one of `Prio_Process`, `Prio_Grp` or `Prio_User`.

sys_epermA process was found, but neither its effective or real user ID match the effective user ID of the caller.

sys_eaccessA non-superuser tried to a priority increase.

See also: `FpGetPriority` ([196](#)), `FpNice` ([205](#))

1.4.66 FpSetRLimit

Synopsis: Set process resource limits

Declaration: `function FpSetRLimit(Resource: cint; rlim: PRLimit) : cint`

Visibility: default

Description: `FpGetRLimit` sets the resource limits for the current process: `resource` determines the resource of which the kernel should set the limits (one of the many `RLIMIT_*` constants). `rlim` should point to a `TRLimit` (238) record which contains the new limits for the resource indicated in `resource`.

The function returns zero if the resource limits were successfully set.

Errors: On error, -1 is returned and `fpgeterrno` (193) can be used to retrieve the error code.

See also: `FpGetRLimit` (196)

1.4.67 FpSetsid

Synopsis: Create a new session.

Declaration: `function FpSetsid : TPid`

Visibility: default

Description: `FpSetsid` creates a new session (process group). It returns the new process group id (as returned by `FpGetgrp` (194)). This call will fail if the current process is already the process group leader.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` (193)

1.4.68 fpsettimeofday

Synopsis: Set kernel time

Declaration: `function fpsettimeofday(tp: ptimeval; tzp: ptimezone) : cint`

Visibility: default

Description: `FpSetTimeOfDay` sets the kernel time to the number of seconds since 00:00, January 1 1970, GMT specified in the `tp` record. This time NOT corrected any way, not taking into account time-zones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

See also: `#rtl.unix.FPGetTimeOfDay` (2114)

1.4.69 FpSetuid

Synopsis: Set the current user ID

Declaration: `function FpSetuid(uid: TUid) : cint`

Visibility: default

Description: `fpSetUID` sets the user ID of the current process. This call will only work if it is executed as root, or the program is `setuid` root.

On success, zero is returned, on error -1 is returned.

Errors: Extended error information can be retrieved with `fpGetErrNo` (193).

See also: `FpGetGid` (194), `FpGetUid` (197), `FpGetEUid` (193), `FpGetEGid` (192), `FpGetPid` (195), `FpGetPPid` (195), `FpSetGid` (216)

1.4.70 FPSigaction

Synopsis: Install signal handler

Declaration: `function FPSigaction(sig: cint; act: psigactionrec; oact: psigactionrec)
: cint`

Visibility: default

Description: `FPSigaction` changes the action to take upon receipt of a signal. `Act` and `Oact` are pointers to a `SigActionRec` (235) record. `Sig` specifies the signal, and can be any signal except **SIGKILL** or **SIGSTOP**.

If `Act` is non-nil, then the new action for signal `Sig` is taken from it. If `Oact` is non-nil, the old action is stored there. `Sa_Handler` may be `SIG_DFL` for the default action or `SIG_IGN` to ignore the signal. `Sa_Mask` Specifies which signals should be ignored during the execution of the signal handler. `Sa_Flags` Specifies a series of flags which modify the behaviour of the signal handler. You can 'or' none or more of the following :

SA_NOCLDSTOPIf `sig` is **SIGCHLD** do not receive notification when child processes stop.

SA_ONESHOT or **SA_RESETHAND**Restore the signal action to the default state once the signal handler has been called.

SA_RESTARTFor compatibility with BSD signals.

SA_NOMASK or **SA_NODEFER**Do not prevent the signal from being received from within its own signal handler.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

sys_einvalan invalid signal was specified, or it was **SIGKILL** or **SIGSTOP**.

sys_efault`Act`, `OldAct` point outside this process address space

sys_eintrSystem call was interrupted.

See also: `FpSigProcMask` (221), `FpSigPending` (221), `FpSigSuspend` (222), `FpKill` (198)

Listing: `./examples/bunixex/ex57.pp`

Program `example57;`

```
{ Program to demonstrate the SigAction function.}

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}
```

uses `BaseUnix;`

Var
 `oa, na : PSigActionRec;`

Procedure `DoSig(sig : cint); cdecl;`

```
begin
    writeln ('Receiving signal: ', sig);
end;
```

```

begin
  new(na);
  new(oa);
  na^.sa_Handler:=SigActionHandler(@DoSig);
  fillchar(na^.Sa_Mask, sizeof(na^.sa_mask), #0);
  na^.Sa_Flags:=0;
  {$ifdef Linux}           // Linux specific
    na^.Sa_Restorer:=Nil;
  {$endif}
  if fpSigAction(SigUsr1, na, oa) <> 0 then
    begin
      writeln('Error: ', fpgeterrno, '.');
      halt(1);
    end;
  Writeln('Send USR1 signal or press <ENTER> to exit');
  readln;
end.

```

1.4.71 FpSigAddSet

Synopsis: Set a signal in a signal set.

Declaration: `function FpSigAddSet(var nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigAddSet` adds signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (219), `FpSigFillSet` (220), `FpSigDelSet` (219), `FpSigIsMember` (220)

1.4.72 FpSigDelSet

Synopsis: Remove a signal from a signal set.

Declaration: `function FpSigDelSet(var nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigDelSet` removes signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (219), `FpSigFillSet` (220), `FpSigAddSet` (219), `FpSigIsMember` (220)

1.4.73 FpsigEmptySet

Synopsis: Clear all signals from signal set.

Declaration: `function FpsigEmptySet(var nset: tsigset) : cint`

Visibility: default

Description: `FpSigEmptySet` clears all signals from the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigFillSet` (220), `FpSigAddSet` (219), `FpSigDelSet` (219), `FpSigIsMember` (220)

1.4.74 FpSigFillSet

Synopsis: Set all signals in signal set.

Declaration: `function FpSigFillSet (var nset: tsigset) : cint`

Visibility: default

Description: `FpSigFillSet` sets all signals in the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigEmptySet` (219), `FpSigAddSet` (219), `FpSigDelSet` (219), `FpSigIsMember` (220)

1.4.75 FpSigIsMember

Synopsis: Check whether a signal appears in a signal set.

Declaration: `function FpSigIsMember (const nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigIsMember` checks whether `SigNo` appears in the set `nset`. If it is a member, then 1 is returned. If not, zero is returned.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (219), `FpSigFillSet` (220), `FpSigAddSet` (219), `FpSigDelSet` (219)

1.4.76 FpSignal

Synopsis: Install signal handler (deprecated)

Declaration: `function FpSignal (signum: LongInt; Handler: signalhandler)
: signalhandler`

Visibility: default

Description: `FpSignal` installs a new signal handler (specified by `Handler`) for signal `SigNum`.

This call has a subset of the functionality provided by the `FpSigAction` (218) call. The return value for `FpSignal` is the old signal handler, or nil on error.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

SIG_ERR An error occurred.

See also: `FpSigAction` (218), `FpKill` (198)

Listing: `./examples/bunixex/ex58.pp`

Program `example58;`

```
{ Program to demonstrate the Signal function. }  
  
{  
do a kill -USR1 pid from another terminal to see what happens.  
replace pid with the real pid of this program.  
You can get this pid by running 'ps'.  
}
```

```

uses BaseUnix;

Procedure DoSig(sig : cint);cdecl;

begin
    writeln('Receiving signal: ',sig);
end;

begin
    if fpSignal(SigUsrc1,SignalHandler(@DoSig))=signalhandler(SIG_ERR) then
        begin
            writeln('Error: ',fpGetErrno, '. ');
            halt(1);
        end;
    Writeln ('Send USR1 signal or press <ENTER> to exit');
    readln;
end.

```

1.4.77 FpSigPending

Synopsis: Return set of currently pending signals

Declaration: `function FpSigPending(var nset: tsigset) : cint`

Visibility: default

Description: `fpSigpending` allows the examination of pending signals (which have been raised while blocked.)
The signal mask of pending signals is returned.

Errors: None

See also: `fpSigAction` (218), `fpSigProcMask` (221), `fpSigSuspend` (222), `fpSignal` (220), `fpKill` (198)

1.4.78 FpSigProcMask

Synopsis: Set list of blocked signals

Declaration: `function FpSigProcMask(how: cint; nset: psigset; oset: psigset) : cint`
`function FpSigProcMask(how: cint; constref nset: tsigset;`
`var oset: tsigset) : cint`

Visibility: default

Description: Changes the list of currently blocked signals. The behaviour of the call depends on `How` :

SIG_BLOCKThe set of blocked signals is the union of the current set and the `nset` argument.

SIG_UNBLOCKThe signals in `nset` are removed from the set of currently blocked signals.

SIG_SETMASKThe list of blocked signals is set so `nset`.

If `oset` is non-nil, then the old set is stored in it.

Errors: `Errno` is used to report errors.

sys_efault`oset` or `nset` point to an address outside the range of the process.

sys_eintrSystem call was interrupted.

See also: `fpSigAction` (218), `fpSigPending` (221), `fpSigSuspend` (222), `fpKill` (198)

1.4.79 FpSigSuspend

Synopsis: Set signal mask and suspend process till signal is received

Declaration: `function FpSigSuspend(const sigmask: tsigset) : cint`

Visibility: default

Description: `FpSigSuspend` temporarily replaces the signal mask for the process with the one given in `SigMask`, and then suspends the process until a signal is received.

Errors: None

See also: `FpSigAction` (218), `FpSigProcMask` (221), `FpSigPending` (221), `FpSignal` (220), `FpKill` (198)

1.4.80 FpSigTimedWait

Synopsis: Wait for signal, with timeout

Declaration: `function FpSigTimedWait(const sigset: tsigset; info: psigninfo; timeout: ptimespec) : cint`

Visibility: default

Description: `FpSigTimedWait` will suspend the current thread and wait for one of the signals in `sigset` to be delivered. information on the delivered signal is placed in the location provided by `info` (or in `info` itself, if the `Var` variant of the call is used). If the signal is not delivered within the time limit set in `timeout`, then the call will return -1, and `FpGetErrno` will return `EAGAIN`.

On success, the signal number is returned.

Errors: On error, -1 is returned, and extended error information can be obtained with `FpGetErrno`.

See also: `FpSigSuspend` (222)

1.4.81 FpSleep

Synopsis: Suspend process for several seconds

Declaration: `function FpSleep(seconds: cuint) : cuint`

Visibility: default

Description: `FpSleep` suspends the process till a time period as specified in `seconds` has passed, then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and the return value is the remaining time till the end of the intended period.

If the function returns without error, the return value is zero.

See also: `FpPause` (208), `FpAlarm` (180), `FpNanoSleep` (204)

Listing: `./examples/bunixex/ex73.pp`

program `example73;`

`{ Program to demonstrate the FpSleep function. }`

uses `BaseUnix;`

Var

```

    Res : Longint;

begin
    Write('Sleep returned : ');
    Flush(Output);
    Res:=(fpSleep(10));
    Writeln(res);
    If (res<>0) then
        Writeln('Remaining seconds      : ',res);
end.

```

1.4.82 FpStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpStat(path: PChar; var buf: Stat) : cint`
`function FpStat(const path: RawByteString; var buf: Stat) : cint`
`function FpStat(path: ShortString; var buf: Stat) : cint`

Visibility: default

Description: `FpFStat` gets information about the file specified in `Path`, and stores it in `Info`, which is of type `stat` (235). The function returns zero if the call was successful, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

`sys_enoent``Path` does not exist.

See also: `FpStat` (223), `FpLStat` (200)

Listing: `./examples/bunixex/ex28.pp`

```

program example28;

{ Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
    { Make a file }
    assign (f, 'test.fil');
    rewrite (f);
    for i:=1 to 10 do writeln (f, 'Testline # ', i);
    close (f);
    { Do the call on made file. }
    if fpstat ('test.fil', info) <> 0 then
        begin
            writeln('Fstat failed. Errno : ', fpgeterrno);
            halt (1);
        end;
    writeln;
    writeln ('Result of fstat on file ''test.fil''.');

```

```

writeln ( 'Inode   : ', info.st_ino );
writeln ( 'Mode    : ', info.st_mode );
writeln ( 'nlink   : ', info.st_nlink );
writeln ( 'uid     : ', info.st_uid );
writeln ( 'gid     : ', info.st_gid );
writeln ( 'rdev    : ', info.st_rdev );
writeln ( 'Size    : ', info.st_size );
writeln ( 'Blksize  : ', info.st_blksize );
writeln ( 'Blocks   : ', info.st_blocks );
writeln ( 'atime    : ', info.st_atime );
writeln ( 'mtime    : ', info.st_mtime );
writeln ( 'ctime    : ', info.st_ctime );
  { Remove file }
  erase ( f );
end .

```

1.4.83 fpSymlink

Synopsis: Create a symbolic link

Declaration: `function fpSymlink(oldname: PChar; newname: PChar) : cint`

Visibility: default

Description: `SymLink` makes `NewName` point to the file in `OldName`, which doesn't necessarily exist. The two files DO NOT have the same inode number. This is known as a 'soft' link.

The permissions of the link are irrelevant, as they are not used when following the link. Ownership of the file is only checked in case of removal or renaming of the link.

The function returns zero if the call was successful, a nonzero value if the call failed.

Errors: Extended error information is returned by the `FpGetErrno` (193) function.

sys_epermThe file system containing `oldpath` and `newpath` does not support linking files.

sys_eaccessWrite access for the directory containing `Newpath` is disallowed, or one of the directories in `OldPath` or `NewPath` has no search (=execute) permission.

sys_enoentA directory entry in `OldPath` or `NewPath` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdirA directory entry in `OldPath` or `NewPath` is not a directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe files are on a read-only file system.

sys_eexist`NewPath` already exists.

sys_eloop`OldPath` or `NewPath` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

sys_enospcThe device containing `NewPath` has no room for another entry.

See also: `FpLink` (198), `FpUnLink` (229), `FpReadLink` (211)

Listing: `./examples/unixex/ex22.pp`

Program Example22;

{ Program to demonstrate the SymLink and UnLink functions. }

Uses baseunix, Unix;

Var F : Text;
 S : **String**;

```
begin
  Assign (F, 'test.txt');
  Rewrite (F);
  Writeln (F, 'This is written to test.txt');
  Close(f);
  { new.txt and test.txt are now the same file }
  if fpSymLink ('test.txt', 'new.txt') <> 0 then
    writeln ('Error when symlinking !');
  { Removing test.txt still leaves new.txt
    Pointing now to a non-existent file ! }
  If fpUnlink ('test.txt') <> 0 then
    Writeln ('Error when unlinking !');
  Assign (f, 'new.txt');
  { This should fail, since the symbolic link
    points to a non-existent file ! }
  {$i-}
  Reset (F);
  {$i+}
  If IOResult=0 then
    Writeln ('This shouldn''t happen');
  { Now remove new.txt also }
  If fpUnlink ('new.txt') <> 0 then
    Writeln ('Error when unlinking !');
end.
```

1.4.84 fpS_ISBLK

Synopsis: Is file a block device

Declaration: function fpS_ISBLK(m: TMode) : Boolean

Visibility: default

Description: FpS_ISBLK checks the file mode m to see whether the file is a block device file. If so it returns True.

See also: FpFStat ([190](#)), FpS_ISLNK ([226](#)), FpS_ISREG ([227](#)), FpS_ISDIR ([226](#)), FpS_ISCHR ([225](#)), FpS_ISFIFO ([226](#)), FpS_ISSOCK ([227](#))

1.4.85 fpS_ISCHR

Synopsis: Is file a character device

Declaration: function fpS_ISCHR(m: TMode) : Boolean

Visibility: default

Description: FpS_ISCHR checks the file mode m to see whether the file is a character device file. If so it returns True.

See also: FpFStat ([190](#)), FpS_ISLNK ([226](#)), FpS_ISREG ([227](#)), FpS_ISDIR ([226](#)), FpS_ISBLK ([225](#)), FpS_ISFIFO ([226](#)), FpS_ISSOCK ([227](#))

1.4.86 fpS_ISDIR

Synopsis: Is file a directory

Declaration: `function fpS_ISDIR(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISDIR` checks the file mode `m` to see whether the file is a directory. If so, it returns `True`

See also: `FpFStat` (190), `FpS_ISLNK` (226), `FpS_ISREG` (227), `FpS_ISCHR` (225), `FpS_ISBLK` (225), `fpS_ISFIFO` (226), `FpS_ISSOCK` (227)

1.4.87 fpS_ISFIFO

Synopsis: Is file a FIFO

Declaration: `function fpS_ISFIFO(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISFIFO` checks the file mode `m` to see whether the file is a fifo (a named pipe). If so it returns `True`.

See also: `FpFStat` (190), `FpS_ISLNK` (226), `FpS_ISREG` (227), `FpS_ISCHR` (225), `FpS_ISBLK` (225), `FpS_ISDIR` (226), `FpS_ISSOCK` (227)

1.4.88 fpS_ISLNK

Synopsis: Is file a symbolic link

Declaration: `function fpS_ISLNK(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISLNK` checks the file mode `m` to see whether the file is a symbolic link. If so it returns `True`

See also: `FpFStat` (190), `FpS_ISFIFO` (226), `FpS_ISREG` (227), `FpS_ISCHR` (225), `FpS_ISBLK` (225), `FpS_ISDIR` (226), `FpS_ISSOCK` (227)

Listing: `./examples/bunixex/ex53.pp`

Program `Example53;`

{ Program to demonstrate the S_ISLNK function. }

Uses `BaseUnix, Unix;`

Var `Info : Stat;`

begin

if `fpLStat (paramstr(1), @info)=0` **then**

begin

if `fpS_ISLNK(info.st_mode)` **then**

WriteLn ('File is a link');

if `fpS_ISREG(info.st_mode)` **then**

WriteLn ('File is a regular file');

if `fpS_ISDIR(info.st_mode)` **then**

WriteLn ('File is a directory');

```

    if fpS_ISCHR(info.st_mode) then
        Writeln ('File is a character device file ');
    if fpS_ISBLK(info.st_mode) then
        Writeln ('File is a block device file ');
    if fpS_ISFIFO(info.st_mode) then
        Writeln ('File is a named pipe (FIFO) ');
    if fpS_ISSOCK(info.st_mode) then
        Writeln ('File is a socket ');
    end;
end.

```

1.4.89 fpS_ISREG

Synopsis: Is file a regular file

Declaration: `function fpS_ISREG(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISREG` checks the file mode `m` to see whether the file is a regular file. If so it returns `True`

See also: `FpFStat` ([190](#)), `FpS_ISFIFO` ([226](#)), `FpS_ISLNK` ([226](#)), `FpS_ISCHR` ([225](#)), `FpS_ISBLK` ([225](#)), `FpS_ISDIR` ([226](#)), `FpS_ISSOCK` ([227](#))

1.4.90 fpS_ISSOCK

Synopsis: Is file a Unix socket

Declaration: `function fpS_ISSOCK(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISSOCK` checks the file mode `m` to see whether the file is a socket. If so it returns `True`.

See also: `FpFStat` ([190](#)), `FpS_ISFIFO` ([226](#)), `FpS_ISLNK` ([226](#)), `FpS_ISCHR` ([225](#)), `FpS_ISBLK` ([225](#)), `FpS_ISDIR` ([226](#)), `fpS_ISREG` ([227](#))

1.4.91 fptime

Synopsis: Return the current Unix time

Declaration: `function FpTime(var tloc: TTime) : TTime`
`function fptime : time_t`

Visibility: default

Description: `FpTime` returns the number of seconds since 00:00:00 GMT, january 1, 1970. it is adjusted to the local time zone, but not to DST. The result is also stored in `tloc`, if it is specified.

Errors: On error, -1 is returned. Extended error information can be retrieved using `fpGetErrno` ([193](#)).

Listing: `./examples/bunixex/ex1.pp`

```

Program Example1;

{ Program to demonstrate the fptime function. }

Uses baseunix;

begin
  Write ( 'Secs past the start of the Epoch (00:00 1/1/1980) : ');
  Writeln ( fptime );
end.

```

1.4.92 FpTimes

Synopsis: Return execution times for the current process

Declaration: `function FpTimes(var buffer: tms) : TClock`

Visibility: default

Description: `fpTimes` stores the execution time of the current process and child processes in `buffer`.

The return value (on Linux) is the number of clock ticks since boot time. On error, -1 is returned, and extended error information can be retrieved with `fpGetErrno` ([193](#)).

See also: `fpUtime` ([229](#))

1.4.93 FpUmask

Synopsis: Set file creation mask.

Declaration: `function FpUmask(cmask: TMode) : TMode`

Visibility: default

Description: `fpUmask` changes the file creation mask for the current user to `cmask`. The current mask is returned.

See also: `fpChmod` ([181](#))

Listing: `./examples/bunixex/ex27.pp`

```

Program Example27;

{ Program to demonstrate the Umask function. }

Uses BaseUnix;

begin
  Writeln ( 'Old Umask was : ', fpUmask(&111));
  Writeln ( 'New Umask is : ', &111);
end.

```

1.4.94 FpUname

Synopsis: Return system name.

Declaration: `function FpUname(var name: UtsName) : cint`

Visibility: default

Description: `Uname` gets the name and configuration of the current Linux kernel, and returns it in the `name` record.

On success, 0 is returned, on error, -1 is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

See also: `FpUTime` (229)

1.4.95 FpUnlink

Synopsis: Unlink (i.e. remove) a file.

Declaration: `function FpUnlink(path: PChar) : cint`
`function FpUnlink(const path: RawByteString) : cint`

Visibility: default

Description: `FpUnlink` decreases the link count on file `Path`. `Path` can be of type `AnsiString` or `PChar`. If the link count is zero, the file is removed from the disk.

The function returns zero if the call was successful, a nonzero value indicates failure.

Note: There exist a portable alternative to erase files: `system.erase`. Please use `fpUnlink` only if you are writing Unix specific code. `System.erase` will work on all operating systems.

For an example, see `FpLink` (198).

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

sys_eaccess You have no write access right in the directory containing `Path`, or you have no search permission in one of the directory components of `Path`.

sys_eperm The directory containing pathname has the sticky-bit set and the process's effective uid is neither the uid of the file to be deleted nor that of the directory containing it.

sys_enoent A component of the path doesn't exist.

sys_enotdir A directory component of the path is not a directory.

sys_eisdir `Path` refers to a directory.

sys_enomem Insufficient kernel memory.

sys_erofs `Path` is on a read-only file system.

See also: `FpLink` (198), `FpSymLink` (224)

1.4.96 FpUtime

Synopsis: Set access and modification times of a file (touch).

Declaration: `function FpUtime(path: PChar; times: pUtimBuf) : cint`
`function FpUtime(const path: RawByteString; times: pUtimBuf) : cint`

Visibility: default

Description: `FpUtime` sets the access and modification times of the file specified in `Path`. the `times` record contains 2 fields, `actime`, and `modtime`, both of type `time_t` (commonly a `longint`). They should be filled with an epoch-like time, specifying, respectively, the last access time, and the last modification time. For some file systems (most notably, FAT), these times are the same.

The function returns zero on success, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

sys_eaccess One of the directories in `Path` has no search (=execute) permission.

sys_enoent A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

Other errors may occur, but aren't documented.

See also: `FpTime` (227), `FpChown` (182), `FpAccess` (179)

Listing: `./examples/bunixex/ex25.pp`

Program `Example25`;

{ Program to demonstrate the UTime function. }

Uses `Dos, BaseUnix, Unix, UnixUtil`;

Var `utim : utimbuf`;
 `dow, msec, year, month, day, hour, minute, second : Word`;

```
begin
  { Set access and modification time of executable source }
  GetTime (hour, minute, second, msec);
  GetDate (year, month, day, dow);
  utim.actime := LocalToEpoch (year, month, day, hour, minute, second);
  utim.modtime := utim.actime;
  if Fputime ('ex25.pp', @utim) <> 0 then
    writeln ('Call to UTime failed !')
  else
    begin
      Write ('Set access and modification times to : ');
      Write (Hour:2, ':', minute:2, ':', second, ', ');
      Writeln (Day:2, '/', month:2, '/', year:4);
    end;
  end.
end.
```

1.4.97 FpWait

Synopsis: Wait for a child to exit.

Declaration: `function FpWait (var stat_loc: cint) : TPid`

Visibility: `default`

Description: `fpWait` suspends the current process and waits for any child to exit or stop due to a signal. It reports the exit status of the exited child in `stat_loc`.

The return value of the function is the process ID of the child that exited, or -1 on error.

Errors: Extended error information can be retrieved using `fpgetErrno` (193).

See also: `fpFork` (190), `fpExecve` (187), `fpWaitPid` (231)

1.4.98 FpWaitPid

Synopsis: Wait for a process to terminate

Declaration: `function FpWaitpid(pid: TPid; stat_loc: pcint; options: cint) : TPid`
`function FpWaitPid(pid: TPid; var Status: cint; Options: cint) : TPid`

Visibility: default

Description: `fpWaitPid` waits for a child process with process ID `Pid` to exit. The value of `Pid` can be one of the following:

Pid < -1 Causes `fpWaitPid` to wait for any child process whose process group ID equals the absolute value of `pid`.

Pid = -1 Causes `fpWaitPid` to wait for any child process.

Pid = 0 Causes `fpWaitPid` to wait for any child process whose process group ID equals the one of the calling process.

Pid > 0 Causes `fpWaitPid` to wait for the child whose process ID equals the value of `Pid`.

The `Options` parameter can be used to specify further how `fpWaitPid` behaves:

WNOHANG Causes `fpWaitpid` to return immediately if no child has exited.

WUNTRACED Causes `fpWaitPid` to return also for children which are stopped, but whose status has not yet been reported.

__WCLONE Causes `fpWaitPid` also to wait for threads created by the `#rtl.linux.Clone` (975) call.

The exit status of the process that caused `fpWaitPID` is reported in `stat_loc` or `Status`.

Upon return, it returns the process id of the process that exited, 0 if no process exited, or -1 in case of failure.

For an example, see `fpFork` (190).

Errors: Extended error information can be retrieved using `fpgetErrno` (193).

See also: `fpFork` (190), `fpExecve` (187), `fpWait` (230)

1.4.99 FpWrite

Synopsis: Write data to file descriptor

Declaration: `function FpWrite(fd: cint; buf: PChar; nbytes: TSize) : TSize`
`function FpWrite(fd: cint; const buf; nbytes: TSize) : TSize`

Visibility: default

Description: `FpWrite` writes at most `nbytes` bytes from `buf` to file descriptor `fd`.

The function returns the number of bytes actually written, or -1 if an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` (193).

See also: `FpOpen` (206), `FpClose` (183), `FpRead` (210), `FpFTruncate` (191), `FpLSeek` (199)

1.4.100 FpWriteV

Synopsis: Vector write: Write from multiple buffers to a file descriptor

Declaration: `function FpWriteV(fd: cint; const iov: piovec; iovcnt: cint) : TsSize`

Visibility: default

Description: `FpWriteV` writes data to file descriptor `fd`. The data is taken from `iovcnt` buffers described by the `tiovec` (177) buffers pointed to by `iov`. It works like `fpWrite` (231) only from multiple buffers.

Errors: On error, -1 is returned.

See also: `FpReadV` (213), `FpPWrite` (210), `FpPRead` (209)

1.4.101 FreeShellArgV

Synopsis: Free the result of a `CreateShellArgV` (179) function

Declaration: `procedure FreeShellArgV(p: PPChar)`

Visibility: default

Description: `FreeShellArgV` frees the memory pointed to by `P`, which was allocated by a call to `CreateShellArgV` (179).

Errors: None.

See also: `CreateShellArgV` (179)

1.4.102 wexitStatus

Synopsis: Extract the exit status from the `fpWaitPID` (231) result.

Declaration: `function wexitStatus(Status: cint) : cint`

Visibility: default

Description: `WEXITSTATUS` can be used to extract the exit status from `Status`, the result of the `FpWaitPID` (231) call.

See also: `FpWaitPID` (231), `WTERMSIG` (233), `WSTOPSIG` (233), `WIFEXITED` (232), `WIFSIGNALED` (233)

1.4.103 wifexited

Synopsis: Check whether the process exited normally

Declaration: `function wifexited(Status: cint) : Boolean`

Visibility: default

Description: `WIFEXITED` checks `Status` and returns `True` if the status indicates that the process terminated normally, i.e. was not stopped by a signal.

See also: `FpWaitPID` (231), `WTERMSIG` (233), `WSTOPSIG` (233), `WIFSIGNALED` (233), `WEXITSTATUS` (232)

1.4.104 wifsignaled

Synopsis: Check whether the process was exited by a signal.

Declaration: `function wifsignaled(Status: cint) : Boolean`

Visibility: default

Description: `WIFSIGNALED` returns `True` if `Status` indicates that the process exited because it received a signal.

See also: `FpWaitPID` (231), `WTERMSIG` (233), `WSTOPSIG` (233), `WIFEXITED` (232), `WEXITSTATUS` (232)

1.4.105 wstopsig

Synopsis: Return the exit code from the process.

Declaration: `function wstopsig(Status: cint) : cint`

Visibility: default

Description: `WSTOPSIG` is an alias for `WEXITSTATUS` (232).

See also: `FpWaitPID` (231), `WTERMSIG` (233), `WIFEXITED` (232), `WIFSIGNALED` (233), `WEXITSTATUS` (232)

1.4.106 wtermSIG

Synopsis: Return the signal that caused a process to exit.

Declaration: `function wtermSIG(Status: cint) : cint`

Visibility: default

Description: `WTERMSIG` extracts from `Status` the signal number which caused the process to exit.

See also: `FpWaitPID` (231), `WSTOPSIG` (233), `WIFEXITED` (232), `WIFSIGNALED` (233), `WEXITSTATUS` (232)

1.5 Dir

```

Dir = record
  dd_fd : LongInt;
  dd_loc : LongInt;
  dd_size : LongInt
  ;
  dd_buf : pDirent;
  dd_nextoff : Cardinal;
  dd_max : Integer
  ;
  dd_lock : pointer;
end

```

Record used in `fpOpenDir` (207) and `fpReadDir` (211) calls

1.6 Dirent

```
Dirent = record
  d_fileno : ino64_t;
  d_off : off_t;
  d_reclen
    : cushort;
  d_type : cuchar;
  d_name : Array[0..4095-sizeof(ino64_t
    )-sizeof(off_t)-sizeof(cushort)-sizeof(cuchar)] of Char;
end
```

Record used in the `fpReadDir` ([211](#)) function to return files in a directory.

1.7 FLock

```
FLock = record
  l_type : cshort;
  l_whence : cshort;
  l_start
    : kernel_off_t;
  l_len : kernel_off_t;
  l_pid : pid_t;
end
```

Lock description type for `fpFCntl` ([188](#)) lock call.

1.8 iovec

```
iovec = record
  iov_base : pointer;
  iov_len : size_t;
end
```

`iovec` is used in `freadv` ([213](#)) for IO to multiple buffers to describe a buffer location.

1.9 pollfd

```
pollfd = record
  fd : cint;
  events : cshort;
  revents : cshort
;
end
```

`pollfd` is used in the `fpPoll` ([209](#)) call to describe the various actions.

1.10 sigactionrec

```
sigactionrec = record
  sa_handler : sigactionhandler_t;
  sa_flags
    : culong;
  sa_restorer : sigrestorerhandler_t;
  sa_mask : sigset_t
;
end
```

Record used in `fpSigAction` (218) call.

1.11 Stat

```
Stat = packed record
  st_dev : QWord;
  __pad0_ : Array[0..3] of
    Byte;
  __st_ino_ : Cardinal;
  st_mode : Cardinal;
  st_nlink :
    Cardinal;
  st_uid : Cardinal;
  st_gid : Cardinal;
  st_rdev : QWord
;
  __pad3_ : Array[0..3] of Byte;
  st_size : QWord;
  st_blksize
    : Cardinal;
  st_blocks : QWord;
  st_atime : Cardinal;
  st_atime_nsec
    : Cardinal;
  st_mtime : Cardinal;
  st_mtime_nsec : Cardinal;
  st_ctime : Cardinal;
  st_ctime_nsec : Cardinal;
  st_ino : QWord
;
end
```

Record describing an inode (file) in the `FPFstat` (190) call.

1.12 tfpreg

```
tfpreg = record
  significand : Array[0..3] of Word;
  exponent :
    Word;
```

end

Record describing floating point register in signal handler.

1.13 tfpstate

```
tfpstate = record
  cw : Cardinal;
  sw : Cardinal;
  tag : Cardinal
;
  ipoff : Cardinal;
  cssel : Cardinal;
  dataoff : Cardinal;
  datasel : Cardinal;
  st : Array[0..7] of tfpreg;
  status : Word
;
  magic : Word;
  fxsr_env : Array[0..5] of DWord;
  mxcsr : DWord
;
  reserved : DWord;
  fxsr_st : Array[0..7] of tfpxreg;
  xmmreg
    : Array[0..7] of txmmreg;
case Byte of
1: (
  padding : Array[0..
    .43] of DWord;
case Byte of
1: (
  padding2 : Array[0..11] of DWord
  ;
);
2: (
  sw_reserved : tfpx_sw_bytes;
);
2: (
  padding1 : Array
    [0..43] of DWord;
);
end
```

Record describing floating point unit in signal handler.

1.14 tfpxreg

```
tfpxreg = record
  significand : Array[0..3] of Word;
```

```

    exponent
    : Word;
    padding : Array[0..2] of Word;
end

```

Record describing 16-byte floating point register in signal handler.

1.15 tfpx_sw_bytes

```

tfpx_sw_bytes = record
    magic1 : DWord;
    extended_size : DWord;
    xfeatures : QWord;
    xstate_size : DWord;
    padding : Array[0..
        .6] of DWord;
end

```

Extended state information in signal handler

1.16 timezone

```

timezone = record
    tz_minuteswest : cint;
    tz_dsttime : cint;
end

```

Record describing a timezone

1.17 tms

```

tms = record
    tms_utime : clock_t;
    tms_stime : clock_t;
    tms_cutime
    : clock_t;
    tms_cstime : clock_t;
end

```

Record containing timings for fpTimes (228) call.

1.18 TRLimit

```

TRLimit = record
    rlim_cur : rlim_t;
    rlim_max : rlim_t;
end

```

TRLimit is the structure used by the kernel to return resource limit information in.

1.19 tsigaltstack

```
tsigaltstack = record
  ss_sp : pointer;
  ss_flags : LongInt;
  ss_size
    : LongInt;
end
```

Provide the location of an alternate signal handler stack.

1.20 TSigContext

```
TSigContext = record
  gs : Word;
  __gsh : Word;
  fs : Word;
  __fsh
    : Word;
  es : Word;
  __esh : Word;
  ds : Word;
  __dsh : Word
  ;
  edi : Cardinal;
  esi : Cardinal;
  ebp : Cardinal;
  esp : Cardinal
  ;
  ebx : Cardinal;
  edx : Cardinal;
  ecx : Cardinal;
  eax : Cardinal
  ;
  trapno : Cardinal;
  err : Cardinal;
  eip : Cardinal;
  cs :
    Word;
  __csh : Word;
  eflags : Cardinal;
  esp_at_signal : Cardinal
  ;
  ss : Word;
  __ssh : Word;
  fpstate : pfpstate;
  oldmask : Cardinal
  ;
  cr2 : Cardinal;
```

end

This type is CPU dependent. Cross-platform code should not use the contents of this record.

1.21 tsiginfo

```
tsiginfo = record
  si_signo : LongInt;
  si_errno : LongInt;
  si_code
  : LongInt;
  _sifields : record
  case LongInt of
    0: (
      _pad
      : Array[0..(SI_PAD_SIZE)-1] of LongInt;
    );
    1: (
      _kill : record
      _pid : pid_t;
      _uid : uid_t;
      end;
    );
    2: (
      _timer : record
      _timer1 : DWord;
      _timer2 : DWord;
      end;
    );
    3: (
      _rt : record
      _pid : pid_t;
      _uid
      : uid_t;
      _sigval : pointer;
      end;
    );
    4: (
      _sigchld
      : record
      _pid : pid_t;
      _uid : uid_t;
      _status :
      LongInt;
      _utime : clock_t;
      _stime : clock_t;
      end;
    );
    5: (
      _sigfault : record
      _addr : pointer;
```



```

        end
    ;
);
6: (
    _sigpoll : record
        _band : LongInt;
        _fd
    : LongInt;
    end;
);
end;
end

```

This type describes the signal that occurred.

1.22 TUcontext

```

TUcontext = record
    uc_flags : Cardinal;
    uc_link : Pucontext;
    uc_stack : tsigaltstack;
    uc_mcontext : TSigContext;
    uc_sigmask
    : tsigset;
end

```

This structure is used to describe the user context in a program or thread. It is not used in this unit, but is provided for completeness.

1.23 txmmreg

```

txmmreg = record
    element : Array[0..3] of DWord;
end

```

Record describing 16-byte MMX register in signal handler.

1.24 UTimBuf

```

UTimBuf = record
    actime : time_t;
    modtime : time_t;
end

```

Record used in `fpUtime` ([229](#)) to set file access and modification times.

1.25 UtsName

```
UtsName = record
  Sysname : Array[0..UTSNAME_LENGTH-1] of Char;
  Nodename : Array[0..UTSNAME_NODENAME_LENGTH-1] of Char;
  Release
    : Array[0..UTSNAME_LENGTH-1] of Char;
  Version : Array[0..UTSNAME_LENGTH
    -1] of Char;
  Machine : Array[0..UTSNAME_LENGTH-1] of Char;
  Domain
    : Array[0..UTSNAME_DOMAIN_LENGTH-1] of Charplatform;
end
```

The elements of this record are null-terminated C style strings, you cannot access them directly. Note that the `Domain` field is a GNU extension, and may not be available on all platforms.

Chapter 2

Reference for unit 'Character'

2.1 Used units

Table 2.1: Used units by unit 'Character'

Name	Page
System	1339
unicodedata	2052

2.2 Overview

The character unit contains the TCharacter ([250](#)) class, which consists mainly of class functions. It should not be constructed, but its class methods can be used. All class methods also exist as regular methods.

Many routines depend on Unicode collation data to be present in the binary (or distributed on disc with the application. This data can be loaded using the routines in the unicodedata ([2052](#)) unit.. The FPC project distributes some Unicode collation data in .bco files which can be loaded using the LoadCollation ([2063](#)) routine from that unit.

2.3 Constants, types and variables

2.3.1 Types

TCharacterOption = (coIgnoreInvalidSequence)

Table 2.2: Enumeration values for type TCharacterOption

Value	Explanation
coIgnoreInvalidSequence	Ignore invalid unicodecode sequences

TCharacterOption is used in the toUpper ([250](#)) and toLower ([249](#)) functions to control the behaviour of the function.

TCharacterOptions = Set of TCharacterOption

TCharacterOptions is the set of TCharacterOption, used in toUpper (250) and toLower (249) functions to control the behaviour of the function.

```
TUnicodeCategory = (ucUppercaseLetter, ucLowercaseLetter,  
    ucTitlecaseLetter, ucModifierLetter, ucOtherLetter,  
    ucNonSpacingMark, ucCombiningMark, ucEnclosingMark  
,  
    ucDecimalNumber, ucLetterNumber, ucOtherNumber  
,  
    ucConnectPunctuation, ucDashPunctuation,  
    ucOpenPunctuation, ucClosePunctuation,  
    ucInitialPunctuation, ucFinalPunctuation,  
    ucOtherPunctuation, ucMathSymbol, ucCurrencySymbol,  
    ucModifierSymbol, ucOtherSymbol, ucSpaceSeparator,  
    ucLineSeparator, ucParagraphSeparator, ucControl,  
    ucFormat, ucSurrogate, ucPrivateUse, ucUnassigned)
```

Table 2.3: Enumeration values for type TUnicodeCategory

Value	Explanation
ucClosePunctuation	Punctuation, close (Pe)
ucCombiningMark	Mark, spacing combining (Mc)
ucConnectPunctuation	Punctuation, connector (Pc)
ucControl	Other, control (Cc)
ucCurrencySymbol	Symbol, currency (Sc)
ucDashPunctuation	Punctuation, dash (Pd)
ucDecimalNumber	Number, decimal digit (Nd)
ucEnclosingMark	Mark, enclosing (Me)
ucFinalPunctuation	Punctuation, final quote (Pf, may behave like Ps or Pe depending on usage)
ucFormat	Other, format (Cf)
ucInitialPunctuation	Punctuation, initial quote (Pi, may behave like Ps or Pe depending on usage)
ucLetterNumber	Number, letter (Nl)
ucLineSeparator	Separator, line (Zl)
ucLowercaseLetter	Letter, lowercase (Ll)
ucMathSymbol	Symbol, math (Sm)
ucModifierLetter	Letter, modifier (Lm)
ucModifierSymbol	Symbol, modifier (Sk)
ucNonSpacingMark	Mark, nonspacing (Mn)
ucOpenPunctuation	Punctuation, open (Ps)
ucOtherLetter	Letter, other (Lo)
ucOtherNumber	Number, other (No)
ucOtherPunctuation	Punctuation, other (Po)
ucOtherSymbol	Symbol, other (So)
ucParagraphSeparator	Separator, paragraph (Zp)
ucPrivateUse	Other, private use (Co)
ucSpaceSeparator	Separator, space (Zs)
ucSurrogate	Other, surrogate (Cs)
ucTitlecaseLetter	Letter, titlecase (Lt)
ucUnassigned	Other, not assigned (including noncharacters) (Cn)
ucUppercaseLetter	Letter, uppercase (Lu)

This enumeration type contains the characterization of all possible Unicode characters. It is used in the `GetUnicodeCategory` (245) and `TCharacter.GetUnicodeCategory` (252) functions.

`TUnicodeCategorySet = Set of TUnicodeCategory`

`TUnicodeCategorySet` is the set of `TUnicodeCategory` (243). It is used internally in the `TCharacter` (250) class.

2.4 Procedures and functions

2.4.1 ConvertFromUtf32

Synopsis: alias for `TCharacter.ConvertFromUtf32`

Declaration: `function ConvertFromUtf32 (AChar: UCS4Char) : UnicodeString`

Visibility: default

Description: `ConvertFromUtf32` is a shortcut for `TCharacter.ConvertFromUtf32` (251).

See also: `TCharacter.ConvertFromUtf32` (251)

2.4.2 ConvertToUtf32

Synopsis: alias for `TCharacter.ConvertToUtf32`

Declaration:

```
function ConvertToUtf32(const AString: UnicodeString; AIndex: Integer)
                        : UCS4Char; Overload
function ConvertToUtf32(const AString: UnicodeString; AIndex: Integer;
                        out ACharLength: Integer) : UCS4Char; Overload
function ConvertToUtf32(const AHighSurrogate: UnicodeChar;
                        const ALowSurrogate: UnicodeChar) : UCS4Char
                        ; Overload
```

Visibility: default

Description: `ConvertToUtf32` is a shortcut for `TCharacter.ConvertToUtf32` (251).

See also: `TCharacter.ConvertToUtf32` (251)

2.4.3 GetNumericValue

Synopsis: Alias for `TCharacter.GetNumericValue`

Declaration:

```
function GetNumericValue(AChar: UnicodeChar) : Double; Overload
function GetNumericValue(const AString: UnicodeString; AIndex: Integer)
                        : Double; Overload
```

Visibility: default

Description: `GetNumericValue` is a shortcut for `TCharacter.GetNumericValue` (252).

See also: `TCharacter.GetNumericValue` (252)

2.4.4 GetUnicodeCategory

Synopsis: Alias for `TCharacter.GetUnicodeCategory`

Declaration:

```
function GetUnicodeCategory(AChar: UnicodeChar) : TUnicodeCategory
                        ; Overload
function GetUnicodeCategory(const AString: UnicodeString;
                        AIndex: Integer) : TUnicodeCategory
                        ; Overload
```

Visibility: default

Description: `GetUnicodeCategory` is a shortcut for `TCharacter.GetUnicodeCategory` (252).

See also: `TCharacter.GetUnicodeCategory` (252)

2.4.5 IsControl

Synopsis: Alias for `TCharacter.IsControl`

Declaration: `function IsControl(AChar: UnicodeChar) : Boolean; Overload`
`function IsControl(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsControl` is a shortcut for `TCharacter.IsControl` ([252](#)).

See also: `TCharacter.IsControl` ([252](#))

2.4.6 IsDigit

Synopsis: Alias for `TCharacter.IsDigit`

Declaration: `function IsDigit(AChar: UnicodeChar) : Boolean; Overload`
`function IsDigit(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsDigit` is a shortcut for `TCharacter.IsDigit` ([253](#)).

See also: `TCharacter.IsDigit` ([253](#))

2.4.7 IsHighSurrogate

Synopsis: Alias for `TCharacter.IsHighSurrogate`

Declaration: `function IsHighSurrogate(AChar: UnicodeChar) : Boolean; Overload`
`function IsHighSurrogate(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsHighSurrogate` is a shortcut for `TCharacter.IsHighSurrogate` ([254](#))

See also: `TCharacter.IsHighSurrogate` ([254](#))

2.4.8 IsLetter

Synopsis: Alias for `TCharacter.IsLetter`

Declaration: `function IsLetter(AChar: UnicodeChar) : Boolean; Overload`
`function IsLetter(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsLetter` is a shortcut for `TCharacter.IsLetter` ([255](#))

See also: `TCharacter.IsLetter` ([255](#))

2.4.9 IsLetterOrDigit

Synopsis: Alias for `TCharacter.IsLetterOrDigit`

Declaration: `function IsLetterOrDigit (AChar: UnicodeChar) : Boolean; Overload`
`function IsLetterOrDigit (const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsLetterOrDigit` is a shortcut for `TCharacter.IsLetterOrDigit` ([255](#)).

See also: `TCharacter.IsLetterOrDigit` ([255](#))

2.4.10 IsLower

Synopsis: Alias for `TCharacter.IsLower`

Declaration: `function IsLower (AChar: UnicodeChar) : Boolean; Overload`
`function IsLower (const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsLower` is a shortcut for `TCharacter.IsLower` ([256](#))

See also: `TCharacter.IsLower` ([256](#))

2.4.11 IsLowSurrogate

Synopsis: Alias for `TCharacter.IsLowSurrogate`

Declaration: `function IsLowSurrogate (AChar: UnicodeChar) : Boolean; Overload`
`function IsLowSurrogate (const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsLowSurrogate` is a shortcut for `TCharacter.IsLowSurrogate` ([254](#))

See also: `TCharacter.IsLowSurrogate` ([254](#))

2.4.12 IsNumber

Synopsis: Alias for `TCharacter.IsNumber`

Declaration: `function IsNumber (AChar: UnicodeChar) : Boolean; Overload`
`function IsNumber (const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsNumber` is a shortcut for `TCharacter.IsNumber` ([256](#))

See also: `TCharacter.IsNumber` ([256](#))

2.4.13 IsPunctuation

Synopsis: Alias for `TCharacter.IsPunctuation`

Declaration: `function IsPunctuation(AChar: UnicodeChar) : Boolean; Overload`
`function IsPunctuation(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsPunctuation` is a shortcut for `TCharacter.IsPunctuation` ([257](#))

See also: `TCharacter.IsPunctuation` ([257](#))

2.4.14 IsSeparator

Synopsis: Alias for `TCharacter.IsSeparator`

Declaration: `function IsSeparator(AChar: UnicodeChar) : Boolean; Overload`
`function IsSeparator(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsSeparator` is a shortcut for `TCharacter.IsSeparator` ([257](#))

See also: `TCharacter.IsSeparator` ([257](#))

2.4.15 IsSurrogate

Synopsis: Alias for `TCharacter.IsSurrogate`

Declaration: `function IsSurrogate(AChar: UnicodeChar) : Boolean; Overload`
`function IsSurrogate(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsSurrogate` is a shortcut for `TCharacter.IsSurrogate` ([253](#)).

See also: `TCharacter.IsSurrogate` ([253](#))

2.4.16 IsSurrogatePair

Synopsis: Alias for `TCharacter.IsSurrogatePair`

Declaration: `function IsSurrogatePair(const AHighSurrogate: UnicodeChar;`
`const ALowSurrogate: UnicodeChar) : Boolean`
`; Overload`
`function IsSurrogatePair(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsSurrogatePair` is a shortcut for `TCharacter.IsSurrogatePair` ([254](#))

See also: `TCharacter.IsSurrogatePair` ([254](#))

2.4.17 IsSymbol

Synopsis: Alias for `TCharacter.IsSymbol`

Declaration: `function IsSymbol(AChar: UnicodeChar) : Boolean; Overload`
`function IsSymbol(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsSymbol` is a shortcut for `TCharacter.IsSymbol` ([257](#))

See also: `TCharacter.IsSymbol` ([257](#))

2.4.18 IsUpper

Synopsis: Alias for `TCharacter.IsUpper`

Declaration: `function IsUpper(AChar: UnicodeChar) : Boolean; Overload`
`function IsUpper(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsUpper` is a shortcut for `TCharacter.IsUpper` ([258](#))

See also: `TCharacter.IsUpper` ([258](#))

2.4.19 IsWhiteSpace

Synopsis: Alias for `TCharacter.IsWhiteSpace`

Declaration: `function IsWhiteSpace(AChar: UnicodeChar) : Boolean; Overload`
`function IsWhiteSpace(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload`

Visibility: default

Description: `IsWhiteSpace` is a shortcut for `TCharacter.IsWhiteSpace` ([258](#))

See also: `TCharacter.IsWhiteSpace` ([258](#))

2.4.20 ToLower

Synopsis: Alias for `TCharacter.ToLower`

Declaration: `function ToLower(AChar: UnicodeChar) : UnicodeChar; Overload`
`function ToLower(const AString: UnicodeString) : UnicodeString`
`; Overload`

Visibility: default

Description: `ToLower` is a shortcut for `TCharacter.ToLower` ([259](#))

See also: `TCharacter.ToLower` ([259](#))

2.4.21 ToUpper

Synopsis: Alias for `TCharacter.ToUpper`

Declaration: `function ToUpper(AChar: UnicodeChar) : UnicodeChar; Overload`
`function ToUpper(const AString: UnicodeString) : UnicodeString`
`; Overload`

Visibility: default

Description: `ToUpper` is a shortcut for `TCharacter.ToUpper` ([259](#))

See also: `TCharacter.ToUpper` ([259](#))

2.5 TCharacter

2.5.1 Description

`TCharacter` is provided for Delphi compatibility. All it's class functions and methods are also available as regular functions.

2.5.2 Method overview

Page	Method	Description
251	<code>ConvertFromUtf32</code>	Convert a UTF32 character to <code>UnicodeString</code>
251	<code>ConvertToUtf32</code>	Convert a UTF16 character to a UTF32 character
250	<code>Create</code>	Constructor (do not call)
252	<code>GetNumericValue</code>	Get the numeric value of the character
252	<code>GetUnicodeCategory</code>	Get the Unicode category of a character
252	<code>IsControl</code>	Check whether a Unicode character is a Unicode control character
253	<code>IsDigit</code>	Check whether a Unicode character is a digit
254	<code>IsHighSurrogate</code>	Check whether a Unicode character is a surrogate in the high range
255	<code>IsLetter</code>	Check if a Unicode character is a letter.
255	<code>IsLetterOrDigit</code>	Check if a Unicode character is a letter or digit
256	<code>IsLower</code>	Check if a Unicode character is a lowercase letter
254	<code>IsLowSurrogate</code>	Check whether a Unicode character is a surrogate in the low range
256	<code>IsNumber</code>	Check if a Unicode character is a number
257	<code>IsPunctuation</code>	Check if a Unicode character is a punctuation character
257	<code>IsSeparator</code>	Check if a Unicode character is a separator character
253	<code>IsSurrogate</code>	Check whether a Unicode character is a surrogate
254	<code>IsSurrogatePair</code>	Check if a pair of characters is a set of high/low surrogate characters
257	<code>IsSymbol</code>	Check if a Unicode character is a symbol character
258	<code>IsUpper</code>	Check whether a Unicode character is an uppercase letter
258	<code>IsWhiteSpace</code>	Check whether a Unicode character is a whitespace character
259	<code>ToLower</code>	Convert a character or string to lowercase
259	<code>ToUpper</code>	Convert a character or string to uppercase

2.5.3 TCharacter.Create

Synopsis: Constructor (do not call)

Declaration: `constructor Create`

Visibility: public

Description: `Create` is provided for completeness and Delphi compatibility, but should not be called in FPC code, it will raise an exception.

Errors: Any attempt to call `Create` will result in an exception being raised.

2.5.4 TCharacter.ConvertFromUtf32

Synopsis: Convert a UTF32 character to UnicodeString

Declaration: `class function ConvertFromUtf32(AChar: UCS4Char) : UnicodeString; Static`

Visibility: public

Description: `TCharacter.ConvertFromUtf32` converts a single UTF32 character `AChar` to a UTF16 string. This is the opposite of `TCharacter.ConvertToUtf32` (251).

The result is a string, since multiple UTF16 characters can be needed to encode a single UTF32 character.

Errors: If `AChar` is not in the valid range of UTF32 characters, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `EArgumentOutOfRangeException` (242), `TCharacter.ConvertToUtf32` (251)

2.5.5 TCharacter.ConvertToUtf32

Synopsis: Convert a UTF16 character to a UTF32 character

Declaration: `class function ConvertToUtf32(const AString: UnicodeString; AIndex: Integer) : UCS4Char; Overload; Static`
`class function ConvertToUtf32(const AString: UnicodeString; AIndex: Integer; out ACharLength: Integer) : UCS4Char; Overload; Static`
`class function ConvertToUtf32(const AHighSurrogate: UnicodeChar; const ALowSurrogate: UnicodeChar) : UCS4Char; Overload; Static`

Visibility: public

Description: `TCharacter.ConvertToUtf32` converts a UTF16-encoded Unicode character to a Unicode32 character. This is the opposite of `TCharacter.ConvertFromUtf32` (251). The function exists in several overloaded versions, to be able to present the Unicode character in one of 2 ways:

1. As a position `AIndex` (in `unicodechar` units) in a string `AString` to a Unicode32 character. The source is a string, since multiple UTF16 characters can be needed to encode a single UTF32 character. In this form, Optionally, the character length (1 or 2) can be returned in `ACharLength`.
2. As 2 UTF16 Unicode characters, representing the high and low surrogate pairs: `AHighSurrogate` and `ALowSurrogate`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

Visibility: public

Description: `IsControl` returns `True` if a Unicode character has category `ucControl`. The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `GetUnicodeCategory` (252), `IsDigit` (253), `IsSurrogate` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsSurrogatePair` (254), `IsLetter` (255), `IsLetterOrDigit` (255), `IsLower` (256), `IsNumber` (256), `IsPunctuation` (257), `IsSeparator` (257), `IsSymbol` (257), `IsUpper` (258), `IsWhiteSpace` (258)

2.5.9 TCharacter.IsDigit

Synopsis: Check whether a Unicode character is a digit

Declaration: `class function IsDigit(AChar: UnicodeChar) : Boolean; Overload; Static`
`class function IsDigit(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload; Static`

Visibility: public

Description: `IsDigit` returns `True` if a Unicode character has category `ucDecimalNumber`. The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `IsControl` (252), `IsDigit` (253), `IsSurrogate` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsSurrogatePair` (254), `IsLetter` (255), `IsLetterOrDigit` (255), `IsLower` (256), `IsNumber` (256), `IsPunctuation` (257), `IsSeparator` (257), `IsSymbol` (257), `IsUpper` (258), `IsWhiteSpace` (258)

2.5.10 TCharacter.IsSurrogate

Synopsis: Check whether a Unicode character is a surrogate

Declaration: `class function IsSurrogate(AChar: UnicodeChar) : Boolean; Overload`
`; Static`
`class function IsSurrogate(const AString: UnicodeString;`
`AIndex: Integer) : Boolean; Overload; Static`

Visibility: public

Description: `IsSurrogate` returns `True` if a Unicode character has category `ucSurrogate`. The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `EArgumentOutOfRangeException` (242), `IsControl` (252), `IsDigit` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsLetter` (255), `IsLetterOrDigit` (255), `IsLower` (256), `IsNumber` (256), `IsPunctuation` (257), `IsSymbol` (257), `IsUpper` (258), `IsWhiteSpace` (258)


```
class function IsSurrogatePair(const AString: UnicodeString;
                              AIndex: Integer) : Boolean; Overload
; Static
```

Visibility: public

Description: `IsSurrogatePair` returns `True` if `AHighSurrogate` and `ALowSurrogate` form a valid Unicode surrogate pair. (`AHighSurrogate` is a high surrogate and `ALowSurrogate` a matching low surrogate) The character can be specified as a UTF16 character `AChar` or a pair of UTF16 encoded characters starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `EArgumentOutOfRangeException` (242), `IsControl` (252), `IsDigit` (253), `IsSurrogate` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsLetter` (255), `IsLetterOrDigit` (255), `IsLower` (256), `IsNumber` (256), `IsPunctuation` (257), `IsSymbol` (257), `IsUpper` (258), `IsWhiteSpace` (258)

2.5.14 TCharacter.IsLetter

Synopsis: Check if a Unicode character is a letter.

Declaration:

```
class function IsLetter(AChar: UnicodeChar) : Boolean; Overload
; Static
class function IsLetter(const AString: UnicodeString; AIndex: Integer)
: Boolean; Overload; Static
```

Visibility: public

Description: `IsLetter` returns `True` if a Unicode character has category that is one of the letter categories (`ucUppercaseLetter`, `ucLowercaseLetter`, `ucTitlecaseLetter`, `ucModifierLetter`, `ucOtherLetter`). The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an

See also: `EArgumentOutOfRangeException` (242), `IsControl` (252), `IsDigit` (253), `IsSurrogate` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsSurrogatePair` (254), `IsLetter` (255), `IsLetterOrDigit` (255), `IsLower` (256), `IsNumber` (256), `IsPunctuation` (257), `IsSymbol` (257), `IsUpper` (258), `IsWhiteSpace` (258)

2.5.15 TCharacter.IsLetterOrDigit

Synopsis: Check if a Unicode character is a letter or digit

Declaration:

```
class function IsLetterOrDigit(AChar: UnicodeChar) : Boolean; Overload
; Static
class function IsLetterOrDigit(const AString: UnicodeString;
                              AIndex: Integer) : Boolean; Overload
; Static
```

Visibility: public

Description: `IsLetterOrDigit` returns `True` if a Unicode character has category that is one of the letter categories (`ucUppercaseLetter`, `ucLowercaseLetter`, `ucTitlecaseLetter`, `ucModifierLetter`, `ucOtherLetter`, `ucDecimalNumber`, `ucLetterNumber`). The character can be specified as

a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `IsControl` (252), `IsDigit` (253), `IsSurrogate` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsSurrogatePair` (254), `IsLetter` (255), `IsLower` (256), `IsNumber` (256), `IsPunctuation` (257), `IsSymbol` (257), `IsUpper` (258), `IsWhiteSpace` (258)

2.5.16 TCharacter.IsLower

Synopsis: Check if a Unicode character is a lowercase letter

Declaration: `class function IsLower(AChar: UnicodeChar) : Boolean; Overload; Static`
`class function IsLower(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload; Static`

Visibility: public

Description: `IsLower` returns `True` if a Unicode character has category `ucLowercaseLetter`. The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `IsControl` (252), `IsDigit` (253), `IsSurrogate` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsSurrogatePair` (254), `IsLetter` (255), `IsLetterOrDigit` (255), `IsNumber` (256), `IsPunctuation` (257), `IsSymbol` (257), `IsUpper` (258), `IsWhiteSpace` (258)

2.5.17 TCharacter.IsNumber

Synopsis: Check if a Unicode character is a number

Declaration: `class function IsNumber(AChar: UnicodeChar) : Boolean; Overload`
`; Static`
`class function IsNumber(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload; Static`

Visibility: public

Description: `IsNumber` returns `True` if a Unicode character has category that is one of the number categories (`ucDecimalNumber`, `ucLetterNumber`, `ucOtherNumber`). The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `IsControl` (252), `IsDigit` (253), `IsSurrogate` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsSurrogatePair` (254), `IsLetter` (255), `IsLetterOrDigit` (255), `IsLower` (256), `IsNumber` (256), `IsPunctuation` (257), `IsSymbol` (257), `IsUpper` (258), `IsWhiteSpace` (258)

2.5.18 TCharacter.IsPunctuation

Synopsis: Check if a Unicode character is a punctuation character

```
Declaration: class function IsPunctuation(AChar: UnicodeChar) : Boolean; Overload
                ; Static
        class function IsPunctuation(const AString: UnicodeString;
                AIndex: Integer) : Boolean; Overload
                ; Static
```

Visibility: public

Description: `IsPunctuation` returns `True` if a Unicode character has category that is one of the punctuation categories (`ucConnectPunctuation`, `ucDashPunctuation`, `ucOpenPunctuation`, `ucClosePunctuation`, `ucInitialPunctuation`, `ucFinalPunctuation`, `ucOtherPunctuation`). The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentException` (242) exception is raised.

See also: [IsControl \(252\)](#), [IsDigit \(253\)](#), [IsSurrogate \(253\)](#), [IsHighSurrogate \(254\)](#), [IsLowSurrogate \(254\)](#), [IsSurrogatePair \(254\)](#), [IsLetter \(255\)](#), [IsLetterOrDigit \(255\)](#), [IsLower \(256\)](#), [IsNumber \(256\)](#), [IsSymbol \(257\)](#), [IsUpper \(258\)](#), [IsWhiteSpace \(258\)](#)

2.5.19 TCharacter.IsSeparator

Synopsis: Check if a Unicode character is a separator character

```
Declaration: class function IsSeparator(AChar: UnicodeChar) : Boolean; Overload
                ; Static
        class function IsSeparator(const AString: UnicodeString;
                AIndex: Integer) : Boolean; Overload; Static
```

Visibility: public

Description: IsSeparator returns True if a Unicode character has category that is one of the separator categories (ucSpaceSeparator, ucLineSeparator, ucParagraphSeparator). The character can be specified as a UTF16 character AChar or a UTF16 encoded character starting at position AIndex in string AString.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentException` (242) exception is raised.

See also: [IsControl \(252\)](#), [IsDigit \(253\)](#), [IsSurrogate \(253\)](#), [IsHighSurrogate \(254\)](#), [IsLowSurrogate \(254\)](#), [IsSurrogatePair \(254\)](#), [IsLetter \(255\)](#), [IsLetterOrDigit \(255\)](#), [IsLower \(256\)](#), [IsNumber \(256\)](#), [IsPunctuation \(257\)](#), [IsSymbol \(257\)](#), [IsUpper \(258\)](#), [IsWhiteSpace \(258\)](#)

2.5.20 TCharacter.IsSymbol

Synopsis: Check if a Unicode character is a symbol character

```
Declaration: class function IsSymbol(AChar: UnicodeChar) : Boolean; Overload
              ; Static
              class function IsSymbol(const AString: UnicodeString; AIndex: Integer)
              : Boolean; Overload; Static
```

Visibility: public

Description: `IsSymbol` returns `True` if a Unicode character has category that is one of the symbol categories (`ucMathSymbol`, `ucCurrencySymbol`, `ucModifierSymbol`, `ucOtherSymbol`). The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `IsControl` (252), `IsDigit` (253), `IsSurrogate` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsSurrogatePair` (254), `IsLetter` (255), `IsLetterOrDigit` (255), `IsLower` (256), `IsNumber` (256), `IsPunctuation` (257), `IsSeparator` (257), `IsUpper` (258), `IsWhiteSpace` (258)

2.5.21 TCharacter.IsUpper

Synopsis: Check whether a Unicode character is an uppercase letter

Declaration: `class function IsUpper(AChar: UnicodeChar) : Boolean; Overload; Static`
`class function IsUpper(const AString: UnicodeString; AIndex: Integer)`
`: Boolean; Overload; Static`

Visibility: public

Description: `IsUpper` returns `True` if a Unicode character has category `ucUppercaseLetter`. The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: `IsControl` (252), `IsDigit` (253), `IsSurrogate` (253), `IsHighSurrogate` (254), `IsLowSurrogate` (254), `IsSurrogatePair` (254), `IsLetter` (255), `IsLetterOrDigit` (255), `IsLower` (256), `IsNumber` (256), `IsPunctuation` (257), `IsSeparator` (257), `IsSymbol` (257), `IsWhiteSpace` (258)

2.5.22 TCharacter.IsWhiteSpace

Synopsis: Check whether a Unicode character is a whitespace character

Declaration: `class function IsWhiteSpace(AChar: UnicodeChar) : Boolean; Overload`
`; Static`
`class function IsWhiteSpace(const AString: UnicodeString;`
`AIndex: Integer) : Boolean; Overload`
`; Static`

Visibility: public

Description: `IsUpper` returns `True` if a Unicode character has is a whitespace character. It checks the character properties. The character can be specified as a UTF16 character `AChar` or a UTF16 encoded character starting at position `AIndex` in string `AString`.

Errors: If `AIndex` is not a valid character index in the string `AString`, an `EArgumentOutOfRangeException` (242) exception is raised. If the character at that position is not complete, an `EArgumentOutOfRangeException` (242) exception is raised.

See also: [IsControl \(252\)](#), [IsDigit \(253\)](#), [IsSurrogate \(253\)](#), [IsHighSurrogate \(254\)](#), [IsLowSurrogate \(254\)](#), [IsSurrogatePair \(254\)](#), [IsLetter \(255\)](#), [IsLetterOrDigit \(255\)](#), [IsLower \(256\)](#), [IsNumber \(256\)](#), [IsPunctuation \(257\)](#), [IsSeparator \(257\)](#), [IsSymbol \(257\)](#), [IsUpper \(258\)](#)

2.5.23 TCharacter.ToLower

Synopsis: Convert a character or string to lowercase

Declaration:

```
class function ToLower(AChar: UnicodeChar) : UnicodeChar; Overload
    ; Static
class function ToLower(const AString: UnicodeString) : UnicodeString
    ; Overload; Static
class function ToLower(const AString: UnicodeString;
    const AOptions: TCharacterOptions) : UnicodeString
    ; Overload; Static
```

Visibility: public

Description: `ToLower` converts the Unicode character `AChar` or string `AString` to lowercase. Options determines the behaviour of the conversion: if `AOptions` contains `coIgnoreInvalidSequence` then no exception will be raised when the string or character contains an invalid Unicode sequence. The default behaviour is to raise an `EArgumentException` (242) exception when this happens.

Errors: If an invalid character is encountered, an `EArgumentException` (242) exception is raised, unless `coIgnoreInvalidSequence` is specified in the options.

See also: [TCharacter.ToUpper \(259\)](#), [TCharacter.IsLower \(256\)](#), [TCharacter.IsUpper \(258\)](#)

2.5.24 TCharacter.ToUpper

Synopsis: Convert a character or string to uppercase

Declaration:

```
class function ToUpper(AChar: UnicodeChar) : UnicodeChar; Overload
    ; Static
class function ToUpper(const AString: UnicodeString) : UnicodeString
    ; Overload; Static
class function ToUpper(const AString: UnicodeString;
    const AOptions: TCharacterOptions) : UnicodeString
    ; Overload; Static
```

Visibility: public

Description: `ToUpper` converts the Unicode character `AChar` or string `AString` to uppercase. Options determines the behaviour of the conversion: if `AOptions` contains `coIgnoreInvalidSequence` then no exception will be raised when the string or character contains an invalid Unicode sequence. The default behaviour is to raise an `EArgumentException` (242) exception when this happens.

Errors: If an invalid character is encountered, an `EArgumentException` (242) exception is raised, unless `coIgnoreInvalidSequence` is specified in the options.

See also: [TCharacter.ToUpper \(259\)](#), [TCharacter.IsLower \(256\)](#), [TCharacter.IsUpper \(258\)](#)

Chapter 3

Reference for unit 'charset'

3.1 Used units

Table 3.1: Used units by unit 'charset'

Name	Page
System	1339

3.2 Overview

The charset unit can be used to load single-byte character set (code page) descriptions. It is used in the `fpwidingstring` ([260](#)) unit to add support for converting single-byte codepage strings to Unicode strings (and vice versa).

Data of a code page may be included using one of the ready-made units, or can be loaded (in a binary form) at runtime with the `loadbinaryunicodemapping` ([262](#)) function. The binary files have the `.bcm` extension and are produced by the `creumap` utility distributed with Free Pascal.

Pre-made units are available for the following codepages: `cp895` ([260](#)), `cp932` ([260](#)), `cp936` ([260](#)), `cp949` ([260](#)) and `cp950` ([260](#)).

3.3 Constants, types and variables

3.3.1 Constants

```
BINARY_MAPPING_FILE_EXT = '.bcm'
```

`BINARY_MAPPING_FILE_EXT` contains the default extension of a file containing a binary-coded map.

3.3.2 Types

```
preversecharmapping = ^treversecharmapping
```

Pointer to `treversecharmapping`

```
punicodecharmapping = ^tunicodecharmapping
```

Pointer to tunicodecharmapping

```
punicodemap = ^tunicodemap
```

Pointer to tunicodemap

```
tunicodechar = Word
```

tunicodechar is a type used to represent Unicode characters in this file, it should not be used for other Unicode routines.

```
tunicodecharmappingflag = (umf_noinfo, umf_leadbyte, umf_undefined,
    umf_unused)
```

Table 3.2: Enumeration values for type tunicodecharmappingflag

Value	Explanation
umf_leadbyte	Unicode character uses leading byte
umf_noinfo	No extra information about Unicode character
umf_undefined	Currently unused
umf_unused	Unused position in code page

tunicodecharmappingflag contains various Flags describing information about a Unicode character.

```
tunicodestring = ^tunicodechar
```

tunicodestring is a type used to represent Unicode strings in this file, it should not be used for other Unicode routines.

3.4 Procedures and functions

3.4.1 getascii

Synopsis: Convert Unicode character or string to single-byte character or string.

Declaration:

```
function getascii(c: tunicodechar; p: punicodemap) : string
function getascii(c: tunicodechar; p: punicodemap; ABuffer: PAnsiChar;
    ABufferLen: LongInt) : LongInt
```

Visibility: default

Description: getascii converts a Unicode character c to one or more single-byte characters according to the map in p. The result can be a string containing up to 2 characters, or the number of characters copied to the buffer ABuffer with length ABufferLen.

Errors: If the character cannot be translated, ASCII character 63 is returned (or copied to the buffer). In the case of the buffer variant of the function, -1 is then returned. If the buffer is not large enough, -1 is returned.

See also: [getunicode \(262\)](#)

3.4.2 getmap

Synopsis: Find a codepage map

Declaration: `function getmap(const s: string) : puniconemap`
`function getmap(cp: Word) : puniconemap`

Visibility: default

Description: `getmap` looks in the registered codepage mappings and returns the mapping for the requested codepage. The codepage can be specified using a name `s` or a numerical identifier `cp`. The search is case sensitive.

Errors: if the requested map is not found, `Nil` is returned.

See also: `registermapping` (264), `registerbinarymapping` (263), `mappingavailable` (263)

3.4.3 getunicode

Synopsis: Map single-byte character to Unicode character.

Declaration: `function getunicode(c: Char; p: puniconemap) : tuniconedchar`
`function getunicode(AAnsiStr: PAnsiChar; AAnsiLen: LongInt;`
`AMap: puniconemap; ADest: tuniconestring) : LongInt`

Visibility: default

Description: The first form of `getunicode` will map a single character `c` to its Unicode equivalent for mapping `p`. If no equivalent can be found, 0 is returned.

The second form of `getunicode` will transform a string (specified using a pointer `AAnsiStr` to a buffer with length `AAnsiLen`) to a Unicode string using single byte codepage map `AMap`. It returns the number of Unicode characters. If `ADest` is `Nil` then just the number of characters is returned. If `ADest` is not `nil`, it must point to a buffer large enough to contain the Unicode string, and the converted string will be copied to it.

Errors: No checking on the validity of the buffers is done.

See also: `getascii` (261)

3.4.4 loadbinaryunicodemapping

Synopsis: Load binary single-byte codepage to Unicode map from file or memory

Declaration: `function loadbinaryunicodemapping(const directory: string;`
`const cpname: string) : puniconemap`
`; Overload`
`function loadbinaryunicodemapping(const filename: string) : puniconemap`
`; Overload`
`function loadbinaryunicodemapping(const AData: Pointer;`
`const ADataLength: Integer)`
`: puniconemap; Overload`

Visibility: default

Description: `loadbinaryunicodemapping` loads a binary description of a single-byte Unicode mapping. The mapping can reside in a file, in which case the file to load can be specified using a filename `filename` or using a directory `directory` and codepage name `cpname`. In the latter case, a

suffix consisting of `_le` or `_be` depending on the endianness of the current platform will be appended, and the filename extension is `.bcm`. Note that the file names may be case sensitive.

The data can also be loaded from a memory block `AData` with size `ADataLength`.

It will produce an in-memory map of the file. It returns a pointer to the map, or `Nil` if something went wrong. The resulting mapping can be registered using `registermapping` (264).

Errors: On error, `Nil` is returned.

See also: `loadunicodemapping` (263), `registermapping` (264)

3.4.5 loadunicodemapping

Synopsis: Load textual single-byte codepage to Unicode map from file

Declaration: `function loadunicodemapping(const cpname: string; const f: string;
cp: Word) : puniconemap`

Visibility: default

Description: `loadunicodemapping` loads a text description of a single-byte Unicode mapping. It will analyse the textual description in file `f`, and produce an in-memory map of the file. It returns a pointer to the map, or `Nil` if something went wrong. The Unicode map name must be specified in `cpName`, and the numerical identifier in `cp`

The resulting mapping can be registered using `registermapping` (264).

Errors: On error, `Nil` is returned.

See also: `loadbinaryunicodemapping` (262), `registermapping` (264)

3.4.6 mappingavailable

Synopsis: Check if a mapping is available for a specified code page.

Declaration: `function mappingavailable(const s: string) : Boolean
function mappingavailable(cp: Word) : Boolean`

Visibility: default

Description: `mappingavailable` returns `True` if a mapping for a specified code page (using name `s` or numerical identifier `cp`) is available, or `False` if it is not.

See also: `registermapping` (264), `registerbinarymapping` (263), `getmap` (262)

3.4.7 registerbinarymapping

Synopsis: Load and register binary single-byte codepage to Unicode map from file

Declaration: `function registerbinarymapping(const directory: string;
const cpname: string) : Boolean`

Visibility: default

Description: `registerbinarymapping` calls `loadbinaryunicodemapping` (262) using `directory` and `cpname` and registers the resulting mapping, if any was successfully loaded, using `registermapping` (264). It returns `True` if the operation was successful.

Errors: On error, `False` is returned.

See also: `loadbinaryunicodemapping` (262), `registermapping` (264)

3.4.8 registermapping

Synopsis: Register mapping

Declaration: `procedure registermapping(p: punicomemap)`

Visibility: default

Description: `RegisterMapping` registers mapping `p` in the registry of single-byte codepages. No attempt is made to avoid double registrations. In case of doubles, the last registered mapping will be used first.

See also: [loadunicodemapping \(263\)](#), [loadbinaryunicodemapping \(262\)](#), [registerbinarymapping \(263\)](#)

3.5 treversecharmapping

```
treversecharmapping = packed record
  unicode : tunicodechar;
  char1
    : Byte;
  char2 : Byte;
end
```

`treversecharmapping` describes how a Unicode character can be created in terms of single-byte characters.

3.6 TSerializedMapHeader

```
TSerializedMapHeader = packed record
  cpName : string;
  cp : UInt16
  ;
  mapLength : UInt32;
  lastChar : Int32;
  reverseMapLength : UInt32
  ;
end
```

`TSerializedMapHeader` is a record describing the binary map data file. The contents of this record can be found at offset zero of a (.bcm) file containing a single-byte Unicode map.

3.7 tunicodecharmapping

```
tunicodecharmapping = packed record
  unicode : tunicodechar;
  flag
    : tunicodecharmappingflag;
  reserved : Byte;
end
```

`tunicodecharmapping` describes a Unicode character. An array of these mappings is built for each character in the single-byte character set,

3.8 tunicodemap

```
tunicodemap = record
  cpname : string;
  cp : Word;
  map : punicodecharmapping
;
  lastchar : LongInt;
  reversemap : preversecharmapping;
  reversemaplength
: LongInt;
  next : tunicodemap;
  internalmap : Boolean;
end
```

`tunicodemap` describes a complete mapping between a single-byte code page and a Unicode character set. It contains both a forward and backward mapping.

Chapter 4

Reference for unit 'Classes'

4.1 Used units

Table 4.1: Used units by unit 'Classes'

Name	Page
rtlconsts	??
System	1339
sysutils	1615
Types	1934
TypeInfo	1970

4.2 Overview

This documentation describes the FPC `classes` unit. The `Classes` unit contains basic classes for the Free Component Library (FCL):

- a `TList` ([408](#)) class for maintaining lists of pointers,
- `TStringList` ([463](#)) for lists of strings,
- `TCollection` ([358](#)) to manage collections of objects
- `TStream` ([448](#)) classes to support streaming.

Furthermore it introduces methods for object persistence, and classes that understand an owner-owned relationship, with automatic memory management.

4.3 Constants, types and variables

4.3.1 Constants

`BITSHIFT` = 5

Used to calculate the size of a bits array

`dupAccept = Types.dupAccept`

Duplicate values can be added to the list.

`dupError = Types.dupError`

If an attempt is made to add a duplicate value to the list, an `EStringListError` (306) exception is raised.

`dupIgnore = Types.dupIgnore`

Duplicate values will not be added to the list, but no error will be triggered.

`FilerSignature : Array[1..4] of Char = 'TPF0'`

Constant that is found at the start of a binary stream containing a streamed component.

`fmCreate = $FF00`

`TFileStream.Create` (389) creates a new file if needed.

`fmOpenRead = 0`

`TFileStream.Create` (389) opens a file with read-only access.

`fmOpenReadWrite = 2`

`TFileStream.Create` (389) opens a file with read-write access.

`fmOpenWrite = 1`

`TFileStream.Create` (389) opens a file with write-only access.

`MASK = 31`

Bitmask with all bits on.

`MaxBitFlags = $7FFFFFFE0`

Maximum number of bits in `TBits` collection.

`MaxBitRec = MaxBitFlags div SizeOf(cardinal) * 8`

Maximum number of bit records in `TBits`.

`MaxListSize = Maxint div 16`

This constant sets the maximum number of elements in a `TList` (408).

`scAlt = $8000`

Indicates ALT key in a keyboard shortcut.

```
scCtrl = $4000
```

indicates CTRL key in a keyboard shortcut.

```
scNone = 0
```

Indicates no special key is pressed in a keyboard shortcut.

```
scShift = $2000
```

Indicates Shift key in a keyboard shortcut.

```
SGUIDObserved = '{663C603C-3F3C-4CC5-823C-AC8079F979E5}'
```

Observed interface GUID as a string

```
SGUIDObserver = '{BC7376EA-199C-4C2A-8684-F4805F0691CA}'
```

Observer interface GUID as a string

```
soFromBeginning = 0
```

Seek (450) starts relative to the stream origin.

```
soFromCurrent = 1
```

Seek (450) starts relative to the current position in the stream.

```
soFromEnd = 2
```

Seek (450) starts relative to the stream end.

```
toEOF = Char(0)
```

Value returned by TParser.Token (428) when the end of the input stream was reached.

```
toFloat = Char(4)
```

Value returned by TParser.Token (428) when a floating point value was found in the input stream.

```
toInteger = Char(3)
```

Value returned by TParser.Token (428) when an integer was found in the input stream.

```
toString = Char(2)
```

Value returned by TParser.Token (428) when a string was found in the input stream.

```
toSymbol = Char(1)
```

Value returned by TParser.Token (428) when a symbol was found in the input stream.

```
toWString = Char(5)
```

Value returned by TParser.Token (428) when a widestring was found in the input stream.

4.3.2 Types

`HMODULE = PtrInt`

FPC doesn't support modules yet, so this is a dummy type.

`HRSRC = TFPResourceHandle deprecated`

This type is provided for Delphi compatibility, it is used for resource streams.

`PPointerList = ^TPointerList`

Pointer to an array of pointers.

`PStringItem = ^TStringItem`

Pointer to a `TStringItem` (302) record.

`PStringItemList = ^TStringItemList`

Pointer to a `TStringItemList` (281).

`TActiveXRegType = (axrComponentOnly, axrIncludeDescendants)`

Table 4.2: Enumeration values for type `TActiveXRegType`

Value	Explanation
<code>axrComponentOnly</code>	
<code>axrIncludeDescendants</code>	

This type is provided for compatibility only, and is currently not used in Free Pascal.

`TAlignment = (taLeftJustify, taRightJustify, taCenter)`

Table 4.3: Enumeration values for type `TAlignment`

Value	Explanation
<code>taCenter</code>	Text is displayed centered.
<code>taLeftJustify</code>	Text is displayed aligned to the left
<code>taRightJustify</code>	Text is displayed aligned to the right.

The `TAlignment` type is used to specify the alignment of the text in controls that display a text.

```
TAncestorNotFoundEvent = procedure(Reader: TReader;
  const ComponentName: string;
  ComponentClass: TPersistentClass;
  var Component: TComponent) of object
```

This event occurs when an ancestor component cannot be found.

`TBasicActionClass = class of TBasicAction`

`TBasicAction` (332) class reference.

`TBasicActionLinkClass = class of TBasicActionLink`

`TBasicActionLink` (336) class reference.

`TBiDiMode = (bdLeftToRight, bdRightToLeft, bdRightToLeftNoAlign,
bdRightToLeftReadingOnly)`

Table 4.4: Enumeration values for type `TBiDiMode`

Value	Explanation
<code>bdLeftToRight</code>	Texts read from left to right.
<code>bdRightToLeft</code>	Texts read from right to left.
<code>bdRightToLeftNoAlign</code>	Texts read from right to left, but not right-aligned
<code>bdRightToLeftReadingOnly</code>	Texts read from right to left

`TBiDiMode` describes bi-directional support for displaying texts.

`TBitArray = Array[0..MaxBitRec-1] of Cardinal`

Array to store bits.

`TCollectionItemClass = class of TCollectionItem`

`TCollectionItemClass` is used by the `TCollection.ItemClass` (364) property of `TCollection` (358) to identify the descendant class of `TCollectionItem` (366) which should be created and managed.

`TCollectionNotification = (cnAdded, cnExtracting, cnDeleting)`

Table 4.5: Enumeration values for type `TCollectionNotification`

Value	Explanation
<code>cnAdded</code>	An item is added to the collection.
<code>cnDeleting</code>	An item is deleted from the collection.
<code>cnExtracting</code>	An item is extracted from the collection.

`TCollectionNotification` is used in the `TCollection` (358) class to send notifications about changes to the collection.

`TCollectionSortCompare = function(Item1: TCollectionItem;
Item2: TCollectionItem) : Integer`

`TCollectionSortCompare` is the prototype for a callback used in the `TCollection.Sort` (363) method. The procedure should compare `Item1` and `Item2` and return an integer:

Result < 0 if `Item1` comes before `Item2`

Result = 0 if `Item1` is at the same level as `Item2`

Result > 0 if `Item1` comes after `Item2`

`TComponentClass` = class of `TComponent`

The `TComponentClass` type is used when constructing `TComponent` (369) descendant instances and when registering components.

`TComponentName` = String

Names of components are of type `TComponentName`. By specifying a different type, the Object inspector can handle this property differently than a standard string property.

```
TComponentState= Set of (csLoading,csReading,csWriting,csDestroying
,
                        csDesigning,csAncestor,csUpdating,csFixups
,
                        csFreeNotification,csInline,csDesignInstance
)
```

Table 4.6: Enumeration values for type

Value	Explanation
<code>csAncestor</code>	The component is being streamed as part of a frame (?)
<code>csDesigning</code>	The component is being designed in an IDE.
<code>csDesignInstance</code>	??
<code>csDestroying</code>	The component is being destroyed.
<code>csFixups</code>	The component's references to other components are being fixed.
<code>csFreeNotification</code>	Indicates whether the component has freenotifications
<code>csInline</code>	Component is part of a frame (?).
<code>csLoading</code>	The component is being loaded from the stream.
<code>csReading</code>	Properties are being read from the stream.
<code>csUpdating</code>	The component is being updated.
<code>csWriting</code>	Properties are being written to the stream.

The following values are possible:

csLoading The component (and all child components) are being loaded from a stream. This means that a `TReader` (433) instance is reading properties from this and child components from a stream and is applying the values found in the stream to the properties.

csReading The properties of this component are being read from a stream. This means that a `TReader` (433) instance is reading properties from this component from a stream and is applying the values.

csWriting The properties of this component are being written to a stream. This means that a `TWriter` (515) instance is writing properties from this component to a stream.

csDestroying The component is being destroyed.

csDesigning The component is being designed in an IDE.

csAncestor The component has a design ancestor. This is used to record differences between a component and its design ancestor. For example a form `TForm2` inherited from a form `TForm1`. `TForm1` and all its components are copied to `TForm2`. `TForm2` and all its inherited components have `csAncestor` set. Only differences between `TForm1` and `TForm2` are stored in the stream of `TForm2`. The child components of a frame put onto a form have `csAncestor` too.

csInline The component is a nested top level component. For example a frame on a form. The children of the frame do not have `csInline`, unless they are other frames.

csDesignInstance The component is designed (`csDesigning`) and is a root component, meaning it has no owner (`Owner=nil`).

csFixups The component's references to other components are being fixed. While reading a component from stream, it can happen that the stream contains a component reference property with a name of a component that was not yet created and read from the stream. Such properties are saved, and the missing references are resolved when the complete stream was read. This resolving step is called fixing up references, and the `csFixups` flag is set during this step.

csFreeNotification This flag indicates that the component has free notifications registered with `TComponent.FreeNotification` (372)

```
TComponentStyle= Set of (csInheritable,csCheckPropAvail,csSubComponent
,
                        csTransient)
```

Table 4.7: Enumeration values for type

Value	Explanation
<code>csCheckPropAvail</code>	??
<code>csInheritable</code>	The component can be on inherited forms.
<code>csSubComponent</code>	Subcomponent - streamed as part of the owning component
<code>csTransient</code>	Transient component

Describes the style of the component.

```
TCreateComponentEvent = procedure(Reader: TReader;
  ComponentClass: TComponentClass;
  var Component: TComponent) of object
```

Event handler type, occurs when a component instance must be created when a component is read from a stream.

```
TDataModuleClass = class of TDataModule
```

`TDataModuleClass` defines the class pointer for `TDataModule` (382).

`TDuplicates = Types.TDuplicates`

Type to describe what to do with duplicate values in a `TStringlist` (463).

`TExceptionClass = class of Exception`

`TExceptionClass` is the class pointer for the `Exception` (1808) class, defined in the `SysUtils` (1615) unit.

`TFilerFlag = (ffInherited, ffChildPos, ffInline)`

Table 4.8: Enumeration values for type `TFilerFlag`

Value	Explanation
<code>ffChildPos</code>	The position of the child on it's parent is included.
<code>ffInherited</code>	Stored object is an inherited object.
<code>ffInline</code>	Used for frames.

The `TFiler` class uses this enumeration type to decide whether the streamed object was streamed as part of an inherited form or not.

`TFilerFlags = Set of TFilerFlag`

Set of `TFilerFlag` (273)

```
TFindAncestorEvent = procedure(Writer: TWriter; Component: TComponent
;
                                const Name: string;
    var Ancestor: TComponent;
    var RootAncestor: TComponent) of object
```

Event that occurs w

```
TFindComponentClassEvent = procedure(Reader: TReader;
    const ClassName: string;
    var ComponentClass: TComponentClass)
of object
```

Event handler type, occurs when a component class pointer must be found when reading a component from a stream.

`TFindGlobalComponent = function(const Name: string) : TComponent`

`TFindGlobalComponent` is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name `Name`, or `Nil` if none is found.

The variable `FindGlobalComponent` (290) is a callback of type `TFindGlobalComponent`. It can be set by the IDE when an unknown reference is found, to offer the designer to redirect the link to a new component.

```

TFindMethodEvent = procedure(Reader: TReader; const MethodName: string
;
                                var Address: CodePointer;
var Error: Boolean) of object

```

If a `TReader` (433) instance needs to locate a method and it doesn't find it in the streamed form, then the `OnFindMethod` (444) event handler will be called, if one is installed. This event can be assigned in order to use different locating methods. If a method is found, then its address should be returned in `Address`. The `Error` should be set to `True` if the reader should raise an exception after the event was handled. If it is set to `False` no exception will be raised, even if no method was found. On entry, `Error` will be set to `True`.

```

TFPObservedOperation = (ooChange, ooFree, ooAddItem, ooDeleteItem, ooCustom
)

```

Table 4.9: Enumeration values for type `TFPObservedOperation`

Value	Explanation
<code>ooAddItem</code>	An item is added to the observed object (generally a list).
<code>ooChange</code>	The observed object has changed.
<code>ooCustom</code>	Custom event.
<code>ooDeleteItem</code>	An item is deleted from the observed object (generally a list).
<code>ooFree</code>	The observed object is being freed.

`TFPObservedOperation` enumerates the possible operations that can be reported to an observer. Which of these operations is reported depends on the implementation of the observed object.

```

TGetChildProc = procedure(Child: TComponent) of object

```

Callback used when obtaining child components.

```

TGetStrProc = procedure(const S: string) of object

```

This event is used as a callback to retrieve string values. It is used, among other things, to pass along string properties in property editors.

```

THandle = System.THandle

```

This type is used as the handle for `THandleStream` (399) stream descendants

```

THelpContext = - MaxLongint..MaxLongint

```

Range type to specify help contexts.

```

THelpEvent = function(Command: Word; Data: LongInt;
var CallHelp: Boolean) : Boolean of object

```

This event is used for display of online help.

```

THelpType = (htKeyword, htContext)

```

Table 4.10: Enumeration values for type THelpType

Value	Explanation
htContext	Help type: Context ID help.
htKeyword	Help type: Keyword help

Enumeration type specifying the kind of help requested.

```
TIdentToInt = function(const Ident: string; var Int: LongInt) :
    Boolean
```

TIdentToInt is a callback used to look up identifiers (Ident) and return an integer value corresponding to this identifier (Int). The callback should return True if a value corresponding to integer Ident was found, False if not.

A callback of type TIdentToInt should be specified when an integer is registered using the RegisterIntegerConsts (299) call.

```
TInitComponentHandler = function(Instance: TComponent;
    RootAncestor: TClass) : Boolean
```

TInitComponentHandler is a callback type. It is used in the InitInheritedComponent (293) call to initialize a component. Callbacks of this type are registered with the RegisterInitComponentHandler (298) call.

```
TIntToIdent = function(Int: LongInt; var Ident: string) : Boolean
```

TIntToIdent is a callback used to look up integers (Ident) and return an identifier (Ident) that can be used to represent this integer value in an IDE. The callback should return True if a value corresponding to integer Ident was found, False if not.

A callback of type TIntToIdent should be specified when an integer is registered using the RegisterIntegerConsts (299) call.

```
TLeftRight = taLeftJustify..taRightJustify
```

TLeftRight is a subrange type based on the TAlignment (269) enumerated type. It contains only the left and right alignment constants.

```
TListAssignOp = (laCopy, laAnd, laOr, laXor, laSrcUnique, laDestUnique
    )
```

Table 4.11: Enumeration values for type TListAssignOp

Value	Explanation
laAnd	Remove all elements not first second list
laCopy	Clear list and copy all strings from second list.
laDestUnique	Keep all elements that exists only in list2
laOr	Add all elements from second (and optional third) list, eliminate duplicates
laSrcUnique	Just keep all elements that exist only in source list
laXor	Remove elements in second lists, Add all elements from second list not in first list

This type determines what operation `TList.Assign` (414) or `TFPList.assign` (395) performs.

```
TListCallback = Types.TListCallback
```

`TListCallback` is the method callback prototype for the function that is passed to the `TFPList.ForEachCall` (396) call. The `data` argument will be filled with all the pointers in the list (one per call) and the `arg` argument is the `Arg` argument passed to the `ForEachCall` call.

```
TListNotification = (lnAdded, lnExtracted, lnDeleted)
```

Table 4.12: Enumeration values for type `TListNotification`

Value	Explanation
<code>lnAdded</code>	List change notification: Element added to the list.
<code>lnDeleted</code>	List change notification: Element deleted from the list.
<code>lnExtracted</code>	List change notification: Element extracted from the list.

Kind of list notification event.

```
TListSortCompare = function(Item1: Pointer; Item2: Pointer) :  
    Integer
```

Callback type for the list sort algorithm.

```
TListStaticCallback = Types.TListStaticCallback
```

`TListCallback` is the procedural callback prototype for the function that is passed to the `TFPList.ForEachCall` (396) call. The `data` argument will be filled with all the pointers in the list (one per call) and the `arg` argument is the `Arg` argument passed to the `ForEachCall` call.

```
TMissingNameValueSeparatorAction = (mnvaValue, mnvaName, mnvaEmpty,  
    mnvaError)
```

Table 4.13: Enumeration values for type `TMissingNameValueSeparatorAction`

Value	Explanation
<code>mnvaEmpty</code>	Consider it an empty line
<code>mnvaError</code>	Raise an exception if the Name=Value functionality is used.
<code>mnvaName</code>	Consider the line a name with empty value
<code>mnvaValue</code>	Consider the line a value

`TMissingNameValueSeparatorAction` is the type of the `TStrings.MissingNameValueSeparatorAction` (487) property and determines what to do if in a `TStrings` (468) descendent the `NameValueSeparator` (488) is missing. It can have the following values:

mnvaValue Consider the line a value

mnvaName Consider the line a name with empty value

mnvaEmpty Consider it an empty line

mnvaError Raise an exception if the Name=Value functionality is used.

TMissingNameValueSeparatorActions = Set of
TMissingNameValueSeparatorAction

TMissingNameValueSeparatorActions is simply a set of TMissingNameValueSeparatorAction (276) values.

TNotifyCallBack = procedure(Sender: TObject; AData: Pointer)

TNotifyCallBack is used to notify about thread termination when using static callbacks. When called, the Sender will contain the thread which is terminating, and AData is the AData parameter passed to TThread.ExecuteInThread (504).

TNotifyEvent = procedure(Sender: TObject) of object

Most event handlers are implemented as a property of type TNotifyEvent. When this is set to a certain method of a class, when the event occurs, the method will be called, and the class that generated the event will pass itself along as the Sender argument.

TObjectTextEncoding = (oteDFM, oteLFM)

Table 4.14: Enumeration values for type TObjectTextEncoding

Value	Explanation
oteDFM	Characters are in DFM (Delphi) format: widechar encoded.
oteLFM	Characters are in LFM format: UTF-8 encoded.

TObjectTextEncoding is an enumerated type which denotes the encoding of non ASCII characters in an object stream file. It is needed for correct encoding when reading string values in the text stream.

TOperation = (opInsert, opRemove)

Table 4.15: Enumeration values for type TOperation

Value	Explanation
opInsert	A new component is being inserted in the child component list.
opRemove	A component is being removed from the child component list.

Operation of which a component is notified.

TPersistentClass = class of TPersistent

TPersistentClass is the class reference type for the TPersistent (428) class.

```
TPoint = Types.TPoint
```

This record describes a coordinate. It is used to handle the [Top \(369\)](#) and [Left \(369\)](#) properties of [TComponent \(369\)](#).

X represents the X-Coordinate of the point described by the record. Y represents the Y-Coordinate of the point described by the record.

```
TPointerList = Array[0..MaxListSize-1] of Pointer
```

Type for an Array of pointers.

```
TPropertyNotFoundEvent = procedure(Reader: TReader;
  Instance: TPersistent;
  var PropName: string;
  IsPath: Boolean;
  var
    Handled: Boolean;
    var Skip: Boolean
  ) of object
```

[TPropertyNotFoundEvent](#) is the prototype for the [TReader.OnPropertyNotFound \(443\)](#) event. [Reader](#) is the sender of the event, [Instance](#) is the instance that is being streamed. [PropInfo](#) is a pointer to the RTTI information for the property being read. [Handled](#) should be set to [True](#) if the handler redirected the unknown property successfully, and [Skip](#) should be set to [True](#) if the value should be skipped. [IsPath](#) determines whether the property refers to a sub-property.

```
TReadComponentsProc = procedure(Component: TComponent) of object
```

Callback type when reading a component from a stream

```
TReaderError = procedure(Reader: TReader; const Message: string;
  var Handled: Boolean) of object
```

Event handler type, called when an error occurs during the streaming.

```
TReaderProc = procedure(Reader: TReader) of object
```

The [TReaderProc](#) reader procedure is a callback procedure which will be used by a [TPersistent \(428\)](#) descendant to read user properties from a stream during the streaming process. The [Reader](#) argument is the writer object which can be used read properties from the stream.

```
TReadWriteStringPropertyEvent = procedure(Sender: TObject;
  const Instance: TPersistent;
  PropInfo: PPropInfo;
  var Content: string) of
  object
```

[TReadWriteStringPropertyEvent](#) is the prototype for the [TReader.OnReadStringProperty \(445\)](#) event handler. [Reader](#) is the sender of the event, [Instance](#) is the instance that is being streamed. [PropInfo](#) is a pointer to the RTTI information for the property being read. [Content](#) is the string as it was read from the stream.

```
TRect = Types.TRect
```

`TRect` describes a rectangle in space with its upper-left (in `(Top,Left>)`) and lower-right (in `(Bottom,Right)`) corners.

```
TReferenceNameEvent = procedure(Reader: TReader; var Name: string
)
                        of object
```

Occurs when a named object needs to be looked up.

```
TSeekOrigin = (soBeginning, soCurrent, soEnd)
```

Table 4.16: Enumeration values for type `TSeekOrigin`

Value	Explanation
<code>soBeginning</code>	Offset is interpreted relative to the start of the stream.
<code>soCurrent</code>	Offset is interpreted relative to the current position in the stream.
<code>soEnd</code>	Offset is interpreted relative to the end of the stream.

Specifies the origin of the `TStream.Seek` (450) method.

```
TSetMethodPropertyEvent = procedure(Reader: TReader;
  Instance: TPersistent;
  PropInfo: PPropInfo;
  const TheMethodName: string;
  var Handled: Boolean) of object
```

`TSetMethodPropertyEvent` is the prototype for the `TReader.OnSetMethodProperty` (444) event. `Reader` is the sender of the event, `Instance` is the instance that is being streamed. `PropInfo` is a pointer to the RTTI information for the property being read, and `TheMethodName` is the name of the method that the property should be set to. `Handled` should be set to `True` if the handler set the property successfully.

```
TSetNameEvent = procedure(Reader: TReader; Component: TComponent;
  var Name: string) of object
```

Occurs when the reader needs to set a component's name.

```
TShiftState = Set of TShiftStateEnum
```

This type is used when describing a shortcut key or when describing what special keys are pressed on a keyboard when a key event is generated.

The set contains the special keys that can be used in combination with a 'normal' key.

```
TShiftStateEnum = (ssShift, ssAlt, ssCtrl, ssLeft, ssRight, ssMiddle,
  ssDouble, ssMeta, ssSuper, ssHyper, ssAltGr, ssCaps
  , ssNum,
                        ssScroll, ssTriple, ssQuad, ssExtral, ssExtra2
  )
```


Table 4.17: Enumeration values for type TShiftStateEnum

Value	Explanation
ssAlt	Alt key pressed
ssAltGr	Alt-GR key pressed.
ssCaps	Caps lock key pressed
ssCtrl	Ctrl key pressed
ssDouble	Double mouse click.
ssExtra1	Extra key 1
ssExtra2	Extra key 2
ssHyper	Hyper key pressed.
ssLeft	Left mouse button pressed.
ssMeta	Meta key pressed.
ssMiddle	Middle mouse button pressed.
ssNum	Num lock key pressed
ssQuad	Quadruple mouse click
ssRight	Right mouse button pressed.
ssScroll	Scroll lock key pressed
ssShift	Shift key pressed
ssSuper	Super key pressed.
ssTriple	Triple mouse click

Keyboard/Mouse shift state enumerator

`TShortCut = (Word) .. (Word)`

Enumeration type to identify shortcut key combinations.

`TSmallPoint = Types.TSmallPoint`

Same as `TPoint` (278), only the X and Y ranges are limited to 2-byte integers instead of 4-byte integers.

`TStreamOwnership = (soReference, soOwned)`

Table 4.18: Enumeration values for type TStreamOwnership

Value	Explanation
soOwned	Stream is owned: it will be freed when the adapter is freed.
soReference	Stream is referenced only, it is not freed by the adapter

The ownership of a streamadapter determines what happens with the stream on which a `TStreamAdapter` (458) acts, when the adapter is freed.

`TStreamProc = procedure(Stream: TStream) of object`

Procedure type used in streaming.

`TStringItemList = Array[0..MaxListSize] of TStringItem`

This declaration is provided for Delphi compatibility, it is not used in Free Pascal.

```
TStringListSortCompare = function(List: TStringList; Index1: Integer
;
                                Index2: Integer) : Integer
```

Callback type used in stringlist compares.

```
TStringsClass = class of TStrings
```

TStringsClass is the class of TStrings (468). It is provided for convenience.

```
TStringsFilterMethod = function(const s: string) : Boolean of
object
```

TStringsFilterMethod is the prototype for the callback in TStrings.Filter (477). Return True if the string S must be included in the TStrings.Filter (477) result, False if it must be excluded.

```
TStringsForEachMethod = procedure(const CurrentValue: string) of
object
```

TStringsForEachMethod is a callback signature for TStrings.ForEach (477). It gets passed the string value in CurrentValue.

```
TStringsForEachMethodEx = procedure(const CurrentValue: string;
const index: Integer) of
object
```

TStringsForEachMethodEx is a callback signature for TStrings.ForEach (477). It gets passed the string value in CurrentValue, string index in Index.

```
TStringsForEachMethodExObj = procedure(const CurrentValue: string
;
                                const index: Integer;
Obj: TObject) of object
```

TStringsForEachMethodExObj is a callback signature for TStrings.ForEach (477). It gets passed the string value in CurrentValue, string index in Index and associated object in Obj.

```
TStringsMapMethod = function(const s: string) : string of object
```

TStringsMapMethod is the prototype for the callback in TStrings.Map (481). The method must return the mapped value for value S.

```
TStringsOption = (soStrictDelimiter, soWriteBOM, soTrailingLineBreak
,
soUseLocale, soPreserveBOM)
```

Table 4.19: Enumeration values for type TStringsOption

Value	Explanation
soPreserveBOM	If this option is enabled, TStrings.WriteBOM (492) is set in TStrings.LoadFromStream (481) or TStrings.LoadFromFile (480).
soStrictDelimiter	See TStrings.StrictDelimiter (490).
soTrailingLineBreak	See TStrings.TrailingLineBreak (489).
soUseLocale	See TStrings.UseLocale (491).
soWriteBOM	See TStrings.WriteBOM (492).

TStringsOption is the type used in the TStrings.Options (489) set property, and it lists various strings options. It has the following values:

soStrictDelimiter See TStrings.StrictDelimiter (490).

soWriteBOM See TStrings.WriteBOM (492).

soTrailingLineBreak See TStrings.TrailingLineBreak (489).

soUseLocale See TStrings.UseLocale (491).

soPreserveBOM If this option is enabled, TStrings.WriteBOM (492) is set in TStrings.LoadFromStream (481) or TStrings.LoadFromFile (480) according to BOM presence in the loaded file.

TStringsOptions = Set of TStringsOption

TStringsOptions is the set type for enumeration TStringsOption (281).

```
TStringsReduceMethod = function(const s1: string; const s2: string
)
: string of object
```

TStringsReduceMethod is the prototype for the callback in TStrings.Reduce (482). The method must return the reduced value for values S1 and S2. On every iteration S1 will contain the result of the previous iteration.

TStringsSortStyle = (sslNone, sslUser, sslAuto)

Table 4.20: Enumeration values for type TStringsSortStyle

Value	Explanation
sslAuto	The TStrings instance keeps the strings sorted.
sslNone	The strings are not sorted
sslUser	The strings are kept sorted by the user.

TStringsSortStyle is the type used in the TStringList.SortStyle (468) property, and describes how the strings are sorted when the TStringList.Sorted (466) property is True. It has the following values:

sslNone The strings are not sorted

sslUser The strings are kept sorted by the user.

sslAuto The TStrings instance keeps the strings sorted.

TStringsSortStyles = Set of TStringsSortStyle

TStringsSortStyles is the set type for enumeration TStringsSortStyle (282).

TSynchronizeProcVar = procedure

Synchronize callback type

TThreadExecuteCallBack = procedure(AData: Pointer)

TThreadExecuteCallBack is the signature of the static procedure to be used when executing something in a thread using TThread.ExecuteInThread (504) when no status reporting is required.

TThreadExecuteHandler = TThreadMethod

TThreadExecuteHandler is the signature of the method to be used when executing something in a thread using TThread.ExecuteInThread (504) when no status reporting is required.

```
TThreadExecuteStatusCallBack = procedure(AData: Pointer;
    ReportStatus: TThreadReportStatus
)
```

TThreadExecuteStatusCallBack is the signature of a procedure to be used when executing something in a thread using TThread.ExecuteInThread (504) when status reporting is required.

On entry in the method, AData is the AData parameter passed to TThread.ExecuteInThread (504). ReportStatus is passed to the method, and the threaded procedure can call ReportStatus at various stages to report about the status of the method: The status will be reported to the main thread using TThread.synchronize (500), so calls to ReportStatus will be blocked as long as the status was not reported.

```
TThreadExecuteStatusHandler = procedure
    (ReportStatus: TThreadReportStatus)
    of object
```

TThreadExecuteStatusHandler is the signature of the method to be used when executing something in a thread using TThread.ExecuteInThread (504) when status reporting is required.

On entry in the method, ReportStatus is passed to the method, and the method can call ReportStatus at various stages to report about the status of the method: The status will be reported to the main thread using TThread.synchronize (500), and calls ReportStatus will be blocked as long as the status was not reported.

TThreadMethod = procedure of object

Procedure variable used when synchronizing threads.

```
TThreadPriority = (tpIdle, tpLowest, tpLower, tpNormal, tpHigher, tpHighest
    ,
    tpTimeCritical)
```

Table 4.21: Enumeration values for type TThreadPriority

Value	Explanation
tpHigher	Thread runs at high priority
tpHighest	Thread runs at highest possible priority.
tpIdle	Thread only runs when other processes are idle.
tpLower	Thread runs at a lower priority.
tpLowest	Thread runs at the lowest priority.
tpNormal	Thread runs at normal process priority.
tpTimeCritical	Thread runs at realtime priority.

Enumeration specifying the priority at which a thread runs.

`TThreadReportStatus = procedure(const status: string) of object`

`TThreadReportStatus` is the callback prototype for the `TThread.ExecuteInThread` (504) method. This callback is used to report thread status to the main thread: the `Status` string can be used to report the status of thread execution.

`TThreadStatusNotifyCallBack = procedure(Sender: TThread;
AData: Pointer;
const status: string)`

`TThreadStatusNotifyCallBack` is the signature of the callback to be provided when executing a static procedure in a thread using `TThread.ExecuteInThread` (504) when status reporting is required.

This callback will be called in the main thread. When called, it has the thread whose status is reported in `Sender`, `AData` is the `AData` parameter passed to `TThread.ExecuteInThread` (504). Finally, the status message in `ReportStatus` is passed to the callback.

Note that the thread reporting its status is blocked while the callback is being handled: The status is be reported to the main thread using `TThread.synchronize` (500).

`TThreadStatusNotifyEvent = procedure(Sender: TThread;
const status: string) of object`

`TThreadStatusNotifyEvent` is the signature of the method to be provided when executing something in a thread using `TThread.ExecuteInThread` (504) when status reporting is required.

This event handler will be called in the main thread. When called, it has the thread whose status is reported in `Sender`, and the status message in `ReportStatus` is passed to the method.

Note that the thread reporting its status is blocked while the callback is being handled: The status is be reported to the main thread using `TThread.synchronize` (500).

`TTopBottom = taAlignTop..taAlignBottom`

`TTopBottom` is a subrange of `TVerticalAlignment` (285) that excludes the vertically centered alignment value.

`TValueType = (vaNull, vaList, vaInt8, vaInt16, vaInt32, vaExtended, vaString
,`

```

    vaIdent, vaFalse, vaTrue, vaBinary, vaSet, vaLString, vaNil
,
    vaCollection, vaSingle, vaCurrency, vaDate, vaWString
, vaInt64,
    vaUTF8String, vaUString, vaQWord)

```

Table 4.22: Enumeration values for type TValueType

Value	Explanation
vaBinary	Binary data follows.
vaCollection	Collection follows
vaCurrency	Currency value follows
vaDate	Date value follows
vaExtended	Extended value.
vaFalse	Boolean False value.
vaIdent	Identifier.
vaInt16	Integer value, 16 bits long.
vaInt32	Integer value, 32 bits long.
vaInt64	Integer value, 64 bits long.
vaInt8	Integer value, 8 bits long.
vaList	Identifies the start of a list of values
vaLString	Ansistring data follows.
vaNil	Nil pointer.
vaNull	Empty value. Ends a list.
vaQWord	QWord (64-bit word) value
vaSet	Set data follows.
vaSingle	Single type follows.
vaString	String value.
vaTrue	Boolean True value.
vaUString	UnicodeString value
vaUTF8String	UTF8 encoded Unicode string.
vaWString	Widestring value follows.

Enumerated type used to identify the kind of streamed property

```
TVerticalAlignment = (taAlignTop, taAlignBottom, taVerticalCenter)
```

Table 4.23: Enumeration values for type TVerticalAlignment

Value	Explanation
taAlignBottom	Align vertically to the bottom
taAlignTop	Align vertically to the top
taVerticalCenter	Align vertically centered.

TVerticalAlignment can be used to specify a vertical alignment. It is not used in the classes unit, and is provided for symmetry with TAlignment (269). It can have the following values:

taAlignTop Align vertically to the top

taAlignBottom Align vertically to the bottom

taVerticalCenter Align vertically centered.

```
TWriteMethodPropertyEvent = procedure(Writer: TWriter;
  Instance: TPersistent;
  PropInfo: PPropInfo;
  const MethodValue: TMethod;
  const DefMethodValue: TMethod;
  var Handled: Boolean) of object
```

TWriteMethodPropertyEvent is the prototype for the TWriter.OnWriteMethodProperty (522) event. Writer is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being written, and MethodValue is the value of the method that the property was set to. DefMethodCodeValue is set to the default value of the property (Nil or the parent value). Handled should be set to True if the handler set the property successfully.

```
TWriterProc = procedure(Writer: TWriter) of object
```

The TWriterProc writer procedure is a callback procedure which will be used by a TPersistent (428) descendant to write user properties from a stream during the streaming process. The Writer argument is the writer object which can be used write properties to the stream.

4.3.3 Variables

```
AddDataModule : procedure(DataModule: TDataModule) of object
```

AddDataModule can be set by an IDE or a streaming mechanism to receive notification when a new instance of a TDataModule (382) descendant is created.

```
ApplicationHandleException : procedure(Sender: TObject) of object
```

ApplicationHandleException can be set by an application object to handle any exceptions that may occur when a TDataModule (382) is created.

```
ApplicationShowException : procedure(E: Exception) of object
```

Unused.

```
CreateVCLComObjectProc : procedure(Component: TComponent) = Nil
```

CreateVCLComObjectProc is called by TComponent if it needs to create a IVCLComObject interface for itself (when the ComObject property is read). It passes itself as the Component parameter.

```
GlobalNameSpace : IReadWriteSync
```

An interface protecting the global namespace. Used when reading/writing to the global namespace list during streaming of forms.

```
MainThreadID : TThreadID
```

ID of main thread. Unused at this point.

```
RegisterComponentsProc : procedure(const Page: string;
    ComponentClasses: Array of TComponentClass)
```

RegisterComponentsProc can be set by an IDE to be notified when new components are being registered. Application programmers should never have to set RegisterComponentsProc

```
RegisterNoIconProc : procedure(ComponentClasses: Array of TComponentClass
    )
```

RegisterNoIconProc can be set by an IDE to be notified when new components are being registered, and which do not need an Icon in the component palette. Application programmers should never have to set RegisterComponentsProc

```
RemoveDataModule : procedure(DataModule: TDataModule) of object
```

RemoveDataModule can be set by an IDE or a streaming mechanism to receive notification when an instance of a TDataModule (382) descendant is freed.

```
WakeMainThread : TNotifyEvent = Nil
```

WakeMainThread is a handler, which, when set, is called by the TThread.Synchronize (500) routine to signal the main thread that a synchronization routine is waiting in the queue.

This handler is by default empty. An actual implementation depends on the main program logic (usually an event loop) and must be provided by the event loop logic: the event loop will normally call CheckSynchronize (288) at regular intervals. The WakeMainThread can make sure this happens as soon as possible.

While this handle should alert the main program thread that a thread is waiting for synchronization, the call is executed by the thread, and should therefore NOT synchronize the thread, but should somehow signal the main thread that a thread is waiting for synchronization. For example, by sending a message.

4.4 Procedures and functions

4.4.1 ActivateClassGroup

Synopsis: Activates a class group

Declaration: `function ActivateClassGroup(AClass: TPersistentClass) : TPersistentClass`

Visibility: default

Description: ActivateClassGroup activates the group of classes to which AClass belongs. The function returns the class that was last used to activate the class group.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

Errors: If AClass does not belong to a class group, an exception is raised.

See also: StartClassGroup (300), GroupDescendentsWith (292), ClassGroupOf (289)

4.4.2 BeginGlobalLoading

Synopsis: Not yet implemented

Declaration: `procedure BeginGlobalLoading`

Visibility: default

Description: Not yet implemented

4.4.3 BinToHex

Synopsis: Convert a binary buffer to a hexadecimal string

Declaration: `procedure BinToHex(BinValue: PChar; HexValue: PChar;
BinBufSize: Integer)`

Visibility: default

Description: `BinToHex` converts the byte values in `BinValue` to a string consisting of 2-character hexadecimal strings in `HexValue`. `BufSize` specifies the length of `BinValue`, which means that `HexValue` must have size $2 * \text{BufSize}$.

For example a buffer containing the byte values 255 and 0 will be converted to FF00.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `HexToBin` ([292](#))

4.4.4 Bounds

Synopsis: Returns a `TRect` structure with the bounding rect of the given location and size.

Declaration: `function Bounds(ALeft: Integer; ATop: Integer; AWidth: Integer;
AHeight: Integer) : TRect`

Visibility: default

Description: `Bounds` returns a `TRect` ([279](#)) record with the given origin (`ALeft`, `ATop`) and dimensions (`AWidth`, `AHeight`) filled in. The bottom-right corner is calculated by adding `AWidth` to `ALeft` and `AHeight` to `ATop`. As a result, a rectangle with width/height set to 0 is exactly 1 pixel.

See also: `Rect` ([297](#))

4.4.5 CheckSynchronize

Synopsis: Check whether there are any synchronize calls in the synchronize queue.

Declaration: `function CheckSynchronize(timeout: LongInt) : Boolean`

Visibility: default

Description: `CheckSynchronize` should be called regularly by the main application thread to handle any `TThread.Synchronize` ([500](#)) calls that may be waiting for execution by the main thread. If any such calls are waiting for execution by the main thread, they are executed at once, in the order that they were scheduled.

The function returns `True` if any `Synchronize` method was executed.

`TimeOut` is the maximum amount of time (in milliseconds) that the `CheckSynchronize` routine will wait for synchronisation requests to appear in the queue.

Calling this routine more often will ensure that synchronize requests are handled faster.

This routine may not be called from any thread other than the main thread, as it will execute the waiting requests.

Threads may call the `WakeMainThread` (287) to signal the main thread that the synchronisation queue contains items, and thus speed up the execution of the synchronize calls.

See also: `TThread.Synchronize` (500), `WakeMainThread` (287)

4.4.6 ClassGroupOf

Synopsis: Returns the class group to which an instance or class belongs

Declaration: `function ClassGroupOf(AClass: TPersistentClass) : TPersistentClass`
`function ClassGroupOf(Instance: TPersistent) : TPersistentClass`

Visibility: default

Description: `ClassGroupOf` returns the class group to which `AClass` or `Instance` belongs.

Errors: The result is `Nil` if no matching class group is found.

See also: `StartClassGroup` (300), `ActivateClassGroup` (287), `GroupDescendentsWith` (292)

4.4.7 CollectionsEqual

Synopsis: Returns `True` if two collections are equal.

Declaration: `function CollectionsEqual(C1: TCollection; C2: TCollection) : Boolean`
`function CollectionsEqual(C1: TCollection; C2: TCollection;`
`Owner1: TComponent; Owner2: TComponent)`
`: Boolean`

Visibility: default

Description: `CollectionsEqual` is not yet implemented. It simply returns `False`

4.4.8 EndGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure EndGlobalLoading`

Visibility: default

Description: Not yet implemented.

4.4.9 ExtractStrings

Synopsis: Split a string in different words.

Declaration: `function ExtractStrings(Separators: TSysCharSet;`
`WhiteSpace: TSysCharSet; Content: PChar;`
`Strings: TStrings; AddEmptyStrings: Boolean)`
`: Integer`

Visibility: default

Description: `ExtractStrings` splits `Content` (a null-terminated string) into words, and adds the words to the `Strings` stringlist. The words are separated by `Separators` and any characters in whitespace are stripped from the strings. The space and CR/LF characters are always considered whitespace.

Errors: No length checking is performed on `Content`. If no null-termination character is present, an access violation may occur. Likewise, if `Strings` is not valid, an access violation may occur.

4.4.10 FindClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function FindClass(const AClassName: string) : TPersistentClass`

Visibility: default

Description: `FindClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, an exception is raised.

The `GetClass` (291) function does not raise an exception when it does not find the class, but returns a `Nil` pointer instead.

See also: `RegisterClass` (297), `GetClass` (291)

4.4.11 FindGlobalComponent

Synopsis: Callback used when a component must be found.

Declaration: `function FindGlobalComponent(const Name: string) : TComponent`

Visibility: default

Description: `FindGlobalComponent` is a callback of type `TFindGlobalComponent` (273). It can be set by the IDE when an unknown reference is found, to offer the user to redirect the link to a new component.

It is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name `Name`, or `Nil` if none is found.

See also: `TFindGlobalComponent` (273)

4.4.12 FindIdentToInt

Synopsis: Return the string to integer converter for an integer type

Declaration: `function FindIdentToInt(AIntegerType: Pointer) : TIdentToInt`

Visibility: default

Description: `FindIdentToInt` returns the handler that handles the conversion of a string representation to an integer that can be used in component streaming, when `IdentToInt` (293) is called.

Errors: `Nil` is returned if no handler is registered for the given type.

4.4.13 FindIntToIdent

Synopsis: Return the integer to string converter for an integer type

Declaration: `function FindIntToIdent (AIntegerType: Pointer) : TIntToIdent`

Visibility: default

Description: `FindIntToIdent` returns the handler that handles the conversion of an integer to a string representation that can be used in component streaming, when `IntToIdent` (293) is called.

Errors: `Nil` is returned if no handler is registered for the given type.

See also: `IntToIdent` (293), `TIntToIdent` (275), `FindIdentToInt` (290)

4.4.14 FindNestedComponent

Synopsis: Finds the component with name path starting at the indicated root component.

Declaration: `function FindNestedComponent (Root: TComponent; APath: string;
CStyle: Boolean) : TComponent`

Visibility: default

Description: `FindNestedComponent` will descend through the list of owned components (starting at `Root`) and will return the component whose name path matches `NamePath`. As a path separator the characters `.` (dot), `-` (dash) and `>` (greater than) can be used

See also: `GlobalFixupReferences` (292)

4.4.15 GetClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function GetClass (const AClassName: string) : TPersistentClass`

Visibility: default

Description: `GetClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, `Nil` is returned.

The `FindClass` (290) function will raise an exception if it does not find the class.

See also: `RegisterClass` (297), `GetClass` (291)

4.4.16 GetFixupInstanceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component, whose reference contains `ReferenceRootName`

Declaration: `procedure GetFixupInstanceNames (Root: TComponent;
const ReferenceRootName: string;
Names: TStrings)`

Visibility: default

Description: `GetFixupInstanceNames` examines the list of unresolved references and returns the names of classes that contain unresolved references to the `Root` component in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupReferenceNames` (292), `GlobalFixupReferences` (292)

4.4.17 GetFixupReferenceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component.

Declaration: `procedure GetFixupReferenceNames (Root: TComponent; Names: TStrings)`

Visibility: `default`

Description: `GetFixupReferenceNames` examines the list of unresolved references and returns the names of properties that must be resolved for the component `Root` in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupInstanceNames` ([291](#)), `GlobalFixupReferences` ([292](#))

4.4.18 GlobalFixupReferences

Synopsis: Called to resolve unresolved references after forms are loaded.

Declaration: `procedure GlobalFixupReferences`

Visibility: `default`

Description: `GlobalFixupReferences` runs over the list of unresolved references and tries to resolve them. This routine should under normal circumstances not be called in an application programmer's code. It is called automatically by the streaming system after a component has been instantiated and its properties read from a stream. It will attempt to resolve references to other global components.

See also: `GetFixupReferenceNames` ([292](#)), `GetFixupInstanceNames` ([291](#))

4.4.19 GroupDescendentsWith

Synopsis: Provided for Delphi compatibility

Declaration: `procedure GroupDescendentsWith (AClass: TPersistentClass;
AClassGroup: TPersistentClass)`

Visibility: `default`

Description: `GroupDescendentsWith` exists for Delphi compatibility, it doesn't actually do anything in Free Pascal.

See also: `RegisterClasses` ([298](#))

4.4.20 HexToBin

Synopsis: Convert a hexadecimal string to a binary buffer

Declaration: `function HexToBin (HexValue: PChar; BinValue: PChar; BinBufSize: Integer)
: Integer`

Visibility: `default`

Description: `HexToBin` scans the hexadecimal string representation in `HexValue` and transforms every 2 character hexadecimal number to a byte and stores it in `BinValue`. The buffer size is the size of the binary buffer. Scanning will stop if the size of the binary buffer is reached or when an invalid character is encountered. The return value is the number of stored bytes.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `BinToHex` ([288](#))

4.4.21 IdentToInt

Synopsis: Looks up an integer value in a integer-to-identifier map list.

Declaration: `function IdentToInt(const Ident: string; out Int: LongInt;
const Map: Array of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IdentToInt` searches `Map` for an entry whose `Name` field matches `Ident` and returns the corresponding integer value in `Int`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: [TIdentToInt \(275\)](#), [TIntToIdent \(275\)](#), [IntToIdent \(293\)](#), [TIdentMapEntry \(302\)](#)

4.4.22 InitComponentRes

Synopsis: Provided for Delphi compatibility only

Declaration: `function InitComponentRes(const ResName: string; Instance: TComponent)
: Boolean`

Visibility: default

Description: This function is provided for Delphi compatibility. It always returns `false`.

See also: [ReadComponentRes \(296\)](#)

4.4.23 InitInheritedComponent

Synopsis: Initializes a component descending from `RootAncestor`

Declaration: `function InitInheritedComponent(Instance: TComponent;
RootAncestor: TClass) : Boolean`

Visibility: default

Description: `InitInheritedComponent` should be called from a constructor to read properties of the component `Instance` from the streaming system. The `RootAncestor` class is the root class from which `Instance` is a descendant. This must be one of `TDatamodule`, `TCustomForm` or `TFrame`. The function returns `True` if the properties were successfully read from a stream or `False` if some error occurred.

See also: [ReadComponentRes \(296\)](#), [ReadComponentResEx \(296\)](#), [ReadComponentResFile \(296\)](#)

4.4.24 IntToIdent

Synopsis: Looks up an identifier for an integer value in a identifier-to-integer map list.

Declaration: `function IntToIdent(Int: LongInt; var Ident: string;
const Map: Array of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IdentToInt` searches `Map` for an entry whose `Value` field matches `Int` and returns the corresponding identifier in `Ident`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: [TIdentToInt \(275\)](#), [TIntToIdent \(275\)](#), [IdentToInt \(293\)](#), [TIdentMapEntry \(302\)](#)

4.4.25 InvalidPoint

Synopsis: Check whether a point is invalid.

Declaration: `function InvalidPoint (X: Integer; Y: Integer) : Boolean`
`function InvalidPoint (const At: TPoint) : Boolean`
`function InvalidPoint (const At: TSmallPoint) : Boolean`

Visibility: default

Description: `InvalidPoint` returns `True` if the X and Y coordinates (of the `TPoint` or `TSmallPoint` records, if one of these versions is used) are -1.

See also: `TPoint` (278), `TSmallPoint` (280), `PointsEqual` (295)

4.4.26 LineStart

Synopsis: Finds the start of a line in `Buffer` before `BufPos`.

Declaration: `function LineStart (Buffer: PChar; BufPos: PChar) : PChar`

Visibility: default

Description: `LineStart` reversely scans `Buffer` starting at `BufPos` for a linefeed character. It returns a pointer at the linefeed character.

4.4.27 NotifyGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure NotifyGlobalLoading`

Visibility: default

Description: Not yet implemented.

4.4.28 ObjectBinaryToText

Synopsis: Converts an object stream from a binary to a text format.

Declaration: `procedure ObjectBinaryToText (Input: TStream; Output: TStream;`
`Encoding: TObjectTextEncoding)`
`procedure ObjectBinaryToText (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectBinaryToText` reads an object stream in binary format from `Input` and writes the object stream in text format to `Output`. No components are instantiated during the process, this is a pure conversion routine.

See also: `ObjectTextToBinary` (295)

4.4.29 ObjectResourceToText

Synopsis: Converts an object stream from a (windows) resource to a text format.

Declaration: `procedure ObjectResourceToText (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectResourceToText` reads the resource header from the `Input` stream and then passes the streams to `ObjectBinaryToText` (294)

See also: `ObjectBinaryToText` (294), `ObjectTextToResource` (295)

4.4.30 ObjectTextToBinary

Synopsis: Converts an object stream from a text to a binary format.

Declaration: `procedure ObjectTextToBinary (Input: TStream; Output: TStream)`

Visibility: default

Description: Converts an object stream from a text to a binary format.

4.4.31 ObjectTextToResource

Synopsis: Converts an object stream from a text to a (windows) resource format.

Declaration: `procedure ObjectTextToResource (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectTextToResource` reads an object stream in text format from `Input` and writes a resource stream to `Output`.

Note that for the current implementation of this method in Free Pascal, the output stream should support positioning. (e.g. it should not be a pipe)

See also: `ObjectBinaryToText` (294), `ObjectResourceToText` (295)

4.4.32 Point

Synopsis: Returns a `TPoint` record with the given coordinates.

Declaration: `function Point (AX: Integer; AY: Integer) : TPoint`

Visibility: default

Description: `Point` returns a `TPoint` (278) record with the given coordinates `AX` and `AY` filled in.

See also: `TPoint` (278), `SmallPoint` (300), `Rect` (297), `Bounds` (288)

4.4.33 PointsEqual

Synopsis: Check whether two `TPoint` variables are equal.

Declaration: `function PointsEqual (const P1: TPoint; const P2: TPoint) : Boolean`
`function PointsEqual (const P1: TSmallPoint; const P2: TSmallPoint)`
`: Boolean`

Visibility: default

Description: `PointsEqual` compares the `P1` and `P2` points (of type `TPoint` (278) or `TSmallPoint` (280)) and returns `True` if the `X` and `Y` coordinates of the points are equal, or `False` otherwise.

See also: `TPoint` (278), `TSmallPoint` (280), `InvalidPoint` (294)

4.4.34 ReadComponentRes

Synopsis: Read component properties from a resource in the current module

Declaration: `function ReadComponentRes(const ResName: string; Instance: TComponent) : TComponent`

Visibility: default

Description: `ReadComponentRes` will read the component's properties from the resource `ResName` in the current module (always program module). It returns `Nil` if the resource was not found. It returns `Instance` if the resource was found and successfully applied to the component.

Errors: The function may raise an exception if the stream contains wrong data.

See also: `ReadComponentResEx` (296)

4.4.35 ReadComponentResEx

Synopsis: Read component properties from a resource in the specified module

Declaration: `function ReadComponentResEx(HInstance: THandle; const ResName: string) : TComponent`

Visibility: default

Description: `ReadComponentRes` will locate the resource `ResName` in instance `HInstance` (the current program, normally). It returns `Nil` if the resource was not found. It returns an instantiated component with all properties found in the stream, applied. This requires that the component is registered using `registerclass`.

Errors: The function may raise an exception if the stream contains wrong data.

See also: `ReadComponentRes` (296)

4.4.36 ReadComponentResFile

Synopsis: Read component properties from a specified resource file

Declaration: `function ReadComponentResFile(const FileName: string; Instance: TComponent) : TComponent`

Visibility: default

Description: `ReadComponentResFile` starts reading properties for `Instance` from the file `FileName`. It creates a filestream from `FileName` and then calls the `TStream.ReadComponentRes` (452) method to read the state of the component from the stream.

See also: `TStream.ReadComponentRes` (452), `WriteComponentResFile` (302)

4.4.37 Rect

Synopsis: Returns a `TRect` record with the given coordinates.

Declaration: `function Rect (ALeft: Integer; ATop: Integer; ARight: Integer;
ABottom: Integer) : TRect`

Visibility: default

Description: `Rect` returns a `TRect` (279) record with the given top-left (`ALeft`, `ATop`) and bottom-right (`ABottom`, `ARight`) corners filled in.

No checking is done to see whether the coordinates are valid.

See also: `TRect` (279), `Point` (295), `SmallPoint` (300), `Bounds` (288)

4.4.38 RedirectFixupReferences

Synopsis: Redirects references under the `root` object from `OldRootName` to `NewRootName`

Declaration: `procedure RedirectFixupReferences (Root: TComponent;
const OldRootName: string;
const NewRootName: string)`

Visibility: default

Description: `RedirectFixupReferences` examines the list of unresolved references and replaces references to a root object named `OldRootName` with references to root object `NewRootName`.

An application programmer should never need to call `RedirectFixupReferences`. This function can be used by an IDE to support redirection of broken component links.

See also: `RemoveFixupReferences` (300)

4.4.39 RegisterClass

Synopsis: Registers a class with the streaming system.

Declaration: `procedure RegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `RegisterClass` registers the class `AClass` in the streaming system. After the class has been registered, it can be read from a stream when a reference to this class is encountered.

See also: `RegisterClasses` (298), `RegisterClassAlias` (297), `RegisterComponents` (298), `UnregisterClass` (301)

4.4.40 RegisterClassAlias

Synopsis: Registers a class alias with the streaming system.

Declaration: `procedure RegisterClassAlias (AClass: TPersistentClass;
const Alias: string)`

Visibility: default

Description: `RegisterClassAlias` registers a class alias in the streaming system. If a reference to a class `Alias` is encountered in a stream, then an instance of the class `AClass` will be created instead by the streaming code.

See also: `RegisterClass` (297), `RegisterClasses` (298), `RegisterComponents` (298), `UnregisterClass` (301)

4.4.41 RegisterClasses

Synopsis: Registers multiple classes with the streaming system.

Declaration: `procedure RegisterClasses (AClasses: Array of TPersistentClass)`

Visibility: default

Description: `RegisterClasses` registers the specified classes `AClass` in the streaming system. After the classes have been registered, they can be read from a stream when a reference to this class is encountered.

See also: `RegisterClass` (297), `RegisterClassAlias` (297), `RegisterComponents` (298), `UnregisterClass` (301)

4.4.42 RegisterComponents

Synopsis: Registers components for the component palette.

Declaration: `procedure RegisterComponents (const Page: string;
ComponentClasses: Array of TComponentClass)`

Visibility: default

Description: `RegisterComponents` registers the component on the appropriate component page. The component pages can be used by an IDE to display the known components so an application programmer may pick and use the components in his programs.

`Registercomponents` inserts the component class in the correct component page. If the `RegisterComponentsProc` procedure is set, this is called as well. Note that this behaviour is different from Delphi's behaviour where an exception will be raised if the procedural variable is not set.

See also: `RegisterClass` (297), `RegisterNoIcon` (299)

4.4.43 RegisterFindGlobalComponentProc

Synopsis: Register a component searching handler

Declaration: `procedure RegisterFindGlobalComponentProc
(AFindGlobalComponent: TFindGlobalComponent)`

Visibility: default

Description: `RegisterFindGlobalComponentProc` registers a global component search callback `AFindGlobalComponent`. When `FindGlobalComponent` (290) is called, then this callback will be used to search for the component.

Errors: None.

See also: `FindGlobalComponent` (290), `UnRegisterFindGlobalComponentProc` (301)

4.4.44 RegisterInitComponentHandler

Synopsis: Register a component initialization handler

Declaration: `procedure RegisterInitComponentHandler (ComponentClass: TComponentClass;
Handler: TInitComponentHandler)`

Visibility: default

Description: `RegisterInitComponentHandler` registers a component initialization handler `Handler` for the component `ComponentClass`. This handler will be used to initialize descendants of `ComponentClass` in the `InitInheritedComponent` (293) call.

See also: `InitInheritedComponent` (293), `TInitComponentHandler` (275)

4.4.45 RegisterIntegerConsts

Synopsis: Registers some integer-to-identifier mappings.

Declaration:

```
procedure RegisterIntegerConsts(IntegerType: Pointer;
                               IdentToIntFn: TIdentToInt;
                               IntToIdentFn: TIntToIdent)
```

Visibility: default

Description: `RegisterIntegerConsts` registers a pair of callbacks to be used when an integer of type `IntegerType` must be mapped to an identifier (using `IntToIdentFn`) or when an identifier must be mapped to an integer (using `IdentToIntFn`).

Component programmers can use `RegisterIntegerConsts` to associate a series of identifier strings with integer values for a property. A necessary condition is that the property should have a separate type declared using the `type integer` syntax. If a type of integer is defined in this way, an IDE can show symbolic names for the values of these properties.

The `IntegerType` should be a pointer to the type information of the integer type. The `IntToIdentFn` and `IdentToIntFn` are two callbacks that will be used when converting between the identifier and integer value and vice versa. The functions `IdentToInt` (293) and `IntToIdent` (293) can be used to implement these callback functions.

See also: `TIdentToInt` (275), `TIntToIdent` (275), `IdentToInt` (293), `IntToIdent` (293)

4.4.46 RegisterNoIcon

Synopsis: Registers components that have no icon on the component palette.

Declaration:

```
procedure RegisterNoIcon(ComponentClasses: Array of TComponentClass)
```

Visibility: default

Description: `RegisterNoIcon` performs the same function as `RegisterComponents` (298) except that it calls `RegisterNoIconProc` (287) instead of `RegisterComponentsProc` (287)

See also: `RegisterNoIconProc` (287), `RegisterComponents` (298)

4.4.47 RegisterNonActiveX

Synopsis: Register non-activex component.

Declaration:

```
procedure RegisterNonActiveX
    (ComponentClasses: Array of TComponentClass;
     AxRegType: TActiveXRegType)
```

Visibility: default

Description: Not yet implemented in Free Pascal

4.4.48 RemoveFixupReferences

Synopsis: Removes references to rootname from the fixup list.

Declaration: `procedure RemoveFixupReferences (Root: TComponent;
const RootName: string)`

Visibility: default

Description: `RemoveFixupReferences` examines the list of unresolved references and removes references to a root object pointing at `Root` or a root component named `RootName`.

An application programmer should never need to call `RemoveFixupReferences`. This function can be used by an IDE to support removal of broken component links.

See also: `RedirectFixupReferences` ([297](#))

4.4.49 RemoveFixups

Synopsis: Removes `Instance` from the fixup list.

Declaration: `procedure RemoveFixups (Instance: TPersistent)`

Visibility: default

Description: `RemoveFixups` removes all entries for component `Instance` from the list of unresolved references.

See also: `RedirectFixupReferences` ([297](#)), `RemoveFixupReferences` ([300](#))

4.4.50 SmallPoint

Synopsis: Returns a `TSmallPoint` record with the given coordinates.

Declaration: `function SmallPoint (AX: SmallInt; AY: SmallInt) : TSmallPoint`

Visibility: default

Description: `SmallPoint` returns a `TSmallPoint` ([280](#)) record with the given coordinates `AX` and `AY` filled in.

See also: `TSmallPoint` ([280](#)), `Point` ([295](#)), `Rect` ([297](#)), `Bounds` ([288](#))

4.4.51 StartClassGroup

Synopsis: Start new class group.

Declaration: `procedure StartClassGroup (AClass: TPersistentClass)`

Visibility: default

Description: `StartClassGroup` starts a new class group and adds `AClass` to it.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

See also: `GroupDescendentsWith` ([292](#)), `ActivateClassGroup` ([287](#)), `ClassGroupOf` ([289](#))

4.4.52 UnRegisterClass

Synopsis: Unregisters a class from the streaming system.

Declaration: `procedure UnRegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `UnRegisterClass` removes the class `AClass` from the class definitions in the streaming system.

See also: `UnRegisterClasses` (301), `UnRegisterModuleClasses` (301), `RegisterClass` (297)

4.4.53 UnRegisterClasses

Synopsis: Unregisters multiple classes from the streaming system.

Declaration: `procedure UnRegisterClasses (AClasses: Array of TPersistentClass)`

Visibility: default

Description: `UnRegisterClasses` removes the classes in `AClasses` from the class definitions in the streaming system.

4.4.54 UnregisterFindGlobalComponentProc

Synopsis: Remove a previously registered component searching handler.

Declaration: `procedure UnregisterFindGlobalComponentProc
(AFindGlobalComponent: TFindGlobalComponent)`

Visibility: default

Description: `UnregisterFindGlobalComponentProc` unregisters the previously registered global component search callback `AFindGlobalComponent`. After this call, when `FindGlobalComponent` (290) is called, then this callback will be no longer be used to search for the component.

Errors: None.

See also: `FindGlobalComponent` (290), `RegisterFindGlobalComponentProc` (298)

4.4.55 UnRegisterModuleClasses

Synopsis: Unregisters classes registered by module.

Declaration: `procedure UnRegisterModuleClasses (Module: HMODULE)`

Visibility: default

Description: `UnRegisterModuleClasses` unregisters all classes which reside in the module `Module`. For each registered class, the definition pointer is checked to see whether it resides in the module, and if it does, the definition is removed.

See also: `UnRegisterClass` (301), `UnRegisterClasses` (301), `RegisterClasses` (298)

4.4.56 WriteComponentResFile

Synopsis: Write component properties to a specified resource file

Declaration: `procedure WriteComponentResFile(const FileName: string;
Instance: TComponent)`

Visibility: default

Description: `WriteComponentResFile` starts writing properties of `Instance` to the file `FileName`. It creates a filestream from `FileName` and then calls `TStream.WriteComponentRes` (453) method to write the state of the component to the stream.

See also: `TStream.WriteComponentRes` (453), `ReadComponentResFile` (296)

4.5 TIdentMapEntry

```
TIdentMapEntry = record
  Value : Integer;
  Name  : string;
end
```

`TIdentMapEntry` is used internally by the `IdentToInt` (293) and `IntToIdent` (293) calls to store the mapping between the identifiers and the integers they represent.

4.6 TStringItem

```
TStringItem = record
  FString : string;
  FObject : TObject;
end
```

The `TStringItem` is used to store the string and object items in a `TStringList` (463) string list instance. It should never be used directly.

4.7 EBitsError

4.7.1 Description

When an index of a bit in a `TBits` (351) is out of the valid range (0 to `Count-1`) then a `EBitsError` exception is raised.

4.8 EClassNotFound

4.8.1 Description

When the streaming system needs to create a component, it looks for the class pointer (VMT) in the list of registered classes by its name. If this name is not found, then an `EClassNotFound` is raised.

See also: `EFilerError` (303)

4.9 EComponentError

4.9.1 Description

When an error occurs during the registration of a component, or when naming a component, then a `EComponentError` is raised. Possible causes are:

1. An name with an illegal character was assigned to a component.
2. A component with the same name and owner already exists.
3. The component registration system isn't set up properly.

See also: `TComponent` ([369](#)), `TComponent.Name` ([378](#))

4.10 EFCreateError

4.10.1 Description

When the operating system reports an error during creation of a new file in the Filestream Constructor ([389](#)), a `EFCreateError` is raised.

See also: `EStreamError` ([305](#)), `EOpenError` ([303](#))

4.11 EFilerError

4.11.1 Description

This class serves as an ancestor class for exceptions that are raised when an error occurs during component streaming. A `EFilerError` exception is raised when a class is registered twice.

See also: `EStreamError` ([305](#)), `EReadError` ([305](#))

4.12 EOpenError

4.12.1 Description

When the operating system reports an error during the opening of a file in the Filestream Constructor ([389](#)), a `EOpenError` is raised.

See also: `EStreamError` ([305](#)), `EFCreateError` ([303](#))

4.13 EInvalidImage

4.13.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

4.14 EInvalidOperation

4.14.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

4.15 EListError

4.15.1 Description

If an error occurs in one of the `TList` (408) or `TStrings` (468) methods, then a `EListError` exception is raised. This can occur in one of the following cases:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. An attempt was made to reduce the capacity of the list below the current element count.
4. An attempt was made to set the list count to a negative value.
5. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
6. An attempt was made to move an item to a position outside the list's bounds.

See also: `TList` (408), `TStrings` (468)

4.16 EMethodNotFound

4.16.1 Description

This exception is no longer used in the streaming system. This error is replaced by a `EReadError` (305).

See also: `EFilerError` (303), `EReadError` (305)

4.17 EObserver

4.17.1 Description

`EObserver` is an error that is raised when an object is registered as an observer, and it does not implement the `IFPObserver` (309) interface.

See also: `IFPObserver` (309), `IFPObserver.FPOAttachObserver` (308)

4.18 EOutOfResources

4.18.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

4.19 EParserError

4.19.1 Description

When an error occurs during the parsing of a stream, an `EParserError` is raised. Usually this indicates that an invalid token was found on the input stream, or the token read from the stream wasn't the expected token.

See also: `TParser` ([422](#))

4.20 EReadError

4.20.1 Description

If an error occurs when reading from a stream, a `EReadError` exception is raised. Possible causes for this are:

1. Not enough data is available when reading from a stream
2. The stream containing a component's data contains invalid data. this will occur only when reading a component from a stream.

See also: `EFileError` ([303](#)), `EWriteError` ([306](#))

4.21 EResNotFound

4.21.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

4.22 EStreamError

4.22.1 Description

An `EStreamError` is raised when an error occurs during reading from or writing to a stream: Possible causes are

1. Not enough data is available in the stream.
2. Trying to seek beyond the beginning or end of the stream.
3. Trying to set the capacity of a memory stream and no memory is available.
4. Trying to write to a read-only stream, such as a resource stream.
5. Trying to read from a write-only stream.

See also: `EFCREATEError` ([303](#))

4.23 TStringListError

4.23.1 Description

When an error occurs in one of the methods of `TStrings` (468) then an `EStringListError` is raised. This can have one of the following causes:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
4. An attempt was made to add a duplicate entry to a `TStringList` (463) when `TStringList.Duplicates` (466) is `False`.

See also: `TStrings` (468), `TStringList` (463)

4.24 EThread

4.24.1 Description

Thread error exception.

4.25 EThreadDestroyCalled

4.25.1 Description

Exception raised when a thread is destroyed illegally.

4.26 EThreadExternalException

4.26.1 Description

`EThreadExternalException` is raised by for example `TThread.CheckTerminated` (501) and `TThread.SetReturnValue` (501) when the thread was not created by the Free Pascal program, but by an external code base (for example a DLL, or the calling application in a DLL).

See also: `TThread.CheckTerminated` (501), `TThread.SetReturnValue` (501)

4.27 EWriteError

4.27.1 Description

If an error occurs when writing to a stream, a `EWriteError` exception is raised. Possible causes for this are:

1. The stream doesn't allow writing.
2. An error occurred when writing a property to a stream.

See also: `EFileError` (303), `EReadError` (305)

4.28 IDesignerNotify

4.28.1 Description

`IDesignerNotify` is an interface that can be used to communicate changes to a designer mechanism. It offers functionality for detecting changes, and notifications when the component is destroyed.

4.28.2 Method overview

Page	Method	Description
307	<code>Modified</code>	Notify that the component is modified.
307	<code>Notification</code>	Notification of owner changes

4.28.3 IDesignerNotify.Modified

Synopsis: Notify that the component is modified.

Declaration: `procedure Modified`

Visibility: `default`

Description: `Modified` can be used to notify a designer of changes, indicating that components should be streamed.

4.28.4 IDesignerNotify.Notification

Synopsis: Notification of owner changes

Declaration: `procedure Notification(AnObject: TPersistent; Operation: TOperation)`

Visibility: `default`

Description: `Notification` is the interface counterpart of `TComponent.Notification` ([370](#)) which is used to communicate adds to the components.

See also: `TComponent.Notification` ([370](#))

4.29 IFPObserved

4.29.1 Description

`IFPObserved` is an interface which can be implemented in objects that must be observable. Objects that wish to observe the object can register themselves with the `FPOAttachObserver` ([266](#)) call, and must be detached using the `FPODetachObserver` ([266](#)) call.

This interface is not reference counted, so care must be taken that the `ooFree` message is sent with `FPONotifyObservers` ([266](#)) when the object is freed.

See also: `FPONotifyObservers` ([266](#))

4.29.2 Method overview

Page	Method	Description
308	FPOAttachObserver	Attach a new observer to the object
308	FPODetachObserver	Remove an observer from the list of observers.
308	FPONotifyObservers	Notify all observers

4.29.3 IFPObserved.FPOAttachObserver

Synopsis: Attach a new observer to the object

Declaration: `procedure FPOAttachObserver(AObserver: TObject)`

Visibility: default

Description: `FPOAttachObserver` must be called with an object instance `AObserver` that implements the `IFPObserver` ([309](#)) interface. The `FPOObservedChanged` ([309](#)) method of the interface will be called whenever `FPONotifyObservers` ([266](#)) is used to notify observers of a change. Objects implementing this interface should check that `AObserver` actually implements the `IFPObserver` ([309](#)) interface.

Do not make assumptions on how the interface behaves if `FPOAttachObserver` is called more than once with the same interface. It may add the object to the list of observers unconditionally (in which case it will be notified twice) or it may check that it is not yet in the list.

Errors: If `AObserver` does not implement the `IFPObserver` ([309](#)) interface, an `EObserver` ([304](#)) exception must be raised. No other errors should be raised, other than a possible out of memory error.

See also: `IFPObserver` ([309](#)), `FPOObservedChanged` ([309](#)), `FPONotifyObservers` ([266](#))

4.29.4 IFPObserved.FPODetachObserver

Synopsis: Remove an observer from the list of observers.

Declaration: `procedure FPODetachObserver(AObserver: TObject)`

Visibility: default

Description: `FPODetachObserver` removes the `AObserver` object from the list of observers. If it was not in the list, then this is silently accepted. Once removed, it will no longer receive notifications when `FPOObservedChanged` ([309](#)) is called.

If the object was added more than once using `FPOAttachObserver` ([266](#)), then it depends on the implementor of the interface whether or `FPODetachObserver` must be called an equal number of times.

See also: `IFPObserver` ([309](#)), `FPOObservedChanged` ([309](#)), `FPONotifyObservers` ([266](#)), `FPOAttachObserver` ([266](#))

4.29.5 IFPObserved.FPONotifyObservers

Synopsis: Notify all observers

Declaration: `procedure FPONotifyObservers(ASender: TObject;
 AOperation: TFPObservedOperation;
 Data: Pointer)`

Visibility: default

Description: `FPONotifyObservers` notifies all observers of the object that a change has occurred. It calls `FPObservedChanged` (309) on the `IFPObserver` (309) interface of all attached objects, and passes on `ASender` (normally this is `Self`), `AOperation` and `Data`. What `Data` is, depends on the implementor of the interface.

There is no guaranteed order in which the change notifications are delivered to the observers. This is an implementation-specific detail, which should not be relied upon in any way.

See also: `IFPObserver` (309), `FPObservedChanged` (309), `FPODetachObserver` (266), `FPOAttachObserver` (266)

4.30 IFPObserver

4.30.1 Description

`IFPObserver` is the interface an object must implement if it wishes to receive change notifications from another object. The presence of this interface will be checked when the object registers itself using `IFPObserver.FPOAttachObserver` (309). The change notifications arrive because the `FPObservedChanged` (266) method is called by the observed object.

See also: `IFPObserved` (307), `FPOAttachObserver` (308)

4.30.2 Method overview

Page	Method	Description
309	<code>FPObservedChanged</code>	Entry point for change notifications

4.30.3 IFPObserver.FPObservedChanged

Synopsis: Entry point for change notifications

Declaration: `procedure FPObservedChanged(ASender: TObject;
Operation: TFPObservedOperation;
Data: Pointer)`

Visibility: default

Description: `FPObservedChanged` is the method that is called by an observed object (`IFPObserved` (307)) when it calls `FPONotifyObservers` (308). The `Sender` is the object under observation, the `Operation` and `Data` are the parameters used in the call to `FPONotifyObservers`.

See also: `IFPObserved` (307), `FPONotifyObservers` (308)

4.31 IInterfaceComponentReference

4.31.1 Description

`IInterfaceComponentReference` is an interface to return the component that implements a given interface. It is implemented by `TComponent` (369).

See also: `TComponent` (369)

4.31.2 Method overview

Page	Method	Description
310	GetComponent	Return component instance

4.31.3 IInterfaceComponentReference.GetComponent

Synopsis: Return component instance

Declaration: `function GetComponent : TComponent`

Visibility: default

Description: `GetComponent` returns the component instance.

Errors: None.

See also: `TComponent` ([369](#))

4.32 IInterfaceList

4.32.1 Description

`IInterfaceList` is an interface for maintaining a list of interfaces, strongly resembling the standard `TList` ([408](#)) class. It offers the same list of public methods as `TList`, with the exception that it uses interfaces instead of pointers.

All interfaces in the list should descend from `IUnknown`.

More detailed descriptions of how the various methods behave can be found in the `TList` reference.

See also: `TList` ([408](#))

4.32.2 Method overview

Page	Method	Description
313	Add	Add an interface to the list
312	Clear	Clear the list
312	Delete	Remove an interface from the list
313	Exchange	Exchange 2 interfaces in the list
313	First	Return the first non-empty interface in the list.
311	Get	Retrieve an interface pointer from the list.
311	GetCapacity	Return the capacity of the list.
311	GetCount	Return the current number of elements in the list.
313	IndexOf	Return the index of an interface.
313	Insert	Insert an interface in the list.
314	Last	Returns the last non-nil interface in the list.
314	Lock	Lock the list
311	Put	Write an item to the list
314	Remove	Remove an interface from the list
312	SetCapacity	Set the capacity of the list
312	SetCount	Set the number of items in the list
314	Unlock	Unlock the list.

4.32.3 Property overview

Page	Properties	Access	Description
314	Capacity	rw	Capacity of the list
315	Count	rw	Current number of elements in the list.
315	Items	rw	Provides Index-based, sequential, access to the interfaces in the list.

4.32.4 IInterfaceList.Get

Synopsis: Retrieve an interface pointer from the list.

Declaration: `function Get(i: Integer) : IUnknown`

Visibility: default

Description: `Get` returns the interface pointer at position `i` in the list. It serves as the `Read` method for the `Items` ([315](#)) property.

See also: `IInterfaceList.Items` ([315](#)), `TList.Items` ([416](#))

4.32.5 IInterfaceList.GetCapacity

Synopsis: Return the capacity of the list.

Declaration: `function GetCapacity : Integer`

Visibility: default

Description: `GetCapacity` returns the current capacity of the list. It serves as the `Read` method for the `Capacity` ([314](#)) property.

See also: `IInterfaceList.Capacity` ([314](#)), `TList.Capacity` ([415](#))

4.32.6 IInterfaceList.GetCount

Synopsis: Return the current number of elements in the list.

Declaration: `function GetCount : Integer`

Visibility: default

Description: It serves as the `Read` method for the `Count` ([315](#)) property.

See also: `IInterfaceList.Count` ([315](#)), `TList.Count` ([416](#))

4.32.7 IInterfaceList.Put

Synopsis: Write an item to the list

Declaration: `procedure Put(i: Integer; item: IUnknown)`

Visibility: default

Description: `Put` writes the interface `Item` at position `I` in the list. It servers as the `Write` method for the `Items` ([315](#)) property.

See also: `IInterfaceList.Items` ([315](#)), `TList.Items` ([416](#))

4.32.8 **InterfaceList.SetCapacity**

Synopsis: Set the capacity of the list

Declaration: `procedure SetCapacity(NewCapacity: Integer)`

Visibility: default

Description: `SetCapacity` sets the capacity of the list to `NewCapacity`. It serves as the `Write` method for the `Capacity` (314) property.

See also: `InterfaceList.Capacity` (314), `TList.Capacity` (415)

4.32.9 **InterfaceList.SetCount**

Synopsis: Set the number of items in the list

Declaration: `procedure SetCount(NewCount: Integer)`

Visibility: default

Description: `SetCount` sets the count of the list to `NewCount`. It serves as the `Write` method for the `Capacity` (314)

See also: `InterfaceList.Count` (315), `TList.Count` (416)

4.32.10 **InterfaceList.Clear**

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: default

Description: `Clear` removes all interfaces from the list. All interfaces in the list will be cleared (i.e. their reference count will decrease with 1)

See also: `TList.Clear` (411)

4.32.11 **InterfaceList.Delete**

Synopsis: Remove an interface from the list

Declaration: `procedure Delete(index: Integer)`

Visibility: default

Description: `Delete` removes the interface at position `Index` from the list. It does this by explicitly clearing the interface and then removing the slot.

See also: `TList.Clear` (411), `InterfaceList.Add` (313), `InterfaceList.Delete` (312), `InterfaceList.Insert` (313)

4.32.12 **IInterfaceList.Exchange**

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange(index1: Integer; index2: Integer)`

Visibility: default

Description: `Exchange` exchanges 2 interfaces in the list at locations `index1` and `Index2`.

See also: `TList.Exchange` (412), `IInterfaceList.Add` (313), `IInterfaceList.Delete` (312), `IInterfaceList.Insert` (313)

4.32.13 **IInterfaceList.First**

Synopsis: Return the first non-empty interface in the list.

Declaration: `function First : IUnknown`

Visibility: default

Description: `First` returns the first non-empty interface in the list.

See also: `TList.First` (413), `IInterfaceList.IndexOf` (313), `IInterfaceList.Last` (314)

4.32.14 **IInterfaceList.IndexOf**

Synopsis: Return the index of an interface.

Declaration: `function IndexOf(const item: IUnknown) : Integer`

Visibility: default

Description: `IndexOf` returns the location in the list of the interface `Item`. If there is no such interface in the list, then -1 is returned.

See also: `TList.IndexOf` (413), `IInterfaceList.First` (313), `IInterfaceList.Last` (314)

4.32.15 **IInterfaceList.Add**

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: default

Description: `Add` adds the interface `Item` to the list, and returns the position at which it has been added.

See also: `TList.Add` (411), `IInterfaceList.Insert` (313), `IInterfaceList.Delete` (312)

4.32.16 **IInterfaceList.Insert**

Synopsis: Insert an interface in the list.

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: default

Description: `Insert` inserts the interface `Item` in the list, at position `I`, shifting all items one position.

See also: `TList.Insert` (413), `IInterfaceList.Add` (313), `IInterfaceList.Delete` (312)

4.32.17 **IInterfaceList.Last**

Synopsis: Returns the last non-nil interface in the list.

Declaration: `function Last : IUnknown`

Visibility: default

Description: `Last` returns the last non-empty interface in the list.

See also: `TList.Last` ([414](#)), `IInterfaceList.First` ([313](#)), `IInterfaceList.IndexOf` ([313](#))

4.32.18 **IInterfaceList.Remove**

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: default

Description: `Remove` searches for the first occurrence of `Item` in the list and deletes it.

See also: `TList.Remove` ([414](#)), `IInterfaceList.Delete` ([312](#)), `IInterfaceList.IndexOf` ([313](#))

4.32.19 **IInterfaceList.Lock**

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: default

Description: `Lock` locks the list. After a call to lock, the object list can only be accessed by the current thread, until `UnLock` ([314](#)) is called.

See also: `TInterfaceList.Lock` ([405](#)), `IInterfaceList.Unlock` ([314](#))

4.32.20 **IInterfaceList.Unlock**

Synopsis: Unlock the list.

Declaration: `procedure Unlock`

Visibility: default

Description: `Unlock` unlocks a locked list. After a call to `UnLock`, other threads are again able to access the list.

See also: `TInterfaceList.UnLock` ([405](#)), `IInterfaceList.Lock` ([314](#))

4.32.21 **IInterfaceList.Capacity**

Synopsis: Capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: default

Access: Read,Write

Description: `Capacity` is the maximum number of elements the list can hold without needing to reallocate memory for the list. It can be set to improve speed when adding a lot of items to the list.

See also: `TList.Capacity` ([415](#)), `IInterfaceList.Count` ([315](#))

4.32.22 `IInterfaceList.Count`

Synopsis: Current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `default`

Access: `Read,Write`

Description: `Count` is the current number of elements in the list. Setting it to a larger number will allocate empty slots. Setting it to a smaller number will clear any interfaces that fall outside the new border.

See also: `IInterfaceList.Capacity` ([314](#)), `TList.Count` ([416](#))

4.32.23 `IInterfaceList.Items`

Synopsis: Provides Index-based, sequential, access to the interfaces in the list.

Declaration: `Property Items[index: Integer]: IUnknown; default`

Visibility: `default`

Access: `Read,Write`

Description: `Items` is the default property of the interface list and provides index-based array access to the interfaces in the list. Allowed values for `Index` include 0 to `Count-1`

See also: `IInterfaceList.Count` ([315](#)), `TList.Items` ([416](#))

4.33 `IStreamPersist`

4.33.1 Description

`IStreamPersist` defines an interface for object persistence streaming to a stream. Any class implementing this interface is expected to be able to save or load it's state from or to a stream.

See also: `TPersistent` ([428](#)), `TComponent` ([369](#)), `TStream` ([448](#))

4.33.2 Method overview

Page	Method	Description
316	<code>LoadFromStream</code>	Load persistent data from stream.
316	<code>SaveToStream</code>	Save persistent data to stream.

4.33.3 IStreamPersist.LoadFromStream

Synopsis: Load persistent data from stream.

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: default

Description: `LoadFromStream` is the method called when the object should load it's state from the stream `stream`. It should be able to read the data which was written using the `SaveToStream` method.

See also: [TPersistent \(428\)](#), [TComponent \(369\)](#), [TStream \(448\)](#), [IStreamPersist.SaveToStream \(316\)](#)

4.33.4 IStreamPersist.SaveToStream

Synopsis: Save persistent data to stream.

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: default

Description: `SaveFromStream` is the method called when the object should load it's state from the stream `stream`. The data written by this method should be readable by the `LoadFromStream` method.

See also: [TPersistent \(428\)](#), [TComponent \(369\)](#), [TStream \(448\)](#), [IStreamPersist.LoadFromStream \(316\)](#)

4.34 IStringsAdapter

4.34.1 Description

Is not yet supported in Free Pascal.

See also: [TStrings \(468\)](#)

4.34.2 Method overview

Page	Method	Description
316	<code>ReferenceStrings</code>	Add a reference to the indicated strings.
316	<code>ReleaseStrings</code>	Release the reference to the strings.

4.34.3 IStringsAdapter.ReferenceStrings

Synopsis: Add a reference to the indicated strings.

Declaration: `procedure ReferenceStrings(S: TStrings)`

Visibility: default

4.34.4 IStringsAdapter.ReleaseStrings

Synopsis: Release the reference to the strings.

Declaration: `procedure ReleaseStrings`

Visibility: default

4.35 IVCLComObject

4.35.1 Description

IVCLComObject is used by TComponent to implement the IUnknown interface used by COM automation servers. Partially, it is the translation to pascal of the IDispatch interface definition by Microsoft. If TComponent needs to return an IUnknown interface, it creates a IVCLComObject interface instead.

See also: TComponent.VCLComObject ([378](#))

4.35.2 Method overview

Page	Method	Description
318	FreeOnRelease	Is called by TComponent.FreeOnRelease
318	GetIDsOfNames	The IDispatch: GetIDsOfNames call for automation servers.
317	GetTypeInfo	The IDispatch: GetTypeInfo call for automation servers
317	GetTypeInfoCount	The IDispatch: GetTypeInfoCount call for automation servers
318	Invoke	The IDispatch: Invoke call for automation servers.
318	SafeCallException	This method can be invoked if an exception occurs during Invoke

4.35.3 IVCLComObject.GetTypeInfoCount

Synopsis: The IDispatch: GetTypeInfoCount call for automation servers

Declaration: `function GetTypeInfoCount(out Count: Integer) : HRESULT`

Visibility: default

Description: GetTypeInfoCount must return in Count either 0 or 1 to indicate that it provides type information (1) or not (0).

Errors: On error, a nonzero (different from S_OK) return value must be returned.

See also: IVCLComObject.GetTypeInfo ([317](#))

4.35.4 IVCLComObject.GetTypeInfo

Synopsis: The IDispatch: GetTypeInfo call for automation servers

Declaration: `function GetTypeInfo(Index: Integer; LocaleID: Integer; out TypeInfo) : HRESULT`

Visibility: default

Description: GetTypeInfo must return the Index-th entry in the type information of the component in TypeInfo. The LocaleID argument can be used to indicate the locale of the caller, as different type information can be returned depending on the locale.

Errors: On error, a nonzero (different from S_OK) return value must be returned.

See also: IVCLComObject.GetTypeInfoCount ([317](#))

4.35.5 IVCLComObject.GetIDsOfNames

Synopsis: The `IDispatch::GetIDsOfNames` call for automation servers.

Declaration: `function GetIDsOfNames(const IID: TGuid; Names: Pointer;
NameCount: Integer; LocaleID: Integer;
DispIDs: Pointer) : HRESULT`

Visibility: default

Description: `GetIDsOfNames` must return in `DispIDs` the dispatch Ids for the `NameCount` names of the methods listed in `Names`. The `LocaleID` indicates the locale of the caller.

Errors: On error, a nonzero (different from `S_OK`) return value must be returned.

See also: `IVCLComObject.Invoke` (318)

4.35.6 IVCLComObject.Invoke

Synopsis: The `IDispatch::Invoke` call for automation servers.

Declaration: `function Invoke(DispID: Integer; const IID: TGuid; LocaleID: Integer;
Flags: Word; var Params; VarResult: Pointer;
ExcepInfo: Pointer; ArgErr: Pointer) : HRESULT`

Visibility: default

Description: `Invoke` must invoke the method designated by `DispID`. `IID` can be ignored. `LocaleID` is used by the caller to indicate the locale it is using. The `Flags` argument describes the context in which `Invoke` is called: a method, or property getter/setter. The `Params` argument contains the parameters to the call. The result should be in `VarResult`. On error, `ExcepInfo` and `ArgError` should be filled.

The function should return 0 (`S_OK`) if all went well.

See also: `IVCLComObject.GetIDsOfNames` (318)

4.35.7 IVCLComObject.SafeCallException

Synopsis: This method can be invoked if an exception occurs during `Invoke`

Declaration: `function SafeCallException(ExceptObject: TObject;
ExceptAddr: CodePointer) : HRESULT`

Visibility: default

Description: `SafeCallException` is called to handle an exception during invocation of the `Invoke` method. The `TObject` implementation of this method returns `E_UNEXPECTED`.

See also: `IVCLComObject.Invoke` (318)

4.35.8 IVCLComObject.FreeOnRelease

Synopsis: Is called by `TComponent.FreeOnRelease`

Declaration: `procedure FreeOnRelease`

Visibility: default

Description: `FreeOnRelease` is called by `TComponent.FreeOnRelease` (373) for the `IVCLComObject` interface implemented by `TComponent`.

See also: `TComponent.FreeOnRelease` (373)

4.36 TAbstractObjectReader

4.36.1 Description

The Free Pascal streaming mechanism, while compatible with Delphi's mechanism, differs from it in the sense that the streaming mechanism uses a driver class when streaming components. The `TAbstractObjectReader` class is the base driver class for reading property values from streams. It consists entirely of abstract methods, which must be implemented by descendant classes.

Different streaming mechanisms can be implemented by making a descendant from `TAbstractObjectReader`. The `TBinaryObjectReader` (338) class is such a descendant class, which streams data in binary (Delphi compatible) format.

All methods described in this class, must be implemented by descendant classes.

See also: `TBinaryObjectReader` (338)

4.36.2 Method overview

Page	Method	Description
320	<code>BeginComponent</code>	Marks the reading of a new component.
321	<code>BeginProperty</code>	Marks the reading of a property value.
320	<code>BeginRootComponent</code>	Starts the reading of the root component.
319	<code>FlushBuffer</code>	Flush the buffer
320	<code>NextValue</code>	Returns the type of the next value in the stream.
321	<code>Read</code>	Read raw data from stream
321	<code>ReadBinary</code>	Read binary data from the stream.
323	<code>ReadCurrency</code>	Read a currency value from the stream.
322	<code>ReadDate</code>	Read a date value from the stream.
322	<code>ReadFloat</code>	Read a float value from the stream.
323	<code>ReadIdent</code>	Read an identifier from the stream.
324	<code>ReadInt16</code>	Read a 16-bit integer from the stream.
324	<code>ReadInt32</code>	Read a 32-bit integer from the stream.
324	<code>ReadInt64</code>	Read a 64-bit integer from the stream.
323	<code>ReadInt8</code>	Read an 8-bit integer from the stream.
325	<code>ReadSet</code>	Reads a set from the stream.
325	<code>ReadSignature</code>	Read resource signature
322	<code>ReadSingle</code>	Read a single (real-type) value from the stream.
325	<code>ReadStr</code>	Read a shortstring from the stream
326	<code>ReadString</code>	Read a string of type <code>StringType</code> from the stream.
326	<code>ReadUnicodeString</code>	Read a Unicode string value
320	<code>ReadValue</code>	Reads the type of the next value.
326	<code>ReadWideString</code>	Read a widestring value from the stream.
326	<code>SkipComponent</code>	Skip till the end of the component.
327	<code>SkipValue</code>	Skip the current value.

4.36.3 TAbstractObjectReader.FlushBuffer

Synopsis: Flush the buffer

Declaration: `procedure FlushBuffer; Virtual`

Visibility: `public`

Description: `FlushBuffer` flushes the buffer. It is provided for Delphi compatibility, and is not used in FPC.

See also: `TFile.FlushBuffer` ([387](#))

4.36.4 TAbstractObjectReader.NextValue

Synopsis: Returns the type of the next value in the stream.

Declaration: `function NextValue : TValueType; Virtual; Abstract`

Visibility: `public`

Description: This function should return the type of the next value in the stream, but should not read the actual value, i.e. the stream position should not be altered by this method. This is used to 'peek' in the stream what value is next.

See also: `TAbstractObjectReader.ReadValue` ([320](#))

4.36.5 TAbstractObjectReader.ReadValue

Synopsis: Reads the type of the next value.

Declaration: `function ReadValue : TValueType; Virtual; Abstract`

Visibility: `public`

Description: This function returns the type of the next value in the stream and reads it. i.e. after the call to this method, the stream is positioned to read the value of the type returned by this function.

See also: `TAbstractObjectReader.ReadValue` ([320](#))

4.36.6 TAbstractObjectReader.BeginRootComponent

Synopsis: Starts the reading of the root component.

Declaration: `procedure BeginRootComponent; Virtual; Abstract`

Visibility: `public`

Description: This function can be used to initialize the driver class for reading a component. It is called once at the beginning of the read process, and is immediately followed by a call to `BeginComponent` ([320](#)).

See also: `TAbstractObjectReader.BeginComponent` ([320](#))

4.36.7 TAbstractObjectReader.BeginComponent

Synopsis: Marks the reading of a new component.

Declaration: `procedure BeginComponent (var Flags: TFileFlags;
var AChildPos: Integer;
var CompClassName: string; var CompName: string)
; Virtual; Abstract`

Visibility: `public`

Description: This method is called when the streaming process wants to start reading a new component.

Descendant classes should override this method to read the start of a component new component definition and return the needed arguments. `Flags` should be filled with any flags that were found at the component definition, as well as `ACHildPos`. The `CompClassName` should be filled with the class name of the streamed component, and the `CompName` argument should be filled with the name of the component.

`ACHildPos` is used to change the ordering in which components appear below their parent component when streaming descendant forms.

See also: `TAbstractObjectReader.BeginRootComponent` (320), `TAbstractObjectReader.BeginProperty` (321)

4.36.8 TAbstractObjectReader.BeginProperty

Synopsis: Marks the reading of a property value.

Declaration: `function BeginProperty : string; Virtual; Abstract`

Visibility: public

Description: `BeginProperty` is called by the streaming system when it wants to read a new property. The return value of the function is the name of the property which can be read from the stream.

See also: `TAbstractObjectReader.BeginComponent` (320)

4.36.9 TAbstractObjectReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual; Abstract`

Visibility: public

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in production code as it will totally mess up the streaming.

See also: `TBinaryObjectReader.Read` (341), `TReader.Read` (437)

4.36.10 TAbstractObjectReader.ReadBinary

Synopsis: Read binary data from the stream.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Virtual; Abstract`

Visibility: public

Description: `ReadBinary` is called when binary data should be read from the stream (i.e. after `ReadValue` (320) returned a value type of `vaBinary`). The data should be stored in the `DestData` memory stream by descendant classes.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TabstractObjectReader.ReadSet` (325), `TabstractObjectReader.ReadStr` (325), `TabstractObjectReader.ReadString` (326)

4.36.11 TAbstractObjectReader.ReadFloat

Synopsis: Read a float value from the stream.

Declaration: `function ReadFloat : Extended; Virtual; Abstract`

Visibility: `public`

Description: `ReadFloat` is called by the streaming system when it wants to read a float from the stream (i.e. after `ReadValue` (320) returned a value type of `vaExtended`). The return value should be the value of the float.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TabstractObjectReader.ReadSet` (325), `TabstractObjectReader.ReadStr` (325), `TabstractObjectReader.ReadString` (326)

4.36.12 TAbstractObjectReader.ReadSingle

Synopsis: Read a single (real-type) value from the stream.

Declaration: `function ReadSingle : Single; Virtual; Abstract`

Visibility: `public`

Description: `ReadSingle` is called by the streaming system when it wants to read a single-type float from the stream (i.e. after `ReadValue` (320) returned a value type of `vaSingle`). The return value should be the value of the float.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TabstractObjectReader.ReadSet` (325), `TabstractObjectReader.ReadStr` (325), `TabstractObjectReader.ReadString` (326)

4.36.13 TAbstractObjectReader.ReadDate

Synopsis: Read a date value from the stream.

Declaration: `function ReadDate : TDateTime; Virtual; Abstract`

Visibility: `public`

Description: `ReadDate` is called by the streaming system when it wants to read a date/time value from the stream (i.e. after `ReadValue` (320) returned a value type of `vaDate`). The return value should be the date/time value. (This value can be stored as a float, since `TDateTime` is nothing but a float.)

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TabstractObjectReader.ReadSet` (325), `TabstractObjectReader.ReadStr` (325), `TabstractObjectReader.ReadString` (326)

4.36.14 TAbstractObjectReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency; Virtual; Abstract`

Visibility: `public`

Description: `ReadCurrency` is called when a currency-typed value should be read from the stream. This abstract method should be overridden by descendant classes, and should return the currency value read from the stream.

See also: `TAbstractObjectWriter.WriteCurrency` (330)

4.36.15 TAbstractObjectReader.ReadIdent

Synopsis: Read an identifier from the stream.

Declaration: `function ReadIdent (ValueType: TValueType) : string; Virtual; Abstract`

Visibility: `public`

Description: `ReadIdent` is called by the streaming system if it expects to read an identifier of type `ValueType` from the stream after a call to `ReadValue` (320) returned `vaIdent`. The identifier should be returned as a string. Note that in some cases the identifier does not actually have to be in the stream. The following table indicates which identifiers must actually be read:

Table 4.24:

ValueType	Expected value
<code>vaIdent</code>	Read from stream.
<code>vaNil</code>	'Nil'. This does not have to be read from the stream.
<code>vaFalse</code>	'False'. This does not have to be read from the stream.
<code>vaTrue</code>	'True'. This does not have to be read from the stream.
<code>vaNull</code>	'Null'. This does not have to be read from the stream.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TabstractObjectReader.ReadSet` (325), `TabstractObjectReader.ReadStr` (325), `TabstractObjectReader.ReadString` (326)

4.36.16 TAbstractObjectReader.ReadInt8

Synopsis: Read an 8-bit integer from the stream.

Declaration: `function ReadInt8 : ShortInt; Virtual; Abstract`

Visibility: `public`

Description: `ReadInt8` is called by the streaming process if it expects to read an integer value with a size of 8 bits (1 byte) from the stream (i.e. after `ReadValue` (320) returned a `valuetype` of `vaInt8`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 1 byte.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TAbstractObjectReader.ReadSet` (325), `TAbstractObjectReader.ReadStr` (325), `TAbstractObjectReader.ReadString` (326)

4.36.17 `TAbstractObjectReader.ReadInt16`

Synopsis: Read a 16-bit integer from the stream.

Declaration: `function ReadInt16 : SmallInt; Virtual; Abstract`

Visibility: public

Description: `ReadInt16` is called by the streaming process if it expects to read an integer value with a size of 16 bits (2 bytes) from the stream (i.e. after `ReadValue` (320) returned a `valuetype` of `vaInt16`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 2 bytes.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TAbstractObjectReader.ReadSet` (325), `TAbstractObjectReader.ReadStr` (325), `TAbstractObjectReader.ReadString` (326)

4.36.18 `TAbstractObjectReader.ReadInt32`

Synopsis: Read a 32-bit integer from the stream.

Declaration: `function ReadInt32 : LongInt; Virtual; Abstract`

Visibility: public

Description: `ReadInt32` is called by the streaming process if it expects to read an integer value with a size of 32 bits (4 bytes) from the stream (i.e. after `ReadValue` (320) returned a `valuetype` of `vaInt32`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 4 bytes.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TAbstractObjectReader.ReadSet` (325), `TAbstractObjectReader.ReadStr` (325), `TAbstractObjectReader.ReadString` (326)

4.36.19 `TAbstractObjectReader.ReadInt64`

Synopsis: Read a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64; Virtual; Abstract`

Visibility: public

Description: `ReadInt64` is called by the streaming process if it expects to read an `int64` value with a size of 64 bits (8 bytes) from the stream (i.e. after `ReadValue` (320) returned a `valuetype` of `vaInt64`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 8 bytes.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadSet` (325), `TAbstractObjectReader.ReadStr` (325), `TAbstractObjectReader.ReadString` (326)

4.36.20 TAbstractObjectReader.ReadSet

Synopsis: Reads a set from the stream.

Declaration: `function ReadSet (EnumType: Pointer) : Integer; Virtual; Abstract`

Visibility: public

Description: This method is called by the streaming system if it expects to read a set from the stream (i.e. after `ReadValue` (320) returned a valuetype of `vaSet`). The return value is the contents of the set, encoded in a bitmask the following way:

For each (enumerated) value in the set, the bit corresponding to the ordinal value of the enumerated value should be set. i.e. as `1 shl ord(value)`.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TAbstractObjectReader.ReadSet` (325), `TAbstractObjectReader.ReadString` (326)

4.36.21 TAbstractObjectReader.ReadSignature

Synopsis: Read resource signature

Declaration: `procedure ReadSignature; Virtual; Abstract`

Visibility: public

Description: `ReadSignature` reads the streaming signature from a stream. This method does nothing. It must be implemented by descendents that have a signature header in the stream. (such as binary streams)

See also: `TAbstractObjectWriter.WriteSignature` (328), `TBinaryObjectReader.ReadSignature` (343)

4.36.22 TAbstractObjectReader.ReadStr

Synopsis: Read a shortstring from the stream

Declaration: `function ReadStr : string; Virtual; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a string from the stream (i.e. after `ReadValue` (320) returned a valuetype of `vaLString`, `vaWstring` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TAbstractObjectReader.ReadSet` (325), `TAbstractObjectReader.ReadString` (326)

4.36.23 TAbstractObjectReader.ReadString

Synopsis: Read a string of type `StringType` from the stream.

Declaration: `function ReadString(StringType: TValueType) : string; Virtual
; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a string from the stream (i.e. after `ReadValue` (320) returned a valuetype of `vaLString`, `vaWstring` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (322), `TAbstractObjectReader.ReadDate` (322), `TAbstractObjectReader.ReadSingle` (322), `TAbstractObjectReader.ReadIdent` (323), `TAbstractObjectReader.ReadInt8` (323), `TAbstractObjectReader.ReadInt16` (324), `TAbstractObjectReader.ReadInt32` (324), `TAbstractObjectReader.ReadInt64` (324), `TAbstractObjectReader.ReadSet` (325), `TAbstractObjectReader.ReadStr` (325)

4.36.24 TAbstractObjectReader.ReadWideString

Synopsis: Read a widestring value from the stream.

Declaration: `function ReadWideString : WideString; Virtual; Abstract`

Visibility: public

Description: `ReadWideString` is called when a widestring-typed value should be read from the stream. This abstract method should be overridden by descendant classes.

See also: `TAbstractObjectWriter.WriteWideString` (332)

4.36.25 TAbstractObjectReader.ReadUnicodeString

Synopsis: Read a Unicode string value

Declaration: `function ReadUnicodeString : UnicodeString; Virtual; Abstract`

Visibility: public

Description: `ReadUnicodeString` should read a `UnicodeString` value from the stream. (indicated by the `vaUString` value type).

Descendant classes should override this method to actually read a `UnicodeString` value.

See also: `TBinaryObjectWriter.WriteUnicodeString` (350), `TAbstractObjectReader.ReadWideString` (326)

4.36.26 TAbstractObjectReader.SkipComponent

Synopsis: Skip till the end of the component.

Declaration: `procedure SkipComponent(SkipComponentInfos: Boolean); Virtual
; Abstract`

Visibility: public

Description: This method is used to skip the entire declaration of a component in the stream. Each descendant of `TAbstractObjectReader` should implement this in a way which is optimal for the implemented stream format.

See also: `TAbstractObjectReader.BeginComponent` (320), `TAbstractObjectReader.SkipValue` (327)

4.36.27 TAbstractObjectReader.SkipValue

Synopsis: Skip the current value.

Declaration: `procedure SkipValue; Virtual; Abstract`

Visibility: `public`

Description: `SkipValue` should be used when skipping a value in the stream; The method should determine the type of the value which should be skipped by itself, if this is necessary.

See also: `TAbstractObjectReader.SkipComponent` ([326](#))

4.37 TAbstractObjectWriter**4.37.1 Description**

Abstract driver class for writing component data.

4.37.2 Method overview

Page	Method	Description
327	<code>BeginCollection</code>	Start writing a collection.
328	<code>BeginComponent</code>	Start writing a component
328	<code>BeginList</code>	Start writing a list.
328	<code>BeginProperty</code>	Start writing a property
328	<code>EndList</code>	Mark the end of a list.
329	<code>EndProperty</code>	Marks the end of writing of a property.
329	<code>FlushBuffer</code>	Flush the buffer
329	<code>Write</code>	Write raw data to stream
329	<code>WriteBinary</code>	Writes binary data to the stream.
329	<code>WriteBoolean</code>	Writes a boolean value to the stream.
330	<code>WriteCurrency</code>	Write a currency value to the stream
330	<code>WriteDate</code>	Writes a date type to the stream.
330	<code>WriteFloat</code>	Writes a float value to the stream.
330	<code>WriteIdent</code>	Writes an identifier to the stream.
331	<code>WriteInteger</code>	Writes an integer value to the stream
331	<code>WriteMethodName</code>	Writes a methodname to the stream.
331	<code>WriteSet</code>	Writes a set value to the stream.
328	<code>WriteSignature</code>	Write stream signature to the stream
330	<code>WriteSingle</code>	Writes a single-type real value to the stream.
332	<code>WriteString</code>	Writes a string value to the stream.
331	<code>WriteUInt64</code>	Write an unsigned 64-bit integer
332	<code>WriteUnicodeString</code>	Write a Unicode string to the stream.
331	<code>WriteVariant</code>	Write a variant to the stream
332	<code>WriteWideString</code>	Write a widestring value to the stream

4.37.3 TAbstractObjectWriter.BeginCollection

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Virtual; Abstract`

Visibility: `public`

Description: Start writing a collection.

4.37.4 TAbstractObjectWriter.BeginComponent

Synopsis: Start writing a component

Declaration: `procedure BeginComponent (Component: TComponent; Flags: TFileFlags;
ChildPos: Integer); Virtual; Abstract`

Visibility: public

Description: Start writing a component

4.37.5 TAbstractObjectWriter.WriteSignature

Synopsis: Write stream signature to the stream

Declaration: `procedure WriteSignature; Virtual; Abstract`

Visibility: public

Description: `WriteSignature` writes the streaming signature to a stream. This method does nothing, it must be implemented by descendents that have a signature header in the stream. (such as binary streams)

See also: `TAbstractObjectReader.ReadSignature` ([325](#)), `TBinaryObjectWriter.WriteSignature` ([346](#))

4.37.6 TAbstractObjectWriter.BeginList

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Virtual; Abstract`

Visibility: public

Description: Start writing a list.

4.37.7 TAbstractObjectWriter.EndList

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Virtual; Abstract`

Visibility: public

Description: Mark the end of a list.

4.37.8 TAbstractObjectWriter.BeginProperty

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: string); Virtual; Abstract`

Visibility: public

Description: Start writing a property

4.37.9 TAbstractObjectWriter.EndProperty

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Virtual; Abstract`

Visibility: `public`

Description: Marks the end of writing of a property.

4.37.10 TAbstractObjectWriter.FlushBuffer

Synopsis: Flush the buffer

Declaration: `procedure FlushBuffer; Virtual`

Visibility: `public`

Description: `FlushBuffer` flushes the buffer. It is provided for Delphi compatibility, and is not used in FPC.

See also: `TFile.FlushBuffer` ([387](#)), `TWriter.FlushBuffer` ([517](#))

4.37.11 TAbstractObjectWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Virtual; Abstract`

Visibility: `public`

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TBinaryObjectWriter.Write` ([348](#)), `TWriter.Write` ([517](#))

4.37.12 TAbstractObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer; Count: LongInt); Virtual; Abstract`

Visibility: `public`

Description: Writes binary data to the stream.

4.37.13 TAbstractObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Virtual; Abstract`

Visibility: `public`

Description: Writes a boolean value to the stream.

4.37.14 TAbstractObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Virtual; Abstract`

Visibility: `public`

Description: Writes a float value to the stream.

4.37.15 TAbstractObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Virtual; Abstract`

Visibility: `public`

Description: Writes a single-type real value to the stream.

4.37.16 TAbstractObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Virtual; Abstract`

Visibility: `public`

Description: Writes a date type to the stream.

4.37.17 TAbstractObjectWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency(const Value: Currency); Virtual; Abstract`

Visibility: `public`

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendant classes.

See also: `TAbstractObjectReader.ReadCurrency` ([323](#))

4.37.18 TAbstractObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: string); Virtual; Abstract`

Visibility: `public`

Description: Writes an identifier to the stream.

4.37.19 TAbstractObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream

Declaration: `procedure WriteInteger(Value: Int64); Virtual; Abstract`

Visibility: public

Description: Writes an integer value to the stream

4.37.20 TAbstractObjectWriter.WriteUInt64

Synopsis: Write an unsigned 64-bit integer

Declaration: `procedure WriteUInt64(Value: QWord); Virtual; Abstract`

Visibility: public

Description: `WriteUInt64` must be overridden by descendant classes to write a 64-bit unsigned Value (value type `QWord`) to the stream.

Errors: None.

See also: `TBinaryObjectWriter.WriteUInt64` ([349](#))

4.37.21 TAbstractObjectWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const Value: Variant); Virtual; Abstract`

Visibility: public

Description: `WriteVariant` must be overridden by descendant classes to write a simple variant type to the stream. `WriteVariant` does not write arrays types or complex types.

See also: `TBinaryObjectWriter.WriteVariant` ([351](#))

4.37.22 TAbstractObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: string); Virtual; Abstract`

Visibility: public

Description: Writes a methodname to the stream.

4.37.23 TAbstractObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Virtual
; Abstract`

Visibility: public

Description: Writes a set value to the stream.

4.37.24 TAbstractObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: string); Virtual; Abstract`

Visibility: public

Description: Writes a string value to the stream.

4.37.25 TAbstractObjectWriter.WriteWideString

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString); Virtual; Abstract`

Visibility: public

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendant classes.

See also: `TAbstractObjectReader.ReadWideString` ([326](#))

4.37.26 TAbstractObjectWriter.WriteUnicodeString

Synopsis: Write a Unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString); Virtual
; Abstract`

Visibility: public

Description: `WriteUnicodeString` must be overridden by descendant classes to write a unicodestring (value type `vaUString`) value to the stream.

See also: `TBinaryObjectWriter.WriteUnicodeString` ([350](#))

4.38 TBasicAction**4.38.1 Description**

`TBasicAction` implements a basic action class from which all actions are derived. It introduces all basic methods of an action, and implements functionality to maintain a list of clients, i.e. components that are connected with this action.

Do not create instances of `TBasicAction`. Instead, create a descendant class and create an instance of this class instead.

See also: `TBasicActionLink` ([336](#)), `TComponent` ([369](#))

4.38.2 Method overview

Page	Method	Description
333	Create	Creates a new instance of a TBasicAction (332) class.
333	Destroy	Destroys the action.
334	Execute	Triggers the OnExecute (336) event
334	ExecuteTarget	Executes the action on the Target object
333	HandlesTarget	Determines whether Target can be handled by this action
335	RegisterChanges	Registers a new client with the action.
335	UnRegisterChanges	Unregisters a client from the list of clients
335	Update	Triggers the OnUpdate (336) event
334	UpdateTarget	Notify client controls when the action updates itself.

4.38.3 Property overview

Page	Properties	Access	Description
335	ActionComponent	rw	Returns the component that initiated the action.
336	OnExecute	rw	Event triggered when the action executes.
336	OnUpdate	rw	Event triggered when the application is idle.

4.38.4 TBasicAction.Create

Synopsis: Creates a new instance of a TBasicAction ([332](#)) class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` calls the inherited constructor, and then initializes the list of clients controls (or action lists).

Under normal circumstances it should not be necessary to create a TBasicAction descendant manually, actions are created in an IDE.

See also: `Destroy` ([333](#)), `AssignClient` ([332](#))

4.38.5 TBasicAction.Destroy

Synopsis: Destroys the action.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the list of client controls and then calls the inherited destructor.

An application programmer should not call `Destroy` directly; Instead `Free` should be called, if it needs to be called at all. Normally the controlling class (e.g. a TActionList) will destroy the action.

4.38.6 TBasicAction.HandlesTarget

Synopsis: Determines whether Target can be handled by this action

Declaration: `function HandlesTarget(Target: TObject) : Boolean; Virtual`

Visibility: `public`

Description: `HandlesTarget` returns `True` if `Target` is a valid client for this action and if so, if it is in a suitable state to execute the action. An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

In `TBasicAction` this method is empty; descendant classes should override this method to implement appropriate checks.

See also: `UpdateTarget` (334), `ExecuteTarget` (334)

4.38.7 `TBasicAction.UpdateTarget`

Synopsis: Notify client controls when the action updates itself.

Declaration: `procedure UpdateTarget(Target: TObject); Virtual`

Visibility: `public`

Description: `UpdateTarget` should update the client control specified by `Target` when the action updates itself. In `TBasicAction`, the implementation of `UpdateTarget` is empty. Descendant classes should override and implement `UpdateTarget` to actually update the `Target` object.

An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

See also: `HandlesTarget` (333), `ExecuteTarget` (334)

4.38.8 `TBasicAction.ExecuteTarget`

Synopsis: Executes the action on the `Target` object

Declaration: `procedure ExecuteTarget(Target: TObject); Virtual`

Visibility: `public`

Description: `ExecuteTarget` performs the action on the `Target` object. In `TBasicAction` this method does nothing. Descendant classes should implement the action to be performed. For instance an action to post data in a dataset could call the `Post` method of the dataset.

An application programmer should never call `ExecuteTarget` directly.

See also: `HandlesTarget` (333), `UpdateTarget` (334), `Execute` (334)

4.38.9 `TBasicAction.Execute`

Synopsis: Triggers the `OnExecute` (336) event

Declaration: `function Execute : Boolean; Dynamic`

Visibility: `public`

Description: `Execute` triggers the `OnExecute` event, if one is assigned. It returns `True` if the event handler was called, `False` otherwise.

4.38.10 TBasicAction.RegisterChanges

Synopsis: Registers a new client with the action.

Declaration: `procedure RegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `RegisterChanges` adds `Value` to the list of clients.

See also: `UnregisterChanges` (335)

4.38.11 TBasicAction.UnRegisterChanges

Synopsis: Unregisters a client from the list of clients

Declaration: `procedure UnRegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `UnregisterChanges` removes `Value` from the list of clients. This is called for instance when the action is destroyed, or when the client is assigned a new action.

See also: `UnregisterChanges` (335), `Destroy` (333)

4.38.12 TBasicAction.Update

Synopsis: Triggers the `OnUpdate` (336) event

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` triggers the `OnUpdate` event, if one is assigned. It returns `True` if the event was triggered, or `False` if no event was assigned.

Application programmers should never run `Update` directly. The `Update` method is called automatically by the action mechanism; Normally this is in the Idle time of an application. An application programmer should assign the `OnUpdate` (336) event, and perform any checks in that handler.

See also: `OnUpdate` (336), `Execute` (334), `UpdateTarget` (334)

4.38.13 TBasicAction.ActionComponent

Synopsis: Returns the component that initiated the action.

Declaration: `Property ActionComponent : TComponent`

Visibility: `public`

Access: `Read, Write`

Description: `ActionComponent` is set to the component that caused the action to execute, e.g. a toolbutton or a menu item. The property is set just before the action executes, and is reset to nil after the action was executed.

See also: `Execute` (334), `OnExecute` (336)

4.38.14 TBasicAction.OnExecute

Synopsis: Event triggered when the action executes.

Declaration: Property OnExecute : TNotifyEvent

Visibility: public

Access: Read,Write

Description: OnExecute is the event triggered when the action is activated (executed). The event is triggered e.g. when the user clicks e.g. on a menu item or a button associated to the action. The application programmer should provide a OnExecute event handler to execute whatever code is necessary when the button is pressed or the menu item is chosen.

Note that assigning an OnExecute handler will result in the Execute (334) method returning a True value. Predefined actions (such as dataset actions) will check the result of Execute and will not perform their normal task if the OnExecute handler was called.

See also: Execute (334), OnUpdate (336)

4.38.15 TBasicAction.OnUpdate

Synopsis: Event triggered when the application is idle.

Declaration: Property OnUpdate : TNotifyEvent

Visibility: public

Access: Read,Write

Description: OnUpdate is the event triggered when the application is idle, and the action is being updated. The OnUpdate event can be used to set the state of the action, for instance disable it if the action cannot be executed at this point in time.

See also: Update (335), OnExecute (336)

4.39 TBasicActionLink

4.39.1 Description

TBasicActionLink links an Action to its clients. With each client for an action, a TBasicActionLink class is instantiated to handle the communication between the action and the client. It passes events between the action and its clients, and thus presents the action with a uniform interface to the clients.

An application programmer should never use a TBasicActionLink instance directly; They are created automatically when an action is associated with a component. Component programmers should create specialized descendants of TBasicActionLink which communicate changes in the action to the component.

See also: TBasicAction (332)

4.39.2 Method overview

Page	Method	Description
337	Create	Creates a new instance of the TBasicActionLink class
337	Destroy	Destroys the TBasicActionLink instance.
337	Execute	Calls the action's Execute method.
338	Update	Calls the action's Update method

4.39.3 Property overview

Page	Properties	Access	Description
338	Action	rw	The action to which the link was assigned.
338	OnChange	rw	Event handler triggered when the action's properties change

4.39.4 TBasicActionLink.Create

Synopsis: Creates a new instance of the TBasicActionLink class

Declaration: `constructor Create(AClient: TObject); Virtual`

Visibility: public

Description: `Create` creates a new instance of a TBasicActionLink and assigns `AClient` as the client of the link.

Application programmers should never instantiate TBasicActionLink classes directly. An instance is created automatically when an action is assigned to a control (client).

Component programmers can override the create constructor to initialize further properties.

See also: `Destroy` ([337](#))

4.39.5 TBasicActionLink.Destroy

Synopsis: Destroys the TBasicActionLink instance.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` unregisters the TBasicActionLink with the action, and then calls the inherited destructor.

Application programmers should never call `Destroy` directly. If a link should be destroyed at all, the `Free` method should be called instead.

See also: `Create` ([337](#))

4.39.6 TBasicActionLink.Execute

Synopsis: Calls the action's `Execute` method.

Declaration: `function Execute(AComponent: TComponent) : Boolean; Virtual`

Visibility: public

Description: `Execute` sets the `ActionComponent` ([335](#)) property of the associated `Action` ([338](#)) to `AComponent` and then calls the `Action`'s `execute` ([334](#)) method. After the action has executed, the `ActionComponent` property is cleared again.

The return value of the function is the return value of the `Action`'s `execute` method.

Application programmers should never call `Execute` directly. This method will be called automatically when the associated control is activated. (e.g. a button is clicked on)

Component programmers should call `Execute` whenever the action should be activated.

See also: `Action` ([338](#)), `TBasicAction.ActionComponent` ([335](#)), `TBasicAction.Execute` ([334](#)), `TBasicAction.onExecute` ([336](#))

4.39.7 TBasicActionLink.Update

Synopsis: Calls the action's Update method

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` calls the associated Action's Update (335) method.

Component programmers can override the `Update` method to provide additional processing when the `Update` method occurs.

4.39.8 TBasicActionLink.Action

Synopsis: The action to which the link was assigned.

Declaration: `Property Action : TBasicAction`

Visibility: `public`

Access: `Read,Write`

Description: `Action` represents the Action (332) which was assigned to the client. Setting this property will unregister the client at the old action (if one existed) and registers the client at the new action.

See also: `TBasicAction` (332)

4.39.9 TBasicActionLink.OnChange

Synopsis: Event handler triggered when the action's properties change

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChange` is the event triggered when the action's properties change.

Application programmers should never need to assign this event. Component programmers can assign this event to have a client control reflect any changes in an Action's properties.

See also: `Change` (336), `TBasicAction.Change` (332)

4.40 TBinaryObjectReader

4.40.1 Description

The `TBinaryObjectReader` class reads component data stored in binary form in a file. For this, it overrides or implements all abstract methods from `TAbstractObjectReader` (319). No new functionality is added by this class, it is a driver class for the streaming system.

It should never be necessary to create an instance of this class directly. Instead, the `TStream.WriteComponent` (453) call should be used.

See also: `TAbstractObjectReader` (319), `TBinaryObjectWriter` (345)

4.40.2 Method overview

Page	Method	Description
340	<code>BeginComponent</code>	Start reading a component.
341	<code>BeginProperty</code>	Start reading a property.
340	<code>BeginRootComponent</code>	Start reading the root component.
339	<code>Create</code>	Creates a new binary data reader instance.
339	<code>Destroy</code>	Destroys the binary data reader.
340	<code>NextValue</code>	Return the type of the next value.
341	<code>Read</code>	Read raw data from stream
341	<code>ReadBinary</code>	Start reading a binary value.
342	<code>ReadCurrency</code>	Read a currency value from the stream.
342	<code>ReadDate</code>	Read a date.
341	<code>ReadFloat</code>	Read a float value
342	<code>ReadIdent</code>	Read an identifier
342	<code>ReadInt16</code>	Read a 16-bits integer.
343	<code>ReadInt32</code>	Read a 32-bits integer.
343	<code>ReadInt64</code>	Read a 64-bits integer.
342	<code>ReadInt8</code>	Read an 8-bits integer.
343	<code>ReadSet</code>	Read a set
343	<code>ReadSignature</code>	Reads the filer signature
341	<code>ReadSingle</code>	Read a single-size float value
344	<code>ReadStr</code>	Read a short string
344	<code>ReadString</code>	Read a string
344	<code>ReadUnicodeString</code>	Read a Unicode string value
340	<code>ReadValue</code>	Read the next value in the stream
344	<code>ReadWideString</code>	Read a widestring value from the stream.
345	<code>SkipComponent</code>	Skip a component's data
345	<code>SkipValue</code>	Skip a value's data

4.40.3 TBinaryObjectReader.Create

Synopsis: Creates a new binary data reader instance.

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: `Create` instantiates a new binary component data reader. The `Stream` stream is the stream from which data will be read. The `BufSize` argument is the size of the internal buffer that will be used by the reader. This can be used to optimize the reading process.

See also: `TAbstractObjectReader` ([319](#))

4.40.4 TBinaryObjectReader.Destroy

Synopsis: Destroys the binary data reader.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees the buffer allocated when the instance was created. It also positions the stream on the last used position in the stream (the buffering may cause the reader to read more bytes than were actually used.)

See also: `TBinaryObjectReader.Create` ([339](#))

4.40.5 TBinaryObjectReader.NextValue

Synopsis: Return the type of the next value.

Declaration: `function NextValue : TValueType; Override`

Visibility: `public`

Description: `NextValue` returns the type of the next value in a binary stream, but does not read the value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.6 TBinaryObjectReader.ReadValue

Synopsis: Read the next value in the stream

Declaration: `function ReadValue : TValueType; Override`

Visibility: `public`

Description: `NextValue` reads the next value in a binary stream and returns the type of the read value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.7 TBinaryObjectReader.BeginRootComponent

Synopsis: Start reading the root component.

Declaration: `procedure BeginRootComponent; Override`

Visibility: `public`

Description: `BeginRootComponent` starts reading the root component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.8 TBinaryObjectReader.BeginComponent

Synopsis: Start reading a component.

Declaration: `procedure BeginComponent (var Flags: TFileFlags;
var AChildPos: Integer;
var CompClassName: string; var CompName: string)
; Override`

Visibility: `public`

Description: This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.9 TBinaryObjectReader.BeginProperty

Synopsis: Start reading a property.

Declaration: `function BeginProperty : string; Override`

Visibility: `public`

Description: This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([319](#))

4.40.10 TBinaryObjectReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Override`

Visibility: `public`

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in production code as it will totally mess up the streaming.

See also: `TAbstractObjectReader.Read` ([321](#)), `TReader.Read` ([437](#))

4.40.11 TBinaryObjectReader.ReadBinary

Synopsis: Start reading a binary value.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Override`

Visibility: `public`

Description: `ReadBinary` reads a binary value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([319](#))

4.40.12 TBinaryObjectReader.ReadFloat

Synopsis: Read a float value

Declaration: `function ReadFloat : Extended; Override`

Visibility: `public`

Description: `ReadFloat` reads a float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([319](#))

4.40.13 TBinaryObjectReader.ReadSingle

Synopsis: Read a single-size float value

Declaration: `function ReadSingle : Single; Override`

Visibility: `public`

Description: `ReadSingle` reads a single-sized float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([319](#))

4.40.14 TBinaryObjectReader.ReadDate

Synopsis: Read a date.

Declaration: `function ReadDate : TDateTime; Override`

Visibility: `public`

Description: `ReadDate` reads a date value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([319](#))

4.40.15 TBinaryObjectReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency; Override`

Visibility: `public`

Description: `var>ReadCurrency` reads a currency-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` ([319](#)).

See also: `TAbstractObjectReader.ReadCurrency` ([323](#)), `TBinaryObjectWriter.WriteCurrency` ([349](#))

4.40.16 TBinaryObjectReader.ReadIdent

Synopsis: Read an identifier

Declaration: `function ReadIdent(ValueType: TValueType) : string; Override`

Visibility: `public`

Description: `ReadIdent` reads an identifier from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([319](#))

4.40.17 TBinaryObjectReader.ReadInt8

Synopsis: Read an 8-bits integer.

Declaration: `function ReadInt8 : ShortInt; Override`

Visibility: `public`

Description: `Read8Int` reads an 8-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([319](#))

4.40.18 TBinaryObjectReader.ReadInt16

Synopsis: Read a 16-bits integer.

Declaration: `function ReadInt16 : SmallInt; Override`

Visibility: `public`

Description: `Read16Int` reads a 16-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.19 `TBinaryObjectReader.ReadInt32`

Synopsis: Read a 32-bits integer.

Declaration: `function ReadInt32 : LongInt; Override`

Visibility: `public`

Description: `Read32Int` reads a 32-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.20 `TBinaryObjectReader.ReadInt64`

Synopsis: Read a 64-bits integer.

Declaration: `function ReadInt64 : Int64; Override`

Visibility: `public`

Description: `Read64Int` reads a 64-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.21 `TBinaryObjectReader.ReadSet`

Synopsis: Read a set

Declaration: `function ReadSet (EnumType: Pointer) : Integer; Override`

Visibility: `public`

Description: `ReadSet` reads a set from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.22 `TBinaryObjectReader.ReadSignature`

Synopsis: Reads the filer signature

Declaration: `procedure ReadSignature; Override`

Visibility: `public`

Description: `ReadSignature` is overridden by `TBinaryObjectReader` to read the signature (TPF0) from binary streams.

Errors: If the stream does not start with the correct signature, an `EReadError` (305) exception is raised.

See also: `TAbstractObjectReader.ReadSignature` (325), `TAbstractObjectWriter.WriteSignature` (328), `TBinaryObjectWriter.WriteSignature` (346)

4.40.23 TBinaryObjectReader.ReadStr

Synopsis: Read a short string

Declaration: `function ReadStr : string; Override`

Visibility: `public`

Description: `ReadStr` reads a short string from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.24 TBinaryObjectReader.ReadString

Synopsis: Read a string

Declaration: `function ReadString(StringType: TValueType) : string; Override`

Visibility: `public`

Description: `ReadStr` reads a string of type `StringType` from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.40.25 TBinaryObjectReader.ReadWideString

Synopsis: Read a widestring value from the stream.

Declaration: `function ReadWideString : WideString; Override`

Visibility: `public`

Description: `var>ReadWideString` reads a widestring-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` (319).

See also: `TAbstractObjectReader.ReadWideString` (326), `TBinaryObjectWriter.WriteWideString` (350)

4.40.26 TBinaryObjectReader.ReadUnicodeString

Synopsis: Read a Unicode string value

Declaration: `function ReadUnicodeString : UnicodeString; Override`

Visibility: `public`

Description: `ReadUnicodeString` is overridden by `TBinaryObjectReader` to read a `UnicodeString` value from the binary stream.

See also: `TAbstractObjectReader.ReadUnicodeString` (326)

4.40.27 TBinaryObjectReader.SkipComponent

Synopsis: Skip a component's data

Declaration: `procedure SkipComponent (SkipComponentInfos: Boolean);` Override

Visibility: public

Description: `SkipComponent` skips the data of a component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319).

4.40.28 TBinaryObjectReader.SkipValue

Synopsis: Skip a value's data

Declaration: `procedure SkipValue;` Override

Visibility: public

Description: `SkipComponent` skips the data of the next value in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (319)

4.41 TBinaryObjectWriter

4.41.1 Description

Driver class which stores component data in binary form.

4.41.2 Method overview

Page	Method	Description
347	BeginCollection	Start writing a collection.
347	BeginComponent	Start writing a component
347	BeginList	Start writing a list.
348	BeginProperty	Start writing a property
346	Create	Creates a new instance of a binary object writer.
346	Destroy	Destroys an instance of the binary object writer.
347	EndList	Mark the end of a list.
348	EndProperty	Marks the end of writing of a property.
347	FlushBuffer	Flush the buffer
348	Write	Write raw data to stream
348	WriteBinary	Writes binary data to the stream.
348	WriteBoolean	Writes a boolean value to the stream.
349	WriteCurrency	Write a currency-valued type to a stream
349	WriteDate	Writes a date type to the stream.
348	WriteFloat	Writes a float value to the stream.
349	WriteIdent	Writes an identifier to the stream.
349	WriteInteger	Writes an integer value to the stream.
350	WriteMethodName	Writes a methodname to the stream.
350	WriteSet	Writes a set value to the stream.
346	WriteSignature	Write stream signature to the stream
349	WriteSingle	Writes a single-type real value to the stream.
350	WriteStr	Write a string to the binary stream
350	WriteString	Writes a string value to the stream.
349	WriteUInt64	Write an unsigned 64-bit integer
350	WriteUnicodeString	Write a Unicode string to the stream.
351	WriteVariant	Write a variant to the stream
350	WriteWideString	Write a widestring-valued type to a stream

4.41.3 TBinaryObjectWriter.Create

Synopsis: Creates a new instance of a binary object writer.

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new instance of a binary object writer.

4.41.4 TBinaryObjectWriter.Destroy

Synopsis: Destroys an instance of the binary object writer.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys an instance of the binary object writer.

4.41.5 TBinaryObjectWriter.WriteSignature

Synopsis: Write stream signature to the stream

Declaration: `procedure WriteSignature; Override`

Visibility: `public`

Description: `WriteSignature` is overridden by `TBinaryObjectWriter` to write the signature (TPF0) to binary streams.

See also: `TAbstractObjectWriter.WriteSignature` (328), `TAbstractObjectReader.ReadSignature` (325), `TBinaryObjectReader.ReadSignature` (343)

4.41.6 TBinaryObjectWriter.FlushBuffer

Synopsis: Flush the buffer

Declaration: `procedure FlushBuffer; Override`

Visibility: `public`

Description: `FlushBuffer` flushes the buffer. It is provided for Delphi compatibility, and is not used in FPC.

See also: `TFile.FlushBuffer` (387), `TWriter.FlushBuffer` (517), `TAbstractObjectWriter.FlushBuffer` (329)

4.41.7 TBinaryObjectWriter.BeginCollection

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Override`

Visibility: `public`

4.41.8 TBinaryObjectWriter.BeginComponent

Synopsis: Start writing a component

Declaration: `procedure BeginComponent(Component: TComponent; Flags: TFileFlags;
ChildPos: Integer); Override`

Visibility: `public`

4.41.9 TBinaryObjectWriter.BeginList

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Override`

Visibility: `public`

4.41.10 TBinaryObjectWriter.EndList

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Override`

Visibility: `public`

4.41.11 TBinaryObjectWriter.BeginProperty

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: string); Override`

Visibility: public

4.41.12 TBinaryObjectWriter.EndProperty

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Override`

Visibility: public

4.41.13 TBinaryObjectWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Override`

Visibility: public

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TAbstractObjectWriter.Write` ([329](#)), `TWriter.Write` ([517](#))

4.41.14 TBinaryObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer; Count: LongInt); Override`

Visibility: public

4.41.15 TBinaryObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Override`

Visibility: public

4.41.16 TBinaryObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Override`

Visibility: public

4.41.17 TBinaryObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Override`

Visibility: public

4.41.18 TBinaryObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Override`

Visibility: public

4.41.19 TBinaryObjectWriter.WriteCurrency

Synopsis: Write a currency-valued type to a stream

Declaration: `procedure WriteCurrency(const Value: Currency); Override`

Visibility: public

Description: `WriteCurrency` writes a currency-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` ([327](#)).

See also: `TAbstractObjectWriter.WriteCurrency` ([330](#))

4.41.20 TBinaryObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: string); Override`

Visibility: public

4.41.21 TBinaryObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream.

Declaration: `procedure WriteInteger(Value: Int64); Override`

Visibility: public

4.41.22 TBinaryObjectWriter.WriteUInt64

Synopsis: Write an unsigned 64-bit integer

Declaration: `procedure WriteUInt64(Value: QWord); Override`

Visibility: public

Description: `WriteUInt64` is overridden by `TBinaryObjectWriter` to write an unsigned 64-bit integer (`QWord`) to the stream. It tries to use the smallest possible storage for the value that is passed. (largest valuetype will be `vaQWord`).

See also: `TAbstractObjectWriter.WriteUInt64` ([331](#))

4.41.23 TBinaryObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: string); Override`

Visibility: public

4.41.24 TBinaryObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Override`

Visibility: public

4.41.25 TBinaryObjectWriter.WriteString

Synopsis: Write a string to the binary stream

Declaration: `procedure WriteStr(const Value: string)`

Visibility: public

Description: `WriteStr` writes a string value to the binary stream. It is exposed so it can be used in `DefineProperties`.

4.41.26 TBinaryObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: string); Override`

Visibility: public

4.41.27 TBinaryObjectWriter.WriteString

Synopsis: Write a widestring-valued type to a stream

Declaration: `procedure WriteWideString(const Value: WideString); Override`

Visibility: public

Description: `WriteWideString` writes a widestring-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` (327).

See also: `TAbstractObjectWriter.WriteString` (332)

4.41.28 TBinaryObjectWriter.WriteString

Synopsis: Write a Unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString); Override`

Visibility: public

Description: `WriteUnicodeString` is overridden `TBinaryObjectWriter` to write a `unicodestring` (valuetype `vaUString`) value to the stream. It simply writes the character length and then all widecharacters.

See also: `TAbstractObjectWriter.WriteString` (332)

4.41.29 TBinaryObjectWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const VarValue: Variant);` Override

Visibility: public

Description: `WriteVariant` is overridden by `TBinaryObjectWriter` to write a simple variant type to the stream. `WriteVariant` does not write arrays types or complex types. Only null, integer (ordinal) float and string types are written.

Errors: If a non-supported type is written, then an `EWriteError` exception is.

4.42 TBits

4.42.1 Description

`TBits` can be used to store collections of bits in an indexed array. This is especially useful for storing collections of booleans: Normally the size of a boolean is the size of the smallest enumerated type, i.e. 1 byte. Since a bit can take 2 values it can be used to store a boolean as well. Since `TBits` can store 8 bits in a byte, it takes 8 times less space to store an array of booleans in a `TBits` class then it would take to store them in a conventional array.

`TBits` introduces methods to store and retrieve bit values, apply masks, and search for bits.

4.42.2 Method overview

Page	Method	Description
353	<code>AndBits</code>	Performs an <code>and</code> operation on the bits.
353	<code>Clear</code>	Clears a particular bit.
353	<code>Clearall</code>	Clears all bits in the array.
353	<code>CopyBits</code>	Copy bits from one bits set to another
352	<code>Create</code>	Creates a new bits collection.
352	<code>Destroy</code>	Destroys a bit collection
355	<code>Equals</code>	Determines whether the bits of 2 arrays are equal.
356	<code>FindFirstBit</code>	Find first bit with a particular value
356	<code>FindNextBit</code>	Searches the next bit with a particular value.
356	<code>FindPrevBit</code>	Searches the previous bit with a particular value.
355	<code>Get</code>	Retrieve the value of a particular bit
352	<code>GetFSize</code>	Returns the number of records used to store the bits.
355	<code>Grow</code>	Expands the bits array to the requested size.
354	<code>NotBits</code>	Performs a <code>not</code> operation on the bits.
357	<code>OpenBit</code>	Returns the position of the first bit that is set to <code>False</code> .
354	<code>OrBits</code>	Performs an <code>or</code> operation on the bits.
355	<code>SetIndex</code>	Sets the start position for <code>FindNextBit</code> (356) and <code>FindPrevBit</code> (356)
352	<code>SetOn</code>	Turn a particular bit on.
354	<code>XorBits</code>	Performs a <code>xor</code> operation on the bits.

4.42.3 Property overview

Page	Properties	Access	Description
357	<code>Bits</code>	<code>rw</code>	Access to all bits in the array.
357	<code>Size</code>	<code>rw</code>	Current size of the array of bits.

4.42.4 TBits.Create

Synopsis: Creates a new bits collection.

Declaration: `constructor Create(TheSize: LongInt); Virtual`

Visibility: `public`

Description: `Create` creates a new bit collection with initial size `TheSize`. The size of the collection can be changed later on.

All bits are initially set to zero.

See also: `Destroy` ([352](#))

4.42.5 TBits.Destroy

Synopsis: Destroys a bit collection

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys a previously created bit collection and releases all memory used to store the bit collection.

`Destroy` should never be called directly, `Free` should be used instead.

Errors: None.

See also: `Create` ([352](#))

4.42.6 TBits.GetFSize

Synopsis: Returns the number of records used to store the bits.

Declaration: `function GetFSize : LongInt`

Visibility: `public`

Description: `GetFSize` returns the number of records used to store the current number of bits.

Errors: None.

See also: `Size` ([357](#))

4.42.7 TBits.SetOn

Synopsis: Turn a particular bit on.

Declaration: `procedure SetOn(Bit: LongInt)`

Visibility: `public`

Description: `SetOn` turns on the bit at position `bit`, i.e. sets it to 1. If `bit` is at a position bigger than the current size, the collection is expanded to the required size using `Grow` ([355](#)).

Errors: If `bit` is larger than the maximum allowed bits array size or is negative, an `EBitsError` ([302](#)) exception is raised.

See also: `Bits` ([357](#)), `Clear` ([353](#))

4.42.8 TBits.Clear

Synopsis: Clears a particular bit.

Declaration: `procedure Clear(Bit: LongInt)`

Visibility: `public`

Description: `Clear` clears the bit at position `bit`. If the array `bit` is at a position bigger than the current size, the collection is expanded to the required size using `Grow` (355).

Errors: If `bit` is larger than the maximum allowed bits array size or is negative, an `EBitsError` (302) exception is raised.

See also: `Bits` (357), `seton` (353)

4.42.9 TBits.Clearall

Synopsis: Clears all bits in the array.

Declaration: `procedure Clearall`

Visibility: `public`

Description: `ClearAll` clears all bits in the array, i.e. sets them to zero. `ClearAll` works faster than clearing all individual bits, since it uses the packed nature of the bits.

Errors: None.

See also: `Bits` (357), `clear` (353)

4.42.10 TBits.CopyBits

Synopsis: Copy bits from one bits set to another

Declaration: `procedure CopyBits(BitSet: TBits)`

Visibility: `public`

Description: `CopyBits` copies the bits from `BitSet` to the current `Bits`. Existing bits will be overwritten. The two sets of bits will be equal after this operation.

Errors: None.

See also: `TBits.Equals` (355)

4.42.11 TBits.AndBits

Synopsis: Performs an and operation on the bits.

Declaration: `procedure AndBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an and operation on the bits in the array with the bits of array `BitSet`. If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are cleared.

Errors: None.

See also: `ClearAll` (353), `OrBits` (354), `XOrBits` (354), `NotBits` (354)

4.42.12 TBits.OrBits

Synopsis: Performs an `or` operation on the bits.

Declaration: `procedure OrBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an `or` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `or` operation is performed.

Errors: None.

See also: `ClearAll` (353), `andBits` (353), `XorBits` (354), `NotBits` (354)

4.42.13 TBits.XorBits

Synopsis: Performs a `xor` operation on the bits.

Declaration: `procedure XorBits(BitSet: TBits)`

Visibility: `public`

Description: `XorBits` performs a `xor` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `xor` operation is performed.

Errors: None.

See also: `ClearAll` (353), `andBits` (353), `OrBits` (354), `NotBits` (354)

4.42.14 TBits.NotBits

Synopsis: Performs a `not` operation on the bits.

Declaration: `procedure NotBits(BitSet: TBits)`

Visibility: `public`

Description: `NotBits` performs a `not` operation on the bits in the array with the bits of array `Bitset`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

Errors: None.

See also: `ClearAll` (353), `andBits` (353), `OrBits` (354), `XorBits` (354)

4.42.15 TBits.Get

Synopsis: Retrieve the value of a particular bit

Declaration: `function Get (Bit: LongInt) : Boolean`

Visibility: public

Description: `Get` returns `True` if the bit at position `bit` is set, or `False` if it is not set.

Errors: If `bit` is not a valid bit index then an `EBitsError` (302) exception is raised.

See also: `Bits` (357), `FindFirstBit` (356), `seton` (352)

4.42.16 TBits.Grow

Synopsis: Expands the bits array to the requested size.

Declaration: `procedure Grow (NBit: LongInt)`

Visibility: public

Description: `Grow` expands the bit array so it can at least contain `nbit` bits. If `nbit` is less than the current size, nothing happens.

Errors: If there is not enough memory to complete the operation, then an `EBitsError` (302) is raised.

See also: `Size` (357)

4.42.17 TBits.Equals

Synopsis: Determines whether the bits of 2 arrays are equal.

Declaration: `function Equals (Obj: TObject) : Boolean; Override; Overload`
`function Equals (BitSet: TBits) : Boolean; Overload`

Visibility: public

Description: `equals` returns `True` if all the bits in `BitSet` are the same as the ones in the current `BitSet`; if not, `False` is returned.

If the sizes of the two `BitSets` are different, the arrays are still reported equal when all the bits in the larger set, which are not present in the smaller set, are zero.

Errors: None.

See also: `ClearAll` (353), `andBits` (353), `OrBits` (354), `XOrBits` (354)

4.42.18 TBits.SetIndex

Synopsis: Sets the start position for `FindNextBit` (356) and `FindPrevBit` (356)

Declaration: `procedure SetIndex (Index: LongInt)`

Visibility: public

Description: `SetIndex` sets the search start position for `FindNextBit` (356) and `FindPrevBit` (356) to `Index`. This means that these calls will start searching from position `Index`.

This mechanism provides an alternative to `FindFirstBit` (356) which can also be used to position for the `FindNextBit` and `FindPrevBit` calls.

Errors: None.

See also: [FindNextBit \(356\)](#), [FindPrevBit \(356\)](#), [FindFirstBit \(356\)](#), [OpenBit \(357\)](#)

4.42.19 TBits.FindFirstBit

Synopsis: Find first bit with a particular value

Declaration: `function FindFirstBit (State: Boolean) : LongInt`

Visibility: public

Description: `FindFirstBit` searches for the first bit with value `State`. It returns the position of this bit, or `-1` if no such bit was found.

The search starts at position 0 in the array. If the first search returned a positive result, the found position is saved, and the [FindNextBit \(356\)](#) and [FindPrevBit \(356\)](#) will use this position to resume the search. To start a search from a certain position, the start position can be set with the [SetIndex \(355\)](#) instead.

Errors: None.

See also: [FindNextBit \(356\)](#), [FindPrevBit \(356\)](#), [OpenBit \(357\)](#), [SetIndex \(355\)](#)

4.42.20 TBits.FindNextBit

Synopsis: Searches the next bit with a particular value.

Declaration: `function FindNextBit : LongInt`

Visibility: public

Description: `FindNextBit` resumes a previously started search. It searches for the next bit with the value specified in the [FindFirstBit \(356\)](#). The search is done towards the end of the array and starts at the position last reported by one of the `Find` calls or at the position set with [SetIndex \(355\)](#).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: [FindFirstBit \(356\)](#), [FindPrevBit \(356\)](#), [OpenBit \(357\)](#), [SetIndex \(355\)](#)

4.42.21 TBits.FindPrevBit

Synopsis: Searches the previous bit with a particular value.

Declaration: `function FindPrevBit : LongInt`

Visibility: public

Description: `FindPrevBit` resumes a previously started search. It searches for the previous bit with the value specified in the [FindFirstBit \(356\)](#). The search is done towards the beginning of the array and starts at the position last reported by one of the `Find` calls or at the position set with [SetIndex \(355\)](#).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: [FindFirstBit \(356\)](#), [FindNextBit \(356\)](#), [OpenBit \(357\)](#), [SetIndex \(355\)](#)

4.42.22 TBits.OpenBit

Synopsis: Returns the position of the first bit that is set to `False`.

Declaration: `function OpenBit : LongInt`

Visibility: `public`

Description: `OpenBit` returns the position of the first bit whose value is 0 (`False`), or `-1` if no open bit was found. This call is equivalent to `FindFirstBit(False)`, except that it doesn't set the position for the next searches.

Errors: None.

See also: `FindNextBit` (356), `FindPrevBit` (356), `FindFirstBit` (356), `SetIndex` (355)

4.42.23 TBits.Bits

Synopsis: Access to all bits in the array.

Declaration: `Property Bits[Bit: LongInt]: Boolean; default`

Visibility: `public`

Access: `Read, Write`

Description: `Bits` allows indexed access to all of the bits in the array. It gives `True` if the bit is 1, `False` otherwise; Assigning to this property will set, respectively clear the bit.

Errors: If an index is specified which is out of the allowed range then an `EBitsError` (302) exception is raised.

See also: `Size` (357)

4.42.24 TBits.Size

Synopsis: Current size of the array of bits.

Declaration: `Property Size : LongInt`

Visibility: `public`

Access: `Read, Write`

Description: `Size` is the current size of the bit array. Setting this property will adjust the size; this is equivalent to calling `Grow(Value-1)`

Errors: If an invalid size (negative or too large) is specified, a `EBitsError` (302) exception is raised.

See also: `Bits` (357)

4.43 TBytesStream

4.43.1 Description

`TBytesStream` is a stream that uses an array of byte (`TBytes` (266)) to keep the stream data. it overrides the `TMemoryStream` (418) memory allocation routine to use the array of bytes. The array of bytes is exposed through the `Bytes` (266) property.

See also: `TBytes` (266), `TMemoryStream` (418), `Bytes` (266)

4.43.2 Method overview

Page	Method	Description
358	Create	Create a new instance of the stream, initializing it with an array of bytes

4.43.3 Property overview

Page	Properties	Access	Description
358	Bytes	r	The stream data as an array of bytes.

4.43.4 TBytesStream.Create

Synopsis: Create a new instance of the stream, initializing it with an array of bytes

Declaration: `constructor Create(const ABytes: TBytes); Virtual; Overload`

Visibility: public

Description: `Create` creates a new instance and initializes the memory with the data in `ABytes`.

See also: `TBytes` ([266](#)), `TMemoryStream` ([418](#)), `Bytes` ([266](#))

4.43.5 TBytesStream.Bytes

Synopsis: The stream data as an array of bytes.

Declaration: `Property Bytes : TBytes`

Visibility: public

Access: Read

Description: `Bytes` provides byte-sized access to the array of bytes that represent the stream data. As a pointer value, it equals `TCustomMemoryStream.Memory` ([382](#)), meaning that `Memory` points to the first byte in the array.

See also: `TBytes` ([266](#)), `TMemoryStream` ([418](#)), `TCustomMemoryStream.Memory` ([382](#))

4.44 TCollection

4.44.1 Description

`TCollection` implements functionality to manage a collection of named objects. Each of these objects needs to be a descendant of the `TCollectionItem` ([366](#)) class. Exactly which type of object is managed can be seen from the `TCollection.ItemClass` ([364](#)) property.

Normally, no `TCollection` is created directly. Instead, a descendants of `TCollection` and `TCollectionItem` ([366](#)) are created as a pair.

See also: `TCollectionItem` ([366](#))

4.44.2 Method overview

Page	Method	Description
360	Add	Creates and adds a new item to the collection.
360	Assign	Assigns one collection to another.
360	BeginUpdate	Start an update batch.
361	Clear	Removes all items from the collection.
359	Create	Creates a new collection.
361	Delete	Delete an item from the collection.
359	Destroy	Destroys the collection and frees all the objects it manages.
361	EndUpdate	Ends an update batch.
363	Exchange	Exchange 2 items in the collection
362	FindItemID	Searches for an Item in the collection, based on its TCollectionItem.ID (368) property.
362	GetEnumerator	Create an IEnumerator instance
362	GetNamePath	Overrides TPersistent.GetNamePath (430) to return a proper pathname.
362	Insert	Insert an item in the collection.
363	Move	Move an item in the collection
360	Owner	Owner of the collection.
363	Sort	Sort the items in the collection

4.44.3 Property overview

Page	Properties	Access	Description
364	Count	r	Number of items in the collection.
364	ItemClass	r	Class pointer for each item in the collection.
364	Items	rw	Indexed array of items in the collection.

4.44.4 TCollection.Create

Synopsis: Creates a new collection.

Declaration: constructor Create(AItemClass: TCollectionItemClass)

Visibility: public

Description: Create instantiates a new instance of the TCollection class which will manage objects of class AItemClass. It creates the list used to hold all objects, and stores the AItemClass for the adding of new objects to the collection.

See also: TCollection.ItemClass ([364](#)), TCollection.Destroy ([359](#))

4.44.5 TCollection.Destroy

Synopsis: Destroys the collection and frees all the objects it manages.

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy first clears the collection, and then frees all memory allocated to this instance.

Don't call Destroy directly, call Free instead.

See also: TCollection.Create ([359](#))

4.44.6 TCollection.Owner

Synopsis: Owner of the collection.

Declaration: `function Owner : TPersistent`

Visibility: `public`

Description: `Owner` returns a reference to the owner of the collection. This property is required by the object inspector to be able to show the collection.

4.44.7 TCollection.Add

Synopsis: Creates and adds a new item to the collection.

Declaration: `function Add : TCollectionItem`

Visibility: `public`

Description: `Add` instantiates a new item of class `TCollection.ItemClass` (364) and adds it to the list. The newly created object is returned.

See also: `TCollection.ItemClass` (364), `TCollection.Clear` (361)

4.44.8 TCollection.Assign

Synopsis: Assigns one collection to another.

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: `Assign` assigns the contents of one collection to another. It does this by clearing the items list, and adding as much elements as there are in the `Source` collection; it assigns to each created element the contents of it's counterpart in the `Source` element.

Two collections cannot be assigned to each other if instances of the `ItemClass` classes cannot be assigned to each other.

Errors: If the objects in the collections cannot be assigned to one another, then an `EConvertError` is raised.

See also: `TPersistent.Assign` (429), `TCollectionItem` (366)

4.44.9 TCollection.BeginUpdate

Synopsis: Start an update batch.

Declaration: `procedure BeginUpdate; Virtual`

Visibility: `public`

Description: `BeginUpdate` is called at the beginning of a batch update. It raises the update count with 1.

Call `BeginUpdate` at the beginning of a series of operations that will change the state of the collection. This will avoid the call to `TCollection.Update` (358) for each operation. At the end of the operations, a corresponding call to `EndUpdate` must be made. It is best to do this in the context of a `Try ... finally` block:

```

With MyCollection Do
  try
    BeginUpdate;
    // Some Lengthy operations
  finally
    EndUpdate;
  end;

```

This insures that the number of calls to `BeginUpdate` always matches the number of calls to `TCollection.EndUpdate` (361), even in case of an exception.

See also: `TCollection.EndUpdate` (361), `TCollection.Changed` (358), `TCollection.Update` (358)

4.44.10 TCollection.Clear

Synopsis: Removes all items from the collection.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` will clear the collection, i.e. each item in the collection is destroyed and removed from memory. After a call to `Clear`, `Count` is zero.

See also: `TCollection.Add` (360), `TCollectionItem.Destroy` (367), `TCollection.Destroy` (359)

4.44.11 TCollection.EndUpdate

Synopsis: Ends an update batch.

Declaration: `procedure EndUpdate; Virtual`

Visibility: `public`

Description: `EndUpdate` signals the end of a series of operations that change the state of the collection, possibly triggering an update event. It does this by decreasing the update count with 1 and calling `TCollection.Changed` (358) it should always be used in conjunction with `TCollection.BeginUpdate` (360), preferably in the `Finally` section of a `Try ... Finally` block.

See also: `TCollection.BeginUpdate` (360), `TCollection.Changed` (358), `TCollection.Update` (358)

4.44.12 TCollection.Delete

Synopsis: Delete an item from the collection.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` deletes the item at (zero based) position `Index` from the collection. This will result in a `cnDeleted` notification.

Errors: If an invalid index is specified, an `EListError` exception is raised.

See also: `TCollection.Items` (364), `TCollection.Insert` (362), `TCollection.Clear` (361)

4.44.13 TCollection.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TCollectionEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1589) interface for `TCollection`. It creates a `TCollectionEnumerator` (365) instance and returns its `IEnumerator` (1589) interface.

See also: `TCollectionEnumerator` (365), `IEnumerator` (1589), `IEnumerable` (1589)

4.44.14 TCollection.GetNamePath

Synopsis: Overrides `TPersistent.GetNamePath` (430) to return a proper pathname.

Declaration: `function GetNamePath : string; Override`

Visibility: public

Description: `GetNamePath` returns the name path for this collection. If the following conditions are satisfied:

1. There is an owner object.
2. The owner object returns a non-empty name path.
3. The `TCollection.Propname` (358) property is not empty

collection has an owner and the owning object has a name, then the function returns the owner name, followed by the propname. If one of the conditions is not satisfied, then the classname is returned.

See also: `TCollection.GetOwner` (358), `TCollection.Propname` (358)

4.44.15 TCollection.Insert

Synopsis: Insert an item in the collection.

Declaration: `function Insert(Index: Integer) : TCollectionItem`

Visibility: public

Description: `Insert` creates a new item instance and inserts it in the collection at position `Index`, and returns the new instance.

In contrast, `TCollection.Add` (360) adds a new item at the end.

Errors: None.

See also: `TCollection.Add` (360), `TCollection.Delete` (361), `TCollection.Items` (364)

4.44.16 TCollection.FindItemID

Synopsis: Searches for an Item in the collection, based on its `TCollectionItem.ID` (368) property.

Declaration: `function FindItemID(ID: Integer) : TCollectionItem`

Visibility: public

Description: `FindItemID` searches through the collection for the item that has a value of `ID` for its `TCollectionItem.ID` (368) property, and returns the found item. If no such item is found in the collection, `Nil` is returned.

The routine performs a linear search, so this can be slow on very large collections.

See also: `TCollection.Items` (364), `TCollectionItem.ID` (368)

4.44.17 TCollection.Exchange

Synopsis: Exchange 2 items in the collection

Declaration: `procedure Exchange(const Index1: Integer; const index2: Integer)`

Visibility: public

Description: `Exchange` exchanges the items at indexes `Index1` and `Index2` in the collection.

Errors: If one of the two indexes is invalid (less than zero or larger than the number of items) an `EListError` exception is raised.

See also: `Items` (364), `TCollectionItem.Index` (368)

4.44.18 TCollection.Move

Synopsis: Move an item in the collection

Declaration: `procedure Move(const Index1: Integer; const index2: Integer)`

Visibility: public

Description: `Move` will move the collection item from position `index1` to `Index2`. In difference with `Exchange` (363) the indexes of the elements between `index1` to `Index2` will shift.

Errors: If an invalid index is specified in `index1` or `Index2`, an exception will be raised.

See also: `TCollection.Exchange` (363)

4.44.19 TCollection.Sort

Synopsis: Sort the items in the collection

Declaration: `procedure Sort(const Compare: TCollectionSortCompare)`

Visibility: public

Description: `Sort` sorts the items in the collection, and uses the `Compare` procedure to compare 2 items in the collection. It is more efficient do use this method than to perform the sort manually, because the list items are manipulated directly.

For more information on how the `Compare` function should behave, see the `TCollectionSortCompare` (271) type.

See also: `TCollectionSortCompare` (271)

4.44.20 TCollection.Count

Synopsis: Number of items in the collection.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` contains the number of items in the collection.

Remark The items in the collection are identified by their `TCollectionItem.Index` (368) property, which is a zero-based index, meaning that it can take values between 0 and `Count-1`, borders included.

See also: `TCollectionItem.Index` (368), `TCollection.Items` (364)

4.44.21 TCollection.ItemClass

Synopsis: Class pointer for each item in the collection.

Declaration: `Property ItemClass : TCollectionItemClass`

Visibility: public

Access: Read

Description: `ItemClass` is the class pointer with which each new item in the collection is created. It is the value that was passed to the collection's constructor when it was created, and does not change during the lifetime of the collection.

See also: `TCollectionItem` (366), `TCollection.Items` (364)

4.44.22 TCollection.Items

Synopsis: Indexed array of items in the collection.

Declaration: `Property Items[Index: Integer]: TCollectionItem`

Visibility: public

Access: Read, Write

Description: `Items` provides indexed access to the items in the collection. Since the array is zero-based, `Index` should be an integer between 0 and `Count-1`.

It is possible to set or retrieve an element in the array. When setting an element of the array, the object that is assigned should be compatible with the class of the objects in the collection, as given by the `TCollection.ItemClass` (364) property.

Adding an element to the array can be done with the `TCollection.Add` (360) method. The array can be cleared with the `TCollection.Clear` (361) method. Removing an element of the array should be done by freeing that element.

See also: `TCollection.Count` (364), `TCollection.ItemClass` (364), `TCollection.Clear` (361), `TCollection.Add` (360)

4.45 TCollectionEnumerator

4.45.1 Description

`TCollectionEnumerator` implements the `#rtl.system.IEnumerator` (1589) interface for the `TCollection` (358) class, so the `TCollection` class can be used in a `for ... in` loop. It is returned by the `TCollection.GetEnumerator` (362) method of `TCollection`.

See also: `TCollection` (358), `TCollection.GetEnumerator` (362), `#rtl.system.IEnumerator` (1589)

4.45.2 Method overview

Page	Method	Description
365	<code>Create</code>	Initialize a new instance of <code>TCollectionEnumerator</code>
365	<code>GetCurrent</code>	Return the current pointer in the list
365	<code>MoveNext</code>	Move the position of the enumerator to the next position in the collection.

4.45.3 Property overview

Page	Properties	Access	Description
366	<code>Current</code>	<code>r</code>	Current pointer in the list

4.45.4 TCollectionEnumerator.Create

Synopsis: Initialize a new instance of `TCollectionEnumerator`

Declaration: `constructor Create (ACollection: TCollection)`

Visibility: `public`

Description: `Create` initializes a new instance of `TCollectionEnumerator` and keeps a reference to the collection `ACollection` that will be enumerated.

See also: `TCollection` (358)

4.45.5 TCollectionEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : TCollectionItem`

Visibility: `public`

Description: `GetCurrent` returns the current `TCollectionItem` (366) instance in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (365), `TCollectionItem` (366)

4.45.6 TCollectionEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the collection.

Declaration: `function MoveNext : Boolean`

Visibility: public

Description: `MoveNext` puts the pointer on the next item in the collection, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` (365)

4.45.7 `TCollectionEnumerator.Current`

Synopsis: Current pointer in the list

Declaration: `Property Current : TCollectionItem`

Visibility: public

Access: Read

Description: `Current` redefines `GetCurrent` (365) as a property.

See also: `GetCurrent` (365)

4.46 `TCollectionItem`

4.46.1 Description

`TCollectionItem` and `TCollection` (358) form a pair of base classes that manage a collection of named objects. The `TCollectionItem` is the named object that is managed, it represents one item in the collection. An item in the collection is represented by three properties: `TCollectionItem.DisplayName` (368), `TCollection.Index` (358) and `TCollectionItem.ID` (368).

A `TCollectionItem` object is never created directly. To manage a set of named items, it is necessary to make a descendant of `TCollectionItem` to which needed properties and methods are added. This descendant can then be managed with a `TCollection` (358) class. The managing collection will create and destroy it's items by itself, it should therefore never be necessary to create `TCollectionItem` descendants manually.

See also: `TCollection` (358)

4.46.2 Method overview

Page	Method	Description
367	<code>Create</code>	Creates a new instance of this collection item.
367	<code>Destroy</code>	Destroys this collection item.
367	<code>GetNamePath</code>	Returns the namepath of this collection item.

4.46.3 Property overview

Page	Properties	Access	Description
367	<code>Collection</code>	rw	Pointer to the collection managing this item.
368	<code>DisplayName</code>	rw	Name of the item, displayed in the object inspector.
368	<code>ID</code>	r	Initial index of this item.
368	<code>Index</code>	rw	Index of the item in its managing collection <code>TCollection.Items</code> (364) property.

4.46.4 TCollectionItem.Create

Synopsis: Creates a new instance of this collection item.

Declaration: `constructor Create(ACollection: TCollection); Virtual`

Visibility: `public`

Description: `Create` instantiates a new item in a `TCollection` (358). It is called by the `TCollection.Add` (360) function and should under normal circumstances never be called directly. called

See also: `TCollectionItem.Destroy` (367)

4.46.5 TCollectionItem.Destroy

Synopsis: Destroys this collection item.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` removes the item from the managing collection and Destroys the item instance.
This is the only way to remove items from a collection;

See also: `TCollectionItem.Create` (367)

4.46.6 TCollectionItem.GetNamePath

Synopsis: Returns the namepath of this collection item.

Declaration: `function GetNamePath : string; Override`

Visibility: `public`

Description: `GetNamePath` overrides the `TPersistent.GetNamePath` (430) method to return the name of the managing collection and appends its `TCollectionItem.Index` (368) property.

See also: `TCollectionItem.Collection` (367), `TPersistent.GetNamePath` (430), `TCollectionItem.Index` (368)

4.46.7 TCollectionItem.Collection

Synopsis: Pointer to the collection managing this item.

Declaration: `Property Collection : TCollection`

Visibility: `public`

Access: `Read,Write`

Description: `Collection` points to the collection managing this item. This property can be set to point to a new collection. If this is done, the old collection will be notified that the item should no longer be managed, and the new collection is notified that it should manage this item as well.

See also: `TCollection` (358)

4.46.8 TCollectionItem.ID

Synopsis: Initial index of this item.

Declaration: `Property ID : Integer`

Visibility: `public`

Access: `Read`

Description: `ID` is the initial value of `TCollectionItem.Index` (368); it doesn't change after the index changes. It can be used to uniquely identify the item. The `ID` property doesn't change as items are added and removed from the collection.

While the `TCollectionItem.Index` (368) property forms a continuous series, `ID` does not. If items are removed from the collection, their `ID` is not used again, leaving gaps. Only when the collection is initially created, the `ID` and `Index` properties will be equal.

See also: `TCollection.Items` (364), `TCollectionItem.Index` (368)

4.46.9 TCollectionItem.Index

Synopsis: Index of the item in its managing collection `TCollection.Items` (364) property.

Declaration: `Property Index : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Index` is the current index of the item in its managing collection's `TCollection.Items` (364) property. This property may change as items are added and removed from the collection.

The index of an item is zero-based, i.e. the first item has index zero. The last item has index `Count-1` where `Count` is the number of items in the collection.

The `Index` property of the items in a collection form a continuous series ranging from 0 to `Count-1`. The `TCollectionItem.ID` (368) property does not form a continuous series, but can also be used to identify an item.

See also: `TCollectionItem.ID` (368), `TCollection.Items` (364)

4.46.10 TCollectionItem.DisplayName

Synopsis: Name of the item, displayed in the object inspector.

Declaration: `Property DisplayName : string`

Visibility: `public`

Access: `Read,Write`

Description: `DisplayName` contains the name of this item as shown in the object inspector. For `TCollectionItem` this returns always the class name of the managing collection, followed by the index of the item.

`TCollectionItem` does not implement any functionality to store the `DisplayName` property. The property can be set, but this will have no effect other than that the managing collection is notified of a change. The actual displayname will remain unchanged. To store the `DisplayName` property, `TCollectionItem` descendants should override the `TCollectionItem.SetDisplayName` (366) and `TCollectionItem.GetDisplayName` (366) to add storage functionality.

See also: `TCollectionItem.Index` (368), `TCollectionItem.ID` (368), `TCollectionItem.GetDisplayName` (366), `TCollectionItem.SetDisplayName` (366)

4.47 TComponent

4.47.1 Description

`TComponent` is the base class for any set of classes that needs owner-owned functionality, and which needs support for property streaming. All classes that should be handled by an IDE (Integrated Development Environment) must descend from `TComponent`, as it includes all support for streaming all its published properties.

Components can 'own' other components. `TComponent` introduces methods for enumerating the child components. It also allows to name the owned components with a unique name. Furthermore, functionality for sending notifications when a component is removed from the list or removed from memory altogether is also introduced in `TComponent`.

`TComponent` introduces a form of automatic memory management: When a component is destroyed, all its child components will be destroyed first.

4.47.2 Interfaces overview

Page	Interfaces	Description
309	<code>IInterfaceComponentReference</code>	Interface for checking component references
1591	<code>IUnknown</code>	Basic interface for all COM-based interfaces

4.47.3 Method overview

Page	Method	Description
371	<code>BeforeDestruction</code>	Overrides standard <code>BeforeDestruction</code> .
371	<code>Create</code>	Creates a new instance of the component.
371	<code>Destroy</code>	Destroys the instance of the component.
371	<code>DestroyComponents</code>	Destroy child components.
372	<code>Destroying</code>	Called when the component is being destroyed
372	<code>ExecuteAction</code>	Standard action execution method.
372	<code>FindComponent</code>	Finds and returns the named component in the owned components.
372	<code>FreeNotification</code>	Ask the component to notify called when it is being destroyed.
373	<code>FreeOnRelease</code>	Part of the <code>IVCLComObject</code> interface.
373	<code>GetEnumerator</code>	Create an <code>IEnumerator</code> instance
373	<code>GetNamePath</code>	Returns the name path of this component.
373	<code>GetParentComponent</code>	Returns the parent component.
374	<code>HasParent</code>	Does the component have a parent ?
374	<code>InsertComponent</code>	Insert the given component in the list of owned components.
375	<code>IsImplementorOf</code>	Checks if the current component is the implementor of the interface
370	<code>Notification</code>	Called by components that are freed and which received a <code>FreeNotification</code> .
375	<code>ReferenceInterface</code>	Interface implementation of <code>Notification</code>
374	<code>RemoveComponent</code>	Remove the given component from the list of owned components.
373	<code>RemoveFreeNotification</code>	Remove a component from the Free Notification list.
374	<code>SafeCallException</code>	Part of the <code>IVCLComObject</code> Interface.
375	<code>SetSubComponent</code>	Sets the <code>csSubComponent</code> style.
375	<code>UpdateAction</code>	Updates the state of an action.
370	<code>WriteState</code>	Writes the component to a stream.

4.47.4 Property overview

Page	Properties	Access	Description
376	ComObject	r	Interface reference implemented by the component
376	ComponentCount	r	Count of owned components
376	ComponentIndex	rw	Index of component in it's owner's list.
376	Components	r	Indexed list (zero-based) of all owned components.
377	ComponentState	r	Current component's state.
377	ComponentStyle	r	Current component's style.
377	DesignInfo	rw	Information for IDE designer.
378	Name	rws	Name of the component.
378	Owner	r	Owner of this component.
378	Tag	rw	Tag value of the component.
378	VCLComObject	rw	Not implemented.

4.47.5 TComponent.Notification

Synopsis: Called by components that are freed and which received a FreeNotification.

Declaration: `procedure Notification(AComponent: TComponent; Operation: TOperation)
; Virtual`

Visibility: protected

Description: `Notification` is called whenever a child component is destroyed, inserted or removed from the list of owned component. Components that were requested to send a notification when they are freed ((with `FreeNotification` ([372](#))) will also call `Notification` when they are freed.

The `AComponent` parameter specifies which component sends the notification, and `Operation` specifies whether the component is being inserted into or removed from the child component list, or whether it is being destroyed.

Descendants of `TComponent` can use `FreeNotification` ([372](#)) to request notification of the destruction of another object. By overriding the `Notification` method, they can do special processing (typically, set a reference to this component to `Nil`) when this component is destroyed. The `Notification` method is called quite often in the streaming process, so speed should be a consideration when overriding this method.

See also: `TOperation` ([277](#)), `TComponent.FreeNotification` ([372](#)), `TComponent.RemoveFreeNotification` ([373](#))

4.47.6 TComponent.WriteState

Synopsis: Writes the component to a stream.

Declaration: `procedure WriteState(Writer: TWriter); Virtual`

Visibility: public

Description: `WriteState` writes the component's current state to a stream through the writer ([515](#)) object `writer`. Values for all published properties of the component can be written to the stream. Normally there is no need to call `WriteState` directly. The streaming system calls `WriteState` itself.

The `TComponent` ([369](#)) implementation of `WriteState` simply calls `TWriter.WriteData` ([515](#)). Descendant classes can, however, override `WriteState` to provide additional processing of stream data.

See also: `ReadState` ([369](#)), `TStream.WriteComponent` ([453](#)), `TWriter.WriteData` ([515](#))

4.47.7 TComponent.Create

Synopsis: Creates a new instance of the component.

Declaration: `constructor Create(AOwner: TComponent); Virtual`

Visibility: `public`

Description: `Create` creates a new instance of a `TComponent` class. If `AOwner` is not `Nil`, the new component attempts to insert itself in the list of owned components of the owner.

See also: [Insert \(369\)](#), [Owner \(378\)](#)

4.47.8 TComponent.Destroy

Synopsis: Destroys the instance of the component.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` sends a `opRemove` notification to all components in the free-notification list. After that, all owned components are destroyed by calling `DestroyComponents (371)` (and hence removed from the list of owned components). When this is done, the component removes itself from its owner's child component list. After that, the parent's `destroy` method is called.

See also: [Notification \(370\)](#), [Owner \(378\)](#), [DestroyComponents \(371\)](#), [Components \(376\)](#)

4.47.9 TComponent.BeforeDestruction

Synopsis: Overrides standard `BeforeDestruction`.

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `BeforeDestruction` is overridden by `TComponent` to set the `csDestroying` flag in `TComponent.ComponentState (377)`

See also: [TComponent.ComponentState \(377\)](#)

4.47.10 TComponent.DestroyComponents

Synopsis: Destroy child components.

Declaration: `procedure DestroyComponents`

Visibility: `public`

Description: `DestroyComponents` calls the destructor of all owned components, till no more components are left in the [Components \(376\)](#) array.

Calling the destructor of an owned component has as the effect that the component will remove itself from the list of owned components, if nothing has disrupted the sequence of destructors.

Errors: If an overridden 'destroy' method does not call it's inherited destructor or raises an exception, it's [TComponent.Destroy \(371\)](#) destructor will not be called, which may result in an endless loop.

See also: [Destroy \(371\)](#), [Components \(376\)](#)

4.47.11 TComponent.Destroying

Synopsis: Called when the component is being destroyed

Declaration: `procedure Destroying`

Visibility: `public`

Description: `Destroying` sets the `csDestroying` flag in the component's state (369) property, and does the same for all owned components.

It is not necessary to call `Destroying` directly, the destructor `Destroy` (371) does this automatically.

See also: State (369), `Destroy` (371)

4.47.12 TComponent.ExecuteAction

Synopsis: Standard action execution method.

Declaration: `function ExecuteAction(Action: TBasicAction) : Boolean; Dynamic`

Visibility: `public`

Description: `ExecuteAction` checks whether `Action` handles the current component, and if yes, calls the `ExecuteAction` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: `TBasicAction` (332), `TBasicAction.ExecuteAction` (332), `TBasicAction.HandlesTarget` (333), `TComponent.UpdateAction` (375)

4.47.13 TComponent.FindComponent

Synopsis: Finds and returns the named component in the owned components.

Declaration: `function FindComponent(const AName: string) : TComponent`

Visibility: `public`

Description: `FindComponent` searches the component with name `AName` in the list of owned components. If `AName` is empty, then `Nil` is returned.

See also: Components (376), Name (378)

4.47.14 TComponent.FreeNotification

Synopsis: Ask the component to notify called when it is being destroyed.

Declaration: `procedure FreeNotification(AComponent: TComponent)`

Visibility: `public`

Description: `FreeNotification` inserts `AComponent` in the freenotification list. When the component is destroyed, the `Notification` (370) method is called for all components in the freenotification list.

See also: Components (376), `Notification` (370), `TComponent.RemoveFreeNotification` (373)

4.47.15 TComponent.RemoveFreeNotification

Synopsis: Remove a component from the Free Notification list.

Declaration: `procedure RemoveFreeNotification (AComponent: TComponent)`

Visibility: `public`

Description: `RemoveFreeNotification` removes `AComponent` from the `freenotification` list.

See also: `TComponent.FreeNotification` ([372](#))

4.47.16 TComponent.FreeOnRelease

Synopsis: Part of the `IVCLComObject` interface.

Declaration: `procedure FreeOnRelease`

Visibility: `public`

Description: Provided for Delphi compatibility, but is not yet implemented.

4.47.17 TComponent.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TComponentEnumerator`

Visibility: `public`

Description: `GetEnumerator` is the implementation of the `IEnumerable` ([1589](#)) interface for `TComponent`. It creates a `TComponentEnumerator` ([379](#)) instance and returns its `IEnumerator` ([1589](#)) interface. The enumerator enumerates all child components of the component instance.

See also: `TComponentEnumerator` ([379](#)), `IEnumerator` ([1589](#)), `IEnumerable` ([1589](#))

4.47.18 TComponent.GetNamePath

Synopsis: Returns the name path of this component.

Declaration: `function GetNamePath : string; Override`

Visibility: `public`

Description: `GetNamePath` returns the name of the component as it will be shown in the object inspector.

`TComponent` overrides `GetNamePath` so it returns the `Name` ([378](#)) property of the component.

See also: `Name` ([378](#)), `TPersistent.GetNamePath` ([430](#))

4.47.19 TComponent.GetParentComponent

Synopsis: Returns the parent component.

Declaration: `function GetParentComponent : TComponent; Dynamic`

Visibility: `public`

Description: `GetParentComponent` can be implemented to return the parent component of this component. The implementation of this method in `TComponent` always returns `Nil`. Descendant classes must override this method to return the visual parent of the component.

See also: `HasParent` (374), `Owner` (378)

4.47.20 TComponent.HasParent

Synopsis: Does the component have a parent ?

Declaration: `function HasParent : Boolean; Dynamic`

Visibility: `public`

Description: `HasParent` can be implemented to return whether the parent of the component exists. The implementation of this method in `TComponent` always returns `False`, and should be overridden by descendant classes to return `True` when a parent is available. If `HasParent` returns `True`, then `GetParentComponent` (373) will return the parent component.

See also: `HasParent` (374), `Owner` (378)

4.47.21 TComponent.InsertComponent

Synopsis: Insert the given component in the list of owned components.

Declaration: `procedure InsertComponent (AComponent : TComponent)`

Visibility: `public`

Description: `InsertComponent` attempts to insert `AComponent` in the list with owned components. It first calls `ValidateComponent` (369) to see whether the component can be inserted. It then checks whether there are no name conflicts by calling `ValidateRename` (369). If neither of these checks have raised an exception the component is inserted, and notified of the insert.

See also: `RemoveComponent` (374), `Insert` (369), `ValidateContainer` (369), `ValidateRename` (369), `Notification` (370)

4.47.22 TComponent.RemoveComponent

Synopsis: Remove the given component from the list of owned components.

Declaration: `procedure RemoveComponent (AComponent : TComponent)`

Visibility: `public`

Description: `RemoveComponent` will send an `opRemove` notification to `AComponent` and will then proceed to remove `AComponent` from the list of owned components.

See also: `InsertComponent` (374), `Remove` (369), `ValidateRename` (369), `Notification` (370)

4.47.23 TComponent.SafeCallException

Synopsis: Part of the `IVCLComObject` Interface.

Declaration: `function SafeCallException (ExceptObject : TObject;
ExceptAddr : CodePointer) : HRESULT; Override`

Visibility: `public`

Description: Provided for Delphi compatibility, but not implemented.

4.47.24 TComponent.SetSubComponent

Synopsis: Sets the `csSubComponent` style.

Declaration: `procedure SetSubComponent (ASubComponent: Boolean)`

Visibility: `public`

Description: `SetSubComponent` includes `csSubComponent` in the `ComponentStyle` (377) property if `ASubComponent` is `True`, and excludes it again if `ASubComponent` is `False`.

See also: `TComponent.ComponentStyle` (377)

4.47.25 TComponent.UpdateAction

Synopsis: Updates the state of an action.

Declaration: `function UpdateAction (Action: TBasicAction) : Boolean; Dynamic`

Visibility: `public`

Description: `UpdateAction` checks whether `Action` handles the current component, and if yes, calls the `UpdateTarget` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: `TBasicAction` (332), `TBasicAction.UpdateTarget` (334), `TBasicAction.HandlesTarget` (333), `TBasicAction.ExecuteAction` (332)

4.47.26 TComponent.IsImplementorOf

Synopsis: Checks if the current component is the implementor of the interface

Declaration: `function IsImplementorOf (const Intf: IInterface) : Boolean`

Visibility: `public`

Description: `IsImplementorOf` returns `True` if the current component implements the given interface. The interface should descend from `IInterfaceComponentReference` (309) and the `GetComponent` method should return the current instance.

See also: `IInterfaceComponentReference` (309)

4.47.27 TComponent.ReferenceInterface

Synopsis: Interface implementation of Notification

Declaration: `procedure ReferenceInterface (const intf: IInterface; op: TOperation)`

Visibility: `public`

Description: `ReferenceInterface` can be used to notify an interface of a component operation: it is the equivalent of the `TComponent.Notification` (370) method of `TComponent` for interfaces. If the interface implements `IInterfaceComponentReference` (309), then the component that implements the interface is notified of the given operation `Op`.

Errors: None.

See also: `TComponent.Notification` (370), `IInterfaceComponentReference` (309)

4.47.28 TComponent.ComObject

Synopsis: Interface reference implemented by the component

Declaration: `Property ComObject : IUnknown`

Visibility: public

Access: Read

Description: `ComObject` returns the COM interface represented by the component. If the component does not represent a COM interface, reading this property will raise an `EComponentError` (303).

See also: `EComponentError` (303)

4.47.29 TComponent.Components

Synopsis: Indexed list (zero-based) of all owned components.

Declaration: `Property Components[Index: Integer]: TComponent`

Visibility: public

Access: Read

Description: `Components` provides indexed access to the list of owned components. `Index` can range from 0 to `ComponentCount-1` (376).

See also: `ComponentCount` (376), `Owner` (378)

4.47.30 TComponent.ComponentCount

Synopsis: Count of owned components

Declaration: `Property ComponentCount : Integer`

Visibility: public

Access: Read

Description: `ComponentCount` returns the number of components that the current component owns. It can be used to determine the valid index range in the `Component` (376) array.

See also: `Components` (376), `Owner` (378)

4.47.31 TComponent.ComponentIndex

Synopsis: Index of component in it's owner's list.

Declaration: `Property ComponentIndex : Integer`

Visibility: public

Access: Read, Write

Description: `ComponentIndex` is the index of the current component in its owner's list of components. If the component has no owner, the value of this property is -1.

See also: `Components` (376), `ComponentCount` (376), `Owner` (378)

4.47.32 TComponent.ComponentState

Synopsis: Current component's state.

Declaration: `Property ComponentState : TComponentState`

Visibility: `public`

Access: `Read`

Description: `ComponentState` indicates the current state of the component. It is a set of flags which indicate the various stages in the lifetime of a component. The following values can occur in this set:

Table 4.25: Component states

Flag	Meaning
<code>csLoading</code>	The component is being loaded from stream
<code>csReading</code>	Component properties are being read from stream.
<code>csWriting</code>	Component properties are being written to stream.
<code>csDestroying</code>	The component or one of it's owners is being destroyed.
<code>csAncestor</code>	The component is being streamed as part of a frame
<code>csUpdating</code>	The component is being updated
<code>csFixups</code>	References to other components are being resolved
<code>csFreeNotification</code>	The component has freenotifications.
<code>csInline</code>	The component is being loaded as part of a frame
<code>csDesignInstance</code>	? not used.

The component state is set by various actions such as reading it from stream, destroying it etc.

See also: `SetAncestor` (369), `SetDesigning` (369), `SetInline` (369), `SetDesignInstance` (369), `Updating` (369), `Updated` (369), `Loaded` (369)

4.47.33 TComponent.ComponentStyle

Synopsis: Current component's style.

Declaration: `Property ComponentStyle : TComponentStyle`

Visibility: `public`

Access: `Read`

Description: Current component's style.

4.47.34 TComponent.DesignInfo

Synopsis: Information for IDE designer.

Declaration: `Property DesignInfo : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `DesignInformation` can be used by an IDE to store design information in the component. It should not be used by an application programmer.

See also: `Tag` (378)

4.47.35 TComponent.Owner

Synopsis: Owner of this component.

Declaration: `Property Owner : TComponent`

Visibility: `public`

Access: `Read`

Description: `Owner` returns the owner of this component. The owner cannot be set except by explicitly inserting the component in another component's owned components list using that component's `InsertComponent` (374) method, or by removing the component from it's owner's owned component list using the `RemoveComponent` (374) method.

See also: `Components` (376), `InsertComponent` (374), `RemoveComponent` (374)

4.47.36 TComponent.VCLComObject

Synopsis: Not implemented.

Declaration: `Property VCLComObject : Pointer`

Visibility: `public`

Access: `Read,Write`

Description: `VCLComObject` is not yet implemented in Free Pascal.

4.47.37 TComponent.Name

Synopsis: Name of the component.

Declaration: `Property Name : TComponentName`

Visibility: `published`

Access: `Read,Write`

Description: `Name` is the name of the component. This name should be a valid identifier, i.e. must start with a letter or underscore, and can contain only letters, numbers and the underscore character. When attempting to set the name of a component, the name will be checked for validity. Furthermore, when a component is owned by another component, the name must be either empty or must be unique among the child component names.

By "letters", 7-bit letters are meant.

Errors: Attempting to set the name to an invalid value will result in an exception being raised.

See also: `ValidateRename` (369), `Owner` (378)

4.47.38 TComponent.Tag

Synopsis: Tag value of the component.

Declaration: `Property Tag : PtrInt`

Visibility: `published`

Access: `Read,Write`

Description: `Tag` can be used to store an integer value in the component. This value is streamed together with all other published properties. It can be used for instance to quickly identify a component in an event handler.

See also: `Name` ([378](#))

4.48 TComponentEnumerator

4.48.1 Description

`TComponentEnumerator` implements the `#rtl.system.IEnumerator` ([1589](#)) interface for the `TComponent` ([369](#)) class, so the `TComponent` class can be used in a `for ... in` loop over the `TComponent.Components` ([376](#)) child components of the component. It is returned by the `TComponent.GetEnumerator` ([373](#)) method of `TComponent`.

See also: `TComponent` ([369](#)), `TComponent.GetEnumerator` ([373](#)), `#rtl.system.IEnumerator` ([1589](#))

4.48.2 Method overview

Page	Method	Description
379	<code>Create</code>	Initialize a new instance of <code>TComponentEnumerator</code>
379	<code>GetCurrent</code>	Return the current pointer in the list
380	<code>MoveNext</code>	Move the position of the enumerator to the next position in the children of the component.

4.48.3 Property overview

Page	Properties	Access	Description
380	<code>Current</code>	<code>r</code>	Current pointer in the list

4.48.4 TComponentEnumerator.Create

Synopsis: Initialize a new instance of `TComponentEnumerator`

Declaration: `constructor Create (AComponent: TComponent)`

Visibility: `public`

Description: `Create` initializes a new instance of `TComponentEnumerator` and keeps a reference to the component `AComponent` that will be enumerated.

See also: `TComponent` ([369](#))

4.48.5 TComponentEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : TComponent`

Visibility: `public`

Description: `GetCurrent` returns the current `TComponent` ([369](#)) child component instance in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` ([380](#)), `TComponent.Components` ([376](#))

4.48.6 TComponentEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the children of the component.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next child in the components child components, and returns `True` if this succeeded, or `False` if the pointer is past the last child in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` (379)

4.48.7 TComponentEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : TComponent`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` (379) as a property.

See also: `GetCurrent` (379)

4.49 TCustomMemoryStream

4.49.1 Description

`TCustomMemoryStream` is the parent class for streams that stored their data in memory. It introduces all needed functions to handle reading from and navigating through the memory, and introduces a `Memory` (382) property which points to the memory area where the stream data is kept.

The only thing which `TCustomMemoryStream` does not do is obtain memory to store data when writing data or the writing of data. This functionality is implemented in descendant streams such as `TMemoryStream` (418). The reason for this approach is that this way it is possible to create e.g. read-only descendants of `TCustomMemoryStream` that point to a fixed part in memory which can be read from, but not written to.

Remark Since `TCustomMemoryStream` is an abstract class, do not create instances of `TMemoryStream` directly. Instead, create instances of descendants such as `TMemoryStream` (418).

See also: `TMemoryStream` (418), `TStream` (448)

4.49.2 Method overview

Page	Method	Description
381	<code>Read</code>	Reads <code>Count</code> bytes from the stream into <code>buffer</code> .
382	<code>SaveToFile</code>	Writes the contents of the stream to a file.
381	<code>SaveToStream</code>	Writes the contents of the memory stream to another stream.
381	<code>Seek</code>	Sets a new position in the stream.

4.49.3 Property overview

Page	Properties	Access	Description
382	Memory	r	Pointer to the data kept in the memory stream.

4.49.4 TCustomMemoryStream.Read

Synopsis: Reads `Count` bytes from the stream into `buffer`.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` reads `Count` bytes from the stream into the memory pointed to by `buffer`. It returns the number of bytes actually read.

This method overrides the `TStream.Read` ([449](#)) method of `TStream` ([448](#)). It will read as much bytes as are still available in the memory area pointer to by `Memory` ([382](#)). After the bytes are read, the internal stream position is updated.

See also: `TCustomMemoryStream.Memory` ([382](#)), `TStream.Read` ([449](#))

4.49.5 TCustomMemoryStream.Seek

Synopsis: Sets a new position in the stream.

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: `public`

Description: `Seek` overrides the abstract `TStream.Seek` ([450](#)) method. It simply updates the internal stream position, and returns the new position.

Errors: No checking is done whether the new position is still a valid position, i.e. whether the position is still within the range `0..Size`. Attempting a seek outside the valid memory range of the stream may result in an exception at the next read or write operation.

See also: `TStream.Position` ([457](#)), `TStream.Size` ([458](#)), `TCustomMemoryStream.Memory` ([382](#))

4.49.6 TCustomMemoryStream.SaveToStream

Synopsis: Writes the contents of the memory stream to another stream.

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: `public`

Description: `SaveToStream` writes the contents of the memory stream to `Stream`. The content of `Stream` is not cleared first. The current position of the memory stream is not changed by this action.

Remark This method will work much faster than the use of the `TStream.CopyFrom` ([452](#)) method:

```
Seek(0, soFromBeginning);
Stream.CopyFrom(Self, Size);
```

because the `CopyFrom` method copies the contents in blocks, while `SaveToStream` writes the contents of the memory as one big block.

Errors: If an error occurs when writing to `Stream` an `EStreamError` ([305](#)) exception will be raised.

See also: `TCustomMemoryStream.SaveToFile` ([382](#)), `TStream.CopyFrom` ([452](#))

4.49.7 TCustomMemoryStream.SaveToFile

Synopsis: Writes the contents of the stream to a file.

Declaration: `procedure SaveToFile(const FileName: string)`

Visibility: public

Description: `SaveToFile` writes the contents of the stream to a file with name `FileName`. It simply creates a filestream and writes the contents of the memorystream to this file stream using `TCustomMemoryStream.SaveToStream` (381).

Remark This method will work much faster than the use of the `TStream.CopyFrom` (452) method:

```
Stream:=TFileStream.Create(fmCreate,FileName);
Seek(0,soFromBeginning);
Stream.CopyFrom(Self,Size);
```

because the `CopyFrom` method copies the contents in blocks, while `SaveToFile` writes the contents of the memory as one big block.

Errors: If an error occurs when creating or writing to the file, an `EStreamError` (305) exception may occur.

See also: `TCustomMemoryStream.SaveToStream` (381), `TFileStream` (388), `TStream.CopyFrom` (452)

4.49.8 TCustomMemoryStream.Memory

Synopsis: Pointer to the data kept in the memory stream.

Declaration: `Property Memory : Pointer`

Visibility: public

Access: Read

Description: `Memory` points to the memory area where stream keeps it's data. The property is read-only, so the pointer cannot be set this way.

Remark Do not write to the memory pointed to by `Memory`, since the memory content may be read-only, and thus writing to it may cause errors.

See also: `TStream.Size` (458)

4.50 TDataModule

4.50.1 Description

`TDataModule` is a container for non-visual objects which can be used in an IDE to group non-visual objects which can be used by various other containers (forms) in a project. Notably, data access components are typically stored on a datamodule. Web components and services can also be implemented as descendants of datamodules.

`TDataModule` introduces some events which make it easier to program, and provides the needed streaming capabilities for persistent storage.

An IDE will typically allow to create a descendant of `TDataModule` which contains non-visual components in it's published property list.

See also: `TDataModule.OnCreate` (385)

4.50.2 Method overview

Page	Method	Description
384	AfterConstruction	Overrides standard TObject (1595) behaviour.
384	BeforeDestruction	
383	Create	Create a new instance of a TDataModule.
383	CreateNew	
384	Destroy	Destroys the TDataModule instance.

4.50.3 Property overview

Page	Properties	Access	Description
384	DesignOffset	rw	Position property needed for manipulation in an IDE.
385	DesignPPI	rw	Design Time PPI
385	DesignSize	rw	Size property needed for manipulation in an IDE.
386	OldCreateOrder	rw	Determines when OnCreate and OnDestroy are triggered.
385	OnCreate	rw	Event handler, called when the datamodule is created.
385	OnDestroy	rw	Event handler, called when the datamodule is destroyed.

4.50.4 TDataModule.Create

Synopsis: Create a new instance of a TDataModule.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TDataModule` and calls `TDataModule.CreateNew` ([383](#)). After that it reads the published properties from a stream using `InitInheritedComponent` ([293](#)) if a descendant class is instantiated. If the `OldCreateOrder` ([386](#)) property is `True`, the `TDataModule.OnCreate` ([385](#)) event is called.

Errors: An exception can be raised during the streaming operation.

See also: `TDataModule.CreateNew` ([383](#))

4.50.5 TDataModule.CreateNew

Synopsis:

Declaration: `constructor CreateNew(AOwner: TComponent)`
`constructor CreateNew(AOwner: TComponent; CreateMode: Integer); Virtual`

Visibility: `public`

Description: `CreateNew` creates a new instance of the class, but bypasses the streaming mechanism. The `CreateMode` parameter (by default zero) is not used in `TDataModule`. If the `AddDataModule` ([286](#)) handler is set, then it is called, with the newly created instance as an argument.

See also: `TDataModule.Create` ([383](#)), `AddDataModule` ([286](#)), `TDataModule.OnCreate` ([385](#))

4.50.6 TDataModule.Destroy

Synopsis: Destroys the TDataModule instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the TDataModule instance. If the `OldCreateOrder` (386) property is `True` the `OnDestroy` (385) event handler is called prior to destroying the data module.

Before calling the inherited `destroy`, the `RemoveDataModule` (287) handler is called if it is set, and `Self` is passed as a parameter.

Errors: An event can be raised during the `OnDestroy` event handler.

See also: `TDataModule.OnDestroy` (385), `RemoveDataModule` (287)

4.50.7 TDataModule.AfterConstruction

Synopsis: Overrides standard TObject (1595) behaviour.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` calls the `OnCreate` (385) handler if the `OldCreateOrder` (386) property is `False`.

See also: `TDataModule.OldCreateOrder` (386), `TDataModule.OnCreate` (385)

4.50.8 TDataModule.BeforeDestruction

Synopsis:

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `BeforeDestruction` calls the `OnDestroy` (385) handler if the `OldCreateOrder` (386) property is `False`.

See also: `TDataModule.OldCreateOrder` (386), `TDataModule.OnDestroy` (385)

4.50.9 TDataModule.DesignOffset

Synopsis: Position property needed for manipulation in an IDE.

Declaration: `Property DesignOffset : TPoint`

Visibility: `public`

Access: `Read, Write`

Description: `DesignOffset` is the position of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignSize` (385)

4.50.10 TDataModule.DesignSize

Synopsis: Size property needed for manipulation in an IDE.

Declaration: `Property DesignSize : TPoint`

Visibility: `public`

Access: `Read,Write`

Description: `DesignSize` is the size of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignOffset` ([384](#))

4.50.11 TDataModule.DesignPPI

Synopsis: Design Time PPI

Declaration: `Property DesignPPI : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `DesignPPI` exists for the benefit of graphical designers, to store the PPI at which the module was designed. It is not used in FPC itself.

4.50.12 TDataModule.OnCreate

Synopsis: Event handler, called when the datamodule is created.

Declaration: `Property OnCreate : TNotifyEvent`

Visibility: `published`

Access: `Read,Write`

Description: The `OnCreate` event is triggered when the datamodule is created and streamed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` ([386](#)) property.

See also: `TDataModule.Create` ([383](#)), `TDataModule.CreateNew` ([383](#)), `TDataModule.OldCreateOrder` ([386](#))

4.50.13 TDataModule.OnDestroy

Synopsis: Event handler, called when the datamodule is destroyed.

Declaration: `Property OnDestroy : TNotifyEvent`

Visibility: `published`

Access: `Read,Write`

Description: The `OnDestroy` event is triggered when the datamodule is destroyed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` ([386](#)) property.

See also: `TDataModule.Destroy` ([384](#)), `TDataModule.OnCreate` ([385](#)), `TDataModule.Create` ([383](#)), `TDataModule.CreateNew` ([383](#)), `TDataModule.OldCreateOrder` ([386](#))

4.50.14 TDataModule.OldCreateOrder

Synopsis: Determines when `OnCreate` and `OnDestroy` are triggered.

Declaration: `Property OldCreateOrder : Boolean`

Visibility: `published`

Access: `Read, Write`

Description: `OldCreateOrder` determines when exactly the `OnCreate` (385) and `OnDestroy` (385) event handlers are called.

If set to `True`, then the `OnCreate` event handler is called after the data module was streamed. If it is set to `False`, then the handler is called prior to the streaming process.

If set to `True`, then the `OnDestroy` event handler is called before the data module is removed from the streaming system. If it is set to `False`, then the handler is called after the data module was removed from the streaming process.

See also: `TDataModule.OnDestroy` (385), `TDataModule.OnCreate` (385), `TDataModule.Destroy` (384), `TDataModule.Create` (383), `TDataModule.CreateNew` (383), `TDataModule.OldCreateOrder` (386)

4.51 TFiler

4.51.1 Description

Class responsible for streaming of components.

4.51.2 Method overview

Page	Method	Description
387	<code>DefineBinaryProperty</code>	
386	<code>DefineProperty</code>	
387	<code>FlushBuffer</code>	Flush the buffer

4.51.3 Property overview

Page	Properties	Access	Description
388	<code>Ancestor</code>	<code>rw</code>	Ancestor component from which an inherited component is streamed.
388	<code>IgnoreChildren</code>	<code>rw</code>	Determines whether children will be streamed as well.
387	<code>LookupRoot</code>	<code>r</code>	Component used to look up ancestor components.
387	<code>Root</code>	<code>rw</code>	The root component is the initial component which is being streamed.

4.51.4 TFiler.DefineProperty

Synopsis:

Declaration: `procedure DefineProperty(const Name: string; ReadData: TReaderProc; WriteData: TWriterProc; HasData: Boolean); Virtual; Abstract`

Visibility: `public`

Description:

4.51.5 TFiler.DefineBinaryProperty

Synopsis:

Declaration: `procedure DefineBinaryProperty(const Name: string;
 ReadData: TStreamProc;
 WriteData: TStreamProc; HasData: Boolean)
 ; Virtual; Abstract`

Visibility: public

Description:

4.51.6 TFiler.FlushBuffer

Synopsis: Flush the buffer

Declaration: `procedure FlushBuffer; Virtual; Abstract`

Visibility: public

Description: `FlushBuffer` flushes the buffer by calling the `flushbuffer` on the driver. It is provided for Delphi compatibility, and is not used in FPC.

See also: `TAbstractObjectReader.FlushBuffer` ([319](#))

4.51.7 TFileer.Root

Synopsis: The root component is the initial component which is being streamed.

Declaration: `Property Root : TComponent`

Visibility: public

Access: Read,Write

Description: The streaming process will stream a component and all the components which it owns. The `Root` component is the component which is initially streamed.

See also: `LookupRoot` ([387](#))

4.51.8 TFileer.LookupRoot

Synopsis: Component used to look up ancestor components.

Declaration: `Property LookupRoot : TComponent`

Visibility: public

Access: Read

Description: When comparing inherited component's values against parent values, the values are compared with the component in `LookupRoot`. Initially, it is set to `Root` ([387](#)).

See also: `Root` ([387](#))

4.51.9 TFile.Ancestor

Synopsis: Ancestor component from which an inherited component is streamed.

Declaration: `Property Ancestor : TPersistent`

Visibility: `public`

Access: `Read, Write`

Description: When streaming a component, this is the parent component. Only properties that differ from the parent's property value will be streamed.

See also: [Root \(387\)](#), [LookupRoot \(387\)](#)

4.51.10 TFile.IgnoreChildren

Synopsis: Determines whether children will be streamed as well.

Declaration: `Property IgnoreChildren : Boolean`

Visibility: `public`

Access: `Read, Write`

Description: By default, all children (i.e. owned objects) will also be streamed when streaming a component. This property can be used to prevent owned objects from being streamed.

4.52 TFileStream

4.52.1 Description

`TFileStream` is a `TStream` ([448](#)) descendant that stores or reads its data from a named file in the file system of the operating system.

To this end, it overrides some of the methods in `TStream` and implements them for the case of files on disk, and it adds the `FileName` ([390](#)) property to the list of public properties.

See also: `TFileStream.Create` ([389](#)), `TStream` ([448](#))

4.52.2 Method overview

Page	Method	Description
389	Create	Creates a file stream.
389	Destroy	Destroys the file stream.

4.52.3 Property overview

Page	Properties	Access	Description
390	FileName	r	The filename of the stream.

4.52.6 TFileStream.FileName

Synopsis: The filename of the stream.

Declaration: `Property FileName : string`

Visibility: `public`

Access: `Read`

Description: `FileName` is the name of the file that the stream reads from or writes to. It is the name as passed in the constructor of the stream; it cannot be changed. To write to another file, the stream must be freed and created again with the new filename.

See also: `TFileStream.Create` (389)

4.53 TFPList

4.53.1 Description

`TFPList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. Contrary to `TList` (408), `TFPList` has no notification mechanism. If no notification mechanism is used, it is better to use `TFPList` instead of `TList`, as the performance of `TFPList` is much higher.

To manage collections of strings, it is better to use a `TStrings` (468) descendant such as `TStringList` (463). To manage general objects, a `TCollection` (358) class exists, from which a descendant can be made to manage collections of various kinds.

See also: `TStrings` (468), `TCollection` (358)

4.53.2 Method overview

Page	Method	Description
391	<code>Add</code>	Adds a new pointer to the list.
391	<code>AddList</code>	Add all pointers from another list
395	<code>Assign</code>	<code>Assign</code> performs the given operation on the list.
391	<code>Clear</code>	Clears the pointer list.
392	<code>Delete</code>	Removes a pointer from the list.
391	<code>Destroy</code>	Destroys the list and releases the memory used to store the list elements.
392	<code>Error</code>	Raises an <code>EListError</code> (304) exception.
392	<code>Exchange</code>	Exchanges two pointers in the list.
392	<code>Expand</code>	Increases the capacity of the list if needed.
393	<code>Extract</code>	Remove the first occurrence of a pointer from the list.
393	<code>First</code>	Returns the first non-nil pointer in the list.
396	<code>ForEachCall</code>	Call a procedure or method for each pointer in the list.
393	<code>GetEnumerator</code>	Create an <code>IEnumerator</code> instance
393	<code>IndexOf</code>	Returns the index of a given pointer.
394	<code>IndexOfItem</code>	Search an item in the list
394	<code>Insert</code>	Inserts a new pointer in the list at a given position.
394	<code>Last</code>	Returns the last non-nil pointer in the list.
394	<code>Move</code>	Moves a pointer from one position in the list to another.
395	<code>Pack</code>	Removes <code>Nil</code> pointers from the list and frees unused memory.
395	<code>Remove</code>	Removes a value from the list.
395	<code>Sort</code>	Sorts the pointers in the list.

4.53.3 Property overview

Page	Properties	Access	Description
396	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
396	Count	rw	Current number of pointers in the list.
397	Items	rw	Provides access to the pointers in the list.
397	List	r	Memory array where pointers are stored.

4.53.4 TFPList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

4.53.5 TFPList.AddList

Synopsis: Add all pointers from another list

Declaration: `procedure AddList (AList: TFPList)`

Visibility: `public`

Description: `AddList` adds all pointers from `AList` to the list. If a pointer is already present, it is added a second time.

See also: `TFPList.Assign` ([395](#)), `TList.AddList` ([411](#))

4.53.6 TFPList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add (Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the `Expand` ([392](#)) method.

To insert a pointer at a certain position in the list, use the `Insert` ([394](#)) method instead.

See also: `Delete` ([392](#)), `Grow` ([408](#)), `Insert` ([394](#))

4.53.7 TFPList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: `Destroy` ([391](#))

4.53.8 TFPList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

4.53.9 TFPList.Error

Synopsis: Raises an `EListError` ([304](#)) exception.

Declaration: `class procedure Error(const Msg: string; Data: PtrInt)`

Visibility: `public`

Description: `Error` raises an `EListError` ([304](#)) exception, with a message formatted with `Msg` and `Data`.

4.53.10 TFPList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: `public`

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` ([304](#)) exception will be raised.

4.53.11 TFPList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TFPList`

Visibility: `public`

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `Capacity` ([396](#))

4.53.12 TFPList.Extract

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract (Item: Pointer) : Pointer`

Visibility: public

Description: `Extract` searches for the first occurrence of `Item` in the list and deletes it from the list. If `Item` was found, it's value is returned. If `Item` was not found, `Nil` is returned.

See also: `TFPList.Delete` ([392](#))

4.53.13 TFPList.First

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: public

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `Last` ([394](#))

4.53.14 TFPList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TFPListEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` ([1589](#)) interface for `TFPList`. It creates a `TFPListEnumerator` ([397](#)) instance and returns it's `IEnumerator` ([1589](#)) interface.

See also: `TFPListEnumerator` ([397](#)), `IEnumerator` ([1589](#)), `IEnumerable` ([1589](#))

4.53.15 TFPList.IndexOf

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf (Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

4.53.16 TFPList.IndexOfItem

Synopsis: Search an item in the list

Declaration: `function IndexOfItem(Item: Pointer; Direction: TDirection) : Integer`

Visibility: public

Description: `IndexOfItem` has the same function as the `IndexOf` (266) function: it searches for `Item` in the list, and returns the index of the first found matching pointer. If none is found, -1 is returned.

In difference with the `IndexOf` function, it accepts a parameter `Direction` indicating the search direction: from the beginning of the list till the end of the list, or from the end of the list till the beginning. The `IndexOf` function starts at the beginning of the list. The search direction is only important if the item can appear multiple times in the list.

See also: `TFPList.TDirection` (??), `TFPList.IndexOf` (393)

4.53.17 TFPList.Insert

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert(Index: Integer; Item: Pointer)`

Visibility: public

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` (304) exception is raised.

See also: `Add` (391), `Delete` (392)

4.53.18 TFPList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: public

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `First` (393)

4.53.19 TFPList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move(CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `Newindex` are not inside the valid range of indices, an `EListError` (304) exception is raised.

See also: `Exchange` (392)

4.53.20 TFPList.Assign

Synopsis: Assign performs the given operation on the list.

Declaration: `procedure Assign(ListA: TFPList; AOperator: TListAssignOp;
ListB: TFPList)`

Visibility: public

Description: Assign can be used to merge or assign lists. It is an extended version of the usual `TPersistent.Assign` mechanism. The arguments `ListA` and `ListB` are used as sources of pointers to add or remove elements from the current list, depending on the operation `AOperation`. The available operations are documented in the `TListAssignOp` (275) type.

See also: `TFPList.Add` (391), `TFPList.Clear` (391)

4.53.21 TFPList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove(Item: Pointer) : Integer`

Visibility: public

Description: Remove searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `Delete` (392), `IndexOf` (393), `Insert` (394)

4.53.22 TFPList.Pack

Synopsis: Removes `Nil` pointers from the list and frees unused memory.

Declaration: `procedure Pack`

Visibility: public

Description: Pack removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TFPList.Clear` (391)

4.53.23 TFPList.Sort

Synopsis: Sorts the pointers in the list.

Declaration: `procedure Sort(Compare: TListSortCompare)`

Visibility: public

Description: `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.

- if the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

4.53.24 TFPList.ForEachCall

Synopsis: Call a procedure or method for each pointer in the list.

Declaration: `procedure ForEachCall(proc2call: TListCallback; arg: pointer)`
`procedure ForEachCall(proc2call: TListStaticCallback; arg: pointer)`

Visibility: public

Description: `ForEachCall` iterates over all pointers in the list and calls `proc2call`, passing it the pointer and the additional `arg` data pointer. `Proc2Call` can be a method or a static procedure.

Errors: None.

See also: `TListStaticCallback` (276), `TListCallback` (276)

4.53.25 TFPList.Capacity

Synopsis: Current capacity (i.e. number of pointers that can be stored) of the list.

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` (391) or `insert` (394), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `SetCapacity` (390), `Count` (396)

4.53.26 TFPList.Count

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read,Write

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

4.53.27 TFPList.Items

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: `Read, Write`

Description: `Items` is used to access the pointers in the list. It is the default property of the `TFPList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

4.53.28 TFPList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: `Read`

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

4.54 TFPListEnumerator

4.54.1 Description

`TFPListEnumerator` implements the `#rtl.system.IEnumerator` (1589) interface for the `TFPList` (390) class, so the `TFPList` class can be used in a `for ... in` loop. It is returned by the `TFPList.GetEnumerator` (393) method of `TFPList`.

See also: `TFPList` (390), `TFPList.GetEnumerator` (393), `#rtl.system.IEnumerator` (1589)

4.54.2 Method overview

Page	Method	Description
397	<code>Create</code>	Initialize a new instance of <code>TFPListEnumerator</code>
398	<code>GetCurrent</code>	Return the current pointer in the list
398	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

4.54.3 Property overview

Page	Properties	Access	Description
398	<code>Current</code>	<code>r</code>	Current pointer in the list

4.54.4 TFPListEnumerator.Create

Synopsis: Initialize a new instance of `TFPListEnumerator`

Declaration: `constructor Create(AList: TFPList)`

Visibility: public

Description: `Create` initializes a new instance of `TFPListEnumerator` and keeps a reference to the list `AList` that will be enumerated.

See also: `TFPList` ([390](#))

4.54.5 `TFPListEnumerator.GetCurrent`

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : Pointer`

Visibility: public

Description: `GetCurrent` returns the current pointer in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` ([398](#))

4.54.6 `TFPListEnumerator.MoveNext`

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: public

Description: `MoveNext` puts the pointer on the next item in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([398](#))

4.54.7 `TFPListEnumerator.Current`

Synopsis: Current pointer in the list

Declaration: `Property Current : Pointer`

Visibility: public

Access: Read

Description: `Current` redefines `GetCurrent` ([398](#)) as a property.

See also: `GetCurrent` ([398](#))

4.55 THandleStream

4.55.1 Description

`THandleStream` is an abstract descendant of the `TStream` (448) class that provides methods for a stream to handle all reading and writing to and from a handle, provided by the underlying OS. To this end, it overrides the `Read` (399) and `Write` (400) methods of `TStream`.

Remark

- `THandleStream` does not obtain a handle from the OS by itself, it just handles reading and writing to such a handle by wrapping the system calls for reading and writing; Descendant classes should obtain a handle from the OS by themselves and pass it on in the inherited constructor.
- Contrary to Delphi, no seek is implemented for `THandleStream`, since pipes and sockets do not support this. The seek is implemented in descendant methods that support it.

See also: `TStream` (448), `TFileStream` (388)

4.55.2 Method overview

Page	Method	Description
399	<code>Create</code>	Create a handlestream from an OS Handle.
399	<code>Read</code>	Overrides standard read method.
400	<code>Seek</code>	Overrides the <code>Seek</code> method.
400	<code>Write</code>	Overrides standard write method.

4.55.3 Property overview

Page	Properties	Access	Description
400	<code>Handle</code>	r	The OS handle of the stream.

4.55.4 THandleStream.Create

Synopsis: Create a handlestream from an OS Handle.

Declaration: `constructor Create(AHandle: THandle)`

Visibility: `public`

Description: `Create` creates a new instance of a `THandleStream` class. It stores `AHandle` in an internal variable and then calls the inherited constructor.

See also: `TStream` (448)

4.55.5 THandleStream.Read

Synopsis: Overrides standard read method.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` overrides the `Read` (449) method of `TStream`. It uses the `Handle` (400) property to read the `Count` bytes into `Buffer`

If no error occurs while reading, the number of bytes actually read will be returned.

Errors: If the operating system reports an error while reading from the handle, -1 is returned.

See also: `TStream.Read` (449), `THandleStream.Write` (400), `THandleStream.Handle` (400)

4.55.6 THandleStream.Write

Synopsis: Overrides standard write method.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` overrides the `Write` (450) method of `TStream`. It uses the `Handle` (400) property to write the `Count` bytes from `Buffer`.

If no error occurs while writing, the number of bytes actually written will be returned.

Errors: If the operating system reports an error while writing to the handle, 0 is returned.

See also: `TStream.Read` (449), `THandleStream.Write` (400), `THandleStream.Handle` (400)

4.55.7 THandleStream.Seek

Synopsis: Overrides the `Seek` method.

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: `public`

Description: `seek` uses the `FileSeek` (1702) method to position the stream on the desired position. Note that handle stream descendants (notably pipes) can override the method to prevent the seek.

4.55.8 THandleStream.Handle

Synopsis: The OS handle of the stream.

Declaration: `Property Handle : THandle`

Visibility: `public`

Access: `Read`

Description: `Handle` represents the Operating system handle to which reading and writing is done. The handle can be read only, i.e. it cannot be set after the `THandleStream` instance was created. It should be passed to the constructor `THandleStream.Create` (399)

See also: `THandleStream` (399), `THandleStream.Create` (399)

4.56 TInterfacedPersistent

4.56.1 Description

TInterfacedPersistent is a direct descendant of TPersistent (428) which implements the #rtl.system.IInterface (1375) interface. In particular, it implements the QueryInterface as a public method.

See also: IInterface (1375)

4.56.2 Interfaces overview

Page	Interfaces	Description
1375	IInterface	Basic interface for all COM based interfaces

4.56.3 Method overview

Page	Method	Description
401	AfterConstruction	Overrides the standard AfterConstruction method.
401	QueryInterface	Implementation of IInterface.QueryInterface

4.56.4 TInterfacedPersistent.QueryInterface

Synopsis: Implementation of IInterface.QueryInterface

Declaration: `function QueryInterface(const IID: TGuid; out Obj) : HRESULT; Virtual`

Visibility: public

Description: QueryInterface simply calls GetInterface using the specified IID, and returns the correct values.

See also: TObject.GetInterface (1603)

4.56.5 TInterfacedPersistent.AfterConstruction

Synopsis: Overrides the standard AfterConstruction method.

Declaration: `procedure AfterConstruction; Override`

Visibility: public

Description: AfterConstruction is overridden to do some extra interface housekeeping: a reference to the IInterface interface of the owning class is obtained (if it exists).

4.57 TInterfaceList

4.57.1 Description

TInterfaceList is a standard implementation of the IInterfaceList (310) interface. It uses a TThreadList (513) instance to store the list of interfaces.

See also: IInterfaceList (310), TList (408)

4.57.2 Interfaces overview

Page	Interfaces	Description
310	<code>IInterfaceList</code>	Interface for maintaining a list of interfaces.

4.57.3 Method overview

Page	Method	Description
404	<code>Add</code>	Add an interface to the list
403	<code>Clear</code>	Removes all interfaces from the list.
402	<code>Create</code>	Create a new instance of <code>TInterfaceList</code>
403	<code>Delete</code>	Delete an interface from the list.
402	<code>Destroy</code>	Destroys the list of interfaces
403	<code>Exchange</code>	Exchange 2 interfaces in the list
406	<code>Expand</code>	Expands the list
403	<code>First</code>	Returns the first non- <code>Nil</code> element in the list.
404	<code>GetEnumerator</code>	Create an <code>IEnumerator</code> instance
404	<code>IndexOf</code>	Returns the index of an interface.
404	<code>Insert</code>	Insert an interface to the list
405	<code>Last</code>	Returns the last non- <code>Nil</code> element in the list.
405	<code>Lock</code>	Lock the list
405	<code>Remove</code>	Remove an interface from the list
405	<code>Unlock</code>	UnLocks a locked list

4.57.4 Property overview

Page	Properties	Access	Description
406	<code>Capacity</code>	<code>rw</code>	The current capacity of the list.
406	<code>Count</code>	<code>rw</code>	The current number of elements in the list.
406	<code>Items</code>	<code>rw</code>	Array-based access to the list's items.

4.57.5 `TInterfaceList.Create`

Synopsis: Create a new instance of `TInterfaceList`

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of the `TInterfaceList` class. It sets up the internal structures needed to store the list of interfaces.

See also: `Destroy` ([402](#))

4.57.6 `TInterfaceList.Destroy`

Synopsis: Destroys the list of interfaces

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` first calls `Clear` ([403](#)) and then frees the `TInterfaceList` instance from memory.

Note that the `Clear` method decreases the reference count of all interfaces.

See also: `Create` ([402](#)), `Clear` ([403](#))

4.57.7 TInterfaceList.Clear

Synopsis: Removes all interfaces from the list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` is the implementation of the `IInterfaceList.Clear` (312) method. It removes all interfaces from the list. It does this by setting each element in the list to `Nil`, in this way the reference count of each interface in the list is decreased.

See also: `IInterfaceList.Clear` (312), `Add` (404), `Destroy` (402), `TList.Clear` (411), `TFPList.Clear` (391)

4.57.8 TInterfaceList.Delete

Synopsis: Delete an interface from the list.

Declaration: `procedure Delete(index: Integer)`

Visibility: `public`

Description: `Delete` is the implementation of the `IInterfaceList.Delete` (312) method. It clears the slot first and then removes the element from the list.

See also: `IInterfaceList.Delete` (312), `TInterfaceList.Remove` (405), `TInterfaceList.Add` (404), `TList.Delete` (411), `TFPList.Delete` (392)

4.57.9 TInterfaceList.Exchange

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange(index1: Integer; index2: Integer)`

Visibility: `public`

Description: `Exchange` is the implementation of the `IInterfaceList.Exchange` (313) method. It exchanges the position of 2 interfaces in the list.

See also: `IInterfaceList.Exchange` (313), `TInterfaceList.Delete` (403), `TInterfaceList.Add` (404), `TList.Exchange` (412), `TFPList.Exchange` (392)

4.57.10 TInterfaceList.First

Synopsis: Returns the first non-`Nil` element in the list.

Declaration: `function First : IUnknown`

Visibility: `public`

Description: `First` is the implementation of the `IInterfaceList.First` (313) method. It returns the first non-`Nil` element from the list.

See also: `IInterfaceList.First` (313), `TList.First` (413)

4.57.11 TInterfaceList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TInterfaceListEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1589) interface for `TInterfaceList`. It creates a `TInterfaceListEnumerator` (407) instance and returns it's `IEnumerator` (1589) interface. The enumerator enumerates all interfaces in the list.

See also: `TInterfaceListEnumerator` (407), `IEnumerator` (1589), `IEnumerable` (1589)

4.57.12 TInterfaceList.IndexOf

Synopsis: Returns the index of an interface.

Declaration: `function IndexOf(const item: IUnknown) : Integer`

Visibility: public

Description: `IndexOf` is the implementation of the `IInterfaceList.IndexOf` (313) method. It returns the zero-based index in the list of the indicated interface, or -1 if the index is not in the list.

See also: `IInterfaceList.IndexOf` (313), `TList.IndexOf` (413)

4.57.13 TInterfaceList.Add

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: public

Description: `Add` is the implementation of the `IInterfaceList.Add` (313) method. It adds an interface to the list, and returns the location of the new element in the list. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Add` (313), `TInterfaceList.Delete` (403), `TInterfaceList.Insert` (404), `TList.Add` (411), `TFPList.Add` (391)

4.57.14 TInterfaceList.Insert

Synopsis: Insert an interface to the list

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: public

Description: `Insert` is the implementation of the `IInterfaceList.Insert` (313) method. It inserts an interface in the list at the indicated position. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Insert` (313), `TInterfaceList.Delete` (403), `TInterfaceList.Add` (404), `TList.Insert` (413), `TFPList.Insert` (394)

4.57.15 TInterfaceList.Last

Synopsis: Returns the last non-`Nil` element in the list.

Declaration: `function Last : IUnknown`

Visibility: `public`

Description: `Last` is the implementation of the `IInterfaceList.Last` (314) method. It returns the last non-`Nil` element from the list.

See also: `IInterfaceList.Last` (314), `TInterfaceList.First` (403), `TList.Last` (414), `TFPList.Last` (394)

4.57.16 TInterfaceList.Remove

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: `public`

Description: `Remove` is the implementation of the `IInterfaceList.Remove` (314) method. It removes the first occurrence of the interface from the list.

See also: `IInterfaceList.Remove` (314), `TInterfaceList.Delete` (403), `TInterfaceList.IndexOf` (404), `TList.Remove` (414), `TFPList.Remove` (395)

4.57.17 TInterfaceList.Lock

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: `public`

Description: `Lock` locks the list. It is the implementation of the `IInterfaceList.Lock` (314) method. It limits access to the list to the current thread.

See also: `IInterfaceList.Lock` (314), `TInterfaceList.Unlock` (405), `TThreadList.LockList` (514)

4.57.18 TInterfaceList.Unlock

Synopsis: Unlocks a locked list

Declaration: `procedure Unlock`

Visibility: `public`

Description: `Unlock` unlocks the list. It is the implementation of the `IInterfaceList.Unlock` (314) method. After a call to unlock, the current thread releases the list for manipulation by other threads.

See also: `IInterfaceList.Unlock` (314), `TInterfaceList.Lock` (405), `TThreadList.UnlockList` (515)

4.57.19 TInterfaceList.Expand

Synopsis: Expands the list

Declaration: `function Expand : TInterfaceList`

Visibility: `public`

Description: `Expand` calls the `expand` method from the internally used list. It returns itself.

See also: `TList.Expand` ([412](#))

4.57.20 TInterfaceList.Capacity

Synopsis: The current capacity of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` is the number of elements that the list can contain without needing to allocate more memory.

See also: `IInterfaceList.Capacity` ([314](#)), `TInterfaceList.Count` ([406](#)), `TList.Capacity` ([415](#)), `TFPList.Capacity` ([396](#))

4.57.21 TInterfaceList.Count

Synopsis: The current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the number of elements in the list. This can include `Nil` elements. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`.

See also: `IInterfaceList.Count` ([315](#)), `TInterfaceList.Items` ([406](#)), `TInterfaceList.Capacity` ([406](#)), `TList.Count` ([416](#)), `TFPList.Count` ([396](#))

4.57.22 TInterfaceList.Items

Synopsis: Array-based access to the list's items.

Declaration: `Property Items[Index: Integer]: IUnknown; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` provides indexed access to the elements in the list. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`. The items are read-write. It is not possible to add elements to the list by accessing an element with index larger or equal to `Count` ([406](#)).

See also: `IInterfaceList.Items` ([315](#)), `TInterfaceList.Count` ([406](#)), `TList.Items` ([416](#)), `TFPList.Items` ([397](#))

4.58 TInterfaceListEnumerator

4.58.1 Description

`TInterfaceListEnumerator` implements the `#rtl.system.IEnumerator` (1589) interface for the `TInterfaceList` (401) class, so the `TInterfaceList` class can be used in a `for ... in` loop over the `TInterfaceList.Components` (401) child components of the component. It is returned by the `TInterfaceList.GetEnumerator` (404) method of `TInterfaceList`.

See also: `TInterfaceList` (401), `TInterfaceList.GetEnumerator` (404), `#rtl.system.IEnumerator` (1589)

4.58.2 Method overview

Page	Method	Description
407	<code>Create</code>	Initialize a new instance of <code>TInterfaceListEnumerator</code>
407	<code>GetCurrent</code>	Return the current pointer in the list
408	<code>MoveNext</code>	Move the position of the enumerator to the next position in the children of the component.

4.58.3 Property overview

Page	Properties	Access	Description
408	<code>Current</code>	<code>r</code>	Current pointer in the list

4.58.4 TInterfaceListEnumerator.Create

Synopsis: Initialize a new instance of `TInterfaceListEnumerator`

Declaration: `constructor Create (AList: TInterfaceList)`

Visibility: `public`

Description: `Create` initializes a new instance of `TInterfaceListEnumerator` and keeps a reference to the component `AComponent` that will be enumerated.

See also: `TInterfaceList` (401)

4.58.5 TInterfaceListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : IUnknown`

Visibility: `public`

Description: `GetCurrent` returns the current interface in the `TInterfaceList` (401) list.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (408), `TInterfaceList.Components` (401)

4.58.6 TInterfaceListEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the children of the component.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next interface in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last interface in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([407](#))

4.58.7 TInterfaceListEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : IUnknown`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([407](#)) as a property.

See also: `GetCurrent` ([407](#))

4.59 TList

4.59.1 Description

`TList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. It has an event notification mechanism which allows to notify of list changes. This slows down some of `TList` mechanisms, and if no notification is used, `TFPList` ([390](#)) may be used instead.

To manage collections of strings, it is better to use a `TStrings` ([468](#)) descendant such as `TStringList` ([463](#)). To manage general objects, a `TCollection` ([358](#)) class exists, from which a descendant can be made to manage collections of various kinds.

See also: `TStrings` ([468](#)), `TCollection` ([358](#))

4.59.2 Interfaces overview

Page	Interfaces	Description
307	<code>IFPObserved</code>	Interface implemented by an object that can be observed.

4.59.3 Method overview

Page	Method	Description
411	Add	Adds a new pointer to the list.
411	AddList	Add all pointers from another list
414	Assign	Copy the contents of other lists.
411	Clear	Clears the pointer list.
409	Create	Class to manage collections of pointers.
411	Delete	Removes a pointer from the list.
409	Destroy	Destroys the list and releases the memory used to store the list elements.
412	Error	Raises an <code>EListError</code> (304) exception.
412	Exchange	Exchanges two pointers in the list.
412	Expand	Increases the capacity of the list if needed.
412	Extract	Remove the first occurrence of a pointer from the list.
413	First	Returns the first non-nil pointer in the list.
410	FPOAttachObserver	Add an observer to the list of observers
410	FPODetachObserver	Remove an observer from the list of observers
410	FPONotifyObservers	Notify observers of changes in the list
413	GetEnumerator	Create an <code>IEnumerator</code> instance
413	IndexOf	Returns the index of a given pointer.
413	Insert	Inserts a new pointer in the list at a given position.
414	Last	Returns the last non-nil pointer in the list.
414	Move	Moves a pointer from one position in the list to another.
415	Pack	Removes <code>Nil</code> pointers from the list and frees unused memory.
414	Remove	Removes a value from the list.
415	Sort	Sorts the pointers in the list.

4.59.4 Property overview

Page	Properties	Access	Description
415	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
416	Count	rw	Current number of pointers in the list.
416	Items	rw	Provides access to the pointers in the list.
416	List	r	Memory array where pointers are stored.

4.59.5 TList.Create

Synopsis: Class to manage collections of pointers.

Declaration: `constructor Create`

Visibility: `public`

Description: `TList.Create` creates a new instance of `TList`. It clears the list and prepares it for use.

See also: `TList` ([408](#)), `TList.Destroy` ([409](#))

4.59.6 TList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

4.59.7 TList.FPOAttachObserver

Synopsis: Add an observer to the list of observers

Declaration: `procedure FPOAttachObserver(AObserver: TObject)`

Visibility: public

Description: `FPOAttachObserver` is part of the implementation of the `IFPObserved` (307) interface in `TList`. It adds a new observer to the list of observers. Calling this multiple times will add the observed object multiple times to the list.

Errors: An `EObserver` exception may be raised if `AObject` does not implement the `IFPObserver` (309) interface.

See also: `IFPObserver` (309), `IFPObserved.FPOAttachObserver` (308), `IFPObserved` (307)

4.59.8 TList.FPODetachObserver

Synopsis: Remove an observer from the list of observers

Declaration: `procedure FPODetachObserver(AObserver: TObject)`

Visibility: public

Description: `FPODetachObserver` is part of the implementation of the `IFPObserved` (307) interface in `TList`. It removes the first found instance of the observer from the list of observers.

See also: `IFPObserved` (307), `IFPObserved.FPODetachObserver` (308), `IFPObserver` (309)

4.59.9 TList.FPONotifyObservers

Synopsis: Notify observers of changes in the list

Declaration: `procedure FPONotifyObservers(ASender: TObject;
AOperation: TFPObservedOperation;
Data: Pointer)`

Visibility: public

Description: `FPONotifyObservers` is called to notify observers of changes in the list. The following notifications are sent:

ooAddItem when a pointer is added. `Data` is the pointer that is added.

ooDeleteItem when a pointer is deleted or extracted. `Data` is the pointer that is deleted or extracted.

ooChange called when 2 pointers are exchanged.

ooFree Called when the list is freed.

See also: `FPODetachObserver` (266), `FPOAttachObserver` (266), `Add` (266), `Exchange` (266), `Delete` (266), `Extract` (266)

4.59.10 TList.AddList

Synopsis: Add all pointers from another list

Declaration: `procedure AddList (AList: TList)`

Visibility: public

Description: `AddList` adds all pointers from `AList` to the list. If a pointer is already present, it is added a second time.

See also: `TList.Assign` (414), `TFPList.AddList` (391)

4.59.11 TList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add (Item: Pointer) : Integer`

Visibility: public

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the `Grow` (408) method.

To insert a pointer at a certain position in the list, use the `Insert` (413) method instead.

See also: `Delete` (411), `Grow` (408), `Insert` (413)

4.59.12 TList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear; Virtual`

Visibility: public

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: `Destroy` (409)

4.59.13 TList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete (Index: Integer)`

Visibility: public

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

4.59.14 TList.Error

Synopsis: Raises an `EListError` (304) exception.

Declaration: `class procedure Error(const Msg: string; Data: PtrInt); Virtual`

Visibility: `public`

Description: `Error` raises an `EListError` (304) exception, with a message formatted with `Msg` and `Data`.

4.59.15 TList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: `public`

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` (304) exception will be raised.

4.59.16 TList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TList`

Visibility: `public`

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `Capacity` (415)

4.59.17 TList.Extract

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract(item: Pointer) : Pointer`

Visibility: `public`

Description: `Extract` searched for an occurrence of `item`, and if a match is found, the match is deleted from the list. If no match is found, nothing is deleted. If `Item` was found, the result is `Item`. If `Item` was not found, the result is `Nil`. A `lnExtracted` notification event is triggered if an element is extracted from the list.

See also: `TList.Delete` (411), `TList.IndexOf` (413), `TList.Remove` (414)

4.59.18 TList.First

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: public

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `Last` ([414](#))

4.59.19 TList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TListEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` ([1589](#)) interface for `TList`. It creates a `TListEnumerator` ([416](#)) instance and returns it's `IEnumerator` ([1589](#)) interface.

See also: `TListEnumerator` ([416](#)), `IEnumerator` ([1589](#)), `IEnumerable` ([1589](#))

4.59.20 TList.IndexOf

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

4.59.21 TList.Insert

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert(Index: Integer; Item: Pointer)`

Visibility: public

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` ([304](#)) exception is raised.

See also: `Add` ([411](#)), `Delete` ([411](#))

4.59.22 TList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: `public`

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `First` ([413](#))

4.59.23 TList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: `public`

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `Newindex` are not inside the valid range of indices, an `EListError` ([304](#)) exception is raised.

See also: `Exchange` ([412](#))

4.59.24 TList.Assign

Synopsis: Copy the contents of other lists.

Declaration: `procedure Assign (ListA: TList; AOperator: TListAssignOp; ListB: TList)`

Visibility: `public`

Description: `Assign` can be used to merge or assign lists. It is an extended version of the usual `TPersistent.Assign` mechanism. The arguments `ListA` and `ListB` are used as sources of pointers to add or remove elements from the current list, depending on the operation `AOperation`. The available operations are documented in the `TListAssignOp` ([275](#)) type.

See also: `TList.Clear` ([411](#))

4.59.25 TList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove (Item: Pointer) : Integer`

Visibility: `public`

Description: `Remove` searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `Delete` ([411](#)), `IndexOf` ([413](#)), `Insert` ([413](#))

4.59.26 TList.Pack

Synopsis: Removes Nil pointers from the list and frees unused memory.

Declaration: `procedure Pack`

Visibility: `public`

Description: `Pack` removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TList.Clear` ([411](#))

4.59.27 TList.Sort

Synopsis: Sorts the pointers in the list.

Declaration: `procedure Sort (Compare: TListSortCompare)`

Visibility: `public`

Description: `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

4.59.28 TList.Capacity

Synopsis: Current capacity (i.e. number of pointers that can be stored) of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read, Write`

Description: `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` ([411](#)) or `insert` ([413](#)), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `SetCapacity` ([408](#)), `Count` ([416](#))

4.59.29 TList.Count

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

4.59.30 TList.Items

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` is used to access the pointers in the list. It is the default property of the `TList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

4.59.31 TList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: `Read`

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

4.60 TListEnumerator

4.60.1 Description

`TListEnumerator` implements the `#rtl.system.IEnumerator` (1589) interface for the `TList` (408) class, so the `TList` class can be used in a `for ... in` loop. It is returned by the `TList.GetEnumerator` (413) method of `TList`.

See also: `TList` (408), `TList.GetEnumerator` (413), `#rtl.system.IEnumerator` (1589)

4.60.2 Method overview

Page	Method	Description
417	<code>Create</code>	Initialize a new instance of <code>TListEnumerator</code>
417	<code>GetCurrent</code>	Return the current pointer in the list
417	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

4.60.3 Property overview

Page	Properties	Access	Description
417	Current	r	Current pointer in the list

4.60.4 TListEnumerator.Create

Synopsis: Initialize a new instance of `TListEnumerator`

Declaration: `constructor Create (AList: TList)`

Visibility: `public`

Description: `Create` initializes a new instance of `TListEnumerator` and keeps a reference to the list `AList` that will be enumerated.

See also: `TList` ([408](#))

4.60.5 TListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : Pointer`

Visibility: `public`

Description: `GetCurrent` returns the current pointer in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` ([417](#))

4.60.6 TListEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([417](#))

4.60.7 TListEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : Pointer`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([417](#)) as a property.

See also: `GetCurrent` ([417](#))

4.61 TMemoryStream

4.61.1 Description

`TMemoryStream` is a `TStream` (448) descendant that stores its data in memory. It descends directly from `TCustomMemoryStream` (380) and implements the necessary to allocate and de-allocate memory directly from the heap. It implements the `Write` (419) method which is missing in `TCustomMemoryStream`.

`TMemoryStream` also introduces methods to load the contents of another stream or a file into the memory stream.

It is not necessary to do any memory management manually, as the stream will allocate or de-allocate memory as needed. When the stream is freed, all allocated memory will be freed as well.

See also: `TCustomMemoryStream` (380), `TStream` (448)

4.61.2 Method overview

Page	Method	Description
418	<code>Clear</code>	Zeroes the position, capacity and size of the stream.
418	<code>Destroy</code>	Frees any allocated memory and destroys the memory stream.
419	<code>LoadFromFile</code>	Loads the contents of a file into memory.
418	<code>LoadFromStream</code>	Loads the contents of a stream into memory.
419	<code>SetSize</code>	Sets the size for the memory stream.
419	<code>Write</code>	Writes data to the stream's memory.

4.61.3 TMemoryStream.Destroy

Synopsis: Frees any allocated memory and destroys the memory stream.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears the memory stream, thus in effect freeing any memory allocated for it, and then frees the memory stream.

4.61.4 TMemoryStream.Clear

Synopsis: Zeroes the position, capacity and size of the stream.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` sets the position and size to 0, and sets the capacity of the stream to 0, thus freeing all memory allocated for the stream.

See also: `TStream.Size` (458), `TStream.Position` (457), `TCustomMemoryStream.Memory` (382)

4.61.5 TMemoryStream.LoadFromStream

Synopsis: Loads the contents of a stream into memory.

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: public

Description: `LoadFromStream` loads the contents of `Stream` into the memorybuffer of the stream. Any previous contents of the memory stream are overwritten. Memory is allocated as needed.

Remark The `LoadFromStream` uses the `Size` (458) property of `Stream` to determine how much memory must be allocated. Some streams do not allow the stream size to be determined, so care must be taken when using this method.

This method will work much faster than the use of the `TStream.CopyFrom` (452) method:

```
Seek(0, soFromBeginning);
CopyFrom(Stream, Stream.Size);
```

because the `CopyFrom` method copies the contents in blocks, while `LoadFromStream` reads the contents of the stream as one big block.

Errors: If an error occurs when reading from the stream, an `EStreamError` (305) may occur.

See also: `TStream.CopyFrom` (452), `TMemoryStream.LoadFromFile` (419)

4.61.6 TMemoryStream.LoadFromFile

Synopsis: Loads the contents of a file into memory.

Declaration: `procedure LoadFromFile(const FileName: string)`

Visibility: public

Description: `LoadFromFile` loads the contents of the file with name `FileName` into the memory stream. The current contents of the memory stream is replaced by the contents of the file. Memory is allocated as needed.

The `LoadFromFile` method simply creates a filestream and then calls the `TMemoryStream.LoadFromStream` (418) method.

See also: `TMemoryStream.LoadFromStream` (418)

4.61.7 TMemoryStream.SetSize

Synopsis: Sets the size for the memory stream.

Declaration: `procedure SetSize(const NewSize: Int64); Override`

Visibility: public

Description: `SetSize` sets the size of the memory stream to `NewSize`. This will set the capacity of the stream to `NewSize` and correct the current position in the stream when needed.

See also: `TStream.Position` (457), `TStream.Size` (458)

4.61.8 TMemoryStream.Write

Synopsis: Writes data to the stream's memory.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` writes `Count` bytes from `Buffer` to the stream's memory, starting at the current position in the stream. If more memory is needed than currently allocated, more memory will be allocated. Any contents in the memory stream at the current position will be overwritten. The function returns the number of bytes actually written (which should under normal circumstances always equal `Count`).

This method overrides the `TStream.Write` (450) method.

Errors: If no more memory could be allocated, then an exception will be raised.

See also: `TCustomMemoryStream.Read` (381)

4.62 TOwnedCollection

4.62.1 Description

`TOwnedCollection` automatically maintains owner information, so it can be displayed in an IDE. Collections that should be displayed in an IDE should descend from `TOwnedCollection` or must implement a `GetOwner` function.

See also: `TCollection` (358)

4.62.2 Method overview

Page	Method	Description
420	<code>Create</code>	Create a new <code>TOwnerCollection</code> instance.

4.62.3 TOwnedCollection.Create

Synopsis: Create a new `TOwnerCollection` instance.

Declaration: `constructor Create(AOwner: TPersistent;
 AItemClass: TCollectionItemClass)`

Visibility: `public`

Description: `Create` creates a new instance of `TOwnedCollection` and stores the `AOwner` references. It will the value returned in the `TCollection.Owner` (360) property of the collection. The `ItemClass` class reference is passed on to the inherited constructor, and will be used to create new instances in the `Insert` (362) and `Add` (360) methods.

See also: `TCollection.Create` (359), `TCollection.Owner` (360)

4.63 TOwnerStream

4.63.1 Description

`TOwnerStream` can be used when creating stream chains such as when using encryption and compression streams. It keeps a reference to the source stream and will automatically free the source stream when ready (if the `SourceOwner` (422) property is set to `True`).

See also: `TStream` (448), `TOwnerStream.Source` (421), `TOwnerStream.SourceOwner` (422)

4.63.2 Method overview

Page	Method	Description
421	Create	Create a new instance of <code>TOwnerStream</code> .
421	Destroy	Destroys the <code>TOwnerStream</code> instance and the source stream.

4.63.3 Property overview

Page	Properties	Access	Description
421	Source	r	Reference to the source stream.
422	SourceOwner	rw	Indicates whether the ownerstream owns it's source

4.63.4 TOwnerStream.Create

Synopsis: Create a new instance of `TOwnerStream`.

Declaration: `constructor Create (ASource: TStream)`

Visibility: `public`

Description: `Create` instantiates a new instance of `TOwnerStream` and stores the reference to `ASource`. If `SourceOwner` is `True`, the source stream will also be freed when the instance is destroyed.

See also: `TOwnerStream.Destroy` ([421](#)), `TOwnerStream.Source` ([421](#)), `TOwnerStream.SourceOwner` ([422](#))

4.63.5 TOwnerStream.Destroy

Synopsis: Destroys the `TOwnerStream` instance and the source stream.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees the source stream if the `SourceOwner` property is `True`.

See also: `TOwnerStream.Create` ([421](#)), `TOwnerStream.Source` ([421](#)), `TOwnerStream.SourceOwner` ([422](#))

4.63.6 TOwnerStream.Source

Synopsis: Reference to the source stream.

Declaration: `Property Source : TStream`

Visibility: `public`

Access: `Read`

Description: `Source` is the source stream. It should be used by descendant streams to access the source stream to read from or write to.

Do not free the `Source` reference directly if `SourceOwner` is `True`. In that case the owner stream instance will free the source stream itself.

See also: `TOwnerStream.Create` ([421](#))

4.63.7 TOwnerStream.SourceOwner

Synopsis: Indicates whether the ownerstream owns it's source

Declaration: `Property SourceOwner : Boolean`

Visibility: `public`

Access: `Read, Write`

Description: `SourceOwner` indicates whether the `TOwnerStream` owns it's `Source` stream or not. If this property is `True` then the `Source` stream is freed when the `TOwnerStream` instance is freed.

See also: `TOwnerStream.Source` ([421](#)), `TOwnerStream.Destroy` ([421](#))

4.64 TParser

4.64.1 Description

This class breaks a stream of text data in tokens. Its primary use is to help reading the contents of a form file (usually a file with `dfm`, `xfm` or `lfm` extension), and for this reason it isn't suitable to be used as a general parser.

The parser is always positioned on a certain token, whose type is stored in the `Token` ([428](#)) property. Various methods are provided to obtain the token value in the desired format.

To advance to the next token, invoke `NextToken` ([425](#)) method.

See also: `TParser.Token` ([428](#)), `TParser.NextToken` ([425](#))

4.64.2 Method overview

Page	Method	Description
423	<code>CheckToken</code>	Checks whether the token if of the given type.
423	<code>CheckTokenSymbol</code>	Checks whether the token equals the given symbol
423	<code>Create</code>	Creates a new parser instance.
423	<code>Destroy</code>	Destroys the parser instance.
424	<code>Error</code>	Raises an <code>EParserError</code> (305) exception with the given message
424	<code>ErrorFmt</code>	Raises an <code>EParserError</code> (305) exception and formats the message.
424	<code>ErrorStr</code>	Raises an <code>EParserError</code> (305) exception with the given message
424	<code>HexToBinary</code>	Writes hexadecimal data to a stream.
425	<code>NextToken</code>	Reads the next token and returns its type.
425	<code>SourcePos</code>	Returns the current position in the stream.
425	<code>TokenComponentIdent</code>	Returns the path of a subcomponent starting from the current token.
426	<code>TokenFloat</code>	Returns the current token as a float.
426	<code>TokenInt</code>	Returns the current token as an integer.
426	<code>TokenString</code>	Returns the current token as a string.
427	<code>TokenSymbolIs</code>	Returns <code>True</code> if the token equals the given symbol.
427	<code>TokenWideString</code>	Returns the current token as a widestring

4.64.3 Property overview

Page	Properties	Access	Description
427	FloatType	r	The type of a float token.
428	SourceLine	r	Current source line number.
428	Token	r	The type of the current token.

4.64.4 TParser.Create

Synopsis: Creates a new parser instance.

Declaration: `constructor Create(Stream: TStream)`

Visibility: `public`

Description: `Create` creates a new `TParser` instance, using `Stream` as the stream to read data from, and reads the first token from the stream.

Errors: If an error occurs while parsing the first token, an `EParserError` ([305](#)) exception is raised.

See also: `TParser.NextToken` ([425](#)), `TParser.Token` ([428](#))

4.64.5 TParser.Destroy

Synopsis: Destroys the parser instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the parser instance.

Errors: None.

4.64.6 TParser.CheckToken

Synopsis: Checks whether the token is of the given type.

Declaration: `procedure CheckToken(T: Char)`

Visibility: `public`

Description: Checks whether the token is of the given type.

Errors: If current token isn't of type `T`, an `EParserError` ([305](#)) exception is raised.

See also: `TParser.Token` ([428](#))

4.64.7 TParser.CheckTokenSymbol

Synopsis: Checks whether the token equals the given symbol

Declaration: `procedure CheckTokenSymbol(const S: string)`

Visibility: `public`

Description: `CheckTokenSymbol` performs a case-insensitive comparison of current token value with `S`.

Current token must be of type `toSymbol` ([268](#)), otherwise an `EParserError` ([305](#)) exception is raised.

Errors: If the comparison fails, or current token isn't a symbol, an `EParserError` (305) exception is raised.

See also: `TParser.TokenSymbolIs` (427), `toSymbol` (268)

4.64.8 `TParser.Error`

Synopsis: Raises an `EParserError` (305) exception with the given message

Declaration: `procedure Error(const Ident: string)`

Visibility: public

Description: Raises an `EParserError` (305) exception with the given message

4.64.9 `TParser.ErrorFmt`

Synopsis: Raises an `EParserError` (305) exception and formats the message.

Declaration: `procedure ErrorFmt(const Ident: string; const Args: Array of const)`

Visibility: public

Description: Raises an `EParserError` (305) exception and formats the message.

4.64.10 `TParser.ErrorStr`

Synopsis: Raises an `EParserError` (305) exception with the given message

Declaration: `procedure ErrorStr(const Message: string)`

Visibility: public

Description: Raises an `EParserError` (305) exception with the given message

4.64.11 `TParser.HexToBinary`

Synopsis: Writes hexadecimal data to a stream.

Declaration: `procedure HexToBinary(Stream: TStream)`

Visibility: public

Description: `HexToBinary` reads a sequence of hexadecimal characters from the input stream and converts them to a sequence of bytes which is written to `Stream`. Each byte is represented by two contiguous hexadecimal characters.

Whitespace is allowed between hexadecimal characters if it doesn't appear between two characters that form the same byte.

`HexToBinary` stops when the first non-hexadecimal and non-whitespace character is found, or the end of the input stream is reached.

Remark This method begins reading after the current token: that is, current token, even if it's a valid hexadecimal value, isn't included.

Errors: If a single hexadecimal character is found, an `EParserError` (305) exception is raised.

4.64.12 TParser.NextToken

Synopsis: Reads the next token and returns its type.

Declaration: `function NextToken : Char`

Visibility: public

Description: `NextToken` parses the next token in the stream and returns its type. The type of the token can also be retrieved later reading `Token` (428) property.

If the end of the stream is reached, `toEOF` (268) is returned.

For details about token types, see `TParser.Token` (428)

Errors: If an error occurs while parsing the token, an `EParserError` (305) exception is raised.

See also: `TParser.Token` (428)

4.64.13 TParser.SourcePos

Synopsis: Returns the current position in the stream.

Declaration: `function SourcePos : LongInt`

Visibility: public

Description: This is not the character position relative to the current source line, but the byte offset from the beginning of the stream.

Errors: None.

See also: `TParser.SourceLine` (428)

4.64.14 TParser.TokenComponentIdent

Synopsis: Returns the path of a subcomponent starting from the current token.

Declaration: `function TokenComponentIdent : string`

Visibility: public

Description: If current token is `toSymbol` (268), `TokenComponentIdent` tries to find subcomponent names separated by a dot (.). The returned string is the longest subcomponent path found. If there are no subcomponents, current symbol is returned.

Remark After this method has been called, subsequent calls to `TokenString` (426) or `TokenWideString` (427) return the same value returned by `TokenComponentIdent`.

Example

If source stream contains `a.b.c` and `TParser` is positioned on the first token (`a`), this method returns `a.b.c`.

Errors: If `Token` (428) isn't `toSymbol` (268), or no valid symbol is found after a dot, an `EParserError` (305) exception is raised.

See also: `TParser.NextToken` (425), `TParser.Token` (428), `TParser.TokenString` (426), `TParser.TokenWideString` (427), `toSymbol` (268)

4.64.15 TParser.TokenFloat

Synopsis: Returns the current token as a float.

Declaration: `function TokenFloat : Extended`

Visibility: `public`

Description: If current token type is `toFloat` (268), this method returns the token value as a float.

To specify a negative number, no space must exist between unary minus and number.

Floating point numbers can be postfixed with a character that specifies the floating point type. See `FloatType` (427) for further information.

Remark In the input stream the decimal separator, if present, must be a dot (.).

Errors: If `Token` (428) isn't `toFloat` (268), an `EParserError` (305) exception is raised.

See also: `TParser.FloatType` (427), `TParser.NextToken` (425), `TParser.Token` (428), `toFloat` (268)

4.64.16 TParser.TokenInt

Synopsis: Returns the current token as an integer.

Declaration: `function TokenInt : Int64`

Visibility: `public`

Description: If current token type is `toInteger` (268), this method returns the token value as an integer.

In the input stream an integer can be an hexadecimal (prefixed by ' \$ ' character) or decimal number. Decimal numbers can be prefixed by an unary minus: if this is the case, no space must exist between minus and number.

Errors: If `Token` (428) isn't `toInteger` (268), an `EConvertError` (266) exception is raised.

See also: `TParser.NextToken` (425), `TParser.Token` (428), `toInteger` (268)

4.64.17 TParser.TokenString

Synopsis: Returns the current token as a string.

Declaration: `function TokenString : string`

Visibility: `public`

Description: If current token type is `toString` (268) or `toWString` (268), this method returns the contents of the string. That is, enclosing quotes are removed, embedded quotes are unescaped and control strings are converted to the appropriate sequence of characters.

If current token type isn't a string, a string containing the token representation in the input stream is returned, without any conversion: hexadecimal integers are returned with the leading \$, and floating point suffixes like `s`, `c` or `d` are kept. For tokens whose type isn't a special type, return value of `TokenString` equals `Token` (428).

Remark If `Token` (428) is `toWString` (268), `TokenWideString` (427) should be used instead.

Errors: None.

See also: `TParser.NextToken` (425), `TParser.TokenWideString` (427), `TParser.Token` (428), `toString` (268), `toWString` (268)

4.64.18 TParser.TokenWideString

Synopsis: Returns the current token as a widestring

Declaration: `function TokenWideString : WideString`

Visibility: public

Description: If current token type is `toWString` (268), this method returns the contents of the string. That is, enclosing quotes are removed, embedded quotes are unescaped and control strings are converted to the appropriate sequence of characters.

If current token isn't a widestring, `TokenWideString` behaviour is the same as `TokenString` (426).

Errors: None.

See also: `TParser.NextToken` (425), `TokenString` (426), `TParser.Token` (428), `toWString` (268)

4.64.19 TParser.TokenSymbols

Synopsis: Returns `True` if the token equals the given symbol.

Declaration: `function TokenSymbolIs(const S: string) : Boolean`

Visibility: public

Description: `TokenSymbolIs` performs a case-insensitive comparison of current token value with `S`.

If current token isn't of type `toSymbol` (268), or comparison fails, `False` is returned.

Errors: None.

See also: `TParser.CheckTokenSymbol` (423), `TParser.Token` (428)

4.64.20 TParser.FloatType

Synopsis: The type of a float token.

Declaration: `Property FloatType : Char`

Visibility: public

Access: Read

Description: Floating point numbers can be postfix with a character specifying the type of floating point value.

When specified, this property holds the character postfix to the number.

It can be one of the following values:

Table 4.28:

s or S	Value is a single.
c or C	Value is a currency.
d or D	Value is a date.

If `Token` (428) isn't `toFloat` (268) or one of the above characters wasn't specified, `FloatType` is the null character (zero).

See also: `TParser.NextToken` (425), `TParser.Token` (428), `TParser.TokenFloat` (426), `toFloat` (268)

4.64.21 TParser.SourceLine

Synopsis: Current source line number.

Declaration: `Property SourceLine : Integer`

Visibility: `public`

Access: `Read`

Description: Current source line number.

See also: `TParser.SourcePos` (425)

4.64.22 TParser.Token

Synopsis: The type of the current token.

Declaration: `Property Token : Char`

Visibility: `public`

Access: `Read`

Description: This property holds the type of the current token. When `Token` isn't one of the special token types (whose value can be retrieved with specific methods) it is the character representing the current token.

Special token types:

Table 4.29:

<code>toEOF</code> (268)	Value returned by <code>TParser.Token</code> (428) when the end of the input stream was reached.
<code>toSymbol</code> (268)	Value returned by <code>TParser.Token</code> (428) when a symbol was found in the input stream.
<code>toString</code> (268)	Value returned by <code>TParser.Token</code> (428) when a string was found in the input stream.
<code>toInteger</code> (268)	Value returned by <code>TParser.Token</code> (428) when an integer was found in the input stream.
<code>toFloat</code> (268)	Value returned by <code>TParser.Token</code> (428) when a floating point value was found in the input stream.
<code>toWString</code> (268)	Value returned by <code>TParser.Token</code> (428) when a wstring was found in the input stream.

To advance to the next token, use `NextToken` (425) method.

See also: `TParser.CheckToken` (423), `TParser.NextToken` (425), `TParser.TokenComponentIdent` (425), `TParser.TokenFloat` (426), `TParser.TokenInt` (426), `TParser.TokenString` (426), `TParser.TokenWideString` (427)

4.65 TPersistent

4.65.1 Description

`TPersistent` is the basic class for the streaming system. Since it is compiled in the `{ $M+ }` state, the compiler generates RTTI (Run-Time Type Information) for it and all classes that descend from it. This information can be used to stream all properties of classes.

It also introduces functionality to assign the contents of 2 classes to each other.

`TPersistent` implements the `IFPObserved` (307) interface for the benefit of descendant classes, but does not call `IFPObserved.FPONotifyObservers` (308). Descendants such as `TStrings` (468) and `TCollection` (358) and `TCollectionItem` (366) do use it.

See also: `TComponent` (369), `IFPObserved` (307), `TStrings` (468), `TCollection` (358), `TCollectionItem` (366)

4.65.2 Interfaces overview

Page	Interfaces	Description
307	IFPObserved	Interface implemented by an object that can be observed.

4.65.3 Method overview

Page	Method	Description
429	Assign	Assign the contents of one class to another.
429	Destroy	Destroys the <code>TPersistent</code> instance.
430	FPOAttachObserver	Add an observer to the list of observers.
430	FPODetachObserver	Remove an observer from the list of observers
430	FPONotifyObservers	Notify observers of changes.
430	GetNamePath	Returns a string that can be used to identify the class instance.

4.65.4 `TPersistent.Destroy`

Synopsis: Destroys the `TPersistent` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` disposes of the persistent object. This method should never be called directly. Instead the `Free` method should be used.

4.65.5 `TPersistent.Assign`

Synopsis: Assign the contents of one class to another.

Declaration: `procedure Assign(Source: TPersistent); Virtual`

Visibility: `public`

Description: `Assign` copies the contents of `Source` to `Self`, if the classes of the destination and source classes are compatible.

The `TPersistent` implementation of `Assign` does nothing but calling the `AssignTo` ([428](#)) method of source. This means that if the destination class does not know how to assign the contents of the source class, the source class instance is asked to assign itself to the destination class. This means that it is necessary to implement only one of the two methods so that two classes can be assigned to one another.

Remark In general, a statement of the form

```
Destination:=Source;
```

(where `Destination` and `Source` are classes) does not achieve the same as a statement of the form

```
Destination.Assign(Source);
```

After the former statement, both `Source` and `Destination` will point to the same object. The latter statement will copy the *contents* of the `Source` class to the `Destination` class.

See also: `AssignTo` ([428](#))

4.65.6 TPersistent.FPOAttachObserver

Synopsis: Add an observer to the list of observers.

Declaration: `procedure FPOAttachObserver(AObserver: TObject)`

Visibility: `public`

Description: `FPOAttachObserver` is part of the implementation of the `IFPObserved` (307) interface in `TPersistent`. It adds a new observer to the list of observers. Calling this multiple times will add the observed object multiple times to the list.

Errors: An `EObserver` exception may be raised if `AObject` does not implement the `IFPObserver` (309) interface.

See also: `IFPObserver` (309), `IFPObserved.FPOAttachObserver` (308), `IFPObserved` (307)

4.65.7 TPersistent.FPODetachObserver

Synopsis: Remove an observer from the list of observers

Declaration: `procedure FPODetachObserver(AObserver: TObject)`

Visibility: `public`

Description: `FPODetachObserver` is part of the implementation of the `IFPObserved` (307) interface in `TPersistent`. It removes the first found instance of the observer from the list of observers.

See also: `IFPObserved` (307), `IFPObserved.FPODetachObserver` (308), `IFPObserver` (309)

4.65.8 TPersistent.FPONotifyObservers

Synopsis: Notify observers of changes.

Declaration: `procedure FPONotifyObservers(ASender: TObject;
AOperation: TFPObservedOperation;
Data: Pointer)`

Visibility: `public`

Description: `FPONotifyObservers` can be called to notify observers of changes in the object. This method simply passes on the parameters that it receives to all attached `IFPObserver` (309) interfaces.

`TPersistent` does not call `FPONotifyObservers`. It is implemented for the benefit of descendant classes.

See also: `IFPObserved` (307), `IFPObserved.FPONotifyObservers` (308), `IFPObserver` (309)

4.65.9 TPersistent.GetNamePath

Synopsis: Returns a string that can be used to identify the class instance.

Declaration: `function GetNamePath : string; Virtual`

Visibility: `public`

Description: `GetNamePath` returns a string that can be used to identify the class instance. This can be used to display a name for this instance in a Object designer.

`GetNamePath` constructs a name by recursively prepending the `Classname` of the Owner instance to the `Classname` of this instance, separated by a dot.

See also: `TPersistent.GetOwner` (428)

4.66 TProxyStream

4.66.1 Description

TProxyStream is a proxy class for the #rtl.types.IStream (1965) interface. It implements all stream methods by relaying them to the IStream interface.

See also: #rtl.types.IStream (1965), TStreamAdapter (458)

4.66.2 Method overview

Page	Method	Description
432	Check	Check errors
431	Create	Create a new instance of the TProxyStream class.
431	Read	
431	Seek	
431	Write	

4.66.3 TProxyStream.Create

Synopsis: Create a new instance of the TProxyStream class.

Declaration: `constructor Create(const Stream: IStream)`

Visibility: public

Description: Create initializes a new instance of the TProxyStream class. It saves var stream for use in the other methods.

See also: #rtl.types.IStream (1965)

4.66.4 TProxyStream.Read

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

4.66.5 TProxyStream.Write

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

4.66.6 TProxyStream.Seek

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: public

4.66.7 TProxyStream.Check

Synopsis: Check errors

Declaration: `procedure Check(err: Integer); Virtual`

Visibility: public

Description: `Check` will check the result of the `IStream` interface. This method must be overridden by descendant classes to return interface-specific errors.

See also: `#rtl.types.IStream` (1965)

4.67 TRawByteStringStream

4.67.1 Description

`TRawByteStringStream` is a `TBytesStream` (357) descendent which introduces some auxiliary methods that help with inserting or extracting single-byte strings from the data: `DataStream` (432), `ReadString` (433) and `WriteString` (433).

In difference with `TStringStream` (494), the data has no codepage information associated with it, so the data is always considered to use the default codepage.

See also: `TStringStream` (494), `DataStream` (432), `ReadString` (433), `WriteString` (433)

4.67.2 Method overview

Page	Method	Description
432	<code>Create</code>	Create a new instance of <code>TRawByteStringStream</code> .
432	<code>DataStream</code>	Return the stream contents as a single-byte string.
433	<code>ReadString</code>	Read a string from the stream
433	<code>WriteString</code>	Write a string to the stream

4.67.3 TRawByteStringStream.Create

Synopsis: Create a new instance of `TRawByteStringStream`.

Declaration: `constructor Create(const aData: RawByteString); Overload`

Visibility: public

Description: `Create` creates a new instance of `TRawByteStringStream` and initializes the `Memory` (382) with the characters in `aData`.

See also: `Memory` (382), `DataStream` (432)

4.67.4 TRawByteStringStream.DataString

Synopsis: Return the stream contents as a single-byte string.

Declaration: `function DataString : RawByteString`

Visibility: public

Description: `DataStream` returns the data in `Memory` (382) as a single-byte string without codepage information associated with it. The operation does not change the current position of the stream.

See also: `Memory` (382), `ReadString` (433), `WriteString` (433)

4.67.5 TRawByteStringStream.ReadString

Synopsis: Read a string from the stream

Declaration: `function ReadString(Count: LongInt) : RawByteString`

Visibility: public

Description: `ReadString` reads at most `Count` bytes from the stream and returns the data as a single-byte string. The operation forwards the current position of the stream with at most `Count` bytes.

See also: `DataString` ([432](#)), `WriteString` ([433](#))

4.67.6 TRawByteStringStream.WriteString

Synopsis: Write a string to the stream

Declaration: `procedure WriteString(const AString: RawByteString)`

Visibility: public

Description: `WriteString` writes the bytes in `aString` to the stream. The operation forwards the current position of the stream with the length of the stream.

See also: `DataString` ([432](#)), `WriteString` ([433](#))

4.68 TReader

4.68.1 Description

The `TReader` class is a reader class that implements generic component streaming capabilities, independent of the format of the data in the stream. It uses a driver class `TAbstractObjectReader` ([319](#)) to do the actual reading of data. The interface of the `TReader` class should be identical to the interface in Delphi.

Note that the `TReader` design is such that it can read a single component from a stream. It will read all children of this component, but it is not designed to read multiple components in succession from one stream.

It should never be necessary to create an instance of this class directly. Instead, the `TStream.ReadComponent` ([452](#)) call should be used.

See also: `TFile` ([386](#)), `TWriter` ([515](#)), `TAbstractObjectReader` ([319](#))

4.68.2 Method overview

Page	Method	Description
436	BeginReferences	Initializes the component referencing mechanism.
436	CheckValue	Raises an exception if the next value in the stream is not of type Value
442	CopyValue	Copy a value to a writer.
435	Create	Creates a new reader class
436	DefineBinaryProperty	Reads a user-defined binary property from the stream.
436	DefineProperty	Reads a user-defined property from the stream.
435	Destroy	Destroys a reader class.
436	EndOfList	Returns true if the stream contains an end-of-list marker.
437	EndReferences	Finalizes the component referencing mechanism.
437	FixupReferences	Tries to resolve all unresolved component references.
435	FlushBuffer	Flush the buffer
437	NextValue	Returns the type of the next value.
437	Read	Read raw data from stream
437	ReadBoolean	Reads a boolean from the stream.
438	ReadChar	Reads a character from the stream.
438	ReadCollection	Reads a collection from the stream.
438	ReadComponent	Starts reading a component from the stream.
439	ReadComponents	Starts reading child components from the stream.
439	ReadCurrency	Read a currency value from the stream.
439	ReadDate	Reads a date from the stream
439	ReadFloat	Reads a float from the stream.
440	ReadIdent	Reads an identifier from the stream.
440	ReadInt64	Reads a 64-bit integer from the stream.
440	ReadInteger	Reads an integer from the stream
440	ReadListBegin	Checks for the beginning of a list.
441	ReadListEnd	Checks for the end of a list.
441	ReadRootComponent	Starts reading a root component.
440	ReadSet	Read a set value from the stream
441	ReadSignature	Read stream signature from the stream
439	ReadSingle	Reads a single-type real from the stream.
441	ReadString	Reads a string from the stream.
438	ReadUnicodeChar	Read Unicode character
442	ReadUnicodeString	Read a UnicodeString value from the stream
442	ReadValue	Reads the next value type from the stream.
441	ReadVariant	Read a variant from the stream
438	ReadWideChar	Read widechar from the stream
442	ReadWideString	Read a WideString value from the stream.

4.68.3 Property overview

Page	Properties	Access	Description
442	Driver	r	The driver in use for streaming the data.
444	OnAncestorNotFound	rw	Handler called when the ancestor component cannot be found.
445	OnCreateComponent	rw	Handler called when a component needs to be created.
443	OnError	rw	Handler called when an error occurs.
445	OnFindComponentClass	rw	Handler called when a component class reference needs to be found.
444	OnFindMethod	rw	Handler to find or change a method address.
443	OnPropertyNotFound	rw	Handler for treating missing properties.
445	OnReadStringProperty	rw	Handler for translating strings when read from the stream.
444	OnReferenceName	rw	Handler called when another component is referenced.
444	OnSetMethodProperty	rw	Handler for setting method properties.
444	OnSetName	rw	Handler called when setting a component name.
443	Owner	rw	Owner of the component being read
443	Parent	rw	Parent of the component being read.

4.68.4 TReader.Create

Synopsis: Creates a new reader class

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new reader class

4.68.5 TReader.Destroy

Synopsis: Destroys a reader class.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys a reader class.

4.68.6 TReader.FlushBuffer

Synopsis: Flush the buffer

Declaration: `procedure FlushBuffer; Override`

Visibility: `public`

Description: `FlushBuffer` flushes the buffer. It is provided for Delphi compatibility, and is not used in FPC.

See also: `TFile.FlushBuffer` ([387](#)), `TAbstractObjectReader.FlushBuffer` ([319](#))

4.68.7 TReader.BeginReferences

Synopsis: Initializes the component referencing mechanism.

Declaration: `procedure BeginReferences`

Visibility: `public`

Description: When streaming components, the streaming mechanism keeps a list of existing components that can be referenced to. This method initializes up that system.

4.68.8 TReader.CheckValue

Synopsis: Raises an exception if the next value in the stream is not of type `Value`

Declaration: `procedure CheckValue(Value: TValueType)`

Visibility: `public`

Description: Raises an exception if the next value in the stream is not of type `Value`

4.68.9 TReader.DefineProperty

Synopsis: Reads a user-defined property from the stream.

Declaration: `procedure DefineProperty(const Name: string; AReadData: TReaderProc;
WriteData: TWriterProc; HasData: Boolean)
; Override`

Visibility: `public`

Description: Reads a user-defined property from the stream.

4.68.10 TReader.DefineBinaryProperty

Synopsis: Reads a user-defined binary property from the stream.

Declaration: `procedure DefineBinaryProperty(const Name: string;
AReadData: TStreamProc;
WriteData: TStreamProc; HasData: Boolean)
; Override`

Visibility: `public`

Description: Reads a user-defined binary property from the stream.

4.68.11 TReader.EndOfList

Synopsis: Returns true if the stream contains an end-of-list marker.

Declaration: `function EndOfList : Boolean`

Visibility: `public`

Description: Returns true if the stream contains an end-of-list marker.

4.68.12 TReader.EndReferences

Synopsis: Finalizes the component referencing mechanism.

Declaration: `procedure EndReferences`

Visibility: `public`

Description: When streaming components, the streaming mechanism keeps a list of existing components that can be referenced to. This method cleans up that system.

4.68.13 TReader.FixupReferences

Synopsis: Tries to resolve all unresolved component references.

Declaration: `procedure FixupReferences`

Visibility: `public`

Description: Tries to resolve all unresolved component references.

4.68.14 TReader.NextValue

Synopsis: Returns the type of the next value.

Declaration: `function NextValue : TValueType`

Visibility: `public`

Description: Returns the type of the next value.

4.68.15 TReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: `public`

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TAbstractObjectReader.Read` ([321](#)), `TBinaryObjectReader.Read` ([341](#))

4.68.16 TReader.ReadBoolean

Synopsis: Reads a boolean from the stream.

Declaration: `function ReadBoolean : Boolean`

Visibility: `public`

Description: Reads a boolean from the stream.

4.68.17 TReader.ReadChar

Synopsis: Reads a character from the stream.

Declaration: `function ReadChar : Char`

Visibility: `public`

Description: Reads a character from the stream.

4.68.18 TReader.ReadWideChar

Synopsis: Read widechar from the stream

Declaration: `function ReadWideChar : WideChar`

Visibility: `public`

Description: `TReader.ReadWideChar` reads a widechar from the stream. This actually reads a widestring and returns the first character.

See also: `TReader.ReadWideString` ([442](#)), `TWriter.WriteWideChar` ([518](#))

4.68.19 TReader.ReadUnicodeChar

Synopsis: Read Unicode character

Declaration: `function ReadUnicodeChar : UnicodeChar`

Visibility: `public`

Description: `ReadUnicodeChar` reads a single Unicode character from the stream. It does this by reading a `UnicodeString` string from the stream and returning the first character.

Errors: If the string has a length different from 1, an `EReadError` exception will occur.

See also: `TReader.ReadUnicodeString` ([442](#))

4.68.20 TReader.ReadCollection

Synopsis: Reads a collection from the stream.

Declaration: `procedure ReadCollection(Collection: TCollection)`

Visibility: `public`

Description: Reads a collection from the stream.

4.68.21 TReader.ReadComponent

Synopsis: Starts reading a component from the stream.

Declaration: `function ReadComponent(Component: TComponent) : TComponent`

Visibility: `public`

Description: Starts reading a component from the stream.

4.68.22 TReader.ReadComponents

Synopsis: Starts reading child components from the stream.

Declaration: `procedure ReadComponents(AOwner: TComponent; AParent: TComponent;
Proc: TReadComponentsProc)`

Visibility: public

Description: Starts reading child components from the stream.

4.68.23 TReader.ReadFloat

Synopsis: Reads a float from the stream.

Declaration: `function ReadFloat : Extended`

Visibility: public

Description: Reads a float from the stream.

4.68.24 TReader.ReadSingle

Synopsis: Reads a single-type real from the stream.

Declaration: `function ReadSingle : Single`

Visibility: public

Description: Reads a single-type real from the stream.

4.68.25 TReader.ReadDate

Synopsis: Reads a date from the stream

Declaration: `function ReadDate : TDateTime`

Visibility: public

Description: Reads a date from the stream

4.68.26 TReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency`

Visibility: public

Description: `ReadCurrency` reads a currency typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteCurrency` ([519](#))

4.68.27 TReader.ReadIdent

Synopsis: Reads an identifier from the stream.

Declaration: `function ReadIdent : string`

Visibility: `public`

Description: Reads an identifier from the stream.

4.68.28 TReader.ReadInteger

Synopsis: Reads an integer from the stream

Declaration: `function ReadInteger : LongInt`

Visibility: `public`

Description: Reads an integer from the stream

4.68.29 TReader.ReadInt64

Synopsis: Reads a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64`

Visibility: `public`

Description: Reads a 64-bit integer from the stream.

4.68.30 TReader.ReadSet

Synopsis: Read a set value from the stream

Declaration: `function ReadSet (EnumType: Pointer) : Integer`

Visibility: `public`

Description: `ReadSet` reads a set of elements with type `EnumType` and returns them as an integer where each element is encoded in a bit of the integer. Thus, at most an enumerated type with 32 elements can be read with this function.

Errors: No checking is performed on the validity of `EnumType`. It is assumed to be a valid `PTypeInfo` pointer.

See also: `TWriter.WriteSet` ([520](#))

4.68.31 TReader.ReadListBegin

Synopsis: Checks for the beginning of a list.

Declaration: `procedure ReadListBegin`

Visibility: `public`

Description: Checks for the beginning of a list.

4.68.32 TReader.ReadListEnd

Synopsis: Checks for the end of a list.

Declaration: `procedure ReadListEnd`

Visibility: `public`

Description: Checks for the end of a list.

4.68.33 TReader.ReadRootComponent

Synopsis: Starts reading a root component.

Declaration: `function ReadRootComponent (ARoot: TComponent) : TComponent`

Visibility: `public`

Description: Starts reading a root component.

4.68.34 TReader.ReadVariant

Synopsis: Read a variant from the stream

Declaration: `function ReadVariant : Variant`

Visibility: `public`

Description: `ReadVariant` reads the next value from the stream and returns it as a variant. No variant array can be read from the stream, only single values.

Errors: If no variant manager is installed, the function will raise an `EReadError` exception. If the next value is not a simple value, again an `EReadError` exception is raised. exception is

See also: `TBinaryObjectWriter.WriteVariant` ([351](#))

4.68.35 TReader.ReadSignature

Synopsis: Read stream signature from the stream

Declaration: `procedure ReadSignature`

Visibility: `public`

Description: `ReadSignature` is called when starting to read a root component from a stream. Some streams contain a signature (header) to detect whether the stream contains correct data.

Errors: If the stream does not start with the correct signature, an `EReadError` ([305](#)) exception will be raised.

See also: `TAbstractObjectReader.ReadSignature` ([325](#)), `TAbstractObjectWriter.WriteSignature` ([328](#))

4.68.36 TReader.ReadString

Synopsis: Reads a string from the stream.

Declaration: `function ReadString : string`

Visibility: `public`

Description: Reads a string from the stream.

4.68.37 TReader.ReadWideString

Synopsis: Read a WideString value from the stream.

Declaration: `function ReadWideString : WideString`

Visibility: public

Description: `ReadWideString` reads a `WideString` typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteString` ([521](#))

4.68.38 TReader.ReadUnicodeString

Synopsis: Read a UnicodeString value from the stream

Declaration: `function ReadUnicodeString : UnicodeString`

Visibility: public

Description: `ReadUnicodeString` reads a `UnicodeString` string from the stream. The stream can contain a string from any type, it will be converted to `UnicodeString`.

See also: `TAbstractObjectReader.ReadUnicodeString` ([326](#)), `TWriter.WriteUnicodeString` ([521](#))

4.68.39 TReader.ReadValue

Synopsis: Reads the next value type from the stream.

Declaration: `function ReadValue : TValueType`

Visibility: public

Description: Reads the next value type from the stream.

4.68.40 TReader.CopyValue

Synopsis: Copy a value to a writer.

Declaration: `procedure CopyValue (Writer: TWriter)`

Visibility: public

Description: `CopyValue` reads the next value from the reader stream, and writes it to the passed `Writer`.

4.68.41 TReader.Driver

Synopsis: The driver in use for streaming the data.

Declaration: `Property Driver : TAbstractObjectReader`

Visibility: public

Access: Read

Description: The driver in use for streaming the data.

4.68.42 TReader.Owner

Synopsis: Owner of the component being read

Declaration: `Property Owner : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Owner of the component being read

4.68.43 TReader.Parent

Synopsis: Parent of the component being read.

Declaration: `Property Parent : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Parent of the component being read.

4.68.44 TReader.OnError

Synopsis: Handler called when an error occurs.

Declaration: `Property OnError : TReaderError`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when an error occurs.

4.68.45 TReader.OnPropertyNotFound

Synopsis: Handler for treating missing properties.

Declaration: `Property OnPropertyNotFound : TPropertyNotFoundEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnPropertyNotFound` can be used to take appropriate action when a property is read from a stream and no such property is found in the RTTI information of the Instance that is being read from the stream. It can be set at runtime, or at design time by an IDE.

For more information about the meaning of the various arguments to the event handler, see `TPropertyNotFoundEvent` ([278](#)).

See also: `TPropertyNotFoundEvent` ([278](#)), `TReader.OnSetMethodProperty` ([444](#)), `TReader.OnReadStringProperty` ([445](#))

4.68.46 TReader.OnFindMethod

Synopsis: Handler to find or change a method address.

Declaration: `Property OnFindMethod : TFindMethodEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler to find or change a method address.

4.68.47 TReader.OnSetMethodProperty

Synopsis: Handler for setting method properties.

Declaration: `Property OnSetMethodProperty : TSetMethodPropertyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnSetMethodProperty` can be set to handle the setting of method properties. This handler can be used by an IDE to prevent methods from actually being assigned when an object is being streamed in the designer.

See also: `TReader.OnReadStringProperty` ([445](#)), `TReader.OnPropertyNotFound` ([443](#))

4.68.48 TReader.OnSetName

Synopsis: Handler called when setting a component name.

Declaration: `Property OnSetName : TSetNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when setting a component name.

4.68.49 TReader.OnReferenceName

Synopsis: Handler called when another component is referenced.

Declaration: `Property OnReferenceName : TReferenceNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when another component is referenced.

4.68.50 TReader.OnAncestorNotFound

Synopsis: Handler called when the ancestor component cannot be found.

Declaration: `Property OnAncestorNotFound : TAncestorNotFoundEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when the ancestor component cannot be found.

4.68.51 TReader.OnCreateComponent

Synopsis: Handler called when a component needs to be created.

Declaration: Property OnCreateComponent : TCreateComponentEvent

Visibility: public

Access: Read,Write

Description: Handler called when a component needs to be created.

4.68.52 TReader.OnFindComponentClass

Synopsis: Handler called when a component class reference needs to be found.

Declaration: Property OnFindComponentClass : TFindComponentClassEvent

Visibility: public

Access: Read,Write

Description: Handler called when a component class reference needs to be found.

4.68.53 TReader.OnReadStringProperty

Synopsis: Handler for translating strings when read from the stream.

Declaration: Property OnReadStringProperty : TReadWriteStringPropertyEvent

Visibility: public

Access: Read,Write

Description: OnReadStringProperty is called whenever a string property is read from the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is loaded. See TReadWriteStringPropertyEvent (278) for a description of the various parameters.

See also: TReader.OnPropertyNotFound (443), TReader.OnSetMethodProperty (444), TReadWriteStringPropertyEvent (278)

4.69 TRecall

4.69.1 Description

TRecall is a helper class used to copy published properties of a class (the reference object) in another class (the storage object). The reference object and storage object must be assignable to each other.

The TRecall can be used to store the state of a persistent class, and restore it at a later time.

When a TRecall object is created, it gets passed a reference instance and a storage instance. It immediately stores the properties of the reference object in the storage object.

The Store (446) method can be called throughout the lifetime of the reference object to update the stored properties.

When the TRecall instance is destroyed then the properties are copied from the storage object to the reference object. The storage object is freed automatically.

If the properties should not be copied back from the storage to the reference object, the Forget (447) can be called.

See also: `TRecall.Create` (446), `TRecall.Destroy` (446), `TRecall.Forget` (447), `TRecall.Store` (446), `TPersistent.Assign` (429)

4.69.2 Method overview

Page	Method	Description
446	<code>Create</code>	Creates a new instance of <code>TRecall</code> .
446	<code>Destroy</code>	Copies the stored properties to the reference object and destroys the <code>TRecall</code> instance.
447	<code>Forget</code>	Clear the reference property.
446	<code>Store</code>	Assigns the reference instance to the storage instance.

4.69.3 Property overview

Page	Properties	Access	Description
447	<code>Reference</code>	<code>r</code>	The reference object.

4.69.4 TRecall.Create

Synopsis: Creates a new instance of `TRecall`.

Declaration: `constructor Create(AStorage: TPersistent; AReference: TPersistent)`

Visibility: `public`

Description: `Create` creates a new instance of `TRecall` and initializes the `Reference` and `Storage` instances. It calls `Store` (446) to assign the reference object properties to the storage instance.

See also: `TRecall.Store` (446), `TRecall.Destroy` (446)

4.69.5 TRecall.Destroy

Synopsis: Copies the stored properties to the reference object and destroys the `TRecall` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` assigns the storage instance to the reference instance, if the latter is still valid. After this, it frees the storage and calls the inherited `destroy`.

Errors: `Destroy` does not check whether the reference (447) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` (447) to clear the reference instance.

See also: `TRecall.Store` (446), `TRecall.Forget` (447)

4.69.6 TRecall.Store

Synopsis: Assigns the reference instance to the storage instance.

Declaration: `procedure Store`

Visibility: `public`

Description: `Store` assigns the reference instance to the storage instance. This will only work if the two classes can be assigned to each other.

This method can be used to refresh the storage.

Errors: `Store` does not check whether the reference (447) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` (447) to clear the reference instance.

4.69.7 TRecall.Forget

Synopsis: Clear the reference property.

Declaration: `procedure Forget`

Visibility: `public`

Description: `Forget` sets the `Reference` (447) property to `Nil`. When the `TRecall` instance is destroyed, the reference instance will not be restored.

Note that after a call to `Forget`, a call to `Store` (446) has no effect.

Errors: None.

See also: `TRecall.Reference` (447), `TRecall.Store` (446), `TRecall.Destroy` (446)

4.69.8 TRecall.Reference

Synopsis: The reference object.

Declaration: `Property Reference : TPersistent`

Visibility: `public`

Access: `Read`

Description: `Reference` is the instance of the reference object. Do not free the reference directly. Call `Forget` (447) to clear the reference and then free the reference object.

See also: `TRecall.Forget` (447)

4.70 TResourceStream

4.70.1 Description

Stream that reads its data from a resource object.

4.70.2 Method overview

Page	Method	Description
448	<code>Create</code>	Creates a new instance of a resource stream.
448	<code>CreateFromID</code>	Creates a new instance of a resource stream with a resource
448	<code>Destroy</code>	Destroys the instance of the resource stream.

4.70.3 TResourceStream.Create

Synopsis: Creates a new instance of a resource stream.

Declaration: constructor `Create`(Instance: TFPResourceHMODULE; const ResName: string;
ResType: PChar)

Visibility: public

Description: Creates a new instance of a resource stream.

4.70.4 TResourceStream.CreateFromID

Synopsis: Creates a new instance of a resource stream with a resource

Declaration: constructor `CreateFromID`(Instance: TFPResourceHMODULE; ResID: Integer;
ResType: PChar)

Visibility: public

Description: The resource is loaded from the loaded module (identified by the handle `Instance`), identifier `ResID` and type `ResType`.

4.70.5 TResourceStream.Destroy

Synopsis: Destroys the instance of the resource stream.

Declaration: destructor `Destroy`; Override

Visibility: public

Description: Destroys the instance of the resource stream.

4.71 TStream

4.71.1 Description

`TStream` is the base class for all streaming classes. It defines methods for reading (449), writing (450) from and to streams, as well as functions to determine the size of the stream as well as the current position of the stream.

Descendant classes such as `TMemoryStream` (418) or `TFileStream` (388) then override these methods to write streams to memory or file.

See also: `TMemoryStream` (418), `TFileStream` (388), `TStringStream` (494)

4.71.2 Method overview

Page	Method	Description
452	CopyFrom	Copy data from one stream to another
454	FixupResourceHeader	Not implemented in FPC
449	Read	Reads data from the stream to a buffer and returns the number of bytes read.
456	ReadAnsiString	Read an ansistring from the stream and return its value.
451	ReadBuffer	Reads data from the stream to a buffer
454	ReadByte	Read a byte from the stream and return its value.
452	ReadComponent	Reads component data from a stream
452	ReadComponentRes	Reads component data and resource header from a stream
455	ReadDWord	Read a DWord from the stream and return its value.
455	ReadQWord	Read a QWord value from the stream and return its value
454	ReadResHeader	Read a resource header from the stream.
455	ReadWord	Read a word from the stream and return its value.
450	Seek	Sets the current position in the stream
450	Write	Writes data from a buffer to the stream and returns the number of bytes written.
457	WriteAnsiString	Write an ansistring to the stream.
451	WriteBuffer	Writes data from a buffer to the stream
456	WriteByte	Write a byte to the stream.
453	WriteComponent	Write component data to the stream
453	WriteComponentRes	Write resource header and component data to a stream
453	WriteDescendent	Write descendent of a component
453	WriteDescendentRes	Write descendent of a component as resource
456	WriteDWord	Write a DWord to the stream.
457	WriteQWord	Write a QWord value to the stream
454	WriteResourceHeader	Write resource header to the stream
456	WriteWord	Write a word to the stream.

4.71.3 Property overview

Page	Properties	Access	Description
457	Position	rw	The current position in the stream.
458	Size	rw	The current size of the stream.

4.71.4 TStream.Read

Synopsis: Reads data from the stream to a buffer and returns the number of bytes read.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Virtual; Overload`

Visibility: public

Description: Read attempts to read `Count` from the stream to `Buffer` and returns the number of bytes actually read.

This method should be used when the number of bytes is not determined. If a specific number of bytes is expected, use `TStream.ReadBuffer` ([451](#)) instead.

As implemented in `TStream`, `Read` does nothing but raises an `EStreamError` ([305](#)) exception to indicate that reading is not supported. Descendant classes that allow reading must override this method to do the actual reading.

Descendant classes should (if they don't explicitly raise an exception) return a positive value (≥ 0), where zero indicates an error.

Errors: In case a descendant class does not allow reading from the stream, an exception is raised.

See also: `TStream.Write` (450), `TStream.ReadBuffer` (451)

4.71.5 TStream.Write

Synopsis: Writes data from a buffer to the stream and returns the number of bytes written.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Virtual
; Overload`

Visibility: public

Description: `Write` attempts to write `Count` bytes from `Buffer` to the stream. It returns the actual number of bytes written to the stream.

This method should be used when the number of bytes that should be written is not determined. If a specific number of bytes should be written, use `TStream.WriteBuffer` (451) instead.

As implemented in `TStream`, `Write` does nothing but raises `EStreamError` (305) exception to indicate that writing is not supported. Descendant classes that allow writing must override this method to do the actual writing.

Descendant classes should (if they don't explicitly raise an exception) return a positive value (≥ 0), where zero indicates an error.

Errors: In case a descendant class does not allow writing to the stream, an exception is raised.

See also: `TStream.Read` (449), `TStream.WriteBuffer` (451)

4.71.6 TStream.Seek

Synopsis: Sets the current position in the stream

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Virtual
; Overload
function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64
; Virtual; Overload`

Visibility: public

Description: `Seek` sets the position of the stream to `Offset` bytes from `Origin`. There is a 32-bit variant of this function and a 64-bit variant. The difference can be made by choosing the correct `Offset` parameter: the integer-typed parameter selects the 32-bit variant, the parameter of type `TSeekOrigin` (279) selects the 64-bit variant of the function.

The `Origin` parameter for the 32-bit version can have one of the following values:

Table 4.30:

Constant	Meaning
<code>soFromBeginning</code>	Set the position relative to the start of the stream.
<code>soFromCurrent</code>	Set the position relative to the current position in the stream.
<code>soFromEnd</code>	Set the position relative to the end of the stream.

These values are defined in the `SysUtils` (266) unit.

The `Origin` parameter for the 64-bit version has one of the following values:

Table 4.31:

Value	Meaning
<code>soBeginning</code>	Offset is interpreted relative to the start of the stream.
<code>soCurrent</code>	Offset is interpreted relative to the current position in the stream.
<code>soEnd</code>	Offset is interpreted relative to the end of the stream.

Offset should be negative when the origin is `SoFromEnd` (`soEnd`). It should be positive for `soFromBeginning` and can have both signs for `soFromCurrent`.

This is an abstract method, which must be overridden by descendant classes. They may choose not to implement this method for all values of `Origin` and `Offset`.

Remark Internally, all calls are re-routed to the 64-bit version of the call. When creating a descendant of `TStream`, the 64-bit version of the call should be overridden.

Errors: An exception may be raised if this method is called with an invalid pair of `Offset`, `Origin` values. e.g. a negative offset for `soFromBeginning` (or `soBeginning`).

See also: `TStream.Position` (457)

4.71.7 TStream.ReadBuffer

Synopsis: Reads data from the stream to a buffer

Declaration: `procedure ReadBuffer(var Buffer; Count: LongInt)`

Visibility: public

Description: `ReadBuffer` reads `Count` bytes of the stream into `Buffer`. If the stream does not contain `Count` bytes, then an exception is raised.

`ReadBuffer` should be used to read in a fixed number of bytes, such as when reading structures or the content of variables. If the number of bytes is not determined, use `TStream.Read` (449) instead. `ReadBuffer` uses `Read` internally to do the actual reading.

Errors: If the stream does not allow to read `Count` bytes, then an exception is raised.

See also: `TStream.Read` (449), `TStream.WriteBuffer` (451)

4.71.8 TStream.WriteBuffer

Synopsis: Writes data from a buffer to the stream

Declaration: `procedure WriteBuffer(const Buffer; Count: LongInt)`

Visibility: public

Description: `WriteBuffer` writes `Count` bytes to the stream from `Buffer`. If the stream does not allow `Count` bytes to be written, then an exception is raised.

`WriteBuffer` should be used to write a fixed number of bytes, such as when writing structures or the content of variables. If the number of bytes is not determined, use `TStream.Write` (450) instead. `WriteBuffer` uses `Write` internally to do the actual writing.

Errors: If the stream does not allow to write `Count` bytes, then an exception is raised.

See also: `TStream.Write` (450), `TStream.ReadBuffer` (451)

4.71.9 TStream.CopyFrom

Synopsis: Copy data from one stream to another

Declaration: `function CopyFrom(Source: TStream; Count: Int64) : Int64`

Visibility: public

Description: `CopyFrom` reads `Count` bytes from `Source` and writes them to the current stream. This updates the current position in the stream. After the action is completed, the number of bytes copied is returned. If `Count` is zero, then the whole contents of the `Source` stream is copied. It is positioned on the first byte of data, and `Size` bytes are copied. Note that this cannot be used with streams that do not allow seeking or do not allow determining the size of the stream.

This can be used to quickly copy data from one stream to another or to copy the whole contents of the stream.

See also: `TStream.Read` (449), `TStream.Write` (450)

4.71.10 TStream.ReadComponent

Synopsis: Reads component data from a stream

Declaration: `function ReadComponent(Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponent` reads a component state from the stream and transfers this state to `Instance`. If `Instance` is `nil`, then it is created first based on the type stored in the stream. `ReadComponent` returns the component as it is read from the stream.

`ReadComponent` simply creates a `TReader` (433) object and calls its `ReadRootComponent` (441) method.

Errors: If an error occurs during the reading of the component, an `EFileError` (303) exception is raised.

See also: `TStream.WriteComponent` (453), `TStream.ReadComponentRes` (452), `TReader.ReadRootComponent` (441)

4.71.11 TStream.ReadComponentRes

Synopsis: Reads component data and resource header from a stream

Declaration: `function ReadComponentRes(Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponentRes` reads a resource header from the stream, and then calls `ReadComponent` (452) to read the component state from the stream into `Instance`.

This method is usually called by the global streaming method when instantiating forms and datamodules as created by an IDE. It should be used mainly on Windows, to store components in Windows resources.

Errors: If an error occurs during the reading of the component, an `EFileError` (303) exception is raised.

See also: `TStream.ReadComponent` (452), `TStream.WriteComponentRes` (453)

4.71.12 TStream.WriteComponent

Synopsis: Write component data to the stream

Declaration: `procedure WriteComponent (Instance: TComponent)`

Visibility: public

Description: `WriteComponent` writes the published properties of `Instance` to the stream, so they can later be read with `TStream.ReadComponent` (452). This method is intended to be used by an IDE, to preserve the state of a form or datamodule as designed in the IDE.

`WriteComponent` simply calls `WriteDescendant` (448) with `Nil` ancestor.

See also: `TStream.ReadComponent` (452), `TStream.WriteComponentRes` (453)

4.71.13 TStream.WriteComponentRes

Synopsis: Write resource header and component data to a stream

Declaration: `procedure WriteComponentRes (const ResName: string; Instance: TComponent)`

Visibility: public

Description: `WriteComponentRes` writes a `ResName` resource header to the stream and then calls `WriteComponent` (453) to write the published properties of `Instance` to the stream.

This method is intended for use by an IDE that can use it to store forms or datamodules as designed in a Windows resource stream.

See also: `TStream.WriteComponent` (453), `TStream.ReadComponentRes` (452)

4.71.14 TStream.WriteDescendent

Synopsis: Write descendent of a component

Declaration: `procedure WriteDescendent (Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendent` will create a `TWriter` (515) writer class and write `Instance` as a descendent of `Ancestor` using the writer. This is used to create diff streams: only the properties where `Instance` differs from `Ancestor` are written to the stream.

See also: `TWriter.WriteDescendent` (519)

4.71.15 TStream.WriteDescendentRes

Synopsis: Write descendent of a component as resource

Declaration: `procedure WriteDescendentRes (const ResName: string;
Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendentRes` calls `WriteDescendent` as a resource stream.

See also: `TWriter.WriteDescendent` (519)

4.71.16 TStream.WriteResourceHeader

Synopsis: Write resource header to the stream

Declaration: `procedure WriteResourceHeader(const ResName: string;
var FixupInfo: LongInt)`

Visibility: public

Description: `WriteResourceHeader` writes a resource-file header for a resource called `ResName`. It returns in `FixupInfo` the argument that should be passed on to `TStream.FixupResourceHeader` (454).

`WriteResourceHeader` should not be used directly. It is called by the `TStream.WriteComponentRes` (453) and `TStream.WriteDescendantRes` (448) methods.

See also: `TStream.FixupResourceHeader` (454), `TStream.WriteComponentRes` (453), `TStream.WriteDescendantRes` (448)

4.71.17 TStream.FixupResourceHeader

Synopsis: Not implemented in FPC

Declaration: `procedure FixupResourceHeader(FixupInfo: LongInt)`

Visibility: public

Description: `FixupResourceHeader` is used to write the size of the resource after a component was written to stream. The size is determined from the current position, and it is written at position `FixupInfo`. After that the current position is restored.

`FixupResourceHeader` should never be called directly; it is handled by the streaming system.

See also: `TStream.WriteResourceHeader` (454), `TStream.WriteComponentRes` (453), `TStream.WriteDescendantRes` (448)

4.71.18 TStream.ReadResHeader

Synopsis: Read a resource header from the stream.

Declaration: `procedure ReadResHeader`

Visibility: public

Description: `ReadResourceHeader` reads a resource file header from the stream. It positions the stream just beyond the header.

`ReadResourceHeader` should not be called directly, it is called by the streaming system when needed.

Errors: If the resource header is invalid an `EInvalidImage` (303) exception is raised.

See also: `TStream.ReadComponentRes` (452), `EInvalidImage` (303)

4.71.19 TStream.ReadByte

Synopsis: Read a byte from the stream and return its value.

Declaration: `function ReadByte : Byte`

Visibility: public

Description: `ReadByte` reads one byte from the stream and returns its value.

Errors: If the byte cannot be read, a `EStreamError` (305) exception will be raised. This is a utility function which simply calls the `Read` (449) function.

See also: `TStream.Read` (449), `TStream.WriteByte` (456), `TStream.ReadWord` (455), `TStream.ReadDWord` (455), `TStream.ReadAnsiString` (456)

4.71.20 `TStream.ReadWord`

Synopsis: Read a word from the stream and return its value.

Declaration: `function ReadWord : Word`

Visibility: `public`

Description: `ReadWord` reads one `Word` (i.e. 2 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (449) function.

Errors: If the word cannot be read, a `EStreamError` (305) exception will be raised.

See also: `TStream.Read` (449), `TStream.WriteWord` (456), `TStream.ReadByte` (454), `TStream.ReadDWord` (455), `TStream.ReadAnsiString` (456)

4.71.21 `TStream.ReadDWord`

Synopsis: Read a `DWord` from the stream and return its value.

Declaration: `function ReadDWord : Cardinal`

Visibility: `public`

Description: `ReadDWord` reads one `DWord` (i.e. 4 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (449) function.

Errors: If the `DWord` cannot be read, a `EStreamError` (305) exception will be raised.

See also: `TStream.Read` (449), `TStream.WriteDWord` (456), `TStream.ReadByte` (454), `TStream.ReadWord` (455), `TStream.ReadAnsiString` (456)

4.71.22 `TStream.ReadQWord`

Synopsis: Read a `QWord` value from the stream and return its value

Declaration: `function ReadQWord : QWord`

Visibility: `public`

Description: `ReadQWord` reads a `QWord` value (8 bytes) from the stream and returns its value.

Errors: If not enough bytes are available on the stream, an `EStreamError` (305) exception will be raised.

See also: `TStream.Read` (449), `TStream.WriteByte` (456), `TStream.ReadWord` (455), `TStream.ReadDWord` (455), `TStream.ReadAnsiString` (456)

4.71.23 TStream.ReadAnsiString

Synopsis: Read an ansistring from the stream and return its value.

Declaration: `function ReadAnsiString : string`

Visibility: `public`

Description: `ReadAnsiString` reads an ansistring from the stream and returns its value. This is a utility function which simply calls the read function several times. The Ansistring should be stored as 4 bytes (a DWord) representing the length of the string, and then the string value itself. The `WriteAnsiString` (457) function writes an ansistring in such a format.

Errors: If the `AnsiString` cannot be read, an `EStreamError` (305) exception will be raised.

See also: `TStream.Read` (449), `TStream.WriteAnsiString` (457), `TStream.ReadByte` (454), `TStream.ReadWord` (455), `TStream.ReadDWord` (455)

4.71.24 TStream.WriteByte

Synopsis: Write a byte to the stream.

Declaration: `procedure WriteByte(b: Byte)`

Visibility: `public`

Description: `WriteByte` writes the byte `B` to the stream. This is a utility function which simply calls the `Write` (450) function. The byte can be read from the stream using the `ReadByte` (454) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (305) exception will be raised.

See also: `TStream.Write` (450), `TStream.ReadByte` (454), `TStream.WriteWord` (456), `TStream.WriteDWord` (456), `TStream.WriteAnsiString` (457)

4.71.25 TStream.WriteWord

Synopsis: Write a word to the stream.

Declaration: `procedure WriteWord(w: Word)`

Visibility: `public`

Description: `WriteWord` writes the word `W` (i.e. 2 bytes) to the stream. This is a utility function which simply calls the `Write` (450) function. The word can be read from the stream using the `ReadWord` (455) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (305) exception will be raised.

See also: `TStream.Write` (450), `TStream.ReadWord` (455), `TStream.WriteByte` (456), `TStream.WriteDWord` (456), `TStream.WriteAnsiString` (457)

4.71.26 TStream.WriteDWord

Synopsis: Write a DWord to the stream.

Declaration: `procedure WriteDWord(d: Cardinal)`

Visibility: `public`

Description: `WriteDWord` writes the `DWord D` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (450) function. The `DWord` can be read from the stream using the `ReadDWord` (455) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (305) exception will be raised.

See also: `TStream.Write` (450), `TStream.ReadDWord` (455), `TStream.WriteByte` (456), `TStream.WriteWord` (456), `TStream.WriteString` (457)

4.71.27 TStream.WriteQWord

Synopsis: Write a `QWord` value to the stream

Declaration: `procedure WriteQWord(q: QWord)`

Visibility: `public`

Description: `WriteQWord` writes the word `W` (i.e. 8 bytes) to the stream. This is a utility function which simply calls the `Write` (450) function. The word can be read from the stream using the `ReadQWord` (455) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (305) exception will be raised.

See also: `TStream.Write` (450), `TStream.ReadByte` (454), `TStream.WriteWord` (456), `TStream.WriteDWord` (456), `TStream.WriteString` (457)

4.71.28 TStream.WriteString

Synopsis: Write an ansistring to the stream.

Declaration: `procedure WriteAnsiString(const S: string); Virtual`

Visibility: `public`

Description: `WriteAnsiString` writes the `AnsiString S` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (450) function. The ansistring is written as a 4 byte length specifier, followed by the ansistring's content. The ansistring can be read from the stream using the `ReadAnsiString` (456) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (305) exception will be raised.

See also: `TStream.Write` (450), `TStream.ReadAnsiString` (456), `TStream.WriteByte` (456), `TStream.WriteWord` (456), `TStream.WriteDWord` (456)

4.71.29 TStream.Position

Synopsis: The current position in the stream.

Declaration: `Property Position : Int64`

Visibility: `public`

Access: `Read,Write`

Description: `Position` can be read to determine the current position in the stream. It can be written to set the (absolute) position in the stream. The position is zero-based, so to set the position at the beginning of the stream, the position must be set to zero.

Remark Not all `TStream` descendants support setting the position in the stream, so this should be used with care.

Errors: Some descendants may raise an `EStreamError` (305) exception if they do not support setting the stream position.

See also: `TStream.Size` (458), `TStream.Seek` (450)

4.71.30 TStream.Size

Synopsis: The current size of the stream.

Declaration: `Property Size : Int64`

Visibility: `public`

Access: `Read,Write`

Description: `Size` can be read to determine the stream size or to set the stream size.

Remark Not all descendants of `TStream` support getting or setting the stream size; they may raise an exception if the `Size` property is read or set.

See also: `TStream.Position` (457), `TStream.Seek` (450)

4.72 TStreamAdapter

4.72.1 Description

Implements `IStream` for `TStream` (448) descendants

4.72.2 Interfaces overview

Page	Interfaces	Description
1965	<code>IStream</code>	COM stream abstraction

4.72.3 Method overview

Page	Method	Description
462	<code>Clone</code>	Clone the stream
461	<code>Commit</code>	Commit data to the stream
460	<code>CopyTo</code>	Copy data to destination stream
459	<code>Create</code>	Create a new instance of <code>TStreamAdapter</code>
459	<code>Destroy</code>	Free the <code>TStreamAdapter</code> instance
461	<code>LockRegion</code>	Lock a region of the stream
459	<code>Read</code>	Read from the stream.
461	<code>Revert</code>	Revert operations on the stream
460	<code>Seek</code>	Set the stream position
460	<code>SetSize</code>	Set the stream size
462	<code>Stat</code>	Return statistical data about the stream
461	<code>UnlockRegion</code>	Unlock a region of the stream
459	<code>Write</code>	Write to the stream

4.72.4 Property overview

Page	Properties	Access	Description
462	Stream	r	Stream on which adaptor works
462	StreamOwnership	rw	Determines what happens with the stream when the adaptor is freed

4.72.5 TStreamAdapter.Create

Synopsis: Create a new instance of `TStreamAdapter`

Declaration: constructor `Create(Stream: TStream; Ownership: TStreamOwnership)`

Visibility: public

Description: `Create` creates a new instance of `TStreamAdapter`. It initializes `TStreamAdapter.Stream` ([462](#)) with `Stream` and initializes `StreamOwnership` ([462](#)) with `Ownership`.

`TStreamAdapter` is an abstract class: descendants must be created that implement the actual functionality.

See also: `StreamOwnership` ([462](#)), `TStreamAdapter.Stream` ([462](#))

4.72.6 TStreamAdapter.Destroy

Synopsis: Free the `TStreamAdapter` instance

Declaration: destructor `Destroy`; Override

Visibility: public

Description: Explicitly free the `TStreamAdapter` instance. Normally, this is done automatically if a reference to the `IStream` interface is freed.

4.72.7 TStreamAdapter.Read

Synopsis: Read from the stream.

Declaration: function `Read(pv: Pointer; cb: DWORD; pcbRead: PDWord) : HRESULT`
; Virtual

Visibility: public

Description: `Read` implements `#rtl.types.ISequentialStream.Read` ([1965](#)) by reading from the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.ISequentialStream.Read` ([1965](#))

4.72.8 TStreamAdapter.Write

Synopsis: Write to the stream

Declaration: function `Write(pv: Pointer; cb: DWORD; pcbWritten: PDWord) : HRESULT`
; Virtual

Visibility: public

Description: `Write` implements `#rtl.types.ISequentialStream.Write` (1965) by writing to the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.ISequentialStream.Write` (1965)

4.72.9 TStreamAdapter.Seek

Synopsis: Set the stream position

Declaration: `function Seek(dlibMove: Largeint; dwOrigin: DWORD;
out libNewPosition: LargeUint) : HRESULT; Virtual`

Visibility: `public`

Description: `Seek` implements `#rtl.types.IStream.Seek` (1966) by setting the position of the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Seek` (1966)

4.72.10 TStreamAdapter.SetSize

Synopsis: Set the stream size

Declaration: `function SetSize(libNewSize: LargeUint) : HRESULT; Virtual`

Visibility: `public`

Description: `SetSize` implements `#rtl.types.IStream.SetSize` (1966) by setting the size of the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.SetSize` (1966)

4.72.11 TStreamAdapter.CopyTo

Synopsis: Copy data to destination stream

Declaration: `function CopyTo(stm: IStream; cb: LargeUint; out cbRead: LargeUint;
out cbWritten: LargeUint) : HRESULT; Virtual`

Visibility: `public`

Description: `CopyTo` implements `#rtl.types.IStream.CopyTo` (1966).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

4.72.12 TStreamAdapter.Commit

Synopsis: Commit data to the stream

Declaration: `function Commit(grfCommitFlags: DWORD) : HRESULT; Virtual`

Visibility: public

Description: `Commit` implements `#rtl.types.IStream.Commit` (1967).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Commit` (1967)

4.72.13 TStreamAdapter.Revert

Synopsis: Revert operations on the stream

Declaration: `function Revert : HRESULT; Virtual`

Visibility: public

Description: `Revert` implements `#rtl.types.IStream.Revert` (1967).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Revert` (1967)

4.72.14 TStreamAdapter.LockRegion

Synopsis: Lock a region of the stream

Declaration: `function LockRegion(libOffset: LargeUint; cb: LargeUint;
dwLockType: DWORD) : HRESULT; Virtual`

Visibility: public

Description: `LockRegion` implements `#rtl.types.IStream.LockRegion` (1967).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.LockRegion` (1967)

4.72.15 TStreamAdapter.UnlockRegion

Synopsis: Unlock a region of the stream

Declaration: `function UnlockRegion(libOffset: LargeUint; cb: LargeUint;
dwLockType: DWORD) : HRESULT; Virtual`

Visibility: public

Description: `UnLockRegion` implements `#rtl.types.IStream.UnLockRegion` (1967).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.UnLockRegion` (1967)

4.72.16 TStreamAdapter.Stat

Synopsis: Return statistical data about the stream

Declaration: `function Stat(out statstg: TStatStg; grfStatFlag: DWORD) : HRESULT; Virtual`

Visibility: public

Description: `Stat` implements `#rtl.types.IStream.Stat` (1968).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Stat` (1968)

4.72.17 TStreamAdapter.Clone

Synopsis: Clone the stream

Declaration: `function Clone(out stm: IStream) : HRESULT; Virtual`

Visibility: public

Description: `Clone` implements `#rtl.types.IStream.Clone` (1968).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Clone` (1968)

4.72.18 TStreamAdapter.Stream

Synopsis: Stream on which adaptor works

Declaration: `Property Stream : TStream`

Visibility: public

Access: Read

Description: This is the stream on which the adaptor works. It was specified at creation.

4.72.19 TStreamAdapter.StreamOwnership

Synopsis: Determines what happens with the stream when the adaptor is freed

Declaration: `Property StreamOwnership : TStreamOwnership`

Visibility: public

Access: Read,Write

Description: `StreamOwnership` determines what happens when the adaptor

4.73 TStringList

4.73.1 Description

`TStringList` is a descendant class of `TStrings` (468) that implements all of the abstract methods introduced there. It also introduces some additional methods:

- Sort the list, or keep the list sorted at all times
- Special handling of duplicates in sorted lists
- Notification of changes in the list

See also: `TStrings` (468), `TStringList.Duplicates` (466), `TStringList.Sorted` (466)

4.73.2 Method overview

Page	Method	Description
464	Add	Implements the <code>TStrings.Add</code> (472) function.
464	Clear	Implements the <code>TStrings.Clear</code> (475) function.
466	CustomSort	Sort the stringlist using a custom sort algorithm
464	Delete	Implements the <code>TStrings.Delete</code> (475) function.
463	Destroy	Destroys the stringlist.
464	Exchange	Implements the <code>TStrings.Exchange</code> (476) function.
465	Find	Locates the index for a given string in sorted lists.
465	IndexOf	Overrides the <code>TStrings.IndexOf</code> (478) property.
465	Insert	Overrides the <code>TStrings.Insert</code> (479) method.
465	Sort	Sorts the strings in the list.

4.73.3 Property overview

Page	Properties	Access	Description
467	CaseSensitive	rw	Indicates whether comparing strings happens in a case sensitive manner.
466	Duplicates	rw	Describes the behaviour of a sorted list with respect to duplicate strings.
467	OnChange	rw	Event triggered after the list was modified.
467	OnChanging	rw	Event triggered when the list is about to be modified.
468	OwnsObjects	rw	Determines whether the stringlist owns it's objects or not.
466	Sorted	rw	Determines whether the list is sorted or not.
468	SortStyle	rw	Sort style for strings

4.73.4 TStringList.Destroy

Synopsis: Destroys the stringlist.

Declaration: `destructor Destroy;` `Override`

Visibility: `public`

Description: `Destroy` clears the stringlist, release all memory allocated for the storage of the strings, and then calls the inherited `destroy` method.

Remark Any objects associated to strings in the list will *not* be destroyed; it is the responsibility of the caller to destroy all objects associated with strings in the list.

4.73.5 TStringList.Add

Synopsis: Implements the TStrings.Add (472) function.

Declaration: `function Add(const S: string) : Integer; Override`

Visibility: public

Description: Add will add S to the list. If the list is sorted and the string S is already present in the list and TStringList.Duplicates (466) is dupError then an EStringListError (306) exception is raised. If Duplicates is set to dupIgnore then the return value is the index of the previous entry.

If the list is sorted, new strings will not necessarily be added to the end of the list, rather they will be inserted at their alphabetical position.

Errors: If the list is sorted and the string S is already present in the list and TStringList.Duplicates (466) is dupError then an EStringListError (306) exception is raised.

See also: TStringList.Insert (465), TStringList.Duplicates (466)

4.73.6 TStringList.Clear

Synopsis: Implements the TStrings.Clear (475) function.

Declaration: `procedure Clear; Override`

Visibility: public

Description: Implements the TStrings.Clear (475) function.

4.73.7 TStringList.Delete

Synopsis: Implements the TStrings.Delete (475) function.

Declaration: `procedure Delete(Index: Integer); Override`

Visibility: public

Description: Implements the TStrings.Delete (475) function.

4.73.8 TStringList.Exchange

Synopsis: Implements the TStrings.Exchange (476) function.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer); Override`

Visibility: public

Description: Exchange will exchange two items in the list as described in TStrings.Exchange (476).

Remark Exchange will not check whether the list is sorted or not; if Exchange is called on a sorted list and the strings are not identical, the sort order of the list will be destroyed.

See also: TStringList.Sorted (466), TStrings.Exchange (476)

4.73.9 TStringList.Find

Synopsis: Locates the index for a given string in sorted lists.

Declaration: `function Find(const S: string; out Index: Integer) : Boolean; Virtual`

Visibility: public

Description: `Find` returns `True` if the string `S` is present in the list. Upon exit, the `Index` parameter will contain the position of the string in the list. If the string is not found, the function will return `False` and `Index` will contain the position where the string will be inserted if it is added to the list.

Remark

1. Use this method only on sorted lists. For unsorted lists, use `TStringList.IndexOf` (465) instead.
2. `Find` uses a binary search method to locate the string

4.73.10 TStringList.IndexOf

Synopsis: Overrides the `TStrings.IndexOf` (478) property.

Declaration: `function IndexOf(const S: string) : Integer; Override`

Visibility: public

Description: `IndexOf` overrides the ancestor method `TStrings.indexOf` (478). It tries to optimize the search by executing a binary search if the list is sorted. The function returns the position of `S` if it is found in the list, or -1 if the string is not found in the list.

See also: `TStrings.IndexOf` (478), `TStringList.Find` (465)

4.73.11 TStringList.Insert

Synopsis: Overrides the `TStrings.Insert` (479) method.

Declaration: `procedure Insert(Index: Integer; const S: string); Override`

Visibility: public

Description: `Insert` will insert the string `S` at position `Index` in the list. If the list is sorted, an `EStringListError` (306) exception will be raised instead. `Index` is a zero-based position.

Errors: If `Index` contains an invalid value (less than zero or larger than `Count`, or the list is sorted, an `EStringListError` (306) exception will be raised.

See also: `TStringList.Add` (464), `TStrings.Insert` (479), `TStrings.InsertObject` (480)

4.73.12 TStringList.Sort

Synopsis: Sorts the strings in the list.

Declaration: `procedure Sort; Virtual`

Visibility: public

Description: `Sort` will sort the strings in the list using the quicksort algorithm. If the list has its `TStringList.Sorted` (466) property set to `True` then nothing will be done.

See also: `TStringList.Sorted` (466)

4.73.13 TStringList.CustomSort

Synopsis: Sort the stringlist using a custom sort algorithm

Declaration: `procedure CustomSort (CompareFn: TStringListSortCompare); Virtual`

Visibility: `public`

Description: `CustomSort` sorts the stringlist with a custom comparison function. The function should compare 2 elements in the list, and return a negative number if the first item is before the second. It should return 0 if the elements are equal, and a positive result indicates that the second elements should be before the first.

See also: `TStringList.Sorted` (466), `TStringList.Sort` (465)

4.73.14 TStringList.Duplicates

Synopsis: Describes the behaviour of a sorted list with respect to duplicate strings.

Declaration: `Property Duplicates : TDuplicates`

Visibility: `public`

Access: `Read,Write`

Description: `Duplicates` describes what to do in case a duplicate value is added to the list:

Table 4.32:

<code>dupIgnore</code>	Duplicate values will not be added to the list, but no error will be triggered.
<code>dupError</code>	If an attempt is made to add a duplicate value to the list, an <code>EStringListError</code> (306) exception is raised.
<code>dupAccept</code>	Duplicate values can be added to the list.

If the stringlist is not sorted, the `Duplicates` setting is ignored.

4.73.15 TStringList.Sorted

Synopsis: Determines whether the list is sorted or not.

Declaration: `Property Sorted : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Sorted` can be set to `True` in order to cause the list of strings to be sorted. Further additions to the list will be inserted at the correct position so the list remains sorted at all times. Setting the property to `False` has no immediate effect, but will allow strings to be inserted at any position.

Remark

1. When `Sorted` is `True`, `TStringList.Insert` (465) cannot be used. For sorted lists, `TStringList.Add` (464) should be used instead.
2. If `Sorted` is `True`, the `TStringList.Duplicates` (466) setting has effect. This setting is ignored when `Sorted` is `False`.

See also: `TStringList.Sort` (465), `TStringList.Duplicates` (466), `TStringList.Add` (464), `TstringList.Insert` (465)

4.73.16 TStringList.CaseSensitive

Synopsis: Indicates whether comparing strings happens in a case sensitive manner.

Declaration: `Property CaseSensitive : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `CaseSensitive` indicates how string values are compared: When `True` this happens case sensitively, and when `False`, the comparison is done in a case insensitive manner.

This property influences `IndexOf` (478), `Find` (465), `IndexOfName` (479) and `Sort` (465).

See also: `IndexOf` (478), `Find` (465), `IndexOfName` (479), `Sort` (465)

4.73.17 TStringList.OnChange

Synopsis: Event triggered after the list was modified.

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChange` can be assigned to respond to changes that have occurred in the list. The handler is called whenever strings are added, moved, modified or deleted from the list.

The `OnChange` event is triggered after the modification took place. When the modification is about to happen, an `TStringList.OnChanging` (467) event occurs.

See also: `TStringList.OnChanging` (467)

4.73.18 TStringList.OnChanging

Synopsis: Event triggered when the list is about to be modified.

Declaration: `Property OnChanging : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChanging` can be assigned to respond to changes that will occurred in the list. The handler is called whenever strings will be added, moved, modified or deleted from the list.

The `Onchanging` event is triggered before the modification will take place. When the modification has happened, an `TStringList.OnChange` (467) event occurs.

See also: `TStringList.OnChange` (467)

4.73.19 TStringList.OwnsObjects

Synopsis: Determines whether the stringlist owns it's objects or not.

Declaration: `Property OwnsObjects : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `OwnsObjects` can be set to `true` to let the stringlist instance own the objects in the list: if an element is removed from the list, the associated object (if there is any) will be freed as well. The same is true if the list is cleared or destroyed.

See also: `TStrings.Objects` ([488](#))

4.73.20 TStringList.SortStyle

Synopsis: Sort style for strings

Declaration: `Property SortStyle : TStringsSortStyle`

Visibility: `public`

Access: `Read,Write`

Description: `SortStyle` sets the sort style for the `TStringList` instance. Setting it to `sslAuto` will keep the list sorted automatically at all times.

`Find` ([465](#)) (and hence `IndexOf` ([478](#))) will use a binary search if `SortStyle` differs from `sslNone`. if `SortStyle` is `sslNone`, then it will raise an exception.

See also: `TStringsSortStyle` ([282](#)), `TStrings.Sorted` ([468](#))

4.74 TStrings

4.74.1 Description

`TStrings` implements an abstract class to manage an array of strings. It introduces methods to set and retrieve strings in the array, searching for a particular string, concatenating the strings and so on. It also allows an arbitrary object to be associated with each string.

It also introduces methods to manage a series of `name=value` settings, as found in many configuration files.

An instance of `TStrings` is never created directly, instead a descendant class such as `TStringList` ([463](#)) should be created. This is because `TStrings` is an abstract class which does not implement all methods; `TStrings` also doesn't store any strings, this is the functionality introduced in descendants such as `TStringList` ([463](#)).

`TStrings` implements the `IFPObserved` ([307](#)) interface: when the stringlist is changed, a `ooChanged` notification is sent to all observers.

See also: `TStringList` ([463](#)), `IFPObserved` ([307](#))

4.74.2 Method overview

Page	Method	Description
472	Add	Add a string to the list
473	AddCommaText	Adds a comma-separated list of strings
474	AddDelimitedtext	Adds a separator-delimited list of strings
472	AddObject	Add a string and associated object to the list.
472	AddPair	Add a name-value pair
473	AddStrings	Add contents of another stringlist to this list.
473	AddText	Add text to the string list.
474	Append	Add a string to the list.
474	Assign	Assign the contents of another stringlist to this one.
475	BeginUpdate	Mark the beginning of an update batch.
475	Clear	Removes all strings and associated objects from the list.
470	Create	Initializ a new TStrings instance
475	Delete	Delete a string from the list.
471	Destroy	Frees all strings and objects, and removes the list from memory.
476	EndUpdate	Mark the end of an update batch.
476	Equals	Compares the contents of two stringlists.
476	Exchange	Exchanges two strings in the list.
477	ExtractName	Extract the name part of a string
477	Fill	Set a range of strings in the list to the specified value.
477	Filter	Return a filtered list.
477	ForEach	Call a callback for each string in the list.
478	GetEnumerator	Create an IEnumerator instance
478	GetNameValue	Return both name and value of a name,value pair based on it's index.
478	GetText	Returns the contents as a PChar
478	IndexOf	Find a string in the list and return its position.
479	IndexOfName	Finds the index of a name in the name-value pairs.
479	IndexOfObject	Finds an object in the list and returns its index.
479	Insert	Insert a string in the list.
480	InsertObject	Insert a string and associated object in the list.
480	LastIndexOf	Return the index of the last occurrence of a string
480	LoadFromFile	Load the contents of a file as a series of strings.
481	LoadFromStream	Load the contents of a stream as a series of strings.
481	Map	Call a map routine for each string in the list
481	Move	Move a string from one place in the list to another.
482	Pop	Remove the last string of the list and return it.
482	Reduce	Get a reduced value from the string list
482	Reverse	Reverse the order of the strings in the list.
483	SaveToFile	Save the contents of the list to a file.
483	SaveToStream	Save the contents of the string to a stream.
473	SetStrings	Replace the strings with the passed strings
484	SetText	Set the contents of the list from a PChar.
483	Shift	Return and remove the first string in the list
484	Slice	Return a subrange of strings starting at a given index.
471	ToObjectArray	Return the objects as an array of object.
471	ToStringArray	Return the strings as an array of string.

4.74.3 Property overview

Page	Properties	Access	Description
484	AlwaysQuote	rw	Always quote strings in DelimitedText
484	Capacity	rw	Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.
485	CommaText	rw	Contents of the list as a comma-separated string.
485	Count	r	Number of strings in the list.
486	DefaultEncoding	rw	Default encoding of stringlist
486	DelimitedText	rw	Get or set all strings in the list in a delimited form.
487	Delimiter	rw	Delimiter character used in DelimitedText (486).
487	Encoding	r	Current encoding of stringlist
487	LineBreak	rw	LineBreak character to use
487	MissingNameValueSeparatorAction	rw	What to do if NameValueSeparator is missing in a string.
488	Names	r	Name parts of the name-value pairs in the list.
488	NameValueSeparator	rw	Value of the character used to separate name,value pairs
488	Objects	rw	Indexed access to the objects associated with the strings in the list.
489	Options	rw	A set of TStringsOption (281) - various boolean properties.
489	QuoteChar	rw	Quote character used in DelimitedText (486).
489	SkipLastLineBreak	rw	Do not add a linebreak to the last item
490	StrictDelimiter	rw	Should only the delimiter character be considered a delimiter
490	Strings	rw	Indexed access to the strings in the list.
490	StringsAdapter	rw	Not implemented in Free Pascal.
491	Text	rw	Contents of the list as one big string.
491	TextLineBreakStyle	rw	Determines which line breaks to use in the Text (491) property
489	TrailingLineBreak	rw	Add a linebreak to the last item
491	UseLocale	rw	Determines what methods are used in strings comparison.
492	ValueFromIndex	rw	Return the value part of a string based on it's index.
492	Values	rw	Value parts of the name-value pairs in the list.
492	WriteBOM	rw	Write BOM when writing stringlist to stream

4.74.4 TStrings.Create

Synopsis: Initializ a new TStrings instance

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes the codepage variables of a new `TStrings` instance. Note that `TStrings` is an abstract class, you must always instantiate a descendent such as `TStringList` (463)

Errors: Only an `EOutOfMemory` exception can occur.

See also: `TStringList` (463)

4.74.5 TStrings.Destroy

Synopsis: Frees all strings and objects, and removes the list from memory.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` is the destructor of `TStrings` it does nothing except calling the inherited destructor.

4.74.6 TStrings.ToArray

Synopsis: Return the objects as an array of object.

Declaration: `function ToArray(aStart: Integer; aEnd: Integer) : TObjectDynArray; Overload`
`function ToArray : TObjectDynArray; Overload`

Visibility: `public`

Description: `ToArray` returns all the values in the `Objects` (488) array as a dynamic array of `TObject` instances. If `aStart` and `aEnd` are specified, only the objects with indexes in the specified array (`aStart` and `aEnd` included) are returned. `Nil` values will also be returned.

Errors: If `aStart` is larger than `aEnd`, no elements are returned.

See also: `TStrings.ToArray` (471), `TStrings.Strings` (490), `TStrings.Objects` (488)

4.74.7 TStrings.ToStringArray

Synopsis: Return the strings as an array of string.

Declaration: `function ToStringArray(aStart: Integer; aEnd: Integer) : TStringDynArray; Overload`
`function ToStringArray : TStringDynArray; Overload`

Visibility: `public`

Description: `ToStringArray` returns all the values in the `Objects` (488) array as a dynamic array of `TObject` instances. If `aStart` and `aEnd` are specified, only the objects with indexes in the specified array (`aStart` and `aEnd` included) are returned. `Nil` values will also be returned.

Errors: If `aStart` is larger than `aEnd`, no elements are returned.

See also: `TStrings.ToArray` (471), `TStrings.Strings` (490), `TStrings.Objects` (488)

4.74.8 TStrings.Add

Synopsis: Add a string to the list

Declaration: `function Add(const S: string) : Integer; Virtual; Overload`
`function Add(const Fmt: string; const Args: Array of const) : Integer`
`; Overload`

Visibility: public

Description: Add adds S at the end of the list and returns the index of S in the list (which should equal TStrings.Count (485))

See also: TStrings.Objects (488), TStrings.AddObject (472), TStrings.Insert (479), TStrings.Delete (475), TStrings.Strings (490), TStrings.Count (485)

4.74.9 TStrings.AddObject

Synopsis: Add a string and associated object to the list.

Declaration: `function AddObject(const S: string; AObject: TObject) : Integer`
`; Virtual; Overload`
`function AddObject(const Fmt: string; Args: Array of const;`
`AObject: TObject) : Integer; Overload`

Visibility: public

Description: AddObject adds S to the list of strings, and associates AObject with it. It returns the index of S.

Remark An object added to the list is not automatically destroyed by the list when the list is destroyed or the string it is associated with is deleted. It is the responsibility of the application to destroy any objects associated with strings.

See also: TStrings.Add (472), TStrings.Strings (490), TStrings.Objects (488), TStrings.InsertObject (480)

4.74.10 TStrings.AddPair

Synopsis: Add a name-value pair

Declaration: `function AddPair(const AName: string; const AValue: string) : TStrings`
`; Overload`
`function AddPair(const AName: string; const AValue: string;`
`AObject: TObject) : TStrings; Overload`

Visibility: public

Description: AddPair adds a Name=Value pair with the AName and AValue parameters, optionally with object AObject. It uses the correct NameValueSeparator (266) character to do so.

AddPair does not test whether aName already exists, so it is possible to add duplicate names.

Errors: None.

See also: TStrings.GetNameValue (478), TStrings.NameValueSeparator (488), TStrings.Add (472), TStrings.AddObject (472)

4.74.11 TStrings.AddStrings

Synopsis: Add contents of another stringlist to this list.

[illegible]

Visibility: public

Description: `AddStrings` adds the contents of `TheStrings` to the stringlist. Any associated objects are added as well.

See also: [TStrings.Add \(472\)](#), [TStrings.Assign \(474\)](#)

4.74.12 TStrings.SetStrings

Synopsis: Replace the strings with the passed strings

```
Declaration: procedure SetStrings(TheStrings: TStrings); Virtual; Overload
           procedure SetStrings(TheStrings: Array of string); Virtual; Overload
```

Visibility: public

Description: `SetStrings` sets the strings of the stringlist to the specified values in `TheStrings`. The values can be specified as another stringlist or as an array of strings. In difference with the `Assign` (474) method it does not copy all other properties.

Internally it clears the array and calls `TStrings.AddStrings` (473).

See also: TStrings.Assign (474), TStrings.AddStrings (473)

4.74.13 TStrings.AddText

Synopsis: Add text to the string list.

```
Declaration: procedure AddText(const S: string); Virtual
```

Visibility: public

Description: `AddText` adds `S` to the strings. It is identical in function to setting `Text` (266) but does not clear the list of strings first: `S` is split into lines, and each line is added to the list.

See also: [TString.Text \(266\)](#)

4.74.14 TStrings.AddCommaText

Synopsis: Adds a comma-separated list of strings

```
Declaration: procedure AddCommaText (const S: string)
```

Visibility: public

Description: `AddCommaText` parses `S` using the same mechanism as when setting `TStrings.CommaText` (485) but adds the values instead of removing existing values.

`AddCommaText` also observes the `TStrings.StrictDelimiter` (490) and `TStrings.QuoteChar` (489) properties.

See also: `TStrings.AddDelimitedText` (474), `TStrings.CommaText` (485), `TStrings.QuoteChar` (489), `TStrings.StrictDelimiter` (490)

4.74.15 TStrings.AddDelimitedtext

Synopsis: Adds a separator-delimited list of strings

Declaration: `procedure AddDelimitedText(const S: string; ADelimiter: Char;
AStrictDelimiter: Boolean); Overload`
`procedure AddDelimitedtext(const S: string); Overload`

Visibility: public

Description: `AddDelimitedText` parses `S` using the same mechanism as when setting `TStrings.DelimitedText` (486) but adds the values instead of removing existing values. In difference with `TStrings.AddCommaText` (473) it uses the `TStrings.Delimiter` (487) character to separate the values.

`AddDelimitedText` also observes the `TStrings.Delimiter` (487), `TStrings.StrictDelimiter` (490) and `TStrings.QuoteChar` (489) properties.

See also: `TStrings.AddCommaText` (473), `TStrings.DelimitedText` (486), `TStrings.Delimiter` (487), `TStrings.StrictDelimiter` (490), `TStrings.QuoteChar` (489)

4.74.16 TStrings.Append

Synopsis: Add a string to the list.

Declaration: `procedure Append(const S: string)`

Visibility: public

Description: `Append` does the same as `TStrings.Add` (472), only it does not return the index of the inserted string.

See also: `TStrings.Add` (472)

4.74.17 TStrings.Assign

Synopsis: Assign the contents of another stringlist to this one.

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: public

Description: `Assign` replaces the contents of the stringlist with the contents of `Source` if `Source` is also of type `TStrings`. Any associated objects are copied as well.

See also: `TStrings.Add` (472), `TStrings.AddStrings` (473), `TPersistent.Assign` (429)

4.74.18 TStrings.BeginUpdate

Synopsis: Mark the beginning of an update batch.

Declaration: `procedure BeginUpdate`

Visibility: `public`

Description: `BeginUpdate` increases the update count by one. It is advisable to call `BeginUpdate` before lengthy operations on the stringlist. At the end of these operation, `TStrings.EndUpdate` (476) should be called to mark the end of the operation. Descendant classes may use this information to perform optimizations. e.g. updating the screen only once after many strings were added to the list.

All `TStrings` methods that modify the string list call `BeginUpdate` before the actual operation, and call `endUpdate` when the operation is finished. Descendant classes should also call these methods when modifying the string list.

Remark Always put the corresponding call to `TStrings.EndUpdate` (476) in the context of a `Finally` block, to ensure that the update count is always decreased at the end of the operation, even if an exception occurred:

```
With MyStrings do
  try
    BeginUpdate;
    // Some lengthy operation.
  Finally
    EndUpdate
  end;
```

See also: `TStrings.EndUpdate` (476)

4.74.19 TStrings.Clear

Synopsis: Removes all strings and associated objects from the list.

Declaration: `procedure Clear; Virtual; Abstract`

Visibility: `public`

Description: `Clear` will remove all strings and their associated objects from the list. After a call to `clear`, `TStrings.Count` (485) is zero.

Since it is an abstract method, `TStrings` itself does not implement `Clear`. Descendant classes such as `TStringList` (463) implement this method.

See also: `TStrings.Objects` (488), `TStrings.Strings` (490), `TStrings.Delete` (475), `TStrings.Count` (485)

4.74.20 TStrings.Delete

Synopsis: Delete a string from the list.

Declaration: `procedure Delete(Index: Integer); Virtual; Abstract`

Visibility: `public`

Description: `Delete` deletes the string at position `Index` from the list. The associated object is also removed from the list, but not destroyed. `Index` is zero-based, and should be in the range 0 to `Count-1`.

Since it is an abstract method, `TStrings` itself does not implement `Delete`. Descendant classes such as `TStringList` (463) implement this method.

Errors: If `Index` is not in the allowed range, an `EStringListError` (306) is raised.

See also: `TStrings.Insert` (479), `TStrings.Objects` (488), `TStrings.Strings` (490), `TStrings.Clear` (475)

4.74.21 TStrings.EndUpdate

Synopsis: Mark the end of an update batch.

Declaration: `procedure EndUpdate`

Visibility: `public`

Description: `EndUpdate` should be called at the end of a lengthy operation on the stringlist, but only if there was a call to `BeginUpdate` before the operation was started. It is best to put the call to `EndUpdate` in the context of a `Finally` block, so it will be called even if an exception occurs.

For more information, see `TStrings.BeginUpdate` (475).

`TStrings` implements the `IFPObserved` (307) interface: when `EndUpdate` is called, a `ooChanged` notification is sent to all observers.

See also: `TStrings.BeginUpdate` (475), `IFPObserved` (307)

4.74.22 TStrings.Equals

Synopsis: Compares the contents of two stringlists.

Declaration: `function Equals(Obj: TObject) : Boolean; Override; Overload`
`function Equals(TheStrings: TStrings) : Boolean; Overload`

Visibility: `public`

Description: `Equals` compares the contents of the stringlist with the contents of `TheStrings`. If the contents match, i.e. the stringlist contain an equal amount of strings, and all strings match, then `True` is returned. If the number of strings in the lists is unequal, or they contain one or more different strings, `False` is returned.

Remark

- 1.The strings are compared case-insensitively.
- 2.The associated objects are not compared

See also: `TStrings.Objects` (488), `TStrings.Strings` (490), `TStrings.Count` (485), `TStrings.Assign` (474)

4.74.23 TStrings.Exchange

Synopsis: Exchanges two strings in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer); Virtual`

Visibility: `public`

Description: `Exchange` exchanges the strings at positions `Index1` and `Index2`. The associated objects are also exchanged.

Both indexes must be in the range of valid indexes, i.e. must have a value between 0 and `Count-1`.

Errors: If either `Index1` or `Index2` is not in the range of valid indexes, an `EStringListError` (306) exception is raised.

See also: `TStrings.Move` (481), `TStrings.Strings` (490), `TStrings.Count` (485)

4.74.24 TStrings.ExtractName

Synopsis: Extract the name part of a string

Declaration: `function ExtractName(const S: string) : string`

Visibility: public

Description: `ExtractName` returns the name part (the part before the `NameValueSeparator` (488) character) of the string. If the character is not present, an empty string is returned. The resulting string is not trimmed, it can end or start with spaces.

See also: `NameValueSeparator` (488)

4.74.25 TStrings.Filter

Synopsis: Return a filtered list.

Declaration: `procedure Filter(aFilter: TStringsFilterMethod; aList: TStrings)`
`function Filter(aFilter: TStringsFilterMethod) : TStrings`

Visibility: public

Description: `Filter` applies `aFilter` to each string in the list, and if `aFilter` returns `True`, adds the string to the `aList` list. If the `aList` argument is not supplied, the result is a `TStringList` (463) instance that must be freed by the caller.

See also: `TStringsFilterMethod` (281), `TStringList` (463), `TStrings.Foreach` (477), `TStrings.Map` (481), `TStrings.Reduce` (482), `TStrings.Reverse` (482)

4.74.26 TStrings.Fill

Synopsis: Set a range of strings in the list to the specified value.

Declaration: `procedure Fill(const aValue: string; aStart: Integer; aEnd: Integer)`

Visibility: public

Description: `Fill` sets the strings with indexes in the range `aStart..aEnd` to `aValue`, if the `aStart..aEnd` are outside the valid range of indexes for the list, their values are adapted to fit the range. (0 to `Count` (485)-1)

See also: `Count` (485), `Strings` (490)

4.74.27 TStrings.Foreach

Synopsis: Call a callback for each string in the list.

Declaration: `procedure Foreach(aCallback: TStringsForeachMethod)`
`procedure Foreach(aCallback: TStringsForeachMethodEx)`
`procedure Foreach(aCallback: TStringsForeachMethodExObj)`

Visibility: public

Description: `Foreach` calls `aCallback` for every string in the list. It passes the string and optionally the string index and associated object to the callback.

See also: `TStrings.Filter` (477), `TStrings.Map` (481), `TStrings.Fill` (477), `TStringsForeachMethod` (281), `TStringsForeachMethodEx` (281), `TStringsForeachMethodExObj` (281), `TStrings.Reverse` (482)

4.74.28 TStrings.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TStringsEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1589) interface for `TStrings`. It creates a `TStringsEnumerator` (493) instance and returns it's `IEnumerator` (1589) interface.

See also: `TStringsEnumerator` (493), `IEnumerator` (1589), `IEnumerable` (1589)

4.74.29 TStrings.GetNameValue

Synopsis: Return both name and value of a name,value pair based on it's index.

Declaration: `procedure GetNameValue(Index: Integer; out AName: string;
out AValue: string)`

Visibility: public

Description: Return both name and value of a name,value pair based on it's index.

4.74.30 TStrings.GetText

Synopsis: Returns the contents as a `PChar`

Declaration: `function GetText : PChar; Virtual`

Visibility: public

Description: `GetText` allocates a memory buffer and copies the contents of the stringlist to this buffer as a series of strings, separated by an end-of-line marker. The buffer is zero terminated.

Remark The caller is responsible for freeing the returned memory buffer.

4.74.31 TStrings.IndexOf

Synopsis: Find a string in the list and return its position.

Declaration: `function IndexOf(const S: string) : Integer; Virtual
function IndexOf(const S: string; aStart: Integer) : Integer; Virtual`

Visibility: public

Description: `IndexOf` searches the list for `S` starting from index `aStart`. The start position `aStart` is 0 if not specified. If it is negative, it is considered an offset from `TStrings.Count` (485). The search is case-insensitive or case sensitive depending on the value of the `CaseSensitive` (??) . If a matching entry is found, its position is returned. if no matching string is found, -1 is returned.

Remark

1. Only the first occurrence of the string is returned.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOfObject` (479), `TStrings.IndexOfName` (479), `TStrings.Strings` (490), `TStrings.LastIndexOf` (480), `TStrings.Count` (485)

4.74.32 TStrings.IndexOfName

Synopsis: Finds the index of a name in the name-value pairs.

Declaration: `function IndexOfName(const Name: string) : Integer; Virtual`

Visibility: public

Description: `IndexOfName` searches in the list of strings for a name-value pair with name part `Name`. If such a pair is found, it returns the index of the pair in the stringlist. If no such pair is found, the function returns `-1`. The search is done case-insensitive.

Remark

1. Only the first occurrence of a matching name-value pair is returned.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOf` (478), `TStrings.IndexOfObject` (479), `TStrings.Strings` (490), `TStrings.LastIndexOf` (480)

4.74.33 TStrings.IndexOfObject

Synopsis: Finds an object in the list and returns its index.

Declaration: `function IndexOfObject(AObject: TObject) : Integer; Virtual`

Visibility: public

Description: `IndexOfObject` searches through the list of strings till it find a string associated with `AObject`, and returns the index of this string. If no such string is found, `-1` is returned.

Remark

1. Only the first occurrence of a string with associated object `AObject` is returned; if more strings in the list can be associated with `AObject`, they will not be found by this routine.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.LastIndexOf` (480), `TStrings.IndexOf` (478), `TStrings.Objects` (488)

4.74.34 TStrings.Insert

Synopsis: Insert a string in the list.

Declaration: `procedure Insert(Index: Integer; const S: string); Virtual; Abstract`

Visibility: public

Description: `Insert` inserts the string `S` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

Remark

1. All methods that add strings to the list use `Insert` to add a string to the list.
2. If the string has an associated object, use `TStrings.InsertObject` (480) instead.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (306) exception is raised.

See also: `TStrings.Add` (472), `TStrings.InsertObject` (480), `TStrings.Append` (474), `TStrings.Delete` (475)

4.74.35 TStrings.InsertObject

Synopsis: Insert a string and associated object in the list.

Declaration: `procedure InsertObject(Index: Integer; const S: string;
AObject: TObject)`

Visibility: public

Description: `InsertObject` inserts the string `S` and its associated object `AObject` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (306) exception is raised.

See also: `TStrings.Insert` (479), `TStrings.AddObject` (472), `TStrings.Append` (474), `TStrings.Delete` (475)

4.74.36 TStrings.LastIndexOf

Synopsis: Return the index of the last occurrence of a string

Declaration: `function LastIndexOf(const S: string; aStart: Integer) : Integer
; Virtual
function LastIndexOf(const S: string) : Integer`

Visibility: public

Description: `LastIndexOf` returns the index of the last occurrence of the string `S`. If `aStart` is specified, the search starts at the specified index in the list (it defaults to `Count-1`). If `aStart` is negative, it is used as an offset to `Count` (485), i.e. `aCount` equal to -1 will start the search at `Count-1`.

If `aStart` is larger than `Count-1` it will be capped to `Count-1`.

See also: `IndexOf` (478), `IndexOfObject` (479)

4.74.37 TStrings.LoadFromFile

Synopsis: Load the contents of a file as a series of strings.

Declaration: `procedure LoadFromFile(const FileName: string); Virtual; Overload
procedure LoadFromFile(const FileName: string; IgnoreEncoding: Boolean)
procedure LoadFromFile(const FileName: string; AEncoding: TEncoding)
; Virtual; Overload`

Visibility: public

Description: `LoadFromFile` loads the contents of a file into the stringlist. Each line in the file (as marked by the end-of-line marker of the particular OS the application runs on) becomes one string in the stringlist. This action replaces the contents of the stringlist, it does not append the strings to the current content.

`LoadFromFile` simply creates a file stream (388) with the given filename, and then executes `TStrings.LoadfromStream` (481); after that the file stream object is destroyed again.

See also: `TStrings.LoadFromStream` (481), `TStrings.SaveToFile` (483), `Tstrings.SaveToStream` (483)

4.74.38 TStrings.LoadFromStream

Synopsis: Load the contents of a stream as a series of strings.

```

Declaration: procedure LoadFromStream(Stream: TStream); Virtual; Overload
              procedure LoadFromStream(Stream: TStream; IgnoreEncoding: Boolean)
                      ; Overload
              procedure LoadFromStream(Stream: TStream; AEncoding: TEncoding)
                      ; Virtual; Overload

```

Visibility: public

Description: `LoadFromStream` loads the contents of `Stream` into the stringlist. Each line in the stream (as marked by the end-of-line marker of the particular OS the application runs on) becomes one string in the stringlist. This action replaces the contents of the stringlist, it does not append the strings to the current content.

See also: `TStrings.LoadFromFile` (480), `TStrings.SaveToFile` (483), `Tstrings.SaveToStream` (483)

4.74.39 TStrings.Map

Synopsis: Call a map routine for each string in the list

```
Declaration: procedure Map(aMap: TStringsMapMethod; aList: TStrings)
              function Map(aMap: TStringsMapMethod) : TStrings
```

Visibility: public

Description: `Map` applies `aMap` to each string in the list and adds the result to the list `aList`. If `aList` is not specified, the result is a `TStringList` (463) instance which must be freed by the caller.

See also: [TStrings.ForEach \(477\)](#), [TStrings.Map \(481\)](#), [TStrings.Filter \(477\)](#), [TStringsMapMethod \(281\)](#), [TStrings.Reverse \(482\)](#)

4.74.40 TStrings.Move

Synopsis: Move a string from one place in the list to another.

```
Declaration: procedure Move (CurIndex: Integer; NewIndex: Integer); Virtual
```

Visibility: public

Description: Move moves the string at position `CurIndex` so it has position `NewIndex` after the move operation. The object associated to the string is also moved. `CurIndex` and `NewIndex` should be in the range of 0 to `Count-1`.

Remark NewIndex is *not* the position in the stringlist before the move operation starts. The move operation

- 1.removes the string from position CurIndex
- 2.inserts the string at position NewIndex

This may not lead to the desired result if `NewIndex` is bigger than `CurIndex`. Consider the following example:

```
With MyStrings do
  begin
    Clear;
    Add('String 0');
```

```

Add('String 1');
Add('String 2');
Add('String 3');
Add('String 4');
Move(1, 3);
end;

```

After the `Move` operation has completed, 'String 1' will be between 'String 3' and 'String 4'.

Errors: If either `CurIndex` or `NewIndex` is outside the allowed range, an `EStringListError` (306) is raised.

See also: `TStrings.Exchange` (476)

4.74.41 TStrings.Pop

Synopsis: Remove the last string of the list and return it.

Declaration: `function Pop : string`

Visibility: `public`

Description: `Pop` returns the last list in the string and removes it from the list. If there are no strings (i.e. `Count` (485) equals zero), an empty string is returned.

See also: `TStrings.Add` (472), `TStrings.Shift` (483), `TStrings.Slice` (484)

4.74.42 TStrings.Reduce

Synopsis: Get a reduced value from the string list

Declaration: `function Reduce(aReduceMethod: TStringsReduceMethod;
const startingValue: string) : string`

Visibility: `public`

Description: `Reduce` iterates over all strings in the list and calls the `aReduceMethod` callback with 2 strings: the result of the previous iteration and the current string. The return value will be used in the next iteration, or will result in the end result of the method if the last string was reached.

See also: `TStrings.Filter` (477), `TStrings.Map` (481), `TStrings.Foreach` (477), `TStrings.ReduceMethod` (282), `TStrings.Reverse` (482)

4.74.43 TStrings.Reverse

Synopsis: Reverse the order of the strings in the list.

Declaration: `function Reverse : TStrings
procedure Reverse(aList: TStrings)`

Visibility: `public`

Description: `Reverse` reverses the order of the strings in the list.

See also: `TStrings.Filter` (477), `TStrings.Map` (481), `TStrings.Foreach` (477), `TStrings.Reduce` (482), `TStrings.Sort` (468)

4.74.47 TStrings.Slice

Synopsis: Return a subrange of strings starting at a given index.

Declaration: `procedure Slice(fromIndex: Integer; aList: TStrings)`
`function Slice(fromIndex: Integer) : TStrings`

Visibility: public

Description: `Slice` adds to `aList` the strings in the current list, starting with the string at index `FromIndex`. If `aList` is not specified, a `TStringList` (463) instance is created and used. The caller must free the new instance.

See also: `TStrings.Filter` (477), `TStrings.Shift` (483), `TStrings.Pop` (482), `TStrings.Map` (481), `TStrings.Delete` (475), `TStrings.Insert` (479)

4.74.48 TStrings.SetText

Synopsis: Set the contents of the list from a `PChar`.

Declaration: `procedure SetText(TheText: PChar); Virtual`

Visibility: public

Description: `SetText` parses the contents of `TheText` and fills the stringlist based on the contents. It regards `TheText` as a series of strings, separated by end-of-line markers. Each of these strings is added to the stringlist.

See also: `TStrings.Text` (491)

4.74.49 TStrings.AlwaysQuote

Synopsis: Always quote strings in `DelimitedText`

Declaration: `Property AlwaysQuote : Boolean`

Visibility: public

Access: Read,Write

Description: `AlwaysQuote` tells the stringlist instance to quote strings in `DelimitedText` (486) . The default is to quote strings only when they have whitespace in them.

See also: `DelimitedText` (486), `CommaText` (486), `StrictDelimiter` (490)

4.74.50 TStrings.Capacity

Synopsis: Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` is the number of strings that the list can hold before it tries to allocate more memory. `TStrings` returns `TStrings.Count` (485) when read. Trying to set the capacity has no effect. Descendant classes such as `TStringList` (463) can override this property such that it actually sets the new capacity.

See also: `TStringList` (463), `TStrings.Count` (485)

4.74.51 TStrings.CommaText

Synopsis: Contents of the list as a comma-separated string.

Declaration: Property CommaText : string

Visibility: public

Access: Read,Write

Description: CommaText represents the stringlist as a single string, consisting of a comma-separated concatenation of the strings in the list. If one of the strings contains spaces, comma's or quotes it will be enclosed by double quotes. Any double quotes in a string will be doubled. For instance the following strings:

```
Comma,string
Quote"string
Space string
NormalString
```

is converted to

```
"Comma,string","Quote""String","Space string",NormalString
```

Conversely, when setting the CommaText property, the text will be parsed according to the rules outlined above, and the strings will be set accordingly. Note that spaces will in this context be regarded as string separators, unless the string as a whole is contained in double quotes. Spaces that occur next to a delimiter will be ignored. The following string:

```
"Comma,string" , "Quote""String",Space string,, NormalString
```

Will be converted to

```
Comma,String
Quote"String
Space
String
```

```
NormalString
```

This is a special case of the TStrings.DelimitedText (486) property where the quote character is always the double quote, and the delimiter is always the colon.

Setting CommaText is equivalent to clearing the stringlist and calling TStrings.AddCommaText (473).

See also: TStrings.Text (491), TStrings.SetText (484), TStrings.DelimitedText (486), TStrings.AddCommaText (473)

4.74.52 TStrings.Count

Synopsis: Number of strings in the list.

Declaration: Property Count : Integer

Visibility: public

Access: Read

Description: `Count` is the current number of strings in the list. `TStrings` does not implement this property; descendant classes should override the property read handler to return the correct value.

Strings in the list are always uniquely identified by their `Index`; the index of a string is zero-based, i.e. it's supported range is 0 to `Count-1`. trying to access a string with an index larger than or equal to `Count` will result in an error. Code that iterates over the list in a stringlist should always take into account the zero-based character of the list index.

See also: `TStrings.Strings` (490), `TStrings.Objects` (488), `TStrings.Capacity` (484)

4.74.53 TStrings.DefaultEncoding

Synopsis: Default encoding of stringlist

Declaration: `Property DefaultEncoding : TEncoding`

Visibility: public

Access: Read,Write

Description: `DefaultEncoding` is the default encoding used by the `TStrings` instance. It is not the actual encoding, as specified by `Encoding` (487).

See also: `Encoding` (487)

4.74.54 TStrings.DelimitedText

Synopsis: Get or set all strings in the list in a delimited form.

Declaration: `Property DelimitedText : string`

Visibility: public

Access: Read,Write

Description: `DelimitedText` returns all strings, properly quoted with `QuoteChar` (489) and separated by the `Delimiter` (487) character.

Strings are quoted if they contain a space or any character with ASCII value less than 32.

The `CommaText` (485) property is a special case of delimited text where the delimiter character is a comma and the quote character is a double quote.

If `StrictDelimiter` (490) is set to `True`, then no quoting is done (The `QuoteChar` property is disregarded completely): the returned text will contain the items in the stringlist, separated by the `Delimiter` character. When writing the `DelimitedText` property, the text will be split at all occurrences of the `Delimiter` character; however, when reading, the `QuoteChar` property will be taken into account.

Setting `TStrings.AddDelimitedText` (474) is equivalent to clearing the list and calling `TStrings.AddDelimitedText` (474).

See also: `TStrings.Delimiter` (487), `TStrings.StrictDelimiter` (490), `TStrings.Text` (491), `TStrings.QuoteChar` (489), `TStrings.CommaText` (485), `TStrings.AddDelimitedText` (474)

4.74.55 TStrings.Delimiter

Synopsis: Delimiter character used in DelimitedText ([486](#)).

Declaration: `Property Delimiter : Char`

Visibility: public

Access: Read,Write

Description: `Delimiter` is the delimiter character used to separate the different strings in the stringlist when they are read or set through the DelimitedText ([486](#)) property.

See also: TStrings.DelimitedText ([486](#))

4.74.56 TStrings.Encoding

Synopsis: Current encoding of stringlist

Declaration: `Property Encoding : TEncoding`

Visibility: public

Access: Read

Description: `Encoding` is the current encoding used by the TStrings instance, and which was specified in the constructor. It is not the default encoding, as specified by DefaultEncoding ([486](#)).

See also: DefaultEncoding ([486](#))

4.74.57 TStrings.LineBreak

Synopsis: LineBreak character to use

Declaration: `Property LineBreak : string`

Visibility: public

Access: Read,Write

Description: `LineBreak` is the character used to separate lines when reading or writing TStrings.Text ([491](#)), and it is also used when reading from file.

See also: TStrings.Text ([491](#))

4.74.58 TStrings.MissingNameValueSeparatorAction

Synopsis: What to do if NameValueSeparator is missing in a string.

Declaration: `Property MissingNameValueSeparatorAction : TMissingNameValueSeparatorAction`

Visibility: public

Access: Read,Write

Description: `MissingNameValueSeparatorAction` describes what to do if a given string in the list does not have a NameValueSeparator ([488](#)) character in it: consider the line a name, a value or an empty line, or raise an error. For a list of possible values and their explanation, see TMissingNameValueSeparatorAction ([276](#))

See also: TMissingNameValueSeparatorAction ([276](#)), IndexOfName ([266](#)), Names ([266](#)), Values ([266](#)), GetNameValue ([266](#)), ValueFromIndex ([266](#))

4.74.59 TStrings.Names

Synopsis: Name parts of the name-value pairs in the list.

Declaration: `Property Names[Index: Integer]: string`

Visibility: public

Access: Read

Description: `Names` provides indexed access to the names of the name-value pairs in the list. It returns the name part of the `Index`-th string in the list.

Remark The index is not an index based on the number of name-value pairs in the list. It is the name part of the name-value pair a string `Index` in the list. If the string at position `Index` is not a name-value pair (i.e. does not contain the equal sign (=)), then an empty name is returned.

See also: `TStrings.Values` (492), `TStrings.IndexOfName` (479)

4.74.60 TStrings.NameValueSeparator

Synopsis: Value of the character used to separate name,value pairs

Declaration: `Property NameValueSeparator : Char`

Visibility: public

Access: Read,Write

Description: `NameValueSeparator` is the character used to separate name,value pair. By default, this is the equal sign (=), resulting in Name=Value pairs.

It can be set to a colon for Name : Value pairs.

4.74.61 TStrings.Objects

Synopsis: Indexed access to the objects associated with the strings in the list.

Declaration: `Property Objects[Index: Integer]: TObject`

Visibility: public

Access: Read,Write

Description: `Objects` provides indexed access to the objects associated to the strings in the list. `Index` is a zero-based index and must be in the range of 0 to `Count-1`.

Setting the `objects` property will not free the previously associated object, if there was one. The caller is responsible for freeing the object that was previously associated to the string.

`TStrings` does not implement any storage for objects. Reading the `Objects` property will always return `Nil`. Setting the property will have no effect. It is the responsibility of the descendant classes to provide storage for the associated objects.

Errors: If an `Index` outside the valid range is specified, an `EStringListError` (306) exception will be raised.

See also: `TStrings.Strings` (490), `TStrings.IndexOfObject` (479), `TStrings.Names` (488), `TStrings.Values` (492)

4.74.62 TStrings.Options

Synopsis: A set of TStringsOption ([281](#)) - various boolean properties.

Declaration: `Property Options : TStringsOptions`

Visibility: public

Access: Read,Write

Description: Set `Options` instead of the underlying boolean properties.

See also: TStringsOption ([281](#))

4.74.63 TStrings QuoteChar

Synopsis: Quote character used in DelimitedText ([486](#)).

Declaration: `Property QuoteChar : Char`

Visibility: public

Access: Read,Write

Description: `QuoteChar` is the character used by the DelimitedText ([486](#)) property to quote strings that have a space or non-printing character in it.

4.74.64 TStrings.SkipLastLineBreak

Synopsis: Do not add a linebreak to the last item

Declaration: `Property SkipLastLineBreak : Boolean`

Visibility: public

Access: Read,Write

Description: `SkipLastLineBreak` can be set to `True` to omit a linebreak character after the last string in the TStrings.Text ([491](#)). This also means when writing to file, that the file will not have a terminating linebreak character.

Note that `SkipLastLineBreak` has the opposite meaning to TStrings.TrailingLineBreak ([489](#)).

See also: TStrings.TrailingLineBreak ([489](#)), TStrings.LineBreak ([487](#)), TStrings.Text ([491](#)), TStrings.Options ([489](#))

4.74.65 TStrings.TrailingLineBreak

Synopsis: Add a linebreak to the last item

Declaration: `Property TrailingLineBreak : Boolean`

Visibility: public

Access: Read,Write

Description: `TrailingLineBreak` can be set to `False` to omit a linebreak character after the last string in the TStrings.Text ([491](#)). This also means when writing to file, that the file will not have a terminating linebreak character.

Note that `TrailingLineBreak` has the opposite meaning to TStrings.SkipLastLineBreak ([489](#)).

See also: TStrings.SkipLastLineBreak ([489](#)), TStrings.LineBreak ([487](#)), TStrings.Text ([491](#)), TStrings.Options ([489](#))

4.74.66 TStrings.StrictDelimiter

Synopsis: Should only the delimiter character be considered a delimiter

Declaration: `Property StrictDelimiter : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `StrictDelimiter` can be used to indicate that only the delimiter character should be considered a delimiter when setting `DelimitedText` (486): under normal circumstances, quotes and spaces are considered specially (see the `TStrings.CommaText` (485) property for more information).

When `StrictDelimiter` is set to `True` then only the `Delimiter` (487) character is considered when splitting the text in items: no quoting whatsoever is performed when writing the `DelimitedText` property. However, when reading the `DelimitedText` property, quoted strings are taken into account (so a quoted string can contain a delimiter that is treated as text instead of a delimiter).

See also: `DelimitedText` (486), `CommaText` (485), `Delimiter` (487), `TStrings.Options` (489)

4.74.67 TStrings.Strings

Synopsis: Indexed access to the strings in the list.

Declaration: `Property Strings[Index: Integer]: string; default`

Visibility: `public`

Access: `Read,Write`

Description: `Strings` is the default property of `TStrings`. It provides indexed read-write access to the list of strings. Reading it will return the string at position `Index` in the list. Writing it will set the string at position `Index`.

`Index` is the position of the string in the list. It is zero-based, i.e. valued values range from 0 (the first string in the list) till `Count-1` (the last string in the list). When browsing through the strings in the list, this fact must be taken into account.

To access the objects associated with the strings in the list, use the `TStrings.Objects` (488) property. The name parts of name-value pairs can be accessed with the `TStrings.Names` (488) property, and the values can be set or read through the `TStrings.Values` (492) property.

Searching through the list can be done using the `TStrings.IndexOf` (478) method.

Errors: If `Index` is outside the allowed range, an `EStringListError` (306) exception is raised.

See also: `TStrings.Count` (485), `TStrings.Objects` (488), `TStrings.Names` (488), `TStrings.Values` (492), `TStrings.IndexOf` (478)

4.74.68 TStrings.StringsAdapter

Synopsis: Not implemented in Free Pascal.

Declaration: `Property StringsAdapter : IStringsAdapter`

Visibility: `public`

Access: `Read,Write`

Description: Not implemented in Free Pascal.

4.74.69 TStrings.Text

Synopsis: Contents of the list as one big string.

Declaration: `Property Text : string`

Visibility: `public`

Access: `Read,Write`

Description: `Text` returns, when read, the contents of the stringlist as one big string consisting of all strings in the list, separated by an end-of-line marker. When this property is set, the string will be cut into smaller strings, based on the positions of end-of-line markers in the string. Any previous content of the stringlist will be lost.

Remark If any of the strings in the list contains an end-of-line marker, then the resulting string will appear to contain more strings than actually present in the list. To avoid this ambiguity, use the `TStrings.CommaText` (485) property instead.

See also: `TStrings.Strings` (490), `TStrings.Count` (485), `TStrings.CommaText` (485)

4.74.70 TStrings.TextLineBreakStyle

Synopsis: Determines which line breaks to use in the `Text` (491) property

Declaration: `Property TextLineBreakStyle : TTextLineBreakStyle`

Visibility: `public`

Access: `Read,Write`

Description: `TextLineBreakStyle` determines which linebreak style is used when constructing the `Text` property: the same rules are used as in the writing to text files:

tlbsLFLines are separated with a linefeed character #10.

tlbsCRLFLines are separated with a carriage-return/linefeed character pair: #13#10.

tlbsCRLines are separated with a carriage-return character #13.

It has no effect when setting the text property.

See also: `Text` (491)

4.74.71 TStrings.UseLocale

Synopsis: Determines what methods are used in strings comparison.

Declaration: `Property UseLocale : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: Set `UseLocale` to `True` to use `AnsiCompareStr` (266) and `AnsiCompareText` (266) for comparing strings in the `TStrings` object.

Set `UseLocale` to `False` to use `CompareStr` (266) and `CompareText` (266) for comparing strings in the `TStrings` object.

The default value is `True`.

See also: `TStrings.Options` (489)

4.74.72 TStrings.ValueFromIndex

Synopsis: Return the value part of a string based on it's index.

Declaration: `Property ValueFromIndex[Index: Integer]: string`

Visibility: public

Access: Read,Write

Description: `ValueFromIndex` returns the value part of a string based on the string index. The value part are all characters in the string after the `NameValueSeparator` (488) character, or all characters if the `NameValueSeparator` character is not present.

4.74.73 TStrings.Values

Synopsis: Value parts of the name-value pairs in the list.

Declaration: `Property Values[Name: string]: string`

Visibility: public

Access: Read,Write

Description: `Values` represents the value parts of the name-value pairs in the list.

When reading this property, if there is a name-value pair in the list of strings that has name part `Name`, then the corresponding value is returned. If there is no such pair, an empty string is returned.

When writing this value, first it is checked whether there exists a name-value pair in the list with name `Name`. If such a pair is found, it's value part is overwritten with the specified value. If no such pair is found, a new name-value pair is added with the specified `Name` and value.

Remark

- 1.Names are compared case-insensitively.
- 2.Any character, including whitespace, up till the first equal (=) sign in a string is considered part of the name.

See also: `TStrings.Names` (488), `TStrings.Strings` (490), `TStrings.Objects` (488)

4.74.74 TStrings.WriteBOM

Synopsis: Write BOM when writing stringlist to stream

Declaration: `Property WriteBOM : Boolean`

Visibility: public

Access: Read,Write

Description: `WriteBOM` signals the stringlist to write a BOM Marker to the stream if the stringlist is written to stream using `TStrings.SaveToStream` (483) or `TStrings.SaveToFile` (483)

See also: `TStrings.SaveToStream` (483), `TStrings.SaveToFile` (483), `TStrings.Options` (489)

4.75 TStringsEnumerator

4.75.1 Description

`TStringsEnumerator` implements the `#rtl.system.IEnumerator` (1589) interface for the `TStrings` (468) class, so the `TStrings` class can be used in a `for ... in` loop. It is returned by the `TStrings.GetEnumerator` (478) method of `TStrings`.

See also: `TStrings` (468), `TStrings.GetEnumerator` (478), `#rtl.system.IEnumerator` (1589)

4.75.2 Method overview

Page	Method	Description
493	<code>Create</code>	Initialize a new instance of <code>TStringsEnumerator</code>
493	<code>GetCurrent</code>	Return the current pointer in the list
493	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

4.75.3 Property overview

Page	Properties	Access	Description
494	<code>Current</code>	<code>r</code>	Current pointer in the list

4.75.4 TStringsEnumerator.Create

Synopsis: Initialize a new instance of `TStringsEnumerator`

Declaration: `constructor Create(AStrings: TStrings)`

Visibility: `public`

Description: `Create` initializes a new instance of `TStringsEnumerator` and keeps a reference to the stringlist `AStrings` that will be enumerated.

See also: `TStrings` (468)

4.75.5 TStringsEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : string`

Visibility: `public`

Description: `GetCurrent` returns the current string item in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (493), `TStringItem` (302)

4.75.6 TStringsEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: public

Description: `MoveNext` puts the pointer on the next item in the stringlist, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` (493)

4.75.7 TStringsEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : string`

Visibility: public

Access: Read

Description: `Current` redefines `GetCurrent` (493) as a property.

See also: `GetCurrent` (493)

4.76 TStringStream

4.76.1 Description

`TStringStream` stores its data in an `ansistring`. The contents of this string is available as the `DataStream` (497) property. It also introduces some methods to read or write parts of the stringstream's data as a string.

The main purpose of a `TStringStream` is to be able to treat a string as a stream from which can be read.

See also: `TStream` (448), `TStringStream.DataStream` (497), `TStringStream.ReadString` (497), `TStringStream.WriteString` (497)

4.76.2 Method overview

Page	Method	Description
495	<code>Create</code>	Creates a new stringstream and sets its initial content.
495	<code>CreateRaw</code>	Create stringstream using codepage of string
495	<code>Destroy</code>	Free the instance of the stream
496	<code>ReadAnsiString</code>	Read an <code>ansistring</code> from the stream
497	<code>ReadString</code>	Reads a string of length <code>Count</code>
496	<code>ReadUnicodeString</code>	Read a unicode string from the stream
496	<code>WriteAnsiString</code>	Write an <code>ansistring</code> to the stream
497	<code>WriteString</code>	<code>WriteString</code> writes a string to the stream.
496	<code>WriteUnicodeString</code>	Write a unicode string to the stream

4.76.3 Property overview

Page	Properties	Access	Description
497	DataStream	r	Contains the contents of the stream in string form
498	Encoding	r	Encoding of the string with the data
498	OwnsEncoding	r	Does the stream instance owns the encoding
497	UnicodeDataStream	r	Datastring as unicode string

4.76.4 TStringStream.Create

Synopsis: Creates a new stringstream and sets its initial content.

Declaration: `constructor Create(const ABytes: TBytes); Override; Overload`
`constructor Create(const AString: string); Overload`
`constructor Create(const AString: string; AEncoding: TEncoding;`
`AOwnsEncoding: Boolean); Overload`
`constructor Create(const AString: string; ACodePage: Integer); Overload`
`constructor Create(const AString: UnicodeString); Overload`
`constructor Create(const AString: UnicodeString; AEncoding: TEncoding;`
`AOwnsEncoding: Boolean); Overload`
`constructor Create(const AString: UnicodeString; ACodePage: Integer)`
`; Overload`

Visibility: public

Description: `Create` creates a new `TStringStream` instance and sets its initial content to `AString`. The position is still 0 but the size of the stream will equal the length of the string.

The `Encoding` argument specifies the codepage with which the bytes in the string will be interpreted. If it is not specified (or `Nil`) the system default encoding will be used. The correct encoding can be detected from the string by using the `TStringStream.CreateRaw` ([495](#)) constructor.

See also: `TStringStream.DataString` ([497](#)), `TStringStream.UnicodeDataStream` ([497](#)), `TStringStream.Encoding` ([498](#)), `TStringStream.CreateRaw` ([495](#))

4.76.5 TStringStream.CreateRaw

Synopsis: Create stringstream using codepage of string

Declaration: `constructor CreateRaw(const AString: RawByteString); Overload`

Visibility: public

Description: `CreateRaw` will create the stream using the codepage of the string passed on in the constructor. The default constructor uses the default codepage of the system.

See also: `TStringStream.Create` ([495](#))

4.76.6 TStringStream.Destroy

Synopsis: Free the instance of the stream

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` frees the encoding if it owns it and calls the inherited destructor.

4.76.7 TStringStream.ReadUnicodeString

Synopsis: Read a unicode string from the stream

Declaration: `function ReadUnicodeString(Count: LongInt) : UnicodeString`

Visibility: public

Description: `ReadUnicodeString` will read a unicodestring and correctly handle the codepage translation if necessary..

See also: `TStream.ReadString` (448), `TStream.ReadAnsiString` (456), `TStringStream.WriteUnicodeString` (496)

4.76.8 TStringStream.WriteUnicodeString

Synopsis: Write a unicode string to the stream

Declaration: `procedure WriteUnicodeString(const AString: UnicodeString)`

Visibility: public

Description: `WriteUnicodeString` will write a unicodestring and correctly handle the codepage translation if necessary.

See also: `TStream.ReadString` (448), `TStringStream.ReadUnicodeString` (496), `TStringStream.ReadAnsiString` (496), `TStringStream.WriteAnsiString` (496)

4.76.9 TStringStream.ReadAnsiString

Synopsis: Read an ansistring from the stream

Declaration: `function ReadAnsiString(Count: LongInt) : AnsiString; Overload`

Visibility: public

Description: `ReadAnsiString` will read an ansistring and correctly handle the codepage translation if necessary..

See also: `TStream.ReadString` (448), `TStringStream.WriteUnicodeString` (496), `TStringStream.WriteAnsiString` (496), `TStringStream.ReadUnicodeString` (496)

4.76.10 TStringStream.WriteAnsiString

Synopsis: Write an ansistring to the stream

Declaration: `procedure WriteAnsiString(const AString: AnsiString); Override`

Visibility: public

Description: `WriteAnsiString` will write an ansistring and correctly handle the codepage translation if necessary.

See also: `TStream.ReadString` (448), `TStringStream.ReadUnicodeString` (496), `TStringStream.ReadAnsiString` (496), `TStringStream.WriteUnicodeString` (496)

4.76.11 TStringStream.ReadString

Synopsis: Reads a string of length `Count`

Declaration: `function ReadString(Count: LongInt) : string`

Visibility: `public`

Description: `ReadString` reads `Count` bytes from the stream and returns the read bytes as a string. If less than `Count` bytes were available, the string has as many characters as bytes could be read.

The `ReadString` method is a wrapper around the `Read` ([494](#)) method. It does not do the same string as the `TStream.ReadAnsiString` ([456](#)) method, which first reads a length integer to determine the length of the string to be read.

See also: `TStringStream.Read` ([494](#)), `TStream.ReadAnsiString` ([456](#))

4.76.12 TStringStream.WriteString

Synopsis: `WriteString` writes a string to the stream.

Declaration: `procedure WriteString(const AString: string)`

Visibility: `public`

Description: `WriteString` writes a string to the stream.

4.76.13 TStringStream.DataString

Synopsis: Contains the contents of the stream in string form

Declaration: `Property DataString : string`

Visibility: `public`

Access: `Read`

Description: Contains the contents of the stream in string form

4.76.14 TStringStream.UnicodeDataString

Synopsis: `Datastring` as unicode string

Declaration: `Property UnicodeDataString : UnicodeString`

Visibility: `public`

Access: `Read`

Description: `UnicodeDataString` returns the data string as a unicode encoded string.

See also: `TStringStream.DataString` ([497](#))

4.76.15 TStringStream.OwnsEncoding

Synopsis: Does the stream instance owns the encoding

Declaration: `Property OwnsEncoding : Boolean`

Visibility: `public`

Access: `Read`

Description: `OwnsEncoding` indicates whether the stream instance owns the encoding or not. If it owns the encoding, it will be freed when the stream instance is freed.

See also: `TStringStream.Encoding` ([498](#))

4.76.16 TStringStream.Encoding

Synopsis: Encoding of the string with the data

Declaration: `Property Encoding : TEncoding`

Visibility: `public`

Access: `Read`

Description: `Encoding` is the encoding of the string which contains the data. If the encoding was not specified (or detected) in the constructor, this is the default system encoding.

See also: `TStringStream.OwnsEncoding` ([498](#)), `TStringStream.Create` ([495](#)), `TStringStream.CreateRaw` ([495](#))

4.77 TTextObjectWriter

4.77.1 Description

Not yet implemented.

4.78 TThread

4.78.1 Description

The `TThread` class encapsulates the native thread support of the operating system. To create a thread, declare a descendant of the `TThread` object and override the `Execute` ([499](#)) method. In this method, the `tthread`'s code should be executed. To run a thread, create an instance of the `tthread` descendant, and call its `execute` method.

It is also possible to simply execute a method or static procedure in a thread using the `TThread.ExecuteInThread` ([504](#)) class method.

See also: `EThread` ([306](#)), `TThread.Execute` ([499](#)), `TThread.ExecuteInThread` ([504](#))

4.78.2 Method overview

Page	Method	Description
508	AfterConstruction	Code to be executed after construction but before execute.
501	CheckTerminated	Check if the current thread has finished executing.
500	Create	Creates a new thread.
501	CreateAnonymousThread	Execute code in an anonymous thread
500	Destroy	Destroys the thread object.
499	Execute	Execute method. Must be overridden in a descendant thread.
504	ExecuteInThread	Execute a method or static procedure in a thread
503	GetSystemTimes	Return CPU stats
503	GetTickCount	Return tick count (32-bit)
503	GetTickCount64	Return tick count (64-bit)
501	NameThreadForDebugging	Set a thread name
500	Queue	Queue a method for execution in the main thread
502	RemoveQueuedEvents	Remove methods scheduled for execution from queue
509	Resume	Resumes the thread's execution. Deprecated, see <code>TThread.Start</code>
501	SetReturnValue	Set return value of a thread
502	Sleep	Prevent thread execution
502	SpinWait	Prevent thread execution in a spin-wait loop
508	Start	Starts a thread that was created in a suspended state.
509	Suspend	Suspends the thread's execution.
500	Synchronize	Synchronizes the thread by executing the method in the main thread.
509	Terminate	Signals the thread it should terminate.
509	WaitFor	Waits for the thread to terminate and returns the exit status.
503	Yield	Yield execution to other threads

4.78.3 Property overview

Page	Properties	Access	Description
510	CurrentThread	r	Return current thread instance
511	ExternalThread	r	Is the thread instance an external thread ?
513	FatalException	r	Exception that occurred during thread execution
512	Finished	r	Has the thread finished executing
511	FreeOnTerminate	rw	Indicates whether the thread should free itself when it stops executing.
511	Handle	r	Returns the thread handle.
510	IsSingleProcessor	r	Is the current system single processor or not
512	OnTerminate	rw	Event called when the thread terminates.
511	Priority	rw	Returns the thread priority.
510	ProcessorCount	r	Return the processor count for this system
512	Suspended	rw	Indicates whether the thread is suspended.
512	ThreadID	r	Returns the thread ID.

4.78.4 TThread.Execute

Synopsis: Execute method. Must be overridden in a descendant thread.

Declaration: `procedure Execute; Virtual; Abstract`

Visibility: `protected`

Description: `Execute` is a method that must be overridden in descendant classes of the thread. It must contain the code that must execute in the thread. The `Execute` method is responsible for checking `Terminated` (266) at regular intervals: when it is set to `True` the execute method must exit.

See also: `Terminated` (266)

4.78.5 `TThread.Synchronize`

Synopsis: Synchronizes the thread by executing the method in the main thread.

Declaration: `procedure Synchronize (AMethod: TThreadMethod)`
`class procedure Synchronize (AThread: TThread; AMethod: TThreadMethod)`

Visibility: `protected`

Description: Synchronizes the thread by executing the method in the main thread.

4.78.6 `TThread.Queue`

Synopsis: `Queue` a method for execution in the main thread

Declaration: `procedure Queue (aMethod: TThreadMethod)`
`class procedure Queue (aThread: TThread; aMethod: TThreadMethod); Static`

Visibility: `protected`

Description: `Queue` schedules a method `aMethod` for execution in the main thread. In difference with `TThread.Synchronize` (500), `Queue` just posts the method for execution in a queue, and does not wait for it to be executed, so this call returns at once.

In the class procedure overloaded version of this call, the thread for which the method must be posted is the first argument. In the protected version of this call (used in the `tthread` instance), this argument is not there, and the thread instance is used.

When a thread object is destroyed (after it has finished executing) all its queued calls are removed from the queue list.

See also: `TThread.Synchronize` (500), `TThread.RemoveQueuedEvents` (502)

4.78.7 `TThread.Create`

Synopsis: Creates a new thread.

Declaration: `constructor Create (CreateSuspended: Boolean; const StackSize: SizeUInt)`

Visibility: `public`

Description: Creates a new thread.

4.78.8 `TThread.Destroy`

Synopsis: Destroys the thread object.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the thread object.

4.78.9 TThread.CreateAnonymousThread

Synopsis: Execute code in an anonymous thread

Declaration: `class function CreateAnonymousThread(aProc: TProcedure) : TThread
; Static`

Visibility: public

Description: `CreateAnonymousThread` will create an instance of a `TThread` descendant and calls `aProc` in this procedure. This can be used to quickly execute a method in another thread without having to explicitly declare a thread for such purposes. It returns the created `TThread` instance, which can be checked for termination etc.

Note that this method differs slightly from Delphi in that FPC does not yet support anonymous methods, so the signature of `aProc` differs slightly.

See also: `TThread.CheckTerminated` ([501](#))

4.78.10 TThread.NameThreadForDebugging

Synopsis: Set a thread name

Declaration: `class procedure NameThreadForDebugging(aThreadName: UnicodeString;
aThreadID: TThreadID); Static
class procedure NameThreadForDebugging(aThreadName: AnsiString;
aThreadID: TThreadID); Static`

Visibility: public

Description: `NameThreadForDebugging` sets the name of thread `aThreadID` to `aThreadName`. The thread name can be Unicode or ansistring. This is mainly useful for debugging purposes, as thread names are more easily recognizable than IDs.

Note that this requires OS support, so at the moment it is Windows and Unix only.

4.78.11 TThread.SetReturnValue

Synopsis: Set return value of a thread

Declaration: `class procedure SetReturnValue(aValue: Integer); Static`

Visibility: public

Description: `TThread.SetReturnValue` sets the return value of an internally created thread.

Errors: If the thread was not created by the FPC program, an `EThreadExternalException` ([306](#)) exception is raised.

See also: `EThreadExternalException` ([306](#)), `TThread.CheckTerminated` ([501](#))

4.78.12 TThread.CheckTerminated

Synopsis: Check if the current thread has finished executing.

Declaration: `class function CheckTerminated : Boolean; Static`

Visibility: public

Description: `Sleep` blocks the execution of the thread for `aMilliseconds`. This function simply calls `sysutils.sleep` (266)

In difference with `TThread.SpinWait` (502), a thread switch may occur during the sleep.

See also: `SysUtils.Sleep` (266), `TThread.SpinWait` (502)

4.78.16 `TThread.Yield`

Synopsis: Yield execution to other threads

Declaration: `class procedure Yield; Static`

Visibility: `public`

Description: `TThread.Yield` yields the processor to other threads. It can be called from methods outside the thread class itself.

4.78.17 `TThread.GetSystemTimes`

Synopsis: Return CPU stats

Declaration: `class procedure GetSystemTimes(out aSystemTimes: TSystemTimes); Static`

Visibility: `public`

Description: `GetSystemTimes` is provided for Delphi compatibility only, it currently returns empty values only.

See also: `TSystemTimes` (266)

4.78.18 `TThread.GetTickCount`

Synopsis: Return tick count (32-bit)

Declaration: `class function GetTickCount : LongWord; Static`

Visibility: `public`

Description: `GetTickCount` is deprecated and should not be used. Use `TThread.GetTickCount64` (503) instead.

See also: `TThread.GetTickCount64` (503)

4.78.19 `TThread.GetTickCount64`

Synopsis: Return tick count (64-bit)

Declaration: `class function GetTickCount64 : QWord; Static`

Visibility: `public`

Description: `GetTickCount64` simply calls `SysUtils.GetTickCount64` (266) and is implemented for Delphi compatibility only.

See also: `SysUtils.GetTickCount64` (266)

4.78.20 TThread.ExecuteInThread

Synopsis: Execute a method or static procedure in a thread

Declaration:

```

class function ExecuteInThread(AMethod: TThreadExecuteHandler;
                               AOnTerminate: TNotifyEvent) : TThread
                               ; Overload; Static
class function ExecuteInThread(AMethod: TThreadExecuteStatusHandler;
                               AOnStatus: TThreadStatusNotifyEvent;
                               AOnTerminate: TNotifyEvent) : TThread
                               ; Overload; Static
class function ExecuteInThread(AMethod: TThreadExecuteCallBack;
                               AData: Pointer;
                               AOnTerminate: TNotifyCallBack) : TThread
                               ; Overload; Static
class function ExecuteInThread(AMethod: TThreadExecuteStatusCallBack;
                               AOnStatus: TThreadStatusNotifyCallBack;
                               AData: Pointer;
                               AOnTerminate: TNotifyCallBack) : TThread
                               ; Overload; Static

```

Visibility: public

Description: `TThread.ExecuteInThread` is a class method which allows to quickly execute a method or procedure in a thread. The method or procedure to be executed is passed in `Method`, this can be a method or a plain (static) procedure.

The caller can be notified of thread termination: In the optional argument `AOnTerminate` a callback (procedure or method, depending on the signature) can be specified that will be called when the thread terminated. This callback is executed in the main thread.

The signature of `AMethod` determines whether status reporting is enabled or not. If the method of type `TThreadExecuteStatusHandler` (283) or `TThreadExecuteStatusCallBack` (283), then an extra `AOnStatus` callback must be specified. This callback will be called in the main thread whenever the thread wishes to be report its status. The status callback should not do extensive work, because while the status callback is called, thread execution is suspended.

When using a plain procedure, extra data can be passed on to the procedure in `AData`. The `AData` pointer will be passed to the thread method, and also to the thread status callback and thread termination callback.

See also: `TThreadExecuteHandler` (283), `TThreadExecuteStatusHandler` (283), `TThreadExecuteStatusCallBack` (283), `TThreadExecuteCallBack` (283)

Listing: `./examples/classessex/tthrc.pp`

```

program tthrc;

uses cthreads, sysutils, classes;

Var
  D : Integer;

Procedure DoneThread(Sender : TObject; AData : Pointer);

begin
  WriteLn('Thread ', TThread(Sender).ThreadID, ' done. D is currently: ', PInteger(AData)^);
end;

```

```

Procedure DoThread(AData : Pointer);

Var
  I : integer;

begin
  for I:=1 to 10 do
    begin
      Sleep(10*Random(30));
      WriteIn( 'Thread ',TThread.CurrentThread.ThreadID, ' ping ',I);
      Inc(PInteger(AData)^,i);
    end;
  end;

Var
  T1,T2 : TThread;

begin
  T1:=TThread.ExecuteInThread(@DoThread,@D,@DoneThread);
  T2:=TThread.ExecuteInThread(@DoThread,@D,@DoneThread);
  WriteIn( 'Main thread done');
  T1.WaitFor;
  T2.WaitFor;
end.

```

Listing: ./examples/classesex/tthre.pp

```

program tthre;

{$mode objfpc}
{$H+}

uses cthreads, sysutils, classes;

Type
  TTestThread = Class(TObject)
    D : Integer;
    Procedure DoneThread(Sender : TObject);
    Procedure DoThread;
    Procedure Run;
  end;

Procedure TTestThread.DoneThread(Sender : TObject);

begin
  WriteIn( 'Thread ',TThread(Sender).ThreadID, ' done. D is currently: ', D);
end;

Procedure TTestThread.DoThread;

Var
  I : integer;

begin
  for I:=1 to 10 do
    begin

```

```

        Sleep(10*Random(30));
        Writeln('Thread ',TThread.CurrentThread.ThreadID,' ping ',I);
        Inc(D,i);
    end;
end;

```

```

Procedure TTestThread.Run;

```

```

Var

```

```

    T1,T2 : TThread;

```

```

begin

```

```

    T1:=TThread.ExecuteInThread(@DoThread,@DoneThread);

```

```

    T2:=TThread.ExecuteInThread(@DoThread,@DoneThread);

```

```

    Writeln('Main thread done');

```

```

    T1.WaitFor;

```

```

    T2.WaitFor;

```

```

end;

```

```

begin

```

```

    With TTestThread.Create do

```

```

        try

```

```

            Run;

```

```

        finally

```

```

            Free;

```

```

        end;

```

```

end.

```

Listing: ./examples/classessex/tthrcs.pp

```

program tthrcs;

```

```

{$h+}

```

```

uses cthreads, sysutils, classes;

```

```

Var

```

```

    D : Integer;

```

```

    DoneThreads : INteger;

```

```

Procedure DoneThread(Sender : TObject; Data : Pointer);

```

```

begin

```

```

    Inc(DoneThreads);

```

```

    Writeln('Thread ',TThread(Sender).ThreadID,' done. D is currently: ', PInteger(Data)^);

```

```

end;

```

```

Procedure ReportThreadStatus(Sender : TThread; AData : Pointer;Const status : String);

```

```

begin

```

```

    Writeln('Thread ',Sender.ThreadID,' Status report : ',Status);

```

```

end;

```

```

Procedure DoThread(AData : Pointer; Report : TThreadReportStatus);

```

```

Var

```

```

    I : integer;

```

```

begin

```

```

    for i:=1 to 10 do
        begin
            Sleep(10*Random(30));
            Report( 'Ping ' + IntToStr(i));
            Inc( PInteger(AData)^, i);
        end;
    end;

Var
    T1,T2 : TThread;

begin
    DoneThreads:=0;
    T1:=TThread.ExecuteInThread(@DoThread,@ReportThreadStatus,@D,@DoneThread);
    T2:=TThread.ExecuteInThread(@DoThread,@ReportThreadStatus,@D,@DoneThread);
    WriteLn('Main thread loop');
    While DoneThreads<2 do
        begin
            Sleep(10);
            CheckSynchronize;
        end;
        T1.WaitFor;
        T2.WaitFor;
    end.

```

Listing: ./examples/classesex/tthres.pp

```

program tthrc;

```

```

{$mode objfpc}
{$H+}

```

```

uses cthreads, sysutils, classes;

```

Type

```

TTestThread = Class(TObject)
    D : Integer;
    DoneThreads : integer;
    Procedure DoneThread(Sender : TObject);
    Procedure ReportThreadStatus(Sender : TThread; Const status : String);
    Procedure DoThread(Report: TThreadReportStatus);
    Procedure Run;
end;

```

```

Procedure TTestThread.DoneThread(Sender : TObject);

```

```

begin
    Inc(DoneThreads);
    WriteLn('Thread ',TThread(Sender).ThreadID,' done. D is currently: ', D);
end;

```

```

Procedure TTestThread.ReportThreadStatus(Sender : TThread; Const status : String);

```

```

begin
    WriteLn('Thread ',Sender.ThreadID,' Status report : ',Status);
end;

```

```

Procedure TTestThread.DoThread(Report : TThreadReportStatus);

```

```

Var
  I : integer;

begin
  for I:=1 to 10 do
    begin
      Sleep(10*Random(30));
      Report('Ping '+IntToStr(i));
      Inc(D,i);
    end;
  end;

Procedure TTestThread.Run;

Var
  T1,T2 : TThread;

begin
  DoneThreads:=0;
  T1:=TThread.ExecuteInThread(@DoThread,@ReportThreadStatus,@DoneThread);
  T2:=TThread.ExecuteInThread(@DoThread,@ReportThreadStatus,@DoneThread);
  Writeln('Main thread loop');
  While DoneThreads<2 do
    begin
      Sleep(10);
      CheckSynchronize;
    end;
    T1.WaitFor;
    T2.WaitFor;
  end;

begin
  With TTestThread.Create do
    try
      Run;
    finally
      Free;
    end;
  end.

```

4.78.21 TThread.AfterConstruction

Synopsis: Code to be executed after construction but before execute.

Declaration: `procedure AfterConstruction; Override`

Visibility: public

Description: `AfterConstruction` is overridden in `TThread`, it actually starts the thread if it was created with `CreateSuspended` equal to `False`, i.e. not suspended. When overriding this method, the inherited method must be called, or the thread will never be started.

4.78.22 TThread.Start

Synopsis: Starts a thread that was created in a suspended state.

Declaration: `procedure Start`

Visibility: `public`

Description: The effect of this method is currently the same as calling `TThread.Resume` after creating a thread in a suspended state. This method was added for Delphi-compatibility, where it was introduced after `TThread.Suspend` and `TThread.Resume` were deprecated.

See also: `TThread.Create` ([500](#))

4.78.23 TThread.Resume

Synopsis: Resumes the thread's execution. Deprecated, see `TThread.Start`

Declaration: `procedure Resume`

Visibility: `public`

Description: Resumes the thread's execution. Deprecated, see `TThread.Start`

See also: `TThread.Start` ([508](#)), `TThread.Suspend` ([509](#))

4.78.24 TThread.Suspend

Synopsis: Suspends the thread's execution.

Declaration: `procedure Suspend`

Visibility: `public`

Description: On non-Windows platforms, a thread can only suspend itself. Other threads can wake up a suspended thread by calling `TThread.Start`.

See also: `TThread.Resume` ([509](#)), `TThread.Start` ([508](#))

4.78.25 TThread.Terminate

Synopsis: Signals the thread it should terminate.

Declaration: `procedure Terminate`

Visibility: `public`

Description: `Terminate` sets the `TThread.Terminated` ([498](#)) flag. It does not in any way attempt to terminate the thread in any other way, this just signals the thread that it should stop executing at the earliest possible moment.

See also: `TThread.Terminated` ([498](#)), `TThread.WaitFor` ([509](#)), `TThread.FreeOnTerminate` ([511](#)), `OnTerminate` ([512](#))

4.78.26 TThread.WaitFor

Synopsis: Waits for the thread to terminate and returns the exit status.

Declaration: `function WaitFor : Integer`

Visibility: `public`

Description: `WaitFor` waits for the thread to terminate, and returns the exit status. Note that when executed in the main thread, this method calls `CheckSynchronize` (288), this is done to avoid deadlocks: if the thread is waiting for a `synchronize` (500), then the `synchronize` methods will be executed and then the `WaitFor` will return.

See also: `TThread.Terminated` (498), `TThread.WaitFor` (509), `TThread.FreeOnTerminate` (511), `TThread.Synchronize` (500)

4.78.27 TThread.CurrentThread

Synopsis: Return current thread instance

Declaration: `Property CurrentThread : TThread`

Visibility: public

Access: Read

Description: `TThread.CurrentThread` can be used to get the current thread instance. This is useful in code that is not inside a `TThread` implementation, but which needs access to the current thread.

For threads that were created outside of FPC code (DLLs or a calling program) this will return a dummy `TThread` instance.

See also: `TThread.ExternalThread` (511)

4.78.28 TThread.ProcessorCount

Synopsis: Return the processor count for this system

Declaration: `Property ProcessorCount : LongWord`

Visibility: public

Access: Read

Description: `ProcessorCount` returns the processor count for this system.

Whether this is the number of cores or the number of CPUs present in the hardware, is deliberately unspecified. The number of cores can also vary during the lifetime of the program, and the FPC implementation does not guarantee that this will always match, the value is set at program start.

As such, the number specified should only be used as an indication of how many threads can be executed at once by the system.

See also: `TThread.IsSingleProcessor` (510)

4.78.29 TThread.IsSingleProcessor

Synopsis: Is the current system single processor or not

Declaration: `Property IsSingleProcessor : Boolean`

Visibility: public

Access: Read

Description: `Thread.IsSingleProcessor` returns `True` if `TThread.ProcessorCount` (510) is less than or equal to 1, `False` otherwise.

See also: `TThread.ProcessorCount` (510)

4.78.30 TThread.FreeOnTerminate

Synopsis: Indicates whether the thread should free itself when it stops executing.

Declaration: `Property FreeOnTerminate : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `FreeOnTerminate`, when set to `True` indicates that the tread instance will freed automatically as soon as the thread stops executing. You can use the `OnTerminate` (512) property to get a notification of when the thread has terminated and will be freed.

When setting this property to `True`, in general you may not read or write any property of the `TThread` instance from a different thread, because there is no guarantee that the thread instance still exists in memory. This implies 2 things:

- 1.The `OnTerminate` event handler should be set before setting `FreeOnTerminate` to `True`
- 2.The properties can still be read and set in the `OnTerminate` event handler, as the thread instance is then still guaranteed to exist.

See also: `OnTerminate` (512)

4.78.31 TThread.Handle

Synopsis: Returns the thread handle.

Declaration: `Property Handle : TThreadID`

Visibility: `public`

Access: `Read`

Description: Returns the thread handle.

4.78.32 TThread.ExternalThread

Synopsis: Is the thread instance an external thread ?

Declaration: `Property ExternalThread : Boolean`

Visibility: `public`

Access: `Read`

Description: `ExternalThread` returns `True` if the thread is an externally created thread. If the thread was created by the FPC program, this returns `False`. This is useful for examining instances returned by `TThread.CurrentThread` (510).

See also: `TThread.CurrentThread` (510)

4.78.33 TThread.Priority

Synopsis: Returns the thread priority.

Declaration: `Property Priority : TThreadPriority`

Visibility: `public`

Access: `Read,Write`

Description: Returns the thread priority.

4.78.34 TThread.Suspended

Synopsis: Indicates whether the thread is suspended.

Declaration: `Property Suspended : Boolean`

Visibility: `public`

Access: `Read, Write`

Description: Indicates whether the thread is suspended.

4.78.35 TThread.Finished

Synopsis: Has the thread finished executing

Declaration: `Property Finished : Boolean`

Visibility: `public`

Access: `Read`

Description: `Finished` is `True` when `TThread.Execue` (498) has finished executing, but the thread is still cleaning up (calling `OnTerminate`, etc).

See also: `TThread.Execue` (498), `TThread.OnTerminate` (512)

4.78.36 TThread.ThreadID

Synopsis: Returns the thread ID.

Declaration: `Property ThreadID : TThreadID`

Visibility: `public`

Access: `Read`

Description: Returns the thread ID.

4.78.37 TThread.OnTerminate

Synopsis: Event called when the thread terminates.

Declaration: `Property OnTerminate : TNotifyEvent`

Visibility: `public`

Access: `Read, Write`

Description: `TThread.OnTerminate` is called when the thread terminates. The event is always called in the context of the main thread, i.e. using `TThread.Synchronize` (500)

See also: `TThread.Synchronize` (500), `TThread.FreeOnTerminate` (511)

4.78.38 TThread.FatalException

Synopsis: Exception that occurred during thread execution

Declaration: `Property FatalException : TObject`

Visibility: `public`

Access: `Read`

Description: `FatalException` contains the exception that occurred during the thread's execution.

4.79 TThreadList

4.79.1 Description

`TThreadList` is a thread-safe `TList` (408) implementation. Unlike `TList`, it can be accessed read-write by multiple threads: the list implementation will take care of locking the list when adding or removing items from the list.

See also: `TList` (408)

4.79.2 Method overview

Page	Method	Description
514	<code>Add</code>	Adds an element to the list.
514	<code>Clear</code>	Removes all elements from the list.
513	<code>Create</code>	Creates a new thread-safe list.
514	<code>Destroy</code>	Destroys the list instance.
514	<code>LockList</code>	Locks the list for exclusive access.
515	<code>Remove</code>	Removes an item from the list.
515	<code>UnlockList</code>	Unlocks the list after it was locked.

4.79.3 Property overview

Page	Properties	Access	Description
515	<code>Duplicates</code>	<code>rw</code>	Describes what to do with duplicates

4.79.4 TThreadList.Create

Synopsis: Creates a new thread-safe list.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new `TThreadList` instance. It initializes a critical section and an internal list object.

See also: `TThreadList.Destroy` ([514](#))

4.79.5 TThreadList.Destroy

Synopsis: Destroys the list instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` finalizes the critical section, clears the internal list object and calls the inherited destructor.

See also: `TThreadList.Create` ([513](#))

4.79.6 TThreadList.Add

Synopsis: Adds an element to the list.

Declaration: `procedure Add(Item: Pointer)`

Visibility: `public`

Description: `Add` attempts to lock the list and adds the pointer `Item` to the list. After the pointer was added, the list is unlocked again.

See also: `LockList` ([514](#)), `Clear` ([514](#)), `Remove` ([515](#)), `UnlockList` ([515](#))

4.79.7 TThreadList.Clear

Synopsis: Removes all elements from the list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` attempts to lock the list and then clears the list; all items are removed from the list. After the list is cleared, it is again unlocked.

See also: `LockList` ([514](#)), `Add` ([514](#)), `Remove` ([515](#)), `UnlockList` ([515](#))

4.79.8 TThreadList.LockList

Synopsis: Locks the list for exclusive access.

Declaration: `function LockList : TList`

Visibility: `public`

Description: `LockList` locks the thread list for exclusive access. The return value for the method is the internal `TList` instance with pointers to the `TThread` instances for the thread list. `Locklist` uses an internal critical section, so all rules for multiple locking of critical sections apply to `locklist/unlocklist` as well.

See also: `Clear` ([514](#)), `Add` ([514](#)), `Remove` ([515](#)), `UnlockList` ([515](#))

4.79.9 TThreadList.Remove

Synopsis: Removes an item from the list.

Declaration: `procedure Remove(Item: Pointer)`

Visibility: `public`

Description: `Remove` attempts to lock the list and then removes `Item` from the list. After the item is removed, the list is again unlocked.

See also: `LockList` (514), `Add` (514), `Clear` (514), `UnlockList` (515)

4.79.10 TThreadList.UnlockList

Synopsis: Unlocks the list after it was locked.

Declaration: `procedure UnlockList`

Visibility: `public`

Description: `UnLockList` unlocks the list when it was locked for exclusive access. `UnLocklist` and `LockList` use an internal critical section, so all rules for multiple locking/unlocking of critical sections apply.

See also: `Clear` (514), `Add` (514), `Remove` (515), `lockList` (514)

4.79.11 TThreadList.Duplicates

Synopsis: Describes what to do with duplicates

Declaration: `Property Duplicates : TDuplicates`

Visibility: `public`

Access: `Read,Write`

Description: `Duplicates` describes what the threadlist should do when a duplicate pointer is added to the list. It is identical in behaviour to the `Duplicates` (466) property of `TStringList` (463).

See also: `TDuplicates` (273)

4.80 TWriter

4.80.1 Description

The `TWriter` class is a writer class that implements generic component streaming capabilities, independent of the format of the data in the stream. It uses a driver class `TAbstractObjectWriter` (327) to do the actual reading of data. The interface of the `TWriter` class should be identical to the interface in Delphi.

Note that the `TWriter` design is such that it will write a single component to a stream. It will write all children of this component, but it is not designed to write multiple components in succession to one stream.

It should never be necessary to create an instance of this class directly. Instead, the `TStream.WriteComponent` (453) call should be used.

See also: `TFile` (386), `TWriter` (515), `TAbstractObjectReader` (319)

4.80.2 Method overview

Page	Method	Description
516	Create	Creates a new Writer with a stream and bufsize.
517	DefineBinaryProperty	Callback used when defining and streaming custom properties.
517	DefineProperty	Callback used when defining and streaming custom properties.
517	Destroy	Destroys the writer instance.
517	FlushBuffer	Flush the buffer
517	Write	Write raw data to stream
518	WriteBoolean	Write boolean value to the stream.
518	WriteChar	Write a character to the stream.
518	WriteCollection	Write a collection to the stream.
518	WriteComponent	Stream a component to the stream.
519	WriteCurrency	Write a currency value to the stream
519	WriteDate	Write a date to the stream.
519	WriteDescendent	Write descendent to stream
519	WriteFloat	Write a float to the stream.
520	WriteIdent	Write an identifier to the stream.
520	WriteInteger	Write an integer to the stream.
520	WriteListBegin	Write a start-of-list marker to the stream.
520	WriteListEnd	Write an end-of-list marker to the stream.
521	WriteRootComponent	Write a root component to the stream.
520	WriteSet	Write a set value to the stream
521	WriteSignature	Write a signature to the stream
519	WriteSingle	Write a single-type real to the stream.
521	WriteString	Write a string to the stream.
521	WriteUnicodeString	Write a Unicode string to the stream.
522	WriteVariant	Write a variant to the stream
518	WriteWideChar	Write widechar to stream
521	WriteWideString	Write a widestring value to the stream

4.80.3 Property overview

Page	Properties	Access	Description
523	Driver	r	Driver used when writing to the stream.
522	OnFindAncestor	rw	Event occurring when an ancestor component must be found.
522	OnWriteMethodProperty	rw	Handler from writing method properties.
523	OnWriteStringProperty	rw	Event handler for translating strings written to stream.
523	PropertyPath	r	Path to the property that is currently being written
522	RootAncestor	rw	Ancestor of root component.

4.80.4 TWriter.Create

Synopsis: Creates a new Writer with a stream and bufsize.

Declaration: `constructor Create(ADriver: TAbstractObjectWriter)`
`constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new Writer with a stream and bufsize.

4.80.5 TWriter.Destroy

Synopsis: Destroys the writer instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the writer instance.

4.80.6 TWriter.FlushBuffer

Synopsis: Flush the buffer

Declaration: `procedure FlushBuffer; Override`

Visibility: `public`

Description: `FlushBuffer` flushes the buffer. It is provided for Delphi compatibility, and is not used in FPC.

See also: `TFile.FlushBuffer` ([387](#)), `TBinaryObjectWriter.FlushBuffer` ([347](#)), `TAbstractObjectWriter.FlushBuffer` ([329](#))

4.80.7 TWriter.DefineProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineProperty(const Name: string; ReadData: TReaderProc;
AWriteData: TWriterProc; HasData: Boolean)
; Override`

Visibility: `public`

Description: Callback used when defining and streaming custom properties.

4.80.8 TWriter.DefineBinaryProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineBinaryProperty(const Name: string;
ReadData: TStreamProc;
AWriteData: TStreamProc; HasData: Boolean)
; Override`

Visibility: `public`

Description: Callback used when defining and streaming custom properties.

4.80.9 TWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Virtual`

Visibility: `public`

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TBinaryObjectWriter.Write` ([348](#)), `TAbstractObjectWriter.Write` ([329](#))

4.80.10 TWriter.WriteBoolean

Synopsis: Write boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean)`

Visibility: `public`

Description: Write boolean value to the stream.

4.80.11 TWriter.WriteCollection

Synopsis: Write a collection to the stream.

Declaration: `procedure WriteCollection(Value: TCollection)`

Visibility: `public`

Description: Write a collection to the stream.

4.80.12 TWriter.WriteComponent

Synopsis: Stream a component to the stream.

Declaration: `procedure WriteComponent(Component: TComponent)`

Visibility: `public`

Description: Stream a component to the stream.

4.80.13 TWriter.WriteChar

Synopsis: Write a character to the stream.

Declaration: `procedure WriteChar(Value: Char)`

Visibility: `public`

Description: Write a character to the stream.

4.80.14 TWriter.WriteWideChar

Synopsis: Write widechar to stream

Declaration: `procedure WriteWideChar(Value: WideChar)`

Visibility: `public`

Description: `WriteWideChar` writes a widechar to the stream. This actually writes a widestring of length 1.

See also: `TReader.ReadWideChar` ([438](#)), `TWriter.WriteWideString` ([521](#))

4.80.15 TWriter.WriteDescendent

Synopsis: Write descendent to stream

Declaration: `procedure WriteDescendent (ARoot: TComponent; AAncestor: TComponent)`

Visibility: public

Description: `WriteDescendent` writes `ARoot` as a descendent of `AAncestor`. This is used to create diff streams: only the properties where `ARoot` differs from `AAncestor` are written to the stream.

See also: `TStream.WriteDescendent` ([453](#))

4.80.16 TWriter.WriteFloat

Synopsis: Write a float to the stream.

Declaration: `procedure WriteFloat (const Value: Extended)`

Visibility: public

Description: Write a float to the stream.

4.80.17 TWriter.WriteSingle

Synopsis: Write a single-type real to the stream.

Declaration: `procedure WriteSingle (const Value: Single)`

Visibility: public

Description: Write a single-type real to the stream.

4.80.18 TWriter.WriteDate

Synopsis: Write a date to the stream.

Declaration: `procedure WriteDate (const Value: TDateTime)`

Visibility: public

Description: Write a date to the stream.

4.80.19 TWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency (const Value: Currency)`

Visibility: public

Description: `WriteCurrency` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadCurrency` ([439](#))

4.80.20 TWriter.WriteIdent

Synopsis: Write an identifier to the stream.

Declaration: `procedure WriteIdent (const Ident: string)`

Visibility: `public`

Description: Write an identifier to the stream.

4.80.21 TWriter.WriteInteger

Synopsis: Write an integer to the stream.

Declaration: `procedure WriteInteger (Value: LongInt); Overload`
`procedure WriteInteger (Value: Int64); Overload`

Visibility: `public`

Description: Write an integer to the stream.

4.80.22 TWriter.WriteSet

Synopsis: Write a set value to the stream

Declaration: `procedure WriteSet (Value: LongInt; SetType: Pointer)`

Visibility: `public`

Description: `WriteSet` writes a set `Value` consisting of elements with type `EnumType`. The set must be encoded as an integer where each element is encoded in a bit of the integer. Thus, at most an enumerated type with 32 elements can be written with this method.

Errors: No checking is performed on the validity of `EnumType`. It is assumed to be a valid `PTypeInfo` pointer.

See also: `TReader.ReadSet` ([440](#))

4.80.23 TWriter.WriteListBegin

Synopsis: Write a start-of-list marker to the stream.

Declaration: `procedure WriteListBegin`

Visibility: `public`

Description: Write a start-of-list marker to the stream.

4.80.24 TWriter.WriteListEnd

Synopsis: Write an end-of-list marker to the stream.

Declaration: `procedure WriteListEnd`

Visibility: `public`

Description: Write an end-of-list marker to the stream.

4.80.25 TWriter.WriteSignature

Synopsis: Write a signature to the stream

Declaration: `procedure WriteSignature`

Visibility: `public`

Description: `WriteSignature` writes the streaming signature (if any) to a stream. It is called once, at the start of writing the root component to a stream.

See also: `TAbstractObjectWriter.WriteSignature` ([328](#)), `TBinaryObjectWriter.WriteSignature` ([346](#))

4.80.26 TWriter.WriteRootComponent

Synopsis: Write a root component to the stream.

Declaration: `procedure WriteRootComponent (ARoot: TComponent)`

Visibility: `public`

Description: Write a root component to the stream.

4.80.27 TWriter.WriteString

Synopsis: Write a string to the stream.

Declaration: `procedure WriteString(const Value: string)`

Visibility: `public`

Description: Write a string to the stream.

4.80.28 TWriter.WriteString

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString)`

Visibility: `public`

Description: `WriteWideString` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadWideString` ([442](#))

4.80.29 TWriter.WriteString

Synopsis: Write a Unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString)`

Visibility: `public`

Description: `WriteUnicodeString` writes `Value`, a `UnicodeString` string to the stream. It simply passes the string on to the `WriteUnicodeString` method of the writer driver class.

See also: `TBinaryObjectWriter.WriteString` ([350](#)), `TReader.ReadUnicodeString` ([442](#))

4.80.30 TWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant (const VarValue: Variant)`

Visibility: `public`

Description: `WriteVariant` writes `Value`, a simple variant, o the stream. It simply passes the string on to the `WriteVariant` method of the writer driver class.

See also: `TBinaryObjectWriter.WriteVariant` ([351](#)), `TReader.ReadVariant` ([441](#))

4.80.31 TWriter.RootAncestor

Synopsis: Ancestor of root component.

Declaration: `Property RootAncestor : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Ancestor of root component.

4.80.32 TWriter.OnFindAncestor

Synopsis: Event occurring when an ancestor component must be found.

Declaration: `Property OnFindAncestor : TFindAncestorEvent`

Visibility: `public`

Access: `Read,Write`

Description: Event occurring when an ancestor component must be found.

4.80.33 TWriter.OnWriteMethodProperty

Synopsis: Handler from writing method properties.

Declaration: `Property OnWriteMethodProperty : TWriteMethodPropertyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnWriteMethodProperty` can be set by an IDE or some streaming mechanism which handles dummy values for method properties; It can be used to write a real value to the stream which will be interpreted correctly when the stream is read. See `TWriteMethodPropertyEvent` ([286](#)) for a description of the arguments.

See also: `TWriteMethodPropertyEvent` ([286](#)), `TReader.OnSetMethodProperty` ([444](#))

4.80.34 TWriter.OnWriteStringProperty

Synopsis: Event handler for translating strings written to stream.

Declaration: `Property OnWriteStringProperty : TReadWriteStringPropertyEvent`

Visibility: `public`

Access: `Read, Write`

Description: `OnWriteStringProperty` is called whenever a string property is written to the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is written. See `TReadWriteStringPropertyEvent` (278) for a description of the various parameters.

See also: `TReader.OnPropertyNotFound` (443), `TReader.OnSetMethodProperty` (444), `TReadWriteStringPropertyEvent` (278)

4.80.35 TWriter.Driver

Synopsis: Driver used when writing to the stream.

Declaration: `Property Driver : TAbstractObjectWriter`

Visibility: `public`

Access: `Read`

Description: Driver used when writing to the stream.

4.80.36 TWriter.PropertyPath

Synopsis: Path to the property that is currently being written

Declaration: `Property PropertyPath : string`

Visibility: `public`

Access: `Read`

Description: `PropertyPath` is set to the property name of the class currently being written to stream. This is only done when `TPersistent` (428) descendant class properties are written.

Chapter 5

Reference for unit 'clocale'

5.1 Used units

Table 5.1: Used units by unit 'clocale'

Name	Page
System	1339

5.2 Overview

The `clocale` offers no API by itself: it just initializes the internationalization settings of the `sysutils` ([1615](#)) unit with the values provided by the C library found on most Unix or Linux systems that are POSIX compliant.

The `clocale` should simply be included in the `uses` clause of the program, preferably as one of the first units, and the initialization section of the unit will do all the work.

Note that including this unit, links your program to the C library of the system.

It makes no sense to use this unit on a non-POSIX system: Windows, OS/2 or DOS - therefore it should always be between an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}clocale{$endif},
  classes, sysutils;
```

Chapter 6

Reference for unit 'cmem'

6.1 Used units

Table 6.1: Used units by unit 'cmem'

Name	Page
System	1339

6.2 Overview

The `cmem` memory manager sets the system units memory manager to a C-based memory manager: all memory management calls are shunted through to the C memory manager, using `Malloc` ([526](#)), `Free` ([526](#)) and `ReAlloc` ([526](#)). For this reason, the `cmem` unit should be the first unit of the uses clause of the program.

The unit also offers the C memory calls directly as external declarations from the C library, but it is recommended to use the normal FPC routines for this.

Obviously, including this unit links your program to the C library.

Remark Note that specifying the `-gv` command-line option, to enable valgrind debugging info will implicitly add this unit to your program.

6.3 Constants, types and variables

6.3.1 Constants

`LibName = 'c'`

`LibName` is the name of the library that is actually used. On most systems, this is simply "libc.so".

6.4 Procedures and functions

6.4.1 CAlloc

Synopsis: Allocate memory based on item size and count

Declaration: `function CAlloc(unitSize: PtrUInt; UnitCount: PtrUInt) : pointer`

Visibility: default

Description: `CAlloc` allocates memory to hold `UnitCount` units of size `UnitSize` each. The memory is one block of memory. It returns a pointer to the newly allocated memory block.

See also: `Malloc` ([526](#)), `Free` ([526](#)), `Realloc` ([526](#))

6.4.2 Free

Synopsis: Free a previously allocated block

Declaration: `procedure Free(P: pointer)`

Visibility: default

Description: `Free` returns the memory block pointed to by `P` to the system. After `Free` was called, the pointer `P` is no longer valid.

See also: `Malloc` ([526](#)), `ReAlloc` ([526](#))

6.4.3 Malloc

Synopsis: `Malloc` external declaration.

Declaration: `function Malloc(Size: PtrUInt) : Pointer`

Visibility: default

Description: `Malloc` is the external declaration of the C libraries `malloc` call. It accepts a size parameter, and returns a pointer to a memory block of the requested size or `Nil` if no more memory could be allocated.

See also: `Free` ([526](#)), `ReAlloc` ([526](#))

6.4.4 ReAlloc

Synopsis: Reallocates a memory block

Declaration: `function ReAlloc(P: Pointer; Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAlloc` re-allocates a block of memory pointed to by `p`. The new block will have size `Size`, and as much data as was available or as much data as fits is copied from the old to the new location.

See also: `Malloc` ([526](#)), `Free` ([526](#))

Chapter 7

Reference for unit 'collation_de'

7.1 Used units

Table 7.1: Used units by unit 'collation_de'

Name	Page
System	1339

7.2 Overview

The `collation_de` unit registers the German Unicode collation (de). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 8

Reference for unit 'collation_es'

8.1 Used units

Table 8.1: Used units by unit 'collation_es'

Name	Page
System	1339

8.2 Overview

The `collation_es` unit registers the Spanish Unicode collation (de). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 9

Reference for unit 'collation_fr_ca'

9.1 Used units

Table 9.1: Used units by unit 'collation_fr_ca'

Name	Page
System	1339

9.2 Overview

The `collation_fr_ca` unit registers the French Unicode collation (fr). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 10

Reference for unit 'collation_ja'

10.1 Used units

Table 10.1: Used units by unit 'collation_ja'

Name	Page
System	1339

10.2 Overview

The `collation_ja` unit registers the Japanese Unicode collation (ja). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 11

Reference for unit 'collation_ko'

11.1 Used units

Table 11.1: Used units by unit 'collation_ko'

Name	Page
System	1339

11.2 Overview

The `collation_ko` unit registers the Korean Unicode collation (ko). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 12

Reference for unit 'collation_ru'

12.1 Used units

Table 12.1: Used units by unit 'collation_ru'

Name	Page
System	1339

12.2 Overview

The `collation_ru` unit registers the Russian Unicode collation (ru). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 13

Reference for unit 'collation_sv'

13.1 Used units

Table 13.1: Used units by unit 'collation_sv'

Name	Page
System	1339

13.2 Overview

The `collation_sv` unit registers the Swedish Unicode collation (sv). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 14

Reference for unit 'collation_zh'

14.1 Used units

Table 14.1: Used units by unit 'collation_zh'

Name	Page
System	1339

14.2 Overview

The `collation_zh` unit registers the Chinese Unicode collation (zh). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 15

Reference for unit 'cp1250'

15.1 Used units

Table 15.1: Used units by unit 'cp1250'

Name	Page
System	1339

15.2 Overview

The `cp1250` unit registers single-byte codepage 1250. This is necessary to convert single-byte strings using codepage 1250 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 16

Reference for unit 'cp1251'

16.1 Used units

Table 16.1: Used units by unit 'cp1251'

Name	Page
System	1339

16.2 Overview

The `cp1251` unit registers single-byte codepage 1251. This is necessary to convert single-byte strings using codepage 1251 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 17

Reference for unit 'cp1252'

17.1 Used units

Table 17.1: Used units by unit 'cp1252'

Name	Page
System	1339

17.2 Overview

The `cp1252` unit registers single-byte codepage 1252. This is necessary to convert single-byte strings using codepage 1252 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 18

Reference for unit 'cp1253'

18.1 Used units

Table 18.1: Used units by unit 'cp1253'

Name	Page
System	1339

18.2 Overview

The `cp1253` unit registers single-byte codepage 1253. This is necessary to convert single-byte strings using codepage 1253 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 19

Reference for unit 'cp1254'

19.1 Used units

Table 19.1: Used units by unit 'cp1254'

Name	Page
System	1339

19.2 Overview

The `cp1254` unit registers single-byte codepage 1254. This is necessary to convert single-byte strings using codepage 1254 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 20

Reference for unit 'cp1255'

20.1 Used units

Table 20.1: Used units by unit 'cp1255'

Name	Page
System	1339

20.2 Overview

The `cp1255` unit registers single-byte codepage 1255. This is necessary to convert single-byte strings using codepage 1255 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 21

Reference for unit 'cp1256'

21.1 Used units

Table 21.1: Used units by unit 'cp1256'

Name	Page
System	1339

21.2 Overview

The `cp1256` unit registers single-byte codepage 1256. This is necessary to convert single-byte strings using codepage 1256 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 22

Reference for unit 'cp1257'

22.1 Used units

Table 22.1: Used units by unit 'cp1257'

Name	Page
System	1339

22.2 Overview

The `cp1257` unit registers single-byte codepage 1257. This is necessary to convert single-byte strings using codepage 1257 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 23

Reference for unit 'cp1258'

23.1 Used units

Table 23.1: Used units by unit 'cp1258'

Name	Page
System	1339

23.2 Overview

The `cp1258` unit registers single-byte codepage 1258. This is necessary to convert single-byte strings using codepage 1258 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 24

Reference for unit 'cp437'

24.1 Used units

Table 24.1: Used units by unit 'cp437'

Name	Page
System	1339

24.2 Overview

The `cp437` unit registers single-byte codepage 437. This is necessary to convert single-byte strings using codepage 437 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 25

Reference for unit 'cp646'

25.1 Used units

Table 25.1: Used units by unit 'cp646'

Name	Page
System	1339

25.2 Overview

The `cp646` unit registers single-byte codepage 646. This is necessary to convert single-byte strings using codepage 646 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 26

Reference for unit 'cp850'

26.1 Used units

Table 26.1: Used units by unit 'cp850'

Name	Page
System	1339

26.2 Overview

The `cp850` unit registers single-byte codepage 850. This is necessary to convert single-byte strings using codepage 850 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 27

Reference for unit 'cp852'

27.1 Used units

Table 27.1: Used units by unit 'cp852'

Name	Page
System	1339

27.2 Overview

The `cp852` unit registers single-byte codepage 852. This is necessary to convert single-byte strings using codepage 852 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 28

Reference for unit 'cp856'

28.1 Used units

Table 28.1: Used units by unit 'cp856'

Name	Page
System	1339

28.2 Overview

The `cp856` unit registers single-byte codepage 856. This is necessary to convert single-byte strings using codepage 856 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 29

Reference for unit 'cp866'

29.1 Used units

Table 29.1: Used units by unit 'cp866'

Name	Page
System	1339

29.2 Overview

The `cp866` unit registers single-byte codepage 866. This is necessary to convert single-byte strings using codepage 866 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 30

Reference for unit 'cp874'

30.1 Used units

Table 30.1: Used units by unit 'cp874'

Name	Page
System	1339

30.2 Overview

The `cp874` unit registers single-byte codepage 874. This is necessary to convert single-byte strings using codepage 874 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 31

Reference for unit 'cp8859_1'

31.1 Used units

Table 31.1: Used units by unit 'cp8859_1'

Name	Page
System	1339

31.2 Overview

The `cp8859_1` unit registers single-byte codepage 8859-1. This is necessary to convert single-byte strings using codepage 8859-1 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 32

Reference for unit 'cp8859_2'

32.1 Used units

Table 32.1: Used units by unit 'cp8859_2'

Name	Page
System	1339

32.2 Overview

The `cp8859_2` unit registers single-byte codepage 8859-2. This is necessary to convert single-byte strings using codepage 8859-2 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 33

Reference for unit 'cp8859_5'

33.1 Used units

Table 33.1: Used units by unit 'cp8859_5'

Name	Page
System	1339

33.2 Overview

The `cp8859_5` unit registers single-byte codepage 8859-5. This is necessary to convert single-byte strings using codepage 8859-5 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 34

Reference for unit 'cp895'

34.1 Used units

Table 34.1: Used units by unit 'cp895'

Name	Page
System	1339

34.2 Overview

The `cp895` unit registers single-byte codepage 895. This is necessary to convert single-byte strings using codepage 895 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 35

Reference for unit 'cp932'

35.1 Used units

Table 35.1: Used units by unit 'cp932'

Name	Page
System	1339

35.2 Overview

The `cp932` unit registers single-byte codepage 932. This is necessary to convert single-byte strings using codepage 932 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 36

Reference for unit 'cp936'

36.1 Used units

Table 36.1: Used units by unit 'cp936'

Name	Page
System	1339

36.2 Overview

The `cp936` unit registers single-byte codepage 936. This is necessary to convert single-byte strings using codepage 936 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 37

Reference for unit 'cp949'

37.1 Used units

Table 37.1: Used units by unit 'cp949'

Name	Page
System	1339

37.2 Overview

The `cp949` unit registers single-byte codepage 949. This is necessary to convert single-byte strings using codepage 949 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 38

Reference for unit 'cp950'

38.1 Used units

Table 38.1: Used units by unit 'cp950'

Name	Page
System	1339

38.2 Overview

The `cp950` unit registers single-byte codepage 950. This is necessary to convert single-byte strings using codepage 950 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 39

Reference for unit 'cpall'

39.1 Used units

Table 39.1: Used units by unit 'cpall'

Name	Page
cp1250	535
cp1251	536
cp1252	537
cp1253	538
cp1254	539
cp1255	540
cp1256	541
cp1257	542
cp1258	543
cp3021	??
cp437	544
cp646	545
cp737	??
cp775	??
cp850	546
cp852	547
cp855	??
cp856	548
cp857	??
cp860	??
cp861	??
cp862	??
cp863	??
cp864	??
cp865	??
cp866	549
cp869	??
cp874	550
cp8859_1	551
cp8859_10	??
cp8859_11	??
cp8859_13	??
cp8859_14	??
cp8859_15	??
cp8859_16	??
cp8859_2	552
cp8859_3	??
cp8859_4	??
cp8859_5	553

39.2 Overview

The `cpall` unit registers all known single-byte codepages: 1251 ([560](#)), 866 ([560](#)), ISO 8856-5 ([560](#)) (cyrillic), 8859-1 ([560](#)), 8859-2 ([560](#)), 1253 ([560](#)) (greek), 850 ([560](#)), 437 ([560](#)), 1252 ([560](#)), 646 ([560](#)), 874 ([560](#)), 856 ([560](#)), 1250 ([560](#)), 1254 ([560](#)), 1255 ([560](#)), 1256 ([560](#)), 1257 ([560](#)), 1258 ([560](#)), 852 ([560](#)).

This unit does not contain any routines. It simply uses the other units so all corresponding code pages are registered.

Chapter 40

Reference for unit 'Crt'

40.1 Used units

Table 40.1: Used units by unit 'Crt'

Name	Page
System	1339

40.2 Overview

This chapter describes the CRT unit for Free Pascal, under all of Dos, Linux and Windows. The unit was first written for Dos by Florian Klaempfl. The unit was ported to Linux by Mark May and enhanced by Michael Van Canneyt and Peter Vreman. It works on the Linux console, and in xterm and rxvt windows under X-Windows. The functionality for both is the same, except that under Linux the use of an early implementation (versions 0.9.1 and earlier of the compiler) the CRT unit automatically cleared the screen at program startup.

There are some caveats when using the CRT unit:

- Programs using the CRT unit will *not* be usable when input/output is being redirected on the command-line.
- For similar reasons they are not usable as CGI-scripts for use with a webserver.
- The use of the CRT unit and the graph unit may not always be supported.
- The CRT unit is not thread safe.
- On Linux or other Unix OSes, executing other programs that expect special terminal behaviour (using one of the special functions in the Linux unit) will not work. The terminal is set in RAW mode, which will destroy most terminal emulation settings.
- The CRT unit stems from the TP/Dos area. It is designed to work with single-byte character sets, where 1 char = 1 byte. That means that widestrings or UTF-8 encoded (ansi)strings will not work correctly.

40.3 Constants, types and variables

40.3.1 Constants

`Black = 0`

Black color attribute

`Blink = 128`

Blink attribute

`Blue = 1`

Blue color attribute

`Brown = 6`

Brown color attribute

`BW40 = 0`

40 columns black and white screen mode.

`BW80 = 2`

80 columns black and white screen mode.

`C40 = CO40`

40 columns color screen mode.

`C80 = CO80`

80 columns color screen mode.

`CO40 = 1`

40 columns color screen mode.

`CO80 = 3`

80 columns color screen mode.

`ConsoleMaxX = 1024`

`ConsoleMaxY = 1024`

`Cyan = 3`

Cyan color attribute

DarkGray = 8

Dark gray color attribute

Flushing = False

Font8x8 = 256

Internal ROM font mode

Green = 2

Green color attribute

LightBlue = 9

Light Blue color attribute

LightCyan = 11

Light cyan color attribute

LightGray = 7

Light gray color attribute

LightGreen = 10

Light green color attribute

LightMagenta = 13

Light magenta color attribute

LightRed = 12

Light red color attribute

Magenta = 5

Magenta color attribute

Mono = 7

Monochrome screen mode (hercules screens)

Red = 4

Red color attribute

```
ScreenHeight : LongInt = 25
```

Current screen height.

```
ScreenWidth : LongInt = 80
```

Current screen width

```
White = 15
```

White color attribute

```
Yellow = 14
```

Yellow color attribute

40.3.2 Types

```
tcrtcoord = 1..255
```

`tcrtcoord` is a subrange type for denoting CRT coordinates. It supports coordinates ranging from 1 to 255. Using this type together with range-checking turned on can be used to debug CRT code.

40.3.3 Variables

```
CheckBreak : Boolean
```

Check for CTRL-Break keystroke. Not used.

```
CheckEOF : Boolean
```

Check for EOF on standard input. Not used.

```
CheckSnow : Boolean
```

Check snow on CGA screens. Not used.

```
ConsoleBuf : PConsoleBuf
```

```
DirectVideo : Boolean
```

The `DirectVideo` variable controls the writing to the screen. If it is `True`, the cursor is set via direct port access. If `False`, then the BIOS is used. This is defined under dos only.

```
LastMode : Word = 3
```

The `Lastmode` variable tells you which mode was last selected for the screen. It is defined on DOS only.

`TextAttr : Byte = $07`

The `TextAttr` variable controls the attributes with which characters are written to screen.

`WindMax : Word = $184f`

The upper byte of `WindMax` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMaxX` and `WindMaxY` instead.

`WindMaxX : DWord`

X coordinate of lower right corner of the defined window

`WindMaxY : DWord`

Y coordinate of lower right corner of the defined window

`WindMin : Word = $0`

The upper byte of `WindMin` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMinX` and `WindMinY` instead.

`WindMinX : DWord`

X coordinate of upper left corner of the defined window

`WindMinY : DWord`

Y coordinate of upper left corner of the defined window

40.4 Procedures and functions

40.4.1 AssignCrt

Synopsis: Assign file to CRT.

Declaration: `procedure AssignCrt (var F: Text)`

Visibility: default

Description: `AssignCrt` Assigns a file `F` to the console. Everything written to the file `F` goes to the console instead. If the console contains a window, everything is written to the window instead.

Errors: None.

See also: `Window` ([577](#))

Listing: `./examples/crtex/ex1.pp`

```

Program Example1;
uses Crt;

{ Program to demonstrate the AssignCrt function. }

var
    F : Text;
begin
    AssignCrt(F);
    Rewrite(F); { Don't forget to open for output! }
    WriteLn(F, 'This is written to the Assigned File');
    Close(F);
end.

```

40.4.2 ClrEol

Synopsis: Clear from cursor position till end of line.

Declaration: `procedure ClrEol`

Visibility: default

Description: `ClrEol` clears the current line, starting from the cursor position, to the end of the window. The cursor doesn't move

Errors: None.

See also: `DelLine` ([569](#)), `InsLine` ([571](#)), `ClrScr` ([568](#))

Listing: `./examples/crtex/ex9.pp`

```

Program Example9;
uses Crt;

{ Program to demonstrate the ClrEol function. }
var
    I, J : integer;

begin
    For I:=1 to 15 do
        For J:=1 to 80 do
            begin
                gotoxy(j, i);
                Write(j mod 10);
            end;
    Window(5,5,75,12);
    Write('This line will be cleared from',
        ' here till the right of the window');
    GotoXY(27,WhereY);
    ReadKey;
    ClrEol;
    WriteLn;
end.

```

40.4.3 ClrScr

Synopsis: Clear current window.

Declaration: `procedure ClrScr`

Visibility: default

Description: `ClrScr` clears the current window (using the current colors), and sets the cursor in the top left corner of the current window.

Errors: None.

See also: Window ([577](#))

Listing: `./examples/crtex/ex8.pp`

```
Program Example8;  
uses Crt;  
  
  { Program to demonstrate the ClrScr function. }  
  
begin  
  WriteLn('Press any key to clear the screen');  
  ReadKey;  
  ClrScr;  
  WriteLn('Have fun with the cleared screen');  
end.
```

40.4.4 cursorbig

Synopsis: Show big cursor

Declaration: `procedure cursorbig`

Visibility: default

Description: `CursorBig` makes the cursor a big rectangle. Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([569](#)), `CursorOff` ([568](#))

40.4.5 cursoroff

Synopsis: Hide cursor

Declaration: `procedure cursoroff`

Visibility: default

Description: `CursorOff` switches the cursor off (i.e. the cursor is no longer visible). Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([569](#)), `CursorBig` ([568](#))

40.4.6 cursoron

Synopsis: Display cursor

Declaration: `procedure cursoron`

Visibility: default

Description: `CursorOn` switches the cursor on. Not implemented on unixes.

Errors: None.

See also: `CursorBig` ([568](#)), `CursorOff` ([568](#))

40.4.7 Delay

Synopsis: Delay program execution.

Declaration: `procedure Delay (MS: Word)`

Visibility: default

Description: `Delay` waits a specified number of milliseconds. The number of specified seconds is an approximation, and may be off a lot, if system load is high.

Errors: None

See also: `Sound` ([574](#)), `NoSound` ([573](#))

Listing: `./examples/crtex/ex15.pp`

```

Program Example15;
uses Crt;

{ Program to demonstrate the Delay function. }
var
  i : longint;
begin
  WriteLn( 'Counting Down' );
  for i:=10 downto 1 do
    begin
      WriteLn(i);
      Delay(1000); { Wait one second }
    end;
  WriteLn( 'BOOM!!! ' );
end.

```

40.4.8 DelLine

Synopsis: Delete line at cursor position.

Declaration: `procedure DelLine`

Visibility: default

Description: `DelLine` removes the current line. Lines following the current line are scrolled 1 line up, and an empty line is inserted at the bottom of the current window. The cursor doesn't move.

Errors: None.

See also: [ClrEol \(567\)](#), [InsLine \(571\)](#), [ClrScr \(568\)](#)

Listing: ./examples/crtex/ex11.pp

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn('Line 1');
  WriteLn('Line 2');
  WriteLn('Line 2');
  WriteLn('Line 3');
  WriteLn;
  WriteLn('Oops, Line 2 is listed twice,',
    ' let''s delete the line at the cursor position');
  GotoXY(1,3);
  ReadKey;
  DelLine;
  GotoXY(1,10);
end.

```

40.4.9 GotoXY

Synopsis: Set cursor position on screen.

Declaration: `procedure GotoXY(X: tcoord; Y: tcoord)`

Visibility: default

Description: `GotoXY` positions the cursor at (X, Y), X in horizontal, Y in vertical direction relative to the origin of the current window. The origin is located at (1, 1), the upper-left corner of the window.

Errors: None.

See also: [WhereX \(576\)](#), [WhereY \(576\)](#), [Window \(577\)](#)

Listing: ./examples/crtex/ex6.pp

```

Program Example6;
uses Crt;

{ Program to demonstrate the GotoXY function. }

begin
  ClrScr;
  GotoXY(10,10);
  Write('10,10');
  GotoXY(70,20);
  Write('70,20');
  GotoXY(1,22);
end.

```

40.4.10 HighVideo

Synopsis: Switch to highlighted text mode

Declaration: `procedure HighVideo`

Visibility: default

Description: `HighVideo` switches the output to highlighted text. (It sets the high intensity bit of the video attribute)

Errors: None.

See also: `TextColor` ([575](#)), `TextBackground` ([574](#)), `LowVideo` ([572](#)), `NormVideo` ([573](#))

Listing: `./examples/crtex/ex14.pp`

```

Program Example14;
uses Crt;

{ Program to demonstrate the LowVideo, HighVideo, NormVideo functions. }

begin
  LowVideo;
  WriteLn('This is written with LowVideo');
  HighVideo;
  WriteLn('This is written with HighVideo');
  NormVideo;
  WriteLn('This is written with NormVideo');
end.

```

40.4.11 InsLine

Synopsis: Insert an empty line at cursor position

Declaration: `procedure InsLine`

Visibility: default

Description: `InsLine` inserts an empty line at the current cursor position. Lines following the current line are scrolled 1 line down, causing the last line to disappear from the window. The cursor doesn't move.

Errors: None.

See also: `ClrEol` ([567](#)), `DelLine` ([569](#)), `ClrScr` ([568](#))

Listing: `./examples/crtex/ex10.pp`

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn('Line 1');
  WriteLn('Line 3');
  WriteLn;

```

```

    WriteLn('Oops, forgot Line 2, let''s insert at the cursor postion');
    GotoXY(1,3);
    ReadKey;
    InsLine;
    Write('Line 2');
    GotoXY(1,10);
end.

```

40.4.12 KeyPressed

Synopsis: Check if there is a keypress in the keybuffer

Declaration: `function KeyPressed : Boolean`

Visibility: default

Description: `KeyPressed` scans the keyboard buffer and sees if a key has been pressed. If this is the case, `True` is returned. If not, `False` is returned. The `Shift`, `Alt`, `Ctrl` keys are not reported. The key is not removed from the buffer, and can hence still be read after the `KeyPressed` function has been called.

Errors: None.

See also: `ReadKey` ([573](#))

Listing: `./examples/crtex/ex2.pp`

```

Program Example2;
uses Crt;

{ Program to demonstrate the KeyPressed function. }

begin
    WriteLn('Waiting until a key is pressed');
    repeat
        until KeyPressed;
    { The key is not Read,
      so it should also be outputted at the commandline}
end.

```

40.4.13 LowVideo

Synopsis: Switch to low intensity colors.

Declaration: `procedure LowVideo`

Visibility: default

Description: `LowVideo` switches the output to non-highlighted text. (It clears the high intensity bit of the video attribute)

For an example, see `HighVideo` ([571](#))

Errors: None.

See also: `TextColor` ([575](#)), `TextBackground` ([574](#)), `HighVideo` ([571](#)), `NormVideo` ([573](#))

40.4.14 NormVideo

Synopsis: Return to normal (startup) modus

Declaration: `procedure NormVideo`

Visibility: default

Description: `NormVideo` switches the output to the defaults, read at startup. (The defaults are read from the cursor position at startup)

For an example, see `HighVideo` (571)

Errors: None.

See also: `TextColor` (575), `TextBackground` (574), `LowVideo` (572), `HighVideo` (571)

40.4.15 NoSound

Synopsis: Stop system speaker

Declaration: `procedure NoSound`

Visibility: default

Description: `NoSound` stops the speaker sound. This call is not supported on all operating systems.

Errors: None.

See also: `Sound` (574)

Listing: `./examples/crtex/ex16.pp`

```

Program Example16;
uses Crt;

{ Program to demonstrate the Sound and NoSound function. }

var
  i : longint;
begin
  WriteLn('You will hear some tones from your speaker');
  i:=0;
  while (i<15000) do
    begin
      inc(i,500);
      Sound(i);
      Delay(100);
    end;
  WriteLn('Quiet now!');
  NoSound; {Stop noise}
end.
```

40.4.16 ReadKey

Synopsis: Read key from keybuffer

Declaration: `function ReadKey : Char`

Visibility: default

Description: `ReadKey` reads 1 key from the keyboard buffer, and returns this. If an extended or function key has been pressed, then the zero ASCII code is returned. You can then read the scan code of the key with a second `ReadKey` call.

Key mappings under Linux can cause the wrong key to be reported by `ReadKey`, so caution is needed when using `ReadKey`.

Errors: None.

See also: `KeyPressed` ([572](#))

Listing: `./examples/crtex/ex3.pp`

```

Program Example3;
uses Crt;

{ Program to demonstrate the ReadKey function. }

var
  ch : char;
begin
  writeln( 'Press Left/Right , Esc=Quit ' );
  repeat
    ch:=ReadKey;
    case ch of
      #0 : begin
        ch:=ReadKey; {Read ScanCode}
        case ch of
          #75 : WriteLn( 'Left ' );
          #77 : WriteLn( 'Right ' );
        end;
      end;
      #27 : WriteLn( 'ESC' );
    end;
  until ch=#27 {Esc}
end.
```

40.4.17 Sound

Synopsis: Sound system speaker

Declaration: `procedure Sound(Hz: Word)`

Visibility: default

Description: `Sound` sounds the speaker at a frequency of `hz`. Under Windows, a system sound is played and the frequency parameter is ignored. On other operating systems, this routine may not be implemented.

Errors: None.

See also: `NoSound` ([573](#))

40.4.18 TextBackground

Synopsis: Set text background

Declaration: `procedure TextBackground(Color: Byte)`

Visibility: default

Description: `TextBackground` sets the background color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: `TextColor` (575), `HighVideo` (571), `LowVideo` (572), `NormVideo` (573)

Listing: `./examples/crtex/ex13.pp`

```
Program Example13;
uses Crt;

{ Program to demonstrate the TextBackground function. }

begin
  TextColor(White);
  WriteLn('This is written in with the default background color');
  TextBackground(Green);
  WriteLn('This is written in with a Green background');
  TextBackground(Brown);
  WriteLn('This is written in with a Brown background');
  TextBackground(Black);
  WriteLn('Back with a black background');
end.
```

40.4.19 TextColor

Synopsis: Set text color

Declaration: `procedure TextColor(Color: Byte)`

Visibility: default

Description: `TextColor` sets the foreground color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: `TextBackground` (574), `HighVideo` (571), `LowVideo` (572), `NormVideo` (573)

Listing: `./examples/crtex/ex12.pp`

```
Program Example12;
uses Crt;

{ Program to demonstrate the TextColor function. }

begin
  WriteLn('This is written in the default color');
  TextColor(Red);
  WriteLn('This is written in Red');
  TextColor(White);
  WriteLn('This is written in White');
  TextColor(LightBlue);
  WriteLn('This is written in Light Blue');
end.
```

40.4.20 TextMode

Synopsis: Set screen mode.

Declaration: `procedure TextMode (Mode: Word)`

Visibility: default

Description: `TextMode` sets the textmode of the screen (i.e. the number of lines and columns of the screen). The lower byte is use to set the VGA text mode.

This procedure is only implemented on dos.

Errors: None.

See also: `Window` ([577](#))

40.4.21 WhereX

Synopsis: Return X (horizontal) cursor position

Declaration: `function WhereX : tcrtcoord`

Visibility: default

Description: `WhereX` returns the current X-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: `GotoXY` ([570](#)), `WhereY` ([576](#)), `Window` ([577](#))

Listing: `./examples/crtex/ex7.pp`

```

Program Example7;
uses Crt;

{ Program to demonstrate the WhereX and WhereY functions. }

begin
  WriteLn ( 'Cursor postion: X= ',WhereX, ' Y= ',WhereY );
end.
```

40.4.22 WhereY

Synopsis: Return Y (vertical) cursor position

Declaration: `function WhereY : tcrtcoord`

Visibility: default

Description: `WhereY` returns the current Y-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: `GotoXY` ([570](#)), `WhereX` ([576](#)), `Window` ([577](#))

Listing: `./examples/crtex/ex7.pp`

```

Program Example7;
uses Crt;

{ Program to demonstrate the WhereX and WhereY functions. }

begin
  WriteLn('Cursor position: X=',WhereX,' Y=',WhereY);
end.

```

40.4.23 Window

Synopsis: Create new window on screen.

Declaration: `procedure Window(X1: Byte; Y1: Byte; X2: Byte; Y2: Byte)`

Visibility: default

Description: `Window` creates a window on the screen, to which output will be sent. (X1, Y1) are the coordinates of the upper left corner of the window, (X2, Y2) are the coordinates of the bottom right corner of the window. These coordinates are relative to the entire screen, with the top left corner equal to (1, 1). Further coordinate operations, except for the next `Window` call, are relative to the window's top left corner.

Errors: None.

See also: [GotoXY \(570\)](#), [WhereX \(576\)](#), [WhereY \(576\)](#), [ClrScr \(568\)](#)

Listing: `./examples/crtex/ex5.pp`

```

Program Example5;
uses Crt;

{ Program to demonstrate the Window function. }

begin
  ClrScr;
  WriteLn('Creating a window from 30,10 to 50,20');
  Window(30,10,50,20);
  WriteLn('We are now writing in this small window we just created, we '+
    'can''t get outside it when writing long lines like this one');
  Write('Press any key to clear the window');
  ReadKey;
  ClrScr;
  Write('The window is cleared, press any key to restore to fullscreen');
  ReadKey;
  { Full Screen is 80x25 }
  Window(1,1,80,25);
  Clrscr;
  WriteLn('Back in Full Screen');
end.

```

40.5 TCharAttr

`TCharAttr` = packed record

```
  ch : Char;  
  attr : Byte;  
end
```

Chapter 41

Reference for unit 'cthreads'

41.1 Used units

Table 41.1: Used units by unit 'cthreads'

Name	Page
System	1339

41.2 Overview

The `CThreads` unit initializes the system unit's thread management routines with an implementation based on the POSIX thread managing routines in the C library. This assures that C libraries that are thread-aware still work if they are linked to by a FPC program.

It doesn't offer any API by itself: the initialization section of the unit just initializes the `ThreadManager` record in the `System` ([1339](#)) unit. This is done using the `SetCThreadManager` ([580](#)) call

The `cthreads` unit simply needs to be included in the `uses` clause of the program, preferably the very first unit, and the initialization section of the unit will do all the work.

Note that including this unit links your program to the C library of the system.

It makes no sense to use this unit on a non-POSIX system: Windows, OS/2 or DOS, therefor it should always be between an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}cthreads{$endif},
  classes, sysutils;
```

The Lazarus IDE inserts this conditional automatically for each new started program.

41.3 Procedures and functions

41.3.1 SetCThreadManager

Synopsis: Sets the thread manager to the C thread manager

Declaration: `procedure SetCThreadManager`

Visibility: `default`

Description: `SetCThreadManager` actually sets the thread manager to the C thread manager. It can be called to re-set the thread manager if the thread manager was set to some other thread manager during the life-time of the program.

Chapter 42

Reference for unit 'ctypes'

42.1 Used units

Table 42.1: Used units by unit 'ctypes'

Name	Page
System	1339
unixtype	2127

42.2 Overview

The `ctypes` unit contains the definitions of commonly found C types. It can be used when interfaces to C libraries need to be defined. The types here are correct on all platforms, 32 or 64 bit.

The main advantage of using this file is to make sure that all C header import units use the same definitions for basic C types.

The `h2pas` program can include the `ctypes` unit automatically in the units it generates. The `-C` command-line switch can be used for this.

42.3 Constants, types and variables

42.3.1 Types

```
cbool = UnixType.cbool
```

C boolean (longbool)

```
cchar = UnixType.cchar
```

C character type (No signedness specification, 8 bit integer)

```
cdouble = UnixType.cdouble
```

Double precision floating point type (double)

`cfloat = UnixType.cfloat`

Single precision floating point type (single)

`cint = UnixType.cint`

C integer (commonly 32 bit)

`cint16 = UnixType.cint16`

16-bit signed integer.

`cint32 = UnixType.cint32`

32-bit signed integer (commonly: int)

`cint64 = UnixType.cint64`

64-bit integer

`cint8 = UnixType.cint8`

8-bit signed integer

`clong = UnixType.clong`

long integer (32/64 bit, depending on CPU register size)

`clongdouble = Double`

Long precision floating point type (extended/double, depending on CPU)

`clonglong = UnixType.clonglong`

Long (64-bit) integer

`coff_t = UnixType.TOff`

Generic type to indicate offset

`cschar = UnixType.cschar`

C signed character type (8 bit signed integer)

`cshort = UnixType.cshort`

Short integer (16 bit)

`csigned = UnixType.csigned`

Signed integer (commonly 32 bit)

`csint = UnixType.csint`

Signed integer (commonly 32 bit)

`csize_t = UnixType.size_t`

Generic type to contain a size of all kinds of structures

`cslong = UnixType.cslong`

Signed long integer (32/64 bit, depending on CPU register size)

`cslonglong = UnixType.cslonglong`

Signed long (64-bit) integer

`csshort = UnixType.csshort`

Short signed integer (16 bit)

`cuchar = UnixType.cuchar`

C unsigned character type (8 bit unsigned integer).

`cuint = UnixType.cuint`

Unsigned integer (commonly 32 bit)

`cuint16 = UnixType.cuint16`

16-bit unsigned integer.

`cuint32 = UnixType.cuint32`

32-bit unsigned integer

`cuint64 = UnixType.cuint64`

Unsigned 64-bit integer

`cuint8 = UnixType.cuint8`

8-bit unsigned integer

`culong = UnixType.culong`

Unsigned long integer (32/64 bit, depending on CPU register size)

`culonglong = UnixType.culonglong`

Unsigned long (64-bit) integer

`cunsigned = UnixType.cunsigned`

Unsigned integer (commonly 32 bit)

`cushort = UnixType.cushort`

Short unsigned integer (16 bit)

`pcbool = UnixType.pcbbool`

Pointer to `cbool` (581) type.

`pcchar = UnixType.pcchar`

Pointer to `cchar` (581) type.

`pcdouble = UnixType.pcdouble`

Pointer to `cdouble` (581) type.

`pcfloat = UnixType.pcfloating`

Pointer to `cfloat` (582) type.

`pcint = UnixType.pcint`

Pointer to `cint` (582) type.

`pcint16 = UnixType.pcint16`

Pointer to `cint16` (582) type.

`pcint32 = UnixType.pcint32`

Pointer to `cint32` (582) type.

`pcint64 = UnixType.pcint64`

Pointer to `cint64` (582) type.

`pcint8 = UnixType.pcint8`

Pointer to `cint8` (582) type.

`pclong = UnixType.pclong`

Pointer to `clong` (582) type.

`pclongdouble = ^clongdouble`

Pointer to `clongdouble` (582) type.

`pclonglong = UnixType.pclonglong`

Pointer to `clonglong` (582) type.

`pcschar = UnixType.pcschar`

Pointer to `cschar` (582) type.

`pcshort = UnixType.pcshort`

Pointer to `cshort` (582) type.

`pcsigned = UnixType.pcsigned`

Pointer to `csigned` (582) type.

`pcsint = UnixType.pcsint`

Pointer to `csint` (583) type.

`pcsize_t = UnixType.psize_t`

Pointer to generic size type

`pcslong = UnixType.pcslong`

Pointer to `clong` (583) type.

`pcslonglong = UnixType.pcslonglong`

Pointer to `cslonglong` (583) type.

`pcsshort = UnixType.pcsshort`

Pointer to `csshort` (583) type.

`pcuchar = UnixType.pcuchar`

Pointer to `cuchar` (583) type.

`pcuint = UnixType.pcuint`

Pointer to `cuint` (583) type.

`pcuint16 = UnixType.pcuint16`

Pointer to `cuint16` (583) type.

`pcuint32 = UnixType.pcuint32`

Pointer to `cuint32` (583) type.

`pcuint64 = UnixType.pcuint64`

Pointer to `cuint64` (583) type.

`pcuint8 = UnixType.pcuint8`

Pointer to `cuint8` (583) type.

`pculong = UnixType.pculong`

Pointer to `culong` (583) type.

`pculonglong = UnixType.pculonglong`

Pointer to `culonglong` (583) type.

`pcunsigned = UnixType.punsigned`

Pointer to `cunsigned` (584) type.

`pcushort = UnixType.pcushort`

Pointer to `cushort` (584) type.

Chapter 43

Reference for unit 'cwstring'

43.1 Used units

Table 43.1: Used units by unit 'cwstring'

Name	Page
System	1339

43.2 Overview

The `cstring` unit offers no API by itself: it just initializes the widestring manager record of the system ([1339](#)) unit with an implementation that uses collation and conversion routines which are provided by the C library found on most Unix or Linux systems that are POSIX compliant.

The `cstring` should simply be included in the `uses` clause of the program, preferably as one of the first units, and the initialization section of the unit will do all the work.

Note that including this unit links your program to the C library of the system.

It makes no sense to use this unit on a non-POSIX system like Windows, OS/2 or DOS. Therefore it should always be enclosed with an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}cstring, {$endif}
  classes, sysutils;
```

43.3 Procedures and functions

43.3.1 SetCWidestringManager

Synopsis: Set the Widestring manager of the system unit to the C version

Declaration: `procedure SetCWidestringManager`

Visibility: `default`

Description: `SetCWideStringManager` actually sets the widestring manager record of the system unit. It is called automatically by the initialization section of the unit.

Chapter 44

Reference for unit 'DateUtils'

44.1 Used units

Table 44.1: Used units by unit 'DateUtils'

Name	Page
Math	986
System	1339
sysutils	1615

44.2 Overview

`DateUtils` contains a large number of date/time manipulation routines, all based on the `TDateTime` type. There are routines for date/time math, for comparing dates and times, for composing dates and decomposing dates in their constituent parts.

44.3 Constants, types and variables

44.3.1 Constants

`ApproxDaysPerMonth : Double = 30.4375`

Average number of days in a month, measured over a year. Used in `MonthsBetween` ([640](#)).

`ApproxDaysPerYear : Double = 365.25`

Average number of days in a year, measured over 4 years. Used in `YearsBetween` ([684](#)).

`DayFriday = 5`

ISO day number for Friday

`DayMonday = 1`

ISO day number for Monday

DaySaturday = 6

ISO day number for Saturday

DaysPerWeek = 7

Number of days in a week.

DaysPerYear : Array[Boolean] of Word = (365, 366)

Array with number of days in a year. The Boolean index indicates whether it is a leap year or not.

DaySunday = 7

ISO day number for Sunday

DayThursday = 4

ISO day number for Thursday

DayTuesday = 2

ISO day number for Tuesday

DayWednesday = 3

ISO day number for Wednesday

MonthApril = 4

ISO month number for April.

MonthAugust = 8

ISO month number for August.

MonthDecember = 12

ISO month number for December

MonthFebruary = 2

ISO month number for february.

MonthJanuary = 1

ISO month number for january.

MonthJuly = 7

ISO month number for July.

MonthJune = 6

ISO month number for June.

MonthMarch = 3

ISO month number for March.

MonthMay = 5

ISO month number for May.

MonthNovember = 11

ISO month number for November.

MonthOctober = 10

ISO month number for October.

MonthSeptember = 9

ISO month number for September.

MonthsPerYear = 12

Number of months in a year

OneHour = TDateTime(1) / HoursPerDay

One hour as a fraction of a day (suitable for TDateTime)

OneMillisecond = TDateTime(1) / MSecsPerDay

One millisecond as a fraction of a day (suitable for TDateTime)

OneMinute = TDateTime(1) / MinsPerDay

One minute as a fraction of a day (suitable for TDateTime)

OneSecond = TDateTime(1) / SecsPerDay

One second as a fraction of a day (suitable for TDateTime)

RecodeLeaveFieldAsIs = High(Word)

Bitmask deciding what to do with each TDateTime field in recode routines

WeeksPerFortnight = 2

Number of weeks in fortnight

`YearsPerCentury = 100`

Number of years in a century

`YearsPerDecade = 10`

Number of years in a decade

`YearsPerMillennium = 1000`

Number of years in a millennium

44.4 Procedures and functions

44.4.1 CompareDate

Synopsis: Compare 2 dates, disregarding the time of day

Declaration: `function CompareDate(const A: TDateTime; const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: `CompareDate` compares the date parts of two timestamps A and B and returns the following results:

< 0 if the day part of A is earlier than the day part of B.

0 if A and B are the on same day (times may differ) .

> 0 if the day part of A is later than the day part of B.

See also: `CompareTime` ([594](#)), `CompareDateTime` ([593](#)), `SameDate` ([649](#)), `SameTime` ([651](#)), `SameDateTime` ([650](#))

Listing: `./examples/datutex/ex99.pp`

Program `Example99;`

{ This program demonstrates the CompareDate function }

Uses `SysUtils, DateUtils;`

Const

`Fmt = 'dddd dd mmm yyyy';`

Procedure `Test(D1,D2 : TDateTime);`

Var

`Cmp : Integer;`

begin

`Write(FormatDateTime(Fmt,D1), ' is ');`

`Cmp:=CompareDate(D1,D2);`

`If Cmp<0 then`

```

        write('earlier than ')
    else if Cmp>0 then
        Write('later than ')
    else
        Write('equal to ');
    WriteLn(FormatDateTime(Fmt,D2));
end;

Var
    D,N : TDateTime;

Begin
    D:=Today;
    N:=Now;
    Test(D,D);
    Test(N,N);
    Test(D+1,D);
    Test(D-1,D);
    Test(D+OneSecond,D);
    Test(D-OneSecond,D);
    Test(N+OneSecond,N);
    Test(N-OneSecond,N);
End.

```

44.4.2 CompareDateTime

Synopsis: Compare 2 dates, taking into account the time of day

Declaration: `function CompareDateTime(const A: TDateTime; const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: CompareDateTime compares two timestamps A and B and returns the following results:

< 0 if A is earlier in date/time than B.
 0 if A and B are the same date/time .
 > 0 if A is later in date/time than B.

See also: CompareTime (594), CompareDate (592), SameDate (649), SameTime (651), SameDateTime (650)

Listing: ./examples/datutex/ex98.pp

Program Example98;

{ This program demonstrates the CompareDateTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

Var

Cmp : Integer;

```

begin
  Write(FormatDateTime(Fmt,D1), ' is ');
  Cmp:=CompareDateTime(D1,D2);
  If Cmp<0 then
    write('earlier than ')
  else if Cmp>0 then
    Write('later than ')
  else
    Write('equal to ');
  WriteIn(FormatDateTime(Fmt,D2));
end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(D+1,D);
  Test(D-1,D);
  Test(D+OneSecond,D);
  Test(D-OneSecond,D);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

44.4.3 CompareTime

Synopsis: Compares two times of the day, disregarding the date part.

Declaration: `function CompareTime(const A: TDateTime; const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: `CompareTime` compares the time parts of two timestamps A and B and returns the following results:

< 0 if the time part of A is earlier than the time part of B.

0 if A and B have the same time part (dates may differ) .

> 0 if the time part of A is later than the time part of B.

See also: `CompareDateTime` (593), `CompareDate` (592), `SameDate` (649), `SameTime` (651), `SameDateTime` (650)

Listing: ./examples/datutex/ex100.pp

Program Example100;

{ This program demonstrates the CompareTime function }

Uses SysUtils, DateUtils;

```

Const
  Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

Var
  Cmp : Integer;

begin
  Write(FormatDateTime(Fmt,D1), ' has ');
  Cmp:=CompareDateTime(D1,D2);
  If Cmp<0 then
    write('earlier time than ')
  else if Cmp>0 then
    Write('later time than ')
  else
    Write('equal time with ');
  WriteLn(FormatDateTime(Fmt,D2));
end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(N+1,N);
  Test(N-1,N);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

44.4.4 DateInRange

Synopsis: Checks whether a date value is in a given rang

Declaration: `function DateInRange(ADate: TDate; AStartDate: TDate; AEndDate: TDate; AInclusive: Boolean) : Boolean`

Visibility: default

Description: `DateInRange` checks whether the value `ADate` lies between `AStartDate` and `AEndDate`, and returns `True` if it is. When `AINclusive` is `True` (the default), then the limits are included. When `AINclusive` is `False`, the limits are excluded. Only the date part of the 3 parameters is considered.

Errors: The `AStartDate` value must be before `AEndDate`, but no check is performed.

See also: `TimeInRange` ([661](#)), `DateTimeInRange` ([596](#))

44.4.5 DateOf

Synopsis: Extract the date part from a `TDateTime` indication.

Declaration: `function DateOf(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `DateOf` extracts the date part from `AValue` and returns the result.

Since the `TDateTime` is actually a double with the date part encoded in the integer part, this operation corresponds to a call to `Trunc`.

See also: `TimeOf` ([661](#)), `YearOf` ([684](#)), `MonthOf` ([639](#)), `DayOf` ([598](#)), `HourOf` ([613](#)), `MinuteOf` ([635](#)), `SecondOf` ([652](#)), `MilliSecondOf` ([631](#))

Listing: `./examples/datutex/ex1.pp`

Program `Example1`;

{ This program demonstrates the DateOf function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn('Date is: ', DateTimeToStr(DateOf(Now)));`
End.

44.4.6 DateTimeInRange

Synopsis: Checks whether a date/time value is in a given range

Declaration: `function DateTimeInRange(ADateTime: TDateTime;
 AStartDateTime: TDateTime;
 AEndDateTime: TDateTime; aInclusive: Boolean)
 : Boolean`

Visibility: default

Description: `DateTimeInRange` checks whether the value `ADateTime` lies between `AStartDateTime` and `AEndDateTime`, and returns `True` if it is. When `AInclusive` is `True` (the default), then the limits are included. When `AInclusive` is `False`, the limits are excluded.

Errors: The `AStartDateTime` value must be before `AEndDateTime`, but no check is performed.

See also: `DateInRange` ([595](#)), `TimeInRange` ([661](#))

44.4.7 DateTimeToDosDateTime

Synopsis: Convert `TDateTime` format to DOS date/time format

Declaration: `function DateTimeToDosDateTime(const AValue: TDateTime) : LongInt`

Visibility: default

Description: `DateTimeToDosDatetime` takes `Value`, a `TDateTime` formatted timestamp, and recodes it to a MS-DOS encoded date/time value. This is a longint with the date/time encoded in the bits as:

0-4Seconds divided by 2

5-10Minutes

11-15Hours

16-20Day

21-24Month

25-31Years since 1980

See also: `DosDateTimeToDateTime` ([606](#))

44.4.8 DateTimeToJulianDate

Synopsis: Converts a `TDateTime` value to a Julian date representation

Declaration: `function DateTimeToJulianDate(const AValue: TDateTime) : Double`

Visibility: default

Description: `DateTimeToJulianDate` converts the `AValue` date/time indication to a Julian (as opposed to Gregorian) date.

See also: `JulianDateToDateTime` ([630](#)), `TryJulianDateToDateTime` ([669](#)), `DateTimeToModifiedJulianDate` ([597](#)), `TryModifiedJulianDateToDateTime` ([669](#))

44.4.9 DateTimeToMac

Synopsis: Convert a `TDateTime` timestamp to a Mac timestamp

Declaration: `function DateTimeToMac(const AValue: TDateTime) : Int64`

Visibility: default

Description: `DateTimeToMac` converts the `TDateTime` value `AValue` to a valid Mac timestamp indication and returns the result.

Errors: None.

See also: `UnixTimeStampToMac` ([671](#)), `MacToDateTime` ([630](#)), `MacTimeStampToUnix` ([630](#))

44.4.10 DateTimeToModifiedJulianDate

Synopsis: Convert a `TDateTime` value to a modified Julian date representation

Declaration: `function DateTimeToModifiedJulianDate(const AValue: TDateTime) : Double`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: `DateTimeToJulianDate` ([597](#)), `JulianDateToDateTime` ([630](#)), `TryJulianDateToDateTime` ([669](#)), `TryModifiedJulianDateToDateTime` ([669](#))

44.4.11 DateTimeToUnix

Synopsis: Convert a `TDateTime` value to Unix epoch time

Declaration: `function DateTimeToUnix(const AValue: TDateTime; AInputIsUTC: Boolean) : Int64`

Visibility: default

Description: `DateTimeToUnix` converts a `TDateTime` value to a epoch time (i.e. the number of seconds elapsed since 1/1/1970).

See also: `UnixToDateTime` ([671](#))

44.4.12 DateToISO8601

Synopsis: Converts a `TDateTime` value to ISO 8601 date/time format

Declaration: `function DateToISO8601(const ADate: TDateTime; AInputIsUTC: Boolean) : string`

Visibility: default

Description: `DateToISO8601` is a `String` function used to convert the `TDateTime` value in `ADate` to ISO 8601 date/time notation.

`ADate` contains the native `TDateTime` value converted in the function.

`AInputIsUTC` indicates if the value in `ADate` represents a date/time value for the UTC time zone. When `AInputIsUTC` contains `True`, the 'Z' (Zulu time) time zone designation is used in the converted ISO 8601 value. Otherwise, the time zone is expressed as a positive or negative number of hours and minutes (such as "-04:00") in the return value.

`DateToISO8601` calls `GetLocalTimeOffset` to determine the time zone offset in use on the local computer. The integer offset is used to adjust the value in `ADate` to the UTC time zone when necessary.

The return value contains the adjusted value in `ADate` formatted using the notation:

- `yyyy-mm-ddThh:nn:ss.zzz±hh:nn` or
- `yyyy-mm-ddThh:nn:ss.zzzZ` for Zulu time

Use `ISO8601ToDate` to convert the return value back to a native `TDateTime` type.

See also: `ISO8601ToDate` ([623](#))

44.4.13 DayOf

Synopsis: Extract the day (of month) part from a `TDateTime` value

Declaration: `function DayOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOf` returns the day of the month part of the `AValue` date/time indication. It is a number between 1 and 31.

For an example, see `YearOf` ([684](#))

See also: `YearOf` ([684](#)), `WeekOf` ([671](#)), `MonthOf` ([639](#)), `HourOf` ([613](#)), `MinuteOf` ([635](#)), `SecondOf` ([652](#)), `MilliSecondOf` ([631](#))

44.4.14 DayOfTheMonth

Synopsis: Extract the day (of month) part of a TDateTime value

Declaration: `function DayOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheMonth` returns the number of days that have passed since the start of the month till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the month will return 1.

For an example, see the `WeekOfTheMonth` (672) function.

See also: `DayOfTheYear` (599), `WeekOfTheMonth` (672), `HourOfTheMonth` (614), `MinuteOfTheMonth` (636), `SecondOfTheMonth` (654), `MilliSecondOfTheMonth` (632)

44.4.15 DayOfTheWeek

Synopsis: Extracts the day of the week from a TDateTime value

Declaration: `function DayOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheWeek` returns the number of days that have passed since the start of the week till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the week will return 1.

See also: `DayOfTheYear` (599), `DayOfTheMonth` (599), `HourOfTheWeek` (614), `MinuteOfTheWeek` (636), `SecondOfTheWeek` (654), `MilliSecondOfTheWeek` (633)

Listing: ./examples/datutex/ex42.pp

Program Example42;

{ This program demonstrates the WeekOfTheMonth function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

Begin

N:=Now;

WriteLn('Day of the Week : ', DayOfTheWeek(N));

WriteLn('Hour of the Week : ', HourOfTheWeek(N));

WriteLn('Minute of the Week : ', MinuteOfTheWeek(N));

WriteLn('Second of the Week : ', SecondOfTheWeek(N));

WriteLn('MilliSecond of the Week : ',
MilliSecondOfTheWeek(N));

End.

44.4.16 DayOfTheYear

Synopsis: Extracts the day of the year from a TDateTime value

Declaration: `function DayOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheYear` returns the number of days that have passed since the start of the year till the moment indicated by `AValue`. This is a one-based number, i.e. January 1 will return 1.

For an example, see the `WeekOfTheYear` (672) function.

See also: `WeekOfTheYear` (672), `HourOfTheYear` (615), `MinuteOfTheYear` (637), `SecondOfTheYear` (654), `MilliSecondOfTheYear` (633)

44.4.17 DaysBetween

Synopsis: Number of whole days between two `TDateTime` values.

Declaration: `function DaysBetween(const ANow: TDateTime; const AThen: TDateTime) : Integer`

Visibility: default

Description: `DaysBetween` returns the number of whole days between `ANow` and `AThen`. This means the fractional part of a day (hours, minutes, etc.) is dropped.

See also: `YearsBetween` (684), `MonthsBetween` (640), `WeeksBetween` (673), `HoursBetween` (615), `MinutesBetween` (637), `SecondsBetween` (655), `MillisecondsBetween` (633)

Listing: `./examples/datutex/ex58.pp`

Program Example58;

{ This program demonstrates the DaysBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

 Write('Number of days between ');

 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

 WriteLn(' : ', DaysBetween(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Now;

 D2 := Today - 23/24;

 Test(D1, D2);

 D2 := Today - 1;

 Test(D1, D2);

 D2 := Today - 25/24;

 Test(D1, D2);

 D2 := Today - 26/24;

 Test(D1, D2);

 D2 := Today - 5.4;

 Test(D1, D2);

 D2 := Today - 2.5;

 Test(D1, D2);

End.

44.4.18 DaysInAMonth

Synopsis: Number of days in a month of a certain year.

Declaration: `function DaysInAMonth(const AYear: Word; const AMonth: Word) : Word`

Visibility: default

Description: `DaysInAMonth` returns the number of days in the month `AMonth` in the year `AYear`. The return value takes leap years into account.

See also: `WeeksInAYear` (674), `WeeksInYear` (675), `DaysInYear` (602), `DaysInAYear` (601), `DaysInMonth` (602)

Listing: `./examples/datutex/ex17.pp`

Program Example17;

{ This program demonstrates the DaysInAMonth function }

Uses SysUtils, DateUtils;

Var

Y, M : Word;

Begin

For Y:=1992 to 2010 do

For M:=1 to 12 do

WriteLn(LongMonthNames[M], ' ', Y, ' has ', DaysInAMonth(Y, M), ' days. ');

End.

44.4.19 DaysInAYear

Synopsis: Number of days in a particular year.

Declaration: `function DaysInAYear(const AYear: Word) : Word`

Visibility: default

Description: `DaysInAYear` returns the number of days in the year `AYear`. The return value is either 365 or 366.

See also: `WeeksInAYear` (674), `WeeksInYear` (675), `DaysInYear` (602), `DaysInMonth` (602), `DaysInAMonth` (601)

Listing: `./examples/datutex/ex15.pp`

Program Example15;

{ This program demonstrates the DaysInAYear function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1992 to 2010 do

WriteLn(Y, ' has ', DaysInAYear(Y), ' days. ');

End.

44.4.20 DaysInMonth

Synopsis: Return the number of days in the month in which a date occurs.

Declaration: `function DaysInMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `DaysInMonth` returns the number of days in the month in which `AValue` falls. The return value takes leap years into account.

See also: [WeeksInAYear \(674\)](#), [WeeksInYear \(675\)](#), [DaysInYear \(602\)](#), [DaysInAYear \(601\)](#), [DaysInAMonth \(601\)](#)

Listing: `./examples/datutex/ex16.pp`

Program Example16;

{ This program demonstrates the DaysInMonth function }

Uses SysUtils, DateUtils;

Var

Y,M : Word;

Begin

For Y:=1992 to 2010 do

For M:=1 to 12 do

WriteLn(LongMonthNames[m], ' ', Y, ' has ', DaysInMonth(EncodeDate(Y,M,1)), ' days.');

End.

44.4.21 DaysInYear

Synopsis: Return the number of days in the year in which a date occurs.

Declaration: `function DaysInYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `daysInYear` returns the number of days in the year part of `AValue`. The return value is either 365 or 366.

See also: [WeeksInAYear \(674\)](#), [WeeksInYear \(675\)](#), [DaysInAYear \(601\)](#), [DaysInMonth \(602\)](#), [DaysInAMonth \(601\)](#)

Listing: `./examples/datutex/ex14.pp`

Program Example14;

{ This program demonstrates the DaysInYear function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1992 to 2010 do

WriteLn(Y, ' has ', DaysInYear(EncodeDate(Y,1,1)), ' days.');

End.

44.4.22 DaySpan

Synopsis: Calculate the approximate number of days between two TDateTime values.

Declaration: `function DaySpan(const ANow: TDateTime; const AThen: TDateTime) : Double`

Visibility: default

Description: DaySpan returns the number of Days between ANow and AThen, including any fractional parts of a Day.

See also: YearSpan (685), MonthSpan (640), WeekSpan (675), HourSpan (616), MinuteSpan (638), SecondSpan (655), MilliSecondSpan (634), DaysBetween (600)

Listing: ./examples/datutex/ex66.pp

Program Example66;

{ This program demonstrates the DaySpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

 Write('Number of days between ');

 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

 WriteLn(' : ', DaySpan(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Now;

 D2 := Today - 23/24;

 Test(D1, D2);

 D2 := Today - 1;

 Test(D1, D2);

 D2 := Today - 25/24;

 Test(D1, D2);

 D2 := Today - 26/24;

 Test(D1, D2);

 D2 := Today - 5.4;

 Test(D1, D2);

 D2 := Today - 2.5;

 Test(D1, D2);

End.

44.4.23 DecodeDateDay

Synopsis: Decode a TDateTime value in year and year of day.

Declaration: `procedure DecodeDateDay(const AValue: TDateTime; out AYear: Word;
 out ADayOfYear: Word)`

Visibility: default

Description: `DecodeDateDay` decomposes the date indication in `AValue` and returns the various components in `AYear`, `ADayOfYear`.

See also: [EncodeDateTime \(607\)](#), [EncodeDateMonthWeek \(607\)](#), [EncodeDateWeek \(608\)](#), [EncodeDateDay \(607\)](#), [DecodeDateTime \(605\)](#), [DecodeDateWeek \(605\)](#), [DecodeDateMonthWeek \(604\)](#)

Listing: `./examples/datutex/ex83.pp`

Program `Example83`;

{ This program demonstrates the DecodeDateDay function }

Uses `SysUtils`, `DateUtils`;

Var

`Y, DoY : Word;`
`TS : TDateTime;`

Begin

`DecodeDateDay(Now, Y, DoY);`
`TS := EncodeDateDay(Y, DoY);`
`WriteLn('Today is : ', DateToStr(TS));`

End.

44.4.24 DecodeDateMonthWeek

Synopsis: Decode a `TDateTime` value in a month, week of month and day of week

Declaration: `procedure DecodeDateMonthWeek(const AValue: TDateTime; out AYear: Word;`
`out AMonth: Word; out AWeekOfMonth: Word;`
`out ADayOfWeek: Word)`

Visibility: `default`

Description: `DecodeDateMonthWeek` decomposes the date indication in `AValue` and returns the various components in `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek`.

See also: [EncodeDateTime \(607\)](#), [EncodeDateMonthWeek \(607\)](#), [EncodeDateWeek \(608\)](#), [EncodeDateDay \(607\)](#), [DecodeDateTime \(605\)](#), [DecodeDateWeek \(605\)](#), [DecodeDateDay \(603\)](#)

Listing: `./examples/datutex/ex85.pp`

Program `Example85`;

{ This program demonstrates the DecodeDateMonthWeek function }

Uses `SysUtils`, `DateUtils`;

Var

`Y, M, WoM, DoW : Word;`
`TS : TDateTime;`

Begin

`DecodeDateMonthWeek(Now, Y, M, WoM, DoW);`
`TS := EncodeDateMonthWeek(Y, M, WoM, DoW);`
`WriteLn('Today is : ', DateToStr(TS));`

End.

44.4.25 DecodeDateTime

Synopsis: Decode a TDateTime value in a date and time value

Declaration: `procedure DecodeDateTime(const AValue: TDateTime; out AYear: Word;
out AMonth: Word; out ADay: Word;
out AHour: Word; out AMinute: Word;
out ASecond: Word; out AMilliSecond: Word)`

Visibility: default

Description: `DecodeDateTime` decomposes the date/time indication in `AValue` and returns the various components in `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond`, `AMilliSecond`

See also: `EncodeDateTime` (607), `EncodeDateMonthWeek` (607), `EncodeDateWeek` (608), `EncodeDateDay` (607), `DecodeDateWeek` (605), `DecodeDateDay` (603), `DecodeDateMonthWeek` (604)

Listing: ./examples/datutex/ex79.pp

Program Example79;

{ This program demonstrates the DecodeDateTime function }

Uses SysUtils, DateUtils;

Var

Y, Mo, D, H, Mi, S, MS : Word;
TS : TDateTime;

Begin

DecodeDateTime(**Now**, Y, Mo, D, H, Mi, S, MS);
TS := EncodeDateTime(Y, Mo, D, H, Mi, S, MS);
WriteLn('Now is : ', **DateTimeToStr**(TS));

End.

44.4.26 DecodeDateWeek

Synopsis: Decode a TDateTime value in a week of year and day of week.

Declaration: `procedure DecodeDateWeek(const AValue: TDateTime; out AYear: Word;
out AWeekOfYear: Word; out ADayOfWeek: Word)`

Visibility: default

Description: `DecodeDateWeek` decomposes the date indication in `AValue` and returns the various components in `AYear`, `AWeekOfYear`, `ADayOfWeek`.

See also: `EncodeDateTime` (607), `EncodeDateMonthWeek` (607), `EncodeDateWeek` (608), `EncodeDateDay` (607), `DecodeDateTime` (605), `DecodeDateDay` (603), `DecodeDateMonthWeek` (604)

Listing: ./examples/datutex/ex81.pp

Program Example81;

{ This program demonstrates the DecodeDateWeek function }

Uses SysUtils, DateUtils;

```

Var
  Y,W,Dow : Word;
  TS : TDateTime;

Begin
  DecodeDateWeek(Now,Y,W,Dow);
  TS:=EncodeDateWeek(Y,W,Dow);
  WriteIn('Today is : ',DateToStr(TS));
End.

```

44.4.27 DecodeDayOfWeekInMonth

Synopsis: Decode a TDateTime value in year, month, day of week parts

Declaration: `procedure DecodeDayOfWeekInMonth(const AValue: TDateTime;`
 `out AYear: Word; out AMonth: Word;`
 `out ANthDayOfWeek: Word;`
 `out ADayOfWeek: Word)`

Visibility: default

Description: DecodeDayOfWeekInMonth decodes the date AValue in a AYear, AMonth, ADayOfWeek and ANthDayOfWeek. (This is the N-th time that this weekday occurs in the month, e.g. the third Saturday of the month.)

See also: NthDayOfWeek ([641](#)), EncodeDateMonthWeek ([607](#)), #rtl.sysutils.DayOfWeek ([1678](#)), EncodeDayOfWeekInMonth ([608](#)), TryEncodeDayOfWeekInMonth ([665](#))

Listing: ./examples/datutex/ex105.pp

Program Example105;

{ This program demonstrates the DecodeDayOfWeekInMonth function }

Uses SysUtils, DateUtils;

```

Var
  Y,M,NDoW,DoW : Word;
  D : TDateTime;
Begin
  DecodeDayOfWeekInMonth(Date,Y,M,NDoW,DoW);
  D:=EncodeDayOfWeekInMonth(Y,M,NDoW,DoW);
  Write(DateToStr(D),' is the ',NDoW,'-th ');
  WriteIn(formatDateTime('dddd',D),' of the month. ');
End.

```

44.4.28 DosDateTimeToDateTime

Synopsis: Convert DOS date/time format to TDateTime format

Declaration: `function DosDateTimeToDateTime(AValue: LongInt) : TDateTime`

Visibility: default

Description: DosDateTimeToDateTime takes a DOS encoded date/time AValue and recodes it as a TDateTime value.

The bit encoding of the DOS date/time is explained in the DateTimeToDosDateTime ([596](#)) function.

See also: [DateTimeToDosDateTime \(596\)](#)

44.4.29 EncodeDateDay

Synopsis: Encodes a year and day of year to a TDateTime value

Declaration: `function EncodeDateDay(const AYear: Word; const ADayOfYear: Word)
: TDateTime`

Visibility: default

Description: EncodeDateDay encodes the values AYear and ADayOfYear to a date value and returns this value.

For an example, see [DecodeDateDay \(603\)](#).

Errors: If any of the arguments is not valid, then an EConvertError exception is raised.

See also: [EncodeDateMonthWeek \(607\)](#), [DecodeDateDay \(603\)](#), [EncodeDateTime \(607\)](#), [EncodeDateWeek \(608\)](#), [TryEncodeDateTime \(664\)](#), [TryEncodeDateMonthWeek \(663\)](#), [TryEncodeDateWeek \(665\)](#)

44.4.30 EncodeDateMonthWeek

Synopsis: Encodes a year, month, week of month and day of week to a TDateTime value

Declaration: `function EncodeDateMonthWeek(const AYear: Word; const AMonth: Word;
const AWeekOfMonth: Word;
const ADayOfWeek: Word) : TDateTime`

Visibility: default

Description: EncodeDateMonthWeek encodes the values AYear, AMonth, AWeekOfMonth, ADayOfWeek, to a date value and returns this value.

For an example, see [DecodeDateMonthWeek \(604\)](#).

Errors: If any of the arguments is not valid, then an EConvertError exception is raised.

See also: [DecodeDateMonthWeek \(604\)](#), [EncodeDateTime \(607\)](#), [EncodeDateWeek \(608\)](#), [EncodeDateDay \(607\)](#), [TryEncodeDateTime \(664\)](#), [TryEncodeDateWeek \(665\)](#), [TryEncodeDateMonthWeek \(663\)](#), [TryEncodeDateDay \(662\)](#), [NthDayOfWeek \(641\)](#)

44.4.31 EncodeDateTime

Synopsis: Encodes a TDateTime value from all its parts

Declaration: `function EncodeDateTime(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word) : TDateTime`

Visibility: default

Description: EncodeDateTime encodes the values AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond to a date/time value and returns this value.

For an example, see [DecodeDateTime \(605\)](#).

Errors: If any of the arguments is not valid, then an EConvertError exception is raised.

See also: [DecodeDateTime \(605\)](#), [EncodeDateMonthWeek \(607\)](#), [EncodeDateWeek \(608\)](#), [EncodeDateDay \(607\)](#), [TryEncodeDateTime \(664\)](#), [TryEncodeDateWeek \(665\)](#), [TryEncodeDateDay \(662\)](#), [TryEncodeDateMonthWeek \(663\)](#)

44.4.32 EncodeDateWeek

Synopsis: Encode a `TDateTime` value from a year, week and day of week triplet

Declaration:

```
function EncodeDateWeek(const AYear: Word; const AWeekOfYear: Word;
                        const ADayOfWeek: Word) : TDateTime
function EncodeDateWeek(const AYear: Word; const AWeekOfYear: Word)
                        : TDateTime
```

Visibility: default

Description: `EncodeDateWeek` encodes the values `AYear`, `AWeekOfYear` and `ADayOfWeek` to a date value and returns this value.

For an example, see [DecodeDateWeek \(605\)](#).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: [EncodeDateMonthWeek \(607\)](#), [DecodeDateWeek \(605\)](#), [EncodeDateTime \(607\)](#), [EncodeDateDay \(607\)](#), [TryEncodeDateTime \(664\)](#), [TryEncodeDateWeek \(665\)](#), [TryEncodeDateMonthWeek \(663\)](#)

44.4.33 EncodeDayOfWeekInMonth

Synopsis: Encodes a year, month, week, day of week specification to a `TDateTime` value

Declaration:

```
function EncodeDayOfWeekInMonth(const AYear: Word; const AMonth: Word;
                                const ANthDayOfWeek: Word;
                                const ADayOfWeek: Word) : TDateTime
```

Visibility: default

Description: `EncodeDayOfWeekInMonth` encodes `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek` to a valid date stamp and returns the result.

`ANthDayOfWeek` is the N-th time that this weekday occurs in the month, e.g. the third Saturday of the month.

For an example, see [DecodeDayOfWeekInMonth \(606\)](#).

Errors: If any of the values is not in range, then an `EConvertError` exception will be raised.

See also: [NthDayOfWeek \(641\)](#), [EncodeDateMonthWeek \(607\)](#), [#rtl.sysutils.DayOfWeek \(1678\)](#), [DecodeDayOfWeekInMonth \(606\)](#), [TryEncodeDayOfWeekInMonth \(665\)](#)

44.4.34 EncodeTimeInterval

Synopsis: Encode an interval as a `TDateTime` value.

Declaration:

```
function EncodeTimeInterval(Hour: Word; Minute: Word; Second: Word;
                            MilliSecond: Word) : TDateTime
```

Visibility: default

Description: `EncodeTimeInterval` encodes a time interval expressed in Hour, Min, Sec, MSec as a `TDateTime` value and returns the value in Time.

Errors: If `Min`, `Sec`, `MSec` do not contain a valid time indication, then an `EConvertError` exception is raised.

See also: `TryEncodeTimeInterval` (666)

44.4.35 EndOfDay

Synopsis: Calculates a `TDateTime` value representing the end of a specified day

Declaration:

```
function EndOfDay(const AYear: Word; const AMonth: Word;
                  const ADay: Word) : TDateTime; Overload
function EndOfDay(const AYear: Word; const ADayOfYear: Word)
                  : TDateTime; Overload
```

Visibility: default

Description: `EndOfDay` returns a `TDateTime` value with the date/time indication of the last moment (23:59:59.999) of the day given by `AYear`, `AMonth`, `ADay`.

The day may also be indicated with a `AYear`, `ADayOfYear` pair.

See also: `StartOfDay` (659), `StartOfDay` (656), `StartOfTheWeek` (660), `StartOfAWeek` (658), `StartOfAMonth` (657), `StartOfTheMonth` (659), `EndOfTheWeek` (612), `EndOfAWeek` (610), `EndOfTheYear` (613), `EndOfAYear` (611), `EndOfTheMonth` (612), `EndOfAMonth` (609), `EndOfTheDay` (611)

Listing: `./examples/datutex/ex39.pp`

Program Example39;

{ This program demonstrates the EndOfDay function }

Uses SysUtils, DateUtils;

Const

Fmt = 'End of the day : "dd mmm yyyy hh:nn:ss";

Var

Y,M,D : Word;

Begin

Y:=YearOf(Today);

M:=MonthOf(Today);

D:=DayOf(Today);

WriteLn (FormatDateTime(Fmt, EndOfDay(Y,M,D)));

DecodeDateDay(Today, Y,D);

WriteLn (FormatDateTime(Fmt, EndOfDay(Y,D)));

End.

44.4.36 EndOfAMonth

Synopsis: Calculate a `TDateTime` value representing the last day of the indicated month

Declaration: `function EndOfAMonth(const AYear: Word; const AMonth: Word) : TDateTime`

Visibility: default

Description: `EndOfAMonth` returns a `TDateTime` value with the date of the last day of the month indicated by the `AYear`, `AMonth` pair.

See also: [StartOfTheMonth \(659\)](#), [StartOfAMonth \(657\)](#), [EndOfTheMonth \(612\)](#), [EndOfTheYear \(613\)](#), [EndOfAYear \(611\)](#), [StartOfAWeek \(658\)](#), [StartOfTheWeek \(660\)](#)

Listing: ./examples/datutex/ex31.pp

Program Example31 ;

{ This program demonstrates the EndOfAMonth function }

Uses SysUtils , DateUtils ;

Const

Fmt = 'Last day of this month : "dd mmm yyyy' ;

Var

Y,M : Word ;

Begin

Y:=YearOf(Today) ;

M:=MonthOf(Today) ;

WriteLn (**FormatDateTime** (Fmt , EndOfAMonth (Y,M))) ;

End.

44.4.37 EndOfAWeek

Synopsis: Return the last moment of day of the week, given a year and a week in the year.

Declaration: `function EndOfAWeek(const AYear: Word; const AWeekOfYear: Word;
const ADayOfWeek: Word) : TDateTime
function EndOfAWeek(const AYear: Word; const AWeekOfYear: Word)
: TDateTime`

Visibility: default

Description: EndOfAWeek returns a TDateTime value with the date of the last moment (23:59:59:999) on the indicated day of the week indicated by the AYear, AWeek, ADayOfWeek values.

The default value for ADayOfWeek is 7.

See also: [StartOfTheWeek \(660\)](#), [EndOfTheWeek \(612\)](#), [EndOfAWeek \(610\)](#), [StartOfAMonth \(657\)](#), [EndOfTheYear \(613\)](#), [EndOfAYear \(611\)](#), [EndOfTheMonth \(612\)](#), [EndOfAMonth \(609\)](#)

Listing: ./examples/datutex/ex35.pp

Program Example35 ;

{ This program demonstrates the EndOfAWeek function }

Uses SysUtils , DateUtils ;

Const

Fmt = 'Last day of this week : "dd mmm yyyy hh:nn:ss' ;

Fmt2 = 'Last-1 day of this week : "dd mmm yyyy hh:nn:ss' ;

Var

Y,W : Word ;

Begin

Y:=YearOf(Today) ;

```

W:=WeekOf( Today );
WriteIn (FormatDateTime ( Fmt , EndOfAWeek ( Y,W ) ) );
WriteIn (FormatDateTime ( Fmt2 , EndOfAWeek ( Y,W, 6 ) ) );
End.

```

44.4.38 EndOfAYear

Synopsis: Calculate a TDateTime value representing the last day of a year

Declaration: `function EndOfAYear(const AYear: Word) : TDateTime`

Visibility: default

Description: `StartOfAYear` returns a TDateTime value with the date of the last day of the year AYear (December 31).

See also: `StartOfTheYear` (660), `EndOfTheYear` (613), `EndOfAYear` (611), `EndOfTheMonth` (612), `EndOfA-Month` (609), `StartOfAWeek` (658), `StartOfTheWeek` (660)

Listing: ./examples/datutex/ex27.pp

Program Example27;

```
{ This program demonstrates the EndOfAYear function }
```

Uses SysUtils , DateUtils ;

Const

```
  Fmt = 'Last day of this year : "dd mmm yyyy ';
```

Begin

```
  WriteIn (FormatDateTime ( Fmt , EndOfAYear ( YearOf ( Today ) ) ) );
```

End.

44.4.39 EndOfTheDay

Synopsis: Calculate a TDateTime value that represents the end of a given day.

Declaration: `function EndOfTheDay(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheDay` extracts the date part of AValue and returns a TDateTime value with the date/-time indication of the last moment (23:59:59.999) of this day.

See also: `StartOfTheDay` (659), `StartOfADay` (656), `StartOfTheWeek` (660), `StartOfAWeek` (658), `StartOfA-Month` (657), `StartOfTheMonth` (659), `EndOfTheWeek` (612), `EndOfAWeek` (610), `EndOfTheYear` (613), `EndOfAYear` (611), `EndOfTheMonth` (612), `EndOfAMonth` (609), `EndOfADay` (609)

Listing: ./examples/datutex/ex37.pp

Program Example37;

```
{ This program demonstrates the EndOfTheDay function }
```

Uses SysUtils , DateUtils ;

Const

```
Fmt = 'End of the day : "dd mmm yyyy hh:nn:ss';
```

Begin

```
WriteIn (FormatDateTime (Fmt, EndOfTheDay (Today)));
End.
```

44.4.40 EndOfTheMonth

Synopsis: Calculate a TDateTime value representing the last day of the month, given a day in that month.

Declaration: `function EndOfTheMonth(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: EndOfTheMonth extracts the year and month parts of AValue and returns a TDateTime value with the date of the first day of that year and month as the EndOfAMonth (609) function.

See also: StartOfAMonth (657), StartOfTheMonth (659), EndOfAMonth (609), EndOfTheYear (613), EndOfAYear (611), StartOfAWeek (658), StartOfTheWeek (660)

Listing: ./examples/datutex/ex29.pp

Program Example29;

```
{ This program demonstrates the EndOfTheMonth function }
```

Uses SysUtils, DateUtils;

Const

```
Fmt = 'last day of this month : "dd mmm yyyy';
```

Begin

```
WriteIn (FormatDateTime (Fmt, EndOfTheMonth (Today)));
End.
```

44.4.41 EndOfTheWeek

Synopsis: Calculate a TDateTime value which represents the end of a week, given a date in that week.

Declaration: `function EndOfTheWeek(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: EndOfTheWeek extracts the year and week parts of AValue and returns a TDateTime value with the date of the last day of that week as the EndOfAWeek (610) function.

See also: StartOfAWeek (658), StartOfTheWeek (660), EndOfAWeek (610), StartOfAMonth (657), EndOfTheYear (613), EndOfAYear (611), EndOfTheMonth (612), EndOfAMonth (609)

Listing: ./examples/datutex/ex33.pp

Program Example33;

{ This program demonstrates the EndOfTheWeek function }

Uses SysUtils, DateUtils;

Const

Fmt = '"last day of this week : "dd mmm yyyy';

Begin

WriteIn (FormatDateTime (Fmt, EndOfTheWeek (Today)));

End.

44.4.42 EndOfTheYear

Synopsis: Calculate a TDateTime value representing the last day of a year, given a date in that year.

Declaration: function EndOfTheYear(const AValue: TDateTime) : TDateTime

Visibility: default

Description: EndOfTheYear extracts the year part of AValue and returns a TDateTime value with the date of the last day of that year (December 31), as the EndOfAYear (611) function.

See also: StartOfAYear (658), StartOfTheYear (660), EndOfTheMonth (612), EndOfAMonth (609), StartOfAWeek (658), StartOfTheWeek (660), EndOfAYear (611)

Listing: ./examples/datutex/ex25.pp

Program Example25;

{ This program demonstrates the EndOfTheYear function }

Uses SysUtils, DateUtils;

Const

Fmt = '"Last day of this year : "dd mmm yyyy';

Begin

WriteIn (FormatDateTime (Fmt, EndOfTheYear (Today)));

End.

44.4.43 HourOf

Synopsis: Extract the hour part from a TDateTime value.

Declaration: function HourOf(const AValue: TDateTime) : Word

Visibility: default

Description: HourOf returns the hour of the day part of the AValue date/time indication. It is a number between 0 and 23.

For an example, see YearOf (684)

See also: YearOf (684), WeekOf (671), MonthOf (639), DayOf (598), MinuteOf (635), SecondOf (652), MilliSecondOf (631)

44.4.44 HourOfDay

Synopsis: Calculate the hour of a given TDateTime value

Declaration: `function HourOfDay(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfDay` returns the number of hours that have passed since the start of the day till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 will return 0.

See also: `HourOfYear` (615), `HourOfMonth` (614), `HourOfWeek` (614), `MinuteOfDay` (635), `SecondOfDay` (653), `MillisecondOfDay` (631)

Listing: ./examples/datutex/ex43.pp

Program Example43;

{ This program demonstrates the HourOfDay function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

Begin

N:=Now;

WriteLn('Hour of the Day : ',HourOfDay(N));

WriteLn('Minute of the Day : ',MinuteOfDay(N));

WriteLn('Second of the Day : ',SecondOfDay(N));

WriteLn('Millisecond of the Day : ',
MillisecondOfDay(N));

End.

44.4.45 HourOfMonth

Synopsis: Calculate the number of hours passed since the start of the month.

Declaration: `function HourOfMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfMonth` returns the number of hours that have passed since the start of the month till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 on the first day of the month will return 0.

For an example, see the `WeekOfMonth` (672) function.

See also: `WeekOfMonth` (672), `DayOfMonth` (599), `MinuteOfMonth` (636), `SecondOfMonth` (654), `MillisecondOfMonth` (632)

44.4.46 HourOfWeek

Synopsis: Calculate the number of hours elapsed since the start of the week.

Declaration: `function HourOfWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheWeek` returns the number of hours that have passed since the start of the Week till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (599) function.

See also: `HourOfTheYear` (615), `HourOfTheMonth` (614), `HourOfTheDay` (614), `DayOfTheWeek` (599), `MinuteOfTheWeek` (636), `SecondOfTheWeek` (654), `MilliSecondOfTheWeek` (633)

44.4.47 HourOfTheYear

Synopsis: Calculate the number of hours passed since the start of the year.

Declaration: `function HourOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheYear` returns the number of hours that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:59:59 will return 0.

For an example, see the `WeekOfTheYear` (672) function.

See also: `WeekOfTheYear` (672), `DayOfTheYear` (599), `MinuteOfTheYear` (637), `SecondOfTheYear` (654), `MilliSecondOfTheYear` (633)

44.4.48 HoursBetween

Synopsis: Calculate the number of whole hours between two `TDateTime` values.

Declaration: `function HoursBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

Visibility: default

Description: `HoursBetween` returns the number of whole hours between `ANow` and `AThen`. This means the fractional part of an hour (minutes,seconds etc.) is dropped.

See also: `YearsBetween` (684), `MonthsBetween` (640), `WeeksBetween` (673), `DaysBetween` (600), `MinutesBetween` (637), `SecondsBetween` (655), `MillisecondsBetween` (633)

Listing: `./examples/datutex/ex59.pp`

Program Example59;

{ This program demonstrates the HoursBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of hours between ');
 Write(**DateTimeToStr**(AThen), ' and ', **DateTimeToStr**(ANow));
 WriteLn(' : ', HoursBetween(ANow, AThen));
end;

Var

 D1, D2 : TDateTime;

Begin

```

D1:=Now;
D2:=D1-(59*OneMinute);
Test(D1,D2);
D2:=D1-(61*OneMinute);
Test(D1,D2);
D2:=D1-(122*OneMinute);
Test(D1,D2);
D2:=D1-(306*OneMinute);
Test(D1,D2);
D2:=D1-(5.4*OneHour);
Test(D1,D2);
D2:=D1-(2.5*OneHour);
Test(D1,D2);

```

End.**44.4.49 HourSpan**

Synopsis: Calculate the approximate number of hours between two TDateTime values.

Declaration: `function HourSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double`

Visibility: default

Description: HourSpan returns the number of Hours between ANow and AThen, including any fractional parts of a Hour.

See also: YearSpan (685), MonthSpan (640), WeekSpan (675), DaySpan (603), MinuteSpan (638), SecondSpan (655), MilliSecondSpan (634), HoursBetween (615)

Listing: ./examples/datutex/ex67.pp

Program Example67;

{ This program demonstrates the HourSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

```

Write('Number of hours between ');
Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
WriteLn(' : ', HourSpan(ANow, AThen));
end;

```

Var

```

D1, D2 : TDateTime;

```

Begin

```

D1:=Now;
D2:=D1-(59*OneMinute);
Test(D1,D2);
D2:=D1-(61*OneMinute);
Test(D1,D2);

```

```

D2:=D1-(122*OneMinute);
Test(D1,D2);
D2:=D1-(306*OneMinute);
Test(D1,D2);
D2:=D1-(5.4*OneHour);
Test(D1,D2);
D2:=D1-(2.5*OneHour);
Test(D1,D2);
End.

```

44.4.50 IncDay

Synopsis: Increase a TDateTime value with a number of days.

Declaration: `function IncDay(const AValue: TDateTime; const ANumberOfDays: Integer) : TDateTime`
`function IncDay(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncDay` adds `ANumberOfDays` days to `AValue` and returns the resulting date/time. `ANumberOfDays` can be positive or negative.

See also: `IncYear` (620), `#rtl.sysutils.IncMonth` (1734), `IncWeek` (619), `IncHour` (617), `IncMinute` (618), `IncSecond` (619), `IncMilliSecond` (618)

Listing: ./examples/datutex/ex74.pp

Program Example74;

```
{ This program demonstrates the IncDay function }
```

Uses SysUtils, DateUtils;

Begin

```
WriteLn('One Day from today is ', DateToStr(IncDay(Today, 1)));
```

```
WriteLn('One Day ago from today is ', DateToStr(IncDay(Today, -1)));
```

End.

44.4.51 IncHour

Synopsis: Increase a TDateTime value with a number of hours.

Declaration: `function IncHour(const AValue: TDateTime; const ANumberOfHours: Int64) : TDateTime`
`function IncHour(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncHour` adds `ANumberOfHours` hours to `AValue` and returns the resulting date/time. `ANumberOfHours` can be positive or negative.

See also: `IncYear` (620), `#rtl.sysutils.IncMonth` (1734), `IncWeek` (619), `IncDay` (617), `IncMinute` (618), `IncSecond` (619), `IncMilliSecond` (618)

Listing: ./examples/datutex/ex75.pp

Program Example75

;

*{ This program demonstrates the IncHour function }***Uses** SysUtils , DateUtils ;**Begin****WriteLn** ('One Hour from now is ', **DateTimeToStr** (IncHour(**Now**, 1)));**WriteLn** ('One Hour ago from now is ', **DateTimeToStr** (IncHour(**Now**, - 1)));**End.****44.4.52 IncMilliSecond****Synopsis:** Increase a TDateTime value with a number of milliseconds.

Declaration: function IncMilliSecond(const AValue: TDateTime;
 const ANumberOfMilliseconds: Int64) : TDateTime
 function IncMilliSecond(const AValue: TDateTime) : TDateTime

Visibility: default**Description:** IncMilliSecond adds ANumberOfMilliseconds milliseconds to AValue and returns the resulting date/time. ANumberOfMilliseconds can be positive or negative.**See also:** IncYear ([620](#)), #rtl.sysutils.IncMonth ([1734](#)), IncWeek ([619](#)), IncDay ([617](#)), IncHour ([617](#)), IncSecond ([619](#)), IncMilliSecond ([618](#))**Listing:** ./examples/datutex/ex78.pp**Program Example78;***{ This program demonstrates the IncMilliSecond function }***Uses** SysUtils , DateUtils ;**Begin****WriteLn** ('One MilliSecond from now is ', **TimeToStr** (IncMilliSecond(**Now**, 1)));**WriteLn** ('One MilliSecond ago from now is ', **TimeToStr** (IncMilliSecond(**Now**, - 1)));**End.****44.4.53 IncMinute****Synopsis:** Increase a TDateTime value with a number of minutes.

Declaration: function IncMinute(const AValue: TDateTime;
 const ANumberOfMinutes: Int64) : TDateTime
 function IncMinute(const AValue: TDateTime) : TDateTime

Visibility: default**Description:** IncMinute adds ANumberOfMinutes minutes to AValue and returns the resulting date/-time. ANumberOfMinutes can be positive or negative.**See also:** IncYear ([620](#)), #rtl.sysutils.IncMonth ([1734](#)), IncWeek ([619](#)), IncDay ([617](#)), IncHour ([617](#)), IncSecond ([619](#)), IncMilliSecond ([618](#))

Listing: ./examples/datutex/ex76.pp

Program Example76;

{ This program demonstrates the IncMinute function }

Uses SysUtils, DateUtils;

Begin

WriteLn('One Minute from now is ', **TimeToStr**(IncMinute(**Time**, 1)));

WriteLn('One Minute ago from now is ', **TimeToStr**(IncMinute(**Time**, -1)));

End.

44.4.54 IncSecond

Synopsis: Increase a TDateTime value with a number of seconds.

Declaration: function IncSecond(const AValue: TDateTime;
 const ANumberOfSeconds: Int64) : TDateTime
 function IncSecond(const AValue: TDateTime) : TDateTime

Visibility: default

Description: IncSecond adds ANumberOfSeconds seconds to AValue and returns the resulting date/-time. ANumberOfSeconds can be positive or negative.

See also: IncYear ([620](#)), #rtl.sysutils.IncMonth ([1734](#)), IncWeek ([619](#)), IncDay ([617](#)), IncHour ([617](#)), IncSecond ([619](#)), IncMilliSecond ([618](#))

Listing: ./examples/datutex/ex77.pp

Program Example77;

{ This program demonstrates the IncSecond function }

Uses SysUtils, DateUtils;

Begin

WriteLn('One Second from now is ', **TimeToStr**(IncSecond(**Time**, 1)));

WriteLn('One Second ago from now is ', **TimeToStr**(IncSecond(**Time**, -1)));

End.

44.4.55 IncWeek

Synopsis: Increase a TDateTime value with a number of weeks.

Declaration: function IncWeek(const AValue: TDateTime; const ANumberOfWeeks: Integer)
 : TDateTime
 function IncWeek(const AValue: TDateTime) : TDateTime

Visibility: default

Description: IncWeek adds ANumberOfWeeks weeks to AValue and returns the resulting date/time. ANumberOfWeeks can be positive or negative.

See also: IncYear ([620](#)), #rtl.sysutils.IncMonth ([1734](#)), IncDay ([617](#)), IncHour ([617](#)), IncMinute ([618](#)), IncSecond ([619](#)), IncMilliSecond ([618](#))

44.4.58 InvalidDateMonthWeekError

Synopsis: Raise an `EConvertError` exception when a `Year,Month,WeekOfMonth,DayOfWeek` is invalid.

Declaration:

```
procedure InvalidDateMonthWeekError(const AYear: Word;
                                   const AMonth: Word;
                                   const AWeekOfMonth: Word;
                                   const ADayOfWeek: Word)
```

Visibility: default

Description: `InvalidDateMonthWeekError` raises an `EConvertError` (1800) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (621), `InvalidDateTimeError` (621), `InvalidDateDayError` (620), `InvalidDay-Of-WeekInMonthError` (622)

44.4.59 InvalidDateTimeError

Synopsis: Raise an `EConvertError` about an invalid date-time specification.

Declaration:

```
procedure InvalidDateTimeError(const AYear: Word; const AMonth: Word;
                               const ADay: Word; const AHour: Word;
                               const AMinute: Word; const ASecond: Word;
                               const AMilliSecond: Word;
                               const ABaseDate: TDateTime)
procedure InvalidDateTimeError(const AYear: Word; const AMonth: Word;
                               const ADay: Word; const AHour: Word;
                               const AMinute: Word; const ASecond: Word;
                               const AMilliSecond: Word)
```

Visibility: default

Description: `InvalidDateTimeError` raises an `EConvertError` (1800) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (621), `InvalidDateDayError` (620), `InvalidDateMonthWeekError` (621), `InvalidDayOf-WeekInMonthError` (622)

44.4.60 InvalidDateWeekError

Synopsis: Raise an `EConvertError` with an invalid `Year`, `WeekOfyear` and `DayOfWeek` specification

Declaration:

```
procedure InvalidDateWeekError(const AYear: Word;
                               const AWeekOfYear: Word;
                               const ADayOfWeek: Word)
```

Visibility: default

Description: `InvalidDateWeekError` raises an `EConvertError` (1800) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AWeek`, `ADayOfWeek`.
Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateTimeError` (621), `InvalidDateDayError` (620), `InvalidDateMonthWeekError` (621), `InvalidDayOfWeekInMonthError` (622)

44.4.61 InvalidDayOfWeekInMonthError

Synopsis: Raise an `EConvertError` exception when a `Year,Month,NthDayOfWeek,DayOfWeek` is invalid.

Declaration: `procedure InvalidDayOfWeekInMonthError(const AYear: Word;
const AMonth: Word;
const ANthDayOfWeek: Word;
const ADayOfWeek: Word)`

Visibility: default

Description: `InvalidDayOfWeekInMonthError` raises an `EConvertError` (1800) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ANthDayOfWeek` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (621), `InvalidDateTimeError` (621), `InvalidDateDayError` (620), `InvalidDateMonthWeekError` (621)

44.4.62 IsInLeapYear

Synopsis: Determine whether a date is in a leap year.

Declaration: `function IsInLeapYear(const AValue: TDateTime) : Boolean`

Visibility: default

Description: `IsInLeapYear` returns `True` if the year part of `AValue` is leap year, or `False` if not.

See also: `YearOf` (684), `IsPM` (624), `IsToday` (625), `IsSameDay` (624)

Listing: `./examples/datutex/ex3.pp`

Program `Example3`;

{ This program demonstrates the IsInLeapYear function }

Uses `SysUtils, DateUtils`;

Begin

`WriteLn('Current year is leap year: ',IsInLeapYear(Date));`

End.

44.4.63 ISO8601ToDate

Synopsis: Converts a date/time value in ISO 8601 notation to a native `TDateTime` type

Declaration: `function ISO8601ToDate(const DateString: string; ReturnUTC: Boolean)
: TDateTime`

Visibility: default

Description: `ISO8601ToDate` is a function used to convert a string using ISO 8601 date/time notation to a native `TDateTime` type.

`DateString` contains the date/time value expressed using ISO 8601 notation.

`ReturnUTC` indicates if the `TDateTime` value should be adjusted to reflect the UTC (Coordinated Universal Time) time zone. The default value for the argument is `True`.

`ISO8601ToDate` calls the `TryISO8601ToDate` function to perform the conversion, and raises an `EConvertError` exception if `DateString` contains an invalid ISO 8601 date/time value. The return value contains the native `TDateTime` value for the timestamp (adjusted to UTC when requested).

Use `DateToISO8601` to convert the native date/time value back to its representation using ISO 8601 date/time notation.

See also: `TryISO8601ToDate` ([666](#)), `DateToISO8601` ([598](#))

44.4.64 ISO8601ToDateDef

Synopsis: Converts an ISO 8601 date/time string to a `TDateTime` type

Declaration: `function ISO8601ToDateDef(const DateString: string; ReturnUTC: Boolean;
aDefault: TDateTime) : TDateTime
function ISO8601ToDateDef(const DateString: string;
aDefault: TDateTime; ReturnUTC: Boolean)
: TDateTime`

Visibility: default

Description: `ISO8601ToDateDef` is used to convert a date/time string in ISO 8601 format to its representation as a `TDateTime` value. `DateString` contains the ISO 8601-formatted date/time value converted in the routine. It can use one of the supported ISO 8601 date/time formats, and may contain an optional time zone offset. `DateString` uses the format returned from the `DateToISO8601` function. Each of the following represent the date/time for Noon on July 4, 2019:

- 20190714 12:00
- 2019-07-14 12:00
- 20190714 12:00:00
- 2019-07-14 12:00:00
- 20190714T12:00
- 20190714T12:00:00
- 2019-07-14T12:00
- 2019-07-14T12:00:00
- 20190714T12:00:00-04:00
- 2019-07-14T12:00:00-04:00

Time values in `DateString` specified without a time zone offset are assumed to be in the local time zone.

`ReturnUTC` indicates if the value in `DateString` is adjusted to UTC (Coordinated Universal Time) in the return value.

`aDefault` contains the default `TDateTime` value used as the return value when `DateString` cannot be successfully parsed and converted.

Please note that the overloaded variant which uses `String`, `Boolean`, and `TDateTime` arguments has been deprecated. Use the variant with `String`, `TDateTime`, and `Boolean` arguments (in that order) instead.

`ISO8601ToDateDef` calls the `TryISO8601ToDate` function in its implementation.

See also: `DateToISO8601` ([598](#)), `TryISO8601ToDate` ([666](#))

44.4.65 IsPM

Synopsis: Determine whether a time is PM or AM.

Declaration: `function IsPM(const AValue: TDateTime) : Boolean`

Visibility: default

Description: `IsPM` returns `True` if the time part of `AValue` is later than 12:00 (PM, or afternoon).

See also: `YearOf` ([684](#)), `IsInLeapYear` ([622](#)), `IsToday` ([625](#)), `IsSameDay` ([624](#))

Listing: `./examples/datutex/ex4.pp`

Program `Example4`;

{ This program demonstrates the IsPM function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn('Current time is PM : ',IsPM(Now));`

End.

44.4.66 IsSameDay

Synopsis: Check if two date/time indications are the same day.

Declaration: `function IsSameDay(const AValue: TDateTime; const ABasis: TDateTime) : Boolean`

Visibility: default

Description: `IsSameDay` checks whether `AValue` and `ABasis` have the same date part, and returns `True` if they do, `False` if not.

See also: `Today` ([662](#)), `Yesterday` ([686](#)), `Tomorrow` ([662](#)), `IsToday` ([625](#))

Listing: `./examples/datutex/ex21.pp`

```

Program Example21;

{ This program demonstrates the IsSameDay function }

Uses SysUtils, DateUtils;

Var
  I : Integer;
  D : TDateTime;

Begin
  For I:=1 to 3 do
    begin
      D:=Today+Random(3)-1;
      Write(FormatDateTime('dd mmm yyyy "is today : "',D));
      WriteLn(IsSameDay(D,Today));
    end;
End.

```

44.4.67 IsSameMonth

Synopsis: Check if 2 dates are in the same month.

Declaration: `function IsSameMonth(const AValue: TDateTime; const ABasis: TDateTime) : Boolean`

Visibility: default

Description: `IsSameMonth` will return `True` if the two dates `AValue` and `ABasis` occur in the same year and month. (i.e. if their month and year parts match). Otherwise, `False` is returned.

See also: `IsSameDay` (624), `IsToday` (625), `SameDate` (649)

44.4.68 IsToday

Synopsis: Check whether a given date is today.

Declaration: `function IsToday(const AValue: TDateTime) : Boolean`

Visibility: default

Description: `IsToday` returns `True` if `AValue` is today's date, and `False` otherwise.

See also: `Today` (662), `Yesterday` (686), `Tomorrow` (662), `IsSameDay` (624)

Listing: `./examples/datutex/ex20.pp`

```

Program Example20;

{ This program demonstrates the IsToday function }

Uses SysUtils, DateUtils;

Begin
  WriteLn( 'Today      : ', IsToday(Today));
  WriteLn( 'Tomorrow   : ', IsToday(Tomorrow));
  WriteLn( 'Yesterday  : ', IsToday(Yesterday));
End.

```

44.4.69 IsValidDate

Synopsis: Check whether a set of values is a valid date indication.

Declaration: `function IsValidDate(const AYear: Word; const AMonth: Word;
const ADay: Word) : Boolean`

Visibility: default

Description: `IsValidDate` returns `True` when the values `AYear`, `AMonth`, `ADay` form a valid date indication. If one of the values is not valid (e.g. the day is invalid or does not exist in that particular month), `False` is returned.

`AYear` must be in the range 1..9999 to be valid.

See also: `IsValidTime` (629), `IsValidDateTime` (628), `IsValidDateDay` (626), `IsValidDateWeek` (629), `IsValidDateMonthWeek` (627)

Listing: `./examples/datutex/ex5.pp`

Program `Example5;`

{ This program demonstrates the IsValidDate function }

Uses `SysUtils, DateUtils;`

Var

`Y,M,D : Word;`

Begin

`For Y:=2000 to 2004 do`

`For M:=1 to 12 do`

`For D:=1 to 31 do`

`If Not IsValidDate(Y,M,D) then`

`Writeln(D, ' is not a valid day in ', Y, '/', M);`

End.

44.4.70 IsValidDateDay

Synopsis: Check whether a given year/day of year combination is a valid date.

Declaration: `function IsValidDateDay(const AYear: Word; const ADayOfYear: Word)
: Boolean`

Visibility: default

Description: `IsValidDateDay` returns `True` if `AYear` and `ADayOfYear` form a valid date indication, or `False` otherwise.

`AYear` must be in the range 1..9999 to be valid.

The `ADayOfYear` value is checked to see whether it falls within the valid range of dates for `AYear`.

See also: `IsValidDate` (626), `IsValidTime` (629), `IsValidDateTime` (628), `IsValidDateWeek` (629), `IsValidDateMonthWeek` (627)

Listing: `./examples/datutex/ex9.pp`

Program Example9;

{ This program demonstrates the IsValidDateDay function }

Uses SysUtils , DateUtils ;

Var

Y : Word;

Begin

For Y:=1996 to 2004 do

if IsValidDateDay(Y,366) then

WriteLn(Y, ' is a leap year');

End.

44.4.71 IsValidDateMonthWeek

Synopsis: Check whether a given year/month/week/day of the week combination is a valid day

Declaration: function IsValidDateMonthWeek(const AYear: Word; const AMonth: Word;
const AWeekOfMonth: Word;
const ADayOfWeek: Word) : Boolean

Visibility: default

Description: IsValidDateMonthWeek returns True if AYear, AMonth, AWeekOfMonth and ADayOfWeek form a valid date indication, or False otherwise.

AYear must be in the range 1..9999 to be valid.

The AWeekOfMonth, ADayOfWeek values are checked to see whether the combination falls within the valid range of weeks for the AYear, AMonth combination.

See also: IsValidDate ([626](#)), IsValidTime ([629](#)), IsValidDateTime ([628](#)), IsValidDateDay ([626](#)), IsValidDate-Week ([629](#))

Listing: ./examples/datutex/ex11.pp

Program Example11;

{ This program demonstrates the IsValidDateMonthWeek function }

Uses SysUtils , DateUtils ;

Var

Y,W,D : Word;

B : Boolean;

Begin

For Y:=2000 to 2004 do

begin

B:=True;

For W:=4 to 6 do

For D:=1 to 7 do

If B then

begin

B:=IsValidDateMonthWeek(Y,12,W,D);

If Not B then

```

        if (D=1) then
            Writeln('December ',Y,' has exactly ',W,' weeks.')
        else
            Writeln('December ',Y,' has ',W,' weeks and ',D-1,' days.');
```

end;

End.

44.4.72 IsValidDateTime

Synopsis: Check whether a set of values is a valid date and time indication.

Declaration: function IsValidDateTime(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word) : Boolean

Visibility: default

Description: IsValidTime returns True when the values AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond form a valid date and time indication. If one of the values is not valid (e.g. the seconds are larger than 60), False is returned.

AYear must be in the range 1..9999 to be valid.

See also: IsValidDate (626), IsValidTime (629), IsValidDateDay (626), IsValidDateWeek (629), IsValidDate-MonthWeek (627)

Listing: ./examples/datutex/ex7.pp

Program Example7;

{ This program demonstrates the IsValidDateTime function }

Uses SysUtils, DateUtils;

Var

Y, Mo, D : Word;
H, M, S, MS : Word;
I : Integer;

Begin

For I:=1 to 10 do

begin

Y:=2000+Random(5);

Mo:=Random(15);

D:=Random(40);

H:=Random(32);

M:=Random(90);

S:=Random(90);

MS:=Random(1500);

If Not IsValidDateTime(Y, Mo, D, H, M, S, MS) then

Writeln(Y, '-', Mo, '-', D, ' ', H, ': ', M, ': ', S, '.', MS, ' is not a valid date/time.');

end;

End.

44.4.73 IsValidDateWeek

Synopsis: Check whether a given year/week/day of the week combination is a valid day.

Declaration: `function IsValidDateWeek(const AYear: Word; const AWeekOfYear: Word;
const ADayOfWeek: Word) : Boolean`

Visibility: default

Description: `IsValidDateWeek` returns `True` if `AYear`, `AWeekOfYear` and `ADayOfWeek` form a valid date indication, or `False` otherwise.

`AYear` must be in the range 1..9999 to be valid.

The `ADayOfWeek`, `ADayOfWeek` values are checked to see whether the combination falls within the valid range of weeks for `AYear`.

See also: `IsValidDate` (626), `IsValidTime` (629), `IsValidDateTime` (628), `IsValidDateDay` (626), `IsValidDateMonthWeek` (627)

Listing: `./examples/datutex/ex10.pp`

Program `Example10;`

{ This program demonstrates the IsValidDateWeek function }

Uses `SysUtils, DateUtils;`

Var

`Y,W,D : Word;
B : Boolean;`

Begin

```
For Y:=2000 to 2004 do
  begin
    B:=True;
    For W:=51 to 54 do
      For D:=1 to 7 do
        If B then
          begin
            B:=IsValidDateWeek(Y,W,D);
            If Not B then
              if (D=1) then
                Writeln(Y, ' has exactly ',W, ' weeks. ')
              else
                Writeln(Y, ' has ',W, ' weeks and ',D-1, ' days. ');
          end;
        end;
      end;
    end;
  end;
```

End.

44.4.74 IsValidTime

Synopsis: Check whether a set of values is a valid time indication.

Declaration: `function IsValidTime(const AHour: Word; const AMinute: Word;
const ASecond: Word; const AMilliSecond: Word)
: Boolean`

Visibility: default

Description: Check whether a set of values is a valid time indication.

44.4.75 JulianDateToDateTime

Synopsis: Convert a Julian date representation to a `TDateTime` value.

Declaration: `function JulianDateToDateTime(const AValue: Double) : TDateTime`

Visibility: default

Description: `JulianDateToDateTime` converts the Julian `AValue` date/time indication to a regular `TDateTime` date/time indication.

See also: `DateTimeToJulianDate` (597), `TryJulianDateToDateTime` (669), `DateTimeToModifiedJulianDate` (597), `TryModifiedJulianDateToDateTime` (669)

44.4.76 LocalTimeToUniversal

Synopsis: Convert local time to UTC time

Declaration: `function LocalTimeToUniversal(LT: TDateTime) : TDateTime`
`function LocalTimeToUniversal(LT: TDateTime; TZOffset: Integer)`
`: TDateTime`

Visibility: default

Description: `LocalTimeToUniversal` converts a local time indication to a universal time indication: it undoes the `TZOffset` time zone offset from the UT Universal time (UTC). If no `TZOffset` is specified, the local time offset as returned by `GetLocalTimeOffset` (589) is used.

Note that for times in the past or in the future, or for time zones with DST, omitting the `TZOffset` may lead to wrong results depending on `GetLocalTimeOffset` being able to compute the correct offset for the UT on the target platform. Currently only Windows Vista and newer return correct offsets for a given date. Older Windows systems or Linux/Unix return always the offset for the current date.

See also: `GetLocalTimeOffset` (589), `UniversalTimeToLocal` (671)

44.4.77 MacTimeStampToUnix

Synopsis: Convert a Mac timestamp to a Unix timestamp

Declaration: `function MacTimeStampToUnix(const AValue: Int64) : Int64`

Visibility: default

Description: `MacTimeStampToUnix` converts the Mac timestamp indication in `AValue` to a UNIX timestamp indication (epoch time)

Errors: None.

See also: `UnixTimeStampToMac` (671), `DateTimeToMac` (597), `MacToDateTime` (630)

44.4.78 MacToDateTime

Synopsis: Convert a Mac timestamp to a `TDateTime` timestamp

Declaration: `function MacToDateTime(const AValue: Int64) : TDateTime`

Visibility: default

Description: `MacToDateTime` converts the Mac timestamp indication in `AValue` to a valid `TDateTime` indication.

Errors: None.

See also: `UnixTimeStampToMac` (671), `DateTimeToMac` (597), `MacTimeStampToUnix` (630)

44.4.79 MilliSecondOf

Synopsis: Extract the millisecond part from a `TDateTime` value.

Declaration: `function MilliSecondOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MilliSecondOf` returns the second of the minute part of the `AValue` date/time indication. It is a number between 0 and 999.

For an example, see `YearOf` (684)

See also: `YearOf` (684), `WeekOf` (671), `MonthOf` (639), `DayOf` (598), `HourOf` (613), `MinuteOf` (635), `MilliSecondOf` (631)

44.4.80 MilliSecondOfDay

Synopsis: Calculate the number of milliseconds elapsed since the start of the day

Declaration: `function MilliSecondOfDay(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfDay` returns the number of milliseconds that have passed since the start of the Day (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 will return 0.

For an example, see the `HourOfDay` (614) function.

See also: `MilliSecondOfTheYear` (633), `MilliSecondOfTheMonth` (632), `MilliSecondOfTheWeek` (633), `MilliSecondOfTheHour` (631), `MilliSecondOfTheMinute` (632), `MilliSecondOfTheSecond` (632), `HourOfTheDay` (614), `MinuteOfTheDay` (635), `SecondOfTheDay` (653)

44.4.81 MilliSecondOfTheHour

Synopsis: Calculate the number of milliseconds elapsed since the start of the hour

Declaration: `function MilliSecondOfTheHour(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheHour` returns the number of milliseconds that have passed since the start of the Hour (HH:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.000 will return 0.

For an example, see the `MinuteOfTheHour` (635) function.

See also: `MilliSecondOfTheYear` (633), `MilliSecondOfTheMonth` (632), `MilliSecondOfTheWeek` (633), `MilliSecondOfTheDay` (631), `MilliSecondOfTheMinute` (632), `MilliSecondOfTheSecond` (632), `MinuteOfTheHour` (635), `SecondOfTheHour` (653)

44.4.82 MilliSecondOfTheMinute

Synopsis: Calculate the number of milliseconds elapsed since the start of the minute

Declaration: `function MilliSecondOfTheMinute(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheMinute` returns the number of milliseconds that have passed since the start of the Minute (HH:MM:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.000 will return 0.

For an example, see the `SecondOfTheMinute` (653) function.

See also: `MilliSecondOfTheYear` (633), `MilliSecondOfTheMonth` (632), `MilliSecondOfTheWeek` (633), `MilliSecondOfTheDay` (631), `MilliSecondOfTheHour` (631), `MilliSecondOfTheMinute` (632), `MilliSecondOfTheSecond` (632), `SecondOfTheMinute` (653)

44.4.83 MilliSecondOfTheMonth

Synopsis: Calculate number of milliseconds elapsed since the start of the month.

Declaration: `function MilliSecondOfTheMonth(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheMonth` returns the number of milliseconds that have passed since the start of the month (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the month will return 0.

For an example, see the `WeekOfTheMonth` (672) function.

See also: `WeekOfTheMonth` (672), `DayOfTheMonth` (599), `HourOfTheMonth` (614), `MinuteOfTheMonth` (636), `SecondOfTheMonth` (654), `MilliSecondOfTheMonth` (632)

44.4.84 MilliSecondOfTheSecond

Synopsis: Calculate the number of milliseconds elapsed since the start of the second

Declaration: `function MilliSecondOfTheSecond(const AValue: TDateTime) : Word`

Visibility: default

Description: `MilliSecondOfTheSecond` returns the number of milliseconds that have passed since the start of the second (HH:MM:SS.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:SS.000 will return 0.

See also: `MilliSecondOfTheYear` (633), `MilliSecondOfTheMonth` (632), `MilliSecondOfTheWeek` (633), `MilliSecondOfTheDay` (631), `MilliSecondOfTheHour` (631), `MilliSecondOfTheMinute` (632), `SecondOfTheMinute` (653)

Listing: `./examples/datutex/ex46.pp`

Program Example46;

{ This program demonstrates the MilliSecondOfTheSecond function }

Uses SysUtils, DateUtils;

Var

```

    N : TDateTime;

Begin
    N:=Now;
    WriteLn('MilliSecond of the Second : ',
            MilliSecondOfTheSecond(N));
End.

```

44.4.85 MilliSecondOfTheWeek

Synopsis: Calculate the number of milliseconds elapsed since the start of the week

Declaration: `function MilliSecondOfTheWeek(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheWeek` returns the number of milliseconds that have passed since the start of the Week (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the Week will return 0.

For an example, see the `DayOfTheWeek` (599) function.

See also: `MilliSecondOfTheYear` (633), `MilliSecondOfTheMonth` (632), `MilliSecondOfTheDay` (631), `MilliSecondOfTheHour` (631), `MilliSecondOfTheMinute` (632), `MilliSecondOfTheSecond` (632), `DayOfTheWeek` (599), `HourOfTheWeek` (614), `MinuteOfTheWeek` (636), `SecondOfTheWeek` (654)

44.4.86 MilliSecondOfTheYear

Synopsis: Calculate the number of milliseconds elapsed since the start of the year.

Declaration: `function MilliSecondOfTheYear(const AValue: TDateTime) : Int64`

Visibility: default

Description: `MilliSecondOfTheYear` returns the number of milliseconds that have passed since the start of the year (January 1, 00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.000 will return 0.

For an example, see the `WeekOfTheYear` (672) function.

See also: `WeekOfTheYear` (672), `DayOfTheYear` (599), `HourOfTheYear` (615), `MinuteOfTheYear` (637), `SecondOfTheYear` (654), `MilliSecondOfTheYear` (633)

44.4.87 MilliSecondsBetween

Synopsis: Calculate the number of whole milliseconds between two `TDateTime` values.

Declaration: `function MilliSecondsBetween(const ANow: TDateTime;
const AThen: TDateTime) : Int64`

Visibility: default

Description: `MilliSecondsBetween` returns the number of whole milliseconds between `ANow` and `AThen`. This means a fractional part of a millisecond is dropped.

See also: `YearsBetween` (684), `MonthsBetween` (640), `WeeksBetween` (673), `DaysBetween` (600), `HoursBetween` (615), `MinutesBetween` (637), `SecondsBetween` (655)

Listing: ./examples/datutex/ex62.pp

Program Example62;

{ This program demonstrates the MilliSecondsBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of milliseconds between ');

Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));

WriteLn(' : ', MilliSecondsBetween(ANow, AThen));

end;

Var

D1, D2 : TDateTime;

Begin

D1:=Now;

D2:=D1-(0.9*OneMilliSecond);

Test(D1, D2);

D2:=D1-(1.0*OneMilliSecond);

Test(D1, D2);

D2:=D1-(1.1*OneMilliSecond);

Test(D1, D2);

D2:=D1-(2.5*OneMilliSecond);

Test(D1, D2);

End.

44.4.88 MilliSecondSpan

Synopsis: Calculate the approximate number of milliseconds between two TDateTime values.

Declaration: function MilliSecondSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double

Visibility: default

Description: MilliSecondSpan returns the number of milliseconds between ANow and AThen. Since millisecond is the smallest fraction of a TDateTime indication, the returned number will always be an integer value.

See also: YearSpan (685), MonthSpan (640), WeekSpan (675), DaySpan (603), HourSpan (616), MinuteSpan (638), SecondSpan (655), MilliSecondsBetween (633)

Listing: ./examples/datutex/ex70.pp

Program Example70;

{ This program demonstrates the MilliSecondSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

```

Write('Number of milliseconds between ');
Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
WriteLn(' : ', MilliSecondSpan(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1:=Now;
  D2:=D1-(0.9*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(1.0*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(1.1*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(2.5*OneMilliSecond);
  Test(D1,D2);
End.

```

44.4.89 MinuteOf

Synopsis: Extract the minute part from a TDateTime value.

Declaration: `function MinuteOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOf` returns the minute of the hour part of the `AValue` date/time indication. It is a number between 0 and 59.

For an example, see [YearOf \(684\)](#)

See also: [YearOf \(684\)](#), [WeekOf \(671\)](#), [MonthOf \(639\)](#), [DayOf \(598\)](#), [HourOf \(613\)](#), [SecondOf \(652\)](#), [MilliSecondOf \(631\)](#)

44.4.90 MinuteOfDay

Synopsis: Calculate the number of minutes elapsed since the start of the day

Declaration: `function MinuteOfDay(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfDay` returns the number of minutes that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 will return 0.

For an example, see the [HourOfDay \(614\)](#) function.

See also: [MinuteOfTheYear \(637\)](#), [MinuteOfTheMonth \(636\)](#), [MinuteOfTheWeek \(636\)](#), [MinuteOfTheHour \(635\)](#), [HourOfTheDay \(614\)](#), [SecondOfTheDay \(653\)](#), [MilliSecondOfTheDay \(631\)](#)

44.4.91 MinuteOfTheHour

Synopsis: Calculate the number of minutes elapsed since the start of the hour

Declaration: `function MinuteOfTheHour(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheHour` returns the number of minutes that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:59 will return 0.

See also: `MinuteOfTheYear` ([637](#)), `MinuteOfTheMonth` ([636](#)), `MinuteOfTheWeek` ([636](#)), `MinuteOfTheDay` ([635](#)), `SecondOfTheHour` ([653](#)), `MilliSecondOfTheHour` ([631](#))

Listing: `./examples/datutex/ex44.pp`

Program `Example44`;

{ This program demonstrates the MinuteOfTheHour function }

Uses `SysUtils`, `DateUtils`;

Var

`N` : `TDateTime`;

Begin

`N:=Now`;

`WriteLn` ('Minute of the Hour : ', `MinuteOfTheHour(N)`);

`WriteLn` ('Second of the Hour : ', `SecondOfTheHour(N)`);

`WriteLn` ('MilliSecond of the Hour : ',
 `MilliSecondOfTheHour(N)`);

End.

44.4.92 MinuteOfTheMonth

Synopsis: Calculate number of minutes elapsed since the start of the month.

Declaration: `function MinuteOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheMonth` returns the number of minutes that have passed since the start of the Month (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` ([672](#)) function.

See also: `WeekOfTheMonth` ([672](#)), `DayOfTheMonth` ([599](#)), `HourOfTheMonth` ([614](#)), `MinuteOfTheMonth` ([636](#)), `SecondOfTheMonth` ([654](#)), `MilliSecondOfTheMonth` ([632](#))

44.4.93 MinuteOfTheWeek

Synopsis: Calculate the number of minutes elapsed since the start of the week

Declaration: `function MinuteOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheWeek` returns the number of minutes that have passed since the start of the week (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` ([599](#)) function.

See also: `MinuteOfTheYear` (637), `MinuteOfTheMonth` (636), `MinuteOfTheDay` (635), `MinuteOfTheHour` (635), `DayOfTheWeek` (599), `HourOfTheWeek` (614), `SecondOfTheWeek` (654), `MilliSecondOfTheWeek` (633)

44.4.94 MinuteOfTheYear

Synopsis: Calculate the number of minutes elapsed since the start of the year

Declaration: `function MinuteOfTheYear(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MinuteOfTheYear` returns the number of minutes that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:59 will return 0.

For an example, see the `WeekOfTheYear` (672) function.

See also: `WeekOfTheYear` (672), `DayOfTheYear` (599), `HourOfTheYear` (615), `MinuteOfTheYear` (637), `SecondOfTheYear` (654), `MilliSecondOfTheYear` (633)

44.4.95 MinutesBetween

Synopsis: Calculate the number of whole minutes between two `TDateTime` values.

Declaration: `function MinutesBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

Visibility: default

Description: `MinutesBetween` returns the number of whole minutes between `ANow` and `AThen`. This means the fractional part of a minute (seconds, milliseconds etc.) is dropped.

See also: `YearsBetween` (684), `MonthsBetween` (640), `WeeksBetween` (673), `DaysBetween` (600), `HoursBetween` (615), `SecondsBetween` (655), `MillisecondsBetween` (633)

Listing: `./examples/datutex/ex60.pp`

Program Example60;

{ This program demonstrates the MinutesBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

 Write('Number of minutes between ');

 Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));

 WriteLn(' : ', MinutesBetween(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Now;

 D2 := D1 - (59 * OneSecond);

```

Test(D1,D2);
D2:=D1-(61*OneSecond);
Test(D1,D2);
D2:=D1-(122*OneSecond);
Test(D1,D2);
D2:=D1-(306*OneSecond);
Test(D1,D2);
D2:=D1-(5.4*OneMinute);
Test(D1,D2);
D2:=D1-(2.5*OneMinute);
Test(D1,D2);
End.

```

44.4.96 MinuteSpan

Synopsis: Calculate the approximate number of minutes between two TDateTime values.

Declaration: `function MinuteSpan(const ANow: TDateTime; const AThen: TDateTime) : Double`

Visibility: default

Description: MinuteSpan returns the number of minutes between ANow and AThen, including any fractional parts of a minute.

See also: YearSpan (685), MonthSpan (640), WeekSpan (675), DaySpan (603), HourSpan (616), SecondSpan (655), MilliSecondSpan (634), MinutesBetween (637)

Listing: ./examples/datutex/ex68.pp

Program Example68;

{ This program demonstrates the MinuteSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

```

Write('Number of minutes between ');
Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
WriteLn(' : ', MinuteSpan(ANow, AThen));
end;

```

Var

```

D1, D2 : TDateTime;

```

Begin

```

D1:=Now;
D2:=D1-(59*OneSecond);
Test(D1,D2);
D2:=D1-(61*OneSecond);
Test(D1,D2);
D2:=D1-(122*OneSecond);
Test(D1,D2);
D2:=D1-(306*OneSecond);
Test(D1,D2);

```

```

D2:=D1-(5.4*OneMinute);
Test(D1,D2);
D2:=D1-(2.5*OneMinute);
Test(D1,D2);
End.
```

44.4.97 ModifiedJulianDateToDateTime

Synopsis: Convert a modified Julian date representation to a `TDateTime` value.

Declaration: `function ModifiedJulianDateToDateTime(const AValue: Double) : TDateTime`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: [DateTimeToJulianDate \(597\)](#), [JulianDateToDateTime \(630\)](#), [TryJulianDateToDateTime \(669\)](#), [DateTimeToModifiedJulianDate \(597\)](#), [TryModifiedJulianDateToDateTime \(669\)](#)

44.4.98 MonthOf

Synopsis: Extract the month from a given date.

Declaration: `function MonthOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MonthOf` returns the month part of the `AValue` date/time indication. It is a number between 1 and 12.

For an example, see [YearOf \(684\)](#)

See also: [YearOf \(684\)](#), [DayOf \(598\)](#), [WeekOf \(671\)](#), [HourOf \(613\)](#), [MinuteOf \(635\)](#), [SecondOf \(652\)](#), [MilliSecondOf \(631\)](#)

44.4.99 MonthOfTheYear

Synopsis: Extract the month of a `TDateTime` indication.

Declaration: `function MonthOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `MonthOfTheYear` extracts the month part of `AValue` and returns it. It is an alias for `MonthOf` ([639](#)), and is provided for completeness only, corresponding to the other `PartOfTheYear` functions.

For an example, see the [WeekOfTheYear \(672\)](#) function.

See also: [MonthOf \(639\)](#), [WeekOfTheYear \(672\)](#), [DayOfTheYear \(599\)](#), [HourOfTheYear \(615\)](#), [MinuteOfTheYear \(637\)](#), [SecondOfTheYear \(654\)](#), [MilliSecondOfTheYear \(633\)](#)

44.4.100 MonthsBetween

Synopsis: Calculate the number of whole months between two TDateTime values

[illegible]

Visibility: default

Description: `MonthsBetween` returns the number of whole months between `ANow` and `AThen`. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years). This means the fractional part of a month is dropped.

See also: [YearsBetween \(684\)](#), [WeeksBetween \(673\)](#), [DaysBetween \(600\)](#), [HoursBetween \(615\)](#), [MinutesBetween \(637\)](#), [SecondsBetween \(655\)](#), [MilliSecondsBetween \(633\)](#)

Listing: ./examples/datutex/ex56.pp

Program Example56;

```
{ This program demonstrates the MonthsBetween function }
```

Uses SysUtils , DateUtils ;

```
Procedure Test (ANow, AThen : TDateTime);
```

begin

```
Write ('Number of months between ');
Write (DateToStr(AThen), ' and ', DateToStr(ANow));
WriteLn (' : ', MonthsBetween(ANow, AThen));
end;
```

Var

D1, D2 : TDateTime;

Begin

```
D1:=Today ;
D2:=Today-364;
Test (D1,D2);
D2:=Today-365;
Test (D1,D2);
D2:=Today-366;
Test (D1,D2);
D2:=Today-390;
Test (D1,D2);
D2:=Today-368;
Test (D1,D2);
D2:=Today-1000;
Test (D1,D2);
```

End.

44.4.101 MonthSpan

Synopsis: Calculate the approximate number of months between two TDateTime values.

```
Declaration: function MonthSpan(const ANow: TDateTime; const AThen: TDateTime)
                : Double
```

Visibility: default

Description: `MonthSpan` returns the number of month between `ANow` and `AThen`, including any fractional parts of a month. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years).

See also: `YearSpan` (685), `WeekSpan` (675), `DaySpan` (603), `HourSpan` (616), `MinuteSpan` (638), `SecondSpan` (655), `MilliSecondSpan` (634), `MonthsBetween` (640)

Listing: `./examples/datutex/ex64.pp`

Program `Example64`;

{ This program demonstrates the MonthSpan function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime);`

begin

Write('Number of months between ');
 Write(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));
 WriteLn(' : ', `MonthSpan`(ANow, AThen));
end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Today;
 D2 := Today - 364;
 Test(D1, D2);
 D2 := Today - 365;
 Test(D1, D2);
 D2 := Today - 366;
 Test(D1, D2);
 D2 := Today - 390;
 Test(D1, D2);
 D2 := Today - 368;
 Test(D1, D2);
 D2 := Today - 1000;
 Test(D1, D2);

End.

44.4.102 NthDayOfWeek

Synopsis: Calculate which occurrence of weekday in the month a given day represents

Declaration: `function NthDayOfWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `NthDayOfWeek` returns the occurrence of the weekday of `AValue` in the month. This is the N-th time that this weekday occurs in the month (e.g. the third Saturday of the month).

See also: `EncodeDateMonthWeek` (607), `#rtl.sysutils.DayOfWeek` (1678), `DecodeDayOfWeekInMonth` (606), `EncodeDayOfWeekInMonth` (608), `TryEncodeDayOfWeekInMonth` (665)

Listing: ./examples/datutex/ex104.pp

Program Example104;

{ This program demonstrates the NthDayOfWeek function }

Uses SysUtils, DateUtils;

Begin

Write('Today is the ', NthDayOfWeek(Today), '-th ');

WriteLn(formatdateTime('dddd', Today), ' of the month.');

End.

44.4.103 PeriodBetween

Synopsis: Return the period (in years, months, days) between two dates

Declaration: procedure PeriodBetween(const ANow: TDateTime; const AThen: TDateTime;
out Years: Word; out months: Word;
out days: Word)

Visibility: default

Description: PeriodBetween returns the timespan between 2 dates (ANow and AThen), expressed as a number of years, months and days in the parameters Years, months and days. Only complete years, months and days are reported.

If ANow is before AThen, their values are reversed so the result is always positive.

See also: YearsBetween (684), MonthsBetween (640), WeeksBetween (673), DaysBetween (600)

44.4.104 PreviousDayOfWeek

Synopsis: Given a day of the week, return the previous day of the week.

Declaration: function PreviousDayOfWeek(DayOfWeek: Word) : Word

Visibility: default

Description: PreviousDayOfWeek returns the previous day of the week. If the current day is the first day of the week (1) then the last day will be returned (7).

Remark Note that the days of the week are in ISO notation, i.e. 1-based.

See also: Yesterday (686)

Listing: ./examples/datutex/ex22.pp

Program Example22;

{ This program demonstrates the PreviousDayOfWeek function }

Uses SysUtils, DateUtils;

Var

D : Word;

Begin

```

    For D:=1 to 7 do
        Writeln('Previous day of ',D,' is : ',PreviousDayOfWeek(D));
    End.

```

44.4.105 RecodeDate

Synopsis: Replace date part of a TDateTime value with another date.

Declaration: `function RecodeDate(const AValue: TDateTime; const AYear: Word; const AMonth: Word; const ADay: Word) : TDateTime`

Visibility: default

Description: `RecodeDate` replaces the date part of the timestamp `AValue` with the date specified in `AYear`, `AMonth`, `ADay`. All other parts (the time part) of the date/time stamp are left untouched.

Errors: If one of the `AYear`, `AMonth`, `ADay` values is not within a valid range then an `EConvertError` exception is raised.

See also: `RecodeYear` (649), `RecodeMonth` (647), `RecodeDay` (644), `RecodeHour` (645), `RecodeMinute` (646), `RecodeSecond` (647), `RecodeDate` (643), `RecodeTime` (648), `RecodeDateTime` (643)

Listing: ./examples/datutex/ex94.pp

Program Example94;

{ This program demonstrates the RecodeDate function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmmm yyyy hh:nn:ss';

Var

 S : AnsiString;

Begin

 S:=**FormatDateTime**(Fmt,RecodeDate(**Now**,2001,1,1));

Writeln('This moment on the first of the millenium : ',S);

End.

44.4.106 RecodeDateTime

Synopsis: Replace selected parts of a TDateTime value with other values

Declaration: `function RecodeDateTime(const AValue: TDateTime; const AYear: Word; const AMonth: Word; const ADay: Word; const AHour: Word; const AMinute: Word; const ASecond: Word; const AMilliSecond: Word) : TDateTime`

Visibility: default

Description: `RecodeDateTime` replaces selected parts of the timestamp `AValue` with the date/time values specified in `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond`. If any of these values equals the predefined constant `RecodeLeaveFieldAsIs` (591), then the corresponding part of the date/time stamp is left untouched.

Errors: If one of the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecondAMilliSecond` is not within a valid range (`RecodeLeaveFieldAsIs` excepted) then an `EConvertError` exception is raised.

See also: [RecodeYear \(649\)](#), [RecodeMonth \(647\)](#), [RecodeDay \(644\)](#), [RecodeHour \(645\)](#), [RecodeMinute \(646\)](#), [RecodeSecond \(647\)](#), [RecodeMilliSecond \(645\)](#), [RecodeDate \(643\)](#), [RecodeTime \(648\)](#), [TryRecodeDateTime \(670\)](#)

Listing: `./examples/datutex/ex96.pp`

Program `Example96`;

{ This program demonstrates the RecodeDateTime function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = 'dddd dd mmm yyyy hh:nn:ss';`

Var

`S : AnsiString;`

`D : TDateTime ;`

Begin

`D:=Now;`

`D:=RecodeDateTime(D,2000,2,RecodeLeaveFieldAsIs,0,0,0,0);`

`S:=FormatDateTime(Fmt,D);`

`WriteLn('This moment in februari 2000 : ',S);`

End.

44.4.107 RecodeDay

Synopsis: Replace day part of a `TDateTime` value with another day.

Declaration: `function RecodeDay(const AValue: TDateTime; const ADay: Word)`
`: TDateTime`

Visibility: `default`

Description: `RecodeDay` replaces the `Day` part of the timestamp `AValue` with `ADay`. All other parts of the date/time stamp are left untouched.

Errors: If the `ADay` value is not within a valid range (1 till the number of days in the month) then an `EConvertError` exception is raised.

See also: [RecodeYear \(649\)](#), [RecodeMonth \(647\)](#), [RecodeHour \(645\)](#), [RecodeMinute \(646\)](#), [RecodeSecond \(647\)](#), [RecodeMilliSecond \(645\)](#), [RecodeDate \(643\)](#), [RecodeTime \(648\)](#), [RecodeDateTime \(643\)](#)

Listing: `./examples/datutex/ex89.pp`

Program `Example89`;

{ This program demonstrates the RecodeDay function }

Uses `SysUtils`, `DateUtils`;

Const

Errors: If the `AMilliSecond` value is not within a valid range (0..999) then an `EConvertError` exception is raised.

See also: [RecodeYear \(649\)](#), [RecodeMonth \(647\)](#), [RecodeDay \(644\)](#), [RecodeHour \(645\)](#), [RecodeMinute \(646\)](#), [RecodeSecond \(647\)](#), [RecodeDate \(643\)](#), [RecodeTime \(648\)](#), [RecodeDateTime \(643\)](#)

Listing: ./examples/datutex/ex93.pp

Program Example93;

{ This program demonstrates the RecodeMilliSecond function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Var

 S : AnsiString;

Begin

 S := **FormatDateTime**(Fmt, RecodeMilliSecond(**Now**, 0));

WriteIn('This moment, milliseconds stripped : ', S);

End.

44.4.110 RecodeMinute

Synopsis: Replace minutes part of a `TDateTime` value with another minute.

Declaration: `function RecodeMinute(const AValue: TDateTime; const AMinute: Word): TDateTime`

Visibility: default

Description: `RecodeMinute` replaces the Minute part of the timestamp `AValue` with `AMinute`. All other parts of the date/time stamp are left untouched.

Errors: If the `AMinute` value is not within a valid range (0..59) then an `EConvertError` exception is raised.

See also: [RecodeYear \(649\)](#), [RecodeMonth \(647\)](#), [RecodeDay \(644\)](#), [RecodeHour \(645\)](#), [RecodeSecond \(647\)](#), [RecodeMilliSecond \(645\)](#), [RecodeDate \(643\)](#), [RecodeTime \(648\)](#), [RecodeDateTime \(643\)](#)

Listing: ./examples/datutex/ex91.pp

Program Example91;

{ This program demonstrates the RecodeMinute function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

 S : AnsiString;

Begin

```
S:=FormatDateTime(Fmt, RecodeMinute(Now, 0));
WriteLn('This moment in the first minute of the hour: ', S);
```

```
End.
```

44.4.111 RecodeMonth

Synopsis: Replace month part of a TDateTime value with another month.

Declaration: `function RecodeMonth(const AValue: TDateTime; const AMonth: Word) : TDateTime`

Visibility: default

Description: RecodeMonth replaces the Month part of the timestamp AValue with AMonth. All other parts of the date/time stamp are left untouched.

Errors: If the AMonth value is not within a valid range (1..12) then an EConvertError exception is raised.

See also: RecodeYear (649), RecodeDay (644), RecodeHour (645), RecodeMinute (646), RecodeSecond (647), RecodeMilliSecond (645), RecodeDate (643), RecodeTime (648), RecodeDateTime (643)

Listing: ./examples/datutex/ex88.pp

Program Example88;

```
{ This program demonstrates the RecodeMonth function }
```

```
Uses SysUtils, DateUtils;
```

Const

```
Fmt = 'dddd dd mmm yyyy hh:nn:ss';
```

Var

```
S : AnsiString;
```

Begin

```
S:=FormatDateTime(Fmt, RecodeMonth(Now, 5));
WriteLn('This moment in May : ', S);
```

```
End.
```

44.4.112 RecodeSecond

Synopsis: Replace seconds part of a TDateTime value with another second.

Declaration: `function RecodeSecond(const AValue: TDateTime; const ASecond: Word) : TDateTime`

Visibility: default

Description: RecodeSecond replaces the Second part of the timestamp AValue with ASecond. All other parts of the date/time stamp are left untouched.

Errors: If the ASecond value is not within a valid range (0..59) then an EConvertError exception is raised.

See also: [RecodeYear \(649\)](#), [RecodeMonth \(647\)](#), [RecodeDay \(644\)](#), [RecodeHour \(645\)](#), [RecodeMinute \(646\)](#), [RecodeMilliSecond \(645\)](#), [RecodeDate \(643\)](#), [RecodeTime \(648\)](#), [RecodeDateTime \(643\)](#)

Listing: ./examples/datutex/ex92.pp

```

Program Example92;

{ This program demonstrates the RecodeSecond function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmmm yyyy hh:nn:ss';

Var
    S : AnsiString;

Begin
    S:=FormatDateTime(Fmt, RecodeSecond(Now, 0));
    WriteLn('This moment, seconds stripped : ', S);
End.

```

44.4.113 RecodeTime

Synopsis: Replace time part of a TDateTime value with another time.

Declaration: `function RecodeTime(const AValue: TDateTime; const AHour: Word; const AMinute: Word; const ASecond: Word; const AMilliSecond: Word) : TDateTime`

Visibility: default

Description: RecodeTime replaces the time part of the timestamp AValue with the date specified in AHour, AMinute, ASecond and AMilliSecond. All other parts (the date part) of the date/time stamp are left untouched.

Errors: If one of the values AHour, AMinute, ASecond, AMilliSecond is not within a valid range then an EConvertError exception is raised.

See also: [RecodeYear \(649\)](#), [RecodeMonth \(647\)](#), [RecodeDay \(644\)](#), [RecodeHour \(645\)](#), [RecodeMinute \(646\)](#), [RecodeSecond \(647\)](#), [RecodeMilliSecond \(645\)](#), [RecodeDate \(643\)](#), [RecodeDateTime \(643\)](#)

Listing: ./examples/datutex/ex95.pp

```

Program Example95;

{ This program demonstrates the RecodeTime function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmmm yyyy hh:nn:ss';

Var
    S : AnsiString;

Begin

```

```

S:=FormatDateTime(Fmt, RecodeTime(Now, 8, 0, 0, 0));
WriteLn('Today, 8 AM : ', S);
End.

```

44.4.114 RecodeYear

Synopsis: Replace year part of a TDateTime value with another year.

Declaration: `function RecodeYear(const AValue: TDateTime; const AYear: Word) : TDateTime`

Visibility: default

Description: `RecodeYear` replaces the year part of the timestamp `AValue` with `AYear`. All other parts of the date/time stamp are left untouched.

Errors: If the `AYear` value is not within a valid range (1..9999) then an `EConvertError` exception is raised.

See also: [RecodeMonth \(647\)](#), [RecodeDay \(644\)](#), [RecodeHour \(645\)](#), [RecodeMinute \(646\)](#), [RecodeSecond \(647\)](#), [RecodeMilliSecond \(645\)](#), [RecodeDate \(643\)](#), [RecodeTime \(648\)](#), [RecodeDateTime \(643\)](#)

Listing: `./examples/datutex/ex87.pp`

Program `Example87;`

{ This program demonstrates the RecodeYear function }

Uses `SysUtils, DateUtils;`

Const

`Fmt = 'dddd dd mmm yyyy hh:nn:ss';`

Var

`S : AnsiString;`

Begin

`S:=FormatDateTime(Fmt, RecodeYear(Now, 1999));`

`WriteLn('This moment in 1999 : ', S);`

End.

44.4.115 SameDate

Synopsis: Check whether two TDateTime values have the same date part.

Declaration: `function SameDate(const A: TDateTime; const B: TDateTime) : Boolean`

Visibility: default

Description: `SameDate` compares the date parts of two timestamps `A` and `B` and returns `True` if they are equal, `False` if they are not.

The function simply checks whether [CompareDate \(592\)](#) returns zero.

See also: [CompareDateTime \(593\)](#), [CompareDate \(592\)](#), [CompareTime \(594\)](#), [SameDateTime \(650\)](#), [SameTime \(651\)](#)

Listing: ./examples/datutex/ex102.pp

Program Example102;

{ This program demonstrates the SameDate function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

begin

 Write(FormatDateTime(Fmt,D1), ' is the same date as ');

 WriteLn(FormatDateTime(Fmt,D2), ' : ', SameDate(D1,D2));

end;

Var

 D,N : TDateTime;

Begin

 D:=Today;

 N:=Now;

 Test(D,D);

 Test(N,N);

 Test(N+1,N);

 Test(N-1,N);

 Test(N+OneSecond,N);

 Test(N-OneSecond,N);

End.

44.4.116 SameDateTime

Synopsis: Check whether two TDateTime values have the same date and time parts.

Declaration: function SameDateTime(const A: TDateTime; const B: TDateTime) : Boolean

Visibility: default

Description: SameDateTime compares the date/time parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareDateTime ([593](#)) returns zero.

See also: CompareDateTime ([593](#)), CompareDate ([592](#)), CompareTime ([594](#)), SameDate ([649](#)), SameTime ([651](#))

Listing: ./examples/datutex/ex101.pp

Program Example101;

{ This program demonstrates the SameDateTime function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';

```

Procedure Test(D1,D2 : TDateTime);

begin
  Write(FormatDateTime(Fmt,D1),' is the same datetime as ');
  WriteLn(FormatDateTime(Fmt,D2),' : ',SameDateTime(D1,D2));
end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(N+1,N);
  Test(N-1,N);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

44.4.117 SameTime

Synopsis: Check whether two TDateTime values have the same time part.

Declaration: function SameTime(const A: TDateTime; const B: TDateTime) : Boolean

Visibility: default

Description: SameTime compares the time parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareTime (594) returns zero.

See also: CompareDateTime (593), CompareDate (592), CompareTime (594), SameDateTime (650), SameDate (649)

Listing: ./examples/datutex/ex103.pp

Program Example102;

{ This program demonstrates the SameTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

begin

Write(FormatDateTime(Fmt,D1),' is the same time as ');

WriteLn(FormatDateTime(Fmt,D2),' : ',SameTime(D1,D2));

end;

Var

D,N : TDateTime;

```

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(N+1,N);
  Test(N-1,N);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

44.4.118 ScanDateTime

Synopsis: Scans a string for a TDateTime pattern and returns the date/time

Declaration:

```

function ScanDateTime(const Pattern: string; const s: string;
                      const fmt: TFormatSettings; startpos: Integer)
                      : TDateTime; Overload
function ScanDateTime(const Pattern: string; const s: string;
                      startpos: Integer) : TDateTime; Overload

```

Visibility: default

Description: ScanDateTime scans string S for the date/time pattern Pattern, starting at position StartPos (default 1). Optionally, the format settings fmt can be specified.

In effect, this function does the opposite of what FormatDateTime (1721) does. The Pattern variable must contain a valid date/time pattern: note that not all possible formatdatetime patterns can be recognized, e.g., hn cannot be detected properly.

- There is a special placeholder: a '?' will match any character in the input string.
- Note that the / and : character will be replaced by the actual date and time separator.
- Similarly, the 'am/pm' and 'a/p' will be replaced with the actual AM/PM indicators.
- A TAB character (ASCII Code 9) will match any whitespace block

Errors: In case of an error, a EConvertError (1800) exception is raised.

See also: FormatDateTime (1721)

44.4.119 SecondOf

Synopsis: Extract the second part from a TDateTime value.

Declaration:

```

function SecondOf(const AValue: TDateTime) : Word

```

Visibility: default

Description: SecondOf returns the second of the minute part of the AValue date/time indication. It is a number between 0 and 59.

For an example, see YearOf (684)

See also: YearOf (684), WeekOf (671), MonthOf (639), DayOf (598), HourOf (613), MinuteOf (635), MilliSecondOf (631)

44.4.120 SecondOfDay

Synopsis: Calculate the number of seconds elapsed since the start of the day

Declaration: `function SecondOfDay(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfDay` returns the number of seconds that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 return 0.

For an example, see the `HourOfDay` (614) function.

See also: `SecondOfYear` (654), `SecondOfMonth` (654), `SecondOfWeek` (654), `SecondOfTheHour` (653), `SecondOfTheMinute` (653), `HourOfDay` (614), `MinuteOfDay` (635), `MilliSecondOfTheDay` (631)

44.4.121 SecondOfTheHour

Synopsis: Calculate the number of seconds elapsed since the start of the hour

Declaration: `function SecondOfTheHour(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOfTheHour` returns the number of seconds that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.999 return 0.

For an example, see the `MinuteOfTheHour` (635) function.

See also: `SecondOfYear` (654), `SecondOfMonth` (654), `SecondOfWeek` (654), `SecondOfDay` (653), `SecondOfTheMinute` (653), `MinuteOfTheHour` (635), `MilliSecondOfTheHour` (631)

44.4.122 SecondOfTheMinute

Synopsis: Calculate the number of seconds elapsed since the start of the minute

Declaration: `function SecondOfTheMinute(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOfTheMinute` returns the number of seconds that have passed since the start of the minute (HH:MM:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.999 return 0.

See also: `SecondOfYear` (654), `SecondOfMonth` (654), `SecondOfWeek` (654), `SecondOfDay` (653), `SecondOfTheHour` (653), `MilliSecondOfTheMinute` (632)

Listing: `./examples/datutex/ex45.pp`

Program Example45;

{ This program demonstrates the SecondOfTheMinute function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

```

Begin
  N:=Now;
  WriteLn('Second of the Minute      : ',SecondOfTheMinute(N));
  WriteLn('MilliSecond of the Minute : ',
          MilliSecondOfTheMinute(N));
End.

```

44.4.123 SecondOfTheMonth

Synopsis: Calculate number of seconds elapsed since the start of the month.

Declaration: `function SecondOfTheMonth(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheMonth` returns the number of seconds that have passed since the start of the month (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (672) function.

See also: `WeekOfTheMonth` (672), `DayOfTheMonth` (599), `HourOfTheMonth` (614), `MinuteOfTheMonth` (636), `MilliSecondOfTheMonth` (632)

44.4.124 SecondOfTheWeek

Synopsis: Calculate the number of seconds elapsed since the start of the week

Declaration: `function SecondOfTheWeek(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheWeek` returns the number of seconds that have passed since the start of the week (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (599) function.

See also: `SecondOfTheYear` (654), `SecondOfTheMonth` (654), `SecondOfTheDay` (653), `SecondOfTheHour` (653), `SecondOfTheMinute` (653), `DayOfTheWeek` (599), `HourOfTheWeek` (614), `MinuteOfTheWeek` (636), `MilliSecondOfTheWeek` (633)

44.4.125 SecondOfTheYear

Synopsis: Calculate the number of seconds elapsed since the start of the year.

Declaration: `function SecondOfTheYear(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheYear` returns the number of seconds that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.999 will return 0.

For an example, see the `WeekOfTheYear` (672) function.

See also: `WeekOfTheYear` (672), `DayOfTheYear` (599), `HourOfTheYear` (615), `MinuteOfTheYear` (637), `SecondOfTheYear` (654), `MilliSecondOfTheYear` (633)

44.4.126 SecondsBetween

Synopsis: Calculate the number of whole seconds between two TDateTime values.

Declaration: `function SecondsBetween(const ANow: TDateTime; const AThen: TDateTime)
: Int64`

Visibility: default

Description: `SecondsBetween` returns the number of whole seconds between `ANow` and `AThen`. This means the fractional part of a second (milliseconds etc.) is dropped.

See also: `YearsBetween` (684), `MonthsBetween` (640), `WeeksBetween` (673), `DaysBetween` (600), `HoursBetween` (615), `MinutesBetween` (637), `MillisecondsBetween` (633)

Listing: ./examples/datutex/ex61.pp

Program Example61 ;

{ This program demonstrates the SecondsBetween function }

Uses SysUtils , DateUtils ;

Procedure Test (ANow, AThen : TDateTime) ;

begin

 Write ('Number of seconds between ') ;

 Write (TimeToStr (AThen) , ' and ' , TimeToStr (ANow)) ;

 WriteLn (' : ' , SecondsBetween (ANow , AThen)) ;

end ;

Var

 D1, D2 : TDateTime ;

Begin

 D1 := Now ;

 D2 := D1 - (999 * OneMilliSecond) ;

 Test (D1 , D2) ;

 D2 := D1 - (1001 * OneMilliSecond) ;

 Test (D1 , D2) ;

 D2 := D1 - (2001 * OneMilliSecond) ;

 Test (D1 , D2) ;

 D2 := D1 - (5001 * OneMilliSecond) ;

 Test (D1 , D2) ;

 D2 := D1 - (5.4 * OneSecond) ;

 Test (D1 , D2) ;

 D2 := D1 - (2.5 * OneSecond) ;

 Test (D1 , D2) ;

End.

44.4.127 SecondSpan

Synopsis: Calculate the approximate number of seconds between two TDateTime values.

Declaration: `function SecondSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double`

Visibility: default

Description: `SecondSpan` returns the number of seconds between `ANow` and `AThen`, including any fractional parts of a second.

See also: `YearSpan` (685), `MonthSpan` (640), `WeekSpan` (675), `DaySpan` (603), `HourSpan` (616), `MinuteSpan` (638), `MilliSecondSpan` (634), `SecondsBetween` (655)

Listing: `./examples/datutex/ex69.pp`

Program `Example69`;

{ This program demonstrates the SecondSpan function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime)`;

begin
 Write('Number of seconds between ');
 Write(**TimeToStr**(AThen), ' and ', **TimeToStr**(ANow));
 WriteLn(' : ', `SecondSpan`(ANow, AThen));
end;

Var
 D1, D2 : TDateTime;

Begin
 D1 := **Now**;
 D2 := D1 - (999 * `OneMilliSecond`);
 Test(D1, D2);
 D2 := D1 - (1001 * `OneMilliSecond`);
 Test(D1, D2);
 D2 := D1 - (2001 * `OneMilliSecond`);
 Test(D1, D2);
 D2 := D1 - (5001 * `OneMilliSecond`);
 Test(D1, D2);
 D2 := D1 - (5.4 * `OneSecond`);
 Test(D1, D2);
 D2 := D1 - (2.5 * `OneSecond`);
 Test(D1, D2);

End.

44.4.128 StartOfADay

Synopsis: Return the start of a day as a `TDateTime` value, given a day indication

Declaration: `function StartOfADay(const AYear: Word; const AMonth: Word;
 const ADay: Word) : TDateTime; Overload`
 `function StartOfADay(const AYear: Word; const ADayOfYear: Word)
 : TDateTime; Overload`

Visibility: `default`

Description: `StartOfADay` returns a `TDateTime` value with the date/time indication of the start (0:0:0.000) of the day given by `AYear`, `AMonth`, `ADay`.

The day may also be indicated with a `AYear`, `ADayOfYear` pair.

See also: [StartOfDay \(659\)](#), [StartOfTheWeek \(660\)](#), [StartOfAWeek \(658\)](#), [StartOfAMonth \(657\)](#), [StartOfTheMonth \(659\)](#), [EndOfTheWeek \(612\)](#), [EndOfAWeek \(610\)](#), [EndOfTheYear \(613\)](#), [EndOfAYear \(611\)](#), [EndOfTheMonth \(612\)](#), [EndOfAMonth \(609\)](#), [EndOfTheDay \(611\)](#), [EndOfADay \(609\)](#)

Listing: ./examples/datutex/ex38.pp

Program Example38;

{ This program demonstrates the StartOfADay function }

Uses SysUtils, DateUtils;

Const

Fmt = ' "Start of the day : "dd mmm yyyy hh:nn:ss ';

Var

Y,M,D : Word;

Begin

Y:=YearOf(Today);

M:=MonthOf(Today);

D:=DayOf(Today);

WriteIn(FormatDateTime(Fmt, StartOfADay(Y,M,D)));

DecodeDateDay(Today,Y,D);

WriteIn(FormatDateTime(Fmt, StartOfADay(Y,D)));

End.

44.4.129 StartOfAMonth

Synopsis: Return first date of month, given a year/month pair.

Declaration: function StartOfAMonth(const AYear: Word; const AMonth: Word)
: TDateTime

Visibility: default

Description: StartOfAMonth returns a TDateTime value with the date of the first day of the month indicated by the AYear, AMonth pair.

See also: [StartOfTheMonth \(659\)](#), [EndOfTheMonth \(612\)](#), [EndOfAMonth \(609\)](#), [EndOfTheYear \(613\)](#), [EndOfAYear \(611\)](#), [StartOfAWeek \(658\)](#), [StartOfTheWeek \(660\)](#)

Listing: ./examples/datutex/ex30.pp

Program Example30;

{ This program demonstrates the StartOfAMonth function }

Uses SysUtils, DateUtils;

Const

Fmt = ' "First day of this month : "dd mmm yyyy ';

Var

Y,M : Word;

Begin

Y:=YearOf(Today);

```

M:=MonthOf( Today );
WriteIn (FormatDateTime (Fmt, StartOfAMonth (Y,M) ));
End.

```

44.4.130 StartOfAWeek

Synopsis: Return a day of the week, given a year, week and day in the week.

Declaration: `function StartOfAWeek(const AYear: Word; const AWeekOfYear: Word; const ADayOfWeek: Word) : TDateTime`
`function StartOfAWeek(const AYear: Word; const AWeekOfYear: Word) : TDateTime`

Visibility: default

Description: `StartOfAWeek` returns a `TDateTime` value with the date of the indicated day of the week indicated by the `AYear`, `AWeek`, `ADayOfWeek` values.

The default value for `ADayOfWeek` is 1.

See also: `StartOfTheWeek` (660), `EndOfTheWeek` (612), `EndOfAWeek` (610), `StartOfAMonth` (657), `EndOfTheYear` (613), `EndOfAYear` (611), `EndOfTheMonth` (612), `EndOfAMonth` (609)

Listing: `./examples/datutex/ex34.pp`

Program Example34;

{ This program demonstrates the StartOfAWeek function }

Uses SysUtils, DateUtils;

Const

```

Fmt = 'First day of this week : "dd mmm yyyy hh:nn:ss';
Fmt2 = 'Second day of this week : "dd mmm yyyy hh:nn:ss';

```

Var

```

Y,W : Word;

```

Begin

```

Y:=YearOf( Today );
W:=WeekOf( Today );
WriteIn (FormatDateTime (Fmt, StartOfAWeek (Y,W) ));
WriteIn (FormatDateTime (Fmt2, StartOfAWeek (Y,W,2) ));

```

End.

44.4.131 StartOfAYear

Synopsis: Return the first day of a given year.

Declaration: `function StartOfAYear(const AYear: Word) : TDateTime`

Visibility: default

Description: `StartOfAYear` returns a `TDateTime` value with the date of the first day of the year `AYear` (January 1).

See also: [StartOfTheYear \(660\)](#), [EndOfTheYear \(613\)](#), [EndOfAYear \(611\)](#), [EndOfTheMonth \(612\)](#), [EndOfAMonth \(609\)](#), [StartOfAWeek \(658\)](#), [StartOfTheWeek \(660\)](#)

Listing: ./examples/datutex/ex26.pp

Program Example26;

{ This program demonstrates the StartOfAYear function }

Uses SysUtils, DateUtils;

Const

Fmt = 'First day of this year : "dd mmm yyyy ';

Begin

WriteIn (FormatDateTime (Fmt, StartOfAYear (YearOf (Today))));

End.

44.4.132 StartOfTheDay

Synopsis: Calculate the start of the day as a TDateTime value, given a moment in the day.

Declaration: function StartOfTheDay (const AValue: TDateTime) : TDateTime

Visibility: default

Description: StartOfTheDay extracts the date part of AValue and returns a TDateTime value with the date/time indication of the start (0:0:0.000) of this day.

See also: [StartOfADay \(656\)](#), [StartOfTheWeek \(660\)](#), [StartOfAWeek \(658\)](#), [StartOfAMonth \(657\)](#), [StartOfTheMonth \(659\)](#), [EndOfTheWeek \(612\)](#), [EndOfAWeek \(610\)](#), [EndOfTheYear \(613\)](#), [EndOfAYear \(611\)](#), [EndOfTheMonth \(612\)](#), [EndOfAMonth \(609\)](#), [EndOftheDay \(611\)](#), [EndOfADay \(609\)](#)

Listing: ./examples/datutex/ex36.pp

Program Example36;

{ This program demonstrates the StartOfTheDay function }

Uses SysUtils, DateUtils;

Const

Fmt = 'Start of the day : "dd mmm yyyy hh:nn:ss ';

Begin

WriteIn (FormatDateTime (Fmt, StartOfTheDay (Today)));

End.

44.4.133 StartOfTheMonth

Synopsis: Calculate the first day of the month, given a date in that month.

Declaration: function StartOfTheMonth (const AValue: TDateTime) : TDateTime

Visibility: default

Description: `StartOfTheMonth` extracts the year and month parts of `AValue` and returns a `TDateTime` value with the date of the first day of that year and month as the `StartOfAMonth` (657) function.

See also: `StartOfAMonth` (657), `EndOfTheYear` (613), `EndOfAYear` (611), `EndOfTheMonth` (612), `EndOfAMonth` (609), `StartOfAWeek` (658), `StartOfTheWeek` (660)

Listing: `./examples/datutex/ex28.pp`

Program `Example28`;

{ This program demonstrates the StartOfTheMonth function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = ' "First day of this month : "dd mmmm yyyy ';`

Begin

`WriteLn (FormatDateTime (Fmt, StartOfTheMonth (Today)));`

End.

44.4.134 StartOfTheWeek

Synopsis: Return the first day of the week, given a date.

Declaration: `function StartOfTheWeek(const AValue: TDateTime) : TDateTime`

Visibility: `default`

Description: `StartOfTheWeek` extracts the year and week parts of `AValue` and returns a `TDateTime` value with the date of the first day of that week as the `StartOfAWeek` (658) function.

See also: `StartOfAWeek` (658), `EndOfTheWeek` (612), `EndOfAWeek` (610), `StartOfAMonth` (657), `EndOfTheYear` (613), `EndOfAYear` (611), `EndOfTheMonth` (612), `EndOfAMonth` (609)

Listing: `./examples/datutex/ex32.pp`

Program `Example32`;

{ This program demonstrates the StartOfTheWeek function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = ' "First day of this week : "dd mmmm yyyy ';`

Begin

`WriteLn (FormatDateTime (Fmt, StartOfTheWeek (Today)));`

End.

44.4.135 StartOfTheYear

Synopsis: Return the first day of the year, given a date in this year.

Declaration: `function StartOfTheYear(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `StartOfTheYear` extracts the year part of `AValue` and returns a `TDateTime` value with the date of the first day of that year (January 1), as the `StartOfAYear` (658) function.

See also: `StartOfAYear` (658), `EndOfTheYear` (613), `EndOfAYear` (611)

Listing: `./examples/datutex/ex24.pp`

Program `Example24`;

{ This program demonstrates the StartOfTheYear function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = 'First day of this year : "dd mmm yyyy';`

Begin

`WriteIn (FormatDateTime (Fmt, StartOfTheYear (Today)));`

End.

44.4.136 TimeInRange

Synopsis: Checks whether a time value is in a given range

Declaration: `function TimeInRange (ATime: TTime; AStartTime: TTime; AEndTime: TTime; AInclusive: Boolean) : Boolean`

Visibility: default

Description: `TimeInRange` checks whether the value `ATime` lies between `AStartTime` and `AEndTime`, and returns `True` if it is. When `AINclusive` is `True` (the default), then the limits are included. When `AINclusive` is `False`, the limits are excluded. Only the time part of the 3 parameters is considered.

Errors: The `AStartTime` value must be before `AEndTime`, but no check is performed.

See also: `DateInRange` (595), `DateTimeInRange` (596)

44.4.137 TimeOf

Synopsis: Extract the time part from a `TDateTime` indication.

Declaration: `function TimeOf (const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `TimeOf` extracts the time part from `AValue` and returns the result.

Since the `TDateTime` is actually a double with the time part encoded in the fractional part, this operation corresponds to a call to `Frac`.

See also: `DateOf` (595), `YearOf` (684), `MonthOf` (639), `DayOf` (598), `HourOf` (613), `MinuteOf` (635), `SecondOf` (652), `MilliSecondOf` (631)

Listing: `./examples/datutex/ex2.pp`

Program Example2;

{ This program demonstrates the TimeOf function }

Uses SysUtils , DateUtils ;

Begin

WriteLn ('Time is : ', TimeToStr (TimeOf (Now)));

End.

44.4.138 Today

Synopsis: Return the current date

Declaration: `function Today : TDateTime`

Visibility: default

Description: `Today` is an alias for the `Date` (1673) function in the `sysutils` (1615) unit.

For an example, see `Yesterday` (686)

See also: `Date` (1673), `Yesterday` (686), `Tomorrow` (662)

44.4.139 Tomorrow

Synopsis: Return the next day

Declaration: `function Tomorrow : TDateTime`

Visibility: default

Description: `Tomorrow` returns tomorrow's date. `Tomorrow` is determined from the system clock, i.e. it is `Today` (662) +1.

See also: `Today` (662), `Yesterday` (686)

Listing: ./examples/datutex/ex19.pp

Program Example19;

{ This program demonstrates the Tomorrow function }

Uses SysUtils , DateUtils ;

Begin

WriteLn (FormatDateTime ('"Today is" dd mmm yyyy ', Today));

WriteLn (FormatDateTime ('"Tomorrow will be" dd mmm yyyy ', Tomorrow));

End.

44.4.140 TryEncodeDateDay

Synopsis: Encode a year and day of year to a TDateTime value

Declaration: `function TryEncodeDateDay (const AYear: Word; const ADayOfYear: Word;
out AValue: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDateDay` encodes the values `AYear` and `ADayOfYear` to a date value and returns this value in `AValue`.

If the encoding was successful, `True` is returned. `False` is returned if any of the arguments is not valid.

See also: `EncodeDateDay` (607), `EncodeDateTime` (607), `EncodeDateMonthWeek` (607), `EncodeDateWeek` (608), `TryEncodeDateTime` (664), `TryEncodeDateMonthWeek` (663), `TryEncodeDateWeek` (665)

Listing: `./examples/datutex/ex84.pp`

Program `Example84`;

{ This program demonstrates the TryEncodeDateDay function }

Uses `SysUtils`, `DateUtils`;

Var

`Y, DoY` : `Word`;
`TS` : `TDateTime`;

Begin

`DecodeDateDay(Now, Y, DoY);`
If `TryEncodeDateDay(Y, DoY, TS)` **then**
 `WriteLn('Today is : ', DateToStr(TS))`
else
 `WriteLn('Wrong year/day of year indication');`

End.

44.4.141 TryEncodeDateMonthWeek

Synopsis: Encode a year, month, week of month and day of week to a `TDateTime` value

Declaration: `function TryEncodeDateMonthWeek(const AYear: Word; const AMonth: Word;
 const AWeekOfMonth: Word;
 const ADayOfWeek: Word;
 out AValue: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDateMonthWeek` encodes the values `AYear`, `AMonth`, `WeekOfMonth`, `ADayOfWeek`, to a date value and returns this value in `AValue`.

If the encoding was successful, `True` is returned, `False` if any of the arguments is not valid.

See also: `DecodeDateMonthWeek` (604), `EncodeDateTime` (607), `EncodeDateWeek` (608), `EncodeDateDay` (607), `EncodeDateMonthWeek` (607), `TryEncodeDateTime` (664), `TryEncodeDateWeek` (665), `TryEncodeDateDay` (662), `NthDayOfWeek` (641)

Listing: `./examples/datutex/ex86.pp`

Program `Example86`;

{ This program demonstrates the TryEncodeDateMonthWeek function }

Uses `SysUtils`, `DateUtils`;

```

Var
  Y,M,Wom,Dow : Word;
  TS : TDateTime;

Begin
  DecodeDateMonthWeek(Now,Y,M,WoM,DoW);
  If TryEncodeDateMonthWeek(Y,M,WoM,Dow,TS) then
    Writeln('Today is : ',DateToStr(TS))
  else
    Writeln('Invalid year/month/week/dow indication');
End.

```

44.4.142 TryEncodeDateTime

Synopsis: Encode a Year, Month, Day, Hour, minute, seconds, milliseconds tuple to a TDateTime value

Declaration: `function TryEncodeDateTime(const AYear: Word; const AMonth: Word; const ADay: Word; const AHour: Word; const AMinute: Word; const ASecond: Word; const AMilliSecond: Word; out AValue: TDateTime) : Boolean`

Visibility: default

Description: EncodeDateTime encodes the values AYearAMonth, ADay,AHour, AMinute,ASecond and AMilliSecond to a date/time value and returns this value in AValue.

If the date was encoded successfully, True is returned, False is returned if one of the arguments is not valid.

See also: EncodeDateTime (607), EncodeDateMonthWeek (607), EncodeDateWeek (608), EncodeDateDay (607), TryEncodeDateDay (662), TryEncodeDateWeek (665), TryEncodeDateMonthWeek (663)

Listing: ./examples/datutex/ex80.pp

Program Example79;

{ This program demonstrates the TryEncodeDateTime function }

Uses SysUtils , DateUtils ;

```

Var
  Y,Mo,D,H,Mi,S,MS : Word;
  TS : TDateTime;

```

```

Begin
  DecodeDateTime(Now,Y,Mo,D,H,Mi,S,MS);
  If TryEncodeDateTime(Y,Mo,D,H,Mi,S,MS,TS) then
    Writeln('Now is : ',DateTimeToStr(TS))
  else
    Writeln('Wrong date/time indication');
End.

```

44.4.143 TryEncodeDateWeek

Synopsis: Encode a year, week and day of week triplet to a TDateTime value

Declaration:

```
function TryEncodeDateWeek(const AYear: Word; const AWeekOfYear: Word;
                           out AValue: TDateTime; const ADayOfWeek: Word)
                           : Boolean
function TryEncodeDateWeek(const AYear: Word; const AWeekOfYear: Word;
                           out AValue: TDateTime) : Boolean
```

Visibility: default

Description: TryEncodeDateWeek encodes the values AYear, AWeekOfYear and ADayOfWeek to a date value and returns this value in AValue.

If the encoding was successful, True is returned. False is returned if any of the arguments is not valid.

See also: EncodeDateMonthWeek (607), EncodeDateWeek (608), EncodeDateTime (607), EncodeDateDay (607), TryEncodeDateTime (664), TryEncodeDateMonthWeek (663), TryEncodeDateDay (662)

Listing: ./examples/datutex/ex82.pp

Program Example82;

{ This program demonstrates the TryEncodeDateWeek function }

Uses SysUtils, DateUtils;

Var

Y,W,Dow : Word;
TS : TDateTime;

Begin

DecodeDateWeek(**Now**, Y,W,Dow);
If TryEncodeDateWeek(Y,W,TS,Dow) **then**
 WriteLn('Today is : ',DateToStr(TS))
else
 WriteLn('Invalid date/week indication');
End.

44.4.144 TryEncodeDayOfWeekInMonth

Synopsis: Encode a year, month, week, day of week triplet to a TDateTime value

Declaration:

```
function TryEncodeDayOfWeekInMonth(const AYear: Word;
                                     const AMonth: Word;
                                     const ANthDayOfWeek: Word;
                                     const ADayOfWeek: Word;
                                     out AValue: TDateTime) : Boolean
```

Visibility: default

Description: EncodeDayOfWeekInMonth encodes AYear, AMonth, ADayOfWeek and ANthDayOfWeek to a valid date stamp and returns the result in AValue.

ANthDayOfWeek is the N-th time that this weekday occurs in the month, e.g. the third Saturday of the month.

The function returns True if the encoding was successful, False if any of the values is not in range.

See also: [NthDayOfWeek \(641\)](#), [EncodeDateMonthWeek \(607\)](#), [#rtl.sysutils.DayOfWeek \(1678\)](#), [DecodeDayOfWeekInMonth \(606\)](#), [EncodeDayOfWeekInMonth \(608\)](#)

Listing: ./examples/datutex/ex106.pp

```

Program Example105;

{ This program demonstrates the DecodeDayOfWeekInMonth function }

Uses SysUtils, DateUtils;

Var
    Y,M,NDoW,DoW : Word;
    D : TDateTime;
Begin
    DecodeDayOfWeekInMonth( Date, Y,M,NDoW,DoW);
    If TryEncodeDayOfWeekInMonth(Y,M,NDoW,DoW,D) then
        begin
            Write( DateToStr(D), ' is the ',NDoW, '-th ');
            Writeln( formatdateTime( 'dddd',D), ' of the month.' );
        end
    else
        Writeln( 'Invalid year/month/NthDayOfweek combination ');
End.

```

44.4.145 TryEncodeTimeInterval

Synopsis: Try to encode an interval as a TDateTime value.

Declaration: `function TryEncodeTimeInterval(Hour: Word; Min: Word; Sec: Word; MSec: Word; out Time: TDateTime) : Boolean`

Visibility: default

Description: TryEncodeTimeInterval encodes a time interval expressed in Hour, Min, Sec, MSec as a TDateTime value and returns the value in Time. It returns True if Min, Sec, MSec contain valid time values (i.e. less than 60, 60 resp. MSec). The number of hours may be larger than 24.

See also: [EncodeTimeInterval \(608\)](#)

44.4.146 TryISO8601ToDate

Synopsis: Attempts to convert an ISO 8601-formatted date/time value to a TDateTime type

Declaration: `function TryISO8601ToDate(const DateString: string; out ADateTime: TDateTime; ReturnUTC: Boolean) : Boolean`

Visibility: default

Description: TryISO8601ToDate is a Boolean function which attempts to convert an ISO 8601-formatted date/-time value to a TDateTime type.

DateString contains the ISO 8601 date/time value converted in the function. DateString must contain one of the supported ISO 8601 date/time notations supported in the routine. It is separated into date, time, and time zone values, and is converted by calling both the TryISOStrToDateTime

and `TryISO TZStrToTZOffset` functions. See `TryISO StrToDateTime` (667) for more information about supported ISO 8601 notations.

`ReturnUTC` indicates if the native date/time value needs to be adjusted to the UTC (Coordinated Universal Time) time zone. The default value for the argument is `True`, and causes `GetLocalTimeOffset` to be called to get and apply the time zone offset for the local computer.

`ADateTime` contains the native `TDateTime` value for the converted timestamp adjusted to the UTC time zone when `ReturnUTC` contains `True`.

Use `DateToISO8601` to convert a native date/time value back to its representation in ISO 8601 notation.

See also: `DateToISO8601` (598)

44.4.147 TryISO StrToDate

Synopsis: Attempts to convert an ISO 8601-formatted date value to a `TDateTime` type

Declaration: `function TryISO StrToDate(const aString: string; out outDate: TDateTime) : Boolean`

Visibility: default

Description: `TryISO StrToDate` is a `Boolean` function which attempts to convert an ISO 8601-formatted date value in `aString` to a `TDateTime` type. The return value is `True` if the string is successfully converted into a native date value.

`aString` contains the date value converted in the function, and can use one of the following ISO 8601 notations :

- `YYYYMMDD`
- `YYYY-MM-DD`

`outDate` is an output parameter where the converted `TDateTime` value is stored in the function. The return value is `False` (and `outDate` is set to an empty date value) if `aString` cannot be converted in the routine. The time portion of the `TDateTime` value is not used or updated in the function.

Use `TryISO StrToTime` to convert a time value to a native `TDateTime` type.

Use `TryISO StrToDateTime` to convert a string which contains both date and time values to a `TDateTime` type.

See also: `TryISO StrToTime` (668), `TryISO StrToDateTime` (667)

44.4.148 TryISO StrToDateTime

Synopsis: Attempts to convert an ISO 8601-formatted date/time value to a `TDateTime` type

Declaration: `function TryISO StrToDateTime(const aString: string; out outDateTime: TDateTime) : Boolean`

Visibility: default

Description: `TryISO StrToDateTime` is a `Boolean` function which attempts to convert an ISO 8601-formatted date/time value to a `TDateTime` type. `aString` contains the date/time value examined in the routine, and can use one of the supported ISO 8601 notations. Internally, `TryISO StrToDateTime` separates the value in `aString` into date and time parts and calls both `TryISO StrToDate` and `TryISO StrToTime`.

`outDateTime` is a `TDateTime` output parameter where the date/time value is stored in the function.

The return value is `True` if `aString` is successfully parsed and converted to a `TDateTime` type. The return value is `False` if `aString` contains a value that cannot be parsed in the function. When the return value is `False`, `outDateTime` is set to `0` (representing an empty date/time value).

Use `TryISOStrToDate` or `TryISOStrToTime` to convert a string using only a date or a time value (respectively).

Use `TryISO8601ToDate` to convert a string value which uses more intricate forms of the ISO 8601 time notation.

See also: `TryISOStrToDate` (667), `TryISOStrToTime` (668), `TryISO8601ToDate` (666)

44.4.149 TryISOStrToTime

Synopsis: Converts an ISO 8601-formatted time value to a `TDateTime` type

Declaration: `function TryISOStrToTime(const aString: string; out outTime: TDateTime) : Boolean`

Visibility: default

Description: `TryISOStrToTime` is a `Boolean` function which attempts to convert the specified ISO 8601 time value to a `TDateTime` type. `aString` contains the ISO 8601 time value examined in the function, and can use one of the following notations:

- HHNN
- HHNNSS
- HHNNSS.ZZZ
- HH:NN
- HH:NN:SS
- HH:NN:SS.ZZZ

`aString` may contain an optional time zone designation at the end of the string value, like `'Z'` for Zulu time zone or a time zone offset expressed using either positive or negative hours and minutes. For example:

- 16:00:00Z
- 12:00:00-04:00

The return value is `True` if the time value in `aString` is successfully converted in the function.

`outTime` is a `TDateTime` type used to store the time value converted in the function. When the return value is `False`, `outTime` contains `0` for an empty time value.

Use `TryISOStrToDate` to convert an ISO 8601 date value to a `TDateTime` type.

Use `TryISOStrToDateTime` to convert a string which contains both date and time values to a `TDateTime` type.

See also: `TryISOStrToDate` (667), `TryISOStrToDateTime` (667)

44.4.150 TryISOTZStrToTZOffset

Synopsis: Attempts to convert an ISO 8601 time zone designation to an offset in minutes

Declaration: `function TryISOTZStrToTZOffset(const TZ: string; out TZOffset: Integer)
: Boolean`

Visibility: default

Description: `TryISOTZStrToTZOffset` is a `Boolean` function which attempts to convert the ISO 8601 time zone designation to a time zone offset expressed as a positive or negative number of minutes. `TZ` contains the time zone designation examined in the function. It should not contain any other portion of a date/time value using ISO 8601 notation - just the time zone designation.

`TryISOTZStrToTZOffset` recognizes the following values in the `TZ` argument:

Z Represents time zone Zulu (short for "Zulu time") as used by the military and in navigation. Refers to UTC (Coordinated Universal Time), formerly known as Greenwich Mean Time.

±HHNN or ±HH:NN time zone designation expressed as a positive or negative number of hours and minutes for a given time value.

`TZOffset` is an `Integer` updated to contains the number of minutes needed to adjust a time value for a given time zone back to UTC (Zulu time). The hour and minute component values in `TZ` are converted to minutes and complemented (multiplied by -1) to derive the offset value. The derived value in `TZOffset` is 0 when `TZ` contains Zulu time, an empty string (""), or cannot be converted successfully.

The return value is `True` if the time zone designation in `TZ` is successfully converted to a time zone offset.

Use `ISOTZStrToTZOffset` to convert the time zone designation and raise an exception for an invalid time zone designation.

See also: `ISOTZStrToTZOffset` ([589](#))

44.4.151 TryJulianDateToDateTime

Synopsis: Convert a Julian date representation to a `TDateTime` value.

Declaration: `function TryJulianDateToDateTime(const AValue: Double;
out ADateTime: TDateTime) : Boolean`

Visibility: default

Description: Try to convert a Julian date to a regular `TDateTime` date/time representation.

See also: `DateTimeToJulianDate` ([597](#)), `JulianDateToDateTime` ([630](#)), `DateTimeToModifiedJulianDate` ([597](#)), `TryModifiedJulianDateToDateTime` ([669](#))

44.4.152 TryModifiedJulianDateToDateTime

Synopsis: Convert a modified Julian date representation to a `TDateTime` value.

Declaration: `function TryModifiedJulianDateToDateTime(const AValue: Double;
out ADateTime: TDateTime)
: Boolean`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: [DateTimeToJulianDate \(597\)](#), [JulianDateToDateTime \(630\)](#), [TryJulianDateToDateTime \(669\)](#), [DateTimeToModifiedJulianDate \(597\)](#), [ModifiedJulianDateToDateTime \(639\)](#)

44.4.153 TryRecodeDateTime

Synopsis: Replace selected parts of a TDateTime value with other values

Declaration:

```
function TryRecodeDateTime(const AValue: TDateTime; const AYear: Word;
                           const AMonth: Word; const ADay: Word;
                           const AHour: Word; const AMinute: Word;
                           const ASecond: Word;
                           const AMilliSecond: Word;
                           out AResult: TDateTime) : Boolean
```

Visibility: default

Description: TryRecodeDateTime replaces selected parts of the timestamp AValue with the date/time values specified in AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond. If any of these values equals the predefined constant RecodeLeaveFieldAsIs ([591](#)), then the corresponding part of the date/time stamp is left untouched.

The resulting date/time is returned in AValue.

The function returns True if the encoding was successful. It returns False if one of the values AYear, AMonth, ADay, AHour, AMinute, ASecondAMilliSecond is not within a valid range.

See also: [RecodeYear \(649\)](#), [RecodeMonth \(647\)](#), [RecodeDay \(644\)](#), [RecodeHour \(645\)](#), [RecodeMinute \(646\)](#), [RecodeSecond \(647\)](#), [RecodeMilliSecond \(645\)](#), [RecodeDate \(643\)](#), [RecodeTime \(648\)](#), [RecodeDateTime \(643\)](#)

Listing: ./examples/datutex/ex97.pp

Program Example97;

{ This program demonstrates the TryRecodeDateTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmmm yyyy hh:nn:ss';

Var

S : AnsiString;

D : TDateTime;

Begin

If TryRecodeDateTime(Now,2000,2,RecodeLeaveFieldAsIs,0,0,0,0,D) **then**
begin
 S:=FormatDateTime(Fmt,D);
 Writeln('This moment in februari 2000 : ',S);
end

else

Writeln('This moment did/does not exist in februari 2000');

End.

44.4.154 UniversalTimeToLocal

Synopsis: Convert UTC time to local time

Declaration: `function UniversalTimeToLocal(UT: TDateTime) : TDateTime`
`function UniversalTimeToLocal(UT: TDateTime; TZOffset: Integer)`
`: TDateTime`

Visibility: default

Description: `UniversalTimeToLocal` converts a universal time indication to a local time: it applies the `TZOffset` time zone offset to the UT Universal time (UTC). If no `TZOffset` is specified, the local time offset as returned by `GetLocalTimeOffset` (589) is used.

Note that for times in the past or in the future, or for time zones with DST, omitting the `TZoffset` may lead to wrong results depending on `GetLocalTimeOffset` being able to compute the correct offset for the LT on the target platform. Currently only Windows Vista and newer return correct offsets for a given date. Older Windows systems or Linux/Unix return always the offset for the current date.

See also: `GetLocalTimeOffset` (589), `LocalTimeToUniversal` (630)

44.4.155 UnixTimeStampToMac

Synopsis: Convert Unix Timestamp to a Mac Timestamp

Declaration: `function UnixTimeStampToMac(const AValue: Int64) : Int64`

Visibility: default

Description: `UnixTimeStampToMac` converts the UNIX epoch time in `AValue` to a valid Mac timestamp indication and returns the result.

Errors: None.

See also: `DateTimeToMac` (597), `MacToDateTime` (630), `MacTimeStampToUnix` (630)

44.4.156 UnixToDateTime

Synopsis: Convert Unix epoch time to a TDateTime value

Declaration: `function UnixToDateTime(const AValue: Int64; aReturnUTC: Boolean)`
`: TDateTime`

Visibility: default

Description: `UnixToDateTime` converts epoch time (seconds elapsed since 1/1/1970) to a `TDateTime` value.

See also: `DateTimeToUnix` (597)

44.4.157 WeekOf

Synopsis: Extract week (of the year) from a given date.

Declaration: `function WeekOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `WeekOf` returns the week-of-the-year part of the `AValue` date/time indication. It is a number between 1 and 53.

For an example, see `YearOf` (684)

See also: `YearOf` (684), `DayOf` (598), `MonthOf` (639), `HourOf` (613), `MinuteOf` (635), `SecondOf` (652), `MilliSecondOf` (631)

44.4.158 WeekOfTheMonth

Synopsis: Extract the week of the month (and optionally month and year) from a `TDateTime` value

Declaration: `function WeekOfTheMonth(const AValue: TDateTime) : Word; Overload`
`function WeekOfTheMonth(const AValue: TDateTime; out AYear: Word;`
`out AMonth: Word) : Word; Overload`

Visibility: default

Description: `WeekOfTheMonth` extracts the week of the month from `AValue` and returns it, and optionally returns the year and month as well (in `AYear`, `AMonth` respectively).

Remark Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year and month may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: `WeekOfTheYear` (672), `DayOfTheMonth` (599), `HourOfTheMonth` (614), `MinuteOfTheMonth` (636), `SecondOfTheMonth` (654), `MilliSecondOfTheMonth` (632)

Listing: `./examples/datutex/ex41.pp`

Program `Example41` ;

{ This program demonstrates the WeekOfTheMonth function }

Uses `SysUtils` , `DateUtils` ;

Var

`N : TDateTime;`

Begin

`N:=Now;`

`WriteLn('Week of the Month : ',WeekOfTheMonth(N));`

`WriteLn('Day of the Month : ',DayOfTheMonth(N));`

`WriteLn('Hour of the Month : ',HourOfTheMonth(N));`

`WriteLn('Minute of the Month : ',MinuteOfTheMonth(N));`

`WriteLn('Second of the Month : ',SecondOfTheMonth(N));`

`WriteLn('MilliSecond of the Month : ',`

`MilliSecondOfTheMonth(N));`

End.

44.4.159 WeekOfTheYear

Synopsis: Extract the week of the year (and optionally year) of a `TDateTime` indication.

Declaration: `function WeekOfTheYear(const AValue: TDateTime) : Word; Overload`
`function WeekOfTheYear(const AValue: TDateTime; out AYear: Word) : Word`
`; Overload`

Visibility: default

Description: `WeekOfTheYear` extracts the week of the year from `AValue` and returns it, and optionally returns the year as well. It returns the same value as `WeekOf` (671).

Remark Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: `WeekOf` (671), `MonthOfTheYear` (639), `DayOfTheYear` (599), `HourOfTheYear` (615), `MinuteOfTheYear` (637), `SecondOfTheYear` (654), `MilliSecondOfTheYear` (633)

Listing: `./examples/datutex/ex40.pp`

Program `Example40`;

{ This program demonstrates the WeekOfTheYear function }

Uses `SysUtils`, `DateUtils`;

Var

`N` : `TDateTime`;

Begin

`N:=Now`;

`WriteLn` ('Month of the year : ', `MonthOfTheYear`(`N`));

`WriteLn` ('Week of the year : ', `WeekOfTheYear`(`N`));

`WriteLn` ('Day of the year : ', `DayOfTheYear`(`N`));

`WriteLn` ('Hour of the year : ', `HourOfTheYear`(`N`));

`WriteLn` ('Minute of the year : ', `MinuteOfTheYear`(`N`));

`WriteLn` ('Second of the year : ', `SecondOfTheYear`(`N`));

`WriteLn` ('MilliSecond of the year : ',
 `MilliSecondOfTheYear`(`N`));

End.

44.4.160 WeeksBetween

Synopsis: Calculate the number of whole weeks between two `TDateTime` values

Declaration: `function WeeksBetween(const ANow: TDateTime; const AThen: TDateTime)`
 `: Integer`

Visibility: default

Description: `WeeksBetween` returns the number of whole weeks between `ANow` and `AThen`. This means the fractional part of a Week is dropped.

See also: `YearsBetween` (684), `MonthsBetween` (640), `DaysBetween` (600), `HoursBetween` (615), `MinutesBetween` (637), `SecondsBetween` (655), `MillisecondsBetween` (633)

Listing: `./examples/datutex/ex57.pp`

Program `Example57`;

{ This program demonstrates the WeeksBetween function }

Uses `SysUtils`, `DateUtils`;

```

Procedure Test(ANow, AThen : TDateTime);

begin
  Write('Number of weeks between ');
  Write(DateToStr(AThen), ' and ', DateToStr(ANow));
  Writeln(' : ', WeeksBetween(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1 := Today;
  D2 := Today - 7;
  Test(D1, D2);
  D2 := Today - 8;
  Test(D1, D2);
  D2 := Today - 14;
  Test(D1, D2);
  D2 := Today - 35;
  Test(D1, D2);
  D2 := Today - 36;
  Test(D1, D2);
  D2 := Today - 17;
  Test(D1, D2);
End.

```

44.4.161 WeeksInAYear

Synopsis: Return the number of weeks in a given year

Declaration: `function WeeksInAYear(const AYear: Word) : Word`

Visibility: default

Description: `WeeksInAYear` returns the number of weeks in the year `AYear`. The return value is either 52 or 53.

Remark The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a Thursday.

See also: `WeeksInYear` (675), `DaysInYear` (602), `DaysInAYear` (601), `DaysInMonth` (602), `DaysInAMonth` (601)

Listing: `./examples/datutex/ex13.pp`

Program Example13;

{ This program demonstrates the WeeksInAYear function }

Uses SysUtils, DateUtils;

Var
Y : Word;

Begin
 For Y:=1992 **to** 2010 **do**
 Writeln(Y, ' has ', WeeksInAYear(Y), ' weeks. ');
End.

44.4.162 WeeksInYear

Synopsis: return the number of weeks in the year, given a date

Declaration: `function WeeksInYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `WeeksInYear` returns the number of weeks in the year part of `AValue`. The return value is either 52 or 53.

Remark The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a Thursday.

See also: `WeeksInAYear` (674), `DaysInYear` (602), `DaysInAYear` (601), `DaysInMonth` (602), `DaysInAMonth` (601)

Listing: `./examples/datutex/ex12.pp`

Program `Example12;`

{ This program demonstrates the WeeksInYear function }

Uses `SysUtils, DateUtils;`

Var

`Y : Word;`

Begin

`For Y:=1992 to 2010 do`

`WriteLn(Y, ' has ', WeeksInYear(EncodeDate(Y,2,1)), ' weeks. ');`

End.

44.4.163 WeekSpan

Synopsis: Calculate the approximate number of weeks between two `TDateTime` values.

Declaration: `function WeekSpan(const ANow: TDateTime; const AThen: TDateTime)
 : Double`

Visibility: default

Description: `WeekSpan` returns the number of weeks between `ANow` and `AThen`, including any fractional parts of a week.

See also: `YearSpan` (685), `MonthSpan` (640), `DaySpan` (603), `HourSpan` (616), `MinuteSpan` (638), `SecondSpan` (655), `MilliSecondSpan` (634), `WeeksBetween` (673)

Listing: `./examples/datutex/ex65.pp`

Program `Example57;`

{ This program demonstrates the WeekSpan function }

Uses `SysUtils, DateUtils;`

Procedure `Test(ANow, AThen : TDateTime);`

begin

```

Write('Number of weeks between ');
Write(DateToStr(AThen), ' and ', DateToStr(ANow));
WriteLn(' : ', WeekSpan(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1:=Today;
  D2:=Today-7;
  Test(D1,D2);
  D2:=Today-8;
  Test(D1,D2);
  D2:=Today-14;
  Test(D1,D2);
  D2:=Today-35;
  Test(D1,D2);
  D2:=Today-36;
  Test(D1,D2);
  D2:=Today-17;
  Test(D1,D2);
End.

```

44.4.164 WithinPastDays

Synopsis: Check whether two TDateTimes are only a number of days apart

Declaration: `function WithinPastDays(const ANow: TDateTime; const AThen: TDateTime; const ADays: Integer) : Boolean`

Visibility: default

Description: `WithinPastDays` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `ADays` days apart, or `False` if they are further apart.

Remark Since this function uses the `DaysBetween` (600) function to calculate the difference in days, this means that fractional days do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half days apart, the result will also be `True`

See also: `WithinPastYears` (683), `WithinPastMonths` (680), `WithinPastWeeks` (682), `WithinPastHours` (677), `WithinPastMinutes` (679), `WithinPastSeconds` (681), `WithinPastMilliseconds` (678)

Listing: `./examples/datutex/ex50.pp`

Program `Example50`;

{ This program demonstrates the WithinPastDays function }

Uses `SysUtils, DateUtils`;

Procedure `Test(ANow, AThen : TDateTime; ADays : Integer)`;

```

begin
  Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
  Write(' are within ', ADays, ' days: ');
  WriteLn(WithinPastDays(ANow, AThen, ADays));
end;

```

```
Var
  D1,D2 : TDateTime;
```

```
Begin
  D1:=Now;
  D2:=Today-23/24;
  Test(D1,D2,1);
  D2:=Today-1;
  Test(D1,D2,1);
  D2:=Today-25/24;
  Test(D1,D2,1);
  D2:=Today-26/24;
  Test(D1,D2,5);
  D2:=Today-5.4;
  Test(D1,D2,5);
  D2:=Today-2.5;
  Test(D1,D2,1);
  Test(D1,D2,2);
  Test(D1,D2,3);
```

```
End.
```

44.4.165 WithinPastHours

Synopsis: Check whether two TDateTimes are only a number of hours apart

Declaration: `function WithinPastHours(const ANow: TDateTime; const AThen: TDateTime; const AHours: Int64) : Boolean`

Visibility: default

Description: `WithinPastHours` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AHours` hours apart, or `False` if they are further apart.

Remark Since this function uses the `HoursBetween` (615) function to calculate the difference in Hours, this means that fractional hours do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half hours apart, the result will also be `True`

See also: `WithinPastYears` (683), `WithinPastMonths` (680), `WithinPastWeeks` (682), `WithinPastDays` (676), `WithinPastMinutes` (679), `WithinPastSeconds` (681), `WithinPastMilliseconds` (678)

Listing: `./examples/datutex/ex51.pp`

Program Example51;

```
{ This program demonstrates the WithinPastHours function }
```

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AHours : Integer);

```
begin
  Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
  Write(' are within ', AHours, ' hours: ');
  WriteLn(WithinPastHours(ANow, AThen, AHours));
end;
```

Var

```
D1,D2 : TDateTime;
```

Begin

```
D1:=Now;
D2:=D1-(59*OneMinute);
Test(D1,D2,1);
D2:=D1-(61*OneMinute);
Test(D1,D2,1);
D2:=D1-(122*OneMinute);
Test(D1,D2,1);
D2:=D1-(306*OneMinute);
Test(D1,D2,5);
D2:=D1-(5.4*OneHour);
Test(D1,D2,5);
D2:=D1-(2.5*OneHour);
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
```

End.**44.4.166 WithinPastMilliseconds**

Synopsis: Check whether two TDateTimes are only a number of milliseconds apart

Declaration: `function WithinPastMilliseconds(const ANow: TDateTime;
const AThen: TDateTime;
const AMilliseconds: Int64) : Boolean`

Visibility: default

Description: `WithinPastMilliseconds` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMilliseconds` milliseconds apart, or `False` if they are further apart.

Remark Since this function uses the `MillisecondsBetween` (633) function to calculate the difference in milliseconds, this means that fractional milliseconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half milliseconds apart, the result will also be `True`

See also: `WithinPastYears` (683), `WithinPastMonths` (680), `WithinPastWeeks` (682), `WithinPastDays` (676), `WithinPastHours` (677), `WithinPastMinutes` (679), `WithinPastSeconds` (681)

Listing: `./examples/datutex/ex54.pp`

Program `Example54;`

{ This program demonstrates the WithinPastMilliseconds function }

Uses `SysUtils, DateUtils;`

Procedure `Test(ANow, AThen : TDateTime; AMilliseconds : Integer);`

begin

```
Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
Write(' are within ', AMilliseconds, ' milliseconds: ');
WriteLn(WithinPastMilliseconds(ANow, AThen, AMilliseconds));
end;
```

Var

```
D1,D2 : TDateTime;
```

Begin

```
D1:=Now;
D2:=D1-(0.9*OneMilliSecond);
Test(D1,D2,1);
D2:=D1-(1.0*OneMilliSecond);
Test(D1,D2,1);
D2:=D1-(1.1*OneMilliSecond);
Test(D1,D2,1);
D2:=D1-(2.5*OneMilliSecond);
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
```

End.**44.4.167 WithinPastMinutes**

Synopsis: Check whether two TDateTimes are only a number of minutes apart

Declaration: `function WithinPastMinutes(const ANow: TDateTime;
const AThen: TDateTime; const AMinutes: Int64)
: Boolean`

Visibility: default

Description: `WithinPastMinutes` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMinutes` minutes apart, or `False` if they are further apart.

Remark Since this function uses the `MinutesBetween` (637) function to calculate the difference in Minutes, this means that fractional minutes do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half minutes apart, the result will also be `True`

See also: `WithinPastYears` (683), `WithinPastMonths` (680), `WithinPastWeeks` (682), `WithinPastDays` (676), `WithinPastHours` (677), `WithinPastSeconds` (681), `WithinPastMilliseconds` (678)

Listing: `./examples/datutex/ex52.pp`

Program Example52;

```
{ This program demonstrates the WithinPastMinutes function }
```

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMinutes : Integer);

begin

```
Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
Write(' are within ', AMinutes, ' Minutes: ');
WriteLn(WithinPastMinutes(ANow, AThen, AMinutes));
end;
```

Var

```
D1,D2 : TDateTime;
```

Begin

```
D1:=Now;
D2:=D1-(59*OneSecond);
```



```

Test(D1,D2,1);
D2:=D1-(61*OneSecond);
Test(D1,D2,1);
D2:=D1-(122*OneSecond);
Test(D1,D2,1);
D2:=D1-(306*OneSecond);
Test(D1,D2,5);
D2:=D1-(5.4*OneMinute);
Test(D1,D2,5);
D2:=D1-(2.5*OneMinute);
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.

```

44.4.168 WithinPastMonths

Synopsis: Check whether two TDateTimes are only a number of months apart

Declaration: `function WithinPastMonths(const ANow: TDateTime;
const AThen: TDateTime; const AMonths: Integer)
: Boolean`

Visibility: default

Description: `WithinPastMonths` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMonths` months apart, or `False` if they are further apart.

Remark Since this function uses the `MonthsBetween` (640) function to calculate the difference in Months, this means that fractional months do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half months apart, the result will also be `True`

See also: `WithinPastYears` (683), `WithinPastWeeks` (682), `WithinPastDays` (676), `WithinPastHours` (677), `WithinPastMinutes` (679), `WithinPastSeconds` (681), `WithinPastMilliseconds` (678)

Listing: `./examples/datutex/ex48.pp`

Program `Example48;`

{ This program demonstrates the WithinPastMonths function }

Uses `SysUtils, DateUtils;`

Procedure `Test(ANow, AThen : TDateTime; AMonths : Integer);`

```

begin
  Write(DateToStr(AThen), ' and ', DateToStr(ANow));
  Write(' are within ', AMonths, ' months: ');
  WriteLn(WithinPastMonths(ANow, AThen, AMonths));
end;

```

Var
`D1, D2 : TDateTime;`

```

Begin
  D1:=Today;
  D2:=Today-364;
  Test(D1,D2,12);

```

```

D2:=Today-365;
Test(D1,D2,12);
D2:=Today-366;
Test(D1,D2,12);
D2:=Today-390;
Test(D1,D2,12);
D2:=Today-368;
Test(D1,D2,11);
D2:=Today-1000;
Test(D1,D2,31);
Test(D1,D2,32);
Test(D1,D2,33);
End.

```

44.4.169 WithinPastSeconds

Synopsis: Check whether two TDateTimes are only a number of seconds apart

Declaration: `function WithinPastSeconds(const ANow: TDateTime;
const AThen: TDateTime; const ASeconds: Int64)
: Boolean`

Visibility: default

Description: `WithinPastSeconds` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `ASeconds` seconds apart, or `False` if they are further apart.

Remark Since this function uses the `SecondsBetween` (655) function to calculate the difference in seconds, this means that fractional seconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half seconds apart, the result will also be `True`

See also: `WithinPastYears` (683), `WithinPastMonths` (680), `WithinPastWeeks` (682), `WithinPastDays` (676), `WithinPastHours` (677), `WithinPastMinutes` (679), `WithinPastMilliseconds` (678)

Listing: `./examples/datutex/ex53.pp`

Program `Example53;`

{ This program demonstrates the WithinPastSeconds function }

Uses `SysUtils, DateUtils;`

Procedure `Test(ANow, AThen : TDateTime; ASeconds : Integer);`

begin

`Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));`

`Write(' are within ', ASeconds, ' seconds: ');`

`WriteLn(WithinPastSeconds(ANow, AThen, ASeconds));`

end;

Var

`D1, D2 : TDateTime;`

Begin

`D1:=Now;`

`D2:=D1-(999*OneMilliSecond);`

`Test(D1,D2,1);`

`D2:=D1-(1001*OneMilliSecond);`

```

Test(D1,D2,1);
D2:=D1-(2001*OneMilliSecond);
Test(D1,D2,1);
D2:=D1-(5001*OneMilliSecond);
Test(D1,D2,5);
D2:=D1-(5.4*OneSecond);
Test(D1,D2,5);
D2:=D1-(2.5*OneSecond);
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.

```

44.4.170 WithinPastWeeks

Synopsis: Check whether two TDateTime's are only a number of weeks apart

Declaration: `function WithinPastWeeks(const ANow: TDateTime; const AThen: TDateTime;
const AWeeks: Integer) : Boolean`

Visibility: default

Description: `WithinPastWeeks` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AWeeks` weeks apart, or `False` if they are further apart.

Remark Since this function uses the `WeeksBetween` (673) function to calculate the difference in Weeks, this means that fractional Weeks do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half weeks apart, the result will also be `True`

See also: `WithinPastYears` (683), `WithinPastMonths` (680), `WithinPastDays` (676), `WithinPastHours` (677), `WithinPastMinutes` (679), `WithinPastSeconds` (681), `WithinPastMilliseconds` (678)

Listing: ./examples/datutex/ex49.pp

Program Example49;

{ This program demonstrates the WithinPastWeeks function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AWeeks : Integer);

begin

Write(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

Write(' are within ', AWeeks, ' weeks: ');

WriteLn(**WithinPastWeeks**(ANow, AThen, AWeeks));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Today;

 D2:=Today-7;

 Test(D1,D2,1);

 D2:=Today-8;

 Test(D1,D2,1);

 D2:=Today-14;

```

Test(D1,D2,1);
D2:=Today-35;
Test(D1,D2,5);
D2:=Today-36;
Test(D1,D2,5);
D2:=Today-17;
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.

```

44.4.171 WithinPastYears

Synopsis: Check whether two TDateTimes are only a number of years apart

Declaration: `function WithinPastYears(const ANow: TDateTime; const AThen: TDateTime;
const AYears: Integer) : Boolean`

Visibility: default

Description: `WithinPastYears` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AYears` years apart, or `False` if they are further apart.

Remark Since this function uses the `YearsBetween` (684) function to calculate the difference in years, this means that fractional years do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half years apart, the result will also be `True`

See also: `WithinPastMonths` (680), `WithinPastWeeks` (682), `WithinPastDays` (676), `WithinPastHours` (677), `WithinPastMinutes` (679), `WithinPastSeconds` (681), `WithinPastMilliseconds` (678)

Listing: `./examples/datutex/ex47.pp`

Program `Example47;`

{ This program demonstrates the WithinPastYears function }

Uses `SysUtils, DateUtils;`

Procedure `Test(ANow, AThen : TDateTime; AYears : Integer);`

```

begin
  Write(DateToStr(AThen), ' and ', DateToStr(ANow));
  Write(' are within ', AYears, ' years: ');
  WriteLn(WithinPastYears(ANow, AThen, AYears));
end;

```

Var
`D1, D2 : TDateTime;`

```

Begin
  D1:=Today;
  D2:=Today-364;
  Test(D1,D2,1);
  D2:=Today-365;
  Test(D1,D2,1);
  D2:=Today-366;
  Test(D1,D2,1);
  D2:=Today-390;

```

```

Test(D1,D2,1);
D2:=Today-368;
Test(D1,D2,1);
D2:=Today-1000;
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.

```

44.4.172 YearOf

Synopsis: Extract the year from a given date.

Declaration: `function YearOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `YearOf` returns the year part of the `AValue` date/time indication. It is a number between 1 and 9999.

See also: `MonthOf` ([639](#)), `DayOf` ([598](#)), `WeekOf` ([671](#)), `HourOf` ([613](#)), `MinuteOf` ([635](#)), `SecondOf` ([652](#)), `MilliSecondOf` ([631](#))

Listing: `./examples/datutex/ex23.pp`

Program `Example23;`

{ This program demonstrates the YearOf function }

Uses `SysUtils, DateUtils;`

Var

`D : TDateTime;`

Begin

```

D:=Now;
WriteLn('Year      : ', YearOf(D));
WriteLn('Month     : ', MonthOf(D));
WriteLn('Day        : ', DayOf(D));
WriteLn('Week        : ', WeekOf(D));
WriteLn('Hour         : ', HourOf(D));
WriteLn('Minute       : ', MinuteOf(D));
WriteLn('Second       : ', SecondOf(D));
WriteLn('MilliSecond  : ', MilliSecondOf(D));

```

End.

44.4.173 YearsBetween

Synopsis: Calculate the number of whole years between two `TDateTime` values

Declaration: `function YearsBetween(const ANow: TDateTime; const AThen: TDateTime; AExact: Boolean) : Integer`

Visibility: default

Description: `YearsBetween` returns the number of whole years between `ANow` and `AThen`. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years). This means the fractional part of a year is dropped.

See also: MonthsBetween (640), WeeksBetween (673), DaysBetween (600), HoursBetween (615), MinutesBetween (637), SecondsBetween (655), MilliSecondsBetween (633), YearSpan (685)

Listing: ./examples/datutex/ex55.pp

Program Example55;

```
{ This program demonstrates the YearsBetween function }
```

Uses SysUtils , DateUtils ;

```
Procedure Test (ANow, AThen : TDateTime);
```

```
begin
  Write ('Number of years between ');
  Write (DateToStr(AThen), ' and ', DateToStr(ANow));
  WriteLn (' : ', YearsBetween(ANow, AThen));
end;
```

```
Var
    D1,D2 : TDateTime;
```

```

Begin
  D1 := Today ;
  D2 := Today - 364 ;
  Test (D1, D2) ;
  D2 := Today - 365 ;
  Test (D1, D2) ;
  D2 := Today - 366 ;
  Test (D1, D2) ;
  D2 := Today - 390 ;
  Test (D1, D2) ;
  D2 := Today - 368 ;
  Test (D1, D2) ;
  D2 := Today - 1000 ;
  Test (D1, D2) ;
End.

```

44.4.174 YearSpan

Synopsis: Calculate the approximate number of years between two TDateTime values.

```
Declaration: function YearSpan(const ANow: TDateTime; const AThen: TDateTime)
                        : Double
```

Visibility: default

Description: YearSpan returns the number of years between ANow and AThen, including any fractional parts of a year. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years).

See also: MonthSpan (640), WeekSpan (675), DaySpan (603), HourSpan (616), MinuteSpan (638), SecondSpan (655), MillisecondSpan (634), YearsBetween (684)

Listing: ./examples/datutex/ex63.pp

Program Example63;

{ This program demonstrates the YearSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of years between ');

Write(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

WriteLn(' : ', YearSpan(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Today;

 D2 := Today - 364;

 Test(D1, D2);

 D2 := Today - 365;

 Test(D1, D2);

 D2 := Today - 366;

 Test(D1, D2);

 D2 := Today - 390;

 Test(D1, D2);

 D2 := Today - 368;

 Test(D1, D2);

 D2 := Today - 1000;

 Test(D1, D2);

End.

44.4.175 Yesterday

Synopsis: Return the previous day.

Declaration: `function Yesterday : TDateTime`

Visibility: default

Description: `Yesterday` returns yesterday's date. Yesterday is determined from the system clock, i.e. it is `Today` (662) -1.

See also: `Today` (662), `Tomorrow` (662)

Listing: ./examples/datutex/ex18.pp

Program Example18;

{ This program demonstrates the Yesterday function }

Uses SysUtils, DateUtils;

Begin

WriteLn(**FormatDateTime**('"Today is " dd mmm yyyy ', Today));

```
WriteIn (FormatDateTime( '"Yesterday was " dd mmm yyyy ', Yesterday ));  
End.
```

Chapter 45

Reference for unit 'Dos'

45.1 Used units

Table 45.1: Used units by unit 'Dos'

Name	Page
BaseUnix	141
System	1339

45.2 Overview

The DOS unit gives access to some operating system calls related to files, the file system, date and time. Except for the PalmOS target, this unit is available to all supported platforms.

The unit was first written for Dos by Florian Klaempfl. It was ported to Linux by Mark May and enhanced by Michael Van Canneyt. The Amiga version was ported by Nils Sjöholm.

Under non-DOS systems, some of the functionality is lost, as it is either impossible or meaningless to implement it. Other than that, the functionality is the same for all operating systems.

Because the DOS unit is a Turbo Pascal compatibility unit, it is no longer actively developed: the interface is frozen and it is maintained only for the purpose of porting Turbo Pascal programs. For new development, it is recommended to use the sysutils ([1615](#)) unit instead.

45.3 System information

Functions for retrieving and setting general system information such as date and time.

Table 45.2:

Name	Description
DosVersion (697)	Get OS version
GetCBreak (702)	Get setting of control-break handling flag
GetDate (703)	Get system date
GetIntVec (705)	Get interrupt vector status
GetTime (707)	Get system time
GetVerify (707)	Get verify flag
Intr (708)	Execute an interrupt
Keep (708)	Keep process in memory and exit
MSDos (708)	Execute MS-Dos function call
PackTime (709)	Pack time for file time
SetCBreak (709)	Set control-break handling flag
SetDate (710)	Set system date
SetIntVec (711)	Set interrupt vectors
SetTime (711)	Set system time
SetVerify (711)	Set verify flag
SwapVectors (712)	Swap interrupt vectors
UnPackTime (712)	Unpack file time

45.4 Process handling

Functions to handle process information and starting new processes.

Table 45.3:

Name	Description
DosExitCode (696)	Exit code of last executed program
EnvCount (698)	Return number of environment variables
EnvStr (698)	Return environment string pair
Exec (699)	Execute program
GetEnv (703)	Return specified environment string

45.5 Directory and disk handling

Routines to handle disk information.

Table 45.4:

Name	Description
AddDisk (694)	Add disk to list of disks (UNIX only)
DiskFree (695)	Return size of free disk space
DiskSize (696)	Return total disk size

45.6 File handling

Routines to handle files on disk.

Table 45.5:

Name	Description
FExpand (699)	Expand filename to full path
FindClose (699)	Close finfirst/findnext session
FindFirst (700)	Start find of file
FindNext (701)	Find next file
FSearch (701)	Search for file in a path
FSplit (702)	Split filename in parts
GetFAttr (704)	Return file attributes
GetFTime (705)	Return file time
GetLongName (706)	Convert short filename to long filename (DOS only)
GetShortName (706)	Convert long filename to short filename (DOS only)
SetFAttr (710)	Set file attributes
SetFTime (711)	Set file time

45.7 File open mode constants.

These constants are used in the `Mode` field of the `TextRec` record. Gives information on the file-mode of the text I/O. For their definitions consult the following table:

Table 45.6: Possible mode constants

Constant	Description	Value
<code>fmclosed</code>	File is closed	<code>\$D7B0</code>
<code>fminput</code>	File is read only	<code>\$D7B1</code>
<code>fmoutput</code>	File is write only	<code>\$D7B2</code>
<code>fminout</code>	File is read and write	<code>\$D7B3</code>

45.8 File attributes

The File Attribute constants are used in `FindFirst` (700), `FindNext` (701) to determine what type of special file to search for in addition to normal files. These flags are also used in the `SetFAttr` (710) and `GetFAttr` (704) routines to set and retrieve attributes of files. For their definitions consult `fileattributes` (690).

Table 45.7: Possible file attributes

Constant	Description	Value
readonly	Read-Only file attribute	\$01
hidden	Hidden file attribute	\$02
sysfile	System file attribute	\$04
volumeid	Volume ID file attribute	\$08
directory	Directory file attribute	\$10
archive	Archive file attribute	\$20
anyfile	Match any file attribute	\$3F

45.9 Constants, types and variables

45.9.1 Constants

`anyfile` = \$3F

Match any file attribute

`archive` = \$20

Archive file attribute

`directory` = \$10

Directory file attribute

`fauxiliary` = \$0010

CPU auxiliary flag. Not used.

`fcarry` = \$0001

CPU carry flag. Not used.

`FileNameLen` = 255

Maximum length of a filename

`fmclosed` = \$D7B0

File is closed

`fminout` = \$D7B3

File is read and write

`fminput` = \$D7B1

File is read only

`fmoutput = $D7B2`

File is write only

`foverflow = $0800`

CPU overflow flag. Not used.

`fparity = $0004`

CPU parity flag. Not used.

`fsign = $0080`

CPU sign flag. Not used.

`fzero = $0040`

CPU zero flag. Not used.

`hidden = $02`

Hidden file attribute

`readonly = $01`

Read-Only file attribute

`sysfile = $04`

System file attribute

`volumeid = $08`

Volume ID file attribute

45.9.2 Types

`ComStr = string`

Command-line string type

`DirStr = string`

Full directory string type.

`ExtStr = string`

Filename extension string type.

```
NameStr = string
```

Full filename string type.

```
PathStr = string
```

Full File path string type.

```
Registers = packed record
case i : Integer of
0: (
  ax : Word;
  f1 : Word;
  bx : Word;
  f2 : Word;
  cx : Word;
  f3 : Word;
  dx : Word;
  f4 : Word;
  bp : Word;
  f5 : Word;
  si : Word;
  f51 : Word;
  di : Word;
  f6 : Word;
  ds : Word;
  f7 : Word;
  es : Word;
  f8 : Word;
  flags : Word;
  fs : Word;
  gs : Word
  ;
);
1: (
  al : Byte;
  ah : Byte;
  f9 : Byte;
  f10 : Byte;
  bl
  : Byte;
  bh : Byte;
  f11 : Byte;
  f12 : Byte;
  cl : Byte;
  ch
  : Byte;
  f13 : Byte;
  f14 : Byte;
  dl : Byte;
  dh : Byte;
```

```
);
  2: (
    eax : LongInt;
    ebx : LongInt;
    ecx : LongInt;
    edx : LongInt
  ;
    ebp : LongInt;
    esi : LongInt;
    edi : LongInt;
  );
end
```

This structure is only defined on a i386 compatible 32-bit platform, and is not used anywhere: it is defined for Turbo Pascal backwards compatibility only.

45.9.3 Variables

`DosError` : Integer

The `DosError` variable is used by the procedures in the `Dos` unit to report errors. It can have the following values :

Table 45.8: Dos error codes

Value	Meaning
2	File not found.
3	Path not found.
5	Access denied.
6	Invalid handle.
8	Not enough memory.
10	Invalid environment.
11	Invalid format.
18	No more files.

Other values are possible, but are not documented.

45.10 Procedures and functions

45.10.1 AddDisk

Synopsis: Add disk definition to list if drives (Unix only)

Declaration: `function AddDisk(const path: string) : Byte`

Visibility: default

Description: `AddDisk` adds a filename `S` to the internal list of disks. It is implemented for systems which do not use DOS type drive letters. This list is used to determine which disks to use in the `DiskFree` (695) and `DiskSize` (696) calls. The `DiskFree` (695) and `DiskSize` (696) functions need a file on the specified drive, since this is required for the `statfs` system call. The names are added sequentially. The `Dos` initialization code presets the first three disks to:

- ' .' for the current drive,
- '/fd0/ .' for the first floppy-drive (Linux only).
- '/fd1/ .' for the second floppy-drive (Linux only).
- '/' for the first hard disk.

The first call to `AddDisk` will therefore add a name for the second harddisk, The second call for the third drive, and so on until 23 drives have been added (corresponding to drives 'D:' to 'Z:')

Errors: None

See also: [DiskFree \(695\)](#), [DiskSize \(696\)](#)

45.10.2 DiskFree

Synopsis: Get free size on Disk.

Declaration: `function DiskFree(drive: Byte) : Int64`

Visibility: default

Description: `DiskFree` returns the number of free bytes on a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy a:, 2 for floppy b:, etc. A value of 0 returns the free space on the current drive.

Remark For Unices: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the `Dos` unit, and have been preset to :

- ' .' for the current drive,
- '/fd0/ .' for the first floppy-drive (Linux only).
- '/fd1/ .' for the second floppy-drive (Linux only).
- '/' for the first hard disk.

There is room for 1-26 drives. You can add a drive with the `AddDisk` ([694](#)) procedure. These settings can be coded in `dos.pp`, in the initialization part.

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: [DiskSize \(696\)](#), [AddDisk \(694\)](#)

Listing: `./examples/dosex/ex6.pp`

Program `Example6;`
uses `Dos;`

{ Program to demonstrate the DiskSize and DiskFree function. }

begin
 WriteLn('This partition size has ', **DiskSize**(0), ' bytes');
 WriteLn('Currently ', **DiskFree**(0), ' bytes are free');
end.

45.10.3 DiskSize

Synopsis: Get total size of disk.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the total size (in bytes) of a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy a:, 2 for floppy b:, etc. A value of 0 returns the size of the current drive.

Remark For Unix only: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the Dos unit, and have been preset to :

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (Linux only).
- `'/fd1/.'` for the second floppy-drive (Linux only).
- `'/'` for the first hard disk.

There is room for 1-26 drives. You can add a drive with the `AddDisk` (694) procedure. These settings can be coded in `dos.pp`, in the initialization part.

For an example, see `DiskFree` (695).

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: `DiskFree` (695), `AddDisk` (694)

45.10.4 DosExitCode

Synopsis: Exit code of last executed program.

Declaration: `function DosExitCode : Word`

Visibility: default

Description: `DosExitCode` contains (in the low byte) the exit-code of a program executed with the `Exec` call.

Errors: None.

See also: `Exec` (699)

Listing: `./examples/dosex/ex5.pp`

```

Program Example5;
uses Dos;

{ Program to demonstrate the Exec and DosExitCode function. }

begin
  {$IFDEF Unix}
    WriteLn( 'Executing /bin/ls -la ');
    Exec( '/bin/ls ', '-la ');
  {$ELSE}
    WriteLn( 'Executing Dir ');
    Exec( GetEnv( 'COMSPEC' ), '/C dir ');
  {$ENDIF}
  WriteLn( 'Program returned with ExitCode ', Lo(DosExitCode));
end.

```

45.10.5 DosVersion

Synopsis: Current OS version

Declaration: `function DosVersion : Word`

Visibility: default

Description: `DosVersion` returns the operating system or kernel version. The low byte contains the major version number, while the high byte contains the minor version number.

Remark On systems where versions consists of more then two numbers, only the first two numbers will be returned. For example Linux version 2.1.76 will give you `DosVersion` 2.1. Some operating systems, such as FreeBSD, do not have system calls to return the kernel version, in that case a value of 0 will be returned.

Errors: None.

Listing: `./examples/dosex/ex1.pp`

```

Program Example1;
uses Dos;

{ Program to demonstrate the DosVersion function. }

var
    OS      : string[32];
    Version : word;
begin
    {$IFDEF LINUX}
        OS:= 'Linux';
    {$ENDIF}
    {$ifdef FreeBSD}
        OS:= 'FreeBSD';
    {$endif}
    {$ifdef NetBSD}
        OS:= 'NetBSD';
    {$endif}
    {$ifdef Solaris}
        OS:= 'Solaris';
    {$endif}
    {$ifdef QNX}
        OS:= 'QNX';
    {$endif}

    {$IFDEF DOS}
        OS:= 'Dos';
    {$ENDIF}
    Version:=DosVersion;
    WriteLn('Current ',OS,' version is ',Lo(Version),'. ',Hi(Version));
end.

```

45.10.6 DTToUnixDate

Synopsis: Convert a `DateTime` to Unix timestamp

Declaration: `function DTToUnixDate(DT: DateTime) : LongInt`

Visibility: default

Description: `DTToUnixDate` converts the `DateTime` value in `DT` to a Unix timestamp. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: `UnixDateToDT` (712), `PackTime` (709), `UnpackTime` (712), `GetTime` (707), `SetTime` (711)

45.10.7 EnvCount

Synopsis: Return the number of environment variables

Declaration: `function EnvCount : LongInt`

Visibility: default

Description: `EnvCount` returns the number of environment variables.

Errors: None.

See also: `EnvStr` (698), `GetEnv` (703)

45.10.8 EnvStr

Synopsis: Return environment variable by index

Declaration: `function EnvStr(Index: LongInt) : string`

Visibility: default

Description: `EnvStr` returns the `Index`-th `Name=Value` pair from the list of environment variables. The index of the first pair is zero.

Errors: The length is limited to 255 characters.

See also: `EnvCount` (698), `GetEnv` (703)

Listing: `./examples/dosex/ex13.pp`

```

Program Example13;
uses Dos;

{ Program to demonstrate the EnvCount and EnvStr function. }

var
  i : Longint;
begin
  WriteLn('Current Environment is:');
  for i:=1 to EnvCount do
    WriteLn(EnvStr(i));
end.

```

45.10.9 Exec

Synopsis: Execute another program, and wait for it to finish.

Declaration: `procedure Exec(const path: PathStr; const comline: ComStr)`

Visibility: default

Description: `Exec` executes the program in `Path`, with the options given by `ComLine`. The program name should *not* appear again in `ComLine`, it is specified in `Path`. `Comline` contains only the parameters that are passed to the program.

After the program has terminated, the procedure returns. The Exit value of the program can be consulted with the `DosExitCode` function.

For an example, see `DosExitCode` (696)

Errors: Errors are reported in `DosError`.

See also: `DosExitCode` (696)

45.10.10 FExpand

Synopsis: Expand a relative path to an absolute path

Declaration: `function FExpand(const path: PathStr) : PathStr`

Visibility: default

Description: `FExpand` takes its argument and expands it to a complete filename, i.e. a filename starting from the root directory of the current drive, prepended with the drive-letter or volume name (when supported).

Remark On case sensitive file systems (such as Unix and Linux), the resulting name is left as it is, otherwise it is converted to uppercase.

Errors: `FSplit` (702)

Listing: `./examples/dosex/ex11.pp`

```

Program Example11;
uses Dos;

{ Program to demonstrate the FExpand function. }

begin
  WriteLn('Expanded Name of this program is ',FExpand(ParamStr(0)));
end.
```

45.10.11 FindClose

Synopsis: Dispose resources allocated by a `FindFirst` (700)/`FindNext` (701) sequence.

Declaration: `procedure FindClose(var f: SearchRec)`

Visibility: default

Description: `FindClose` frees any resources associated with the search record `F`.

This call is needed to free any internal resources allocated by the `FindFirst` (700) or `FindNext` (701) calls.

The Unix implementation of the Dos unit therefore keeps a table of open directories, and when the table is full, closes one of the directories, and reopens another. This system is adequate but slow if you use a lot of `searchrecs`.

So, to speed up the `findfirst/findnext` system, the `FindClose` call was implemented. When you don't need a `searchrec` any more, you can tell this to the Dos unit by issuing a `FindClose` call. The directory which is kept open for this `searchrec` is then closed, and the table slot freed.

Remark It is recommended to use the Linux call `Glob` when looking for files on Linux.

Errors: Errors are reported in `DosError`.

See also: `FindFirst` (700), `FindNext` (701)

45.10.12 FindFirst

Synopsis: Start search for one or more files.

Declaration: `procedure FindFirst(const path: PathStr; attr: Word; var f: SearchRec)`

Visibility: default

Description: `FindFirst` searches the file specified in `Path`. Normal files, as well as all special files which have the attributes specified in `Attr` will be returned.

It returns a `SearchRec` record for further searching in `F`. `Path` can contain the wildcard characters `?` (matches any single character) and `*` (matches 0 ore more arbitrary characters). In this case `FindFirst` will return the first file which matches the specified criteria. If `DosError` is different from zero, no file(s) matching the criteria was(were) found.

Remark On the EMX target, you cannot issue two different `FindFirst` calls. That is, you must close any previous search operation with `FindClose` (699) before starting a new one. Failure to do so will end in a Run-Time Error 6 (Invalid file handle)

Errors: Errors are reported in `DosError`.

See also: `FindNext` (701), `FindClose` (699)

Listing: `./examples/dosex/ex7.pp`

```

Program Example7;
uses Dos;

{ Program to demonstrate the FindFirst and FindNext function. }

var
  Dir : SearchRec;
begin
  FindFirst( ' *.* ', archive, Dir);
  WriteLn( 'FileName '+Space(32), 'FileSize ':9);
  while (DosError=0) do
    begin
      WriteLn( Dir.Name+Space(40-Length( Dir.Name)), Dir.Size:9);
      FindNext( Dir);
    end;
  FindClose( Dir);
end.

```

45.10.13 FindNext

Synopsis: Find next matching file after FindFirst (700)

Declaration: `procedure FindNext (var f: SearchRec)`

Visibility: default

Description: `FindNext` takes as an argument a `SearchRec` from a previous `FindNext` call, or a `FindFirst` call, and tries to find another file which matches the criteria, specified in the `FindFirst` call. If `DosError` is different from zero, no more files matching the criteria were found.

For an example, see `FindFirst` (700).

Errors: `DosError` is used to report errors.

See also: `FindFirst` (700), `FindClose` (699)

45.10.14 FSearch

Synopsis: Search a file in searchpath

Declaration: `function FSearch (path: PathStr; dirlist: string) : PathStr`

Visibility: default

Description: `FSearch` searches the file `Path` in all directories listed in `DirList`. The full name of the found file is returned. `DirList` must be a list of directories, separated by semi-colons. When no file is found, an empty string is returned.

Remark On Unix systems, `DirList` can also be separated by colons, as is customary on those environments.

Errors: None.

See also: `FExpand` (699)

Listing: `./examples/dosex/ex10.pp`

```

program Example10;

uses Dos;

{ Program to demonstrate the FSearch function. }

var s:pathstr;

begin
  s:=FSearch(ParamStr(1),GetEnv('PATH'));
  if s='' then
    WriteLn(ParamStr(1),' not Found in PATH')
  else
    WriteLn(ParamStr(1),' Found in PATH at ',s);
end.

```

45.10.15 FSplit

Synopsis: Split a full-path filename in parts.

Declaration: `procedure FSplit(path: PathStr; var dir: DirStr; var name: NameStr;
var ext: ExtStr)`

Visibility: default

Description: `FSplit` splits a full file name into 3 parts : A Path, a Name and an extension (in `ext`.) The extension is taken to be all letters after the *last* dot (.). For Dos, however, an exception is made when `LFNSupport=False`, then the extension is defined as all characters after the *first* dot.

Errors: None.

See also: `FSearch` ([701](#))

Listing: `./examples/dosex/ex12.pp`

```

program Example12;

uses Dos;

{ Program to demonstrate the FSplit function. }

var dir: dirstr;
    name: namestr;
    ext: extstr;

begin
    FSplit(ParamStr(1), dir, name, ext);
    WriteLn('Splitted ', ParamStr(1), ' in: ');
    WriteLn('Path      : ', dir);
    WriteLn('Name       : ', name);
    WriteLn('Extension: ', ext);
end.

```

45.10.16 GetCBreak

Synopsis: Get control-Break flag

Declaration: `procedure GetCBreak(var breakvalue: Boolean)`

Visibility: default

Description: `GetCBreak` gets the status of CTRL-Break checking under Dos and Amiga. When `BreakValue` is false, then Dos only checks for the CTRL-Break key-press when I/O is performed. When it is set to True, then a check is done at every system call.

Remark Under non-Dos and non-Amiga operating systems, `BreakValue` always returns True.

Errors: None

See also: `SetCBreak` ([709](#))

45.10.17 GetDate

Synopsis: Get the current date

Declaration: `procedure GetDate(var year: Word; var month: Word; var mday: Word;
var wday: Word)`

Visibility: default

Description: `GetDate` returns the system's date. `Year` is a number in the range 1980..2099. `mday` is the day of the month, `wday` is the day of the week, starting with Sunday as day 0.

Errors: None.

See also: `GetTime` (707), `SetDate` (710)

Listing: ./examples/dosex/ex2.pp

```

Program Example2;
uses Dos;

{ Program to demonstrate the GetDate function. }

const
  DayStr: array [0..6] of string [3] = ( 'Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat' );
  MonthStr: array [1..12] of string [3] = ( 'Jan', 'Feb', 'Mar', 'Apr', 'May', 'Jun',
                                           'Jul', 'Aug', 'Sep', 'Oct', 'Nov', 'Dec' );

var
  Year, Month, Day, WDay : word;
begin
  GetDate (Year, Month, Day, WDay);
  WriteLn ( 'Current date' );
  WriteLn ( DayStr[WDay], ', ', ' ', Day, ' ', MonthStr[Month], ' ', Year, ' ' );
end.

```

45.10.18 GetEnv

Synopsis: Get environment variable by name.

Declaration: `function GetEnv(envvar: string) : string`

Visibility: default

Description: `Getenv` returns the value of the environment variable `EnvVar`. When there is no environment variable `EnvVar` defined, an empty string is returned.

Remark Under some operating systems (such as Unix), case is important when looking for `EnvVar`.

Errors: None.

See also: `EnvCount` (698), `EnvStr` (698)

Listing: ./examples/dosex/ex14.pp

```

Program Example14;
uses Dos;

{ Program to demonstrate the GetEnv function. }

begin

```

```

  WriteLn('Current PATH is ',GetEnv('PATH'));
end.

```

45.10.19 GetFAttr

Synopsis: Get file attributes

Declaration: `procedure GetFAttr(var f; var attr: Word)`

Visibility: default

Description: `GetFAttr` returns the file attributes of the file-variable `f`. `F` can be a untyped or typed file, or of type `Text`. `f` must have been assigned, but not opened. The attributes can be examined with the following constants :

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

Under Linux, supported attributes are:

- `Directory`
- `ReadOnly` if the current process doesn't have access to the file.
- `Hidden` for files whose name starts with a dot (`'.'`).

Errors: Errors are reported in `DosError`

See also: `SetFAttr` ([710](#))

Listing: `./examples/dosex/ex8.pp`

```

Program Example8;
uses Dos;

{ Program to demonstrate the GetFAttr function. }

var
  Attr : Word;
  f    : File;
begin
  Assign(f,ParamStr(1));
  GetFAttr(f,Attr);
  WriteLn('File ',ParamStr(1),' has attribute ',Attr);
  if (Attr and archive)<>0 then WriteLn('– Archive');
  if (Attr and directory)<>0 then WriteLn('– Directory');
  if (Attr and readonly)<>0 then WriteLn('– Read-Only');
  if (Attr and sysfile)<>0 then WriteLn('– System');
  if (Attr and hidden)<>0 then WriteLn('– Hidden');
end.

```

45.10.20 GetFTime

Synopsis: Get file last modification time.

Declaration: `procedure GetFTime(var f; var time: LongInt)`

Visibility: default

Description: `GetFTime` returns the modification time of a file. This time is encoded and must be decoded with `UnPackTime`. `F` must be a file type, which has been assigned, and opened.

Errors: Errors are reported in `DosError`

See also: `SetFTime` (711), `PackTime` (709), `UnPackTime` (712)

Listing: `./examples/dosex/ex9.pp`

```

Program Example9;
uses Dos;

{ Program to demonstrate the GetFTime function. }

Function L0(w:word): string;
var
  s : string;
begin
  Str(w,s);
  if w<10 then
    L0:= '0'+s
  else
    L0:=s;
end;

var
  f      : File;
  Time   : Longint;
  DT     : DateTime;
begin
  if Paramcount>0 then
    Assign(f,ParamStr(1))
  else
    Assign(f,'ex9.pp');
  Reset(f);
  GetFTime(f,Time);
  Close(f);
  UnPackTime(Time,DT);
  Write('File ',ParamStr(1),' is last modified on ');
  Writeln(L0(DT.Month),'-',L0(DT.Day),'-',DT.Year,
    ' at ',L0(DT.Hour),':',L0(DT.Min));
end.

```

45.10.21 GetIntVec

Synopsis: Get interrupt vector

Declaration: `procedure GetIntVec(intno: Byte; var vector: pointer)`

Visibility: default

Description: `GetIntVec` returns the address of interrupt vector `IntNo`.

Remark This call does nothing, it is present for compatibility only. Modern systems do not allow low level access to the hardware.

Errors: None.

See also: `SetIntVec` (711)

45.10.22 GetLongName

Synopsis: Get the long filename of a DOS 8.3 filename.

Declaration: `function GetLongName (var p: string) : Boolean`

Visibility: default

Description: This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetLongName` changes the filename `p` to a long filename if the API call to do this is successful. The resulting string is the long file name corresponding to the short filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the API call was not successful, `False` is returned.

See also: `GetShortName` (706)

45.10.23 GetMsCount

Synopsis: Number of milliseconds since a starting point.

Declaration: `function GetMsCount : Int64`

Visibility: default

Description: `GetMsCount` returns a number of milliseconds elapsed since a certain moment in time. This moment in time is implementation dependent. This function is used for timing purposes: Subtracting the results of 2 subsequent calls to this function returns the number of milliseconds elapsed between the two calls.

This call is not very reliable, it is recommended to use some system specific calls for timings.

See also: `GetTime` (707)

45.10.24 GetShortName

Synopsis: Get the short (8.3) filename of a long filename.

Declaration: `function GetShortName (var p: string) : Boolean`

Visibility: default

Description: This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetShortName` changes the filename `p` to a short filename if the API call to do this is successful. The resulting string is the short file name corresponding to the long filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the API call was not successful, `False` is returned.

See also: `GetLongName` ([706](#))

45.10.25 GetTime

Synopsis: Return the current time

Declaration: `procedure GetTime(var hour: Word; var minute: Word; var second: Word; var sec100: Word)`

Visibility: default

Description: `GetTime` returns the system's time. `Hour` is on a 24-hour time scale. `sec100` is in hundredth of a second.

Remark Certain operating systems (such as Amiga), always set the `sec100` field to zero.

Errors: None.

See also: `GetDate` ([703](#)), `SetTime` ([711](#))

Listing: `./examples/dosex/ex3.pp`

```

Program Example3;
uses Dos;

{ Program to demonstrate the GetTime function. }

Function L0(w: word): string;
var
  s : string;
begin
  Str(w, s);
  if w<10 then
    L0:= '0'+s
  else
    L0:=s;
end;

var
  Hour, Min, Sec, HSec : word;
begin
  GetTime(Hour, Min, Sec, HSec);
  WriteLn('Current time ');
  WriteLn(L0(Hour), ': ', L0(Min), ': ', L0(Sec));
end.

```

45.10.26 GetVerify

Synopsis: Get verify flag

Declaration: `procedure GetVerify(var verify: Boolean)`

Visibility: default

Description: `GetVerify` returns the status of the verify flag under Dos. When `Verify` is `True`, then Dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

Remark Under non-Dos systems (excluding EMX applications running under vanilla DOS), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` ([711](#))

45.10.27 Intr

Synopsis: Execute interrupt

Declaration: `procedure Intr(intno: Byte; var regs: Registers)`

Visibility: default

Description: `Intr` executes a software interrupt number `IntNo` (must be between 0 and 255), with processor registers set to `Regs`. After the interrupt call returned, the processor registers are saved in `Regs`.

Remark Under non-Dos operating systems, this call does nothing.

Errors: None.

See also: `MSDos` ([708](#))

45.10.28 Keep

Synopsis: Terminate and stay resident.

Declaration: `procedure Keep(exitcode: Word)`

Visibility: default

Description: `Keep` terminates the program, but stays in memory. This is used for TSR (Terminate Stay Resident) programs which catch some interrupt. `ExitCode` is the same parameter as the `Halt` function takes.

Remark This call does nothing, it is present for compatibility only.

Errors: None.

45.10.29 MSDos

Synopsis: Execute MS-DOS system call

Declaration: `procedure MSDos(var regs: Registers)`

Visibility: default

Description: `MSDos` executes an operating system call. This is the same as doing a `Intr` call with the interrupt number for an OS call.

Remark Under non-Dos operating systems, this call does nothing. On DOS systems, this calls interrupt \$21.

Errors: None.

See also: `Intr` ([708](#))

45.10.30 PackTime

Synopsis: Pack DateTime value to a packed-time format.

Declaration: `procedure PackTime(var t: DateTime; var p: LongInt)`

Visibility: default

Description: `UnPackTime` converts the date and time specified in `T` to a packed-time format which can be fed to `SetFTime`.

Errors: None.

See also: `SetFTime` (711), `FindFirst` (700), `FindNext` (701), `UnPackTime` (712)

Listing: `./examples/dosex/ex4.pp`

```

Program Example4;
uses Dos;

{ Program to demonstrate the PackTime and UnPackTime functions. }

var
  DT   : DateTime;
  Time : longint;
begin
  with DT do
    begin
      Year:=2008;
      Month:=11;
      Day:=11;
      Hour:=11;
      Min:=11;
      Sec:=11;
    end;
  PackTime(DT,Time);
  WriteLn('Packed Time : ',Time);
  UnPackTime(Time,DT);
  WriteLn('Unpacked Again:');
  with DT do
    begin
      WriteLn('Year   ',Year);
      WriteLn('Month  ',Month);
      WriteLn('Day    ',Day);
      WriteLn('Hour   ',Hour);
      WriteLn('Min    ',Min);
      WriteLn('Sec    ',Sec);
    end;
end.

```

45.10.31 SetCBreak

Synopsis: Set Control-Break flag status

Declaration: `procedure SetCBreak(breakvalue: Boolean)`

Visibility: default

Description: `SetCBreak` sets the status of CTRL-Break checking. When `BreakValue` is `false`, then `Dos` only checks for the CTRL-Break key-press when I/O is performed. When it is set to `True`, then a check is done at every system call.

Remark Under non-Dos and non-Amiga operating systems, this call does nothing.

Errors: None.

See also: `GetCBreak` (702)

45.10.32 `SetDate`

Synopsis: Set system date

Declaration: `procedure SetDate(year: Word; month: Word; day: Word)`

Visibility: default

Description: `SetDate` sets the system's internal date. `Year` is a number between 1980 and 2099.

Remark On a Unix machine, there must be root privileges, otherwise this routine will do nothing. On other Unix systems, this call currently does nothing.

Errors: None.

See also: `GetDate` (703), `SetTime` (711)

45.10.33 `SetFAttr`

Synopsis: Set file attributes

Declaration: `procedure SetFAttr(var f; attr: Word)`

Visibility: default

Description: `SetFAttr` sets the file attributes of the file-variable `F`. `F` can be a untyped or typed file, or of type `Text`. `F` must have been assigned, but not opened. The attributes can be a sum of the following constants:

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

Remark Under Unix like systems (such as Linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`.

See also: `GetFAttr` (704)

45.10.34 SetFTime

Synopsis: Set file modification time.

Declaration: `procedure SetFTime(var f; time: LongInt)`

Visibility: default

Description: `SetFTime` sets the modification time of a file, this time is encoded and must be encoded with `PackTime`. `F` must be a file type, which has been assigned, and opened.

Remark Under Unix like systems (such as Linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`

See also: `GetFTime` (705), `PackTime` (709), `UnPackTime` (712)

45.10.35 SetIntVec

Synopsis: Set interrupt vector

Declaration: `procedure SetIntVec(intno: Byte; vector: pointer)`

Visibility: default

Description: `SetIntVec` sets interrupt vector `IntNo` to `Vector`. `Vector` should point to an interrupt procedure.

Remark This call does nothing, it is present for compatibility only.

Errors: None.

See also: `GetIntVec` (705)

45.10.36 SetTime

Synopsis: Set system time

Declaration: `procedure SetTime(hour: Word; minute: Word; second: Word; sec100: Word)`

Visibility: default

Description: `SetTime` sets the system's internal clock. The `Hour` parameter is on a 24-hour time scale.

Remark On a Linux machine, there must be root privileges, otherwise this routine will do nothing. On other Unix systems, this call currently does nothing.

Errors: None.

See also: `GetTime` (707), `SetDate` (710)

45.10.37 SetVerify

Synopsis: Set verify flag

Declaration: `procedure SetVerify(verify: Boolean)`

Visibility: default

Description: `SetVerify` sets the status of the verify flag under Dos. When `Verify` is `True`, then Dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

Remark Under non-Dos operating systems (excluding EMX applications running under vanilla Dos), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` (711)

45.10.38 SwapVectors

Synopsis: Swap interrupt vectors

Declaration: `procedure SwapVectors`

Visibility: `default`

Description: `SwapVectors` swaps the contents of the internal table of interrupt vectors with the current contents of the interrupt vectors. This is called typically in before and after an `Exec` call.

Remark Under certain operating systems, this routine may be implemented as an empty stub.

Errors: None.

See also: `Exec` (699), `SetIntVec` (711)

45.10.39 UnixDateToDt

Synopsis: Convert a Unix timestamp to a `DateTime` record

Declaration: `procedure UnixDateToDt (SecsPast: LongInt; var Dt: DateTime)`

Visibility: `default`

Description: `DTToUnixDate` converts the Unix timestamp value in `SecsPast` to a `DateTime` representation in `DT`. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: `DTToUnixDate` (697), `PackTime` (709), `UnpackTime` (712), `GetTime` (707), `SetTime` (711)

45.10.40 UnpackTime

Synopsis: Unpack packed file time to a `DateTime` value

Declaration: `procedure UnpackTime (p: LongInt; var t: DateTime)`

Visibility: `default`

Description: `UnPackTime` converts the file-modification time in `p` to a `DateTime` record. The file-modification time can be returned by `GetFTime`, `FindFirst` or `FindNext` calls.

For an example, see `PackTime` (709).

Errors: None.

See also: `GetFTime` (705), `FindFirst` (700), `FindNext` (701), `PackTime` (709)

45.10.41 weekday

Synopsis: Return the day of the week

Declaration: `function weekday(y: LongInt; m: LongInt; d: LongInt) : LongInt`

Visibility: default

Description: `WeekDay` returns the day of the week on which the day Y/M/D falls. Sunday is represented by 0, Saturday is 6.

Errors: On error, -1 is returned.

See also: `PackTime` (709), `UnpackTime` (712), `GetTime` (707), `SetTime` (711)

45.11 DateTime

```

DateTime = packed record
  Year : Word;
  Month : Word;
  Day : Word
;
  Hour : Word;
  Min : Word;
  Sec : Word;
end

```

The `DateTime` type is used in `PackTime` (709) and `UnPackTime` (712) for setting/reading file times with `GetFTime` (705) and `SetFTime` (711).

45.12 SearchRec

```

SearchRec = packed record
  SearchPos : TOff;
  SearchNum : LongInt
;
  DirPtr : Pointer;
  SearchType : Byte;
  SearchAttr : Byte;
  Mode : Word;
  Fill : Array[1..1] of Byte;
  Attr : Byte;
  Time
  : LongInt;
  Size : LongInt;
  Reserved : Word;
  Name : string;
  SearchSpec : string;
  NamePos : Word;
end

```

`SearchRec` is filled by the `FindFirst` (700) call and can be used in subsequent `FindNext` (701) calls to search for files. The structure of this record depends on the platform. Only the following fields are present on all platforms:

Attr File attributes.

Time File modification time.

Size File size

Name File name (name part only, no path)

Mode File access mode (Linux only)

Chapter 46

Reference for unit 'dxeload'

46.1 Used units

Table 46.1: Used units by unit 'dxeload'

Name	Page
System	1339

46.2 Overview

The `dxeload` unit was implemented by Pierre Mueller for dos, it allows to load a DXE file (an object file with 1 entry point) into memory and return a pointer to the entry point.

It exists only for dos.

46.3 Procedures and functions

46.3.1 `dxeload`

Synopsis: Load DXE file in memory

Declaration: `function dxeload(filename: string) : pointer`

Visibility: default

Description: `dxeload` loads the contents of the file `filename` into memory. It performs the necessary relocations in the object code, and returns then a pointer to the entry point of the code.

For an example, see the `emu387` ([720](#)) unit in the RTL.

Errors: If an error occurs during the load or relocations, `Nil` is returned.

Chapter 47

Reference for unit 'dynlibs'

47.1 Used units

Table 47.1: Used units by unit 'dynlibs'

Name	Page
System	1339

47.2 Overview

The Dynlibs unit provides support for dynamically loading shared libraries. It is available only on those platforms that support shared libraries. The functionality available here may only be a part of the functionality available on each separate platform, in the interest of portability.

On UNIX platforms, using this unit will cause the program to be linked to the C library, as most shared libraries are implemented in C and the dynamical linker too.

47.3 Constants, types and variables

47.3.1 Constants

`NilHandle = System.NilHandle`

Correctly typed Nil handle - returned on error by `LoadLibrary` ([718](#))

`SharedSuffix = System.SharedSuffix`

`SharedSuffix` contains the extension of a shared library (dynamically loadable library) on the current platform. It does not contain the . (dot) character. This can be used to determine the name of a shared library in a platform independent way.

47.3.2 Types

`HModule = TLibHandle`

Alias for `TLibHandle` (717) type.

```
TLibHandle = System.TLibHandle
```

`TLibHandle` should be considered an opaque type. It is defined differently on various platforms. The definition shown here depends on the platform for which the documentation was generated.

47.4 Procedures and functions

47.4.1 FreeLibrary

Synopsis: For compatibility with Delphi/Windows: Unload a library

Declaration: `function FreeLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

Description: `FreeLibrary` provides the same functionality as `UnloadLibrary` (719), and is provided for compatibility with Delphi.

See also: `UnloadLibrary` (719)

47.4.2 GetLoadErrorStr

Synopsis: Return a description of the last error during load/get procedure address operations.

Declaration: `function GetLoadErrorStr : string`

Visibility: default

Description: `GetLoadErrorStr` returns a textual description of the last library loading or unloading error, or a call to `GetProcAddress` (718). No other system calls may be made between the load call and the call of `GetLoadErrorStr`.

See also: `LoadLibrary` (718), `GetProcAddress` (718)

47.4.3 GetProcAddress

Synopsis: For compatibility with Delphi/Windows: Get the address of a procedure

Declaration: `function GetProcAddress(Lib: TLibHandle; const ProcName: AnsiString)
: Pointer`

Visibility: default

Description: `GetProcAddress` provides the same functionality as `GetProcAddress` (718), and is provided for compatibility with Delphi.

See also: `GetProcAddress` (718)

47.4.4 GetProcedureAddress

Synopsis: Get the address of a procedure or symbol in a dynamic library.

Declaration:

```
function GetProcedureAddress(Lib: TLibHandle;
                           const ProcName: AnsiString) : Pointer
function GetProcedureAddress(Lib: TLibHandle; Ordinal: TOrdinalEntry)
                           : Pointer
```

Visibility: default

Description: `GetProcedureAddress` returns a pointer to the location in memory of the symbol `ProcName` or ordinal value `Ordinal` in the dynamically loaded library specified by its handle `lib`. If the symbol cannot be found or the handle is invalid, `Nil` is returned.

On Windows, only an exported procedure or function can be searched this way. On Unix platforms the location of any exported symbol can be retrieved this way.

Only windows and OS/2 support getting the address of a function using an ordinal value.

Errors: If the symbol cannot be found, `Nil` is returned.

See also: [LoadLibrary \(718\)](#), [UnLoadLibrary \(719\)](#)

47.4.5 LoadLibrary

Synopsis: Load a dynamic library and return a handle to it.

Declaration:

```
function LoadLibrary(const Name: RawByteString) : TLibHandle
function LoadLibrary(const Name: UnicodeString) : TLibHandle
```

Visibility: default

Description: `LoadLibrary` loads a dynamic library in file `Name` and returns a handle to it. If the library cannot be loaded, `NilHandle (716)` is returned.

No assumptions should be made about the location of the loaded library if a relative pathname is specified. The behaviour is dependent on the platform. Therefore it is best to specify an absolute pathname if possible.

Errors: On error, `NilHandle (716)` is returned.

See also: [UnloadLibrary \(719\)](#), [GetProcedureAddress \(718\)](#)

47.4.6 SafeLoadLibrary

Synopsis: Saves the control word and loads a library

Declaration:

```
function SafeLoadLibrary(const Name: RawByteString) : TLibHandle
function SafeLoadLibrary(const Name: UnicodeString) : TLibHandle
```

Visibility: default

Description: `SafeLoadLibrary` saves the FPU control word, and calls `LoadLibrary (718)` with library name `Name`. After that function has returned, the FPU control word is saved again. (only on Intel i386 CPUs).

See also: [LoadLibrary \(718\)](#)

47.4.7 UnloadLibrary

Synopsis: Unload a previously loaded library

Declaration: `function UnloadLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

Description: `UnloadLibrary` unloads a previously loaded library (specified by the handle `lib`). The call returns `True` if successful, `False` otherwise.

Errors: On error, `False` is returned.

See also: `LoadLibrary` ([718](#)), `GetProcAddress` ([718](#))

Chapter 48

Reference for unit 'emu387'

48.1 Used units

Table 48.1: Used units by unit 'emu387'

Name	Page
System	1339

48.2 Overview

The `emu387` unit was written by Pierre Mueller for dos. It sets up the coprocessor emulation for FPC under dos. It is not necessary to use this unit on other OS platforms because they either simply do not run on a machine without coprocessor, or they provide the coprocessor emulation themselves.

It shouldn't be necessary to use the function in this unit, it should be enough to place this unit in the `uses` clause of your program to enable the coprocessor emulation under dos. The unit initialization code will try and load the coprocessor emulation code and initialize it.

48.3 Procedures and functions

48.3.1 `npxsetup`

Synopsis: Set up coprocessor emulation.

Declaration: `procedure npxsetup(prog_name: string)`

Visibility: `default`

Description: `npxsetup` checks whether a coprocessor is found. If not, it loads the file `wmemu387.dxe` into memory and initializes the code in it.

If the environment variable `387` is set to `N`, then the emulation will be loaded, even if there is a coprocessor present. If the variable doesn't exist, or is set to any other value, the unit will try to detect the presence of a coprocessor unit.

The function searches the file `wmemu387.dxe` in the following way:

- 1.If the environment variable `EMU387` is set, then it is assumed to point at the `wmemu387.dxe` file.
- 2.if the environment variable `EMU387` does not exist, then the function will take the path part of `prog_name` and look in that directory for the file `wmemu387.dxe`.

It should never be necessary to call this function, because the initialization code of the unit contains a call to the function with as an argument `paramstr(0)`. This means that you should deliver the file `wmemu387.dxe` together with your program.

Errors: If there is an error, an error message is printed to standard error, and the program is halted, since any floating-point code is bound to fail anyhow.

Chapter 49

Reference for unit 'errors'

49.1 Used units

Table 49.1: Used units by unit 'errors'

Name	Page
System	1339
unixtype	2127

49.2 Overview

The errors unit contains routines to convert a UNIX system call error code to an error message: `StrError` ([724](#)). It is only available on UNIX platforms.

49.3 Constants, types and variables

49.3.1 Constants

```
sys_errlist : Array[0..sys_errn-1] of PChar = ('Success', 'Operation not permitted',  
  , 'No such file or directory', 'No such process', 'Interrupted system call',  
  , 'I/O error', 'No such device or address', 'Arg list too long', 'Exec format error',  
  , 'Bad file number', 'No child processes', 'Try again', 'Out of memory',  
  , 'Permission denied', 'Bad address', 'Block device required', 'Device or resource busy',  
  , 'File exists', 'Cross-device link', 'No such device', 'Not a directory',  
  , 'Is a directory', 'Invalid argument', 'File table overflow', 'Too many open files',  
  , 'Not a typewriter', 'Text (code segment) file busy', 'File too large',  
  , 'No space left on device', 'Illegal seek', 'Read-only file system',  
  , 'Too many links', 'Broken pipe', 'Math argument out of domain of function',  
  , 'Math result not representable', 'Resource deadlock would occur',  
  , 'File name too long', 'No record locks available', 'Function not implemented',  
  , 'Directory not empty', 'Too many symbolic links encountered', 'Operation would block',  
  , 'No message of desired type', 'Identifier removed', 'Channel number out of range',  
  , 'Level 2 not synchronized', 'Level 3 halted', 'Level 3 reset', 'Link number out of range',  
  , 'Protocol driver not attached', 'No CSI structure available', 'Level 2 halted'
```

```
, 'Invalid exchange', 'Invalid request descriptor', 'Exchange full'
, 'No anode', 'Invalid request code', 'Invalid slot', 'File locking deadlock error'
, 'Bad font file format', 'Device not a stream', 'No data available'
, 'Timer expired', 'Out of streams resources', 'Machine is not on the network'
, 'Package not installed', 'Object is remote', 'Link has been severed'
, 'Advertise error', 'Srmount error', 'Communication error on send'
, 'Protocol error', 'Multihop attempted', 'RFS specific error', 'Not a data message'
, 'Value too large for defined data type', 'Name not unique on network'
, 'File descriptor in bad state', 'Remote address changed', 'Can not access a needed file'
, 'Accessing a corrupted shared library', '.lib section in a.out corrupted'
, 'Attempting to link in too many shared libraries', 'Cannot exec a shared library'
, 'Illegal byte sequence', 'Interrupted system call should be restarted'
, 'Streams pipe error', 'Too many users', 'Socket operation on non-socket'
, 'Destination address required', 'Message too long', 'Protocol wrong type for socket'
, 'Protocol not available', 'Protocol not supported', 'Socket type not supported'
, 'Operation not supported on transport endpoint', 'Protocol family not supported'
, 'Address family not supported by protocol', 'Address already in use'
, 'Cannot assign requested address', 'Network is down', 'Network is unreachable'
, 'Network dropped connection because of reset', 'Software caused connection abort'
, 'Connection reset by peer', 'No buffer space available', 'Transport endpoint is already connected'
, 'Transport endpoint is not connected', 'Cannot send after transport endpoint shutdown'
, 'Too many references: cannot splice', 'Connection timed out', 'Connection refused'
, 'Host is down', 'No route to host', 'Operation already in progress'
, 'Operation now in progress', 'Stale NFS file handle', 'Structure needs cleaning'
, 'Not a XENIX named type file', 'No XENIX semaphores available',
'Is a named type file', 'Remote I/O error', 'Quota exceeded', 'No medium found'
, 'Wrong medium type')
```

`sys_errn` is an array with then error codes for the current operating system. It should not be used directly, instead use `StrError` (724).

```
sys_errn = 125
```

`sys_errn` is the number of error codes for the current operating system. It should not be used directly, instead use `StrError` (724).

49.4 Procedures and functions

49.4.1 PError

Synopsis: Print error on standard error output

Declaration: `procedure PError(const s: string; Errno: cint)`

Visibility: default

Description: `PError` will print the error message `S` followed by the `errNo` and the result for `StrError(errNo)` for `ErrNo` on standard output.

Errors: None.

See also: `StrError` (724)

49.4.2 StrError

Synopsis: Convert an error code to a string

Declaration: `function StrError(err: cint) : string`

Visibility: default

Description: `StrError` will convert the error code `err` to a string.

Errors: If the error code is unknown or out of bounds, an 'Unknown error (err)' string will be returned.

See also: `PError` ([723](#))

Chapter 50

Reference for unit 'exeinfo'

50.1 Used units

Table 50.1: Used units by unit 'exeinfo'

Name	Page
System	1339

50.2 Overview

The `exeinfo` unit implements some cross-platform routines to examine the contents of an executable: information about sections, mapping addresses to loaded modules etc.

It is mainly used by the `lineinfo` ([955](#)) and `Infodwrf` ([984](#)) unit to examine the binary for debug info.

50.3 Constants, types and variables

50.3.1 Types

`TExeOffset = PtrUInt`

The exact type of `TExeOffset` will differ per platform.

`TExeProcessAddress = PtrUInt`

The exact type of `TExeProcessAddress` will differ per platform.

50.4 Procedures and functions

50.4.1 CloseExeFile

Synopsis: Close a previously opened file.

Declaration: `function CloseExeFile(var e: TExeFile) : Boolean`

Visibility: default

Description: `CloseExeFile` closes an executable file image previously opened with `OpenExeFile` (726), and represented by `e`.

The function returns `True` if the file was closed successfully, or `False` if something went wrong.

Errors: In case of an error, `False` is returned.

See also: `OpenExeFile` (726)

50.4.2 FindExeSection

Synopsis: Find a section in the binary image.

Declaration:

```
function FindExeSection(var e: TExeFile; const secname: string;
                        var secofs: LongInt; var seclen: LongInt)
                        : Boolean
```

Visibility: default

Description: `FindExeSection` examines the binary that was opened with `OpenExeFile` (726) (represented by `e`) and searches for the section named `secname`. If found, the section offset is returned in `secofs` and the section length (in bytes) is returned in `seclen`.

The function returns `True` if the section was found, `False` if not.

See also: `OpenExeFile` (726)

50.4.3 GetModuleByAddr

Synopsis: Return the module name by address

Declaration:

```
procedure GetModuleByAddr(addr: pointer; var baseaddr: pointer;
                        var filename: string)
```

Visibility: default

Description: `GetModuleByAddr` returns the name of the module that contains address `addr`. If successful, it returns `True` and returns the filename in `FileName` and the base address at which it is loaded in `BaseAddr`.

50.4.4 OpenExeFile

Synopsis: Open an executable file

Declaration:

```
function OpenExeFile(var e: TExeFile; const fn: string) : Boolean
```

Visibility: default

Description: `OpenExeFile` opens the executable file `fn` and initializes the structure `e` for subsequent calls to routines in the `exeinfo` unit.

The function returns `True` if the file was opened successfully, false otherwise.

See also: `FindExeSection` (726), `CloseExeFile` (725), `ReadDebugLink` (727)

50.4.5 ReadDebugLink

Synopsis: Read the location of a debug info filename

Declaration: `function ReadDebugLink(var e: TExeFile; var dbgfn: string) : Boolean`

Visibility: default

Description: `ReadDebugLink` examines the `.gnu_debuglink` section to see if the debug information is stored in an external file. If so, then the name of the file with the debug information is returned in the `dbgfn` parameter.

The function returns `false` if there is no external debug information file, or if the file with debug information does not exist. It is searched next to the binary file or in the current directory.

See also: `OpenExeFile` ([726](#)), `CloseExeFile` ([725](#))

50.5 TExeFile

```
TExeFile = record
  f : File;
  size : Int64;
  isopen : Boolean;
  nsects : LongInt;
  sechdrofs : TExeOffset;
  secstrofs : TExeOffset
;
  processaddress : TExeProcessAddress;
  FunctionRelative : Boolean
;
  ImgOffset : TExeOffset;
  filename : string;
  buf : Array[0..
    .4095] of Byte;
  bufsize : LongInt;
  bufcnt : LongInt;
end
```

`TExeFile` is a record used in the various calls of this unit. It contains a file descriptor, and various fields that describe the executable.

The structure of `TExeFile` is opaque, that is, one shouldn't rely on the exactness of this structure, it may change any time in the future.

Chapter 51

Reference for unit 'fgl'

51.1 Used units

Table 51.1: Used units by unit 'fgl'

Name	Page
System	1339
sysutils	1615
Types	1934

51.2 Overview

The `fgl` unit contains some basic list-related generic classes.

51.3 Constants, types and variables

51.3.1 Constants

```
MaxGListSize = MaxInt div 1024
```

deprecated

`MaxGListSize` is the maximum number of elements in the `TFPGList` ([733](#)) list.

```
MaxListSize = Maxint div 16
```

`MaxListSize` is the maximum number of elements a list can contain before the memory runs out.

51.3.2 Types

```
TFPSListCompareFunc = function(Key1: Pointer; Key2: Pointer) : Integer  
  of object
```

`TFPSListCompareFunc` is used in the `TFPSList.Sort` ([765](#)) method to compare 2 elements. The list passes 2 pointers to the actual items to the compare function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

51.4 EListError

51.4.1 Description

`EListError` is the exception used in the `TFPSList` (759) class to indicate errors such as a list index out of bounds, wrong capacity etc.

See also: `TFPSList.Capacity` (765), `TFPSList.Exchange` (762), `TFPSList.Items` (766)

51.5 TFPGInterfacedObjectList

51.5.1 Description

`TFPGList` can be used to specialize a list for any class type `T` that requires reference counting (all objects that implement `IInterface` or `IUnknown`). It will specialize to a list with the same methods as `TFPSList` (759) or classes `TFPList` (728) or `TFPObjectList`

Classes that implement `IInterface` or `IUnknown` require special care to maintain the reference count. The `TFPGInterfacedObjectList` list provides the necessary functionality to deal with this.

See also: `TFPSList` (759), classes `TFPList` (728)

51.5.2 Method overview

Page	Method	Description
730	<code>Add</code>	Add new object of class <code>T</code> to the list.
731	<code>AddList</code>	Adds the elements from another list
731	<code>Assign</code>	Copy objects from Source list
730	<code>Create</code>	Instantiate a new interfaced object list.
730	<code>Extract</code>	Extract an item from the list
730	<code>GetEnumerator</code>	Return a list enumerator for <code>T</code>
731	<code>IndexOf</code>	Index of object
731	<code>Insert</code>	Insert a new object in the list
732	<code>Remove</code>	Remove an object from the list.
732	<code>Sort</code>	Sort the objects in the list

51.5.3 Property overview

Page	Properties	Access	Description
732	<code>First</code>	rw	First non-nil object
733	<code>Items</code>	rw	Indexed access to objects in the list.
733	<code>Last</code>	rw	Last non- <code>Nil</code> object
733	<code>List</code>	r	Internal list pointer

51.5.4 TFPGInterfacedObjectList.Create

Synopsis: Instantiate a new interfaced object list.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new object list. It will simply call the inherited constructor with the correct item size.

See also: `TFPSList.Destroy` ([760](#))

51.5.5 TFPGInterfacedObjectList.Add

Synopsis: Add new object of class `T` to the list.

Declaration: `function Add(const Item: T) : Integer`

Visibility: `public`

Description: `Add` adds a new item `Item` of class type `T` to the list and returns the position at which the item was added. `Add` will increase the reference count of the object.

Errors: If the item could not be added, an `EListError` ([729](#)) exception is raised.

See also: `TFPGInterfacedObjectList.Extract` ([730](#)), `TFPGInterfacedObjectList.Items` ([733](#)), `TFPGInterfacedObjectList.IndexOf` ([731](#))

51.5.6 TFPGInterfacedObjectList.Extract

Synopsis: Extract an item from the list

Declaration: `function Extract(const Item: T) : T`

Visibility: `public`

Description: `Extract` removes `Item` from the list and returns the removed item, or `Nil` if it was not found.
The extracted object will not be destroyed.

Errors: None.

See also: `TFPSList.Delete` ([761](#))

51.5.7 TFPGInterfacedObjectList.GetEnumerator

Synopsis: Return a list enumerator for `T`

Declaration: `function GetEnumerator : TFPGListEnumeratorSpec`

Visibility: `public`

Description: `GetEnumerator` returns an enumerator for the elements in the list. It is a specialized version of `TFPGListEnumerator` ([738](#)).

See also: `TFPGListEnumerator` ([738](#))

51.5.8 TFPGInterfacedObjectList.IndexOf

Synopsis: Index of object

Declaration: `function IndexOf(const Item: T) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `Item` in the list, or -1 if the object does not appear in the list.

Errors: None.

See also: `TFPGInterfacedObjectList.Items` (733), `TFPGInterfacedObjectList.Insert` (731), `TFPGInterfacedObjectList.Add` (730)

51.5.9 TFPGInterfacedObjectList.Insert

Synopsis: Insert a new object in the list

Declaration: `procedure Insert(Index: Integer; const Item: T)`

Visibility: public

Description: `Insert` inserts a new object (`Item`) in the list at position `Index`. The index is zero based and must be less than `Count` (766).

Errors: If an invalid index is specified, an `EListError` (729) exception is raised.

See also: `TFPGInterfacedObjectList.Items` (733), `TFPGInterfacedObjectList.Add` (730)

51.5.10 TFPGInterfacedObjectList.Assign

Synopsis: Copy objects from Source list

Declaration: `procedure Assign(Source: TFPGInterfacedObjectList)`

Visibility: public

Description: `Assign` clears the list and copies all items in `Source` to the list. The source list must be of the same type as the destination list.

See also: `TFPSList.Clear` (761), `TFPGObjectList.Add` (755)

51.5.11 TFPGInterfacedObjectList.AddList

Synopsis: Adds the elements from another list

Declaration: `procedure AddList(Source: TFPGInterfacedObjectList)`

Visibility: public

Description: `AddList` adds all the elements from list `Source` to the current list.

See also: `TFPGList.AddList` (736), `TFPSList.AddList` (764), `TFPGObjectList.AddList` (757), `TFPGInterfacedObjectList.Add` (730)

51.5.12 TFPGInterfacedObjectList.Remove

Synopsis: Remove an object from the list.

Declaration: `function Remove(const Item: T) : Integer`

Visibility: public

Description: `Remove` removes the object `Item` from the list, and returns the index of the removed item. If no item was removed, `-1` is returned. Only the first object is removed.

Removing an object from the list may cause the object to be freed.

Errors: None.

See also: `TFPGInterfacedObjectList.IndexOf` ([731](#)), `TFPSList.Delete` ([761](#)), `TFPGInterfacedObjectList.FreeObjects` ([729](#))

51.5.13 TFPGInterfacedObjectList.Sort

Synopsis: Sort the objects in the list

Declaration: `procedure Sort(Compare: TCompareFunc)`

Visibility: public

Description: `Sort` sorts the elements in the list using the provided `Compare` function. The list passes 2 items to the compare function. The result of this function determines how the items will be sorted:

- If the result of this function is negative, the first object (`Item1`) is assumed to be 'less' than the second object (`Item2`) and will be moved before the second in the list.
- If the function result is positive, the first object (`Item1`) is assumed to be 'greater than' the second object (`Item2`) and will be moved after the second in the list.
- If the function result is zero, the objects are assumed to be 'equal' and no moving will take place.

Errors: None.

See also: `TFPSList.Sorted` ([759](#))

51.5.14 TFPGInterfacedObjectList.First

Synopsis: First non-nil object

Declaration: `Property First : T`

Visibility: public

Access: Read, Write

Description: `First` returns the first non-nil object. If no such element is present, `Nil` is returned.

See also: `TFPSList.First` ([767](#)), `TFPGInterfacedObjectList.Last` ([733](#)), `TFPSList.Pack` ([765](#))

51.5.15 TFPGInterfacedObjectList.Last

Synopsis: Last non-`Nil` object

Declaration: `Property Last : T`

Visibility: `public`

Access: `Read, Write`

Description: `Last` returns the last non-`Nil` object. If no such element is present, `Nil` is returned.

See also: `TFPGInterfacedObjectList.First` ([732](#)), `TFPSList.Last` ([767](#))

51.5.16 TFPGInterfacedObjectList.Items

Synopsis: Indexed access to objects in the list.

Declaration: `Property Items[Index: Integer]: T; default`

Visibility: `public`

Access: `Read, Write`

Description: `Items` provides indexed access to the objects in the list. The objects can be get or set.

The index `Index` is zero based, and has a maximum value of `Count-1` ([766](#)).

The previous object at position `Index` may be freed when setting the property, depending on its reference count.

Errors: If an invalid index is used, an `EListError` ([729](#)) exception is raised.

See also: `TFPSList.Count` ([766](#))

51.5.17 TFPGInterfacedObjectList.List

Synopsis: Internal list pointer

Declaration: `Property List : PTypeList`

Visibility: `public`

Access: `Read`

Description: `List` is the internal list of objects. It should not be used directly.

See also: `TFPGInterfacedObjectList.Items` ([733](#))

51.6 TFPGList

51.6.1 Description

`TFPGList` can be used to specialize a list for any type `T` that does not require reference counting (such as interfaced objects). It will specialize to a list with the same methods as `TFPSList` ([759](#)) or `classes.TFPList` ([728](#))

See also: `TFPSList` ([759](#)), `classes.TFPList` ([728](#))

51.6.2 Method overview

Page	Method	Description
734	Add	Add new item of type T to the list.
736	AddList	Adds the elements from another list
736	Assign	Copy elements from Source list
734	Create	Instantiate a new list
735	Extract	Extract an item from the list
735	GetEnumerator	Return a list enumerator for T.
735	IndexOf	Index of item
735	Insert	Insert a new item in the list
734	ItemsManaged	Indicates whether the list item is a managed type or not
736	Remove	Remove an item from the list.
736	Sort	Sort the list

51.6.3 Property overview

Page	Properties	Access	Description
737	First	rw	First non-empty item
737	Items	rw	Indexed access to items in the list
737	Last	rw	Last non-empty item
737	List	r	Internal list object

51.6.4 TFPGList.Create

Synopsis: Instantiate a new list

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new list. It will simply call the inherited constructor with the correct item size: `sizeof(T)`.

51.6.5 TFPGList.ItemsManaged

Synopsis: Indicates whether the list item is a managed type or not

Declaration: `class function ItemIsManaged : Boolean; Override`

Visibility: `public`

Description: `ItemIsManaged` indicates whether the list item type is a managed type or not. If not, faster codepaths are sometimes taken in the code.

51.6.6 TFPGList.Add

Synopsis: Add new item of type T to the list.

Declaration: `function Add(const Item: T) : Integer`

Visibility: `public`

Description: `Add` adds a new item `Item` of generic type T to the list and returns the position at which the item was added.

Errors: If the item could not be added, an `EListError` (729) exception is raised.

See also: `TFPGList.Extract` (735), `TFPGList.Items` (737), `TFPGList.IndexOf` (735)

51.6.7 TFPGList.Extract

Synopsis: Extract an item from the list

Declaration: `function Extract(const Item: T) : T`

Visibility: public

Description: `Extract` removes `Item` from the list and returns the removed item, or an expression equivalent to `T(0)` if it was not found.

Errors: None.

See also: `TFPSList.Delete` (761)

51.6.8 TFPGList.GetEnumerator

Synopsis: Return a list enumerator for T.

Declaration: `function GetEnumerator : TFPGListEnumeratorSpec`

Visibility: public

Description: `GetEnumerator` returns an enumerator for the elements in the list. It is a specialized version of `TFPGListEnumerator` (738).

See also: `TFPGListEnumerator` (738)

51.6.9 TFPGList.IndexOf

Synopsis: Index of item

Declaration: `function IndexOf(const Item: T) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `Item` in the list, or -1 if the item does not appear in the list.

Errors: None.

See also: `TFPGList.Items` (737), `TFPGList.Insert` (735), `TFPSList.Add` (761)

51.6.10 TFPGList.Insert

Synopsis: Insert a new item in the list

Declaration: `procedure Insert(Index: Integer; const Item: T)`

Visibility: public

Description: `Insert` inserts a new item in the list at position `Index`. The index is zero based and must be less than `Count` (766).

Errors: If an invalid index is specified, an `EListError` (729) exception is raised.

See also: `TFPGList.Items` (737), `TFPGList.Insert` (735), `TFPSList.Add` (761)

51.6.11 TFPGList.Assign

Synopsis: Copy elements from Source list

Declaration: `procedure Assign(Source: TFPGList)`

Visibility: public

Description: `Assign` clears the list and copies all items in `Source` to the list. The source list must be of the same type as the destination list.

See also: `TFPSList.Clear` ([761](#)), `TFPGList.Add` ([734](#))

51.6.12 TFPGList.AddList

Synopsis: Adds the elements from another list

Declaration: `procedure AddList(Source: TFPGList)`

Visibility: public

Description: `AddList` adds all the elements from list `Source` to the current list.

See also: `TFPGList.Add` ([734](#)), `TFPSList.AddList` ([764](#)), `TFPGObjectList.AddList` ([757](#))

51.6.13 TFPGList.Remove

Synopsis: Remove an item from the list.

Declaration: `function Remove(const Item: T) : Integer`

Visibility: public

Description: `Remove` removes the item `Item` from the list, and returns the index of the removed item. If no item was removed, `-1` is returned. Only the first item is removed.

Errors: None.

See also: `TFPGList.IndexOf` ([735](#))

51.6.14 TFPGList.Sort

Synopsis: Sort the list

Declaration: `procedure Sort(Compare: TCompareFunc)`

Visibility: public

Description: `Sort` sorts the elements in the list using the provided `Compare` function. The list passes 2 items to the compare function. The result of this function determines how the items will be sorted:

- If the result of this function is negative, the first item (`Item1`) is assumed to be 'less' than the second item (`Item2`) and will be moved before the second in the list.
- If the function result is positive, the first item (`Item1`) is assumed to be 'greater than' the second item (`Item2`) and will be moved after the second in the list.
- if the function result is zero, the items are assumed to be 'equal' and no moving will take place.

51.6.15 TFPGList.First

Synopsis: First non-empty item

Declaration: `Property First : T`

Visibility: public

Access: Read,Write

Description: `First` returns the first non-empty item, which means the first item not equal to `T (0)`. If no such element is present, `T (0)` is returned.

See also: `TFPSList.First` (767), `TFPGList.Last` (737)

51.6.16 TFPGList.Last

Synopsis: Last non-empty item

Declaration: `Property Last : T`

Visibility: public

Access: Read,Write

Description: `Last` returns the last non-empty item, which means the last item not equal to `T (0)`. If no such element is present, `T (0)` is returned.

See also: `TFPGList.First` (737), `TFPSList.Last` (767)

51.6.17 TFPGList.Items

Synopsis: Indexed access to items in the list

Declaration: `Property Items[Index: Integer]: T; default`

Visibility: public

Access: Read,Write

Description: `Items` provides indexed access to the items in the list. The items can be get or set.

The index `Index` is zero based, and has a maximum value of `Count-1` (766).

Errors: If an invalid index is used, an `EListError` (729) exception is raised.

See also: `TFPSList.Count` (766)

51.6.18 TFPGList.List

Synopsis: Internal list object

Declaration: `Property List : PTypeList`

Visibility: public

Access: Read

Description: `List` is the internal list of items. It should not be used directly.

See also: `TFPGList.Items` (737)

51.7 TFPGListEnumerator

51.7.1 Description

`TFPGListEnumerator` is a generic list enumerator. It is used in the `TFPGList` (733) class to implement the enumerator for the list.

Normally there should be no need to instantiate or use this class directly.

See also: `TFPGList` (733)

51.7.2 Method overview

Page	Method	Description
738	<code>Create</code>	Create a new list enumerator
738	<code>MoveNext</code>	Move to next element in the list

51.7.3 Property overview

Page	Properties	Access	Description
738	<code>Current</code>	<code>r</code>	Current enumerated element

51.7.4 TFPGListEnumerator.Create

Synopsis: Create a new list enumerator

Declaration: `constructor Create (AList: TFPList)`

Visibility: `public`

Description: `Create` is called by the list `AList` to initialize a new enumerator. There should be no need to call this directly.

See also: `TFPGList` (733)

51.7.5 TFPGListEnumerator.MoveNext

Synopsis: Move to next element in the list

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` moves to the next element in the list.

See also: `TFPGListEnumerator.Current` (738)

51.7.6 TFPGListEnumerator.Current

Synopsis: Current enumerated element

Declaration: `Property Current : T`

Visibility: `public`

Access: `Read`

Description: `Current` returns the currently enumerated element. It is only valid after `TFPGLListEnumerator.MoveNext` (738) was called and returned `True`.

See also: `TFPGLListEnumerator.MoveNext` (738)

51.8 TFPGMap

51.8.1 Description

`TFPGMap` is a generic map class. It can be used to specialize a map for any key type and data type that do not require manual reference counting: For reference counted interface objects, `TFPGMapInterfacedObjectData` (744) must be used.

See also: `TFPGMapInterfacedObjectData` (744)

51.8.2 Method overview

Page	Method	Description
740	<code>Add</code>	Add a key and value to the map
740	<code>AddOrSetData</code>	Add data with given or set value if the key already exists.
739	<code>Create</code>	Create a new instance of the map
740	<code>Find</code>	Find item based on key
741	<code>IndexOf</code>	Find index of a key in the list.
741	<code>IndexOfData</code>	Find index of data value in the list.
741	<code>InsertKey</code>	Insert a new key in the list
741	<code>InsertKeyData</code>	Insert a new key with associated data in the list
742	<code>Remove</code>	Remove a key from the list
740	<code>TryGetData</code>	Find data or return default

51.8.3 Property overview

Page	Properties	Access	Description
742	<code>Data</code>	rw	Indexed access to the data in the list
743	<code>KeyData</code>	rw	Access to data based on key
742	<code>Keys</code>	rw	Indexed access to the keys in the list.
743	<code>OnCompare</code>	rw	Alias for <code>OnKeyCompare</code>
744	<code>OnDataCompare</code>	rw	Compare function for data values.
743	<code>OnKeyCompare</code>	rw	Compare function for key values.

51.8.4 TFPGMap.Create

Synopsis: Create a new instance of the map

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new map. It mainly initializes the `TFPSMap` (767) parent with the sized of the key and data.

See also: `TFPSMap.Create` (768)

51.8.5 TFPGMap.Add

Synopsis: Add a key and value to the map

Declaration: `function Add(const AKey: TKey; const AData: TData) : Integer`
`function Add(const AKey: TKey) : Integer`

Visibility: public

Description: Add adds a new key AKey of generic type TKey with data value AData to the list and returns the position at which the key was added.

Errors: If the item could not be added, an EListError (729) exception is raised. If Duplicates (771) is set to dupError and a duplicate key is added, an EListError (729) exception is raised.

See also: TFPGMap.Keys (742), TFPGMap.IndexOf (741), TFPGMap.KeyData (743), TFPGMap.Data (742), TFPSMap.Duplicates (771)

51.8.6 TFPGMap.Find

Synopsis: Find item based on key

Declaration: `function Find(const AKey: TKey; out Index: Integer) : Boolean`

Visibility: public

Description: Find will search the key equal to AKey and return its index in AIndex. The return value of the function is True if an exact match for AKey is found, False otherwise.

The behaviour of Find is undefined if the map is not sorted. For unsorted maps, use IndexOf (741) instead.

See also: TFPGMap.IndexOf (741), TFPGMap.IndexOfData (741)

51.8.7 TFPGMap.TryGetData

Synopsis: Find data or return default

Declaration: `function TryGetData(const AKey: TKey; out AData: TData) : Boolean`

Visibility: public

Description: TryGetData will search the map for AKey and return True or False depending on whether the value with the given key was found. If the key was found, the associated value is returned in AData, if it is not found a default value (using Default) is returned.

Errors: None.

See also: TFPGMap.Find (740)

51.8.8 TFPGMap.AddOrSetData

Synopsis: Add data with given or set value if the key already exists.

Declaration: `procedure AddOrSetData(const AKey: TKey; const AData: TData)`

Visibility: public

Description: AddOrSetData will check if key AKey already exists. if yes, the value associated with it will be replaced with AData. If the key does not yet exist, it will be added with value AData.

Errors: None.

See also: `TFPGMap.TryGetData` (740), `TFPGMap.Add` (740), `TFPGMap.Find` (740)

51.8.9 `TFPGMap.IndexOf`

Synopsis: Find index of a key in the list.

Declaration: `function IndexOf(const AKey: TKey) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `AKey` in the list, or -1 if the key was not found in the list.

Errors: None.

See also: `TFPGMap.Find` (740), `TFPGMap.IndexOfData` (741)

51.8.10 `TFPGMap.IndexOfData`

Synopsis: Find index of data value in the list.

Declaration: `function IndexOfData(const AData: TData) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of `AData` in the list, or -1 if the data was not found in the list.

Errors: None.

See also: `TFPGMap.Find` (740), `TFPGMap.IndexOf` (741)

51.8.11 `TFPGMap.InsertKey`

Synopsis: Insert a new key in the list

Declaration: `procedure InsertKey(Index: Integer; const AKey: TKey)`

Visibility: public

Description: `InsertKey` inserts key `AKey` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (729) exception will be raised.

See also: `TFPGMap.InsertKeyData` (741), `TFPGMap.Add` (740), `TFPSMap.Delete` (767), `TFPSMap.Remove` (770)

51.8.12 `TFPGMap.InsertKeyData`

Synopsis: Insert a new key with associated data in the list

Declaration: `procedure InsertKeyData(Index: Integer; const AKey: TKey;
const AData: TData)`

Visibility: public

Description: `InsertKey` inserts key `AKey` with associated data `AData` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (729) exception will be raised.

See also: `TFPGMap.InsertKey` (741), `TFPGMap.Add` (740), `TFPSMap.Delete` (767), `TFPGMap.Remove` (742)

51.8.13 TFPGMap.Remove

Synopsis: Remove a key from the list

Declaration: `function Remove(const AKey: TKey) : Integer`

Visibility: public

Description: `Remove` removes the key `AKey` from the list, together with its associated data. The function returns the index of `AKey` prior to removal from the list, or -1 if `AKey` was not present in the list.

Errors: None.

See also: `TFPGMap.InsertKey` (741), `TFPGMap.InsertKeyData` (741), `TFPGMap.Add` (740), `TFPSMap.Delete` (767)

51.8.14 TFPGMap.Keys

Synopsis: Indexed access to the keys in the list.

Declaration: `Property Keys[Index: Integer]: TKey`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to the key values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Key values can always be read, but can only be written if the list is unsorted.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (729) exception will be raised. The same exception is raised if a key is written and the list is sorted.

See also: `TFPSList.Count` (766), `TFPGMap.Data` (742), `TFPGMap.KeyData` (743)

51.8.15 TFPGMap.Data

Synopsis: Indexed access to the data in the list

Declaration: `Property Data[Index: Integer]: TData`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to the data values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Data can always be read or written.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (729) exception will be raised.

See also: `TFPSList.Count` (766), `TFPGMap.Keys` (742), `TFPGMap.KeyData` (743)

51.8.16 TFPGMap.KeyData

Synopsis: Access to data based on key

Declaration: `Property KeyData[AKey: TKey]: TData; default`

Visibility: public

Access: Read,Write

Description: `KeyData` allows access to the data based on the key value `AKey`. The data can be read and written. When writing, writing using an existing key will overwrite the current data. If it does not exist yet, it will be created. When reading, if the key is not present, an `EListError` (729) will be raised.

Errors: If the key does not exist, an `EListError` (729) exception will be raised.

See also: `TFPSList.Count` (766), `TFPGMap.Keys` (742), `TFPGMap.Data` (742)

51.8.17 TFPGMap.OnCompare

Synopsis: Alias for `OnKeyCompare`

Declaration: `Property OnCompare : TKeyCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnCompare` is a deprecated property, use `TFPGMap.OnKeyCompare` (743) instead.

See also: `TFPGMap.OnKeyCompare` (743)

51.8.18 TFPGMap.OnKeyCompare

Synopsis: Compare function for key values.

Declaration: `Property OnKeyCompare : TKeyCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnKeyCompare` can be set to a function that compares key values. The default value for this event is a function that compares keys based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

See also: `TFPGMap.OnDataCompare` (744)

51.8.19 TFPGMap.OnDataCompare

Synopsis: Compare function for data values.

Declaration: `Property OnDataCompare : TDataCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnDataCompare` can be set to a function that compares data values. The default value for this event is a function that compares data based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first data item (`Data1`) is assumed to be 'less' than the second data item (`Data2`) and will be moved before the second in the list.
- If the function result is positive, the first data item (`Data1`) pointer is assumed to be 'greater than' the second data item (`Data2`) and will be moved after the second in the list.
- if the function result is zero, the data items are assumed to be 'equal' and no moving will take place.

See also: `TFPGMap.OnKeyCompare` ([743](#))

51.9 TFPGMapInterfacedObjectData

51.9.1 Description

`TFPGInterfacedObjectMap` is a generic map class. It can be used to specialize a map for any key type, with associated data type that requires manual reference counting: any type which implements `IInterface`. For non-reference counted objects, `TFPGMap` ([739](#)) should be used.

This map class is entirely equivalent to `TFPGMap` ([739](#)), but operates on data items that require additional reference counting code on the data.

See also: `TFPGMap` ([739](#))

51.9.2 Method overview

Page	Method	Description
745	<code>Add</code>	Add a key and value to the map
746	<code>AddOrSetData</code>	Add data with given or set value if the key already exists.
745	<code>Create</code>	Create a new instance of the map
745	<code>Find</code>	Find item based on key
746	<code>IndexOf</code>	Find index of a key in the list.
746	<code>IndexOfData</code>	Find index of data value in the list.
747	<code>InsertKey</code>	Insert a new key in the list
747	<code>InsertKeyData</code>	Insert a new key with associated data in the list
747	<code>Remove</code>	Remove a key from the list
746	<code>TryGetData</code>	Find data or return default

51.9.3 Property overview

Page	Properties	Access	Description
748	Data	rw	Indexed access to the data in the list
748	KeyData	rw	Access to data based on key
747	Keys	rw	Indexed access to the keys in the list.
748	OnCompare	rw	Alias for <code>OnKeyCompare</code>
749	OnDataCompare	rw	Compare function for data values.
749	OnKeyCompare	rw	Compare function for key values.

51.9.4 TFPGMapInterfacedObjectData.Create

Synopsis: Create a new instance of the map

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new map. It mainly initializes the `TFPSMap` ([767](#)) parent with the sized of the key and data.

See also: `TFPSMap.Create` ([768](#))

51.9.5 TFPGMapInterfacedObjectData.Add

Synopsis: Add a key and value to the map

Declaration: `function Add(const AKey: TKey; const AData: TData) : Integer`
`function Add(const AKey: TKey) : Integer`

Visibility: `public`

Description: `Add` adds a new key `AKey` of generic type `TKey` with data value `AData` to the list and returns the position at which the key was added.

Errors: If the item could not be added, an `EListError` ([729](#)) exception is raised. If `Duplicates` ([771](#)) is set to `dupError` and a duplicate key is added, an `EListError` ([729](#)) exception is raised.

See also: `TFPGMapInterfacedObjectData.Keys` ([747](#)), `TFPGMapInterfacedObjectData.IndexOf` ([746](#)), `TFPGMapInterfacedObjectData.KeyData` ([748](#)), `TFPGMapInterfacedObjectData.Data` ([748](#)), `TFPS.Duplicates` ([728](#))

51.9.6 TFPGMapInterfacedObjectData.Find

Synopsis: Find item based on key

Declaration: `function Find(const AKey: TKey; out Index: Integer) : Boolean`

Visibility: `public`

Description: `Find` will search the first key smaller than or equal to `AKey` and return its index in `AIndex`. If the key was not found then -1 is returned. The return value of the function is `True` if an exact match for `AKey` is found, `False` otherwise.

See also: `TFPGMapInterfacedObjectData.IndexOf` ([746](#)), `TFPGMapInterfacedObjectData.IndexOfData` ([746](#))

51.9.7 TFPGMapInterfacedObjectData.TryGetData

Synopsis: Find data or return default

Declaration: `function TryGetData(const AKey: TKey; out AData: TData) : Boolean`

Visibility: public

Description: `TryGetData` will search the map for `AKey` and return `True` or `False` depending on whether the value with the given key was found. If the key was found, the associated value is returned in `AData`, if it is not found a default value (using `Default`) is returned.

Errors: None.

See also: `TFPGMapInterfacedObjectData.Find` (745)

51.9.8 TFPGMapInterfacedObjectData.AddOrSetData

Synopsis: Add data with given or set value if the key already exists.

Declaration: `procedure AddOrSetData(const AKey: TKey; const AData: TData)`

Visibility: public

Description: `AddOrSetData` will check if key `AKey` already exists. if yes, the value associated with it will be replaced with `AData`. If the key does not yet exist, it will be added with value `AData`.

Errors: None.

See also: `TFPGMapInterfacedObjectData.TryGetData` (746), `TFPGMapInterfacedObjectData.Add` (745), `TFPGMapInterfacedObjectData.Find` (745)

51.9.9 TFPGMapInterfacedObjectData.IndexOf

Synopsis: Find index of a key in the list.

Declaration: `function IndexOf(const AKey: TKey) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `AKey` in the list, or -1 if the key was not found in the list.

Errors: None.

See also: `TFPGMapInterfacedObjectData.Find` (745), `TFPGMapInterfacedObjectData.IndexOfData` (746)

51.9.10 TFPGMapInterfacedObjectData.IndexOfData

Synopsis: Find index of data value in the list.

Declaration: `function IndexOfData(const AData: TData) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of `AData` in the list, or -1 if the data was not found in the list.

Errors: None.

See also: `TFPGMapInterfacedObjectData.Find` (745), `TFPGMapInterfacedObjectData.IndexOf` (746)

51.9.11 TFPGMapInterfacedObjectData.InsertKey

Synopsis: Insert a new key in the list

Declaration: `procedure InsertKey(Index: Integer; const AKey: TKey)`

Visibility: public

Description: `InsertKey` inserts key `AKey` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (729) exception will be raised.

See also: `TFPGMapInterfacedObjectData.InsertKeyData` (747), `TFPGMapInterfacedObjectData.Add` (745), `TFPSMapInterfacedObjectData.Delete` (728), `TFPSMapInterfacedObjectData.Remove` (728)

51.9.12 TFPGMapInterfacedObjectData.InsertKeyData

Synopsis: Insert a new key with associated data in the list

Declaration: `procedure InsertKeyData(Index: Integer; const AKey: TKey;
const AData: TData)`

Visibility: public

Description: `InsertKey` inserts key `AKey` with associated data `AData` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (729) exception will be raised.

See also: `TFPGMapInterfacedObjectData.InsertKey` (747), `TFPGMapInterfacedObjectData.Add` (745), `TFPSMapInterfacedObjectData.Delete` (728), `TFPGMapInterfacedObjectData.Remove` (747)

51.9.13 TFPGMapInterfacedObjectData.Remove

Synopsis: Remove a key from the list

Declaration: `function Remove(const AKey: TKey) : Integer`

Visibility: public

Description: `Remove` removes the key `AKey` from the list, together with its associated data. The function returns the index of `AKey` prior to removal from the list, or -1 if `AKey` was not present in the list.

Errors: None.

See also: `TFPGMap.InsertKey` (741), `TFPGMap.InsertKeyData` (741), `TFPGMap.Add` (740), `TFPGMapInterfacedObjectData.Delete` (744)

51.9.14 TFPGMapInterfacedObjectData.Keys

Synopsis: Indexed access to the keys in the list.

Declaration: `Property Keys[Index: Integer]: TKey`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to the key values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Key values can always be read, but can only be written if the list is unsorted.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (729) exception will be raised. The same exception is raised if a key is written and the list is sorted.

See also: `TFPSList.Count` (766), `TFPGMapInterfacedObjectData.Data` (748), `TFPGMapInterfacedObjectData.KeyData` (748)

51.9.15 TFPGMapInterfacedObjectData.Data

Synopsis: Indexed access to the data in the list

Declaration: `Property Data[Index: Integer]: TData`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to the data values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Data can always be read or written.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (729) exception will be raised.

See also: `TFPSList.Count` (766), `TFPGMapInterfacedObjectData.Keys` (747), `TFPGMapInterfacedObjectData.KeyData` (748)

51.9.16 TFPGMapInterfacedObjectData.KeyData

Synopsis: Access to data based on key

Declaration: `Property KeyData[AKey: TKey]: TData; default`

Visibility: public

Access: Read,Write

Description: `KeyData` allows access to the data based on the key value `AKey`. The data can be read and written. When writing, writing using an existing key will overwrite the current data. If it does not exist yet, it will be created. When reading, if the key is not present, an `EListError` (729) will be raised.

Errors: If the key does not exist, an `EListError` (729) exception will be raised.

See also: `TFPSList.Count` (766), `TFPGMapInterfacedObjectData.Keys` (747), `TFPGMapInterfacedObjectData.Data` (748)

51.9.17 TFPGMapInterfacedObjectData.OnCompare

Synopsis: Alias for `OnKeyCompare`

Declaration: `Property OnCompare : TKeyCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnCompare` is a deprecated property, use `TFPGMapInterfacedObjectData.OnKeyCompare` (749) instead.

See also: `TFPGMapInterfacedObjectData.OnKeyCompare` (749)

51.9.18 TFPGMapInterfacedObjectData.OnKeyCompare

Synopsis: Compare function for key values.

Declaration: `Property OnKeyCompare : TKeyCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnKeyCompare` can be set to a function that compares key values. The default value for this event is a function that compares keys based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapInterfacedObjectData.OnDataCompare` ([749](#))

51.9.19 TFPGMapInterfacedObjectData.OnDataCompare

Synopsis: Compare function for data values.

Declaration: `Property OnDataCompare : TDataCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnDataCompare` can be set to a function that compares data values. The default value for this event is a function that compares data based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first data item (`Data1`) is assumed to be 'less' than the second data item (`Data2`) and will be moved before the second in the list.
- If the function result is positive, the first data item (`Data1`) pointer is assumed to be 'greater than' the second data item (`Data2`) and will be moved after the second in the list.
- if the function result is zero, the data items are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapInterfacedObjectData.OnKeyCompare` ([749](#))

51.10 TFPGMapObject

51.10.1 Description

`TFPGMapObject` is a generic map class. It can be used to specialize a map for object types, but not objects with automated reference counting: For reference counted interface objects, `TFPGMapInterfacedObjectData` ([744](#)) must be used.

See also: `TFPGMapInterfacedObjectData` ([744](#))

51.10.2 Method overview

Page	Method	Description
750	Add	Add a key and value to the map
751	AddOrSetData	Add data with given or set value if the key already exists.
750	Create	Create a new instance of the map
751	Find	Find item based on key
751	IndexOf	Find index of a key in the list.
752	IndexOfData	Find index of data value in the list.
752	InsertKey	Insert a new key in the list
752	InsertKeyData	Insert a new key with associated data in the list
752	Remove	Remove a key from the list
751	TryGetData	Find data or return default

51.10.3 Property overview

Page	Properties	Access	Description
753	Data	rw	Indexed access to the data in the list
753	KeyData	rw	Access to data based on key
753	Keys	rw	Indexed access to the keys in the list.
754	OnCompare	rw	Alias for OnKeyCompare
754	OnDataCompare	rw	Compare function for data values.
754	OnKeyCompare	rw	Compare function for key values.

51.10.4 TFPGMapObject.Create

Synopsis: Create a new instance of the map

Declaration: `constructor Create(AFreeObjects: Boolean)`
`constructor Create`

Visibility: public

Description: `Create` instantiates a new map. It mainly initializes the `TFPSMap` ([767](#)) parent with the sized of the key and data.

See also: `TFPSMap.Create` ([768](#))

51.10.5 TFPGMapObject.Add

Synopsis: Add a key and value to the map

Declaration: `function Add(const AKey: TKey; const AData: TData) : Integer`
`function Add(const AKey: TKey) : Integer`

Visibility: public

Description: `Add` adds a new key `AKey` of generic type `TKey` with data object `AData` to the list and returns the position at which the key was added.

Errors: If the item could not be added, an `EListError` ([729](#)) exception is raised. If `Duplicates` ([771](#)) is set to `dupError` and a duplicate key is added, an `EListError` ([729](#)) exception is raised.

See also: `TFPGMapObject.Keys` ([753](#)), `TFPGMapObject.IndexOf` ([751](#)), `TFPGMapObject.KeyData` ([753](#)), `TFPGMapObject.Data` ([753](#)), `TFPSMap.Duplicates` ([771](#))

51.10.6 TFPGMapObject.Find

Synopsis: Find item based on key

Declaration: `function Find(const AKey: TKey; out Index: Integer) : Boolean`

Visibility: public

Description: `Find` will search the first key smaller than or equal to `AKey` and return its index in `AIndex`. If the key was not found then -1 is returned. The return value of the function is `True` if an exact match for `AKey` is found, `False` otherwise.

See also: `TFPGMapObject.IndexOf` ([751](#)), `TFPGMapObject.IndexOfData` ([752](#))

51.10.7 TFPGMapObject.TryGetData

Synopsis: Find data or return default

Declaration: `function TryGetData(const AKey: TKey; out AData: TData) : Boolean`

Visibility: public

Description: `TryGetData` will search the map for `AKey` and return `True` or `False` depending on whether the value with the given key was found. If the key was found, the associated value is returned in `AData`, if it is not found a default value (using `Default`) is returned.

Errors: None.

See also: `TFPGMapObject.Find` ([751](#))

51.10.8 TFPGMapObject.AddOrSetData

Synopsis: Add data with given or set value if the key already exists.

Declaration: `procedure AddOrSetData(const AKey: TKey; const AData: TData)`

Visibility: public

Description: `AddOrSetData` will check if key `AKey` already exists. if yes, the value associated with it will be replaced with `AData`. If the key does not yet exist, it will be added with value `AData`.

Errors: None.

See also: `TFPGMapObject.TryGetData` ([751](#)), `TFPGMapObject.Add` ([750](#)), `TFPGMapObject.Find` ([751](#))

51.10.9 TFPGMapObject.IndexOf

Synopsis: Find index of a key in the list.

Declaration: `function IndexOf(const AKey: TKey) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `AKey` in the list, or -1 if the key was not found in the list.

Errors: None.

See also: `TFPGMapObject.Find` ([751](#)), `TFPGMapObject.IndexOfData` ([752](#))

51.10.10 TFPGMapObject.IndexOfData

Synopsis: Find index of data value in the list.

Declaration: `function IndexOfData(const AData: TData) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of object `AData` in the list, or -1 if the data was not found in the list.

Errors: None.

See also: `TFPGMapObject.Find` (751), `TFPGMapObject.IndexOf` (751)

51.10.11 TFPGMapObject.InsertKey

Synopsis: Insert a new key in the list

Declaration: `procedure InsertKey(Index: Integer; const AKey: TKey)`

Visibility: public

Description: `InsertKey` inserts key `AKey` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (729) exception will be raised.

See also: `TFPGMapObject.InsertKeyData` (752), `TFPGMapObject.Add` (750), `TFPSMap.Delete` (767), `TFPSMap.Remove` (770)

51.10.12 TFPGMapObject.InsertKeyData

Synopsis: Insert a new key with associated data in the list

Declaration: `procedure InsertKeyData(Index: Integer; const AKey: TKey;
const AData: TData)`

Visibility: public

Description: `InsertKey` inserts key `AKey` with associated data `AData` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (729) exception will be raised.

See also: `TFPGMapObject.InsertKey` (752), `TFPGMapObject.Add` (750), `TFPSMap.Delete` (767), `TFPGMapObject.Remove` (752)

51.10.13 TFPGMapObject.Remove

Synopsis: Remove a key from the list

Declaration: `function Remove(const AKey: TKey) : Integer`

Visibility: public

Description: `Remove` removes the key `AKey` from the list, together with its associated data. The function returns the index of `AKey` prior to removal from the list, or -1 if `AKey` was not present in the list.

Errors: None.

See also: `TFPGMapObject.InsertKey` (752), `TFPGMapObject.InsertKeyData` (752), `TFPGMapObject.Add` (750), `TFPSMap.Delete` (767)

51.10.14 `TFPGMapObject.Keys`

Synopsis: Indexed access to the keys in the list.

Declaration: `Property Keys[Index: Integer]: TKey`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to the key values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Key values can always be read, but can only be written if the list is unsorted.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (729) exception will be raised. The same exception is raised if a key is written and the list is sorted.

See also: `TFPSList.Count` (766), `TFPGMapObject.Data` (753), `TFPGMapObject.KeyData` (753)

51.10.15 `TFPGMapObject.Data`

Synopsis: Indexed access to the data in the list

Declaration: `Property Data[Index: Integer]: TData`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to the data values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Data can always be read or written.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (729) exception will be raised.

See also: `TFPSList.Count` (766), `TFPGMapObject.Keys` (753), `TFPGMapObject.KeyData` (753)

51.10.16 `TFPGMapObject.KeyData`

Synopsis: Access to data based on key

Declaration: `Property KeyData[AKey: TKey]: TData; default`

Visibility: public

Access: Read,Write

Description: `KeyData` allows access to the data based on the key value `AKey`. The data can be read and written. When writing, writing using an existing key will overwrite the current data. If it does not exist yet, it will be created. When reading, if the key is not present, an `EListError` (729) will be raised.

Errors: If the key does not exist, an `EListError` (729) exception will be raised.

See also: `TFPSList.Count` (766), `TFPGMapObject.Keys` (753), `TFPGMapObject.Data` (753)

51.10.17 TFPGMapObject.OnCompare

Synopsis: Alias for `OnKeyCompare`

Declaration: `Property OnCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnCompare` is a deprecated property, use `TFPGMapObject.OnKeyCompare` (754) instead.

See also: `TFPGMapObject.OnKeyCompare` (754)

51.10.18 TFPGMapObject.OnKeyCompare

Synopsis: Compare function for key values.

Declaration: `Property OnKeyCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnKeyCompare` can be set to a function that compares key values. The default value for this event is a function that compares keys based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapObject.OnDataCompare` (754)

51.10.19 TFPGMapObject.OnDataCompare

Synopsis: Compare function for data values.

Declaration: `Property OnDataCompare : TDataCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnDataCompare` can be set to a function that compares data values. The default value for this event is a function that compares data based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first data item (`Data1`) is assumed to be 'less' than the second data item (`Data2`) and will be moved before the second in the list.
- If the function result is positive, the first data item (`Data1`) pointer is assumed to be 'greater than' the second data item (`Data2`) and will be moved after the second in the list.
- if the function result is zero, the data items are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapObject.OnKeyCompare` (754)

51.11 TFPGObjectList

51.11.1 Description

`TFPGList` can be used to specialize a list for any class type `T` that does not require reference counting (such as interfaced objects). It will specialize to a list with the same methods as `TFPSList` (759) or `classes.TFPList` (728) or `TFPObjectList`

See also: `TFPSList` (759), `classes.TFPList` (728)

51.11.2 Method overview

Page	Method	Description
755	<code>Add</code>	Add new object of class <code>T</code> to the list.
757	<code>AddList</code>	Adds the elements from another list
757	<code>Assign</code>	Copy objects from Source list
755	<code>Create</code>	Instantiate a new object list.
756	<code>Extract</code>	Extract an item from the list
756	<code>GetEnumerator</code>	Return a list enumerator for <code>T</code> .
756	<code>IndexOf</code>	Index of item
757	<code>Insert</code>	Insert a new object in the list
757	<code>Remove</code>	Remove an object from the list.
758	<code>Sort</code>	Sort the objects in the list

51.11.3 Property overview

Page	Properties	Access	Description
758	<code>First</code>	<code>rw</code>	First non-nil item
759	<code>FreeObjects</code>	<code>rw</code>	Does the list own the objects or not?
758	<code>Items</code>	<code>rw</code>	Indexed access to objects in the list.
758	<code>Last</code>	<code>rw</code>	Last non- <code>Nil</code> object
759	<code>List</code>	<code>r</code>	Internal list pointer

51.11.4 TFPGObjectList.Create

Synopsis: Instantiate a new object list.

Declaration: `constructor Create(FreeObjects: Boolean)`

Visibility: `public`

Description: `Create` instantiates a new object list. It will simply call the inherited constructor with the correct item size and will initialize `TFPGObjectList.FreeObjects` (759) with `FreeObjects`.

If `FreeObjects` is true, then the list owns the objects. Freeing or clearing the list will remove all objects from memory by calling the destructor. Deleting or removing an item from the list will also dispose of the element.

See also: `TFPGObjectList.FreeObjects` (759)

51.11.5 TFPGObjectList.Add

Synopsis: Add new object of class `T` to the list.

Declaration: `function Add(const Item: T) : Integer`

Visibility: public

Description: `Add` adds a new item `Item` of class type `T` to the list and returns the position at which the item was added.

Errors: If the item could not be added, an `EListError` (729) exception is raised.

See also: `TFPGObjectList.Extract` (756), `TFPGObjectList.Items` (758), `TFPGObjectList.IndexOf` (756)

51.11.6 TFPGObjectList.Extract

Synopsis: Extract an item from the list

Declaration: `function Extract(const Item: T) : T`

Visibility: public

Description: `Extract` removes `Item` from the list and returns the removed item, or `Nil` if it was not found.

The extracted object will not be destroyed even if the list owns the objects.

Errors: None.

See also: `TFPSList.Delete` (761)

51.11.7 TFPGObjectList.GetEnumerator

Synopsis: Return a list enumerator for `T`.

Declaration: `function GetEnumerator : TFPGListEnumeratorSpec`

Visibility: public

Description: `GetEnumerator` returns an enumerator for the elements in the list. It is a specialized version of `TFPGListEnumerator` (738).

See also: `TFPGListEnumerator` (738)

51.11.8 TFPGObjectList.IndexOf

Synopsis: Index of item

Declaration: `function IndexOf(const Item: T) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `Item` in the list, or -1 if the item does not appear in the list.

Errors: None.

See also: `TFPGObjectList.Items` (758), `TFPGObjectList.Insert` (757), `TFPGObjectList.Add` (755)

51.11.9 TFPGObjectList.Insert

Synopsis: Insert a new object in the list

Declaration: `procedure Insert(Index: Integer; const Item: T)`

Visibility: public

Description: `Insert` inserts a new object (`Item`) in the list at position `Index`. The index is zero based and must be less than `Count` (766).

Errors: If an invalid index is specified, an `EListError` (729) exception is raised.

See also: `TFPGList.Items` (737), `TFPGList.Insert` (735), `TFPSList.Add` (761)

51.11.10 TFPGObjectList.AddList

Synopsis: Adds the elements from another list

Declaration: `procedure AddList(Source: TFPGObjectList)`

Visibility: public

Description: `AddList` adds all the elements from list `Source` to the current list.

See also: `TFPGList.AddList` (736), `TFPSList.AddList` (764), `TFPGObjectList.Add` (755)

51.11.11 TFPGObjectList.Assign

Synopsis: Copy objects from Source list

Declaration: `procedure Assign(Source: TFPGObjectList)`

Visibility: public

Description: `Assign` clears the list and copies all items in `Source` to the list. The source list must be of the same type as the destination list.

Take care if both the list owns the objects (i.e. have `TFPGObjectList.FreeObjects` (759) set to `True`), this may result to access violations.

See also: `TFPSList.Clear` (761), `TFPGObjectList.Add` (755)

51.11.12 TFPGObjectList.Remove

Synopsis: Remove an object from the list.

Declaration: `function Remove(const Item: T) : Integer`

Visibility: public

Description: `Remove` removes the object `Item` from the list, and returns the index of the removed item. If no item was removed, `-1` is returned. Only the first object is removed.

If the list owns the objects, (`TFPGObjectList.FreeObjects` (759) is set to `True`) then the object is freed.

Errors: None.

See also: `TFPGObjectList.IndexOf` (756), `TFPSList.Delete` (761), `TFPGObjectList.FreeObjects` (759)

51.11.13 TFPGObjectList.Sort

Synopsis: Sort the objects in the list

Declaration: `procedure Sort (Compare: TCompareFunc)`

Visibility: `public`

Description: `Sort` sorts the elements in the list using the provided `Compare` function. The list passes 2 items to the compare function. The result of this function determines how the items will be sorted:

- If the result of this function is negative, the first object (`Item1`) is assumed to be 'less' than the second object (`Item2`) and will be moved before the second in the list.
- If the function result is positive, the first object (`Item1`) is assumed to be 'greater than' the second object (`Item2`) and will be moved after the second in the list.
- if the function result is zero, the objects are assumed to be 'equal' and no moving will take place.

Errors: None.

51.11.14 TFPGObjectList.First

Synopsis: First non-nil item

Declaration: `Property First : T`

Visibility: `public`

Access: Read, Write

Description: `First` returns the first non-nil item. If no such element is present, `Nil` is returned.

See also: `TFPSList.First` ([767](#)), `TFPGList.Last` ([737](#)), `TFPSList.Pack` ([765](#))

51.11.15 TFPGObjectList.Last

Synopsis: Last non-`Nil` object

Declaration: `Property Last : T`

Visibility: `public`

Access: Read, Write

Description: `Last` returns the last non-`Nil` object. If no such element is present, `Nil`. is returned.

See also: `TFPGObjectList.First` ([758](#)), `TFPSList.Last` ([767](#))

51.11.16 TFPGObjectList.Items

Synopsis: Indexed access to objects in the list.

Declaration: `Property Items[Index: Integer]: T; default`

Visibility: `public`

Access: Read, Write

Description: `Items` provides indexed access to the objects in the list. The objects can be get or set.

The index `Index` is zero based, and has a maximum value of `Count-1` (766).

If the list owns the objects, (`TFPGObjectList.FreeObjects` (759) is set to `True`) then the previous object at position `Index` is freed when setting the property.

Errors: If an invalid index is used, an `EListError` (729) exception is raised.

See also: `TFPSList.Count` (766), `TFPGObjectList.FreeObjects` (759)

51.11.17 TFPGObjectList.List

Synopsis: Internal list pointer

Declaration: `Property List : PTypeList`

Visibility: public

Access: Read

Description: `List` is the internal list of objects. It should not be used directly.

See also: `TFPGObjectList.Items` (758)

51.11.18 TFPGObjectList.FreeObjects

Synopsis: Does the list own the objects or not?

Declaration: `Property FreeObjects : Boolean`

Visibility: public

Access: Read,Write

Description: `FreeObjects` indicates whether the list owns the objects or not. If set to `True`, freeing or clearing the list will remove all objects from memory by calling the destructor. Deleting or removing an item from the list will also dispose of the element.

The initial value for this property is set in the constructor and is `True` by default.

See also: `TFPGObjectList.FreeObjects` (759)

51.12 TFPSList

51.12.1 Description

`TFPSList` can be seen as the generalized equivalent of the classes unit `TFPList` (728) list. It is used as a base class for the `TFPGList` (733), `TFPGMap` (739), `TFPGObjectList` (755), `TFPGInterfaceObjectList` (729) and `TFPGMapInterfacedObjectData` (744) generic classes.

This list is not meant to be used directly, it is an auxiliary class for the actual generic list classes.

See also: `classes.TFPList` (728), `TFPGMap` (739), `TFPGObjectList` (755), `TFPGInterfacedObjectList` (729), `TFPGMapInterfacedObjectData` (744)

51.12.2 Method overview

Page	Method	Description
761	Add	Add a new item to the list
764	AddList	Adds the elements from another list
764	Assign	Copy one list to another
761	Clear	Clear the list
760	Create	Create a new instance of <code>TFPSList</code>
761	Delete	Delete an item from the list
762	DeleteRange	Delete a range of elements
760	Destroy	Destroy the list instance.
762	Error	Raise an <code>EListError</code> exception.
762	Exchange	Exchange two items in the list
762	Expand	Expand the capacity of the list
763	Extract	delete an element from the list
763	IndexOf	Search an item in the list
763	Insert	Insert a new item in the list.
761	ItemIsManaged	Indicates whether the list item is a managed type or not
764	Move	Moves an item from one position in the list to another.
765	Pack	Remove empty items from the list
764	Remove	Remove the item from the list
765	Sort	Sort the list

51.12.3 Property overview

Page	Properties	Access	Description
765	Capacity	rw	Current capacity of the list
766	Count	rw	Current element count
767	First	rw	Pointer to first non-empty item in the list
766	Items	rw	Items in the list
766	ItemSize	r	Size of the items in the list
767	Last	rw	Pointer to last non-empty item in the list
766	List	r	Internal list pointer

51.12.4 TFPSList.Create

Synopsis: Create a new instance of `TFPSList`

Declaration: `constructor Create(AItemSize: Integer)`

Visibility: `public`

Description: `Create` creates a new instance of `TFPSList`, and initializes the item size to `ItemSize`, which defaults to the size of a pointer.

See also: `TFPSList.ItemSize` ([766](#)), `TFPSList.Destroy` ([760](#))

51.12.5 TFPSList.Destroy

Synopsis: Destroy the list instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears and cleans up the list instance. Depending on the descendant, this may also remove the items in the list from memory.

See also: `TFPSList.Clear` (761)

51.12.6 TFPSList.ItemIsManaged

Synopsis: Indicates whether the list item is a managed type or not

Declaration: `class function ItemIsManaged : Boolean; Virtual`

Visibility: `public`

Description: `ItemIsManaged` indicates whether the list item type is a managed type or not. If not, faster codepaths are sometimes taken in the code.

51.12.7 TFPSList.Add

Synopsis: Add a new item to the list

Declaration: `function Add(Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds the item pointed to by `Item` to the list. It is not the pointer `Item` itself which is added to the list, but rather the `TFPSList.ItemSize` (766) bytes of memory to which `Item` is pointing.

The function returns the index of the newly added item.

Errors: If the maximum list size is reached, an `EListError` (729) is raised.

See also: `TFPSList.Delete` (761), `TFPSList.Items` (766), `TFPSList.Clear` (761)

51.12.8 TFPSList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all the items in the list. Depending on the descendent, the list items themselves may be cleared as well.

See also: `TFPSList.Delete` (761), `TFPSList.Items` (766), `TFPSList.Add` (761)

51.12.9 TFPSList.Delete

Synopsis: Delete an item from the list

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` deletes the item at position `Index` from the list. Depending on the descendent, the list items itself may be cleared as well.

Errors: If `Index` is out of bounds, an `EListError` (729) exception is raised.

See also: `TFPSList.Clear` (761), `TFPSList.Items` (766), `TFPSList.Add` (761)

51.12.10 TFPSList.DeleteRange

Synopsis: Delete a range of elements

Declaration: `procedure DeleteRange(IndexFrom: Integer; IndexTo: Integer)`

Visibility: public

Description: `DeleteRange` deletes elements from `IndexFrom` till `IndexTo`. Both indexes are zero based, and `IndexTo` must be bigger than `IndexFrom`. Using this method results in less moving of data in memory, and as such is more effective than deleting the elements one by one using `TFPSList.Delete` (761).

Errors: If invalid indexes are specified, an `EListError` (729) exception will be raised.

See also: `EListError` (729), `TFPSList.Delete` (761)

51.12.11 TFPSList.Error

Synopsis: Raise an `EListError` exception.

Declaration: `class procedure Error(const Msg: string; Data: PtrInt)`

Visibility: public

Description: `Error` is an auxiliary routine which raises an `EListError` (729) exception formatted from `Msg` and `Data`.

See also: `EListError` (729)

51.12.12 TFPSList.Exchange

Synopsis: Exchange two items in the list

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: public

Description: `Exchange` will exchange 2 items at positions `Index1` and `Index2` in the list.

Errors: If `Index1` or `Index2` are out of bounds, an `EListError` (729) exception is raised.

51.12.13 TFPSList.Expand

Synopsis: Expand the capacity of the list

Declaration: `function Expand : TFPSList`

Visibility: public

Description: `Expand` will expand the capacity of the list, and returns itself.

Errors: If the size will become larger than `MaxListSize` (728) an `EListError` (729) exception will be raised.

See also: `MaxListSize` (728), `TFPSList.Capacity` (765)

51.12.14 TFPSList.Extract

Synopsis: delete an element from the list

Declaration: `procedure Extract (Item: Pointer; ResultPtr: Pointer)`

Visibility: public

Description: `Extract` removes the item pointed to by `Item` from the list. It returns a pointer to the actually removed item from the list. The item is searched using `TFPSList.IndexOf` (763). If the item is not found, `nil` is returned.

Some descendants own the items in the list. `Extract` will not dispose of the item, as `TFPSList.Delete` (761) does.

Errors: None.

See also: `TFPSList.Delete` (761), `TFPSList.Add` (761), `TFPSList.IndexOf` (763)

51.12.15 TFPSList.IndexOf

Synopsis: Search an item in the list

Declaration: `function IndexOf (Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches in the list for the item pointed to by `Item`, and returns the position (0-based index) of the item in the list, or -1 if it was not found. The items are compared using `sysutils.CompareMem` (728), so an exact memory layout match.

See also: `TFPSList.Extract` (763)

51.12.16 TFPSList.Insert

Synopsis: Insert a new item in the list.

Declaration: `procedure Insert (Index: Integer; Item: Pointer)`
`function Insert (Index: Integer) : Pointer`

Visibility: public

Description: `Insert` comes in 2 overloaded version. The version without `Item` creates a slot for a new item at position `Index` in the list, and returns a pointer to the new slot. The slot will be of size `TFPSList.ItemSize` (766).

The version with `Item` argument will allocate a slot in the list at position `Index` and will copy the item pointed to by `Item` to the slot in the list.

In both cases, `Index` must be 0-based.

Errors: If `Index` is invalid, an `EListError` (729) exception will be raised.

See also: `TFPSList.Add` (761), `TFPSList.Delete` (761), `TFPSList.Extract` (763)

51.12.17 TFPSList.Move

Synopsis: Moves an item from one position in the list to another.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the item at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`

Errors: If `CurIndex` or `NewIndex` are not inside the valid range of indices, an `EListError` (729) exception is raised.

See also: `Exchange` (762)

51.12.18 TFPSList.Assign

Synopsis: Copy one list to another

Declaration: `procedure Assign (Obj: TFPSList)`

Visibility: public

Description: `Assign` clears the list and will add all items from `Obj` to the list. The items are copied one by one.

Errors: If the `TFPSList.ItemSize` (766) differs for the two lists, an `EListError` (729) exception is raised.

See also: `TFPSList.Add` (761)

51.12.19 TFPSList.AddList

Synopsis: Adds the elements from another list

Declaration: `procedure AddList (Obj: TFPSList)`

Visibility: public

Description: `AddList` adds all the elements from list `Obj` to the current list. A check is done that the 2 lists have the same element size.

Errors: If the lists have different element size, an `EListError` (729) exception will be raised.

See also: `TFPSList.Add` (761), `EListError` (729)

51.12.20 TFPSList.Remove

Synopsis: Remove the item from the list

Declaration: `function Remove (Item: Pointer) : Integer`

Visibility: public

Description: `Remove` searches `Item` in the list, and deletes it from the list. It returns the index of the item that was removed, or -1 if it was not found. Only the first match is removed.

If a descendent of `TFPSList` owns the object of the list, the item is removed from memory. If this is not desired, then `TFPSList.Extract` (763) must be used instead.

See also: `TFPSList.Extract` (763), `TFPSList.IndexOf` (763)

51.12.21 TFPSList.Pack

Synopsis: Remove empty items from the list

Declaration: `procedure Pack`

Visibility: `public`

Description: `Pack` will remove all empty items from the list. An item is considered to be empty if the memory location where the item is stored contains only zero bytes.

See also: `TFPSList.Clear` (761), `TFPSList.Sort` (765)

51.12.22 TFPSList.Sort

Synopsis: Sort the list

Declaration: `procedure Sort (Compare: TFPSListCompareFunc)`

Visibility: `public`

Description: `Sort` sorts the items in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first item is assumed to be 'less' than the second and will be moved before the second item in the list.
- If the function result is positive, the first item is assumed to be 'greater than' the second and will be moved after the second item in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

See also: `TFPSListCompareFunc` (728)

51.12.23 TFPSList.Capacity

Synopsis: Current capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: Read, Write

Description: `Capacity` is the current capacity (maximum amount of elements) of the list. The list capacity will expand automatically if an item is added and the capacity is reached (i.e. `TFPSList.Count` (766) equals `capacity`). Expanding the list is an expensive operation involving reallocation of memory and moving of list data in memory, so capacity can be set to a large amount to avoid frequent reallocations.

See also: `TFPSList.Count` (766), `TFPSList.Expand` (762), `TFPSList.Items` (766)

51.12.24 TFPSList.Count

Synopsis: Current element count

Declaration: `Property Count : Integer`

Visibility: public

Access: Read,Write

Description: `Count` is the current amount of elements in the list. It is initially zero. A valid item index is always a value between zero and `Count-1`.

See also: `TFPSList.Items` (766), `TFPSList.Capacity` (765)

51.12.25 TFPSList.Items

Synopsis: Items in the list

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: public

Access: Read,Write

Description: `Items` provides indexed access to the items in the list, the returned pointers are not the actual list items, but pointers to the elements in the list. The items can be get or set.

When assigning to the `Items` property, the memory area pointed to by the assigned pointer is copied to the list. Exactly `TFPSList.ItemSize` (766) bytes are copied.

The index `Index` is zero based, and has a maximum value of `Count-1` (766).

Errors: If an invalid index is used, an `EListError` (729) exception is raised.

See also: `TFPSList.ItemSize` (766), `TFPSList.Count` (766)

51.12.26 TFPSList.ItemSize

Synopsis: Size of the items in the list

Declaration: `Property ItemSize : Integer`

Visibility: public

Access: Read

Description: `ItemSize` is the memory size of the items in the list. It is specified in the constructor and cannot be changed during the lifetime of the list.

See also: `TFPSList.Create` (760)

51.12.27 TFPSList.List

Synopsis: Internal list pointer

Declaration: `Property List : PByte`

Visibility: public

Access: Read

Description: `List` is a pointer to the memory area used for the items in the list. It should not be manipulated.

51.12.28 TFPSList.First

Synopsis: Pointer to first non-empty item in the list

Declaration: `Property First : Pointer`

Visibility: public

Access: Read,Write

Description: `First` returns the value of the first non-empty item in the list. An item is considered empty if consists of `TFPSList.ItemSize` (766) zero bytes.

If there are no non-empty items in the list, then `Nil` is returned.

See also: `TFPSList.Last` (767), `TFPSList.Pack` (765)

51.12.29 TFPSList.Last

Synopsis: Pointer to last non-empty item in the list

Declaration: `Property Last : Pointer`

Visibility: public

Access: Read,Write

Description: `Last` returns the value of the last non-empty item in the list. An item is considered empty if consists of `TFPSList.ItemSize` (766) zero bytes.

If there are no non-empty items in the list, then `Nil` is returned.

See also: `TFPSList.Last` (767), `TFPSList.Pack` (765)

51.13 TFPSMap**51.13.1 Description**

`TFPSMap` can be used to create a map for any type `T` that does not require reference counting (such as interfaced objects). It will specialize to a map which is a generalized list with an arbitrary type as the list index (called the key).

This class should normally not be used directly, instead use one of the generic map objects such as `TFPGMap` (739).

See also: `TFPGMap` (739)

51.13.2 Method overview

Page	Method	Description
768	Add	Add a key, value pair to the map.
768	Create	Create a new map with given key and data size.
768	Find	Find data using the associated key
769	IndexOf	Index of key pointed to by <code>AKey</code>
769	IndexOfData	Index of data item <code>AData</code>
769	Insert	Insert a new slot for key and associated data item in the list
770	InsertKey	Insert a key in the list
770	InsertKeyData	Insert a key and associated in the list
770	Remove	Remove a key/value pair from the map.
770	Sort	Sort the list according to key

51.13.3 Property overview

Page	Properties	Access	Description
772	Data	rw	Indexed access to the locations of all data items
771	DataSize	r	Size (in bytes) for the data associated with keys
771	Duplicates	rw	What to do with duplicate key values
772	KeyData	rw	Access to data locations using key
772	Keys	rw	Indexed access to the locations of all keys
771	KeySize	r	Size (in bytes) for the key
773	OnDataPtrCompare	rw	Callback to compare 2 data items
773	OnKeyPtrCompare	rw	Callback to compare 2 keys
773	OnPtrCompare	rw	Alias for OnKeyPtrCompare
772	Sorted	rw	Is the map permanently sorted on key ?

51.13.4 TFPSMap.Create

Synopsis: Create a new map with given key and data size.

Declaration: `constructor Create(AKeySize: Integer; ADataSize: Integer)`

Visibility: `public`

Description: `Create` instantiates a new `TFPSMap` instance and initializes `TFPSMap.KeySize` ([771](#)) and `TFPSMap.DataSize` ([771](#)) with `AKeySize` and `ADataSize`, respectively. It also initializes the `TFPSMap.OnDataPtrCompare` ([773](#)) and `TFPSMap.OnKeyPtrCompare` ([773](#)) properties to functions that compare memory blocks.

Errors: None.

See also: `TFPSMap.Destroy` ([767](#)), `TFPSMap.KeySize` ([771](#)), `TFPSMap.DataSize` ([771](#)), `TFPSMap.OnDataPtrCompare` ([773](#)), `TFPSMap.OnKeyPtrCompare` ([773](#))

51.13.5 TFPSMap.Add

Synopsis: Add a key, value pair to the map.

Declaration: `function Add(AKey: Pointer; AData: Pointer) : Integer`
`function Add(AKey: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds the memory pointed to by `AData` to the map using the memory pointed to by `AKey` as the key. If no data is specified, it allocates a slot for `AKey` and returns a pointer to that slot.

Errors: If the maximum amount of values is reached, `Add` will raise an `EListError` ([729](#)) exception.

See also: `TFPSMap.Insert` ([769](#)), `TFPSMap.IndexOf` ([769](#))

51.13.6 TFPSMap.Find

Synopsis: Find data using the associated key

Declaration: `function Find(AKey: Pointer; out Index: Integer) : Boolean`

Visibility: `public`

Description: `Find` searches for the first key less than or equal to `AKey` and returns its index in the list in `Index`. It returns `True` if an exact match for the key was found. It returns `False` if the key was not found, and `Index` is then set to `-1`.

This function performs a binary search using the key comparing function specified in `OnKeyPtrCompare` (773).

Errors: if `OnKeyPtrCompare` is not set, an access violation will occur.

See also: `TFPSMap.OnKeyPtrCompare` (773)

51.13.7 TFPSMap.IndexOf

Synopsis: Index of key pointed to by `AKey`

Declaration: `function IndexOf(AKey: Pointer) : Integer`

Visibility: `public`

Description: `IndexOf` returns the index of the element with a key pointed to by `AKey`. It returns `-1` if the key was not found.

If the list is sorted, then a binary search is performed, otherwise a linear search is used to find the key.

Errors: None.

See also: `TFPSMap.Find` (768), `TFPSMap.IndexOfData` (769), `TFPSMap.Keys` (772), `TFPSMap.Data` (772)

51.13.8 TFPSMap.IndexOfData

Synopsis: Index of data item `AData`

Declaration: `function IndexOfData(AData: Pointer) : Integer`

Visibility: `public`

Description: `IndexOfData` returns the index of the element with data pointed to by `AData`. It returns `-1` if the data item was not found. The search is always performed using a linear search.

See also: `TFPSMap.Find` (768), `TFPSMap.IndexOf` (769), `TFPSMap.Keys` (772), `TFPSMap.Data` (772)

51.13.9 TFPSMap.Insert

Synopsis: Insert a new slot for key and associated data item in the list

Declaration: `function Insert(Index: Integer) : Pointer`
`procedure Insert(Index: Integer; out AKey: Pointer; out AData: Pointer)`

Visibility: `public`

Description: `Insert` will allocate a new slot in the list. It returns a pointer to the new slot. If `Akey` and `AData` are given, then they will point to the positions in the slot for the key and data items.

Errors: If the maximum amount of values is reached or an invalid index is specified, `Insert` will raise an `EListError` (729) exception.

See also: `TFPSMap.Add` (768), `TFPSMap.InsertKey` (770), `TFPSMap.InsertKeyData` (770)

51.13.10 TFPSMap.InsertKey

Synopsis: Insert a key in the list

Declaration: `procedure InsertKey(Index: Integer; AKey: Pointer)`

Visibility: public

Description: `InsertKey` will allocate a new slot in the list for a key value as pointed to by `AKey`, and copy the key pointed to by `AKey` to the slot.

Errors: If the maximum amount of values is reached or an invalid index is specified, `InsertKey` will raise an `EListError` (729) exception.

See also: `TFPSMap.Add` (768), `TFPSMap.Insert` (769), `TFPSMap.InsertKeyData` (770)

51.13.11 TFPSMap.InsertKeyData

Synopsis: Insert a key and associated in the list

Declaration: `procedure InsertKeyData(Index: Integer; AKey: Pointer; AData: Pointer)`

Visibility: public

Description: `InsertKeyData` will allocate a new slot in the list for a key value as pointed to by `AKey`, and copy the key pointed to by `AKey` as well as the data pointed to by `AData` to the newly allocated slot.

Errors: If the maximum amount of values is reached or an invalid index is specified, `InsertKeyData` will raise an `EListError` (729) exception.

See also: `TFPSMap.Add` (768), `TFPSMap.Insert` (769), `TFPSMap.InsertKey` (770)

51.13.12 TFPSMap.Remove

Synopsis: Remove a key/value pair from the map.

Declaration: `function Remove(AKey: Pointer) : Integer`

Visibility: public

Description: `Remove` removes the key/value pair pointing to by `AKey` from the map. It returns the index of `Akey` prior to removal from the list. If `AKey` was not found, -1 is returned.

Errors: None.

See also: `TFPSList.Delete` (761), `TFPSMap.IndexOf` (769)

51.13.13 TFPSMap.Sort

Synopsis: Sort the list according to key

Declaration: `procedure Sort`

Visibility: public

Description: `Sort` sorts the list according to the key value, using the compare function provided in `TFPSMap.OnKeyPtrCompare` (773)

Errors: None.

See also: `TFPSMap.OnKeyPtrCompare` (773), `TFPSMap.OnDataPtrCompare` (773)

51.13.14 TFPSMap.Duplicates

Synopsis: What to do with duplicate key values

Declaration: `Property Duplicates : TDuplicates`

Visibility: public

Access: Read, Write

Description: `Duplicates` can be set to determine what to do with duplicate key values in the map:

dupIgnore Ignore the new item, do not add it to the list.

dupAccept Accept duplicates, adding them to the list.

dupError Raise an error when an attempt is made to add a duplicate.

The value is ignored if `Sorted` (772) is `False`.

See also: `TFPSMap.Sorted` (772), `types.TDuplicates` (728)

51.13.15 TFPSMap.KeySize

Synopsis: Size (in bytes) for the key

Declaration: `Property KeySize : Integer`

Visibility: public

Access: Read

Description: `KeySize` is the size (in bytes) for the keys in the map. This size is initialized during list construction and defaults to the size of a pointer.

See also: `TFPSMap.Create` (768), `TFPSMap.DataSize` (771), `TFPSMap.Keys` (772), `TFPSMap.KeyData` (772)

51.13.16 TFPSMap.DataSize

Synopsis: Size (in bytes) for the data associated with keys

Declaration: `Property DataSize : Integer`

Visibility: public

Access: Read

Description: `DataSize` is the size (in bytes) for the data in the map. This size is initialized during list construction and defaults to the size of a pointer.

See also: `TFPSMap.Create` (768), `TFPSMap.KeySize` (771), `TFPSMap.Keys` (772), `TFPSMap.KeyData` (772), `TFPSMap.Data` (772)

51.13.17 TFPSMap.Keys

Synopsis: Indexed access to the locations of all keys

Declaration: `Property Keys[Index: Integer]: Pointer`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to all keys. It does not return the key, but returns a pointer to the key value. When setting the `Keys` property, a pointer to the key value must be set, and the key value is copied from the pointer.

See also: `TFPSMap.KeySize` ([771](#)), `TFPSMap.KeyData` ([772](#)), `TFPSMap.Data` ([772](#))

51.13.18 TFPSMap.Data

Synopsis: Indexed access to the locations of all data items

Declaration: `Property Data[Index: Integer]: Pointer`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to all data. It does not return the actual data, but returns a pointer to the data. When setting the `Data` property, a pointer to the data value must be set, and the data value is copied from the pointer.

See also: `TFPSMap.DataSize` ([771](#)), `TFPSMap.KeyData` ([772](#)), `TFPSMap.Keys` ([772](#))

51.13.19 TFPSMap.KeyData

Synopsis: Access to data locations using key

Declaration: `Property KeyData[Key: Pointer]: Pointer; default`

Visibility: public

Access: Read,Write

Description: `KeyData` provides access to the data items, using their key value (as pointed to by `AKey`) as an index. When reading a non-existent key value, `Nil` is returned. If the key is found, a pointer to the associated data's location is returned. When writing, the key pointed to by `Key` is added if it was not present, and the data data is copied from the written pointer.

See also: `TFPSMap.DataSize` ([771](#)), `TFPSMap.KeyData` ([772](#)), `TFPSMap.Data` ([772](#)), `TFPSMap.Keys` ([772](#)), `TFPSMap.KeySize` ([771](#))

51.13.20 TFPSMap.Sorted

Synopsis: Is the map permanently sorted on key ?

Declaration: `Property Sorted : Boolean`

Visibility: public

Access: Read,Write

Description: `Sorted` can be set to `true` to keep the map permanently sorted on key value. The sorting happens using `TFPSMap.OnKeyPtrCompare` (773).

See also: `TFPSMap.OnKeyPtrCompare` (773), `TFPSMap.Sort` (770), `TFPSMap.Duplicates` (771)

51.13.21 TFPSMap.OnPtrCompare

Synopsis: Alias for `OnKeyPtrCompare`

Declaration: `Property OnPtrCompare : TFPSListCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnPtrCompare` is a deprecated alias for `OnKeyPtrCompare` (773).

See also: `TFPSMap.OnKeyPtrCompare` (773), `TFPSMap.OnDataPtrCompare` (773)

51.13.22 TFPSMap.OnKeyPtrCompare

Synopsis: Callback to compare 2 keys

Declaration: `Property OnKeyPtrCompare : TFPSListCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnKeyPtrCompare` is used to compare the values of 2 keys. By default it simply compares the byte values of the key memory block. It can be set to any function that performs another comparison. (e.g. a function that treats the memory blocks as a string pointer and compare the actual strings).

This function is used to sort the list or find a key.

See also: `TFPSListCompareFunc` (728), `TFPSMap.OnDataPtrCompare` (773), `TFPSMap.Sort` (770), `TFPSMap.Find` (768), `TFPSMap.IndexOf` (769)

51.13.23 TFPSMap.OnDataPtrCompare

Synopsis: Callback to compare 2 data items

Declaration: `Property OnDataPtrCompare : TFPSListCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnKeyPtrCompare` is used to compare the values of 2 keys. By default it simply compares the byte values of the key memory block. It can be set to any function that performs another comparison. (e.g. a function that treats the memory blocks as a string pointer and compare the actual strings).

This function is used to find a data item (`IndexOf` (769)).

See also: `TFPSListCompareFunc` (728), `TFPSMap.OnKeyPtrCompare` (773), `TFPSMap.IndexOfData` (769)

Chapter 52

Reference for unit 'fpwiderstring'

52.1 Used units

Table 52.1: Used units by unit 'fpwiderstring'

Name	Page
System	1339
unicodedata	2052

52.2 Overview

`fpwiderstring` implements Unicode string support for the Free Pascal RTL using native Object Pascal routines. It is meant to be used on operating systems where the operating system does not natively support Unicode transformations and operations.

In general, it is sufficient to include the unit in the uses clause of a program. The initialization code of the unit will set the Unicode string manager of the system unit to the object pascal implementation contained in this unit.

This unit needs Unicode collation and character set tables in order to be able to do its work correctly. These must be registered using the routines of the `unicodedata` ([774](#)) unit: the FPC project distributes some Unicode collation data in `.bco` files which can be loaded using the `LoadCollation` ([2063](#)) routine.

In order for sorting and comparing of strings to work, a collation must be used. The collation in general depends on the internationalization of the application. Since the system unit does not know about collations, the collation must be set in the `fpWideString` unit using the `SetActiveCollation` ([775](#)) function. The collation can be set on a per-thread basis.

New threads get `DefaultCollationName` ([775](#)) as the active collation name.

The `fpwiderstring` unit performs conversions between Unicode and single-byte ansistring conversions (excluding UTF8). Support for various single-byte encodings are based on the `charset` ([774](#)) unit. This unit can be used to load single byte code pages. Various code page units such as `cp895`, `cp932`, `cp950` are provided by the "rtl-unicode" package.

The `fpwiderstring` requires at least the Default Unicode Collation Element Table to be registered (called `DUCET`). The `DUCET` encoding is provided by the `unicodeducet` unit. More information can be found in the `unicodedata` ([774](#)) unit.

52.3 Constants, types and variables

52.3.1 Variables

`DefaultCollationName` : `UnicodeString` = ''

`DefaultCollationName` is the collation name for new threads. It is empty by default.

52.4 Procedures and functions

52.4.1 GetActiveCollation

Synopsis: Return the currently active collation for the current thread

Declaration: `function GetActiveCollation : PUCA_DataBook`

Visibility: default

Description: `GetActiveCollation` returns the currently active collation, for the current thread, as set using the `SetActiveCollation` (775) function.

New threads get `DefaultCollationName` (775) as the active collation name. The collation can be changed per thread using the `SetActiveCollation` (775) function.

Errors: None.

See also: `SetActiveCollation` (775), `DefaultCollationName` (775)

52.4.2 SetActiveCollation

Synopsis: Set the active collation for the current thread.

Declaration: `function SetActiveCollation(const AName: UnicodeString) : Boolean`
`function SetActiveCollation(const ACollation: PUCA_DataBook) : Boolean`

Visibility: default

Description: `SetActiveCollation` sets the collation used in the current thread of the application. This can be done using the name of the collation (`AName`) as registered or in the `unicodedata` (774) unit or using the actual collation data (`ACollation`).

Errors: If the collation `AName` was not found, or `ACollation` is nil, then `False` is returned.

See also: `GetActiveCollation` (775), `DefaultCollationName` (775)

Chapter 53

Reference for unit 'getopts'

53.1 Used units

Table 53.1: Used units by unit 'getopts'

Name	Page
System	1339

53.2 Overview

This document describes the GETOPTS unit for Free Pascal. It was written for Linux by Michael Van Canneyt. It now also works for all supported platforms.

The getopts unit provides a mechanism to handle command-line options in a structured way, much like the GNU getopts mechanism. It allows you to define the valid options for your program, and the unit will then parse the command-line options for you, and inform you of any errors.

53.3 Constants, types and variables

53.3.1 Constants

`EndOfOptions = #255`

Returned by `getopt` ([778](#)), `getlongopts` ([777](#)) to indicate that there are no more options.

`No_Argument = 0`

Specifies that a long option does not take an argument.

`Optional_Argument = 2`

Specifies that a long option optionally takes an argument.

`OptSpecifier : Set of Char = ['-']`

Character indicating an option on the command-line.

`Required_Argument = 1`

Specifies that a long option needs an argument.

53.3.2 Types

`Orderings = (require_order, permute, return_in_order)`

Table 53.2: Enumeration values for type `Orderings`

Value	Explanation
<code>permute</code>	Change command-line options.
<code>require_order</code>	Don't touch the ordering of the command-line options
<code>return_in_order</code>	Return options in the correct order.

Command-line ordering options.

`POption = ^TOption`

Pointer to `TOption` (781) record.

53.3.3 Variables

`OptArg : string`

Set to the argument of an option, if the option needs one.

`OptErr : Boolean`

Indicates whether `getopt()` prints error messages.

`OptInd : LongInt`

when all options have been processed, `optind` is the index of the first non-option parameter. This is a read-only variable. Note that it can become equal to `paramcount+1`.

`OptOpt : Char`

In case of an error, contains the character causing the error.

53.4 Procedures and functions

53.4.1 GetLongOpts

Synopsis: Return next long option.

Declaration: `function GetLongOpts (ShortOpts: string; LongOpts: POption;
var Longind: LongInt) : Char`

Visibility: default

Description: Returns the next option found on the command-line, taking into account long options as well. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

if any of the option definitions in `LongOpts` array has the `Flag` pointer set, then the return value is the null character (`#0` or `char(0)`) and the actual option letter is written in the location pointed to by `Flag`.

`ShortOptions` is a string containing all possible one-letter options. (see [Getopt \(778\)](#) for its description and use) `LongOpts` is a pointer to the first element of an array of `Option` records, the last of which needs a name of zero length.

The function tries to match the names even partially (i.e. `-app` will match e.g. the append option), but will report an error in case of ambiguity.

If the option needs an argument, set `Has_arg` to `Required_argument` (1), if the option optionally has an argument, set `Has_arg` to `Optional_argument` (2). If the option needs no argument, set `Has_arg` to zero.

Required arguments can be specified in two ways :

1. Pasted to the option : `-option=value`
2. As a separate argument : `-option value`

Optional arguments can only be specified through the first method.

Errors: see [Getopt \(778\)](#).

See also: [Getopt \(778\)](#)

53.4.2 GetOpt

Synopsis: Get next short option.

Declaration: `function GetOpt (ShortOpts: string) : Char`

Visibility: default

Description: Returns the next option found on the command-line. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

`ShortOptions` is a string containing all possible one-letter options. If a letter is followed by a colon (:), then that option needs an argument. If a letter is followed by 2 colons, the option has an optional argument. If the first character of `shortoptions` is a '+' then options following a non-option are regarded as non-options (standard Unix behavior). If it is a '-', then all non-options are treated as arguments of a option with character #0. This is useful for applications that require their options in the exact order as they appear on the command-line. If the first character of `shortoptions` is none of the above, options and non-options are permuted, so all non-options are behind all options. This allows options and non-options to be in random order on the command line.

Errors: Errors are reported through giving back a '?' character. `OptOpt` then gives the character which caused the error. If `OptErr` is `True` then `getopt` prints an error-message to `stdout`.

See also: [GetLongOpts \(777\)](#)

Listing: `./examples/optex/optex.pp`

```

program testopt;

{ Program to depmonstrate the getopt function. }

{
  Valid calls to this program are
  optex —verbose —add me —delete you
  optex —append —create child
  optex -ab -c me -d you
  and so on
}
uses getopt;

var c : char;
    optionindex : Longint;
    theopts : array[1..7] of TOption;

begin
  with theopts[1] do
    begin
      name:= 'add';
      has_arg:=1;
      flag:= nil;
      value:=#0;
    end;
  with theopts[2] do
    begin
      name:= 'append';
      has_arg:=0;
      flag:= nil;
      value:=#0;
    end;
  with theopts[3] do
    begin
      name:= 'delete';
      has_arg:=1;
      flag:= nil;
      value:=#0;
    end;
  with theopts[4] do
    begin
      name:= 'verbose';
      has_arg:=0;
      flag:= nil;
      value:=#0;
    end;
  with theopts[5] do
    begin
      name:= 'create';
      has_arg:=1;
      flag:= nil;
      value:= 'c'
    end;
  with theopts[6] do
    begin
      name:= 'file';
      has_arg:=1;
      flag:= nil;

```

```

    value:=#0;
end;
with theopts[7] do
begin
    name:= '';
    has_arg:=0;
    flag:=nil;
end;
c:=#0;
repeat
    c:=getlongopts ('abc:d:012',@theo[1],optionindex);
    case c of
        '1','2','3','4','5','6','7','8','9' :
            begin
                writeln ('Got optind : ',c)
            end;
        #0 : begin
                write ('Long option : ',theo[optionindex].name);
                if theopts[optionindex].has_arg>0 then
                    writeln (' With value : ',optarg)
                else
                    writeln
                end;
                'a' : writeln ('Option a. ');
                'b' : writeln ('Option b. ');
                'c' : writeln ('Option c : ', optarg);
                'd' : writeln ('Option d : ', optarg);
                '?' : writeln ('Error with opt : ',optopt);
            end; { case }
    until c=endofoptions;
    if optind<=paramcount then
        begin
            write ('Non options : ');
            while optind<=paramcount do
                begin
                    write (paramstr(optind), ' ');
                    inc(optind)
                end;
            writeln
        end
    end.

```

53.5 TOption

```

TOption = record
public
    Name : string;
    Has_arg : Integer;
    Flag
    : PChar;
    Value : Char;
    procedure SetOption(const aName: string
    ; AHas_Arg: Integer;
    AFlag: PChar; AValue: Char
    );

```

end

The `TOption` type is used to communicate the long options to `GetLongOpts` (777). The `Name` field is the name of the option. `Has_arg` specifies if the option wants an argument, `Flag` is a pointer to a char, which is set to `Value`, if it is non-nil.

53.5.1 Method overview

Page	Method	Description
781	<code>SetOption</code>	Set all option fields in 1 call

53.5.2 `TOption.SetOption`

Synopsis: Set all option fields in 1 call

Declaration: `procedure SetOption(const aName: string; AHas_Arg: Integer;
AFlag: PChar; AValue: Char)`

Visibility: public

Description: `SetOption` can be used to set all fields in 1 single call:

- Name is set to `aName`
- Has_arg is set to `aHas_arg`
- Flag is set to `aFlag`
- Value is set to `aValue`

Chapter 54

Reference for unit 'go32'

54.1 Used units

Table 54.1: Used units by unit 'go32'

Name	Page
System	1339

54.2 Overview

This document describes the GO32 unit for the Free Pascal compiler under dos. It was donated by Thomas Schatzl (tom_at_work@geocities.com), for which my thanks. This unit was first written for dos by Florian Klaempfl.

Only the GO32V2 DPMI mode is discussed by me here due to the fact that new applications shouldn't be created with the older GO32V1 model. The go32v2 version is much more advanced and better. Additionally a lot of functions only work in DPMI mode anyway. I hope the following explanations and introductions aren't too confusing at all. If you notice an error or bug send it to the FPC mailing list or directly to me. So let's get started and happy and error free coding I wish you.... Thomas Schatzl, 25. August 1998

54.3 Real mode callbacks

The callback mechanism can be thought of as the converse of calling a real mode procedure (i.e. interrupt), which allows your program to pass information to a real mode program, or obtain services from it in a manner that's transparent to the real mode program. In order to make a real mode callback available, you must first get the real mode callback address of your procedure and the selector and offset of a register data structure. This real mode callback address (this is a segment:offset address) can be passed to a real mode program via a software interrupt, a dos memory block or any other convenient mechanism. When the real mode program calls the callback (via a far call), the DPMI host saves the registers contents in the supplied register data structure, switches into protected mode, and enters the callback routine with the following settings:

- interrupts disabled

- `%CS : %EIP` = 48 bit pointer specified in the original call to `get_rm_callback` (808)
- `%DS : %ESI` = 48 bit pointer to real mode `SS : SP`
- `%ES : %EDI` = 48 bit pointer of real mode register data structure.
- `%SS : %ESP` = locked protected mode stack
- All other registers undefined

The callback procedure can then extract its parameters from the real mode register data structure and/or copy parameters from the real mode stack to the protected mode stack. Recall that the segment register fields of the real mode register data structure contain segment or paragraph addresses that are not valid in protected mode. Far pointers passed in the real mode register data structure must be translated to virtual addresses before they can be used with a protected mode program. The callback procedure exits by executing an `IRET` with the address of the real mode register data structure in `%ES : %EDI`, passing information back to the real mode caller by modifying the contents of the real mode register data structure and/or manipulating the contents of the real mode stack. The callback procedure is responsible for setting the proper address for resumption of real mode execution into the real mode register data structure; typically, this is accomplished by extracting the return address from the real mode stack and placing it into the `%CS : %EIP` fields of the real mode register data structure. After the `IRET`, the DPMI host switches the CPU back into real mode, loads ALL registers with the contents of the real mode register data structure, and finally returns control to the real mode program. All variables and code touched by the callback procedure **MUST** be locked to prevent page faults.

See also: `get_rm_callback` (808), `free_rm_callback` (803), `lock_code` (819), `lock_data` (819)

54.4 Executing software interrupts

Simply execute a `realintr()` call with the desired interrupt number and the supplied register data structure. But some of these interrupts require you to supply them a pointer to a buffer where they can store data to or obtain data from in memory. These interrupts are real mode functions and so they only can access the first Mb of linear address space, not FPC's data segment. For this reason FPC supplies a pre-initialized dos memory location within the GO32 unit. This buffer is internally used for dos functions too and so it's contents may change when calling other procedures. It's size can be obtained with `tb_size` (829) and it's linear address via `transfer_buffer` (830). Another way is to allocate a completely new dos memory area via the `global_dos_alloc` (815) function for your use and supply its real mode address.

See also: `tb_size` (829), `transfer_buffer` (830), `global_dos_alloc` (815), `global_dos_free` (817), `realintr` (821)

Listing: `./examples/go32ex/softint.pp`

```
{ Executes a real mode software interrupt

Exactly the interrupt call to get the DOS version.

get DOS version Int 21h / function 30h
Input:
    AH = $30
    AL = $1
Return:
    AL = major version number
    AH = minor version number
}
```



```

uses
    go32;

var
    r : trealregs;

begin
    r.ah := $30;
    r.al := $01;
    realintr($21, r);
    WriteLn('DOS v', r.al, '.', r.ah, ' detected');
end.

```

Listing: ./examples/go32ex/rmpmint.pp

{ This example shows the difference between protected and real mode interrupts; it redirects the protected mode handler to an own handler which returns an impossible function result and calls it afterwards. Then the real mode handler is called directly, to show the difference between the two. }

Used Interrupt:
get DOS version Int 21h / function 30h
Input: AH = \$30
AL = \$1
Return: AL = major version number
AH = minor version number
}

```

uses
    crt ,
    go32;

var
    r : trealregs;
    { temporary variable used for the protected mode int call }
    axreg : Word;

    oldint21h : tseginfo;
    newint21h : tseginfo;

{ this is our int 21h protected mode interupt handler. It catches the function call to get the DOS version, all other int 21h calls are redirected to the old handler; it is written in assembly because the old handler can't be called with pascal }
procedure int21h_handler; assembler;
asm
    cmpw $0x3001, %ax
    jne .LCallOld
    movw $0x3112, %ax
    iret

.LCallOld:
    ljmp %cs:oldint21h
end;

{ a small helper procedure, which waits for a keypress }
procedure resume;

```

```

begin
    Writeln;
    Write('— press any key to resume —'); readkey;
    gotoxy(1, wherey); clreol;
end;

begin
    { see the text messages for further detail }
    clrscr;
    Writeln('Executing real mode interrupt');
    resume;
    r.ah := $30; r.al := $01; realintr($21, r);
    Writeln('DOS v', r.al, '.', r.ah, ' detected');
    resume;
    Writeln('Executing protected mode interrupt without our own',
            ' handler');
    Writeln;
    asm
        movb $0x30, %ah
        movb $0x01, %al
        int $0x21
        movw %ax, axreg
    end;
    Writeln('DOS v', r.al, '.', r.ah, ' detected');
    resume;
    Writeln('As you can see the DPML hosts default protected mode',
            ' handler');
    Writeln('simply redirects it to the real mode handler');
    resume;
    Writeln('Now exchanging the protected mode interrupt with our ',
            ' own handler');
    resume;

    newint21h.offset := @int21h_handler;
    newint21h.segment := get_cs;
    get_pm_interrupt($21, oldint21h);
    set_pm_interrupt($21, newint21h);

    Writeln('Executing real mode interrupt again');
    resume;
    r.ah := $30; r.al := $01; realintr($21, r);
    Writeln('DOS v', r.al, '.', r.ah, ' detected');
    Writeln;
    Writeln('See, it didn''t change in any way.');
    resume;
    Writeln('Now calling protected mode interrupt');
    resume;
    asm
        movb $0x30, %ah
        movb $0x01, %al
        int $0x21
        movw %ax, axreg
    end;
    Writeln('DOS v', lo(axreg), '.', hi(axreg), ' detected');
    Writeln;
    Writeln('Now you can see that there''s a distinction between ',
            ' the two ways of calling interrupts...');
    set_pm_interrupt($21, oldint21h);

```

end.

54.5 Software interrupts

Ordinarily, a handler installed with `set_pm_interrupt` (826) only services software interrupts that are executed in protected mode; real mode software interrupts can be redirected by `set_rm_interrupt` (828).

See also: `set_rm_interrupt` (828), `get_rm_interrupt` (812), `set_pm_interrupt` (826), `get_pm_interrupt` (807), `lock_data` (819), `lock_code` (819), `enable` (802), `disable` (800), `outportb` (820)

54.6 Hardware interrupts

Hardware interrupts are generated by hardware devices when something unusual happens; this could be a keypress or a mouse move or any other action. This is done to minimize CPU time, else the CPU would have to check all installed hardware for data in a big loop (this method is called 'polling') and this would take much time. A standard IBM-PC has two interrupt controllers, that are responsible for these hardware interrupts: both allow up to 8 different interrupt sources (IRQs, interrupt requests). The second controller is connected to the first through IRQ 2 for compatibility reasons, e.g. if controller 1 gets an IRQ 2, he hands the IRQ over to controller 2. Because of this up to 15 different hardware interrupt sources can be handled. IRQ 0 through IRQ 7 are mapped to interrupts 8h to Fh and the second controller (IRQ 8 to 15) is mapped to interrupt 70h to 77h. All of the code and data touched by these handlers MUST be locked (via the various locking functions) to avoid page faults at interrupt time. Because hardware interrupts are called (as in real mode) with interrupts disabled, the handler has to enable them before it returns to normal program execution. Additionally a hardware interrupt must send an EOI (end of interrupt) command to the responsible controller; this is accomplished by sending the value 20h to port 20h (for the first controller) or A0h (for the second controller). The following example shows how to redirect the keyboard interrupt.

Listing: ./examples/go32ex/keyclick.pp

{ This example demonstrates how to chain to a hardware interrupt.

In more detail, it hooks the keyboard interrupt, calls a user procedure which in this case simply turns the PC speaker on and off. Then the old interrupt is called.

```
{ $ASMMODE ATT }
{ $MODE FPC }
```

uses

```
crt ,
go32;
```

const

```
{ keyboard is IRQ 1 -> interrupt 9 }
kbdint = $9;
```

var

```
{ holds old PM interrupt handler address }
oldint9_handler : tseginfo;
{ new PM interrupt handler }
```

```

newint9_handler : tseinfo;

{ pointer to interrupt handler }
clickproc : pointer;
{ the data segment selector }
backupDS : Word; external name '___v2prt0_ds_alias';

{ interrupt handler }
procedure int9_handler; assembler;
asm
    cli
    { save all registers, because we don't know which the compiler
      uses for the called procedure }
    pushl %ds
    pushl %es
    pushl %fs
    pushl %gs
    pushal
    { set up to call a FPC procedure }
    movw %cs:backupDS, %ax
    movw %ax, %ds
    movw %ax, %es
    movw dosmemselector, %ax
    movw %ax, %fs
    { call user procedure }
    call *clickproc
    { restore all registers }
    popal
    popl %gs
    popl %fs
    popl %es
    popl %ds
    { note: in go32v2 mode %cs=%ds=%es !!!}
    jmp %cs:oldint9_handler { call old handler }
    { we don't need to do anything more, because the old interrupt
      handler does this for us (send EOI command, iret, sti...) }
end;
{ dummy procedure to retrieve exact length of handler, for locking
  and unlocking functions }
procedure int9_dummy; begin end;

{ demo user procedure, simply clicks on every keypress }
procedure clicker;
begin
    sound(500); delay(10); nosound;
end;
{ dummy procedure to retrieve exact length of user procedure for
  locking and unlocking functions }
procedure clicker_dummy; begin end;

{ installs our new handler }
procedure install_click;
begin
    clickproc := @clicker;
    { lock used code and data }
    lock_data(clickproc, sizeof(clickproc));
    lock_data(dosmemselector, sizeof(dosmemselector));

```

```

lock_code(@clicker ,
          longint(@clicker_dummy) - longint(@clicker));
lock_code(@int9_handler ,
          longint(@int9_dummy)-longint(@int9_handler));
{ fill in new handler's 48 bit pointer }
newint9_handler.offset := @int9_handler;
newint9_handler.segment := get_cs;
{ get old PM interrupt handler }
get_pm_interrupt(kbdint , oldint9_handler);
{ set the new interrupt handler }
set_pm_interrupt(kbdint , newint9_handler);
end;

{ deinstalls our interrupt handler }
procedure remove_click;
begin
    { set old handler }
    set_pm_interrupt(kbdint , oldint9_handler);
    { unlock used code & data }
    unlock_data(dosmemselector , sizeof(dosmemselector));
    unlock_data(clickproc , sizeof(clickproc));

    unlock_code(@clicker ,
                longint(@clicker_dummy)-longint(@clicker));
    unlock_code(@int9_handler ,
                longint(@int9_dummy)-longint(@int9_handler));
end;

var
    ch : char;

begin
    install_click;
    WriteLn('Enter any message. Press return when finished');
    while (ch <> #13) do begin
        ch := readkey; write(ch);
    end;
    remove_click;
end.

```

54.7 Disabling interrupts

The GO32 unit provides the two procedures `disable()` and `enable()` to disable and enable all interrupts.

54.8 Creating your own interrupt handlers

Interrupt redirection with FPC pascal is done via the `set_pm_interrupt()` for protected mode interrupts or via the `set_rm_interrupt()` for real mode interrupts.

54.9 Protected mode interrupts vs. Real mode interrupts

As mentioned before, there's a distinction between real mode interrupts and protected mode interrupts; the latter are protected mode programs, while the former must be real mode programs. To call a protected mode interrupt handler, an assembly 'int' call must be issued, while the other is called via the `realintr()` or `intr()` function. Consequently, a real mode interrupt then must either reside in dos memory (<1MB) or the application must allocate a real mode callback address via the `get_rm_callback()` function.

54.10 Handling interrupts with DPMI

The interrupt functions are real-mode procedures; they normally can't be called in protected mode without the risk of an protection fault. So the DPMI host creates an interrupt descriptor table for the application. Initially all software interrupts (except for int 31h, 2Fh and 21h function 4Ch) or external hardware interrupts are simply directed to a handler that reflects the interrupt in real-mode, i.e. the DPMI host's default handlers switch the CPU to real-mode, issue the interrupt and switch back to protected mode. The contents of general registers and flags are passed to the real mode handler and the modified registers and flags are returned to the protected mode handler. Segment registers and stack pointer are not passed between modes.

54.11 Interrupt redirection

Interrupts are program interruption requests, which in one or another way get to the processor; there's a distinction between software and hardware interrupts. The former are explicitly called by an 'int' instruction and are a bit comparable to normal functions. Hardware interrupts come from external devices like the keyboard or mouse. Functions that handle hardware interrupts are called handlers.

54.12 Processor access

These are some functions to access various segment registers (`%cs`, `%ds`, `%ss`) which makes your work a bit easier.

See also: `get_cs` (803), `get_ds` (804), `get_ss` (814)

54.13 I/O port access

The I/O port access is done via the various `inportb` (818), `outportb` (820) functions which are available. Additionally Free Pascal supports the Turbo Pascal `PORT[]`-arrays but it is by no means recommended to use them, because they're only for compatibility purposes.

See also: `outportb` (820), `inportb` (818)

54.14 dos memory access

Dos memory is accessed by the predefined `dosmemselector` selector; the GO32 unit additionally provides some functions to help you with standard tasks, like copying memory from heap to dos memory and the likes. Because of this it is strongly recommended to use them, but you are still free

to use the provided standard memory accessing functions which use 48 bit pointers. The third, but only thought for compatibility purposes, is using the `mem[]`-arrays. These arrays map the whole 1 Mb dos space. They shouldn't be used within new programs. To convert a segment:offset real mode address to a protected mode linear address you have to multiply the segment by 16 and add its offset. This linear address can be used in combination with the `DOSMEMSELECTOR` variable.

See also: `dosmemget` (791), `dosmempnt` (792), `dosmemmove` (792), `dosmemfillchar` (791), `dosmemfillword` (791), `seg_move` (825), `seg_fillchar` (823), `seg_fillword` (824)

54.15 FPC specialities

The `%ds` and `%es` selector MUST always contain the same value or some system routines may crash when called. The `%fs` selector is preloaded with the `DOSMEMSELECTOR` variable at startup, and it MUST be restored after use, because again FPC relies on this for some functions. Luckily we asm programmers can still use the `%gs` selector for our own purposes, but for how long ?

See also: `get_cs` (803), `get_ds` (804), `get_ss` (814), `allocate_ldt_descriptors` (795), `free_ldt_descriptor` (802), `segment_to_descriptor` (823), `get_next_selector_increment_value` (806), `get_segment_base_address` (814), `set_segment_base_address` (828), `set_segment_limit` (828), `create_code_segment_alias_descriptor` (800)

54.16 Selectors and descriptors

Descriptors are a bit like real mode segments; they describe (as the name implies) a memory area in protected mode. A descriptor contains information about segment length, its base address and the attributes of it (i.e. type, access rights, ...). These descriptors are stored internally in a so-called descriptor table, which is basically an array of such descriptors. Selectors are roughly an index into this table. Because these 'segments' can be up to 4 GB in size, 32 bits aren't sufficient anymore to describe a single memory location like in real mode. 48 bits are now needed to do this, a 32 bit address and a 16 bit sized selector. The GO32 unit provides the `tseginfo` record to store such a pointer. But due to the fact that most of the time data is stored and accessed in the `%ds` selector, FPC assumes that all pointers point to a memory location of this selector. So a single pointer is still only 32 bits in size. This value represents the offset from the data segment base address to this memory location.

54.17 What is DPMI

The dos Protected Mode Interface helps you with various aspects of protected mode programming. These are roughly divided into descriptor handling, access to dos memory, management of interrupts and exceptions, calls to real mode functions and other stuff. Additionally it automatically provides swapping to disk for memory intensive applications. A DPMI host (either a Windows dos box or `CWSDPMI.EXE`) provides these functions for your programs.

54.18 Constants, types and variables

54.18.1 Constants

```
auxcarryflag = $010
```

Check for auxiliary carry flag in `trealregs` (795)

```
carryflag = $001
```

Check for carry flag in `trealregs` (795)

```
directionflag = $400
```

Check for direction flag in `trealregs` (795)

```
dosmemfillchar : procedure(seg: Word; ofs: Word; count: LongInt; c
    : Char) = @ dpmi_dosmemfillchar
```

Sets a region of dos memory to a specific byte value.

Parameters:

seg real mode segment.

ofs real mode offset.

count number of bytes to set.

c value to set memory to.

Notes: No range check is performed.

```
dosmemfillword : procedure(seg: Word; ofs: Word; count: LongInt; w
    : Word) = @ dpmi_dosmemfillword
```

Sets a region of dos memory to a specific word value.

Parameters:

seg real mode segment.

ofs real mode offset.

count number of words to set.

w value to set memory to.

Notes: No range check is performed.

```
dosmemget : procedure(seg: Word; ofs: Word; var data; count: LongInt
    ) = @ dpmi_dosmemget
```

Copies data from the dos memory onto the heap.

Parameters:

seg source real mode segment.

ofs source real mode offset.

data destination.

count number of bytes to copy.

Notes: No range checking is performed.

For an example, see `global_dos_alloc` (815).

```
dosmemmove : procedure(sseg: Word; sofs: Word; dseg: Word; dofs: Word
;
count: LongInt) = @ dpmi_dosmemmove
```

Copies count bytes of data between two dos real mode memory locations.

Parameters:

sseg source real mode segment.

sofs source real mode offset.

dseg destination real mode segment.

dofs destination real mode offset.

count number of bytes to copy.

Notes: No range check is performed in any way.

```
dosmemput : procedure(seg: Word; ofs: Word; var data; count: LongInt
) = @ dpmi_dosmemput
```

Copies heap data to dos real mode memory.

Parameters:

seg destination real mode segment.

ofs destination real mode offset.

data source.

count number of bytes to copy.

Notes: No range checking is performed.

For an example, see `global_dos_alloc` (815).

```
interruptflag = $200
```

Check for interrupt flag in `trealregs` (795)

```
overflowflag = $800
```

Check for overflow flag in `trealregs` (795)

```
parityflag = $004
```

Check for parity flag in `trealregs` (795)

```
rm_dpml = 4
```

get_run_mode (813) return value: DPML (e.g. dos box or 386Max)

```
rm_raw = 1
```

get_run_mode (813) return value: raw (without HIMEM)

```
rm_unknown = 0
```

get_run_mode (813) return value: Unknown runmode

```
rm_vcpi = 3
```

get_run_mode (813) return value: VCPI (with HIMEM and EMM386)

```
rm_xms = 2
```

get_run_mode (813) return value: XMS (with HIMEM, without EMM386)

```
signflag = $080
```

Check for sign flag in trealregs (795)

```
trapflag = $100
```

Check for trap flag in trealregs (795)

```
zeroflag = $040
```

Check for zero flag in trealregs (795)

54.18.2 Types

```
registers = trealregs
```

Alias for trealregs (795)

```
treallregs = record
case Integer of
1: (
    EDI : LongInt;
    ESI : LongInt
    ;
    EBP : LongInt;
    Res : LongInt;
    EBX : LongInt;
    EDX : LongInt
    ;
    ECX : LongInt;
    EAX : LongInt;
```

```
Flags : Word;
ES : Word;
DS : Word;
FS : Word;
GS : Word;
IP : Word;
CS : Word;
SP : Word;
SS : Word;
);
2: (
  DI : Word;
  DI2 : Word;
  SI
  : Word;
  SI2 : Word;
  BP : Word;
  BP2 : Word;
  R1 : Word;
  R2
  : Word;
  BX : Word;
  BX2 : Word;
  DX : Word;
  DX2 : Word;
  CX
  : Word;
  CX2 : Word;
  AX : Word;
  AX2 : Word;
);
3: (
  stuff
  : Array[1..4] of LongInt;
  BL : Byte;
  BH : Byte;
  BL2 : Byte
  ;
  BH2 : Byte;
  DL : Byte;
  DH : Byte;
  DL2 : Byte;
  DH2 : Byte
  ;
  CL : Byte;
  CH : Byte;
  CL2 : Byte;
  CH2 : Byte;
  AL : Byte
  ;
  AH : Byte;
  AL2 : Byte;
  AH2 : Byte;
);
```

```

4: (
    RealEDI : LongInt
    ;
    RealESI : LongInt;
    RealEBP : LongInt;
    RealRES : LongInt;
    RealEBX : LongInt;
    RealEDX : LongInt;
    RealECX : LongInt;
    RealEAX
    : LongInt;
    RealFlags : Word;
    RealES : Word;
    RealDS : Word;
    RealFS : Word;
    RealGS : Word;
    RealIP : Word;
    RealCS : Word
    ;
    RealSP : Word;
    RealSS : Word;
);
end

```

The `trealregs` type contains the data structure to pass register values to a interrupt handler or real mode callback.

54.18.3 Variables

```
dosmemselector : Word
```

Selector to the dos memory. The whole dos memory is automatically mapped to this single descriptor at startup. This selector is the recommended way to access dos memory.

```
int31error : Word
```

This variable holds the result of a DPMI interrupt call. Any nonzero value must be treated as a critical failure.

54.19 Procedures and functions

54.19.1 `allocate_ldt_descriptors`

Synopsis: Allocate a number of descriptors

Declaration: `function allocate_ldt_descriptors(count: Word) : Word`

Visibility: default

Description: Allocates a number of new descriptors.

Parameters:

count: \specifies the number of requested unique descriptors.

Return value: The base selector.

Remark Notes: The descriptors allocated must be initialized by the application with other function calls. This function returns descriptors with a limit and size value set to zero. If more than one descriptor was requested, the function returns a base selector referencing the first of a contiguous array of descriptors. The selector values for subsequent descriptors in the array can be calculated by adding the value returned by the `get_next_selector_increment_value` (806) function.

Errors: Check the `int31error` (795) variable.

See also: `free_ldt_descriptor` (802), `get_next_selector_increment_value` (806), `segment_to_descriptor` (823), `create_code_segment_alias_descriptor` (800), `set_segment_limit` (828), `set_segment_base_address` (828)

Listing: `./examples/go32ex/seldes.pp`

```
{
This example demonstrates the usage of descriptors and the effects of
changing its limit and base address.
```

```
In more detail, the program fills the region described by an
allocated descriptor in text screen memory with various characters.
Before doing this it saves the entire screen contents to the heap and
restores it afterwards.
```

Some additional background:

*The text screen of a VGA card has it's address space at \$B800:0;
screen memory is organized in a linear fashion, e.g. the second line
comes directly after the first, where each cell occupies 2 bytes of
memory (1 byte character data, 1 byte attributes). It is 32 kb in
size.*

Hence the offset of a single memory cell from its origin is:

$$Y * columns * 2 + X * 2$$

*where X and Y mark the point and columns is the number of character
cells per line*

```
}
{$mode delphi}
```

uses

```
crt ,
go32;
```

const

```
{ screen x and y dimensions }
maxx = 80;
maxy = 25;
{ bytes used for every character cell }
bytespercell = 2;
{ screen size in bytes }
screensize = maxx * maxy * bytespercell;
```

```
{ the linear address of $B800:0 }
linB8000 = $B800 * 16;
```

type

```
string80 = string[80];
```

```

var
    { holds the old screen contents }
    text_save : array[0..screensize-1] of byte;
    { old cursor x and y coordinates }
    text_oldx, text_oldy : Word;

    { selector to the text mode screen }
    text_sel : Word;

{ prints a status message on the first line of the screen and then
waits for a keypress }
procedure status(s : string80);
begin
    gotoxy(1, 1); clreol; write(s); readkey;
end;

{ writes some descriptor info on the last 2 lines }
procedure selinfo(sel : Word);
begin
    gotoxy(1, 24);
    clreol; writeln('Descriptor base address : $',
        hexstr(get_segment_base_address(sel), 8));
    clreol; write('Descriptor limit : ', get_segment_limit(sel));
end;

{ returns a 2 byte character cell, which includes character data
and its color attributes }
function makechar(ch : char; color : byte) : Word;
begin
    result := byte(ch) or (color shl 8);
end;

begin
    { save original screen contents to variable, this time by using
    seg_move() and the dosmemselector variable }
    seg_move(dosmemselector, linB8000, get_ds, longint(@text_save),
        screensize);
    { additionally we have to save the old screen cursor
    coordinates }
    text_oldx := wherex; text_oldy := wherey;
    { clear the whole screen }
    seg_fillword(dosmemselector, linB8000, screensize div 2,
        makechar(' ', Black or (Black shl 4)));
    { output message }
    status('Creating selector ''text_sel'' to a part of ' +
        'text screen memory');
    { allocate descriptor }
    text_sel := allocate_ldt_descriptors(1);
    { set its base address to the linear address of the text screen
    + the byte size of one line (=maxx * bytespercell * 1) }
    set_segment_base_address(text_sel,
        linB8000 + bytespercell * maxx * 1);
    { the limit is set to the screensize reduced by one (a must be)
    and the number of lines we don't want to have touched (first
    line + lower 2 lines) }
    set_segment_limit(text_sel, screensize - 1 - bytespercell *
        maxx * 3);

```

```

{ write descriptor info }
selinfo(text_sel);

status('and clearing entire memory selected by ''text_sel''' +
      ' descriptor');
{ fill the entire selected memory with single characters }
seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
             makechar(' ', LightBlue shl 4));

status('Notice that only the memory described by the ' +
      'descriptor changed, nothing else');

status('Now reducing it''s limit and base and setting it''s ' +
      'described memory');
{ set the base address of the descriptor (increase it by the
  byte size of one line) }
set_segment_base_address(text_sel,
                        get_segment_base_address(text_sel) + bytespercell * maxx);
{ decrease the limit by byte size of 2 lines (1 line because
  base address changed, one line on the lower end) }
set_segment_limit(text_sel,
                  get_segment_limit(text_sel) - bytespercell * maxx * 2);
{ write descriptor info }
selinfo(text_sel);
status('Notice that the base addr increased by one line but ' +
      'the limit decreased by 2 lines');
status('This should give you the hint that the limit is ' +
      'relative to the base');
{ fill the descriptor area }
seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
             makechar(#176, LightMagenta or Brown shl 4));

status('Now let''s get crazy and copy 10 lines of data from ' +
      'the previously saved screen');
{ copy memory from the data segment to screen }
seg_move(get_ds, longint(@text_save), text_sel,
         maxx * bytespercell * 2, maxx * bytespercell * 10);

status('At last freeing the descriptor and restoring the old ' +
      'screen contents..');
status('I hope this little program may give you some hints ' +
      'on working with descriptors');
{ free the descriptor so that it can be used for things }
free_ldt_descriptor(text_sel);
{ restore old state }
seg_move(get_ds, longint(@text_save), dosmemselector,
         linB8000, screensize);
gotoxy(text_oldx, text_oldy);
end.

```

54.19.2 allocate_memory_block

Synopsis: Allocate a block of linear memory

Declaration: function allocate_memory_block(size: LongInt) : LongInt

Visibility: default

Description: Allocates a block of linear memory.

Parameters:

size:Size of requested linear memory block in bytes.

Returned values: blockhandle - the memory handle to this memory block. Linear address of the requested memory.

Remark *warning* According to my DPMI docs this function is not implemented correctly. Normally you should also get a blockhandle to this block after successful operation. This handle can then be used to free the memory block afterwards or use this handle for other purposes. Since the function isn't implemented correctly, and doesn't return a blockhandle, the block can't be deallocated and is hence unusable ! This function doesn't allocate any descriptors for this block, it's the applications responsibility to allocate and initialize for accessing this memory.

Errors: Check the int31error (795) variable.

See also: free_memory_block (802)

54.19.3 copyfromdos

Synopsis: Copy data from DOS to heap

Declaration: `procedure copyfromdos(var addr; len: LongInt)`

Visibility: default

Description: Copies data from the pre-allocated dos memory transfer buffer to the heap.

Parameters:

addrdata to copy to.

lennumber of bytes to copy to heap.

Notes: Can only be used in conjunction with the dos memory transfer buffer.

Errors: Check the int31error (795) variable.

See also: tb_size (829), transfer_buffer (830), copytodos (799)

54.19.4 copytodos

Synopsis: Copy data from heap to DOS memory

Declaration: `procedure copytodos(var addr; len: LongInt)`

Visibility: default

Description: Copies data from heap to the pre-allocated dos memory buffer.

Parameters:

addrdata to copy from.

lennumber of bytes to copy to dos memory buffer.

Notes: This function fails if you try to copy more bytes than the transfer buffer is in size. It can only be used in conjunction with the transfer buffer.

Errors: Check the int31error (795) variable.

See also: tb_size (829), transfer_buffer (830), copyfromdos (799)

54.19.5 create_code_segment_alias_descriptor

Synopsis: Create new descriptor from existing descriptor

Declaration: `function create_code_segment_alias_descriptor(seg: Word) : Word`

Visibility: default

Description: Creates a new descriptor that has the same base and limit as the specified descriptor.

Parameters:

segDescriptor.

Return values: The data selector (alias).

Notes: In effect, the function returns a copy of the descriptor. The descriptor alias returned by this function will not track changes to the original descriptor. In other words, if an alias is created with this function, and the base or limit of the original segment is then changed, the two descriptors will no longer map the same memory.

Errors: Check the `int31error` (795) variable.

See also: `allocate_ldt_descriptors` (795), `set_segment_limit` (828), `set_segment_base_address` (828)

54.19.6 disable

Synopsis: Disable hardware interrupts

Declaration: `procedure disable`

Visibility: default

Description: Disables all hardware interrupts by execution a CLI instruction.

Errors: None.

See also: `enable` (802)

54.19.7 dpmi_dosmemfillchar

Synopsis: Fill DOS memory with a character

Declaration: `procedure dpmi_dosmemfillchar(seg: Word; ofs: Word; count: LongInt; c: Char)`

Visibility: default

Description: `dpmi_dosmemfillchar` fills the DOS memory region indicated by `seg,ofs` with `count` characters `c`.

See also: `dpmi_dosmempout` (801), `dpmi_dosmemget` (801), `dpmi_dosmemmove` (801), `dpmi_dosmemfillword` (801)

54.19.8 dpmi_dosmemfillword

Synopsis: Fill DOS memory with a word value

Declaration: `procedure dpmi_dosmemfillword(seg: Word; ofs: Word; count: LongInt; w: Word)`

Visibility: default

Description: `dpmi_dosmemfillword` fills the DOS memory region indicated by `seg,ofs` with `count` words `W`.

See also: `dpmi_dosmempout` (801), `dpmi_dosmemget` (801), `dpmi_dosmemfillchar` (800), `dpmi_dosmemmove` (801)

54.19.9 dpmi_dosmemget

Synopsis: Move data from DOS memory to DPMI memory

Declaration: `procedure dpmi_dosmemget(seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmempout` moves `count` bytes of data from the DOS memory location indicated by `seg` and `ofs` to DPMI memory indicated by `data`.

See also: `dpmi_dosmempout` (801), `dpmi_dosmemmove` (801), `dpmi_dosmemfillchar` (800), `dpmi_dosmemfillword` (801)

54.19.10 dpmi_dosmemmove

Synopsis: Move DOS memory

Declaration: `procedure dpmi_dosmemmove(sseg: Word; sofs: Word; dseg: Word; dofs: Word; count: LongInt)`

Visibility: default

Description: `dpmi_dosmemmove` moves `count` bytes from DOS memory `sseg,sofs` to `dseg,dofs`.

See also: `dpmi_dosmempout` (801), `dpmi_dosmemget` (801), `dpmi_dosmemfillchar` (800), `dpmi_dosmemfillword` (801)

54.19.11 dpmi_dosmempout

Synopsis: Move data from DPMI memory to DOS memory.

Declaration: `procedure dpmi_dosmempout(seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmempout` moves `count` bytes of data from `data` to the DOS memory location indicated by `seg` and `ofs`.

See also: `dpmi_dosmemget` (801), `dpmi_dosmemmove` (801), `dpmi_dosmemfillchar` (800), `dpmi_dosmemfillword` (801)

54.19.12 enable

Synopsis: Enable hardware interrupts

Declaration: `procedure enable`

Visibility: default

Description: Enables all hardware interrupts by executing a STI instruction.

Errors: None.

See also: `disable` (800)

54.19.13 free_ldt_descriptor

Synopsis: Free a descriptor

Declaration: `function free_ldt_descriptor(d: Word) : Boolean`

Visibility: default

Description: Frees a previously allocated descriptor.

Parameters:

desThe descriptor to be freed.

Return value: `True` if successful, `False` otherwise. Notes: After this call this selector is invalid and must not be used for any memory operations anymore. Each descriptor allocated with `allocate_ldt_descriptors` (795) must be freed individually with this function, even if it was previously allocated as a part of a contiguous array of descriptors.

For an example, see `allocate_ldt_descriptors` (795).

Errors: Check the `int31error` (795) variable.

See also: `allocate_ldt_descriptors` (795), `get_next_selector_increment_value` (806)

54.19.14 free_linear_addr_mapping

Synopsis: ? No description available

Declaration: `function free_linear_addr_mapping(linear_addr: DWord) : Boolean`

Visibility: default

54.19.15 free_memory_block

Synopsis: Free allocated memory block

Declaration: `function free_memory_block(blockhandle: LongInt) : Boolean`

Visibility: default

Description: Frees a previously allocated memory block.

Parameters:

blockhandlethe handle to the memory area to free.

Return value: `True` if successful, `false` otherwise. Notes: Frees memory that was previously allocated with `allocate_memory_block` (798) . This function doesn't free any descriptors mapped to this block, it's the application's responsibility.

Errors: Check `int31error` (795) variable.

See also: `allocate_memory_block` (798)

54.19.16 `free_rm_callback`

Synopsis: Release real mode callback.

Declaration: `function free_rm_callback(var intaddr: tseginfo) : Boolean`

Visibility: `default`

Description: Releases a real mode callback address that was previously allocated with the `get_rm_callback` (808) function.

Parameters:

intaddr real mode address buffer returned by `get_rm_callback` (808) .

Return values: `True` if successful, `False` if not

For an example, see `get_rm_callback` (808).

Errors: Check the `int31error` (795) variable.

See also: `set_rm_interrupt` (828), `get_rm_callback` (808)

54.19.17 `get_cs`

Synopsis: Get CS selector

Declaration: `function get_cs : Word`

Visibility: `default`

Description: Returns the cs selector.

Return value: The content of the cs segment register.

For an example, see `set_pm_interrupt` (826).

Errors: None.

See also: `get_ds` (804), `get_ss` (814)

54.19.18 `get_descriptor_access_right`

Synopsis: Get descriptor's access rights

Declaration: `function get_descriptor_access_right(d: Word) : LongInt`

Visibility: `default`

Description: Gets the access rights of a descriptor.

Parameters:

`dselector` to descriptor.

Return value: Access rights bit field.

Errors: Check the `int31error` ([795](#)) variable.

See also: `set_descriptor_access_right` ([825](#))

54.19.19 `get_dpmi_version`

Synopsis: Return DPMI information

Declaration: `function get_dpmi_version(var version: tdpmiversioninfo) : Boolean`

Visibility: default

Description: `get_dpmi_version` returns version information (Int \$31 Function \$0400) in `Version` and returns `True` if the information was retrieved successfully, `false` if the call failed.

Errors: The call returns `false` if the information could not be retrieved.

See also: `tdpmiversioninfo` ([831](#))

54.19.20 `get_ds`

Synopsis: Get DS Selector

Declaration: `function get_ds : Word`

Visibility: default

Description: Returns the ds selector.

Return values: The content of the ds segment register.

Errors: None.

See also: `get_cs` ([803](#)), `get_ss` ([814](#))

54.19.21 `get_exception_handler`

Synopsis: Return current exception handler

Declaration: `function get_exception_handler(e: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: `get_exception_handler` returns the exception handler for exception `E` in `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` ([825](#)), `get_pm_exception_handler` ([807](#))

54.19.22 get_linear_addr

Synopsis: Convert physical to linear address

Declaration: `function get_linear_addr(phys_addr: DWord; size: LongInt) : DWord`

Visibility: default

Description: Converts a physical address into a linear address.

Parameters:

phys_addr physical address of device.

size Size of region to map in bytes.

Return value: Linear address that can be used to access the physical memory. Notes: It's the applications responsibility to allocate and set up a descriptor for access to the memory. This function shouldn't be used to map real mode addresses.

Errors: Check the `int31error` (795) variable.

See also: `allocate_ldt_descriptors` (795), `set_segment_limit` (828), `set_segment_base_address` (828)

54.19.23 get_meminfo

Synopsis: Return information on the available memory

Declaration: `function get_meminfo(var meminfo: tmeminfo) : Boolean`

Visibility: default

Description: Returns information about the amount of available physical memory, linear address space, and disk space for page swapping.

Parameters:

meminfo buffer to fill memory information into.

Return values: Due to an implementation bug this function always returns `False`, but it always succeeds.

Remark Notes: Only the first field of the returned structure is guaranteed to contain a valid value. Any fields that are not supported by the DPMI host will be set by the host to `-1` (`0FFFFFFFFH`) to indicate that the information is not available. The size of the pages used by the DPMI host can be obtained with the `get_page_size` (807) function.

Errors: Check the `int31error` (795) variable.

See also: `get_page_size` (807)

Listing: `./examples/go32ex/meminfo.pp`

```
{ Shows how to obtain memory information via get_meminfo();

notice the checks if any of the returned information is invalid (-1)
}

uses
    go32;

var
```

```

        meminfo : tmeminfo;

begin
    get_meminfo(meminfo);
    if (int31error <> 0) then begin
        Writeln('Error getting DPML memory information... Halting');
        Writeln('DPML error number : ', int31error);
    end else begin
        with meminfo do begin
            Writeln('Largest available free block : ',
                available_memory div 1024, ' kbytes');
            if (available_pages <> -1) then
                Writeln('Maximum available unlocked pages : ',
                    available_pages);
            if (available_lockable_pages <> -1) then
                Writeln('Maximum lockable available pages : ',
                    available_lockable_pages);
            if (linear_space <> -1) then
                Writeln('Linear address space size : ',
                    linear_space*get_page_size div 1024, ' kbytes');
            if (unlocked_pages <> -1) then
                Writeln('Total number of unlocked pages : ',
                    unlocked_pages);
            if (available_physical_pages <> -1) then
                Writeln('Total number of free pages : ',
                    available_physical_pages);
            if (total_physical_pages <> -1) then
                Writeln('Total number of physical pages : ',
                    total_physical_pages);
            if (free_linear_space <> -1) then
                Writeln('Free linear address space : ',
                    free_linear_space*get_page_size div 1024,
                    ' kbytes');
            if (max_pages_in_paging_file <> -1) then
                Writeln('Maximum size of paging file : ',
                    max_pages_in_paging_file*get_page_size div 1024,
                    ' kbytes');
        end;
    end;
end.

```

54.19.24 get_next_selector_increment_value

Synopsis: Return selector increment value

Declaration: function get_next_selector_increment_value : Word

Visibility: default

Description: Returns the selector increment value when allocating multiple subsequent descriptors via allocate_ldt_descriptors (795).

Return value: Selector increment value.

Remark Notes: Because allocate_ldt_descriptors (795) only returns the selector for the first descriptor and so the value returned by this function can be used to calculate the selectors for subsequent descriptors in the array.

Errors: Check the int31error (795) variable.

See also: [allocate_ldt_descriptors \(795\)](#), [free_ldt_descriptor \(802\)](#)

54.19.25 `get_page_attributes`

Synopsis: ? No description available

Declaration: `function get_page_attributes(handle: DWord; offset: DWord;
pagecount: DWord; buf: pointer) : Boolean`

Visibility: default

54.19.26 `get_page_size`

Synopsis: Return the page size

Declaration: `function get_page_size : LongInt`

Visibility: default

Description: Returns the size of a single memory page.

Return value: Size of a single page in bytes.

Remark The returned size is typically 4096 bytes.

For an example, see [get_meminfo \(805\)](#).

Errors: Check the `int31error` ([795](#)) variable.

See also: [get_meminfo \(805\)](#)

54.19.27 `get_pm_exception_handler`

Synopsis: Get protected mode exception handler

Declaration: `function get_pm_exception_handler(e: Byte; var intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `get_pm_exception_handler` returns the protected mode exception handler for exception `E` in `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: [get_exception_handler \(804\)](#), [set_pm_exception_handler \(826\)](#)

54.19.28 `get_pm_interrupt`

Synopsis: Return protected mode interrupt handler

Declaration: `function get_pm_interrupt(vector: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Returns the address of a current protected mode interrupt handler.

Parameters:

vector interrupt handler number you want the address to.

intaddr buffer to store address.

Return values: `True` if successful, `False` if not.

Remark The returned address is a protected mode selector:offset address.

For an example, see `set_pm_interrupt` (826).

Errors: Check the `int31error` (795) variable.

See also: `set_pm_interrupt` (826), `set_rm_interrupt` (828), `get_rm_interrupt` (812)

54.19.29 `get_rm_callback`

Synopsis: Return real mode callback

Declaration: `function get_rm_callback(pm_func: pointer; const reg: trealregs;
var rmcb: tseginfo) : Boolean`

Visibility: default

Description: Returns a unique real mode `segment:offset` address, known as a "real mode callback," that will transfer control from real mode to a protected mode procedure.

Parameters:

pm_func pointer to the protected mode callback function.

regs supplied registers structure.

rmcb buffer to real mode address of callback function.

Return values: `True` if successful, otherwise `False`.

Remark Callback addresses obtained with this function can be passed by a protected mode program for example to an interrupt handler, device driver, or TSR, so that the real mode program can call procedures within the protected mode program or notify the protected mode program of an event. The contents of the supplied `regs` structure is not valid after function call, but only at the time of the actual callback.

Errors: Check the `int31error` (795) variable.

See also: `free_rm_callback` (803)

Listing: `./examples/go32ex/callback.pp`

*{ This program tries to give an example how to install a callback
procedure with the help of the GO32 unit.*

*It installs a callback which is supplied by any Microsoft compatible
mouse driver; at a specified mouse action this routine is called.
This callback must provide the services explained in the docs. The
main callback has to be in assembly, because it isn't possible to do
these services with pascal alone. But is written as general as
possible to provide maximum re-usability for other applications and
hence it simply calls a normal pascal user procedure in addition to
some initialization and callback service code, so you don't need to
hassle around with it too much.*

Notes to this user procedure :

**) it should not last too long to execute it*

**) ALL data and code touched in this proc MUST be locked BEFORE it is
called the first time*

Used software interrupt calls (rough descriptions, only what's used):

Int 33h 0000h – Microsoft Mouse driver : Reset mouse

Input : AX = 0000h

Return : AX = FFFFh if successful

BX = number of buttons (if FFFFh then mouse has 2 buttons)

Int 33h 0001h – Microsoft Mouse driver : Show mouse cursor

Input : AX = 0001h

Return : Mouse cursor shown on screen

Int 33h 0002h – Microsoft mouse driver : Hide mouse cursor

Input : AX = 0002h

Return : Hides mouse cursor again

Int 33h 000Ch – Microsoft mouse driver : Install user callback

Input : AX = 000Ch

CX = bit mask which tells the mouse driver at which actions the callback should be called, i.e. if button pressed, mouse moved etc.

(In this example it's set to 7Fh so that the callback is called on every action)

ES:EDX = pointer to callback procedure to call

Note : The registers structure supplied to the callback contains valid mouse data when the handler is called.

BX = button state information

CX = mouse X coordinates

DX = mouse Y coordinates

For more detailed information consult any mouse reference or interrupt list.

```

}
{$CALLING REGISTER}
{$ASMMODE ATT}
{$MODE FPC}

```

uses

```

crt,
go32;

```

const

```

{ the mouse interrupt number }
mouseint = $33;

```

var

```

{ supplied register structure to the callback }
mouse_regs : trealregs; external name '___v2prt0_rmcb_regs';
{ real mode 48 bit pointer to the callback }
mouse_seginfo : tseginfo;

```

var

```

{ number of mouse buttons }
mouse_numbuttons : longint;

{ bit mask for the action which triggered the callback }
mouse_action : word;
{ current mouse x and y coordinates }
mouse_x, mouse_y : Word;

```

```

    { button state }
    mouse_b : Word;

    { is an additional user procedure installed }
    userproc_installed : Longbool;
    { length of additional user procedure }
    userproc_length : Longint;
    { pointer to user proc }
    userproc_proc : pointer;

{ callback control handler, calls a user procedure if installed }

{ callback control handler, calls a user procedure if installed }
procedure callback_handler; assembler;
asm
    pushw %ds
    pushl %eax
    movw %es, %ax
    movw %ax, %ds

    { give control to user procedure if installed }
    cmpl $0, USERPROC_INSTALLED
    je .LNoCallback
    pushal
    movw DOSmemSELECTOR, %ax
    movw %ax, %fs { set fs for FPC }
    call *USERPROC_PROC
    popal
.LNoCallback:

    popl %eax
    popw %ds

    pushl %eax
    movl (%esi), %eax
    movl %eax, %es: 42(%edi) { adjust stack }
    addw $4, %es:46(%edi)
    popl %eax
    iret
end;
{ This dummy is used to obtain the length of the callback control
function. It has to be right after the callback_handler() function.
}
procedure mouse_dummy; begin end;

{ This is the supplied user procedure. In this case we simply
transform the virtual 640x200 mouse coordinate system to a 80x25
text mode coordinate system }
procedure textuserproc;
begin
    { the mouse_regs record contains the real mode registers now }
    mouse_b := mouse_regs.bx;
    mouse_x := (mouse_regs.cx shr 3) + 1;
    mouse_y := (mouse_regs.dx shr 3) + 1;
end;

{ Description : Installs the mouse callback control handler and
handles all necessary mouse related initialization.
}

```

```

    Input : userproc – pointer to a user procedure, nil if none
           userproclen – length of user procedure
}
procedure install_mouse(userproc : pointer; userproclen : longint);
var r : trealregs;
begin
    { mouse driver reset }
    r.eax := $0; realintr(mouseint, r);
    if (r.eax <> $FFFF) then begin
        WriteLn('No Microsoft compatible mouse found');
        WriteLn('A Microsoft compatible mouse driver is necessary ',
            'to run this example');
        halt;
    end;
    { obtain number of mouse buttons }
    if (r.bx = $ffff) then mouse_numbuttons := 2
    else mouse_numbuttons := r.bx;
    WriteLn(mouse_numbuttons, ' button Microsoft compatible mouse ',
        ' found. ');
    { check for additional user procedure, and install it if
    available }
    if (userproc <> nil) then begin
        userproc_proc := userproc;
        userproc_installed := true;
        userproc_length := userproclen;
        { lock code for user procedure }
        lock_code(userproc_proc, userproc_length);
    end else begin
        { clear variables }
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    { lock code & data which is touched in the callback handler }
    lock_data(mouse_x, sizeof(mouse_x));
    lock_data(mouse_y, sizeof(mouse_y));
    lock_data(mouse_b, sizeof(mouse_b));
    lock_data(mouse_action, sizeof(mouse_action));

    lock_data(userproc_installed, sizeof(userproc_installed));
    lock_data(userproc_proc, sizeof(userproc_proc));

    lock_data(mouse_regs, sizeof(mouse_regs));
    lock_data(mouse_seginf, sizeof(mouse_seginf));
    lock_code(@callback_handler,
        longint(@mouse_dummy) – longint(@callback_handler));
    { allocate callback (supply registers structure) }
    get_rm_callback(@callback_handler, mouse_regs, mouse_seginf);
    { install callback }
    r.eax := $0c; r.ecx := $7f;
    r.edx := longint(mouse_seginf.offset);
    r.es := mouse_seginf.segment;
    realintr(mouseint, r);
    { show mouse cursor }
    r.eax := $01;
    realintr(mouseint, r);
end;

```

```

procedure remove_mouse;
var
    r : trealregs;
begin
    { hide mouse cursor }
    r.eax := $02; realintr(mouseint, r);
    { remove callback handler }
    r.eax := $0c; r.ecx := 0; r.edx := 0; r.es := 0;
    realintr(mouseint, r);
    { free callback }
    free_rm_callback(mouse_seginf);
    { check if additional userproc is installed, and clean up if needed }
    if (userproc_installed) then begin
        unlock_code(userproc_proc, userproc_length);
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    { unlock used code & data }
    unlock_data(mouse_x, sizeof(mouse_x));
    unlock_data(mouse_y, sizeof(mouse_y));
    unlock_data(mouse_b, sizeof(mouse_b));
    unlock_data(mouse_action, sizeof(mouse_action));

    unlock_data(userproc_proc, sizeof(userproc_proc));
    unlock_data(userproc_installed, sizeof(userproc_installed));

    unlock_data(mouse_regs, sizeof(mouse_regs));
    unlock_data(mouse_seginf, sizeof(mouse_seginf));
    unlock_code(@callback_handler,
        longint(@mouse_dummy) - longint(@callback_handler));
    fillchar(mouse_seginf, sizeof(mouse_seginf), 0);
end;

begin
    install_mouse(@textuserproc, 400);
    Writeln('Press any key to exit...');
    while (not keypressed) do begin
        { write mouse state info }
        gotoxy(1, wherey);
        write('MouseX : ', mouse_x:2, ' MouseY : ', mouse_y:2,
            ' Buttons : ', mouse_b:2);
    end;
    remove_mouse;
end.

```

54.19.30 get_rm_interrupt

Synopsis: Get real mode interrupt vector

Declaration: `function get_rm_interrupt(vector: Byte; var intaddr: tseginf) : Boolean`

Visibility: default

Description: Returns the contents of the current machine's real mode interrupt vector for the specified interrupt.

Parameters:

vector interrupt vector number.

intaddr buffer to store real mode segment : offset address.

Return values: `True` if successful, `False` otherwise.

Remark The returned address is a real mode segment address, which isn't valid in protected mode.

Errors: Check the `int31error` (795) variable.

See also: `set_rm_interrupt` (828), `set_pm_interrupt` (826), `get_pm_interrupt` (807)

54.19.31 `get_run_mode`

Synopsis: Return current run mode

Declaration: `function get_run_mode : Word`

Visibility: `default`

Description: Returns the current mode your application runs with.

Return values: One of the constants used by this function.

Errors: None.

See also: `get_run_mode` (813)

Listing: `./examples/go32ex/getrunmd.pp`

```
{ Simply write a message according to the current environment }

uses
    go32;

begin
    { depending on the detected environment we simply write
    another message Note: in go32v2 this will always be rm_dpml. }

    case (get_run_mode) of
        rm_unknown :
            WriteLn ('Unknown environment found');
        rm_raw :
            WriteLn ('You are currently running in raw mode ',
                '(without HIMEM)');
        rm_xms :
            WriteLn ('You are currently using HIMEM.SYS only');
        rm_vcpi :
            WriteLn ('VCPI server detected. You''re using HIMEM and ',
                'EMM386');
        rm_dpml :
            WriteLn ('DPML detected. You''re using a DPML host like ',
                'a windows DOS box or CWSDPML');
    end;
end.
```

54.19.32 get_segment_base_address

Synopsis: Return base address from descriptor table

Declaration: `function get_segment_base_address(d: Word) : DWord`

Visibility: default

Description: Returns the 32-bit linear base address from the descriptor table for the specified segment.

Parameters:

dselector of the descriptor you want the base address of.

Return values: Linear base address of specified descriptor.

For an example, see `allocate_ldt_descriptors` (795).

Errors: Check the `int31error` (795) variable.

See also: `allocate_ldt_descriptors` (795), `set_segment_base_address` (828), `allocate_ldt_descriptors` (795), `set_segment_limit` (828), `get_segment_limit` (814)

54.19.33 get_segment_limit

Synopsis: Return segment limits from descriptor

Declaration: `function get_segment_limit(d: Word) : DWord`

Visibility: default

Description: Returns a descriptors segment limit.

Parameters:

dselector.

Return value: Limit of the descriptor in bytes.

Errors: Returns zero if descriptor is invalid.

See also: `allocate_ldt_descriptors` (795), `set_segment_limit` (828), `set_segment_base_address` (828), `get_segment_base_address` (814)

54.19.34 get_ss

Synopsis: Return SS selector

Declaration: `function get_ss : Word`

Visibility: default

Description: Returns the ss selector.

Return values: The content of the ss segment register.

Errors: None.

See also: `get_ds` (804), `get_cs` (803)

54.19.35 global_dos_alloc

Synopsis: Allocate DOS real mode memory

Declaration: `function global_dos_alloc(bytes: LongInt) : LongInt`

Visibility: default

Description: Allocates a block of dos real mode memory.

Parameters:

bytesize of requested real mode memory.

Return values: The low word of the returned value contains the selector to the allocated dos memory block, the high word the corresponding real mode segment value. The offset value is always zero. This function allocates memory from dos memory pool, i.e. memory below the 1 MB boundary that is controlled by dos. Such memory blocks are typically used to exchange data with real mode programs, TSRs, or device drivers. The function returns both the real mode segment base address of the block and one descriptor that can be used by protected mode applications to access the block. This function should only be used for temporary buffers to get real mode information (e.g. interrupts that need a data structure in ES:(E)DI), because every single block needs a unique selector. The returned selector should only be freed by a `global_dos_free` (817) call.

Errors: Check the `int31error` (795) variable.

See also: `global_dos_free` (817)

Listing: `./examples/go32ex/buffer.pp`

{ This program demonstrates the usage of DOS real mode memory by executing a software interrupt which needs a buffer to store data into. Because these interrupts are real mode funcs, the buffer must be located in real mode memory space (first MB of memory). Such memory can only be allocated by the global_dos_alloc() and global_dos_free() functions of the GO32 unit.

In more detail this program tries to detect a VESA 2.0 BIOS extension of your graphics card and outputs its version.

Here's the necessary interrupt call description:

*Int 10h 4f00h : VESA BIOS extension installation check
Input : AX = 4F00h
 ES:DI = pointer to 512 byte information buffer
Output : AX = 004Fh if successful
 ES:DI = pointer to filled buffer*

Buffer structure : (relevant to this example)

*must be 'VESA' in the first 4 chars of the buffer to be
 valid VBE version in the next word*

*Note : to request VBE 2.0 information, the first 4 bytes of the
 buffer must contain 'VBE2' prior to the interrupt call.*

*(this makes the problem a bit tougher; we first have to copy the
 buffer with the 'VBE2' id to dos memory...)*

}

uses

go32;

*{The following 2 functions are wrappers to the GO32
global_dos_alloc() and global_dos_free() functions to simplify their
usage }*

{ Function : dosalloc }

{ Input : size of a real mode location }

{ Output : selector and segment of a real mode location }

procedure dosalloc(**var** selector : word;
var segment : word; size : longint);

var

res : longint;

begin

{ try to allocate real mode memory }

res := global_dos_alloc(size);

*{ the lower 16 bits of the result contain the selector to the
allocated memory block }*

selector := word(res);

*{ the upper 16 bits contain the real mode segment address of
this block; the offset is always 0, so we don't need to return
this }*

segment := word(res shr 16);

end;

{ Function : dosfree }

{ Input : selector of a real mode block }

{ Output : none }

*{ Description : de-allocates a previously allocated real mode
memory }*

procedure dosfree(selector : word);

begin

{ call the GO32 function with the selector }

global_dos_free(selector);

end;

type

VBEInfoBuf = **packed record**

{ contains 'VESA' if successful }

Signature : **array**[0..3] **of** char;

Version : Word;

{ pad to 512 bytes length }

reserved : **array**[0..505] **of** byte;

end;

var

{ selector to our real mode buffer }

selector,

{ real mode segment address of buffer }

segment : Word;

{ register structure to issue a software interrupt }

r : treatregs;

infobuf : VBEInfoBuf;

begin

{ first we reset the registers and infobuf variable }

```

    fillchar(r, sizeof(r), 0);
    fillchar(infobuf, sizeof(VBEInfoBuf), 0);
    { allocate real mode memory }
    dosalloc(selector, segment, sizeof(VBEInfoBuf));
    { check if an error occurred during allocation }
    if (int31error <> 0) then begin
        Writeln('Error while allocating real mode memory, halting');
        halt;
    end;
    { request VBE 2.0 information, fill out information buffer }
    infobuf.Signature := 'VBE2';
    { copy buffer to the allocated real mode memory }
    dosmemput(segment, 0, infobuf, sizeof(infobuf));
    { issue the interrupt; remember : DI = 0 }
    r.ax := $4f00; r.es := segment;
    realintr($10, r);
    { copy buffer to our infobuf variable again }
    dosmemget(segment, 0, infobuf, sizeof(infobuf));
    { free allocated real mode memory, because we don't need it anymore }
    dosfree(selector);
    { check if interrupt call was successful }
    if (r.ax <> $4f) then begin
        { write message and exit, because the infobuf doesn't contain any useful data we could tell the user }
        Writeln('VBE BIOS extension not available, function call ', 'failed');
        halt;
    end;
    { check if buffer is valid }
    if (infobuf.signature[0] = 'V') and
        (infobuf.signature[1] = 'E') and
        (infobuf.signature[2] = 'S') and
        (infobuf.signature[3] = 'A') then begin
        Writeln('VBE version ', hi(infobuf.version), '.', lo(infobuf.version), ' detected');
    end;
end.

```

54.19.36 global_dos_free

Synopsis: Free DOS memory block

Declaration: function global_dos_free(selector: Word) : Boolean

Visibility: default

Description: Frees a previously allocated dos memory block.

Parameters:

selector selector to the dos memory block.

Return value: True if successful, False otherwise.

Remark The descriptor allocated for the memory block is automatically freed and hence invalid for further use. This function should only be used for memory allocated by global_dos_alloc (815).

For an example, see global_dos_alloc (815).

Errors: Check the `int31error` (795) variable.

See also: `global_dos_alloc` (815)

54.19.37 `inportb`

Synopsis: Read byte from I/O port

Declaration: `function inportb(port: Word) : Byte`

Visibility: default

Description: Reads 1 byte from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` (820), `inportw` (818), `inportl` (818)

54.19.38 `inportl`

Synopsis: Read longint from I/O port

Declaration: `function inportl(port: Word) : LongInt`

Visibility: default

Description: Reads 1 longint from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` (820), `inportb` (818), `inportw` (818)

54.19.39 `inportw`

Synopsis: Read word from I/O port

Declaration: `function inportw(port: Word) : Word`

Visibility: default

Description: Reads 1 word from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportw` (821), `inportb` (818), `inportl` (818)

54.19.40 lock_code

Synopsis: Lock code memory range

Declaration: `function lock_code(functionaddr: pointer; size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which is in the code segment selector.

Parameters:

functionaddr address of the function to be locked.

size size in bytes to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (808).

Errors: Check the `int31error` (795) variable.

See also: `lock_linear_region` (819), `lock_data` (819), `unlock_linear_region` (831), `unlock_data` (830), `unlock_code` (830)

54.19.41 lock_data

Synopsis: Lock data memory range

Declaration: `function lock_data(var data; size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which resides in the data segment selector.

Parameters:

data address of data to be locked.

size length of data to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (808).

Errors: Check the `int31error` (795) variable.

See also: `lock_linear_region` (819), `lock_code` (819), `unlock_linear_region` (831), `unlock_data` (830), `unlock_code` (830)

54.19.42 lock_linear_region

Synopsis: Lock linear memory region

Declaration: `function lock_linear_region(linearaddr: LongInt; size: LongInt)
: Boolean`

Visibility: default

Description: Locks a memory region to prevent swapping of it.

Parameters:

linearaddr the linear address of the memory are to be locked.

size size in bytes to be locked.

Return value: True if successful, False otherwise.

Errors: Check the `int31error` (795) variable.

See also: `lock_data` (819), `lock_code` (819), `unlock_linear_region` (831), `unlock_data` (830), `unlock_code` (830)

54.19.43 `map_device_in_memory_block`

Synopsis: Map a device into program's memory space

Declaration: `function map_device_in_memory_block(handle: DWord; offset: DWord; pagecount: DWord; device: DWord) : Boolean`

Visibility: default

Description: `map_device_in_memory_block` allows to map a device in memory. This function is a direct call of the extender. For more information about it's arguments, see the extender documentation.

54.19.44 `outportb`

Synopsis: Write byte to I/O port

Declaration: `procedure outportb(port: Word; data: Byte)`

Visibility: default

Description: Sends 1 byte of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

Errors: None.

See also: `inportb` (818), `outportl` (821), `outportw` (821)

Listing: `./examples/go32ex/outport.pp`

```
{ This example demonstrates the use of the outport functions.

It simply turns the PC's internal speaker on for 50 ms and off again
}
uses
    crt ,
    go32;

begin
    { turn on speaker }
    outportb($61, $ff);
    { wait a little bit }
    delay(50);
    { turn it off again }
    outportb($61, $0);

end.
```

54.19.45 outportl

Synopsis: Write longint to I/O port

Declaration: `procedure outportl(port: Word; data: LongInt)`

Visibility: default

Description: Sends 1 longint of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

For an example, see [outportb \(820\)](#).

Errors: None.

See also: [inportl \(818\)](#), [outportw \(821\)](#), [outportb \(820\)](#)

54.19.46 outportw

Synopsis: Write word to I/O port

Declaration: `procedure outportw(port: Word; data: Word)`

Visibility: default

Description: Sends 1 word of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

For an example, see [outportb \(820\)](#).

Errors: None.

See also: [inportw \(818\)](#), [outportl \(821\)](#), [outportb \(820\)](#)

54.19.47 realintr

Synopsis: Simulate interrupt

Declaration: `function realintr(intnr: Word; var regs: trealregs) : Boolean`

Visibility: default

Description: Simulates an interrupt in real mode.

Parameters:

intnr interrupt number to issue in real mode.

regs registers data structure.

Return values: The supplied registers data structure contains the values that were returned by the real mode interrupt. `True` if successful, `False` if not.

Remark The function transfers control to the address specified by the real mode interrupt vector of `intr`. The real mode handler must return by executing an `IRET`.

Errors: Check the `int31error` (795) variable.

Listing: `./examples/go32ex/flags.pp`

```
{ This example demonstrates the use of the flag constants in
conjunction with an interrupt call

In detail it checks if APM (advanced power management) is
available.

Int 15h 5300h – APM specification : Installation check
Input : AX = 5300h
        BX = device id of system BIOS (= 0000h)
Return : Carry clear if successful
        AH = major version (BCD)
        AL = minor version (BCD)
}
```

```
uses
    go32;

var
    r : trealregs;

begin
    { set register values and issue real mode interrupt call }
    r.ax := $5300;
    r.bx := 0;
    realintr($15, r);
    { check if carry clear and write a suited message }
    if ((r.flags and carryflag)=0) then begin
        Writeln('APM v', (r.ah and $f), '.',
                (r.al shr 4), (r.al and $f), ' detected');
    end else
        Writeln('APM not present');
end.
```

54.19.48 request_linear_region

Synopsis: Request linear address region.

Declaration: `function request_linear_region(linearaddr: LongInt; size: LongInt; var blockhandle: LongInt) : Boolean`

Visibility: default

Description: `request_linear_region` requests a linear range of addresses of size `Size`, starting at `linearaddr`. If successful, `True` is returned, and a handle to the address region is returned in `blockhandle`.

Errors: On error, `False` is returned.

54.19.49 segment_to_descriptor

Synopsis: Map segment address to descriptor

Declaration: `function segment_to_descriptor(seg: Word) : Word`

Visibility: default

Description: Maps a real mode segment (paragraph) address onto an descriptor that can be used by a protected mode program to access the same memory.

Parameters:

seg the real mode segment you want the descriptor to.

Return values: Descriptor to real mode segment address.

Remark The returned descriptors limit will be set to 64 kB. Multiple calls to this function with the same segment address will return the same selector. Descriptors created by this function can never be modified or freed. Programs which need to examine various real mode addresses using the same selector should use the function `allocate_ldt_descriptors` (795) and change the base address as necessary.

For an example, see `seg_fillchar` (823).

Errors: Check the `int31error` (795) variable.

See also: `allocate_ldt_descriptors` (795), `free_ldt_descriptor` (802), `set_segment_base_address` (828)

54.19.50 seg_fillchar

Synopsis: Fill segment with byte value

Declaration: `procedure seg_fillchar(seg: Word; ofs: LongInt; count: LongInt; c: Char)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

seg selector to memory area.

ofs offset to memory.

count number of bytes to set.

c byte data which is set.

Return values: None.

Notes: No range check is done in any way.

Errors: None.

See also: `seg_move` (825), `seg_fillword` (824), `dosmemfillchar` (791), `dosmemfillword` (791), `dosmemget` (791), `dosmemput` (792), `dosmemmove` (792)

Listing: `./examples/go32ex/vgasel.pp`

{ This example demonstrates the use of the segment_to_descriptor() function .

It switches to VGA mode 13h (320x200x256 color), creates a selector to the memory (based at \$A000:0000), clears this memory with color 15 (white) and waits until the enter key is pressed }

uses go32;

var

 vgasel : Word;
 r : treatregs;

begin

{ set VGA mode 13h }
 r.eax := \$13; realintr(\$10, r);
 { allocate descriptor to VGA memory quickly; it could be done with allocate_ldt_descriptors() too, but we would have to initialize it by ourselves... unlike segment_to_descriptor() which automatically sets the limit and the base address correctly }
 vgasel := segment_to_descriptor(\$A000);
 { simply fill the screen memory with color 15 }
 seg_fillchar(vgasel, 0, 64000, #15);
 { wait for a return press }
 readln;
 { back to text mode }
 r.eax := \$3; realintr(\$10, r);
 { don't deallocate vgasel, that can't be done }

end.

54.19.51 seg_fillword

Synopsis: Fill segment with word value

Declaration: `procedure seg_fillword(seg: Word; ofs: LongInt; count: LongInt; w: Word)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

seg selector to memory area.

ofs offset to memory.

count number of words to set.

w word data which is set.

Return values: None.

Notes: No range check is done in any way.

For an example, see `allocate_ldt_descriptors` ([795](#)).

Errors: None.

See also: `seg_move` ([825](#)), `seg_fillchar` ([823](#)), `dosmemfillchar` ([791](#)), `dosmemfillword` ([791](#)), `dosmemget` ([791](#)), `dosmemput` ([792](#)), `dosmemmove` ([792](#))

54.19.52 seg_move

Synopsis: Move data between 2 locations

Declaration: `procedure seg_move(sseg: Word; source: LongInt; dseg: Word;
dest: LongInt; count: LongInt)`

Visibility: default

Description: Copies data between two memory locations.

Parameters:

ssegsource selector.

sourcesource offset.

dsegdestination selector.

destdestination offset.

countsize in bytes to copy.

Return values: None.

Remark Overlapping is only checked if the source selector is equal to the destination selector. No range check is done.

For an example, see `allocate_ldt_descriptors` (795).

Errors: None.

See also: `seg_fillchar` (823), `seg_fillword` (824), `dosmemfillchar` (791), `dosmemfillword` (791), `dosmemget` (791), `dosmemput` (792), `dosmemmove` (792)

54.19.53 set_descriptor_access_right

Synopsis: Set access rights to memory descriptor

Declaration: `function set_descriptor_access_right(d: Word; w: Word) : Boolean`

Visibility: default

Description: `set_descriptor_access_right` sets the access rights for descriptor `d` to `w`

54.19.54 set_exception_handler

Synopsis: Set exception handler

Declaration: `function set_exception_handler(e: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `set_exception_handler` sets the exception handler for exception `E` to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `get_exception_handler` (804), `set_pm_exception_handler` (826)

54.19.55 set_page_attributes

Synopsis: ? No description available

Declaration: `function set_page_attributes(handle: DWord; offset: DWord;
pagecount: DWord; buf: pointer) : Boolean`

Visibility: default

54.19.56 set_pm_exception_handler

Synopsis: Set protected mode exception handler

Declaration: `function set_pm_exception_handler(e: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `set_pm_exception_handler` sets the protected mode exception handler for exception E to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` (825), `get_pm_exception_handler` (807)

54.19.57 set_pm_interrupt

Synopsis: Set protected mode interrupt handler

Declaration: `function set_pm_interrupt(vector: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: Sets the address of the protected mode handler for an interrupt.

Parameters:

vector number of protected mode interrupt to set.

intaddr selector:offset address to the interrupt vector.

Return values: `True` if successful, `False` otherwise.

Remark The address supplied must be a valid `selector:offset` protected mode address.

Errors: Check the `int31error` (795) variable.

See also: `get_pm_interrupt` (807), `set_rm_interrupt` (828), `get_rm_interrupt` (812)

Listing: `./examples/go32ex/intpm.pp`

*{ This example shows how to redirect a software interrupt by
changing the protected mode handler of the DPMI host.*

*In more detail it hooks interrupt 1Ch which is called every
time the timer interrupt (int 08) is executed. This is the
preferred way to hook the timer, because int 1Ch is a software
interrupt which doesn't need so much initialization stuff
compared to hooking a hardware interrupt.
}*

uses

```

    crt ,
    go32;

const
    { interrupt number we want to hook }
    int1c = $1c;

var
    { 48 bit pointer to old interrupt handler }
    oldint1c : tseinfo;
    { 48 bit pointer to new interrupt handler }
    newint1c : tseinfo;

    { increased every time the interrupt is called }
    int1c_counter : Longint;

    { the current data selector }
    int1c_ds : Word; external name '___v2prt0_ds_alias';

    { the actual handler code }
procedure int1c_handler; assembler;
asm
    cli
    { save all registers }
    pushw %ds
    pushw %ax
    { prepare segment registers for FPC procedure }
    movw %cs:int1c_ds, %ax
    movw %ax, %ds
    { simply increase the counter by one }
    incl int1c_counter
    { restore registers }
    popw %ax
    popw %ds
    sti
    iret
end;

var i : Longint;

begin
    { insert right handler data into new handler variable }
    newint1c.offset := @int1c_handler;
    newint1c.segment := get_cs;
    { get the old handler }
    get_pm_interrupt(int1c, oldint1c);
    Writeln('— Press any key to exit —');
    { set new handler }
    set_pm_interrupt(int1c, newint1c);
    { write the number of interrupts occurred }
    while (not keypressed) do begin
        gotoxy(1, wherey);
        write('Number of interrupts occurred : ', int1c_counter);
    end;
    { restore old handler }
    set_pm_interrupt(int1c, oldint1c);
end.

```

54.19.58 set_rm_interrupt

Synopsis: Set real mode interrupt handler

Declaration: `function set_rm_interrupt(vector: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: Sets a real mode interrupt handler.

Parameters:

vector the interrupt vector number to set.

intaddr address of new interrupt vector.

Return values: True if successful, otherwise False.

Remark The address supplied MUST be a real mode segment address, not a `selector:offset` address. So the interrupt handler must either reside in dos memory (below 1 Mb boundary) or the application must allocate a real mode callback address with `get_rm_callback` (808).

Errors: Check the `int31error` (795) variable.

See also: `get_rm_interrupt` (812), `set_pm_interrupt` (826), `get_pm_interrupt` (807), `get_rm_callback` (808)

54.19.59 set_segment_base_address

Synopsis: Set descriptor's base address

Declaration: `function set_segment_base_address(d: Word; s: DWord) : Boolean`

Visibility: default

Description: Sets the 32-bit linear base address of a descriptor.

Parameters:

d selector.

s new base address of the descriptor.

Errors: Check the `int31error` (795) variable.

See also: `allocate_ldt_descriptors` (795), `get_segment_base_address` (814), `allocate_ldt_descriptors` (795), `set_segment_limit` (828), `get_segment_base_address` (814), `get_segment_limit` (814)

54.19.60 set_segment_limit

Synopsis: Set descriptor limit

Declaration: `function set_segment_limit(d: Word; s: DWord) : Boolean`

Visibility: default

Description: Sets the limit of a descriptor.

Parameters:

d selector.

s new limit of the descriptor.

Return values: Returns `True` if successful, else `False`.

Remark The new limit specified must be the byte length of the segment - 1. Segment limits bigger than or equal to 1MB must be page aligned, they must have the lower 12 bits set.

For an example, see `allocate_ldt_descriptors` (795).

Errors: Check the `int31error` (795) variable.

See also: `allocate_ldt_descriptors` (795), `set_segment_base_address` (828), `get_segment_limit` (814), `set_segment_limit` (828)

54.19.61 `tb_offset`

Synopsis: Return DOS transfer buffer offset

Declaration: `function tb_offset : LongInt`

Visibility: default

Description: `tb_offset` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (830), `tb_segment` (829), `tb_size` (829)

54.19.62 `tb_segment`

Synopsis: Return DOS transfer buffer segment

Declaration: `function tb_segment : LongInt`

Visibility: default

Description: `tb_segment` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (830), `tb_offset` (829), `tb_size` (829)

54.19.63 `tb_size`

Synopsis: Return DOS transfer memory buffer size

Declaration: `function tb_size : LongInt`

Visibility: default

Description: Returns the size of the pre-allocated dos memory buffer.

Return values: The size of the pre-allocated dos memory buffer. This block always seems to be 16k in size, but don't rely on this.

Errors: None.

See also: `transfer_buffer` (830), `copyfromdos` (799), `copytodos` (799)

54.19.64 transfer_buffer

Synopsis: Return offset of DOS transfer buffer

Declaration: `function transfer_buffer : LongInt`

Visibility: default

Description: `transfer_buffer` returns the offset of the transfer buffer.

Errors: None.

See also: `tb_size` ([829](#))

54.19.65 unlock_code

Synopsis: Unlock code segment

Declaration: `function unlock_code(functionaddr: pointer; size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the code segment selector.

Parameters:

functionaddr address of function to be unlocked.

size size bytes to be unlocked.

Return value: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` ([808](#)).

Errors: Check the `int31error` ([795](#)) variable.

See also: `unlock_linear_region` ([831](#)), `unlock_data` ([830](#)), `lock_linear_region` ([819](#)), `lock_data` ([819](#)), `lock_code` ([819](#))

54.19.66 unlock_data

Synopsis: Unlock data segment

Declaration: `function unlock_data(var data; size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the data segment selector.

Parameters:

data address of memory to be unlocked.

size size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` ([808](#)).

Errors: Check the `int31error` ([795](#)) variable.

See also: `unlock_linear_region` ([831](#)), `unlock_code` ([830](#)), `lock_linear_region` ([819](#)), `lock_data` ([819](#)), `lock_code` ([819](#))

54.19.67 unlock_linear_region

Synopsis: Unlock linear memory region

Declaration: `function unlock_linear_region(linearaddr: LongInt; size: LongInt)
: Boolean`

Visibility: default

Description: Unlocks a previously locked linear region range to allow it to be swapped out again if needed.

Parameters:

linearaddr linear address of the memory to be unlocked.

size size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

Errors: Check the `int31error` (795) variable.

See also: `unlock_data` (830), `unlock_code` (830), `lock_linear_region` (819), `lock_data` (819), `lock_code` (819)

54.20 tdpmiversioninfo

```
tdpmiversioninfo = record  
  major : Byte;  
  minor : Byte;  
  flags  
  : Word;  
  cpu : Byte;  
  master_pic : Byte;  
  slave_pic : Byte;  
end
```

`tdpmiversioninfo` describes the dpmi version information, as returned by `get_dpmi_version` (804). The CPU field can have the following values:

\$02H 80286

\$03H 80386

\$04H 80486

\$05H- Newer than 80486

The flags field is a bitmask with the following bits:

0 0 for 16 bit DPML, 1 for 32-bit

1 0 for virtual 86 mode for reflected interrupts, 1 for return to real mode.

2 0 for no virtual memory support, 1 for virtual memory support.

54.21 tmeminfo

```
tmeminfo = record
  available_memory : LongInt;
  available_pages
    : LongInt;
  available_lockable_pages : LongInt;
  linear_space
    : LongInt;
  unlocked_pages : LongInt;
  available_physical_pages
    : LongInt;
  total_physical_pages : LongInt;
  free_linear_space
    : LongInt;
  max_pages_in_paging_file : LongInt;
  reserved0 : LongInt
;
  reserved1 : LongInt;
  reserved2 : LongInt;
end
```

tmeminfo Holds information about the memory allocation, etc.

NOTE: The value of a field is -1 (0fffffffh) if the value is unknown, it's only guaranteed, that available_memory contains a valid value. The size of the pages can be determined by the get_page_size() function.

54.22 tseginfo

```
tseginfo = record
  offset : pointer;
  segment : Word;
end
```

This record is used to store a full 48-bit pointer. This may be either a protected mode selector:offset address or in real mode a segment:offset address, depending on application.

See also: Selectors and descriptors, dos memory access, Interrupt redirection

Chapter 55

Reference for unit 'gpm'

55.1 Used units

Table 55.1: Used units by unit 'gpm'

Name	Page
BaseUnix	141
System	1339

55.2 Overview

The GPM unit implements an interface to `libgpm`, the console program for mouse handling. This unit was created by Peter Vreman, and is only available on Linux.

When this unit is used, your program is linked to the C libraries, so you must take care of the C library version. Also, it will only work with version 1.17 or higher of the `libgpm` library.

55.3 Constants, types and variables

55.3.1 Constants

`GPM_BOT` = 2

Bottom of area.

`GPM_B_LEFT` = 4

Left mouse button identifier.

`GPM_B_MIDDLE` = 2

Middle mouse button identifier.

`GPM_B_RIGHT` = 1

Right mouse button identifier.

GPM_DOUBLE = 32

Mouse double click event.

GPM_DOWN = 4

Mouse button down event.

GPM_DRAG = 2

Mouse drag event.

GPM_ENTER = 512

Enter area event.

GPM_HARD = 256

?

GPM_LEAVE = 1024

Leave area event.

GPM_LEFT = 4

Left side of area.

GPM_MAGIC = \$47706D4C

Constant identifying GPM in Gpm_Open ([840](#)).

GPM_MFLAG = 128

Motion flag.

GPM_MOVE = 1

Mouse move event.

GPM_NODE_CTL = GPM_NODE_DEV

Control socket

GPM_NODE_DEV = '/dev/gpmctl'

Device socket filename

GPM_NODE_DIR = _PATH_VARRUN

Where to write socket.

```
GPM_NODE_DIR_MODE = 0775
```

Mode of socket.

```
GPM_NODE_FIFO = '/dev/gpmdata'
```

FIFO name

```
GPM_NODE_PID = '/var/run/gpm.pid'
```

Name of PID file.

```
GPM_RGT = 8
```

Right side of area.

```
GPM_SINGLE = 16
```

Mouse single click event.

```
GPM_TOP = 1
```

Top of area.

```
GPM_TRIPLE = 64
```

Mouse triple click event.

```
GPM_UP = 8
```

Mouse button up event.

```
_PATH_DEV = '/dev/'
```

Location of `/dev` directory.

```
_PATH_VARRUN = '/var/run/'
```

Location of run PID files directory.

55.3.2 Types

```
Pgpmconnect = Pgpm_connect
```

Pointer to `TGpmConnect` (836) record.

```
Pgpmevent = Pgpm_event
```

Pointer to TGpmEvent (836) record

```
Pgpmroi = Pgpm_roi
```

Pointer to TGpmRoi (836) record.

```
Pgpm_connect = ^TGpm_connect
```

Pointer to TGpm_Connect (843) record.

```
Pgpm_event = ^Tgpm_event
```

Pointer to TGpm_Event (843) record

```
Pgpm_roi = ^Tgpm_roi
```

Pointer to Tgpm_roi (844) record.

```
Tgpmconnect = Tgpm_connect
```

Alias for TGpm_Connect (843) record.

```
TGpmEtype = LongInt
```

Type for event type.

```
Tgpmevent = Tgpm_event
```

Alias for TGPM_EVent (843) record

```
TGpmHandler = function(var event: Tgpmevent; clientdata: pointer)
    : LongInt
```

Mouse event handler callback.

```
TGpmMargin = LongInt
```

Type to hold area margin.

```
Tgpmroi = Tgpm_roi
```

Alias for TGpm_roi (844)Record

55.3.3 Variables

```
gpm_current_roi : Pgpm_roi
```

Internal gpm library variable. Do not use.

```
gpm_handler : TGpmHandler
```

Internal gpm library variable. Do not use.

`gpm_roi : Pgpm_roi`

Internal gpm library variable. Do not use.

`gpm_roi_data : pointer`

Internal gpm library variable. Do not use.

`gpm_roi_handler : TGpmHandler`

Internal gpm library variable. Do not use.

55.4 Procedures and functions

55.4.1 Gpm_AnyDouble

Synopsis: Check whether event has double click event.

Declaration: `function Gpm_AnyDouble(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnyDouble` returns True if `EventType` contains the `GPM_DOUBLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (842), `Gpm_AnySingle` (837), `Gpm_StrictDouble` (842), `Gpm_StrictTriple` (842), `Gpm_AnyTriple` (837)

55.4.2 Gpm_AnySingle

Synopsis: Check whether event has a single click event.

Declaration: `function Gpm_AnySingle(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns True if `EventType` contains the `GPM_SINGLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (842), `Gpm_AnyDouble` (837), `Gpm_StrictDouble` (842), `Gpm_StrictTriple` (842), `Gpm_AnyTriple` (837)

55.4.3 Gpm_AnyTriple

Synopsis: Check whether event has a triple click event.

Declaration: `function Gpm_AnyTriple(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns `True` if `EventType` contains the `GPM_TRIPLE` flag, `False` otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (842), `Gpm_AnyDouble` (837), `Gpm_StrictDouble` (842), `Gpm_StrictTriple` (842), `Gpm_AnySingle` (837)

55.4.4 `gpm_close`

Synopsis: Close connection to GPM server.

Declaration: `function gpm_close : LongInt`

Visibility: `default`

Description: `Gpm_Close` closes the current connection, and pops the connection stack; this means that the previous connection becomes active again.

The function returns `-1` if the current connection is not the last one, and it returns `0` if the current connection is the last one.

for an example, see `Gpm_GetEvent` (839).

Errors: None.

See also: `Gpm_Open` (840)

55.4.5 `gpm_fitvalues`

Synopsis: Change coordinates to fit physical screen.

Declaration: `function gpm_fitvalues(var x: LongInt; var y: LongInt) : LongInt`

Visibility: `default`

Description: `Gpm_fitValues` changes `x` and `y` so they fit in the visible screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValuesM` (838)

55.4.6 `gpm_fitvaluesM`

Synopsis: Change coordinates to fit margin.

Declaration: `function gpm_fitvaluesM(var x: LongInt; var y: LongInt; margin: LongInt) : LongInt`

Visibility: `default`

Description: `Gpm_FitValuesM` changes `x` and `y` so they fit in the margin indicated by `margin`. If `margin` is `-1`, then the values are fitted to the screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValues` (838)

55.4.7 gpm_getevent

Synopsis: Get event from event queue.

Declaration: `function gpm_getevent (var event: Tgpm_event) : LongInt`

Visibility: default

Description: `Gpm_GetEvent` Reads an event from the file descriptor `gpm_fd`. This file is only for internal use and should never be called by a client application.

It returns 1 on success, and -1 on failure.

Errors: On error, -1 is returned.

See also: `Gpm_GetSnapshot` ([840](#))

Listing: `./examples/gpmex/gpmex.pp`

```

program gpmex;

{
  Example program to demonstrate the use of the gpm unit.
}

uses gpm;

var
  connect : TGPMConnect;
  event : tgpmevent;

begin
  connect.EventMask:=GPM_MOVE or GPM_DRAG or GPM_DOWN or GPM_UP;
  connect.DefaultMask:=0;
  connect.MinMod:=0;
  connect.MaxMod:=0;
  if Gpm_Open(connect,0)=-1 then
    begin
      WriteLn('No mouse handler present. ');
      Halt(1);
    end;
  WriteLn('Click right button to end. ');
  Repeat
    gpm_getevent(Event);
    With Event do
      begin
        Write('Pos = (' ,X, ', ',Y, ') Buttons : ( ');
        if (buttons and Gpm_b_left)<>0 then
          write('left ');
        if (buttons and Gpm_b_right)<>0 then
          write('right ');
        if (buttons and Gpm_b_middle)<>0 then
          Write('middle ');
        Write(') Event : ');
        Case EventType and $F of
          GPM_MOVE: write('Move ');
          GPM_DRAG: write('Drag ');
          GPM_DOWN: write('Down ');
          GPM_UP: write('Up ');
        end;
      end;
    until Event = GPM_UP;
  end;

```

```

        WriteLn ;
    end ;
    Until (Event.Buttons and gpm_b_right) <> 0;
    gpm_close ;
end .

```

55.4.8 gpm_getsnapshot

Synopsis: Return servers' current image of mouse state.

Declaration: `function gpm_getsnapshot(eptr: Pgpmevent) : LongInt`
`function gpm_getsnapshot(var eptr: Tgpmevent) : LongInt`

Visibility: default

Description: `Gpm_GetSnapshot` returns the picture that the server has of the current situation in `Event`. This call will not read the current situation from the mouse file descriptor, but returns a buffered version.

The function returns the number of mouse buttons, or -1 if this information is not available.

Errors: None.

See also: `Gpm_GetEvent` ([839](#))

55.4.9 gpm_lowerroi

Synopsis: Lower a region of interest in the stack.

Declaration: `function gpm_lowerroi(which: Pgpm_roi; after: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_LowerRoi` lowers the region of interest which after `after`. If `after` is `Nil`, the region of interest is moved to the bottom of the stack.

The return value is the new top of the region-of-interest stack.

Errors: None.

See also: `Gpm_RaiseRoi` ([841](#)), `Gpm_PopRoi` ([841](#)), `Gpm_PushRoi` ([841](#))

55.4.10 gpm_open

Synopsis: Open connection to GPM server.

Declaration: `function gpm_open(var conn: Tgpm_connect; flag: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Open` opens a new connection to the mouse server. The connection is described by the fields of the `conn` record of type `TGPMConnect` ([836](#)).

if `Flag` is 0, then the application only receives events that come from its own terminal device. If it is negative it will receive all events. If the value is positive then it is considered a console number to which to connect.

The return value is -1 on error, or the file descriptor used to communicate with the client. Under an X-Term the return value is -2.

for an example, see `Gpm_GetEvent` ([839](#)).

Errors: On Error, the return value is -1.

See also: [Gpm_Open \(840\)](#)

55.4.11 gpm_poproi

Synopsis: Pop region of interest from the stack.

Declaration: `function gpm_poproi(which: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_PopRoi` pops the topmost region of interest from the stack. It returns the next element on the stack, or `Nil` if the current element was the last one.

Errors: None.

See also: [Gpm_RaiseRoi \(841\)](#), [Gpm_LowerRoi \(840\)](#), [Gpm_PushRoi \(841\)](#)

55.4.12 gpm_pushroi

Synopsis: Push region of interest on the stack.

Declaration: `function gpm_pushroi(x1: LongInt; y1: LongInt; x2: LongInt;
y2: LongInt; mask: LongInt; fun: TGpmHandler;
xtradata: pointer) : Pgpm_roi`

Visibility: default

Description: `Gpm_PushRoi` puts a new *region of interest* on the stack. The region of interest is defined by a rectangle described by the corners `(X1, Y1)` and `(X2, Y2)`.

The mask describes which events the handler {fun} will handle; `ExtraData` will be put in the `xtradata` field of the {TGPM_Roi} record passed to the fun handler.

Errors: None.

See also: [Gpm_RaiseRoi \(841\)](#), [Gpm_PopRoi \(841\)](#), [Gpm_LowerRoi \(840\)](#)

55.4.13 gpm_raiseroi

Synopsis: Raise region of interest in the stack.

Declaration: `function gpm_raiseroi(which: Pgpm_roi; before: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_RaiseRoi` raises the *region of interest* which till it is on top of region before. If before is nil then the region is put on top of the stack. The returned value is the top of the stack.

Errors: None.

See also: [Gpm_PushRoi \(841\)](#), [Gpm_PopRoi \(841\)](#), [Gpm_LowerRoi \(840\)](#)

55.4.14 **gpm_repeat**

Synopsis: Check for presence of mouse event.

Declaration: `function gpm_repeat (millisec: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Repeat` returns 1 if no mouse event arrives in the next `millisec` milliseconds, it returns 0 otherwise.

Errors: None.

See also: `Gpm_GetEvent` ([839](#))

55.4.15 **Gpm_StrictDouble**

Synopsis: Check whether event contains only a double-click event.

Declaration: `function Gpm_StrictDouble (EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictDouble` returns true if `EventType` contains only a doubleclick event, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` ([842](#)), `Gpm_AnyTriple` ([837](#)), `Gpm_AnyDouble` ([837](#)), `Gpm_StrictTriple` ([842](#)), `Gpm_AnySingle` ([837](#))

55.4.16 **Gpm_StrictSingle**

Synopsis: Check whether event contains only a single-click event.

Declaration: `function Gpm_StrictSingle (EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictDouble` returns True if `EventType` contains only a singleclick event, False otherwise.

Errors: None.

See also: `Gpm_AnyTriple` ([837](#)), `Gpm_StrictDouble` ([842](#)), `Gpm_AnyDouble` ([837](#)), `Gpm_StrictTriple` ([842](#)), `Gpm_AnySingle` ([837](#))

55.4.17 **Gpm_StrictTriple**

Synopsis: Check whether event contains only a triple-click event.

Declaration: `function Gpm_StrictTriple (EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictTriple` returns true if `EventType` contains only a triple click event, False otherwise.

Errors: None.

See also: `Gpm_AnyTriple` ([837](#)), `Gpm_StrictDouble` ([842](#)), `Gpm_AnyDouble` ([837](#)), `Gpm_StrictSingle` ([842](#)), `Gpm_AnySingle` ([837](#))

55.5 Tgpm_connect

```
Tgpm_connect = record
  eventMask : Word;
  defaultMask : Word;
  minMod : Word;
  maxMod : Word;
  pid : LongInt;
  vc : LongInt;
end
```

GPM server connection information.

55.6 Tgpm_event

```
Tgpm_event = record
  buttons : Byte;
  modifiers : Byte;
  vc : Word
;
  dx : Word;
  dy : Word;
  x : Word;
  y : Word;
  EventType :
  TGpmEtype;
  clicks : LongInt;
  margin : TGpmMargin;
  wdx : Word
;
  wdy : Word;
end
```

Tgpm_event describes the events that are reported by GPM.

55.7 Tgpm_roi

```
Tgpm_roi = record
  xmin : Integer;
  xmax : Integer;
  ymin : Integer
;
  ymax : Integer;
  minmod : Word;
  maxmod : Word;
  eventmask
  : Word;
  owned : Word;
  handler : TGpmHandler;
  clientdata : pointer
;
```

```
prev : Pgpm_roi;  
next : Pgpm_roi;  
end
```

Record used to define regions of interest.

Chapter 56

Reference for unit 'Graph'

56.1 Used units

Table 56.1: Used units by unit 'Graph'

Name	Page
System	1339

56.2 Overview

This document describes the `GRAPH` unit for Free Pascal, for all platforms. The unit was first written for dos by Florian Klaempfl, but was later completely rewritten by Carl-Eric Codere to be completely portable. The unit is provided for compatibility only: It is recommended to use more modern graphical systems. The graph unit will allow to recompile old programs. They will work to some extent, but if the application has heavy graphical needs, it's recommended to use another set of graphical routines, suited to the platform the program should work on.

56.3 Categorized functions: Text and font handling

Functions to set texts on the screen.

Table 56.2:

Name	Description
GetTextSettings (884)	Get current text settings
InstallUserFont (887)	Install a new font
OutText (888)	Write text at current cursor position
OutTextXY (876)	Write text at coordinates X,Y
RegisterBGIFont (890)	Register a new font
SetTextJustify (893)	Set text justification
SetTextStyle (893)	Set text style
SetUserCharSize (894)	Set text size
TextHeight (895)	Calculate height of text
TextWidth (895)	Calculate width of text

56.4 Categorized functions: Filled drawings

Functions for drawing filled regions.

Table 56.3:

Name	Description
Bar3D (877)	Draw a filled 3D-style bar
Bar (877)	Draw a filled rectangle
FloodFill (879)	Fill starting from coordinate
FillEllipse (879)	Draw a filled ellipse
FillPoly (879)	Draw a filled polygon
GetFillPattern (881)	Get current fill pattern
GetFillSettings (881)	Get current fill settings
SetFillPattern (891)	Set current fill pattern
SetFillStyle (891)	Set current fill settings

56.5 Categorized functions: Drawing primitives

Functions for simple drawing.

Table 56.4:

Name	Description
Arc (877)	Draw an arc
Circle (874)	Draw a complete circle
DrawPoly (878)	Draw a polygon with N points
Ellipse (879)	Draw an ellipse
GetArcCoords (880)	Get arc coordinates
GetLineSettings (882)	Get current line drawing settings
Line (876)	Draw line between 2 points
LineRel (887)	Draw line relative to current position
LineTo (888)	Draw line from current position to absolute position
MoveRel (888)	Move cursor relative to current position
MoveTo (888)	Move cursor to absolute position
PieSlice (889)	Draw a pie slice
PutPixel (876)	Draw 1 pixel
Rectangle (889)	Draw a non-filled rectangle
Sector (890)	Draw a sector
SetLineStyle (892)	Set current line drawing style

56.6 Categorized functions: Color management

All functions related to color management.

Table 56.5:

Name	Description
GetBkColor (875)	Get current background color
GetColor (880)	Get current foreground color
GetDefaultPalette (880)	Get default palette entries
GetMaxColor (882)	Get maximum valid color
GetPaletteSize (884)	Get size of palette for current mode
GetPixel (875)	Get color of selected pixel
GetPalette (884)	Get palette entry
SetAllPalette (876)	Set all colors in palette
SetBkColor (876)	Set background color
SetColor (891)	Set foreground color
SetPalette (893)	Set palette entry
SetRGBPalette (877)	Set palette entry with RGB values

56.7 Categorized functions: Screen management

General drawing screen management functions.

Table 56.6:

Name	Description
ClearViewPort (875)	Clear the current viewport
GetImage (875)	Copy image from screen to memory
GetMaxX (883)	Get maximum X coordinate
GetMaxY (883)	Get maximum Y coordinate
GetX (885)	Get current X position
GetY (885)	Get current Y position
ImageSize (875)	Get size of selected image
GetViewSettings (884)	Get current viewport settings
PutImage (876)	Copy image from memory to screen
SetActivePage (876)	Set active video page
SetAspectRatio (890)	Set aspect ratio for drawing routines
SetViewPort (894)	Set current viewport
SetVisualPage (877)	Set visual page
SetWriteMode (895)	Set write mode for screen operations

56.8 Categorized functions: Initialization

Initialization of the graphics screen.

Table 56.7:

Name	Description
ClearDevice (878)	Empty the graphics screen
CloseGraph (878)	Finish drawing session, return to text mode
DetectGraph (878)	Detect graphical modes
GetAspectRatio (880)	Get aspect ratio of screen
GetModeRange (883)	Get range of valid modes for current driver
GraphDefaults (885)	Set defaults
GetDriverName (881)	Return name of graphical driver
GetGraphMode (882)	Return current or last used graphics mode
GetMaxMode (882)	Get maximum mode for current driver
GetModeName (883)	Get name of current mode
GraphErrorMsg (885)	String representation of graphical error
GraphResult (886)	Result of last drawing operation
InitGraph (886)	Initialize graphics drivers
InstallUserDriver (887)	Install a new driver
RegisterBGIDriver (889)	Register a new driver
RestoreCRTMode (890)	Go back to text mode
SetGraphMode (892)	Set graphical mode

56.9 Target specific issues: Linux

There are several issues on Linux that need to be taken care of:

The Linux version of the Graph unit uses the `libvga` library. This library works on the console, not under X.

If you get an error similar to

```
/usr/bin/ld: cannot find -lvga
```

This can mean one of two things: either `libvga` and its development package is not installed properly, or the directory where it is installed is not in the linker path.

To remedy the former, you should install both the `libvga` package and `libvga-devel` package (or compile and install from scratch).

To remedy the latter, you should add the path to the compiler command-line using the `-F1` option.

Programs using `libvga` need root privileges to run. You can make them `setuid` root with the following command:

```
chown root.root myprogram
chmod u+s myprogram
```

The `libvga` library will give up the root privileges after it is initialized.

there is an experimental version of the Graphics library available that uses GGI to do all the drawing, but it is not well tested. It's called `ggigraph` and is distributed in source form only.

Do not use the CRT unit together with the Graph unit: the console may end up in an unusable state. Instead, the `ncurses` unit may function fine.

56.10 Target specific issues: DOS

VESA modes (i.e., anything but 320x200x256 and 640x480x16) do not work under most installations of Windows NT, Windows 2000 and Windows XP. They also do not work for some people under Windows 98 and Windows ME, depending on their graphics drivers. However, the graph unit cannot detect this, because no errors are returned from the system. In such cases, the screen simply turns black, or will show garbage.

Nothing can be done about this, the reason is missing or buggy support in the graphics drivers of the operating system.

56.11 A word about mode selection

The graph unit was implemented for compatibility with the old Turbo Pascal graph unit. For this reason, the mode constants as they were defined in the Turbo Pascal graph unit are retained.

However, since

1. Video cards have evolved very much
2. Free Pascal runs on multiple platforms

it was decided to implement new mode and graphic driver constants, which are more independent of the specific platform the program runs on.

In this section we give a short explanation of the new mode system. the following drivers were defined:

```
D1bit = 11;
D2bit = 12;
```

```

D4bit = 13;
D6bit = 14; { 64 colors Half-brite mode - Amiga }
D8bit = 15;
D12bit = 16; { 4096 color modes HAM mode - Amiga }
D15bit = 17;
D16bit = 18;
D24bit = 19; { not yet supported }
D32bit = 20; { not yet supported }
D64bit = 21; { not yet supported }

lowNewDriver = 11;
highNewDriver = 21;

```

Each of these drivers specifies a desired color-depth.

The following modes have been defined:

```

detectMode = 30000;
m320x200 = 30001;
m320x256 = 30002; { amiga resolution (PAL) }
m320x400 = 30003; { amiga/atari resolution }
m512x384 = 30004; { mac resolution }
m640x200 = 30005; { vga resolution }
m640x256 = 30006; { amiga resolution (PAL) }
m640x350 = 30007; { vga resolution }
m640x400 = 30008;
m640x480 = 30009;
m800x600 = 30010;
m832x624 = 30011; { mac resolution }
m1024x768 = 30012;
m1280x1024 = 30013;
m1600x1200 = 30014;
m2048x1536 = 30015;

lowNewMode = 30001;
highNewMode = 30015;

```

These modes start at 30000 because Borland specified that the mode number should be ascending with increasing X resolution, and the new constants shouldn't interfere with the old ones.

The above constants can be used to set a certain color depth and resolution, as demonstrated in the below example.

If other modes than the ones above are supported by the graphics card, you will not be able to select them with this mechanism.

For this reason, there is also a 'dynamic' mode number, which is assigned at run-time. This number increases with increasing X resolution. It can be queried with the `getmoderange` call. This call will return the range of modes which are valid for a certain graphics driver. The numbers are guaranteed to be consecutive, and can be used to search for a certain resolution, as in the second example below.

Thus, the `getmoderange` function can be used to detect all available modes and drivers, as in the third example below:

Listing: `./examples/graphex/inigraph1.pp`

Program `inigraph1` ;

```
{ Program to demonstrate static graphics mode selection }
```

```
uses graph;
```

```
const
```

```
  TheLine = 'We are now in 640 x 480 x 256 colors!' +  
            ' (press <Return> to continue)';
```

```
var
```

```
  gd, gm, lo, hi, error, tw, th: integer;  
  found: boolean;
```

```
begin
```

```
  { We want an 8 bit mode }  
  gd := D8bit;  
  gm := m640x480;  
  initgraph(gd, gm, '');  
  { Make sure you always check graphresult! }  
  error := graphResult;  
  if (error <> grOk) Then  
    begin  
      writeln('640x480x256 is not supported!');  
      halt(1)  
    end;  
  { We are now in 640x480x256 }  
  setColor(cyan);  
  rectangle(0,0,getmaxx,getmaxy);  
  { Write a nice message in the center of the screen }  
  setTextStyle(defaultFont, horizDir, 1);  
  tw := TextWidth(TheLine);  
  th := TextHeight(TheLine);  
  outTextXY((getMaxX - TW) div 2,  
            (getMaxY - TH) div 2, TheLine);  
  { Wait for return }  
  readln;  
  { Back to text mode }  
  closegraph;
```

```
end.
```

Listing: ./examples/graphex/inigraph2.pp

Program inigraph2;

```
{ Program to demonstrate dynamic graphics mode selection }
```

```
uses graph;
```

```
const
```

```
  TheLine = 'We are now in 640 x 480 x 256 colors!' +  
            ' (press <Return> to continue)';
```

```
var
```

```
  th, tw, gd, gm, lo, hi, error: integer;  
  found: boolean;
```

```
begin
```

```
  { We want an 8 bit mode }
```

```

gd := D8bit;
{ Get all available resolutions for this bitdepth }
getmoderange(gd, lo, hi);
{ If the highest available mode number is -1,
  no resolutions are supported for this bitdepth }
if hi = -1 then
  begin
    writeln('no 8 bit modes supported!');
    halt
  end;
found := false;
{ Search all resolutions for 640x480 }
for gm := lo to hi do
  begin
    initgraph(gd, gm, '');
    { Make sure you always check graphresult! }
    error := graphResult;
    if (error = grOk) and
      (getmaxx = 639) and (getmaxy = 479) then
      begin
        found := true;
        break;
      end;
  end;
if not found then
  CloseGraph();
  begin
    writeln('640x480x256 is not supported!');
    halt(1)
  end;
{ We are now in 640x480x256 }
setColor(cyan);
rectangle(0,0,getmaxx,getmaxy);
{ Write a nice message in the center of the screen }
setTextStyle(defaultFont, horizDir, 1);
TW:=TextWidth(TheLine);
TH:=TextHeight(TheLine);
outTextXY((getMaxX - TW) div 2,
          (getMaxY - TH) div 2, TheLine);
{ Wait for return }
readln;
{ Back to text mode }
closegraph;
end.

```

Listing: ./examples/graphex/modrange.pp

Program GetModeRange_Example;

```
{ This program demonstrates how to find all available graph modes }
```

```
uses graph;
```

```
const
```

```

{ Currently, only 4, 8, 15 and 16 bit modes are supported
  but this may change in the future }
gdnames: array[D4bit..D16bit] of string[6] =
  ('4 bit', '6 bit', '8 bit', '12 bit', '15 bit', '16 bit');
```

```

procedure WriteRes(const depth : integer);
var
    tw, th : integer;
    v, text : String;
begin
    text := 'Current resolution is '; str(getmaxx+1, v);
    text := text + v + 'x'; str(getmaxy+1, v);
    text := text + v + 'x' + gdnames[depth];
    setTextStyle(defaultFont, horizDir, 1);
    TW:=TextWidth(text);
    TH:=TextHeight(text);
    outTextXY((getMaxX - TW) div 2,
              (getMaxY - TH) div 2, text);
end;

var
    t: text;
    line : string;
    gd, c, low, high, res: integer;
begin
    assign(t, 'modes.txt');
    rewrite(t);
    close(t);
    for gd := D4bit to D16bit do
        begin
            { Get the available mode numbers for this driver }
            getModeRange(gd, low, high);
            append(t);
            write(t, gdnames[gd]);
            writeln(t, ': low modenr = ', low, ', high modenr = ', high);
            close(t);
            { If high is -1,
              no resolutions are supported for this bitdepth }
            if high = -1 then
                begin
                    append(t);
                    writeln(t, ' No modes supported!');
                    writeln(t);
                    close(t);
                end
            else
                { Enter all supported resolutions for this bitdepth
                  and write their characteristics to the file }
                for c := low to high do
                    begin
                        append(t);
                        writeln(t, ' testing mode nr ', c);
                        close(t);
                        initgraph(gd, c, '');
                        res := graphresult;
                        append(t);
                        { An error occurred when entering the mode? }
                        if res <> grok then
                            writeln(t, grapherrormsg(res))
                        else
                            begin
                                write(t, 'maxx: ', getmaxx, ', maxy: ', getmaxy);

```

```

        Writeln(t, ', maxcolor: ', getmaxcolor);
        closegraph;
    end;
    writeln(t);
    WriteRes(gd);
    close(t);
    end;
    append(t);
    writeln(t);
    close(t);
    end;
    Writeln('All supported modes are listed in modes.txt files');
end.

```

56.12 Requirements

The unit Graph exports functions and procedures for graphical output. It requires at least a VGA-compatible Card or a VGA-Card with software-driver (min. **512Kb** video memory).

56.13 Constants, types and variables

56.13.1 Constants

AndPut = 3

Draw operation: use AND

```

AnsiToASCIITransTable : TCharsetTransTable = (#$00, #$01, #$02, #
    $03, #$04, #$05, #$06, #$07, #$08, #$09, #$0a, #$0b, #$0c, #$0d,
    #$0e, #$0f, #$10, #$11, #$12, #$13, #$14, #$15, #$16, #$17, #$18,
    #$19, #$1a, #$1b, #$1c, #$1d, #$1e, #$1f, #$20, #$21, #$22, #$23
    , #$24, #$25, #$26, #$27, #$28, #$29, #$2a, #$2b, #$2c, #$2d, #$2e
    , #$2f, #$30, #$31, #$32, #$33, #$34, #$35, #$36, #$37, #$38, #$39
    , #$3a, #$3b, #$3c, #$3d, #$3e, #$3f, #$40, #$41, #$42, #$43, #$44
    , #$45, #$46, #$47, #$48, #$49, #$4a, #$4b, #$4c, #$4d, #$4e, #$4f
    , #$50, #$51, #$52, #$53, #$54, #$55, #$56, #$57, #$58, #$59, #$5a
    , #$5b, #$5c, #$5d, #$5e, #$5f, #$60, #$61, #$62, #$63, #$64, #$65
    , #$66, #$67, #$68, #$69, #$6a, #$6b, #$6c, #$6d, #$6e, #$6f, #$70
    , #$71, #$72, #$73, #$74, #$75, #$76, #$77, #$78, #$79, #$7a, #$7b
    , #$7c, #$7d, #$7e, #$7f, '?', '?', '?', '?', '?', '?', '?', '?',
    '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?',
    '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '$ff, $ad
    , $9b, $9c, '?', $9d, '?', '?', '?', '?', $a6, $ae, $aa, '?'
    , '?', '?', $f8, $f1, $fd, '?', '?', $e6, '?', $fa, '?', '?'
    , $a7, $af, $ac, $ab, '?', $a8, '?', '?', '?', '?', $8e, $8f
    , $92, $80, '?', $90, '?', '?', '?', '?', '?', '?', '?', $a5,
    '?', '?', '?', '?', $99, '?', '?', '?', '?', '?', $9a, '?', '?'
    , $e1, $85, $a0, $83, '?', $84, $86, $91, $87, $8a, $82
    , $88, $89, $8d, $a1, $8c, $8b, '?', $a4, $95, $a2, $93
    , '?', $94, $f6, '?', $97, $a3, $96, $81, '?', '?', $98)

```

Default ansi transliteration table.

BkSlashFill = 5

Fill style: Diagonal (backslash) lines

black = 0

Color code: black.

blue = 1

Color code: blue

BoldFont = 10

Font number: Bold font.

BottomText = 0

Vertical text alignment: Align text to bottom

brown = 6

Color code: brown

CenterLn = 2

Line style: centered line

CenterText = 1

Horizontal text alignment: Center text

CGA = 1

Graphic driver for CGA cards

CGAC0 = 0

CGA Graphic driver mode C0

CGAC1 = 1

CGA Graphic driver mode C1

CGAC2 = 2

CGA Graphic driver mode C2

CGAC3 = 3

CGA Graphic driver mode C3

CGAHi = 4

CGA Graphic driver Hi-res mode

ClipOff = False

Viewport clipping off

ClipOn = True

Viewport clipping on

CloseDotFill = 11

Fill style: Closely spaced dotted lines

CopyPut = 0

Draw operation: use Copy

CurrentDriver = - 128

Currently used driver

cyan = 3

Color code: Cyan

D12bit = 16

Mode: Depth 12 bit

D15bit = 17

Mode: Depth 15 bit

D16bit = 18

Mode: Depth 16 bit

D1bit = 11

Mode: Depth 1 bit

D24bit = 19

Mode: Depth 24 bit

D2bit = 12

Mode: Depth 2 bit

D32bit = 20

Mode: Depth 32 bit

D4bit = 13

Mode: Depth 4 bit

D64bit = 21

Mode: Depth 64 bit

D6bit = 14

Mode: Depth 6 bit

D8bit = 15

Mode: Depth 8 bit

darkgray = 8

Color code: Dark gray

DashedLn = 3

Line style: dashed line

Default = 0

Default mode

DefaultFont = 0

Font number: Normal font

Detect = 0

Mode: Detect mode.

detectMode = 30000

Mode: Autodetect optimal mode

DottedLn = 1

Line style: Dotted line

DrawTextBackground : Boolean = False

Should the background of texts be drawn or should it be left untouched ?

EGA = 3

Graphic driver for EGA cards

EGA64 = 4

Graphic driver for EGA 64 cards

EGA64Hi = 1

EGA64 graphic driver high resolution mode

EGA64Lo = 0

EGA64 graphic driver low resolution mode

EGABlack = 0

Color code: EGA Black

EGABlue = 1

Color code: EGA blue

EGABrown = 20

Color code: EGA brown

EGACyan = 3

Color code: EGA cyan

EGADarkgray = 56

Color code: EGA dark gray

EGAGreen = 2

Color code: EGA green

EGAHi = 1

EGA graphic driver high resolution mode

EGALightblue = 57

Color code: EGA Light blue

EGALightcyan = 59

Color code: EGA Light cyan

EGALightgray = 7

Color code: EGA Light gray

EGALightgreen = 58

Color code: EGA Light green

EGALightmagenta = 61

Color code: EGA light magenta

EGALightred = 60

Color code: EGA light red

EGALo = 0

EGA graphic driver low resolution mode

EGAMagenta = 5

Color code: EGA magenta

EGAMono = 5

Graphic driver for EGA monochrome cards

EGAMonoHi = 3

EGAMono graphic driver high resolution mode

EGARed = 4

Color code: EGA red

EGAWhite = 63

Color code: EGA white

EGAYellow = 62

Color code: EGA yellow

EmptyFill = 0

Fill style: Do not fill

EuroFont = 9

Font number: ?

```
fillpatternTable : Array[0..12] of FillPatternType = (($00, $00,
    $00, $00, $00, $00, $00, $00), ($ff, $ff, $ff, $ff, $ff, $ff, $ff,
    $ff), ($ff, $ff, $00, $00, $ff, $ff, $00, $00), ($01, $02, $04,
    $08, $10, $20, $40, $80), ($07, $0e, $1c, $38, $70, $e0, $c1, $83
    ), ($07, $83, $c1, $e0, $70, $38, $1c, $0e), ($5a, $2d, $96, $4b,
    $a5, $d2, $69, $b4), ($ff, $88, $88, $88, $ff, $88, $88, $88), (
    $18, $24, $42, $81, $81, $42, $24, $18), ($cc, $33, $cc, $33, $cc
    , $33, $cc, $33), ($80, $00, $08, $00, $80, $00, $08, $00), ($88,
    $00, $22, $00, $88, $00, $22, $00), (0, 0, 0, 0, 0, 0, 0, 0))
```

Table with standard fill patterns

G1024x768x16 = 30

Mode: Resolution 1024x768, 16 colors

G1024x768x16M = 25

Mode: Resolution 1024x768, 16M colors

G1024x768x16M32 = 36

Mode: Resolution 1024x758, 16M 32-bit colors

G1024x768x256 = 12

Mode: Resolution 1024x768, 256 colors

G1024x768x32K = 23

Mode: Resolution 1024x768, 32K colors

G1024x768x64K = 24

Mode: Resolution 1024x768, 64K colors

G1152x864x16 = 38

Mode: Resolution 1152x864, 16 colors

G1152x864x16M = 42

Mode: Resolution 1152x864, 16M colors

G1152x864x16M32 = 43

Mode: Resolution 1152x864, 16M 32-bitcolors

G1152x864x256 = 39

Mode: Resolution 1152x864, 256 colors

G1152x864x32K = 40

Mode: Resolution 1152x864, 32K colors

G1152x864x64K = 41

Mode: Resolution 1152x864, 64K colors

G1280x1024x16 = 31

Mode: Resolution 1280x1024, 16 colors

G1280x1024x16M = 28

Mode: Resolution 1280x1024, 16M colors

G1280x1024x16M32 = 37

Mode: Resolution 1280x1024, 16M 32-bit colors

G1280x1024x256 = 13

Mode: Resolution 1280x1024, 256 colors

G1280x1024x32K = 26

Mode: Resolution 1280x1024, 32K colors

G1280x1024x64K = 27

Mode: Resolution 1280x1024, 64K colors

G1600x1200x16 = 44

Mode: Resolution 1600x1200, 16 colors

G1600x1200x16M = 48

Mode: Resolution 1600x1200, 16M colors

G1600x1200x16M32 = 49

Mode: Resolution 1600x1200, 16M 32-bit colors

G1600x1200x256 = 45

Mode: Resolution 1600x1200, 256 colors

G1600x1200x32K = 46

Mode: Resolution 1600x1200, 32K colors

G1600x1200x64K = 47

Mode: Resolution 1600x1200, 64K colors

G320x200x16 = 1

Mode: Resolution 320x200, 16 colors

G320x200x16M = 16

Mode: Resolution 320x200, 16M colors

G320x200x16M32 = 33

Mode: Resolution 320x200, 16M 32-bit colors

G320x200x256 = 5

Mode: Resolution 320x200, 256 colors

G320x200x32K = 14

Mode: Resolution 320x200, 32K colors

G320x200x64K = 15

Mode: Resolution 320x200, 64K colors

G320x240x256 = 6

Mode: Resolution 320x240, 256 colors

G320x400x256 = 7

Mode: Resolution 320x400, 256 colors

G360x480x256 = 8

Mode: Resolution 360x480, 256 colors

G640x200x16 = 2

Mode: Resolution x, colors

G640x350x16 = 3

Mode: Resolution x, colors

G640x480x16 = 4

Mode: Resolution x, colors

G640x480x16M = 19

Mode: Resolution 640x480, 16M colors

G640x480x16M32 = 34

Mode: Resolution 640x480, 16M 32-bit colors

G640x480x2 = 9

Mode: Resolution 640x480, 2 colors

G640x480x256 = 10

Mode: Resolution 640x480, 256 colors

G640x480x32K = 17

Mode: Resolution 640x480, 32K colors

G640x480x64K = 18

Mode: Resolution 640x480, 64K colors

G720x348x2 = 32

Mode: Resolution 720x348, 2 colors

G800x600x16 = 29

Mode: Resolution 800x600, 16 colors

G800x600x16M = 22

Mode: Resolution 800x600, 16M colors

G800x600x16M32 = 35

Mode: Resolution 800x600, 16M 32-bit colors

G800x600x256 = 11

Mode: Resolution 800x600, 256 colors

G800x600x32K = 20

Mode: Resolution 800x600, 32K colors

G800x600x64K = 21

Mode: Resolution 800x600, 64K colors

GothicFont = 4

Font number: Gothic font

GraphStringTransTable : PCharsetTransTable = Nil

Table used when transliterating strings.

green = 2

Color code: green

grError = - 11

Error: Unknown error.

grFileNotFound = - 3

Error: File for driver not found.

grFontNotFound = - 8

Error: font description file not found.

grInvalidDriver = - 4

Error: Invalid driver specified

grInvalidFont = - 13

Error: Invalid font description

grInvalidFontNum = - 14

Error: Invalid font number

grInvalidMode = - 10

Error: Invalid mode specified.

grInvalidVersion = - 18

Error: Invalid version.

grIOerror = - 12

Error: Unspecified Input/Output error.

grNoFloodMem = - 7

Error: Could not allocate memory for flood operation.

`grNoFontMem = - 9`

Error: Not enough memory to load font.

`grNoInitGraph = - 1`

Error: Graphical system not initialized

`grNoLoadMem = - 5`

Error: Memory error.

`grNoScanMem = - 6`

Error: Could not allocate memory for scan

`grNotDetected = - 2`

Error: Graphics device not detected.

`grOk = 0`

Graphical operation went OK.

`HatchFill = 7`

Fill style: Hatch lines

`HercMono = 7`

Mode: Hercules, mono color

`HercMonoHi = 0`

Mode: Hercules card, monochrome, high resolution

`highNewDriver = 21`

Mode: highest number for new driver

`highNewMode = m2048x1536`

Mode: Highest possible value of the new modes.

`HorizDir = 0`

Text write direction: Horizontal

`InterleaveFill = 9`

Fill style: Interleaving lines

LCOMFont = 8

Font number: ?

LeftText = 0

Horizontal text alignment: Align text left

lightblue = 9

Color code: Light blue

lightcyan = 11

Color code: Light cyan

lightgray = 7

Color code: Light gray

lightgreen = 10

Color code: Light green

lightmagenta = 13

Color code: Light magenta

lightred = 12

Color code: Light red

LineFill = 2

Fill style: Fill using horizontal lines

lowNewDriver = 11

Mode: lowest number for new driver

lowNewMode = m320x200

Mode: Lowest possible value of the new modes.

LowRes = 6

Mode: Low resolution.

LtBkSlashFill = 6

Fill style: Light diagonal (backslash) lines

LtSlashFill = 3

Fill style: Light diagonal (slash) lines

m1024x768 = detectMode + 12

Mode: Resolution 1024x768

m1280x1024 = detectMode + 13

Mode: Resolution 1280x1024

m1600x1200 = detectMode + 14

Mode: Resolution 1600x1200

m2048x1536 = detectMode + 15

Mode: Resolution 2048x1536

m320x200 = detectMode + 1

Mode: Resolution 320x200

m320x256 = detectMode + 2

Mode: Resolution 320x256

m320x400 = detectMode + 3

Mode: Resolution 320x400

m512x384 = detectMode + 4

Mode: Resolution 512x384

m640x200 = detectMode + 5

Mode: Resolution 640x200

m640x256 = detectMode + 6

Mode: Resolution 640x256

m640x350 = detectMode + 7

Mode: Resolution 640x350

m640x400 = detectMode + 8

Mode: Resolution 640x400

`m640x480 = detectMode + 9`

Mode: Resolution 640x480

`m800x600 = detectMode + 10`

Mode: Resolution 800x600

`m832x624 = detectMode + 11`

Mode: Resolution 832x624

`magenta = 5`

Color code: Magenta

`MaxColors = 255`

Max amount of colors in a palette

`maxsmallint = high(smallint)`

Maximum value for smallint type

`MCGA = 2`

Graphic driver for MCGA cards

`MCGAC0 = 0`

MCGA Graphic driver mode C0

`MCGAC1 = 1`

MCGA Graphic driver mode C1

`MCGAC2 = 2`

MCGA Graphic driver mode C2

`MCGAC3 = 3`

MCGA Graphic driver mode C3

`MCGAHi = 5`

MCGA Graphic driver high resolution mode

`MCGAMed = 4`

MCGA Graphic driver medium resolution mode

NormalPut = 0

Draw operation: Use Normal (copy) operation

NormWidth = 1

Line width: Normal width

NotPut = 4

Draw operation: use NOT

OrPut = 2

Draw operation: use OR

red = 4

Color code: Red

```
resolutions : Array[lowNewMode..highNewMode] of TResolutionRec =
  ((x: 320; y: 200), (x: 320; y: 256), (x: 320; y: 400), (x: 512; y
   : 384), (x: 640; y: 200), (x: 640; y: 256), (x: 640; y: 350), (x:
   640; y: 400), (x: 640; y: 480), (x: 800; y: 600), (x: 832; y: 624
   ), (x: 1024; y: 768), (x: 1280; y: 1024), (x: 1600; y: 1200), (x:
   2048; y: 1536))
```

Array with actual resolutions of the new modes

RightText = 2

Horizontal text alignment: Align text right

SansSerifFont = 3

Font number: Sans Serif font

ScriptFont = 5

Font number: Script font

SimpleFont = 6

Font number: Simple font

SlashFill = 4

Fill style: Diagonal (slash) lines

SmallFont = 2

Font number: Small font

`SolidFill = 1`

Fill style: Solid fill.

`SolidLn = 0`

Line style: Solid line

`ThickWidth = 3`

Line width: double width

`TopOff = False`

Top off

`TopOn = True`

Top on

`TopText = 2`

Vertical text alignment: Align text to top

`TriplexFont = 1`

Font number: Triplex font

`TSCRFonT = 7`

Font number: Terminal font

`UserBitLn = 4`

Line style: User defined

`UserCharSize = 0`

User character size

`UserFill = 12`

Fill style: User-defined fill.

`VertDir = 1`

Text write direction: Vertical

`VESA = 10`

Mode: VESA graphics adaptor.

VGA = 9

Mode: VGA graphics adaptor.

VGAHi = 2

Mode: VGA high resolution (640x480)

VGALo = 0

Mode: VGA low resolution (640x200)

VGAMed = 1

Mode: VGA medium resolution (640x350)

white = 15

Color code: White

WideDotFill = 10

Fill style: Widely spaced dotted lines

XHatchFill = 8

Fill style: Heavy hatch lines

XORPut = 1

Draw operation: use XOR

yellow = 14

Color code: Yellow

56.13.2 Types

CircleProc = procedure(X: SmallInt; Y: SmallInt; Radius: Word)

Standard circle drawing routine prototype.

clrviewproc = procedure

Standard clearviewport routine prototype

ColorType = Word

Color type alias

```
defpixelproc = procedure(X: SmallInt; Y: SmallInt)
```

This is the standard putpixel routine used by all function drawing routines, it will use the viewport settings, as well as clip, and use the current foreground color to plot the desired pixel.

```
ellipseproc = procedure(X: SmallInt; Y: SmallInt; XRadius: Word;
    YRadius: Word; stAngle: Word; EndAngle: Word
    ;
    fp: patternlineproc)
```

Standard ellipse drawing routine prototype.

```
FillPatternType = Array[1..8] of Byte
```

Bit pattern used when drawing lines. Set bits are drawn.

```
GetBkColorProc = function : ColorType
```

GetBkColorProc is the procedure prototype for the GetBkColor (875) method handler in TMod-
eInfo (898). The function should return the color code of the background color.

```
getimageproc = procedure(X1: SmallInt; Y1: SmallInt; X2: SmallInt
    ;
    Y2: SmallInt; var Bitmap)
```

Standard GetImage (875) procedure prototype.

```
getpixelproc = function(X: SmallInt; Y: SmallInt) : ColorType
```

Standard pixel fetching routine prototype

```
getrgbpaletteproc = procedure(ColorNum: SmallInt;
    var RedValue: SmallInt;
    var GreenValue: SmallInt;
    var
    BlueValue: SmallInt)
```

This routine prototype is a hook for GetRGBPalette (875)

```
getscanlineproc = procedure(X1: SmallInt; X2: SmallInt; Y: SmallInt
    ;
    var data)
```

This routine is used for FloodFill (879) It returns an entire screen scan line with a word for each pixel in the scanline. Also handy for GetImage.

```
graphfreememprc = procedure(var P: Pointer; size: Word)
```

Procedure prototype, used when heap memory is freed by the graph routines.

```
graphgetmemproc = procedure(var P: pointer; size: Word)
```

Procedure prototype, used when heap memory is needed by the graph routines.

```
graph_float = single
```

The platform's preferred floating point size for fast graph operations

```
hlineproc = procedure(x: SmallInt; x2: SmallInt; y: SmallInt)
```

Standard procedure prototype to draw a single horizontal line

```
imagesizeproc = function(X1: SmallInt; Y1: SmallInt; X2: SmallInt
;
                        Y2: SmallInt) : LongInt
```

Standard ImageSize (875) calculation procedure prototype.

```
initmodeproc = procedure
```

Standard routine prototype to initialize a mode.

```
lineproc = procedure(X1: SmallInt; Y1: SmallInt; X2: SmallInt;
Y2: SmallInt)
```

Standard line drawing routine prototype.

```
OutTextXYProc = procedure(x: SmallInt; y: SmallInt;
const TextString: string)
```

This routine prototype is a hook for OutTextXY (876)

```
patternlineproc = procedure(x1: SmallInt; x2: SmallInt; y: SmallInt
)
```

Standard procedure prototype to draw a patterned line

```
PCharsetTransTable = ^TCharsetTransTable
```

Pointer to TCharsetTransTable (874) array.

```
PModeInfo = ^TModeInfo
```

Pointer to TModeInfo (898) record

```
putimageproc = procedure(X: SmallInt; Y: SmallInt; var Bitmap;
BitBlt: Word)
```

Standard PutImage (876) procedure prototype.

```
putpixelproc = procedure(X: SmallInt; Y: SmallInt; Color: ColorType
)
```

Standard pixel drawing routine prototype

```
restorestateproc = procedure
```

Standard routine prototype to restore the graphical state at a closegraph call.

```
savestateproc = procedure
```

Standard routine prototype to save the graphical state before a mode is set.

```
setactivepageproc = procedure (page: Word)
```

Standard SetActivePage (876) procedure prototype.

```
SetAllPaletteProc = procedure (const Palette: PaletteType)
```

This routine prototype is a hook for SetAllPalette (876)

```
SetBkColorProc = procedure (ColorNum: ColorType)
```

SetBkColorProc is the procedure prototype for the SetBkColor (876) method handler in TMod-Info (898). The procedure gets passed the color code for the color to set as background color.

```
setrgbpaletteproc = procedure (ColorNum: SmallInt; RedValue: SmallInt
;
                                GreenValue: SmallInt; BlueValue:
                                SmallInt)
```

This routine prototype is a hook for SetRGBPalette (877)

```
setvisualpageproc = procedure (page: Word)
```

Standard SetVisualPage (877) procedure prototype.

```
TCharsetTransTable = Array[Char] of Char
```

Character transliteration table, with entries for 256 characters

```
vlineproc = procedure (x: SmallInt; y: SmallInt; y2: SmallInt)
```

Standard procedure prototype to draw a single vertical line

56.13.3 Variables

```
Circle : CircleProc
```

Circle draws a complete circle with center at (X, Y), radius radius.

```
ClearViewPort : clrviewproc
```

Clears the current viewport. The current background color is used as filling color. The pointer is set at (0, 0).

DirectPutPixel : defpixelproc

Hook to directly draw a pixel on the screen.

GetBkColor : GetBkColorProc

GetBkColor returns the current background color (the palette entry).

GetImage : getimageproc

GetImage Places a copy of the screen area (X1, Y1) to X2, Y2 in BitMap

GetPixel : getpixelproc

GetPixel returns the color of the point at (X, Y)

GetRGBPalette : getrgbpaletteproc

Hook to set a RGB palette entries.

GetScanLine : getscanlineproc

Hook to get a scan line from the screen.

GraphFreeMemPtr : graphfreememprc

Hook to free heap memory.

GraphGetMemPtr : graphgetmemprc

Hook to get heap memory

HLine : hlineproc

Hook to draw a solid horizontal line

ImageSize : imagesizeproc

ImageSize returns the number of bytes needed to store the image in the rectangle defined by (X1, Y1) and (X2, Y2).

InternalEllipse : ellipseproc

Hook to draw an ellipse

Line : lineproc

`Line` draws a line starting from `(X1, Y1)` to `(X2, Y2)`, in the current line style and color. The current position is put to `(X2, Y2)`

`OutTextXY` : `OutTextXYProc`

`OutText` puts `TextString` on the screen, at position `(X, Y)`, using the current font and text settings. The current position is moved to the end of the text.

`PatternLine` : `patternlineproc`

Hook to draw a patterned line

`PutImage` : `putimageproc`

`PutImage` Places the bitmap in `Bitmap` on the screen at `(X1, Y1)`. `How` determines how the bitmap will be placed on the screen. Possible values are:

- `CopyPut`
- `XORPut`
- `ORPut`
- `AndPut`
- `NotPut`

`PutPixel` : `putpixelproc`

Puts a point at `(X, Y)` using color `Color`

`RestoreVideoState` : `restorestateproc`

Hook to restore a saved video mode

`SaveVideoState` : `savestateproc`

Hook to save the current video state

`SetActivePage` : `setactivepageproc`

Sets `Page` as the active page for all graphical output.

`SetAllPalette` : `SetAllPaletteProc`

Sets the current palette to `Palette`. `Palette` is an untyped variable, usually pointing to a record of type `PaletteType`

`SetBkColor` : `SetBkColorProc`

Sets the background color to `Color`.

`SetRGBPalette` : `setrgbpaletteproc`

SetRGBPalette sets the ColorNr-th entry in the palette to the color with RGB-values Red, Green Blue.

SetVisualPage : setvisualpageproc

SetVisualPage sets the video page to page number Page.

VLine : vlineproc

Hook to draw a solid vertical line

56.14 Procedures and functions

56.14.1 Arc

Synopsis: Draw part of a circle

Declaration: `procedure Arc(X: SmallInt; Y: SmallInt; StAngle: Word; EndAngle: Word; Radius: Word)`

Visibility: default

Description: Arc draws part of a circle with center at (X,Y), radius radius, starting from angle start, stopping at angle stop. These angles are measured counterclockwise.

Errors: None.

See also: Circle ([874](#)), Ellipse ([879](#)), GetArcCoords ([880](#)), PieSlice ([889](#)), Sector ([890](#))

56.14.2 Bar

Synopsis: Draw filled rectangle

Declaration: `procedure Bar(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1,Y1) and (X2,Y2) and fills it with the current color and fill-style.

Errors: None.

See also: Bar3D ([877](#)), Rectangle ([889](#))

56.14.3 Bar3D

Synopsis: Draw filled 3-dimensional rectangle

Declaration: `procedure Bar3D(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt; depth: Word; top: Boolean)`

Visibility: default

Description: Bar3d draws a 3-dimensional Bar with corners at (X1,Y1) and (X2,Y2) and fills it with the current color and fill-style. Depth specifies the number of pixels used to show the depth of the bar.

If Top is true; then a 3-dimensional top is drawn.

Errors: None.

See also: Bar ([877](#)), Rectangle ([889](#))

56.14.4 ClearDevice

Synopsis: Clear the complete screen

Declaration: `procedure ClearDevice`

Visibility: default

Description: Clears the graphical screen (with the current background color), and sets the pointer at (0, 0).

Errors: None.

See also: `ClearViewPort` (875), `SetBkColor` (876)

56.14.5 Closegraph

Synopsis: Close graphical system.

Declaration: `procedure Closegraph`

Visibility: default

Description: Closes the graphical system, and restores the screen modus which was active before the graphical modus was activated.

Errors: None.

See also: `InitGraph` (886)

56.14.6 DetectGraph

Synopsis: Detect correct graphical driver to use

Declaration: `procedure DetectGraph(var GraphDriver: SmallInt;
var GraphMode: SmallInt)`

Visibility: default

Description: `DetectGraph` checks the hardware in the PC and determines the driver and screen-modus to be used. These are returned in `Driver` and `Modus`, and can be fed to `InitGraph`. See the `InitGraph` for a list of drivers and modi.

Errors: None.

See also: `InitGraph` (886)

56.14.7 DrawPoly

Synopsis: Draw a polygon

Declaration: `procedure DrawPoly(NumPoints: Word; var polypoints)`

Visibility: default

Description: `DrawPoly` draws a polygon with `NumberOfPoints` corner points, using the current color and line-style. `PolyPoints` is an array of type `PointType` (897).

Errors: None.

See also: `Bar` (877), `Bar3D` (877), `Rectangle` (889)

56.14.8 Ellipse

Synopsis: Draw an ellipse

Declaration: `procedure Ellipse(X: SmallInt; Y: SmallInt; stAngle: Word;
EndAngle: Word; XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Ellipse` draws part of an ellipse with center at (X, Y) . `XRadius` and `Yradius` are the horizontal and vertical radii of the ellipse. `Start` and `Stop` are the starting and stopping angles of the part of the ellipse. They are measured counterclockwise from the X-axis (3 o'clock is equal to 0 degrees). Only positive angles can be specified.

Errors: None.

See also: `Arc` (877), `Circle` (874), `FillEllipse` (879)

56.14.9 FillEllipse

Synopsis: Draw and fill an ellipse

Declaration: `procedure FillEllipse(X: SmallInt; Y: SmallInt; XRadius: Word;
YRadius: Word)`

Visibility: default

Description: `Ellipse` draws an ellipse with center at (X, Y) . `XRadius` and `Yradius` are the horizontal and vertical radii of the ellipse. The ellipse is filled with the current color and fill-style.

Errors: None.

See also: `Arc` (877), `Circle` (874), `GetArcCoords` (880), `PieSlice` (889), `Sector` (890)

56.14.10 FillPoly

Synopsis: Draw, close and fill a polygon

Declaration: `procedure FillPoly(NumPoints: Word; var PolyPoints)`

Visibility: default

Description: `FillPoly` draws a polygon with `NumberOfPoints` corner points and fills it using the current color and line-style. `PolyPoints` is an array of type `PointType`.

Errors: None.

See also: `Bar` (877), `Bar3D` (877), `Rectangle` (889)

56.14.11 FloodFill

Synopsis: Fill an area with a given color

Declaration: `procedure FloodFill(x: SmallInt; y: SmallInt; Border: ColorType)`

Visibility: default

Description: Fills the area containing the point (X, Y) , bounded by the color `BorderColor`.

Errors: None

See also: `SetColor` (891), `SetBkColor` (876)

56.14.12 GetArcCoords

Synopsis: Return coordinates of last drawn arc or ellipse.

Declaration: `procedure GetArcCoords (var ArcCoords: ArcCoordsType)`

Visibility: default

Description: `GetArcCoords` returns the coordinates of the latest `Arc` or `Ellipse` call.

Errors: None.

See also: `Arc` ([877](#)), `Ellipse` ([879](#))

56.14.13 GetAspectRatio

Synopsis: Return screen resolution

Declaration: `procedure GetAspectRatio (var Xasp: Word; var Yasp: Word)`

Visibility: default

Description: `GetAspectRatio` determines the effective resolution of the screen. The aspect ration can then be calculated as `Xasp/Yasp`.

Errors: None.

See also: `InitGraph` ([886](#)), `SetAspectRatio` ([890](#))

56.14.14 GetColor

Synopsis: Return current drawing color

Declaration: `function GetColor : ColorType`

Visibility: default

Description: `GetColor` returns the current drawing color (the palette entry).

Errors: None.

See also: `GetColor` ([880](#)), `SetBkColor` ([876](#))

56.14.15 GetDefaultPalette

Synopsis: Return default palette

Declaration: `procedure GetDefaultPalette (var Palette: PaletteType)`

Visibility: default

Description: `GetDefaultPalette` returns the current palette in `Palette`.

Errors: None.

See also: `GetColor` ([880](#)), `GetBkColor` ([875](#))

56.14.16 GetDirectVideo

Synopsis: Determine whether direct video mode is active.

Declaration: `function GetDirectVideo : Boolean`

Visibility: default

Description: Determine whether direct video mode is active.

56.14.17 GetDriverName

Synopsis: Return current driver name

Declaration: `function GetDriverName : string`

Visibility: default

Description: `GetDriverName` returns a string containing the name of the current driver.

Errors: None.

See also: `GetModeName` ([883](#)), `InitGraph` ([886](#))

56.14.18 GetFillPattern

Synopsis: Return current fill pattern

Declaration: `procedure GetFillPattern(var FillPattern: FillPatternType)`

Visibility: default

Description: `GetFillPattern` returns an array with the current fill-pattern in `FillPattern`

Errors: None

See also: `SetFillPattern` ([891](#))

56.14.19 GetFillSettings

Synopsis: Return current fill settings

Declaration: `procedure GetFillSettings(var Fillinfo: FillSettingsType)`

Visibility: default

Description: `GetFillSettings` returns the current fill-settings in `FillInfo`

Errors: None.

See also: `SetFillPattern` ([891](#))

56.14.20 GetGraphMode

Synopsis: Get current graphical modus

Declaration: `function GetGraphMode : SmallInt`

Visibility: default

Description: `GetGraphMode` returns the current graphical modus

Errors: None.

See also: `InitGraph` ([886](#))

56.14.21 GetLineSettings

Synopsis: Get current line drawing settings

Declaration: `procedure GetLineSettings (var ActiveLineInfo: LineSettingsType)`

Visibility: default

Description: `GetLineSettings` returns the current Line settings in `LineInfo`

Errors: None.

See also: `SetLineStyle` ([892](#))

56.14.22 GetMaxColor

Synopsis: return maximum number of colors

Declaration: `function GetMaxColor : ColorType`

Visibility: default

Description: `GetMaxColor` returns the maximum color-number which can be set with `SetColor`. Contrary to Turbo Pascal, this color isn't always guaranteed to be white (for instance in 256+ color modes).

Errors: None.

See also: `SetColor` ([891](#)), `GetPaletteSize` ([884](#))

56.14.23 GetMaxMode

Synopsis: Return biggest mode for the current driver

Declaration: `function GetMaxMode : SmallInt`

Visibility: default

Description: `GetMaxMode` returns the highest modus for the current driver.

Errors: None.

See also: `InitGraph` ([886](#))

56.14.24 GetMaxX

Synopsis: Return maximal X coordinate

Declaration: `function GetMaxX : SmallInt`

Visibility: default

Description: `GetMaxX` returns the maximum horizontal screen length

Errors: None.

See also: `GetMaxY` ([883](#))

56.14.25 GetMaxY

Synopsis: Return maximal Y coordinate

Declaration: `function GetMaxY : SmallInt`

Visibility: default

Description: `GetMaxY` returns the maximum number of screen lines

Errors: None.

See also: `GetMaxX` ([883](#))

56.14.26 GetModeName

Synopsis: Return description a modus

Declaration: `function GetModeName (ModeNumber: SmallInt) : string`

Visibility: default

Description: `GetModeName` Returns a string with the name of modus Modus

Errors: None.

See also: `GetDriverName` ([881](#)), `InitGraph` ([886](#))

56.14.27 GetModeRange

Synopsis: Return lowest and highest modus of current driver

Declaration: `procedure GetModeRange (GraphDriver: SmallInt; var LoMode: SmallInt;
var HiMode: SmallInt)`

Visibility: default

Description: `GetModeRange` returns the Lowest and Highest modus of the currently installed driver. If no modes are supported for this driver, `HiModus` will be -1.

Errors: None.

See also: `InitGraph` ([886](#))

56.14.28 GetPalette

Synopsis: Return current palette

Declaration: `procedure GetPalette (var Palette: PaletteType)`

Visibility: default

Description: `GetPalette` returns in `Palette` the current palette.

Errors: None.

See also: `GetPaletteSize` ([884](#)), `SetPalette` ([893](#))

56.14.29 GetPaletteSize

Synopsis: Return maximal number of entries in current palette

Declaration: `function GetPaletteSize : SmallInt`

Visibility: default

Description: `GetPaletteSize` returns the maximum number of entries in the current palette.

Errors: None.

See also: `GetPalette` ([884](#)), `SetPalette` ([893](#))

56.14.30 GetTextSettings

Synopsis: Return current text style

Declaration: `procedure GetTextSettings (var TextInfo: TextSettingsType)`

Visibility: default

Description: `GetTextSettings` returns the current text style settings : The font, direction, size and placement as set with `SetTextStyle` and `SetTextJustify`

Errors: None.

See also: `SetTextStyle` ([893](#)), `SetTextJustify` ([893](#))

56.14.31 GetViewSettings

Synopsis: Return current viewport

Declaration: `procedure GetViewSettings (var viewport: ViewPortType)`

Visibility: default

Description: `GetViewSettings` returns the current viewport and clipping settings in `ViewPort`.

Errors: None.

See also: `SetViewPort` ([894](#))

56.14.32 GetX

Synopsis: Return current cursor X position

Declaration: `function GetX : SmallInt`

Visibility: default

Description: `GetX` returns the X-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetY` ([885](#))

56.14.33 GetY

Synopsis: Return current cursor Y position

Declaration: `function GetY : SmallInt`

Visibility: default

Description: `GetY` returns the Y-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetX` ([885](#))

56.14.34 GraphDefaults

Synopsis: Reset graphical mode to defaults

Declaration: `procedure GraphDefaults`

Visibility: default

Description: `GraphDefaults` resets all settings for viewport, palette, foreground and background pattern, line-style and pattern, filling style, filling color and pattern, font, text-placement and text size.

Errors: None.

See also: `SetViewPort` ([894](#)), `SetFillStyle` ([891](#)), `SetColor` ([891](#)), `SetBkColor` ([876](#)), `SetLineStyle` ([892](#))

56.14.35 GraphErrorMsg

Synopsis: Return a description of an error

Declaration: `function GraphErrorMsg(ErrorCode: SmallInt) : string`

Visibility: default

Description: `GraphErrorMsg` returns a string describing the error `Errorcode`. This string can be used to let the user know what went wrong.

Errors: None.

See also: `GraphResult` ([886](#))

56.14.36 GraphResult

Synopsis: Result of last graphical operation

Declaration: `function GraphResult : SmallInt`

Visibility: default

Description: `GraphResult` returns an error-code for the last graphical operation. If the returned value is zero, all went well. A value different from zero means an error has occurred. besides all operations which draw something on the screen, the following procedures also can produce a `GraphResult` different from zero:

- `InstallUserFont` ([887](#))
- `SetLineStyle` ([892](#))
- `SetWriteMode` ([895](#))
- `SetFillStyle` ([891](#))
- `SetTextJustify` ([893](#))
- `SetGraphMode` ([892](#))
- `SetTextStyle` ([893](#))

Errors: None.

See also: `GraphErrorMsg` ([885](#))

56.14.37 InitGraph

Synopsis: Initialize graphical system

Declaration: `procedure InitGraph(var GraphDriver: SmallInt; var GraphMode: SmallInt; const PathToDriver: string)`

Visibility: default

Description: `InitGraph` initializes the graph package. `GraphDriver` has two valid values: `GraphDriver=0` which performs an auto detect and initializes the highest possible mode with the most colors. 1024x768x64K is the highest possible resolution supported by the driver, if you need a higher resolution, you must edit `MODES.PPI`. If you need another mode, then set `GraphDriver` to a value different from zero and `graphmode` to the mode you wish (VESA modes where 640x480x256 is 101h etc.). `PathToDriver` is only needed, if you use the BGI fonts from Borland. Free Pascal does not offer BGI fonts like Borland, these must be obtained separately.

Example code:

```
var
  gd,gm : integer;
  PathToDriver : string;
begin
  gd:=detect; { highest possible resolution }
  gm:=0; { not needed, auto detection }
  PathToDriver:='C:\PP\BGI'; { path to BGI fonts,
                             drivers aren't needed }

  InitGraph(gd,gm,PathToDriver);
  if GraphResult<>grok then
    halt; ..... { whatever you need }
  CloseGraph; { restores the old graphics mode }
end.
```

Errors: None.

See also: Modes (849), DetectGraph (878), CloseGraph (878), GraphResult (886)

56.14.38 InstallUserDriver

Synopsis: Install a user driver

Declaration: `function InstallUserDriver (Name: string; AutoDetectPtr: Pointer)
: SmallInt`

Visibility: default

Description: `InstallUserDriver` adds the device-driver `DriverPath` to the list of .BGI drivers. `AutoDetectPtr` is a pointer to a possible auto-detect function.

Errors: None.

See also: `InitGraph` (886), `InstallUserFont` (887)

56.14.39 InstallUserFont

Synopsis: Install a user-defined font

Declaration: `function InstallUserFont (const FontFileName: string) : SmallInt`

Visibility: default

Description: `InstallUserFont` adds the font in `FontPath` to the list of fonts of the .BGI system.

Errors: None.

See also: `InitGraph` (886), `InstallUserDriver` (887)

56.14.40 LineRel

Synopsis: Draw a line starting from current position in given direction

Declaration: `procedure LineRel (Dx: SmallInt; Dy: SmallInt)`

Visibility: default

Description: `LineRel` draws a line starting from the current pointer position to the point (DX, DY) , **relative** to the current position, in the current line style and color. The Current Position is set to the endpoint of the line.

Errors: None.

See also: `Line` (876), `LineTo` (888)

56.14.41 LineTo

Synopsis: Draw a line starting from current position to a given point

Declaration: `procedure LineTo(X: SmallInt; Y: SmallInt)`

Visibility: default

Description: `LineTo` draws a line starting from the current pointer position to the point (DX, DY), **relative** to the current position, in the current line style and color. The Current position is set to the end of the line.

Errors: None.

See also: `LineRel` (887), `Line` (876)

56.14.42 MoveRel

Synopsis: Move cursor relative to current position

Declaration: `procedure MoveRel(Dx: SmallInt; Dy: SmallInt)`

Visibility: default

Description: `MoveRel` moves the pointer to the point (DX, DY), relative to the current pointer position

Errors: None.

See also: `MoveTo` (888)

56.14.43 MoveTo

Synopsis: Move cursor to absolute position.

Declaration: `procedure MoveTo(X: SmallInt; Y: SmallInt)`

Visibility: default

Description: `MoveTo` moves the pointer to the point (X, Y).

Errors: None.

See also: `MoveRel` (888)

56.14.44 OutText

Synopsis: Write text on the screen at the current location.

Declaration: `procedure OutText(const TextString: string)`

Visibility: default

Description: `OutText` puts `TextString` on the screen, at the current pointer position, using the current font and text settings. The current position is moved to the end of the text.

Errors: None.

See also: `OutTextXY` (876)

56.14.45 PieSlice

Synopsis: Draw a pie-slice

Declaration: `procedure PieSlice(X: SmallInt; Y: SmallInt; stangle: SmallInt;
 endAngle: SmallInt; Radius: Word)`

Visibility: default

Description: `PieSlice` draws and fills a sector of a circle with center (X, Y) and radius Radius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: Arc ([877](#)), Circle ([874](#)), Sector ([890](#))

56.14.46 queryadapterinfo

Synopsis: Function called to retrieve the current video adapter settings.

Declaration: `function queryadapterinfo : PModeInfo`

Visibility: default

56.14.47 Rectangle

Synopsis: Draw a rectangle on the screen.

Declaration: `procedure Rectangle(x1: SmallInt; y1: SmallInt; x2: SmallInt;
 y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1, Y1) and (X2, Y2), using the current color and style.

Errors: None.

See also: Bar ([877](#)), Bar3D ([877](#))

56.14.48 RegisterBGIDriver

Synopsis: Register a new BGI driver.

Declaration: `function RegisterBGIDriver(driver: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: `InstallUserDriver` ([887](#)), `RegisterBGIFont` ([890](#))

56.14.49 RegisterBGIfont

Synopsis: Register a new BGI font

Declaration: `function RegisterBGIfont(font: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: [InstallUserFont \(887\)](#), [RegisterBGIDriver \(889\)](#)

56.14.50 RestoreCrtMode

Synopsis: Restore text screen

Declaration: `procedure RestoreCrtMode`

Visibility: default

Description: Restores the screen modus which was active before the graphical modus was started.

To get back to the graph mode you were last in, you can use `SetGraphMode(GetGraphMode)`

Errors: None.

See also: [InitGraph \(886\)](#)

56.14.51 Sector

Synopsis: Draw and fill a sector of an ellipse

Declaration: `procedure Sector(x: SmallInt; y: SmallInt; StAngle: Word;
EndAngle: Word; XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Sector` draws and fills a sector of an ellipse with center (X, Y) and radii XRadius and YRadius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: [Arc \(877\)](#), [Circle \(874\)](#), [PieSlice \(889\)](#)

56.14.52 SetAspectRatio

Synopsis: Set aspect ration of the screen

Declaration: `procedure SetAspectRatio(Xasp: Word; Yasp: Word)`

Visibility: default

Description: Sets the aspect ratio of the current screen to Xasp/Yasp.

Errors: None

See also: [InitGraph \(886\)](#), [GetAspectRatio \(880\)](#)

56.14.53 SetColor

Synopsis: Set foreground drawing color

Declaration: `procedure SetColor (Color: ColorType)`

Visibility: default

Description: Sets the foreground color to `Color`.

Errors: None.

See also: [GetColor \(880\)](#), [SetBkColor \(876\)](#), [SetWriteMode \(895\)](#)

56.14.54 SetDirectVideo

Synopsis: Attempt to enter direct video mode.

Declaration: `procedure SetDirectVideo (DirectAccess: Boolean)`

Visibility: default

Description: `SetDirectVideo` attempts to enter direct video mode. In that mode, everything is drawn straight in the video buffer.

56.14.55 SetFillPattern

Synopsis: Set drawing fill pattern

Declaration: `procedure SetFillPattern (Pattern: FillPatternType; Color: ColorType)`

Visibility: default

Description: `SetFillPattern` sets the current fill-pattern to `FillPattern`, and the filling color to `Color`. The pattern is an 8x8 raster, corresponding to the 64 bits in `FillPattern`.

Errors: None

See also: [GetFillPattern \(881\)](#), [SetFillStyle \(891\)](#), [SetWriteMode \(895\)](#)

56.14.56 SetFillStyle

Synopsis: Set drawing fill style

Declaration: `procedure SetFillStyle (Pattern: Word; Color: ColorType)`

Visibility: default

Description: `SetFillStyle` sets the filling pattern and color to one of the predefined filling patterns. `Pattern` can be one of the following predefined constants :

EmptyFill Uses backgroundcolor.

SolidFill Uses filling color

LineFill Fills with horizontal lines.

ltSlashFill Fills with lines from left-under to top-right.

SlashFill Idem as previous, thick lines.

BkSlashFill Fills with thick lines from left-Top to bottom-right.

LtBkSlashFill Idem as previous, normal lines.

HatchFill Fills with a hatch-like pattern.

XHatchFill Fills with a hatch pattern, rotated 45 degrees.

InterLeaveFill

WideDotFill Fills with dots, wide spacing.

CloseDotFill Fills with dots, narrow spacing.

UserFill Fills with a user-defined pattern.

Errors: None.

See also: [SetFillPattern \(891\)](#), [SetWriteMode \(895\)](#)

56.14.57 SetGraphMode

Synopsis: Set graphical mode

Declaration: `procedure SetGraphMode (Mode: SmallInt)`

Visibility: default

Description: `SetGraphMode` sets the graphical mode and clears the screen.

Errors: None.

See also: [InitGraph \(886\)](#)

56.14.58 SetLineStyle

Synopsis: Set line drawing style

Declaration: `procedure SetLineStyle (LineStyle: Word; Pattern: Word; Thickness: Word)`

Visibility: default

Description: `SetLineStyle` sets the drawing style for lines. You can specify a `LineStyle` which is one of the following predefined constants:

SolidLn Draws a solid line.

DottedLn Draws a dotted line.

CenterLn Draws a non-broken centered line.

DashedLn Draws a dashed line.

UserBitLn Draws a User-defined bit pattern.

If `UserBitLn` is specified then `Pattern` contains the bit pattern. In all another cases, `Pattern` is ignored. The parameter `Width` indicates how thick the line should be. You can specify one of the following predefined constants:

NormWidth Normal line width

ThickWidth Double line width

Errors: None.

See also: [GetLineSettings \(882\)](#), [SetWriteMode \(895\)](#)

56.14.59 SetPalette

Synopsis: Set palette entry using color constant

Declaration: `procedure SetPalette (ColorNum: Word; Color: ShortInt)`

Visibility: default

Description: `SetPalette` changes the `ColorNr`-th entry in the palette to `NewColor`

Errors: None.

See also: `SetAllPalette` (876), `SetRGBPalette` (877)

56.14.60 SetTextJustify

Synopsis: Set text placement style

Declaration: `procedure SetTextJustify (horiz: Word; vert: Word)`

Visibility: default

Description: `SetTextJustify` controls the placement of new text, relative to the (graphical) cursor position. `Horizontal` controls horizontal placement, and can be one of the following predefined constants:

LeftTextText is set left of the pointer.

CenterTextText is set centered horizontally on the pointer.

RightTextText is set to the right of the pointer.

`Vertical` controls the vertical placement of the text, relative to the (graphical) cursor position. Its value can be one of the following predefined constants :

BottomTextText is placed under the pointer.

CenterTextText is placed centered vertically on the pointer.

TopTextText is placed above the pointer.

Errors: None.

See also: `OutText` (888), `OutTextXY` (876)

56.14.61 SetTextStyle

Synopsis: Set text style

Declaration: `procedure SetTextStyle (font: Word; direction: Word; charsize: Word)`

Visibility: default

Description: `SetTextStyle` controls the style of text to be put on the screen. predefined constants for `Font` are:

DefaultFontThe default font

TriplexFontA special font

SmallFontA smaller font

SansSerifFontA sans-serif font (like Arial)

GothicFontA gothic font

ScriptFontA script font

SimpleFontA simple font

TSCRFonTerminal screen font

LCOMFont?

EuroFont?

BoldFontA bold typeface font

predefined constants for `Direction` are :

HorizDirWrite horizontal

VertDirWrite vertical

Errors: None.

See also: `GetTextSettings` ([884](#))

56.14.62 SetUserCharSize

Synopsis: Set user character size for vector font

Declaration: `procedure SetUserCharSize (Multx: Word; Divx: Word; Multy: Word;
Divy: Word)`

Visibility: default

Description: Sets the width and height of vector-fonts. The horizontal size is given by `Xasp1/Xasp2`, and the vertical size by `Yasp1/Yasp2`.

Errors: None.

See also: `SetTextStyle` ([893](#))

56.14.63 SetViewPort

Synopsis: Set the graphical drawing window

Declaration: `procedure SetViewPort (X1: SmallInt; Y1: SmallInt; X2: SmallInt;
Y2: SmallInt; Clip: Boolean)`

Visibility: default

Description: Sets the current graphical viewport (window) to the rectangle defined by the top-left corner `(X1, Y1)` and the bottom-right corner `(X2, Y2)`. If `Clip` is true, anything drawn outside the viewport (window) will be clipped (i.e. not drawn). Coordinates specified after this call are relative to the top-left corner of the viewport.

Errors: None.

See also: `GetViewSettings` ([884](#))

56.14.64 SetWriteMode

Synopsis: Specify binary operation to perform when drawing on screen

Declaration: `procedure SetWriteMode (WriteMode: SmallInt)`

Visibility: default

Description: `SetWriteMode` controls the drawing of lines on the screen. It controls the binary operation used when drawing lines on the screen. Mode can be one of the following predefined constants:

CopyPutDraw as specified using current bitmask and color

XORPutDraw XOR-ing current bitmask and color

Errors: None.

See also: `SetColor` (891), `SetBkColor` (876), `SetLineStyle` (892), `SetFillStyle` (891)

56.14.65 SetWriteModeEx

Synopsis: Set write mode (extended version)

Declaration: `procedure SetWriteModeEx (WriteMode: SmallInt)`

Visibility: default

Description: `SetWriteModeEx` sets the graph write mode similar to `SetWriteMode` (895) but only if the `WriteMode` is in the range `CopyPut..NotPut`. If the provided value is outside this range, it is not set.

See also: `SetWriteMode` (895)

56.14.66 TextHeight

Synopsis: Return height (in pixels) of the given string

Declaration: `function TextHeight (const TextString: string) : Word`

Visibility: default

Description: `TextHeight` returns the height (in pixels) of the string `S` in the current font and text-size.

Errors: None.

See also: `TextWidth` (895)

56.14.67 TextWidth

Synopsis: Return width (in pixels) of the given string

Declaration: `function TextWidth (const TextString: string) : Word`

Visibility: default

Description: `TextWidth` returns the width (in pixels) of the string `S` in the current font and text-size.

Errors: None.

See also: `TextHeight` (895)

56.15 ArcCoordsType

```
ArcCoordsType = record
  x : SmallInt;
  y : SmallInt;
  xstart :
    SmallInt;
  ystart : SmallInt;
  xend : SmallInt;
  yend : SmallInt
;
end
```

Describe the last arc which was drawn on screen

56.16 FillSettingsType

```
FillSettingsType = record
  pattern : Word;
  color : ColorType;
end
```

Record describing fill mode

56.17 LineSettingsType

```
LineSettingsType = record
  linestyle : Word;
  pattern : Word;
  thickness : Word;
end
```

Record describing current line drawing mode

56.18 PaletteType

```
PaletteType = record
  Size : LongInt;
  Colors : Array[0..MaxColors
] of RGBRec;
end
```

Record describing palette.

56.19 PointType

```
PointType = record
```

```

    x : SmallInt;
    y : SmallInt;
end

```

Record describing a point in a 2 dimensional plane

56.20 RGBRec

```

RGBRec = packed record
    Red : SmallInt;
    Green : SmallInt;
    Blue
    : SmallInt;
end

```

Record describing palette RGB color

56.21 TextSettingsType

```

TextSettingsType = record
    font : Word;
    direction : Word;
    charsize
    : Word;
    horiz : Word;
    vert : Word;
end

```

Record describing how texts are drawn.

56.22 TModeInfo

```

TModeInfo = record
    DriverNumber : SmallInt;
    ModeNumber : SmallInt
    ;
    internModeNumber : SmallInt;
    MaxColor : LongInt;
    PaletteSize
    : LongInt;
    XAspect : Word;
    YAspect : Word;
    MaxX : Word;
    MaxY
    : Word;
    DirectColor : Boolean;
    Hardwarepages : Byte;
    ModeName

```

```

: string;
DirectPutPixel : defpixelproc;
GetPixel : getpixelproc
;
PutPixel : putpixelproc;
SetRGBPalette : setrgbpaletteproc;
GetRGBPalette : getrgbpaletteproc;
SetAllPalette : SetAllPaletteProc
;
SetVisualPage : setvisualpageproc;
SetActivePage : setactivepageproc
;
ClearViewPort : clrviewproc;
PutImage : putimageproc;
GetImage
: getimageproc;
ImageSize : imagesizeproc;
GetScanLine : getscanlineproc
;
Line : lineproc;
InternalEllipse : ellipseproc;
PatternLine
: patternlineproc;
HLine : hlineproc;
VLine : vlineproc;
Circle
: CircleProc;
InitMode : initmodeproc;
OutTextXY : OutTextXYProc
;
SetBKColor : SetBkColorProc;
GetBKColor : GetBkColorProc;
next : PModeInfo;
end

```

Record describing a graphical mode.

56.23 TResolutionRec

```

TResolutionRec = record
  x : LongInt;
  y : LongInt;
end

```

Record describing resolution

56.24 ViewPortType

```

ViewPortType = record
  x1 : SmallInt;

```

```
y1 : SmallInt;  
x2 : SmallInt  
;  
y2 : SmallInt;  
Clip : Boolean;  
end
```

Record describing a viewport

Chapter 57

Reference for unit 'heaptrc'

57.1 Used units

Table 57.1: Used units by unit 'heaptrc'

Name	Page
System	1339

57.2 Overview

This document describes the HEAPTRC unit for Free Pascal. It was written by Pierre Muller. It is system independent, and works on all supported systems.

The HEAPTRC unit can be used to debug your memory allocation/deallocation. It keeps track of the calls to `getmem/freemem`, and, implicitly, of `New/Dispose` statements.

When the program exits, or when you request it explicitly. It displays the total memory used, and then dumps a list of blocks that were allocated but not freed. It also displays where the memory was allocated.

If there are any inconsistencies, such as memory blocks being allocated or freed twice, or a memory block that is released but with wrong size, this will be displayed also.

The information that is stored/displayed can be customized using some constants.

Do not use this unit directly, instead use the `-gh` switch, to let the compiler insert the unit in the `uses` clause.

57.3 Controlling HeapTrc with environment variables

The `HeapTrc` unit can be controlled with the `HEAPTRC` environment variable. The contents of this variable controls the initial setting of some constants in the unit. `HEAPTRC` consists of one or more of the following strings, separated by spaces:

keepreleased If this string occurs, then the `KeepReleased` ([902](#)) variable is set to `True`

disabled If this string occurs, then the `UseHeapTrace` ([903](#)) variable is set to `False` and the heap trace is disabled. It does not make sense to combine this value with other values.

nohalt If this string occurs, then the `HaltOnError` (902) variable is set to `False`, so the program continues executing even in case of a heap error.

log=filename If this string occurs, then the output of `heaptrc` is sent to the specified `Filename`. (see also `SetHeapTraceOutput` (906))

The following are valid values for the `HEAPTRC` variable:

```
HEAPTRC=disabled
HEAPTRC="keepreleased log=heap.log"
HEAPTRC="log=myheap.log nohalt"
```

Note that these strings are case sensitive, and the name of the variable too.

57.4 HeapTrc Usage

You must use the `-gh` switch, to let the compiler insert the unit by itself, so you don't have to include it in your `uses` clause. In fact, as of version 3.0.0 you may no longer do so.

The below example shows how to use the `heaptrc` unit.

This is the memory dump shown when running this program in a standard way:

```
Marked memory at 0040FA50 invalid
Wrong size : 128 allocated 64 freed
  0x00408708
  0x0040CB49
  0x0040C481
Call trace for block 0x0040FA50 size 128
  0x0040CB3D
  0x0040C481
```

If you use the `lineinfo` unit (or use the `-gl` switch) as well, then `heaptrc` will also give you the filenames and line-numbers of the procedures in the backtrace:

```
Marked memory at 00410DA0 invalid
Wrong size : 128 allocated 64 freed
  0x004094B8
  0x0040D8F9  main,   line 25 of heapex.pp
  0x0040D231
Call trace for block 0x00410DA0 size 128
  0x0040D8ED  main,   line 23 of heapex.pp
  0x0040D231
```

If lines without filename/line-number occur, this means there is a unit which has no debug info included.

Listing: `./examples/heapex/heapex.pp`

Program `heapex`;

```
{
  Program used to demonstrate the usage of heaptrc unit
  Compile this program with the -gh command-line option
}
```

```

Var P1 : ^Longint;
      P2 : Pointer;
      I : longint;

begin
  {$IF NOT DECLARED(heaptrc)}
  {$ERROR You must compile this program with -gh}
  {$ENDIF}
  New(P1);
  // causes previous allocation not to be de-allocated
  New(P1);
  Dispose(P1);
  For I:=1 to 10 do
    begin
      GetMem (P2,128);
      // When I is even, deallocate block. We loose 5 times 128
      // bytes this way.
      If (I mod 2) = 0 Then FreeMem(P2,128);
    end;
    GetMem(P2,128);
    // This will provoke an error and a memory dump
    FreeMem (P2,64);
  end.

```

57.5 Constants, types and variables

57.5.1 Constants

```
add_tail : Boolean = True
```

If `add_tail` is `True` (the default) then a check is also performed on the memory location just behind the allocated memory.

```
GlobalSkipIfNoLeaks : Boolean = False
```

`GlobalSkipIfNoLeaks` will, when set to `true`, disable the output of the `heaptrc` unit if no memory leaks will be detected, i.e. there will only be output if there were actual memory leaks.

```
HaltOnError : Boolean = True
```

If `HaltOnError` is set to `True` then an illegal call to `FreeMem` will cause the memory manager to execute a `halt (1)` instruction, causing a memory dump. By Default it is set to `True`.

```
HaltOnNotReleased : Boolean = False
```

`HaltOnNotReleased` can be set to `True` to make the `DumpHeap` (904) procedure halt (exit code 203) the program if any memory was not released when the dump is made. If it is `False` (the default) then `DumpHeap` just returns.

```
keepreleased : Boolean = False
```

If `keepreleased` is set to `true`, then a list of freed memory blocks is kept. This is useful if you suspect that the same memory block is released twice. However, this option is very memory intensive, so use it sparingly, and only when it's really necessary.

```
maxprintedblocklength : Integer = 128
```

`maxprintedblocklength` determines the maximum number of bytes written by a memory block dump, as produced when `printleakedblock` (903) or `printfaultyblock` (903) are true. If the size of the memory block is larger than this size, then only the first `maxprintedblocklength` will be included in the dump.

```
printfaultyblock : Boolean = False
```

`printleakedblock` can be set to `True` to print a memory dump of faulty memory blocks (in case a memory override occurs) The block is printed as a series of hexadecimal numbers, representing the bytes in the memory block. At most `maxprintedblocklength` (903) bytes of the memory block will be printed.

```
printleakedblock : Boolean = False
```

`printleakedblock` can be set to `True` to print a memory dump of unreleased blocks when the `heaptrc` unit produces a summary of memory leaks. The block is printed as a series of hexadecimal numbers, representing the bytes in the memory block. At most `maxprintedblocklength` (903) bytes of the memory block will be printed.

```
quicktrace : Boolean = True
```

`Quicktrace` determines whether the memory manager checks whether a block that is about to be released is allocated correctly. This is a rather time consuming search, and slows program execution significantly, so by default it is set to `True`.

```
tail_size : LongInt = sizeof(ptruint)
```

This is the size of the tail block added to every memory block when `add_tail` (902) is `True`.

```
tracesize = 16
```

`Tracesize` specifies how many levels of calls are displayed of the call stack during the memory dump. If you specify `keepreleased:=True` then half the `TraceSize` is reserved for the `GetMem` call stack, and the other half is reserved for the `FreeMem` call stack. For example, the default value of 8 will cause eight levels of call frames to be dumped for the `getmem` call if `keepreleased` is `False`. If `KeepReleased` is `true`, then 4 levels of call frames will be dumped for the `GetMem` call and 4 frames will be dumped for the `FreeMem` call. If you want to change this value, you must recode the `heaptrc` unit.

```
usecrc : Boolean = True
```

If `usecrc` is `True` (the default) then a crc check is performed on locations before and after the allocated memory. This is useful to detect memory overwrites.

```
useheaptrace : Boolean = True
```

This variable must be set at program startup, through the help of an environment variable.

57.5.2 Types

```
tdisplayextrainfoProc = procedure(var ptext: text; p: pointer)
```

The `TDisplayExtraInfoType` is a procedural type used in the `SetHeapExtraInfo` (904) call to display a memory location which was previously filled with `TFillExtraInfoProc` (904)

```
tFillExtraInfoProc = procedure(p: pointer)
```

The `TFillExtraInfoProc` is a procedural type used in the `SetHeapExtraInfo` (904) call to fill a memory location with extra data for displaying.

57.6 Procedures and functions

57.6.1 CheckPointer

Synopsis: Check if a pointer is in the address range of the application

Declaration: `procedure CheckPointer(p: pointer)`

Visibility: default

Description: `CheckPointer` checks if the pointer is in the address range of the application, more specifically, if it is in the heap. if not, it prints an error and stops the program with aruntime error 204.

57.6.2 DumpHeap

Synopsis: Dump memory usage report to stderr.

Declaration: `procedure DumpHeap`
`procedure DumpHeap(SkipIfNoLeaks: Boolean)`

Visibility: default

Description: `DumpHeap` dumps to standard error a summary of memory usage. It is called automatically by the `heaptrc` unit when your program exits (by installing an exit procedure), but it can be called at any time.

Errors: None.

57.6.3 SetHeapExtraInfo

Synopsis: Store extra information in blocks.

Declaration: `procedure SetHeapExtraInfo(size: PtrUInt; fillproc: tFillExtraInfoProc;`
`displayproc: tdisplayextrainfoProc)`

Visibility: default

Description: You can use `SetHeapExtraInfo` to store extra info in the blocks that the `heaptrc` unit reserves when tracing `getmem` calls. `Size` indicates the size (in bytes) that the trace mechanism should reserve for your extra information. For each call to `getmem`, `FillProc` will be called, and passed a pointer to the memory reserved.

When dumping the memory summary, the extra info is shown by calling `displayproc` and passing it the memory location which was filled by `fillproc`. It should write the information in readable form to the text file provided in the call to `displayproc`

Errors: You can only call `SetHeapExtraInfo` if no memory has been allocated yet. If memory was already allocated prior to the call to `SetHeapExtraInfo`, then an error will be displayed on standard error output, and a `DumpHeap` (904) is executed.

See also: `DumpHeap` (904), `SetHeapTraceOutput` (906)

Listing: ./examples/heapex/setinfo.pp

Program heapex;

{ Program used to demonstrate the usage of heaptrc unit }

Uses heaptrc;

Var P1 : ^Longint;
 P2 : Pointer;
 I : longint;
 Marker : Longint;

Procedure SetMarker (P : pointer);

Type PLongint = ^Longint;

begin
 PLongint(P)^:=Marker;
end;

Procedure Part1;

begin
 // Blocks allocated here are marked with \$FFAAFFAA = -5570646
 Marker := \$FFAAFFAA;
 New(P1);
 New(P1);
 Dispose(P1);
 For I:=1 to 10 do
 begin
 GetMem (P2,128);
 If (I mod 2) = 0 Then FreeMem(P2,128);
 end;
 GetMem(P2,128);
end;

Procedure Part2;

begin
 // Blocks allocated here are marked with \$FAFAFAFA = -84215046
 Marker := \$FAFAFAFA;
 New(P1);
 New(P1);
 Dispose(P1);
 For I:=1 to 10 do
 begin
 GetMem (P2,128);
 If (I mod 2) = 0 Then FreeMem(P2,128);
 end;
 GetMem(P2,128);
end;

```
begin
  SetExtraInfo ( SizeOf (Marker) , @SetMarker );
  Writeln ( 'Part 1' );
  part1;
  Writeln ( 'Part 2' );
  part2;
end.
```

57.6.4 SetHeapTraceOutput

Synopsis: Specify filename or text file for heap trace output.

Declaration: `procedure SetHeapTraceOutput(const name: string); Overload`
`procedure SetHeapTraceOutput(var ATextOutput: Text); Overload`

Visibility: default

Description: `SetHeapTraceOutput` using the `name` argument sets the filename into which heap trace info will be written. You can also use the `ATextOutput` form, where you pass an initialized text file record, this record will then be used to write the heap trace.

By default information is written to standard error, this function allows you to redirect the information to a file with full filename `name` or a text file `ATextOutput`.

Errors: If the file cannot be written to, errors will occur when writing the trace.

See also: `SetHeapExtraInfo` ([904](#))

Chapter 58

Reference for unit 'ipc'

58.1 Used units

Table 58.1: Used units by unit 'ipc'

Name	Page
BaseUnix	141
System	1339
unixtype	2127

58.2 Overview

This document describes the IPC unit for Free Pascal. It was written for Linux by Michael Van Canneyt. It gives all the functionality of System V Inter-Process Communication: shared memory, semaphores and messages. It works only on the Linux operating system.

Many constants here are provided for completeness only, and should under normal circumstances not be used by the programmer.

58.3 Constants, types and variables

58.3.1 Constants

`IPC_CREAT = 1 shl 9`

Create if key is nonexistent

`IPC_EXCL = 2 shl 9`

fail if key exists

`IPC_INFO = 3`

For ipcs call

IPC_NOWAIT = 4 shl 9

return error on wait

IPC_PRIVATE = Tkey(0)

IPC_RMID = 0

Remove resource

IPC_SET = 1

set ipc_perm options

IPC_STAT = 2

get ipc_perm options

MSGMAX = 4056

Internal Message control code. Do not use

MSGMNB = 16384

Internal Message control code. Do not use

MSGMNI = 128

Internal Message control code. Do not use

MSG_EXCEPT = 2 shl 12

Internal Message control code. Do not use

MSG_NOERROR = 1 shl 12

Internal Message control code. Do not use

SEM_GETALL = 13

Semaphore operation: Get all semaphore values

SEM_GETNCNT = 14

Semaphore operation: Get number of processes waiting for resource.

SEM_GETPID = 11

Semaphore operation: Get process ID of last operation.

SEM_GETVAL = 12

Semaphore operation: Get current value of semaphore

SEM_GETZCNT = 15

Semaphore operation: Get number of processes waiting for semaphores to reach zero

SEM_SEMMNI = 128

Semaphore operation: ?

SEM_SEMNS = SEM_SEMMNI * SEM_SEMMSL

Semaphore operation: ?

SEM_SEMMSL = 32

Semaphore operation: ?

SEM_SEMOPM = 32

Semaphore operation: ?

SEM_SEVMX = 32767

Semaphore operation: ?

SEM_SETALL = 17

Semaphore operation: Set all semaphore values

SEM_SETVAL = 16

Semaphore operation: Set semaphore value

SEM_UNDO = \$1000

Constant for use in semop ([921](#))

SHM_LOCK = 11

This constant is used in the shmctl ([923](#)) call.

SHM_R = 4 shl 6

This constant is used in the shmctl ([923](#)) call.

SHM_RDONLY = 1 shl 12

This constant is used in the shmctl ([923](#)) call.

`SHM_REMAP = 4 shl 12`

This constant is used in the `shmctl` (923) call.

`SHM_RND = 2 shl 12`

This constant is used in the `shmctl` (923) call.

`SHM_UNLOCK = 12`

This constant is used in the `shmctl` (923) call.

`SHM_W = 2 shl 6`

This constant is used in the `shmctl` (923) call.

58.3.2 Types

`key_t = TKey`

Alias for `TKey` (911) type

`msglen_t = culong`

Message length type

`msgqnum_t = culong`

Message queue number type

`PIPC_Perm = ^TIPC_Perm`

Pointer to `TIPC_Perm` (926) record.

`PMSG = ^TMSG`

Pointer to `TMSG` (926) record

`PMSGbuf = ^TMSGbuf`

Pointer to `TMsgBuf` (926) record

`PMSQid_ds = ^TMSQid_ds`

Pointer to `TMSQid_ds` (927)

`PSEMBuf = ^TSEMBuf`

Pointer to `TSembuf` (927) record.

```
PSEMid_ds = ^TSEMid_ds
```

Pointer to TSEMid_ds (928) record.

```
PSEMinfo = ^TSEMinfo
```

Pointer to TSEMinfo (928) record.

```
PSEMun = ^TSEMun
```

Pointer to TSEMun (911) record

```
PShmid_DS = ^TShmid_ds
```

Pointer to TSHMid_ds (928) record.

```
PSHM_info = ^TSHM_info
```

```
TKey = cint
```

Type returned by the ftok (911) key generating function.

```
TSEMun = record
case cint of
0: (
    val : cint;
);
1: (
    buf : PSEMid_ds
    ;
);
2: (
    arr : PWord;
);
3: (
    padbuf : PSEMinfo;
);
4: (
    padpad
    : pointer;
);
end
```

Record used in semctl (916) call.

58.4 Procedures and functions

58.4.1 ftok

Synopsis: Create token from filename

Declaration: `function ftok(Path: PChar; ID: cint) : TKey`

Visibility: `default`

Description: `ftok` returns a key that can be used in a `semget` (921), `shmget` (925) or `msgget` (914) call to access a new or existing IPC resource.

`Path` is the name of a file in the file system, `ID` is a character of your choice. The `ftok` call does the same as it's C counterpart, so a pascal program and a C program will access the same resource if they use the same `Path` and `ID`.

For an example, see `msgctl` (912), `semctl` (916) or `shmctl` (923).

Errors: `ftok` returns -1 if the file in `Path` doesn't exist.

See also: `semget` (921), `shmget` (925), `msgget` (914)

58.4.2 msgctl

Synopsis: Perform various operations on a message queue

Declaration: `function msgctl(msqid: cint; cmd: cint; buf: PMSQid_ds) : cint`

Visibility: `default`

Description: `msgctl` performs various operations on the message queue with id `ID`. Which operation is performed, depends on the `cmd` parameter, which can have one of the following values:

IPC_STAT In this case, the `msgctl` call fills the `TMSQid_ds` structure with information about the message queue.

IPC_SET In this case, the `msgctl` call sets the permissions of the queue as specified in the `ipc_perm` record inside `buf`.

IPC_RMID If this is specified, the message queue will be removed from the system.

`buf` contains the data that are needed by the call. It can be `Nil` in case the message queue should be removed.

The function returns `True` if success full, `False` otherwise.

Errors: On error, `False` is returned, and `IPCError` is set accordingly.

See also: `msgget` (914), `msgsnd` (915), `msgrcv` (915)

Listing: `./examples/ipcex/msgtool.pp`

program `msgtool`;

Uses `ipc`, `baseunix`;

Type

```
PMyMsgBuf = ^TMyMsgBuf;
TMyMsgBuf = record
  mtype : Longint;
  mtext : string[255];
end;
```

Procedure `DoError (Const Msg : string);`

begin

```
  WriteLn (msg, ' returned an error : ', fpgeterrno);
```

```

    halt(1);
end;

Procedure SendMessage (Id : Longint;
                        Var Buf : TMyMsgBuf;
                        MType : Longint;
                        Const MText : String);

begin
    Writeln ('Sending message. ');
    Buf.mtype:=mtype;
    Buf.Mtext:=mtext;
    If msgsnd(Id, PMsgBuf(@Buf), 256, 0)=-1 then
        DoError('msgsnd');
end;

Procedure ReadMessage (ID : Longint;
                       Var Buf : TMyMsgBuf;
                       MType : longint);

begin
    Writeln ('Reading message. ');
    Buf.MType:=MType;
    If msgrcv(ID, PMSGBuf(@Buf), 256, mtype, 0)<>-1 then
        Writeln ('Type : ', buf.mtype, ' Text : ', buf.mtext)
    else
        DoError ('msgrcv');
end;

Procedure RemoveQueue ( ID : Longint);

begin
    If msgctl (id, IPC_RMID, Nil)<>-1 then
        Writeln ('Removed Queue with id ', Id);
end;

Procedure ChangeQueueMode (ID, mode : longint);

Var QueueDS : TMSQid_ds;

begin
    If msgctl (Id, IPC_STAT, @QueueDS)=-1 then
        DoError ('msgctl : stat');
    Writeln ('Old permissions : ', QueueDS.msg_perm.mode);
    QueueDS.msg_perm.mode:=Mode;
    if msgctl (ID, IPC_SET, @QueueDS)=0 then
        Writeln ('New permissions : ', QueueDS.msg_perm.mode)
    else
        DoError ('msgctl : IPC_SET');
end;

procedure usage;

begin
    Writeln ('Usage : msgtool s(end) <type> <text> (max 255 characters)');
    Writeln ('          r(eceive) <type>');
    Writeln ('          d(etele)');
    Writeln ('          m(ode) <decimal mode>');

```

```

    halt(1);
end;

Function StrToInt (S : String): longint;

Var M : longint;
    C : Integer;

begin
    val (S,M,C);
    If C<>0 Then DoError ('StrToInt : '+S);
    StrToInt:=M;
end;

Var
    Key : TKey;
    ID : longint;
    Buf : TMyMsgBuf;

const ipckey = '.'#0;

begin
    If Paramcount<1 then Usage;
    key := Ftok (@ipckey[1], ord('M'));
    ID:=msgget(key,IPC_CREAT or 438);
    If ID<0 then DoError ('MsgGet');
    Case upCase(Paramstr(1)[1]) of
        'S' : If ParamCount<>3 then
            Usage
        else
            SendMessage (id, Buf, StrToInt(Paramstr(2)), paramstr(3));
        'R' : If ParamCount<>2 then
            Usage
        else
            ReadMessage (id, buf, strtoint(Paramstr(2)));
        'D' : If ParamCount<>1 then
            Usage
        else
            RemoveQueue (ID);
        'M' : If ParamCount<>2 then
            Usage
        else
            ChangeQueueMode (id, strtoint(paramstr(2)));
    else
        Usage
    end;
end.

```

58.4.3 msgget

Synopsis: Return message queue ID, possibly creating the queue

Declaration: `function msgget(key: TKey; msgflg: cint) : cint`

Visibility: default

Description: `msgget` returns the ID of the message queue described by `key`. Depending on the flags in `msgflg`, a new queue is created.

`msgflg` can have one or more of the following values (combined by ORs):

IPC_CREAT The queue is created if it doesn't already exist.

IPC_EXCL If used in combination with `IPC_CREAT`, causes the call to fail if the queue already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

For an example, see `msgctl` (912).

Errors: On error, -1 is returned, and `IPCError` is set.

See also: `ftok` (911), `msgsnd` (915), `msgrcv` (915), `msgctl` (912)

58.4.4 msgrcv

Synopsis: Retrieve a message from the queue

Declaration: `function msgrcv(msqid: cint; msgp: PMSGbuf; msgsz: size_t; msgtyp: clong; msgflg: cint) : cint`

Visibility: default

Description: `msgrcv` retrieves a message of type `msgtyp` from the message queue with ID `msqid`. `msgtyp` corresponds to the `mtype` field of the `TMSGbuf` record. The message is stored in the `MSGbuf` structure pointed to by `msgp`.

The `msgflg` parameter can be used to control the behaviour of the `msgrcv` call. It consists of an ORed combination of the following flags:

0 No special meaning.

IPC_NOWAIT If no messages are available, then the call returns immediately, with the `ENOMSG` error.

MSG_NOERROR If the message size is wrong (too large), no error is generated, instead the message is truncated. Normally, in such cases, the call returns an error (`E2BIG`)

The function returns `True` if the message was received correctly, `False` otherwise.

For an example, see `msgctl` (912).

Errors: In case of error, `False` is returned, and `IPCError` is set.

See also: `msgget` (914), `msgsnd` (915), `msgctl` (912)

58.4.5 msgsnd

Synopsis: Send a message to the message queue

Declaration: `function msgsnd(msqid: cint; msgp: PMSGbuf; msgsz: size_t; msgflg: cint) : cint`

Visibility: default

Description: `msgsnd` sends a message to a message queue with ID `msqid`. `msgp` is a pointer to a message buffer, that should be based on the `TMsgBuf` type. `msgsz` is the size of the message (NOT of the message buffer record !)

The `msgflg` can have a combination of the following values (ORed together):

0No special meaning. The message will be written to the queue. If the queue is full, then the process is blocked.

IPC_NOWAITIf the queue is full, then no message is written, and the call returns immediately.

The function returns `True` if the message was sent successfully, `False` otherwise.

For an example, see `msgctl` (912).

Errors: In case of error, the call returns `False`, and `IPCError` is set.

See also: `msgget` (914), `msgrcv` (915), `msgctl` (912)

58.4.6 `semctl`

Synopsis: Perform various control operations on a semaphore set

Declaration: `function semctl(semid: cint; semnum: cint; cmd: cint; var arg: TSEMun) : cint`

Visibility: `default`

Description: `semctl` performs various operations on the semaphore `semnum` with semaphore set id `ID`.

The `arg` parameter supplies the data needed for each call. This is a variant record that should be filled differently, according to the command:

```
Type
TSEMun = record
  case longint of
    0 : ( val : longint );
    1 : ( buf : PSEMid_ds );
    2 : ( arr : PWord );
    3 : ( padbuf : PSeminfo );
    4 : ( padpad : pointer );
  end;
```

Which operation is performed, depends on the `cmd` parameter, which can have one of the following values:

IPC_STATIn this case, the `arg` record should have its `buf` field set to the address of a `TSEMid_ds` record. The `semctl` call fills this `TSEMid_ds` structure with information about the semaphore set.

IPC_SETIn this case, the `arg` record should have its `buf` field set to the address of a `TSEMid_ds` record. The `semctl` call sets the permissions of the queue as specified in the `ipc_perm` record.

IPC_RMIDIf this is specified, the semaphore set is removed from the system.

GETALLIn this case, the `arr` field of `arg` should point to a memory area where the values of the semaphores will be stored. The size of this memory area is `SizeOf(Word) * Number of semaphores in the set`. This call will then fill the memory array with all the values of the semaphores.

GETNCNTThis will fill the `val` field of the `arg` union with the number of processes waiting for resources.

GETPID`semctl` returns the process ID of the process that performed the last `semop` (921) call.

GETVAL`semctl` returns the value of the semaphore with number `semnum`.

GETZCNT `semctl` returns the number of processes waiting for semaphores that reach value zero.

SETALL In this case, the `arr` field of `arg` should point to a memory area where the values of the semaphores will be retrieved from. The size of this memory area is `SizeOf(Word) * Number of semaphores in the set`. This call will then set the values of the semaphores from the memory array.

SETVAL This will set the value of semaphore `semnum` to the value in the `val` field of the `arg` parameter.

The function returns -1 on error.

Errors: The function returns -1 on error, and `IPCError` is set accordingly.

See also: `semget` (921), `semop` (921)

Listing: `./examples/ipcex/semtool.pp`

```

Program semtool;

{ Program to demonstrate the use of semaphores }

Uses ipc,baseunix;

Const MaxSemValue = 5;

Procedure DoError (Const Msg : String);
var
  error: cint;
begin
  error:=fpgeterrno;
  WriteLn ('Error : ',msg,' Code : ',error);
  Halt(1);
end;

Function getsemval (ID,Member : longint) : longint;

Var S : TSEMun;

begin
  GetSemVal:=SemCtl(id ,member,SEM_GETVAL,S);
end;

Procedure DispVal (ID,member : longint);

begin
  writeln ('Value for member ',member,' is ',GetSemVal(ID ,Member));
end;

Function GetMemberCount (ID : Longint) : longint;

Var opts : TSEMun;
    semds : TSEMids;

begin
  opts.buf:=@semds;
  If semctl(Id,0,IPC_STAT,opts)<>-1 then
    GetMemberCount:=semds.sem_nsems
  else
    GetMemberCount:=-1;

```

```

end;

Function OpenSem (Key : TKey) : Longint;

begin
  OpenSem:=semget(Key,0,438);
  If OpenSem=-1 then
    DoError ('OpenSem');
end;

Function CreateSem (Key : TKey; Members : Longint) : Longint;

Var Count : Longint;
    Semopts : TSemun;

begin
  // the semmsl constant seems kernel specific
  { If members>semmsl then
    DoError ('Sorry, maximum number of semaphores in set exceeded');
  }
  WriteLn ('Trying to create a new semaphore set with ',members,' members. ');
  CreateSem:=semget(key,members,IPC_CREAT or IPC_Excl or 438);
  If CreateSem=-1 then
    DoError ('Semaphore set already exists. ');
  Semopts.val:=MaxSemValue; { Initial value of semaphores }
  For Count:=0 to Members-1 do
    semctl(CreateSem,count,SEM_SETVAL,semopts);
end;

Procedure lockSem (ID,Member: Longint);

Var lock : TSEMbuf;

begin
  With lock do
    begin
      sem_num:=0;
      sem_op:=-1;
      sem_flg:=IPC_NOWAIT;
    end;
    if (member<0) or (member>GetMemberCount(ID)-1) then
      DoError ('semaphore member out of range');
    if getsemval(ID,member)=0 then
      DoError ('Semaphore resources exhausted (no lock)');
    lock.sem_num:=member;
    WriteLn ('Attempting to lock member ',member, ' of semaphore ',ID);
    if semop(Id,@lock,1)=-1 then
      DoError ('Lock failed')
    else
      WriteLn ('Semaphore resources decremented by one');
      dispval(ID,Member);
end;

Procedure UnlockSem (ID,Member: Longint);

Var Unlock : TSEMbuf;

begin

```

```

With Unlock do
  begin
    sem_num:=0;
    sem_op:=1;
    sem_flg:=IPC_NOWAIT;
  end;
  if (member<0) or (member>GetMemberCount(ID)-1) then
    DoError ('semaphore member out of range');
  if getsemval(ID,member)=MaxSemValue then
    DoError ('Semaphore not locked');
  Unlock.sem_num:=member;
  Writeln ('Attempting to unlock member ',member, ' of semaphore ',ID);
  if semop(Id,@unlock,1)=-1 then
    DoError ('Unlock failed')
  else
    Writeln ('Semaphore resources incremented by one');
    dispval(ID,Member);
end;

Procedure RemoveSem (ID : longint);

var S : TSemun;

begin
  if semctl(Id,0,IPC_RMID,s)<>-1 then
    Writeln ('Semaphore removed')
  else
    DoError ('Couldn't remove semaphore');
end;

Procedure ChangeMode (ID,Mode : longint);

Var rc : longint;
    opts : TSEMun;
    semds : TSEMid_ds;

begin
  opts.buf:=@semds;
  if not semctl (Id,0,IPC_STAT,opts)<>-1 then
    DoError ('Couldn't stat semaphore');
  Writeln ('Old permissions were : ',semds.sem_perm.mode);
  semds.sem_perm.mode:=mode;
  if semctl(id,0,IPC_SET,opts)<>-1 then
    Writeln ('Set permissions to ',mode)
  else
    DoError ('Couldn't set permissions');
end;

Procedure PrintSem (ID : longint);

Var l,cnt : longint;

begin
  cnt:=getmembercount(ID);
  Writeln ('Semaphore ',ID,' has ',cnt,' Members');
  For l:=0 to cnt-1 Do
    DispVal(id,l);

```


end;

Procedure USage;

```
begin
  Writeln ('Usage : semtool c(reate) <count>');
  Writeln ('                l(ock) <member>');
  Writeln ('                u(nlock) <member>');
  Writeln ('                d(etele)');
  Writeln ('                m(ode) <mode>');
  Writeln ('                p(rint)');
  halt(1);
end;
```

Function StrToInt (S : **String**): longint;

```
Var M : longint;
    C : Integer;
```

```
begin
  val (S,M,C);
  If C<>0 Then DoError ('StrToInt : '+S);
  StrToInt:=M;
end;
```

```
Var Key : TKey;
    ID : Longint;
```

const ipckey='.#0;

```
begin
  If ParamCount<1 then USage;
  key:=ftok (@ipckey[1],ORD('s'));
  Case UpCase(Paramstr(1)[1]) of
    'C' : begin
      if paramcount<>2 then usage;
      CreateSem (key, strtoint(paramstr(2)));
      end;
    'L' : begin
      if paramcount<>2 then usage;
      ID:=OpenSem (key);
      LockSem (ID, strtoint(paramstr(2)));
      end;
    'U' : begin
      if paramcount<>2 then usage;
      ID:=OpenSem (key);
      UnLockSem (ID, strtoint(paramstr(2)));
      end;
    'M' : begin
      if paramcount<>2 then usage;
      ID:=OpenSem (key);
      ChangeMode (ID, strtoint(paramstr(2)));
      end;
    'D' : Begin
      ID:=OpenSem(Key);
      RemoveSem(Id);
      end;
```

```

    'P' : begin
        ID:=OpenSem(Key);
        PrintSem(Id);
    end;
else
    Usage
end;
end.

```

58.4.7 semget

Synopsis: Return the ID of a semaphore set, possibly creating the set

Declaration: `function semget(key: TKey; nsems: cint; semflg: cint) : cint`

Visibility: default

Description: `msgget` returns the ID of the semaphore set described by `key`. Depending on the flags in `semflg`, a new queue is created.

`semflg` can have one or more of the following values (combined by ORs):

IPC_CREAT The queue is created if it doesn't already exist.

IPC_EXCL If used in combination with `IPC_CREAT`, causes the call to fail if the set already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

if a new set of semaphores is created, then there will be `nsems` semaphores in it.

Errors: On error, -1 is returned, and `IPCError` is set.

See also: `ftok` (911), `semop` (921), `semctl` (916)

58.4.8 semop

Synopsis: Perform semaphore operation.

Declaration: `function semop(semid: cint; sops: PSEMbuf; nsops: cuint) : cint`

Visibility: default

Description: `semop` performs a set of operations on a message queue. `sops` points to an array of type `TSEMbuf`. The array should contain `nsops` elements.

The fields of the `TSEMbuf` (927) structure

```

TSEMbuf = record
    sem_num : word;
    sem_op  : integer;
    sem_flg : integer;

```

should be filled as follows:

sem_num The number of the semaphore in the set on which the operation must be performed.

sem_op The operation to be performed. The operation depends on the sign of `sem_op`: A positive number is simply added to the current value of the semaphore. If 0 (zero) is specified, then the process is suspended until the specified semaphore reaches zero. If a negative number is specified, it is subtracted from the current value of the semaphore. If the value would become negative then the process is suspended until the value becomes big enough, unless `IPC_NOWAIT` is specified in the `sem_flg`.

sem_flg Optional flags: if `IPC_NOWAIT` is specified, then the calling process will never be suspended.

The function returns `True` if the operations were successful, `False` otherwise.

Errors: In case of error, `False` is returned, and `IPCError` is set.

See also: `semget` (921), `semctl` (916)

58.4.9 semtimedop

Synopsis: Perform semaphore operation using timeout.

Declaration: `function semtimedop(semid: cint; sops: PSEMbuf; nsops: cuint; timeout: timespec) : cint`

Visibility: default

Description: `semop` performs a set of operations on a message queue, just as `semop` (921). `sops` points to an array of type `TSEMbuf`. The array should contain `nsops` elements. The `timeout` argument points to a time specification: if the operations cannot be performed within the specified time, the function will return with an error.

For more information on the actual operations, see `semop` (921).

See also: `semop` (921)

58.4.10 shmat

Synopsis: Attach a shared memory block.

Declaration: `function shmat(shmid: cint; shmaddr: pointer; shmflg: cint) : pointer`

Visibility: default

Description: `shmat` attaches a shared memory block with identified `shmid` to the current process. The function returns a pointer to the shared memory block.

If `shmaddr` is `Nil`, then the system chooses a free unmapped memory region, as high up in memory space as possible.

If `shmaddr` is non-nil, and `SHM_RND` is in `shmflg`, then the returned address is `shmaddr`, rounded down to `SHMLBA`. If `SHM_RND` is not specified, then `shmaddr` must be a page-aligned address.

The parameter `shmflg` can be used to control the behaviour of the `shmat` call. It consists of a ORed combination of the following constants:

SHM_RND The suggested address in `shmaddr` is rounded down to `SHMLBA`.

SHM_RDONLY the shared memory is attached for read access only. Otherwise the memory is attached for read-write. The process then needs read-write permissions to access the shared memory.

For an example, see `shmctl` (923).

Errors: If an error occurs, -1 is returned, and `IPCError` is set.

See also: `shmget` (925), `shmdt` (925), `shmctl` (923)

58.4.11 `shmctl`

Synopsis: Perform control operations on a shared memory block.

Declaration: `function shmctl(shmid: cint; cmd: cint; buf: PShmid_DS) : cint`

Visibility: default

Description: `shmctl` performs various operations on the shared memory block identified by identifier `shmid`.

The `buf` parameter points to a `TSHMid_ds` record. The `cmd` parameter is used to pass which operation is to be performed. It can have one of the following values :

IPC_STAT `shmctl` fills the `TSHMid_ds` record that `buf` points to with the available information about the shared memory block.

IPC_SET applies the values in the `ipc_perm` record that `buf` points to, to the shared memory block.

IPC_RMID the shared memory block is destroyed (after all processes to which the block is attached, have detached from it).

If successful, the function returns `True`, `False` otherwise.

Errors: If an error occurs, the function returns `False`, and `IPCError` is set.

See also: `shmget` (925), `shmat` (922), `shmdt` (925)

Listing: `./examples/ipcex/shmtool.pp`

```

Program shmtool;

uses ipc , strings , Baseunix;

Const SegSize = 100;

var key : Tkey;
    shmid, cntr : longint;
    segptr : pchar;

Procedure USage;

begin
  Writeln ('Usage : shmtool w(rite) text');
  writeln ('          r(ead)');
  writeln ('          d(elete)');
  writeln ('          m(ode change) mode');
  halt(1);
end;

Procedure Writeshm (ID : Longint; ptr : pchar; S : string);

begin
  strcpy (ptr, s);

```

```

end;

Procedure Readshm(ID : longint; ptr : pchar);

begin
  Writeln ('Read : ',ptr);
end;

Procedure removeshm (ID : Longint);

begin
  shmctl (ID,IPC_RMID,Nil);
  writeln ('Shared memory marked for deletion');
end;

Procedure CHangeMode (ID : longint; mode : String);

Var m : word;
    code : integer;
    data : TSHMid_ds;

begin
  val (mode,m,code);
  if code<>0 then
    usage;
  If shmctl (shmctl,IPC_STAT,@data)=-1 then
    begin
      writeln ('Error : shmctl : ',fpgeterrno);
      halt(1);
    end;
  writeln ('Old permissions : ',data.shm_perm.mode);
  data.shm_perm.mode:=m;
  If shmctl (shmctl,IPC_SET,@data)=-1 then
    begin
      writeln ('Error : shmctl : ',fpgeterrno);
      halt(1);
    end;
  writeln ('New permissions : ',data.shm_perm.mode);
end;

const ftokpath = '.'#0;

begin
  if paramcount<1 then usage;
  key := ftok (pchar(@ftokpath[1]),ord('S'));
  shmctl := shmget(key,segsz,IPC_CREAT or IPC_EXCL or 438);
  If shmctl=-1 then
    begin
      writeln ('Shared memory exists. Opening as client');
      shmctl := shmget(key,segsz,0);
      If shmctl = -1 then
        begin
          writeln ('shmget : Error !',fpgeterrno);
          halt(1);
        end
      end
    else
      writeln ('Creating new shared memory segment. ');
    end
  end

```

```

segptr:=shmat(shmid,nil,0);
if longint(segptr)=-1 then
begin
  Writeln ('Shmat : error !',fpgeterrno);
  halt(1);
end;
case upcase(paramstr(1)[1]) of
  'W' : writeshm (shmid,segptr,paramstr(2));
  'R' : readshm (shmid,segptr);
  'D' : removeshm(shmid);
  'M' : changemode (shmid,paramstr(2));
else
begin
  writeln (paramstr(1));
  usage;
end;
end;
end.

```

58.4.12 shmdt

Synopsis: Detach shared memory block.

Declaration: `function shmdt(shmaddr: pointer) : cint`

Visibility: default

Description: `shmdt` detaches the shared memory at address `shmaddr`. This shared memory block is unavailable to the current process, until it is attached again by a call to `shmat` (922).

The function returns `True` if the memory block was detached successfully, `False` otherwise.

Errors: On error, `False` is returned, and `IPCError` is set.

See also: `shmget` (925), `shmat` (922), `shmctl` (923)

58.4.13 shmget

Synopsis: Return the ID of a shared memory block, possibly creating it

Declaration: `function shmget(key: TKey; size: size_t; flag: cint) : cint`

Visibility: default

Description: `shmget` returns the ID of a shared memory block, described by `key`. Depending on the flags in `flag`, a new memory block is created.

`flag` can have one or more of the following values (combined by ORs):

IPC_CREAT The queue is created if it doesn't already exist.

IPC_EXCL If used in combination with `IPC_CREAT`, causes the call to fail if the queue already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

if a new memory block is created, then it will have size `Size` bytes in it.

Errors: On error, -1 is returned, and `IPCError` is set.

58.5 TIPC_Perm

```
TIPC_Perm = record
  key : TKey;
  uid : kernel_uid_t;
  gid : kernel_gid_t
  ;
  cuid : kernel_uid_t;
  cgid : kernel_gid_t;
  mode : kernel_mode_t
  ;
  __pad1 : Array[1..4-sizeof(mode_t)] of Byte;
  seq : cushort;
  __pad2 : cushort;
  __unused1 : culong;
  __unused2 : culong;
end
```

TIPC_Perm is used in all IPC systems to specify the permissions. It should never be used directly.

58.6 TMSG

```
TMSG = record
  msg_next : PMSG;
  msg_type : LongInt;
  msg_spot
  : PChar;
  msg_stime : LongInt;
  msg_ts : Integer;
end
```

Record used in the handling of message queues. Do not use directly.

58.7 TMSGbuf

```
TMSGbuf = record
  mtype : clong;
  mtext : Array[0..0] of Char;
end
```

The TMSGbuf record is a record containing the data of a record. you should never use this record directly, instead you should make your own record that follows the structure of the TMSGbuf record, but that has a size that is big enough to accommodate your messages. The mtype field should always be present, and should always be filled.

58.8 TMSGinfo

```
TMSGinfo = record
```

```

msgpool : cint;
msgmap : cint;
msgmax : cint
;
msgmnb : cint;
msgmni : cint;
msgssz : cint;
msgtql : cint
;
msgseg : cushort;
end

```

Internal message system record. Do not use directly.

58.9 TMSQid_ds

```

TMSQid_ds = record
  msg_perm : TIPC_Perm;
  msg_stime : time_t;
  msg_rtime : time_t;
  msg_ctime : time_t;
  msg_cbytes : QWord;
  msg_qnum : QWord;
  msg_qbytes : QWord;
  msg_lspid : ipc_pid_t
;
  msg_lrpid : ipc_pid_t;
  pad1 : QWord;
  pad2 : QWord;
end

```

This record should never be used directly, it is an internal kernel record. It's fields may change at any time.

58.10 TSEMbuf

```

TSEMbuf = record
  sem_num : cushort;
  sem_op : cshort;
  sem_flg
  : cshort;
end

```

The TSEMbuf record is used in the semop ([921](#)) call, and is used to specify which operations you want to do.

58.11 TSEMid_ds

```

TSEMid_ds = record

```



```

sem_perm : TIPC_Perm;
sem_otime : time_t;
unused1 : culong;
sem_ctime : time_t;
unused2 : culong;
sem_nsems
: culong;
unused3 : culong;
unused4 : culong;
end

```

Structure returned by the `semctl` (916) call, contains all data of a semaphore

58.12 TSEMinfo

```

TSEMinfo = record
  semmap : cint;
  semmni : cint;
  semmns : cint
;
  semmnu : cint;
  semmsl : cint;
  semopm : cint;
  semume : cint
;
  semusz : cint;
  semvmx : cint;
  semaem : cint;
end

```

Internal semaphore system record. Do not use.

58.13 TShmid_ds

```

TShmid_ds = record
  shm_perm : TIPC_Perm;
  shm_segsz : size_t;
  shm_atime : time_t;
  shm_dtime : time_t;
  shm_ctime : time_t;
  shm_cpid : pid_t;
  shm_lpid : pid_t;
  shm_nattch : culong;
  __unused4 : culong;
  __unused5 : culong;
end

```

Record used in the `shmctl` (923) call to set or retrieve settings for shared memory.

58.14 TSHMinfo

```
TSHMinfo = record
  shmmax : cint;
  shmmmin : cint;
  shmmni : cint
  ;
  shmseg : cint;
  shmall : cint;
end
```

Record used by the shared memory system, Do not use directly.

58.15 TSHM_info

```
TSHM_info = record
  used_ids : cint;
  shm_tot : culong;
  shm_rss
  : culong;
  shm_swp : culong;
  swap_attempts : culong;
  swap_successes
  : culong;
end
```

Chapter 59

Reference for unit 'keyboard'

59.1 Used units

Table 59.1: Used units by unit 'keyboard'

Name	Page
System	1339

59.2 Overview

The **Keyboard** unit implements a keyboard access layer which is system independent. It can be used to poll the keyboard state and wait for certain events. Waiting for a keyboard event can be done with the [GetKeyEvent \(944\)](#) function, which will return a driver-dependent key event. This key event can be translated to a interpretable event by the [TranslateKeyEvent \(952\)](#) function. The result of this function can be used in the other event examining functions.

A custom keyboard driver can be installed using the [SetKeyboardDriver \(951\)](#) function. The current keyboard driver can be retrieved using the [GetKeyboardDriver \(943\)](#) function. The last section of this chapter demonstrates how to make a keyboard driver.

59.3 Unix specific notes

On Unix, applications run on a "terminal", and the application writes to the screen and reads from the keyboard by communicating with the terminal. Unix keyboard handling is mostly backward compatible with the DEC VT100 and VT220 terminals from tens of years ago. The VT100 and VT220 had very different keyboards than todays PC's and this is where the problems start. To make it worse the protocol of both terminals has not been very well designed.

Because of this, the keyboard unit on Unix operating systems does a best effort to provide keyboard functionality. An implementation with full keyboard facilities like on other operating systems is not possible.

The exception is the Linux kernel. The terminal emulation of the Linux kernel is from a PC keyboard viewpoint hopeless as well, but unlike other terminal emulators it is configurable. On the Linux console, the Free Pascal keyboard unit tries to implement full functionality.

Users of applications using the keyboard unit should expect the following:

- Full functionality on the Linux console. It must be the bare console, SSH into another machine will kill the full functionality.
- Limited functionality otherwise.

Notes about Linux full functionality:

- The keyboard is reprogrammed. If the keyboard is for whatever reason not restored in its original state, please load your keymap to reinitialize it.
- Alt+function keys generate keycodes for those keys. To switch virtual consoles, use ctrl+alt+function key.
- Unlike what you're used to with other Unix software, escape works as you intuitively expect, it generates the keycode for an escape key **without a delay**.

The limited functionality does include these quirks:

- Escape must be pressed two times before it has effect.
- On the Linux console, when the users runs the program by logging into another machine:
 - Shift+F1 and Shift+F12 will generate keycodes for F11 and F12.
 - Shift+arrow keys, shift+ins, shift+del, shift+home, shift+end do not work. The same is true about the control and alt combinations.
 - Alt+function keys will switch virtual consoles instead of generating the right key sequences.
 - Ctrl+function keys will generate the keycodes for the function keys without ctrl
- In Xterm:
 - Shift+insert pastes the x clipboard, no keycode will be generated.
- In Konsole:
 - Shift+insert pastes the x clipboard, no keycode will be generated.
 - Shift+arrow keys doesn't work, nor does ctrl+arrow keys

If you have a non-standard terminal, some keys may not work at all. When in limited functionality mode, the user can work around using an escape prefix:

- Esc+1 = F1, Esc+2 = F2.
- Esc before another key is equal to alt+key.

In such cases, if the terminal does output an escape sequence for those keys, please submit a bug report so we can add them.

59.4 Writing a keyboard driver

Writing a keyboard driver means that hooks must be created for most of the keyboard unit functions. The `TKeyboardDriver` record contains a field for each of the possible hooks:

```
TKeyboardDriver = Record
  InitDriver : Procedure;
  DoneDriver : Procedure;
  GetKeyEvent : Function : TKeyEvent;
  PollKeyEvent : Function : TKeyEvent;
  GetShiftState : Function : Byte;
  TranslateKeyEvent : Function (KeyEvent: TKeyEvent): TKeyEvent;
  TranslateKeyEventUniCode: Function (KeyEvent: TKeyEvent): TKeyEvent;
end;
```

The meaning of these hooks is explained below:

InitDriver Called to initialize and enable the driver. Guaranteed to be called only once. This should initialize all needed things for the driver.

DoneDriver Called to disable and clean up the driver. Guaranteed to be called after a call to `initDriver`. This should clean up all things initialized by `InitDriver`.

GetKeyEvent Called by `GetKeyEvent` (944). Must wait for and return the next key event. It should NOT store keys.

PollKeyEvent Called by `PollKeyEvent` (949). It must return the next key event if there is one. Should not store keys.

GetShiftState Called by `PollShiftStateEvent` (949). Must return the current shift state.

TranslateKeyEvent Should translate a raw key event to a correct key event, i.e. should fill in the shiftstate and convert function key scancodes to function key keycodes. If the `TranslateKeyEvent` is not filled in, a default translation function will be called which converts the known scancodes from the tables in the previous section to a correct keyevent.

TranslateKeyEventUniCode Should translate a key event to a UNICODE key representation.

Strictly speaking, only the `GetKeyEvent` and `PollKeyEvent` hooks must be implemented for the driver to function correctly.

The example unit demonstrates how a keyboard driver can be installed. It takes the installed driver, and hooks into the `GetKeyEvent` function to register and log the key events in a file. This driver can work on top of any other driver, as long as it is inserted in the `uses` clause *after* the real driver unit, and the real driver unit should set the driver record in its initialization section.

Note that with a simple extension of this unit could be used to make a driver that is capable of recording and storing a set of keyboard strokes, and replaying them at a later time, so a 'keyboard macro' capable driver. This driver could sit on top of any other driver.

Listing: `./examples/kbdex/logkeys.pp`

```
unit logkeys;
```

```
interface
```

```
Procedure StartKeyLogging;
```

```
Procedure StopKeyLogging;
```

```

Function IsKeyLogging : Boolean;
Procedure SetKeyLogFileName (FileName : String);

implementation

uses sysutils , keyboard;

var
    NewKeyBoardDriver ,
    OldKeyBoardDriver : TKeyboardDriver;
    Active , Logging : Boolean;
    LogFileName : String;
    KeyLog : Text;

Function TimeStamp : String;

begin
    TimeStamp:=FormatDateTime( 'hh:nn:ss ' , Time ( ) );
end;

Procedure StartKeyLogging;

begin
    Logging:=True;
    WriteLn(KeyLog, 'Start logging keystrokes at: ', TimeStamp);
end;

Procedure StopKeyLogging;

begin
    WriteLn(KeyLog, 'Stop logging keystrokes at: ', TimeStamp);
    Logging:=False;
end;

Function IsKeyLogging : Boolean;

begin
    IsKeyLogging:=Logging;
end;

Function LogGetKeyEvent : TKeyEvent;

Var
    K : TKeyEvent;

begin
    K:=OldkeyboardDriver . GetKeyEvent ( );
    If Logging then
        begin
            Write (KeyLog, TimeStamp, ': Key event: ');
            WriteLn (KeyLog, KeyEventToString ( TranslateKeyEvent (K) ));
        end;
    LogGetKeyEvent:=K;
end;

Procedure LogInitKeyBoard;

```

```

begin
  OldKeyBoardDriver.InitDriver();
  Assign(KeyLog, logFileName);
  Rewrite(KeyLog);
  Active := True;
  StartKeyLogging;
end;

Procedure LogDoneKeyBoard;

begin
  StopKeyLogging;
  Close(KeyLog);
  Active := False;
  OldKeyBoardDriver.DoneDriver();
end;

Procedure SetKeyLogFileName(FileName : String);

begin
  If Not Active then
    LogFileName := FileName;
  end;

Initialization
  GetKeyBoardDriver(OldKeyBoardDriver);
  NewKeyBoardDriver := OldKeyBoardDriver;
  NewKeyBoardDriver.GetKeyEvent := @LogGetKeyEvent;
  NewKeyBoardDriver.InitDriver := @LogInitKeyboard;
  NewKeyBoardDriver.DoneDriver := @LogDoneKeyboard;
  LogFileName := 'keyboard.log';
  Logging := False;
  SetKeyboardDriver(NewKeyBoardDriver);
end.

```

Listing: ./examples/kbdex/ex9.pp

```

program example9;

{ This program demonstrates the logkeys unit }

uses keyboard, logkeys;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  Writeln('Press keys, press "q" to end, "s" toggles logging. ');
  Repeat
    K := GetKeyEvent;
    K := TranslateKeyEvent(K);
    Writeln('Got key : ', KeyEventToString(K));
    if GetKeyEventChar(K) = 's' then
      if IsKeyLogging then
        StopKeyLogging
      else
        StartKeyLogging;
    Until (GetKeyEventChar(K) = 'q');

```

```
    DoneKeyBoard ;  
end .
```

59.5 Keyboard scan codes

Special physical keys are encoded with the DOS scan codes for these keys in the second byte of the TKeyEvent (942) type. A complete list of scan codes can be found in the below table. This is the list of keys that is used by the default key event translation mechanism. When writing a keyboard driver, either these constants should be returned by the various key event functions, or the TranslateKeyEvent hook should be implemented by the driver.

Table 59.2: Key Scancodes

Code	Key	Code	Key	Code	Key
00	NoKey	3D	F3	70	ALT-F9
01	ALT-Esc	3E	F4	71	ALT-F10
02	ALT-Space	3F	F5	72	CTRL-PrtSc
04	CTRL-Ins	40	F6	73	CTRL-Left
05	SHIFT-Ins	41	F7	74	CTRL-Right
06	CTRL-Del	42	F8	75	CTRL-end
07	SHIFT-Del	43	F9	76	CTRL-PgDn
08	ALT-Back	44	F10	77	CTRL-Home
09	ALT-SHIFT-Back	47	Home	78	ALT-1
0F	SHIFT-Tab	48	Up	79	ALT-2
10	ALT-Q	49	PgUp	7A	ALT-3
11	ALT-W	4B	Left	7B	ALT-4
12	ALT-E	4C	Center	7C	ALT-5
13	ALT-R	4D	Right	7D	ALT-6
14	ALT-T	4E	ALT-GrayPlus	7E	ALT-7
15	ALT-Y	4F	end	7F	ALT-8
16	ALT-U	50	Down	80	ALT-9
17	ALT-I	51	PgDn	81	ALT-0
18	ALT-O	52	Ins	82	ALT-Minus
19	ALT-P	53	Del	83	ALT-Equal
1A	ALT-LftBrack	54	SHIFT-F1	84	CTRL-PgUp
1B	ALT-RgtBrack	55	SHIFT-F2	85	F11
1E	ALT-A	56	SHIFT-F3	86	F12
1F	ALT-S	57	SHIFT-F4	87	SHIFT-F11
20	ALT-D	58	SHIFT-F5	88	SHIFT-F12
21	ALT-F	59	SHIFT-F6	89	CTRL-F11
22	ALT-G	5A	SHIFT-F7	8A	CTRL-F12
23	ALT-H	5B	SHIFT-F8	8B	ALT-F11
24	ALT-J	5C	SHIFT-F9	8C	ALT-F12
25	ALT-K	5D	SHIFT-F10	8D	CTRL-Up
26	ALT-L	5E	CTRL-F1	8E	CTRL-Minus
27	ALT-SemiCol	5F	CTRL-F2	8F	CTRL-Center
28	ALT-Quote	60	CTRL-F3	90	CTRL-GreyPlus
29	ALT-OpQuote	61	CTRL-F4	91	CTRL-Down
2B	ALT-BkSlash	62	CTRL-F5	94	CTRL-Tab
2C	ALT-Z	63	CTRL-F6	97	ALT-Home
2D	ALT-X	64	CTRL-F7	98	ALT-Up
2E	ALT-C	65	CTRL-F8	99	ALT-PgUp
2F	ALT-V	66	CTRL-F9	9B	ALT-Left
30	ALT-B	67	CTRL-F10	9D	ALT-Right
31	ALT-N	68	ALT-F1	9F	ALT-end
32	ALT-M	69	ALT-F2	A0	ALT-Down
33	ALT-Comma	6A	ALT-F3	A1	ALT-PgDn
34	ALT-Period	6B	ALT-F4	A2	ALT-Ins
35	ALT-Slash	6C	ALT-F5	A3	ALT-Del
37	ALT-GreyAst	6D	ALT-F6	A5	ALT-Tab
3B	F1	6E	ALT-F7		
3C	F2	6F	ALT-F8		

A list of scan codes for special keys and combinations with the SHIFT, ALT and CTRL keys can be found in the following table: They are for quick reference only.

Table 59.3: Special keys scan codes

Key	Code	SHIFT-Key	CTRL-Key	Alt-Key
NoKey	00			
F1	3B	54	5E	68
F2	3C	55	5F	69
F3	3D	56	60	6A
F4	3E	57	61	6B
F5	3F	58	62	6C
F6	40	59	63	6D
F7	41	5A	64	6E
F8	42	5B	65	6F
F9	43	5C	66	70
F10	44	5D	67	71
F11	85	87	89	8B
F12	86	88	8A	8C
Home	47		77	97
Up	48		8D	98
PgUp	49		84	99
Left	4B		73	9B
Center	4C		8F	
Right	4D		74	9D
end	4F		75	9F
Down	50		91	A0
PgDn	51		76	A1
Ins	52	05	04	A2
Del	53	07	06	A3
Tab	8	0F	94	A5
GreyPlus			90	4E

59.6 Constants, types and variables

59.6.1 Constants

`AltPrefix : Byte = 0`

Keycode for alternate prefix key for Alt key. Unix Only

`CtrlPrefix : Byte = 0`

Keycode for alternate prefix key for Ctrl key. Unix only

`errKbdBase = 1010`

Base of keyboard routine error reporting constants.

`errKbdInitError = errKbdBase + 0`

Failed to initialize keyboard driver

```
errKbdNotImplemented = errKbdBase + 1
```

Keyboard driver not implemented.

```
kbAlt = 8
```

Alt key modifier

```
kbASCII = $00
```

ASCII code key event

```
kbCtrl = 4
```

Control key modifier

```
kbdApps = $FF17
```

Application key (popup-menu) pressed.

```
kbdDelete = $FF2A
```

Delete key pressed

```
kbdDown = $FF27
```

Arrow down key pressed

```
kbdEnd = $FF26
```

End key pressed

```
kbdF1 = $FF01
```

F1 function key pressed.

```
kbdF10 = $FF0A
```

F10 function key pressed.

```
kbdF11 = $FF0B
```

F12 function key pressed.

```
kbdF12 = $FF0C
```

F12 function key pressed.

```
kbdF13 = $FF0D
```

F13 function key pressed.

kbdF14 = \$FF0E

F14 function key pressed.

kbdF15 = \$FF0F

F15 function key pressed.

kbdF16 = \$FF10

F16 function key pressed.

kbdF17 = \$FF11

F17 function key pressed.

kbdF18 = \$FF12

F18 function key pressed.

kbdF19 = \$FF13

F19 function key pressed.

kbdF2 = \$FF02

F2 function key pressed.

kbdF20 = \$FF14

F20 function key pressed.

kbdF3 = \$FF03

F3 function key pressed.

kbdF4 = \$FF04

F4 function key pressed.

kbdF5 = \$FF05

F5 function key pressed.

kbdF6 = \$FF06

F6 function key pressed.

kbdF7 = \$FF07

F7 function key pressed.

kbdF8 = \$FF08

F8 function key pressed.

kbdF9 = \$FF09

F9 function key pressed.

kbdHome = \$FF20

Home key pressed

kbdInsert = \$FF29

Insert key pressed

kbdLeft = \$FF23

Arrow left key pressed

kbdLWin = \$FF15

Left windows key pressed.

kbdMiddle = \$FF24

Middle key pad key pressed (numerical 5)

kbdPgDn = \$FF28

Page down key pressed

kbdPgUp = \$FF22

Page Up key pressed

kbdRight = \$FF25

Arrow right key pressed

kbdRWin = \$FF16

Right windows key pressed.

kbdUp = \$FF21

Arrow up key pressed

kbFnKey = \$02

function key pressed.

```
kbLeftShift = 1
```

Left shift key modifier

```
kbPhys = $03
```

Physical key code event

```
kbReleased = $04
```

Key release event (not implemented in FPC)

```
kbRightShift = 2
```

Right shift key modifier

```
kbShift = kbLeftShift or kbRightShift
```

Shift key modifier

```
kbUnicode = $01
```

Unicode code key event

```
SAnd : string = 'AND'
```

This constant is used as the 'And' word in key descriptions. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
ShiftPrefix : Byte = 0
```

Keycode for alternate prefix key for Shift key. Unix Only

```
SKeyPad : Array[0..($FF2F-kbdHome)] of string = ('Home', 'Up', 'PgUp',
    , 'Left', 'Middle', 'Right', 'End', 'Down', 'PgDn', 'Insert', 'Delete'
    , '', '', '', '', '')
```

This constant describes all keypad keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SLeftRight : Array[1..2] of string = ('LEFT', 'RIGHT')
```

This constant contains strings to describe left and right keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SScanCode : string = 'Key with scancode '
```

This constant contains a string to denote a scancode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

`SShift : Array[1..3] of string = ('SHIFT', 'CTRL', 'ALT')`

This constant describes the various modifier keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

`SUnicodeChar : string = 'Unicode character '`

This constant contains a string to denote a Unicode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

`SUnknownFunctionKey : string = 'Unknown function key : '`

This constant contains a string to denote that an unknown function key was found. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

59.6.2 Types

`PTreeElement = ^TTreeElement`

Pointer to `TTreeElement` (954) record

`TKeyEvent = Cardinal`

The `TKeyEvent` type is the base type for all keyboard events.

The key stroke is encoded in the 4 bytes of the `TKeyEvent` type. The various fields of the key stroke encoding can be obtained by typecasting the `TKeyEvent` type to the `TKeyRecord` (953) type.

`Tprocedure = procedure`

Procedure prototype

59.7 Procedures and functions

59.7.1 DoneKeyboard

Synopsis: Deactivate keyboard driver.

Declaration: `procedure DoneKeyboard`

Visibility: default

Description: `DoneKeyboard` de-initializes the keyboard interface if the keyboard driver is active. If the keyboard driver is not active, the function does nothing.

This will cause the keyboard driver to clear up any allocated memory, or restores the console or terminal the program was running in to its initial state before the call to `InitKeyBoard` (947). This function should be called on program exit. Failing to do so may leave the terminal or console window in an unusable state. Its exact action depends on the platform on which the program is running.

On Unix the default keyboard driver restores the line ending of `system.output` to #10.

For an example, see most other functions.

Errors: None.

See also: `InitKeyBoard` (947)

59.7.2 FunctionKeyName

Synopsis: Return string representation of a function key code.

Declaration: `function FunctionKeyName(KeyCode: Word) : string`

Visibility: default

Description: `FunctionKeyName` returns a string representation of the function key with code `KeyCode`. This can be an actual function key, or one of the cursor movement keys.

Errors: In case `KeyCode` does not contain a function code, the `SUnknownFunctionKey` string is returned, appended with the `KeyCode`.

See also: `ShiftStateToString` ([951](#)), `KeyEventToString` ([948](#))

Listing: `./examples/kbdex/ex8.pp`

Program Example8;

{ Program to demonstrate the FunctionKeyName function. }

Uses keyboard;

Var

 K : TKeyEvent;

begin

 InitKeyboard;

 WriteLn('Press function keys, press "q" to end.');

 Repeat

 K:=GetKeyEvent;

 K:=TranslateKeyEvent(K);

 If IsFunctionKey(k) then

 begin

 Write('Got function key : ');

 WriteLn(FunctionKeyName(TkeyRecord(K).KeyCode));

 end;

 Until (GetKeyEventChar(K)='q');

 DoneKeyboard;

end.

59.7.3 GetKeyboardDriver

Synopsis: Return the current keyboard driver record.

Declaration: `procedure GetKeyboardDriver(var Driver: TKeyboardDriver)`

Visibility: default

Description: `GetKeyboardDriver` returns in `Driver` the currently active keyboard driver. This function can be used to enhance an existing keyboarddriver.

For more information on getting and setting the keyboard driver `kbd driver` ([932](#)).

Errors: None.

See also: `SetKeyboardDriver` ([951](#))

59.7.4 GetKeyEvent

Synopsis: Get the next raw key event, wait if needed.

Declaration: `function GetKeyEvent : TKeyEvent`

Visibility: default

Description: `GetKeyEvent` returns the last keyevent if it is available, or waits for one if none is available. A non-blocking version is available in `PollKeyEvent` (949).

The returned key is encoded as a `TKeyEvent` type variable, and is normally the physical key scan code, (the scan code is driver dependent) which can be translated with one of the translation functions `TranslateKeyEvent` (952) or `TranslateKeyEventUnicode` (952). See the types section for a description of how the key is described.

Errors: If no key became available (e.g. when the driver does not support it), 0 is returned.

See also: `PutKeyEvent` (950), `PollKeyEvent` (949), `TranslateKeyEvent` (952), `TranslateKeyEventUnicode` (952)

Listing: `./examples/kbdex/ex1.pp`

```

program example1;

{ This program demonstrates the GetKeyEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  Writeln('Press keys, press "q" to end. ');
  Repeat
    K:=GetKeyEvent;
    K:=TranslateKeyEvent(K);
    Write('Got key event with ');
    Case GetKeyEventFlags(K) of
      kbASCII      : Writeln('ASCII key');
      kbUnicode    : Writeln('Unicode key');
      kbFnKey      : Writeln('Function key');
      kbPhys       : Writeln('Physical key');
      kbReleased   : Writeln('Released key event');
    end;
    Writeln('Got key : ',KeyEventToString(K));
  Until (GetKeyEventChar(K)='q');
  DoneKeyBoard;
end.
```

59.7.5 GetKeyEventChar

Synopsis: Get the character key part of a key event.

Declaration: `function GetKeyEventChar(KeyEvent: TKeyEvent) : Char`

Visibility: default

Description: `GetKeyEventChar` returns the charcode part of the given `KeyEvent`, if it contains a translated character key keycode. The charcode is simply the ascii code of the character key that was pressed.

It returns the null character if the key was not a character key, but e.g. a function key.

For an example, see `GetKeyEvent` (944)

Errors: None.

See also: `GetKeyEventUnicode` (947), `GetKeyEventShiftState` (946), `GetKeyEventFlags` (946), `GetKeyEventCode` (945), `GetKeyEvent` (944)

59.7.6 `GetKeyEventCode`

Synopsis: Translate function key part of a key event code.

Declaration: `function GetKeyEventCode(KeyEvent: TKeyEvent) : Word`

Visibility: default

Description: `GetKeyEventCode` returns the translated function keycode part of the given `KeyEvent`, if it contains a translated function key.

If the key pressed was not a function key, the null character is returned.

Errors: None.

See also: `GetKeyEventUnicode` (947), `GetKeyEventShiftState` (946), `GetKeyEventFlags` (946), `GetKeyEventChar` (944), `GetKeyEvent` (944)

Listing: `./examples/kbdex/ex2.pp`

Program Example2;

{ Program to demonstrate the GetKeyEventCode function. }

Uses keyboard;

Var

 K : TKeyEvent;

begin

 InitKeyboard;

WriteIn ('Press function keys, or press "q" to end.');

Repeat

 K:=GetKeyEvent;

 K:=TranslateKeyEvent(K);

If (GetKeyEventFlags(K)<>KbfnKey) **then**

WriteIn ('Not a function key')

else

begin

Write ('Got key (',GetKeyEventCode(K));

WriteIn (') : ',KeyEventToString(K));

end;

Until (GetKeyEventChar(K)= 'q');

 DoneKeyboard;

end.

59.7.7 GetKeyEventFlags

Synopsis: Extract the flags from a key event.

Declaration: `function GetKeyEventFlags (KeyEvent: TKeyEvent) : Byte`

Visibility: default

Description: `GetKeyEventFlags` returns the flags part of the given `KeyEvent`.

For an example, see `GetKeyEvent` (944)

Errors: None.

See also: `GetKeyEventUnicode` (947), `GetKeyEventShiftState` (946), `GetKeyEventCode` (945), `GetKeyEventChar` (944), `GetKeyEvent` (944)

59.7.8 GetKeyEventShiftState

Synopsis: Return the current state of the shift keys.

Declaration: `function GetKeyEventShiftState (KeyEvent: TKeyEvent) : Byte`

Visibility: default

Description: `GetKeyEventShiftState` returns the shift-state values of the given `KeyEvent`. This can be used to detect which of the modifier keys `Shift`, `Alt` or `Ctrl` were pressed. If none were pressed, zero is returned.

Note that this function does not always return expected results; In a UNIX X-Term, the modifier keys do not always work.

Errors: None.

See also: `GetKeyEventUnicode` (947), `GetKeyEventFlags` (946), `GetKeyEventCode` (945), `GetKeyEventChar` (944), `GetKeyEvent` (944)

Listing: `./examples/kbdex/ex3.pp`

Program Example3;

{ Program to demonstrate the GetKeyEventShiftState function. }

Uses keyboard;

Var

 K : TKeyEvent;
 S : Byte;

begin

 InitKeyBoard;
 Write('Press keys combined with CTRL/SHIFT/ALT');
 WriteLn(' , or press "q" to end.');

 Repeat
 K:=GetKeyEvent;
 K:=TranslateKeyEvent(K);
 S:=GetKeyEventShiftState(K);
 If (S=0) then
 WriteLn('No special keys pressed')
 else
 begin

```

    Writeln('Detected special keys : ', ShiftStateToString(K, False));
    Writeln('Got key : ', KeyEventToString(K));
    end;
    Until (GetKeyEventChar(K) = 'q');
    DoneKeyboard;
end.

```

59.7.9 GetKeyEventUnicode

Synopsis: Return the Unicode key event.

Declaration: `function GetKeyEventUnicode(KeyEvent: TKeyEvent) : Word`

Visibility: default

Description: `GetKeyEventUnicode` returns the Unicode part of the given `KeyEvent` if it contains a translated Unicode character.

Errors: None.

See also: `GetKeyEventShiftState` (946), `GetKeyEventFlags` (946), `GetKeyEventCode` (945), `GetKeyEventChar` (944), `GetKeyEvent` (944)

59.7.10 InitKeyboard

Synopsis: Initialize the keyboard driver.

Declaration: `procedure InitKeyboard`

Visibility: default

Description: `InitKeyboard` initializes the keyboard driver. If the driver is already active, it does nothing. When the driver is initialized, it will do everything necessary to ensure the functioning of the keyboard, including allocating memory, initializing the terminal etc.

This function should be called once, before using any of the keyboard functions. When it is called, the `DoneKeyboard` (942) function should also be called before exiting the program or changing the keyboard driver with `SetKeyboardDriver` (951).

On Unix, the default keyboard driver sets terminal in raw mode. In raw mode the line feed behaves as an actual linefeed, i.e. the cursor is moved down one line. while the x coordinate does not change. To compensate, the default keyboard sets driver line ending of `system.output` to #13#10.

For an example, see most other functions.

Errors: None.

See also: `DoneKeyboard` (942), `SetKeyboardDriver` (951)

59.7.11 IsFunctionKey

Synopsis: Check whether a given event is a function key event.

Declaration: `function IsFunctionKey(KeyEvent: TKeyEvent) : Boolean`

Visibility: default

Description: `IsFunctionKey` returns `True` if the given key event in `KeyEvent` was a function key or not.

Errors: None.

See also: [GetKeyEvent \(944\)](#)

Listing: ./examples/kbdex/ex7.pp

```

program example1;

{ This program demonstrates the GetKeyEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  Repeat
    K:=GetKeyEvent;
    K:=TranslateKeyEvent(K);
    If IsFunctionKey(K) then
      WriteLn('Got function key : ',KeyEventToString(K))
    else
      WriteLn('not a function key. ');
  Until (GetKeyEventChar(K)= 'q ');
  DoneKeyBoard;
end.

```

59.7.12 KeyEventToString

Synopsis: Return a string describing the key event.

Declaration: `function KeyEventToString(KeyEvent: TKeyEvent) : string`

Visibility: default

Description: `KeyEventToString` translates the key event in `KeyEvent` to a human-readable description of the pressed key. It will use the constants described in the constants section to do so.

For an example, see most other functions.

Errors: If an unknown key is passed, the scancode is returned, prefixed with the `SScanCode` string.

See also: [FunctionKeyName \(943\)](#), [ShiftStateToString \(951\)](#)

59.7.13 KeyPressed

Synopsis: Check event queue for key press

Declaration: `function KeyPressed : Boolean`

Visibility: default

Description: `KeyPressed` checks the keyboard event queue to see whether a key event is present, and returns `True` if a key event is available. This function simply calls [PollKeyEvent \(949\)](#) and checks for a valid result.

Errors: None.

See also: [PollKeyEvent \(949\)](#), [GetKeyEvent \(944\)](#)

59.7.14 PollKeyEvent

Synopsis: Get next key event, but does not wait.

Declaration: `function PollKeyEvent : TKeyEvent`

Visibility: default

Description: `PollKeyEvent` checks whether a key event is available, and returns it if one is found. If no event is pending, it returns 0.

Note that this does not remove the key from the pending keys. The key should still be retrieved from the pending key events list with the `GetKeyEvent` (944) function.

Errors: None.

See also: `PutKeyEvent` (950), `GetKeyEvent` (944)

Listing: `./examples/kbdex/ex4.pp`

```

program example4;

{ This program demonstrates the PollKeyEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  Writeln('Press keys, press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
        writeln;
        Writeln('Got key : ',KeyEventToString(K));
      end
    else
      write(' ');
    Until (GetKeyEventChar(K)= 'q ');
  DoneKeyBoard;
end.

```

59.7.15 PollShiftStateEvent

Synopsis: Check current shift state.

Declaration: `function PollShiftStateEvent : TKeyEvent`

Visibility: default

Description: `PollShiftStateEvent` returns the current shiftstate in a keyevent. This will return 0 if there is no key event pending.

Errors: None.

See also: [PollKeyEvent \(949\)](#), [GetKeyEvent \(944\)](#)

Listing: ./examples/kbdex/ex6.pp

```

program example6;

{ This program demonstrates the PollShiftStateEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=PollShiftStateEvent;
        WriteLn('Got shift state : ', ShiftStateToString(K, False));
        // Consume the key.
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
      end
    { else
      write ( '. ' );
    }
    Until (GetKeyEventChar(K)= 'q ');
    DoneKeyBoard;
  end.

```

59.7.16 PutKeyEvent

Synopsis: Put a key event in the event queue.

Declaration: `procedure PutKeyEvent (KeyEvent : TKeyEvent)`

Visibility: default

Description: `PutKeyEvent` adds the given `KeyEvent` to the input queue. Please note that depending on the implementation this can hold only one value, i.e. when calling `PutKeyEvent` multiple times, only the last pushed key will be remembered.

Errors: None

See also: [PollKeyEvent \(949\)](#), [GetKeyEvent \(944\)](#)

Listing: ./examples/kbdex/ex5.pp

```

program example5;

{ This program demonstrates the PutKeyEvent function }

uses keyboard;

Var
  K, k2 : TKeyEvent;

```

```

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  K2:=0;
  Repeat
    K:=GetKeyEvent;
    If k<>0 then
      begin
        if (k2 mod 2)=0 then
          K2:=K+1
        else
          K2:=0;
        K:=TranslateKeyEvent(K);
        WriteLn('Got key : ',KeyEventToString(K));
        if (K2<>0) then
          begin
            PutKeyEvent(k2);
            K2:=TranslateKeyEvent(K2);
            WriteLn('Put key : ',KeyEventToString(K2))
          end
        end
      Until (GetKeyEventChar(K)= 'q ');
    DoneKeyBoard;
  end.

```

59.7.17 SetKeyboardDriver

Synopsis: Set a new keyboard driver.

Declaration: `function SetKeyboardDriver(const Driver: TKeyboardDriver) : Boolean`

Visibility: default

Description: `SetKeyBoardDriver` sets the keyboard driver to `Driver`, if the current keyboard driver is not yet initialized. If the current keyboard driver is initialized, then `SetKeyboardDriver` does nothing. Before setting the driver, the currently active driver should be disabled with a call to `DoneKeyboard` (942).

The function returns `True` if the driver was set, `False` if not.

For more information on setting the keyboard driver, see `kbddriver` (932).

Errors: None.

See also: `GetKeyboardDriver` (943), `DoneKeyboard` (942)

59.7.18 ShiftStateToString

Synopsis: Return description of key event shift state

Declaration: `function ShiftStateToString(KeyEvent: TKeyEvent; UseLeftRight: Boolean) : string`

Visibility: default

Description: `ShiftStateToString` returns a string description of the shift state of the key event `KeyEvent`. This can be an empty string.

The shift state is described using the strings in the `SShift` constant.

For an example, see `PollShiftStateEvent` (949).

Errors: None.

See also: `FunctionKeyName` (943), `KeyEventToString` (948)

59.7.19 TranslateKeyEvent

Synopsis: Translate raw event to ascii key event

Declaration: `function TranslateKeyEvent (KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEvent` performs ASCII translation of the `KeyEvent`. It translates a physical key to a function key if the key is a function key, and translates the physical key to the ordinal of the ascii character if there is an equivalent character key.

For an example, see `GetKeyEvent` (944)

Errors: None.

See also: `TranslateKeyEventUnicode` (952)

59.7.20 TranslateKeyEventUnicode

Synopsis: Translate raw event to UNICODE key event

Declaration: `function TranslateKeyEventUnicode (KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEventUnicode` performs Unicode translation of the `KeyEvent`. It is not yet implemented for all platforms.

Errors: If the function is not yet implemented, then the `ErrorCode` of the `system` unit will be set to `errKbdNotImplemented`

See also: `TranslateKeyEvent` (952)

59.8 TKeyboardDriver

```
TKeyboardDriver = record
  InitDriver : procedure;
  DoneDriver :
  procedure;
  GetKeyEvent : function : TKeyEvent;
  PollKeyEvent
  : function : TKeyEvent;
  GetShiftState : function : Byte;
  TranslateKeyEvent
  : function (KeyEvent: TKeyEvent) : TKeyEvent;
```

```

    TranslateKeyEventUnicode
    : function(KeyEvent: TKeyEvent) : TKeyEvent;
end

```

The `TKeyboardDriver` record can be used to install a custom keyboard driver with the `SetKeyboardDriver` (951) function.

The various fields correspond to the different functions of the keyboard unit interface. For more information about this record see `kbddriver` (932)

59.9 TKeyEvent

```

TKeyEvent = packed record
    Flags : Byte;
    ShiftState : Byte;
    KeyCode : Word;
end

```

The structure of a `TKeyEvent` structure is explained in the following table:

Table 59.4: Structure of TKeyEvent

Field	Meaning
KeyCode	Depending on <code>flags</code> either the physical representation of a key (under DOS scancode, ASCII code pair), or the
ShiftState	Shift-state when this key was pressed (or shortly after)
Flags	Determine how to interpret <code>KeyCode</code>

The shift-state can be checked using the various shift-state constants, and the flags in the last byte can be checked using one of the `kbASCII`, `kbUnicode`, `kbFnKey`, `kbPhys`, `kbReleased` constants.

If there are two keys returning the same char-code, there's no way to find out which one was pressed (Gray+ and Simple+). If it needs to be known which was pressed, the untranslated keycodes must be used, but these are system dependent. System dependent constants may be defined to cover those, with possibly having the same name (but different value).

59.10 TTreeElement

```

TTreeElement = record
    Next : PTreeElement;
    Parent : PTreeElement
    ;
    Child : PTreeElement;
    CanBeTerminal : Boolean;
    char : Byte
    ;
    ScanValue : Byte;
    CharValue : Byte;
    SpecialHandler : Tprocedure
    ;
end

```

`TTreeElement` is used to describe key scancode sequences, and is used to handle special key combinations in `AddSpecialSequence` (??) on UNIX platforms. There should be no need to handle records of this type.

Chapter 60

Reference for unit 'lineinfo'

60.1 Used units

Table 60.1: Used units by unit 'lineinfo'

Name	Page
System	1339

60.2 Overview

The `lineinfo` provides a routine that reads the debug information of an executable (if any exists) and returns source code information about this address. It works with `Stabs` debug information. Note that this unit is not thread-safe, and that its behaviour is undefined if multiple threads try to write a backtrace at the same time.

For DWARF debug information, the `Infodwrf` ([984](#)) unit must be used.

60.3 Constants, types and variables

60.3.1 Types

`CodePointer = Pointer`

`CodePointer` is added for 16-bit dos compatibility.

60.3.2 Variables

`AllowReuseOfLineInfoData : Boolean = True`

`AllowReuseOfLineInfoData` can be set to `True` to keep the last opened file open. When regularly creating backtraces (e.g. in a program log), this will significantly speed up operations.

60.4 Procedures and functions

60.4.1 CloseStabs

Synopsis: Close stabs info file descriptor

Declaration: `procedure CloseStabs`

Visibility: default

Description: `CloseStabs` will close the file descriptor that was used to read STABS debug information. This is useful if `AllowReuseOfLineInfoData` (955) is used to cache STABS information.

Errors: None.

See also: `AllowReuseOfLineInfoData` (955)

60.4.2 GetLineInfo

Synopsis: Return source line information about an address.

Declaration: `function GetLineInfo(addr: PtrUInt; var func: string;
var source: string; var line: LongInt) : Boolean`

Visibility: default

Description: `GetLineInfo` returns source line information about the address `addr`. It searches this information in the stabs debugging information found in the binary: If the file was compiled without debug information, nothing will be returned. Upon successful retrieval of the debug information, `True` is returned, and the `func` parameter is filled with the name of the function in which the address is located. The `source` parameter contains the name of the file in which the function was implemented, and `line` contains the line number in the source file for `addr`.

Errors: If no debug information is found, `False` is returned.

60.4.3 StabBackTraceStr

Synopsis: Get a backtrace from an address

Declaration: `function StabBackTraceStr(addr: CodePointer) : string`

Visibility: default

Description: `StabBackTraceStr` returns a backtrace from a memory address `Addr`.

This is the actual callback for the backtrace handler `System.BackTraceStrFunc` (955).

Errors: None.

See also: `GetLineInfo` (956)

Chapter 61

Reference for unit 'Linux'

61.1 Used units

Table 61.1: Used units by unit 'Linux'

Name	Page
BaseUnix	141
System	1339
unixtype	2127

61.2 Overview

The linux unit contains Linux specific operating system calls.

The platform independent functionality of the FPC 1.0.X version of the linux unit has been split out over the UNIX ([2089](#)), baseunix ([141](#)) and unixutil ([2143](#)) units.

The X86-specific parts have been moved to the X86 ([2226](#)) unit.

61.3 Constants, types and variables

61.3.1 Constants

`CAP_AUDIT_CONTROL = 30`

Allow manipulation of kernel auditing features

`CAP_AUDIT_WRITE = 29`

Allow writing to kernel audit log

`CAP_CHOWN = 0`

Perform chown operation

`CAP_DAC_OVERRIDE = 1`

Bypass file operation (rwx) checks

`CAP_DAC_READ_SEARCH = 2`

Bypass file read-only operation checks

`CAP_FOWNER = 3`

Bypass owner ID checks

`CAP_FSETID = 4`

Do not clear SUID/GUID bits on modified files

`CAP_FS_MASK = 0xf`

?

`CAP_IPC_LOCK = 14`

Allow memory locking calls

`CAP_IPC_OWNER = 15`

Bypass permission checks on IPC operations

`CAP_KILL = 5`

Bypass permission checks for sending signals

`CAP_LEASE = 28`

Allow file leases

`CAP_LINUX_IMMUTABLE = 9`

Allow setting ext2 file attributes

`CAP_MKNOD = 27`

Allow creation of special files through mknod calls

`CAP_NET_ADMIN = 12`

Allow network operations (e.g. setting socket options)

`CAP_NET_BIND_SERVICE = 10`

Allow binding to ports less than 1024

`CAP_NET_BROADCAST = 11`

Allow socket broadcast operations

`CAP_NET_RAW = 13`

Allow use of RAW and PACKET sockets

`CAP_SETGID = 6`

Allow GID manipulations

`CAP_SETPCAP = 8`

Allow to set other process' capabilities

`CAP_SETUID = 7`

Allow process ID manipulations

`CAP_SYS_ADMIN = 21`

Allow various system administration calls

`CAP_SYS_BOOT = 22`

Allow reboot calls

`CAP_SYS_CHROOT = 18`

Allow chroot calls.

`CAP_SYS_MODULE = 16`

Allow loading/unloading of kernel modules

`CAP_SYS_NICE = 23`

Allowing raising process and thread priorities

`CAP_SYS_PACCT = 20`

Allow acct calls

`CAP_SYS_PTRACE = 19`

Allow ptrace calls

`CAP_SYS_RAWIO = 17`

Allow raw I/O port operations

`CAP_SYS_RESOURCE = 24`

Allow use of special resources or raising of resource limits

`CAP_SYS_TIME = 25`

Allow system or real-time clock modification

`CAP_SYS_TTY_CONFIG = 26`

Allow vhangup calls

`CLOCKS_MASK = CLOCK_REALTIME or CLOCK_MONOTONIC`

Mask for supported clocks

`CLOCKS_MONO = CLOCK_MONOTONIC`

Monotonic clocks mask

`CLOCK_MONOTONIC = 1`

Monotonic system time since some undetermined start point. Can change if time is set.

`CLOCK_MONOTONIC_COARSE = 6`

Less precise (but faster) version of `CLOCK_MONOTONIC`

`CLOCK_MONOTONIC_RAW = 4`

Like `CLOCK_MONOTONIC`, not subject to NTP adjustments

`CLOCK_PROCESS_CPUTIME_ID = 2`

Process-specific high-resolution timer from the CPU.

`CLOCK_REALTIME = 0`

System wide real-time clock. Can only be set by root.

`CLOCK_REALTIME_COARSE = 5`

Less precise (but faster) version of `CLOCK_REALTIME`

`CLOCK_SGI_CYCLE = 10`

High resolution timer

`CLOCK_THREAD_CPUTIME_ID = 3`

Thread-specific high-resolution timer from the CPU.

`CLONE_CHILD_CLEARTID = $00200000`

Clone option: Erase child thread ID in child memory space when child exits.

`CLONE_CHILD_SETTID = $01000000`

Clone option: Store child thread ID in child memory.

`CLONE_DETACHED = $00400000`

Clone option: Start clone detached.

`CLONE_FILES = $00000400`

Clone (975) option: open files shared between processes

`CLONE_FS = $00000200`

Clone (975) option: fs info shared between processes

`CLONE_NEWNS = $00020000`

Clone options: Start child in new (file system) namespace.

`CLONE_PARENT = $00008000`

Clone options: Set child parent to parent of calling process.

`CLONE_PARENT_SETTID = $00100000`

Clone option: Store child thread ID in memory in both parent and child.

`CLONE_PID = $00001000`

Clone (975) option: PID shared between processes

`CLONE_PTRACE = $00002000`

Clone options: if parent is traced, trace child also

`CLONE_SETTLS = $00080000`

Clone option: The newtls parameter is the TLS descriptor of the child

`CLONE_SIGHAND = $00000800`

Clone (975) option: signal handlers shared between processes

`CLONE_STOPPED = $02000000`

Clone option: Start child in stopped state.

CLONE_SYSVSEM = \$00040000

Clone option: Caller and child share the same semaphore undo values

CLONE_THREAD = \$00010000

Clone options: Set child in thread group of calling process.

CLONE_UNTRACED = \$00800000

Clone option: Do not allow a ptrace call on this clone.

CLONE_VFORK = \$00004000

Clone options: suspend parent till child execs

CLONE_VM = \$00000100

Clone (975) option: VM shared between processes

CSIGNAL = \$000000ff

Clone (975) option: Signal mask to be sent at exit

EPOLLERR = \$08

event_wait error condition on file descriptor

EPOLLET = \$80000000

Set event_wait edge trigger behaviour on file descriptor

EPOLLHUP = \$10

event_wait hang up event

EPOLLIN = \$01

event_wait input file descriptor ready event

EPOLLONESHOT = \$40000000

Set single-shot behaviour on epoll_wait.

EPOLLOUT = \$04

event_wait output file descriptor ready event

EPOLLPRI = \$02

event_wait high priority data available on input file descriptor

`EPOLL_CTL_ADD = 1`

Add filedescriptor to list of events

`EPOLL_CTL_DEL = 2`

Delete event for filedescriptor

`EPOLL_CTL_MOD = 3`

Modify event for filedescriptor

`FUTEX_CMP_REQUEUE = 4`

Futex option: requeue waiting processes on other futex, but check it's value first

`FUTEX_FD = 2`

Futex option: Associate file descriptor with futex.

`FUTEX_LOCK_PI = 6`

Futex option: Undocumented

`FUTEX_OP_ADD = 1`

Futex operation: Undocumented

`FUTEX_OP_ANDN = 3`

Futex operation: Undocumented

`FUTEX_OP_CMP_EQ = 0`

Futex operation: Undocumented

`FUTEX_OP_CMP_GE = 5`

Futex operation: Undocumented

`FUTEX_OP_CMP_GT = 4`

Futex operation: Undocumented

`FUTEX_OP_CMP_LE = 3`

Futex operation: Undocumented

`FUTEX_OP_CMP_LT = 2`

Futex operation: Undocumented

FUTEX_OP_CMP_NE = 1

Futex operation: Undocumented

FUTEX_OP_OPARG_SHIFT = 8

Futex operation: Undocumented

FUTEX_OP_OR = 2

Futex operation: Undocumented

FUTEX_OP_SET = 0

Futex operation: Undocumented

FUTEX_OP_XOR = 4

Futex operation: Undocumented

FUTEX_REQUEUE = 3

Futex option: requeue waiting processes on other futex.

FUTEX_TRYLOCK_PI = 8

Futex option: Undocumented

FUTEX_UNLOCK_PI = 7

Futex option: Undocumented

FUTEX_WAIT = 0

Futex option: Wait on futex till wake call arrives.

FUTEX_WAKE = 1

Futex option: wakes any waiting processes on this futex

FUTEX_WAKE_OP = 5

Futex option: Undocumented

GIO_CMAP = \$4B70

IOCTL: Get color palette on VGA+

GIO_FONT = \$4B60

IOCTL: Get font in expanded form.

GIO_FONTX = \$4B6B

IOCTL: Get font in consolefontdesc record.

GIO_SCRNMAP = \$4B40

IOCTL: get screen mapping from kernel

GIO_UNIMAP = \$4B66

IOCTL: get unicode-to-font mapping from kernel

GIO_UNISCRNMAP = \$4B69

IOCTL: get full Unicode screen mapping

IN_ACCESS = \$00000001

Data was read from file.

IN_ALL_EVENTS = IN_ACCESS or IN_MODIFY or IN_ATTRIB or IN_CLOSE or
IN_OPEN or IN_MOVE or IN_CREATE or IN_DELETE or IN_DELETE_SELF or
IN_MOVE_SELF

All possible events OR-ed together.

IN_ATTRIB = \$00000004

File attributes changed.

IN_CLOEXEC = &02000000

IN_CLOEXEC can be set to indicate that the inotify file handle must be closed on exec.

IN_CLOSE = IN_CLOSE_WRITE or IN_CLOSE_NOWRITE

File was closed (read or write)

IN_CLOSE_NOWRITE = \$00000010

File opened for read was closed

IN_CLOSE_WRITE = \$00000008

File opened for write was closed

IN_CREATE = \$00000100

A file was created in the directory.

IN_DELETE = \$00000200

A file was deleted from the directory.

IN_DELETE_SELF = \$00000400

Directory or file under observation was deleted.

IN_DONT_FOLLOW = \$02000000

Do not follow symlinks

IN_IGNORED = \$00008000

Watch was ignored (removed). Only reported.

IN_ISDIR = \$40000000

Event subject is a directory (reported only)

IN_MASK_ADD = \$20000000

Add events to existing watch (OR-ing the sets) if one exists.

IN_MODIFY = \$00000002

Data was written to file.

IN_MOVE = IN_MOVED_FROM or IN_MOVED_TO

File was moved (in or out of directory)

IN_MOVED_FROM = \$00000040

File was moved away from watched directory

IN_MOVED_TO = \$00000080

File was moved into watched directory

IN_MOVE_SELF = \$00000800

Directory or file under observation was moved.

IN_NONBLOCK = &00004000

IN_NONBLOCK can be set to indicate that the inotify file handle should not block read operations.

IN_ONESHOT = \$80000000

Only report one event, then remove the watch.

IN_ONLYDIR = \$01000000

Only watch filename if it is a directory.

IN_OPEN = \$00000020

File was opened

IN_Q_OVERFLOW = \$00004000

Queue overflowed. Only reported.

IN_UNMOUNT = \$00002000

File system on which file resides was unmounted. Only reported.

KB_101 = 2

IOCTL: Keyboard types: 101 keys

KB_84 = 1

IOCTL: Keyboard types: 84 keys

KB_OTHER = 3

IOCTL: Keyboard types: other type

KDADDIO = \$4B34

IOCTL: add i/o port as valid

KDDELIO = \$4B35

IOCTL: delete i/o port as valid

KDDISABIO = \$4B37

IOCTL: disable i/o to video board

KDENABIO = \$4B36

IOCTL: enable i/o to video board

KDFONTOP = \$4B72

IOCTL: font operations

KDGETKEYCODE = \$4B4C

IOCTL: read kernel keycode table entry

KDGETLED = \$4B31

IOCTL: return current led state

KDGETMODE = \$4B3B

IOCTL: get current mode

KDGKBDIACR = \$4B4A

IOCTL: read kernel accent table

KDGKBTYPE = \$4B33

IOCTL: get keyboard type

KDMAPDISP = \$4B3C

IOCTL: map display into address space

KDMKTONE = \$4B30

IOCTL: generate tone

KDSETKEYCODE = \$4B4D

IOCTL: write kernel keycode table entry

KDSETLED = \$4B32

IOCTL: set led state

KDSETMODE = \$4B3A

IOCTL: set text/graphics mode

KDSIGACCEPT = \$4B4E

IOCTL: accept kbd generated signals

KDSKBDIACR = \$4B4B

IOCTL: write kernel accent table

KDUNMAPDISP = \$4B3D

IOCTL: unmap display from address space

KD_GRAPHICS = 1

IOCTL: Tty modes: graphics mode

KD_TEXT = 0

IOCTL: Tty modes: Text mode

KD_TEXT0 = 2

IOCTL: Tty modes: Text mode (obsolete)

KD_TEXT1 = 3

IOCTL: Tty modes: Text mode (obsolete)

KIOCSOUND = \$4B2F

IOCTL: start/stop sound generation (0 for off)

LED_CAP = 4

IOCTL: LED_CAP : caps lock led

LED_NUM = 2

IOCTL: LED_SCR : Num lock led

LED_SCR = 1

IOCTL: LED_SCR : scroll lock led

LINUX_CAPABILITY_VERSION = \$19980330

Current capability version in use by kernel

MAP_DENYWRITE = \$800

Read-only

MAP_EXECUTABLE = \$1000

Memory area is marked as executable

MAP_GROWSDOWN = \$100

Memory map grows down, like stack

MAP_LOCKED = \$2000

Memory pages are locked

MAP_NORESERVE = \$4000

Do not check for reservations

MAX_CLOCKS = 16

Maximum number of clocks in the system

MODIFY_LDT_CONTENTS_CODE = 2

Modify_ldt option: Undocumented

MODIFY_LDT_CONTENTS_DATA = 0

Modify_ldt option: Undocumented

MODIFY_LDT_CONTENTS_STACK = 1

Modify_ldt option: Undocumented

O_CLOEXEC = \$80000

Close on exec flag: close file handle on exec call

PIO_CMAP = \$4B71

IOCTL: Set color palette on VGA+

PIO_FONT = \$4B61

IOCTL: Use font in expanded form.

PIO_FONTRESET = \$4B6D

IOCTL: Reset to default font

PIO_FONTX = \$4B6C

IOCTL: Set font in consolefontdesc record.

PIO_SCRNMAP = \$4B41

IOCTL: put screen mapping table in kernel

PIO_UNIMAP = \$4B67

IOCTL: put unicode-to-font mapping in kernel

PIO_UNIMAPCLR = \$4B68

IOCTL: clear table, possibly advise hash algorithm

PIO_UNISCRNMAP = \$4B6A

IOCTL: set full Unicode screen mapping

POLLMSG = \$0400

Unused in Linux

POLLRDHUP = \$2000

Peer Shutdown/closed writing half of connection

POLLREMOVE = \$1000

Undocumented Linux extension of Poll

SPLICE_F_GIFT = 8

Pages spliced in are a gift

SPLICE_F_MORE = 4

Expect more data

SPLICE_F_MOVE = 1

Move pages instead of copying

SPLICE_F_NONBLOCK = 2

Don't block on pipe splicing operations

SYNC_FILE_RANGE_WAIT_AFTER = 4

Wait upon write-out of specified pages in the range after performing any write.

SYNC_FILE_RANGE_WAIT_BEFORE = 1

Wait for write-out of previously-submitted specified pages before writing more data.

SYNC_FILE_RANGE_WRITE = 2

Initiate write of all dirty pages in the specified range.

UD_CONTENTS_CODE = MODIFY_LDT_CONTENTS_CODE shl 1

TLS segment descriptor: Undocumented

UD_CONTENTS_DATA = MODIFY_LDT_CONTENTS_DATA shl 1

TLS segment descriptor: Undocumented

UD_CONTENTS_STACK = MODIFY_LDT_CONTENTS_STACK shl 1

TLS segment descriptor: Undocumented

UD_LIMIT_IN_PAGES = \$10

TLS segment descriptor: Undocumented

UD_LM = \$80

TLS segment descriptor: Undocumented

UD_READ_EXEC_ONLY = \$08

TLS segment descriptor: Undocumented

UD_SEG_32BIT = \$01

TLS segment descriptor : Undocumented

UD_SEG_NOT_PRESENT = \$20

TLS segment descriptor: Undocumented

UD_USEABLE = \$40

TLS segment descriptor: Undocumented

61.3.2 Types

clockid_t = cint

Clock id type

```
EPoll_Data = record
case Integer of
0: (
    ptr : pointer;
);
1: (
    fd : cint;
);
2: (
    u32 : cuint;
);
3: (
    u64 : cuint64;
);
end
```

Data structure used in EPOLL IOCTL call.

PEPoll_Data = ^EPoll_Data

Pointer to EPoll_Data ([972](#)) record

`PEpoll_Event = ^EPoll_Event`

Pointer to `EPoll_Event` (982) type

`Pinotify_event = ^inotify_event`

Pointer to `inotify_event` (982) structure.

`PSysInfo = ^TSysInfo`

Pointer to `TSysInfo` (983) record.

`Puser_cap_data = ^user_cap_data`

Pointer to `user_cap_data` (983) record

`Puser_cap_header = ^user_cap_header`

Pointer to `user_cap_header` (983) record

`PUser_Desc = ^user_desc`

`PUser_Desc` is a pointer to the `user_desc` (983) type.

`TCloneFunc = function(args: pointer) : LongInt`

Clone function prototype.

`TEPoll_Data = EPoll_Data`

Alias for `EPoll_Data` (972) type

`TEPoll_Event = EPoll_Event`

Alias for `EPoll_Event` (982) type

`TUser_Desc = user_desc`

`TUser_Desc` is an alias for the `user_desc` (983) type.

61.4 Procedures and functions

61.4.1 capget

Synopsis: Return the capabilities for the indicated thread

Declaration: `function capget(header: Puser_cap_header; data: Puser_cap_data) : cint`

Visibility: default

Description: `capget` returns the capabilities of the indicated thread in `header`. The thread is identified by the process ID, or -1 for all caller (and child) process ID's.

Refer to the Linux man pages (7 capabilities) for more info.

Errors: On success, zero is returned, on error -1 is returned, and `fperno` is set to the error.

See also: `capset` (974)

61.4.2 capset

Synopsis: Set the capabilities for the indicated thread

Declaration: `function capset(header: Puser_cap_header; data: Puser_cap_data) : cint`

Visibility: default

Description: `capset` sets the capabilities of the indicated thread in `header`. The thread is identified by the process ID, or -1 for all caller (and child) process ID's.

Refer to the Linux man pages (7 capabilities) for more info.

Errors: On success, zero is returned, on error -1 is returned, and `fperrno` is set to the error.

See also: `capget` ([973](#))

61.4.3 clock_getres

Synopsis: Get clock resolution

Declaration: `function clock_getres(clk_id: clockid_t; res: ptimespec) : cint`

Visibility: default

Description: `clock_getres` returns the resolution of the clock specified in `clk_id` in the `res` structure. It can be `Nil`. if the clock exists and the resolution can be retrieved, 0 is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `clock_gettime` ([974](#)), `clock_settime` ([974](#))

61.4.4 clock_gettime

Synopsis: Get the time of a clock

Declaration: `function clock_gettime(clk_id: clockid_t; tp: ptimespec) : cint`

Visibility: default

Description: `clock_gettime` returns the current time of the clock specified in `clk_id` in the `tp` structure. If the clock exists and the time can be retrieved, 0 is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `clock_getres` ([974](#)), `clock_settime` ([974](#))

61.4.5 clock_settime

Synopsis: Set the time of a clock

Declaration: `function clock_settime(clk_id: clockid_t; tp: ptimespec) : cint`

Visibility: default

Description: `clock_settime` sets the current time of the clock specified in `clk_id`. The time is specified in the `tp` structure. If the clock exists and the time can be retrieved, 0 is returned. The resolution is truncated to the resolution supported by the specified clock. Note that not all clocks can be set.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `clock_getres` ([974](#)), `clock_gettime` ([974](#))

61.4.6 clone

Synopsis: Clone current process (create new thread)

Declaration: `function clone(func: TCloneFunc; sp: pointer; flags: LongInt; args: pointer) : LongInt`

Visibility: default

Description: `Clone` creates a child process which is a copy of the parent process, just like `FpFork` (190) does. In difference with `Fork`, however, the child process shares some parts of it's execution context with its parent, so it is suitable for the implementation of threads: many instances of a program that share the same memory.

When the child process is created, it starts executing the function `Func`, and passes it `Args`. The return value of `Func` is either the explicit return value of the function, or the exit code of the child process.

The `sp` pointer points to the memory reserved as stack space for the child process. This address should be the top of the memory block to be used as stack.

The `Flags` determine the behaviour of the `Clone` call. The low byte of the `Flags` contains the number of the signal that will be sent to the parent when the child dies. This may be bitwise OR'ed with the following constants:

CLONE_VMParent and child share the same memory space, including memory (un)mapped with subsequent `mmap` calls.

CLONE_FSParent and child have the same view of the file system; the `chroot`, `chdir` and `umask` calls affect both processes.

CLONE_FILESthe file descriptor table of parent and child is shared.

CLONE_SIGHANDthe parent and child share the same table of signal handlers. The signal masks are different, though.

CLONE_PIDParent and child have the same process ID.

`Clone` returns the process ID in the parent process, and -1 if an error occurred.

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagainToo many processes are running.

sys_enomemNot enough memory to create child process.

See also: `#rtl.baseunix.FpFork` (190)

61.4.7 epoll_create

Synopsis: Create new epoll file descriptor

Declaration: `function epoll_create(size: cint) : cint`

Visibility: default

Description: `epoll_create` creates a new epoll file descriptor. The `size` argument indicates to the kernel approximately how many structures should be allocated, but is by no means an upper limit.

On success, a file descriptor is returned that can be used in subsequent `epoll_ctl` (976) or `epoll_wait` (976) calls, and should be closed using the `fpClose` (183) call.

Errors: On error, -1 is returned, and `errno` (193) is set.

See also: `epoll_ctl` (976), `epoll_wait` (976), `fpClose` (183)

61.4.8 `epoll_ctl`

Synopsis: Modify an epoll file descriptor

Declaration: `function epoll_ctl(epfd: cint; op: cint; fd: cint; event: PEpoll_Event)
: cint`

Visibility: default

Description: `epoll_ctl` performs the `op` operation on epoll file descriptor `epfd`. The operation will be monitored on file descriptor `fd`, and is optionally controlled by `event`.

`op` can be one of the following values:

EPOLL_CTL_ADDAdd filedescriptor to list of events

EPOLL_CTL_MODModify event for filedescriptor

EPOLL_CTL_DELDelete event for filedescriptor

The `events` field in `event_data` is a bitmask of one or more of the following values:

EPOLLINThe file is ready for read operations

EPOLLOUTThe file is ready for write operations.

EPOLLPRIUrgent data is available for read operations.

EPOLLERRAn error condition is signaled on the file descriptor.

EPOLLHUPA Hang up happened on the file descriptor.

EPOLLETSet the Edge Triggered behaviour for the file descriptor.

EPOLLONESHOTSet One-Shot behaviour for the file descriptor. The event will be triggered only once.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` (975), `epoll_wait` (976), `fpClose` (183)

61.4.9 `epoll_wait`

Synopsis: Wait for an event on an epoll file descriptor.

Declaration: `function epoll_wait(epfd: cint; events: PEpoll_Event; maxevents: cint;
timeout: cint) : cint`

Visibility: default

Description: `epoll_wait` waits for `timeout` milliseconds for an event to occur on epoll file descriptor `epfd`. If `timeout` is -1, it waits indefinitely, if `timeout` is zero, it does not wait, but returns immediately, even if no events were detected.

On return, data for at most `maxevents` will be returned in the memory pointed to by `events`. The function returns the number of file descriptors for which events were reported. This can be zero if the timeout was reached.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` (975), `epoll_ctl` (976), `fpClose` (183)

61.4.10 fdatasync

Synopsis: Synchronize the data in memory with the data on storage device

Declaration: `function fdatasync(fd: cint) : cint`

Visibility: default

Description: `fdatasync` does the same as `ffsync` but does not flush the metadata, unless it is vital to the correct reading/writing of the file. In practice, this means that unless the file size changed, the file metadata will not be synced.

See also: `#rtl.unix.fsync` ([2089](#))

61.4.11 futex

Synopsis: Perform a futex operation

Declaration: `function futex(uaddr: pcint; op: cint; val: cint; timeout: timespec; addr2: pcint; val3: cint) : cint`
`function futex(var uaddr; op: cint; val: cint; timeout: timespec; var addr2; val3: cint) : cint`
`function futex(var uaddr; op: cint; val: cint; var timeout: TTimeSpec; var addr2; val3: cint) : cint`
`function futex(uaddr: pcint; op: cint; val: cint; timeout: timespec) : cint`
`function futex(var uaddr; op: cint; val: cint; timeout: timespec) : cint`
`function futex(var uaddr; op: cint; val: cint; var timeout: TTimeSpec) : cint`

Visibility: default

Description: `futex` performs an operation on a memory futex as described in the kernel manual page for `futex`. The mutex is located at `uaddr`, the operation `op` is one of the following constants:

FUTEX_WAITFutex option: Wait on futex till wake call arrives.

FUTEX_WAKEFutex option: Wait on futex till wake call arrives.

FUTEX_FDFutex option: Associate file descriptor with futex.

FUTEX_REQUEUEFutex option: requeue waiting processes on other futex.

FUTEX_CMP_REQUEUEFutex option: requeue waiting processes on other futex, but check it's value first

The value to check for is indicated in `val`, and a timeout can be specified in `timeout`. The optional arguments `addr2` and `val3` are used only with the `FUTEX_REQUEUE` and `FUTEX_CMP_REQUEUE` operations.

In case of an error, -1 is return. All other return values must be interpreted according to the operation performed.

This call directly interfaces with the Linux kernel, more information can be found in the kernel manual pages.

Errors: On error, -1 is returned. Use `#rtl.baseunix.fpgeterrno` ([193](#)) to get the error code.

61.4.12 futex_op

Synopsis: Futex operation:

Declaration: `function futex_op(op: cint; oparg: cint; cmp: cint; cmparg: cint) : cint`

Visibility: default

Description: `FUTEX_OP` Performs an operation on a futex:

```
FUTEX_OP := ((op and $F) shl 28) or
             ((cmp and $F) shl 24) or
             ((oparg and $FFF) shl 12)
             or (cmparg and $FFF);
```

61.4.13 inotify_add_watch

Synopsis: Add a watch to a notify file descriptor

Declaration: `function inotify_add_watch(fd: cint; name: PChar; mask: cuint32) : cint`

Visibility: default

Description: `inotify_add_watch` can be used to add a watch to an initialized inotify file descriptor (`fd`). The file or directory to watch can be specified in the `name` parameter, and the events that must be reported can be specified in `mask`. The following flags can be specified:

- IN_ACCESS**Data was read from file.
- IN_MODIFY**Data was written to file.
- IN_ATTRIB**File attributes changed.
- IN_CLOSE_WRITE**File opened for write was closed
- IN_CLOSE_NOWRITE**File opened for read was closed
- IN_CLOSE**File was closed (read or write)
- IN_OPEN**File was opened
- IN_MOVED_FROM**File was moved away from watched directory
- IN_MOVED_TO**File was moved into watched directory
- IN_MOVE**File was moved (in or out of directory)
- IN_CREATE**A file was created in the directory.
- IN_DELETE**A file was deleted from the directory.
- IN_DELETE_SELF**Directory or file under observation was deleted.
- IN_MOVE_SELF**Directory or file under observation was moved.
- IN_ALL_EVENTS**All possible events OR-ed together.

These events can be OR-ed with some flags, controlling the behaviour of the watch:

- IN_ONLYDIR**Only watch filename if it is a directory.
- IN_ISDIR**Event occurred against directory.
- IN_DONT_FOLLOW**Do not follow symlinks
- IN_MASK_ADD**Add events to existing watch (OR-ing the sets) if one exists.
- IN_ONESHOT**Only report one event, then remove the watch.

On return, the function returns a watch descriptor, which will be reported in the `inotify_event` (982) structure's `wd`.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `inotify_init` (979), `inotify_init1` (979), `inotify_rm_watch` (979), `inotify_event` (982)

61.4.14 inotify_init

Synopsis: Initialize a new inotify file descriptor

Declaration: `function inotify_init : cint`

Visibility: default

Description: `inotify_init` initializes a new `INotify` file descriptor. No options can be specified. On return, the file descriptor is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information

See also: `inotify_init1` (979), `inotify_add_watch` (978), `inotify_rm_watch` (979)

61.4.15 inotify_init1

Synopsis: Initialize a new inotify file descriptor with extra options.

Declaration: `function inotify_init1(flags: cint) : cint`

Visibility: default

Description: `inotify_init1` initializes a new `INotify` file descriptor. The following options can be OR-ed and passed in flags:

IN_NONBLOCK Do not block on read

IN_CLOEXEC Inotify close on exec flag.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `inotify_init` (979), `inotify_add_watch` (978), `inotify_rm_watch` (979)

61.4.16 inotify_rm_watch

Synopsis: Remove watch from Inotify file descriptor.

Declaration: `function inotify_rm_watch(fd: cint; wd: cint) : cint`

Visibility: default

Description: `inotify_rm_watch` removes watch descriptor `wd` from inotify descriptor `fd`. On success, 0 is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `inotify_init` (979), `inotify_init1` (979), `inotify_add_watch` (978), `inotify_event` (982)

61.4.17 modify_ldt

Declaration: `function modify_ldt(func: cint; p: pointer; bytecount: culong) : cint`

Visibility: default

61.4.18 sched_yield

Synopsis: Yield the processor to another thread.

Declaration: `procedure sched_yield`

Visibility: default

Description: `sched_yield` yields the processor to another thread. The current thread is put at the back of its queue. If there is only 1 thread in the application, the thread continues to run. The call always returns zero.

61.4.19 setregid

Synopsis: Set Real and Effective Group ID

Declaration: `function setregid(rgid: uid_t; egid: uid_t) : cint`

Visibility: default

Description: `setregid` sets the real group ID to `rgid` and the effective group ID to `egid`. Passing a value of -1 tells the system not to change that value.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `setreuid` (980)

61.4.20 setreuid

Declaration: `function setreuid(ruid: uid_t; euid: uid_t) : cint`

Visibility: default

Description: `setreuid` sets the real user ID to `ruid` and the effective user ID to `euid`. Passing a value of -1 tells the system not to change that value.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `setregid` (980)

61.4.21 sync_file_range

Synopsis: Force committing of data to disk

Declaration: `function sync_file_range(fd: cint; offset: off64_t; nbytes: off64_t; flags: cuint) : cint`

Visibility: default

Description: `sync_file_range` forces the Linux kernel to write any data pages of a specified file (file descriptor `fd`) to disk. The range of the file is specified by the offset `offset` and the number of bytes `nbytes`. `Options` is an OR-ed combination of

SYNC_FILE_RANGE_WAIT_BEFORE Wait for write-out of previously-submitted specified pages before writing more data.

SYNC_FILE_RANGE_WRITE Initiate write of all dirty pages in the specified range.

SYNC_FILE_RANGE_WAIT_AFTER Wait upon write-out of specified pages in the range after performing any write.

If none is specified, the operation does nothing.

Errors: On return -1 is returned and `fperno` is set to the actual error code. See the Linux man page for more on the error codes.

See also: `fdatasync` ([977](#))

61.4.22 Sysinfo

Synopsis: Return kernel system information

Declaration: `function Sysinfo(Info: PSysInfo) : cint`

Visibility: default

Description: `SysInfo` returns system information in `Info`. Returned information in `Info` includes:

- uptime** Number of seconds since boot.
- loads** 1, 5 and 15 minute load averages.
- totalram** total amount of main memory.
- freeram** amount of free memory.
- sharedram** amount of shared memory.
- bufferram** amount of memory used by buffers.
- totalswap** total amount of swap space.
- freeswap** amount of free swap space.
- procs** number of current processes.

Errors: None.

See also: `#rtl.baseunix.fpUname` ([229](#))

Listing: `./examples/linuxex/ex64.pp`

```

program Example64;

{ Example to demonstrate the SysInfo function.
  Sysinfo is Linux-only. }

{$ifdef Linux}
Uses Linux;

Function Mb(L : Longint) : longint;

begin
  Mb:=L div (1024*1024);
end;

Var Info : TSysInfo;
      D,M,Secs,H : longint;
{$endif}

begin
  {$ifdef Linux}
  If Not (SysInfo(@Info)=0) then
    Halt(1);
  
```

```

With Info do
  begin
    D:=Uptime div (3600*24);
    UpTime:=UpTime mod (3600*24);
    h:=uptime div 3600;
    uptime:=uptime mod 3600;
    m:=uptime div 60;
    secs:=uptime mod 60;
    Writeln('Uptime : ',d,'days, ',h,' hours, ',m,' min, ',secs,' s. ');
    Writeln('Loads   : ',Loads[1], '/',Loads[2], '/',Loads[3]);
    Writeln('Total Ram   : ',Mb(totalram), 'Mb. ');
    Writeln('Free Ram    : ',Mb(freeram), 'Mb. ');
    Writeln('Shared Ram  : ',Mb(sharedram), 'Mb. ');
    Writeln('Buffer Ram  : ',Mb(bufferram), 'Mb. ');
    Writeln('Total Swap  : ',Mb(totalswap), 'Mb. ');
    Writeln('Free Swap   : ',Mb(freeswap), 'Mb. ');
  end;
{ $endif }
end.

```

61.5 EPoll_Event

```

EPoll_Event = packed record
  Events : cuint32;
  Data : TEPoll_Data
;
end

```

Structure used in `epoll_ctl` ([976](#)) call.

61.6 inotify_event

```

inotify_event = record
  wd : cint;
  mask : cuint32;
  cookie : cuint32
;
  len : cuint32;
  name : Char;
end

```

`inotify_event` is the structure used to report changes in a directory. When reading a `inotify` file descriptor, one or more `inotify_event` records can be read from the file descriptor.

61.7 TSysInfo

```

TSysInfo = record
  uptime : clong;
  loads : Array[0..2] of culong
;

```

```

totalram : culong;
freeram : culong;
sharedram : culong;
bufferram : culong;
totalswap : culong;
freeswap : culong;
procs : cushort;
pad : cushort;
totalhigh : culong;
freehigh
: culong;
mem_unit : cuint;
end

```

Record with system information, used by the SysInfo (981) call.

61.8 user_cap_data

```

user_cap_data = record
  effective : cuint32;
  permitted : cuint32
;
  inheritable : cuint32;
end

```

user_cap_data describes the set of capabilities for the indicated thread.

61.9 user_cap_header

```

user_cap_header = record
  version : cuint32;
  pid : cint;
end

```

user_cap_header describes the root user capabilities for the current thread, as set by capget (973) and capset (974)

61.10 user_desc

```

user_desc = record
  entry_number : cuint;
  base_addr : cuint;
  limit : cuint;
  flags : cuint;
end

```

user_desc is the TLS (Thread Local Storage) segment descriptor used in the Clone call. It should not be used, as it contains highly kernel-specific data.

Chapter 62

Reference for unit 'Infodwrf'

62.1 Used units

Table 62.1: Used units by unit 'Infodwrf'

Name	Page
System	1339

62.2 Overview

The `Infodwrf` provides a routine that reads the debug information of an executable (if any exists) and returns source code information about this address. It works with DWARF debug information. Note that this unit is not thread-safe, and that its behaviour is undefined if multiple threads try to write a backtrace at the same time.

For stabs debug information, the `lineinfo` ([955](#)) unit must be used.

62.3 Constants, types and variables

62.3.1 Types

`CodePointer = Pointer`

`CodePointer` is added for 16-bit dos compatibility.

62.3.2 Variables

`AllowReuseOfLineInfoData : Boolean = True`

`AllowReuseOfLineInfoData` can be set to `True` to keep the last opened file open. When regularly creating backtraces (e.g. in a program log), this will significantly speed up operations.

62.4 Procedures and functions

62.4.1 CloseDwarf

Synopsis: Close DWARF info file descriptor

Declaration: `procedure CloseDwarf`

Visibility: default

Description: `CloseDwarf` will close the file descriptor that was used to read DWARF debug information. This is useful if `AllowReuseOfLineInfoData` (984) is used to cache DWARF information.

Errors: None.

See also: `AllowReuseOfLineInfoData` (984)

62.4.2 DwarfBackTraceStr

Synopsis: Get a backtrace from an address

Declaration: `function DwarfBackTraceStr(addr: CodePointer) : string`

Visibility: default

Description: `DwarfBackTraceStr` returns a backtrace from a memory address `Addr`.

This is the actual callback for the backtrace handler `System.BackTraceStrFunc` (984).

Errors: None.

See also: `GetLineInfo` (985)

62.4.3 GetLineInfo

Synopsis: Return source line information about an address.

Declaration: `function GetLineInfo(addr: CodePtrUInt; var func: string;
var source: string; var line: LongInt) : Boolean`

Visibility: default

Description: `GetLineInfo` returns source line information about the address `addr`. It searches this information in the DWARF debugging information found in the binary: If the file was compiled without debug information, nothing will be returned. Upon successful retrieval of the debug information, `True` is returned, and the `func` parameter is filled with the name of the function in which the address is located. The `source` parameter contains the name of the file in which the function was implemented, and `line` contains the line number in the source file for `addr`.

Errors: If no debug information is found, `False` is returned.

Chapter 63

Reference for unit 'Math'

63.1 Used units

Table 63.1: Used units by unit 'Math'

Name	Page
System	1339
sysutils	1615

63.2 Overview

This document describes the `math` unit. The `math` unit was initially written by Florian Klaempfl. It provides mathematical functions which aren't covered by the system unit.

This chapter starts out with a definition of all types and constants that are defined, after which an overview is presented of the available functions, grouped by category, and the last part contains a complete explanation of each function.

The following things must be taken into account when using this unit:

1. This unit is compiled in Object Pascal mode so all `integers` are 32 bit.
2. Some overloaded functions exist for data arrays of integers and floats. When using the address operator (`@`) to pass an array of data to such a function, make sure the address is typecasted to the right type, or turn on the 'typed address operator' feature. failing to do so, will cause the compiler not be able to decide which function you want to call.

63.3 Cash flow functions

The cash flow functions in the `math` unit resolve the following equation:

$$FV + PV * q^n + PMT (q^n - 1) / (q - 1) = 0$$

In this formula, the following variables are present:

FV Future value

PV Present value

PMT Payment per period

n Number of payments (number of periods)

q> Interest Rate (return rate)

The financial functions FutureValue (1003), NumberOfPeriods (1019), Payment (1020), PresentValue (1023) and InterestRate (1006) solve this equation for one of the variables, when the other variables are known.

See also: FutureValue (1003), NumberOfPeriods (1019), Payment (1020), PresentValue (1023), TPaymentTime (991)

63.4 Geometrical functions

Table 63.2:

Name	Description
hypot (1005)	Hypotenuse of triangle
norm (1019)	Euclidean norm

63.5 Statistical functions

Table 63.3:

Name	Description
mean (1013)	Mean of values
meanandstddev (1014)	Mean and standard deviation of values
momentskewkurtosis (1017)	Moments, skew and kurtosis
popnstddev (1020)	Population standard deviation
popnvariance (1021)	Population variance
randg (1024)	Gaussian distributed random value
stddev (1029)	Standard deviation
sum (1030)	Sum of values
sumofsquares (1031)	Sum of squared values
sumsandsquares (1032)	Sum of values and squared values
totalvariance (1034)	Total variance of values
variance (1035)	variance of values

63.6 Number converting

Table 63.4:

Name	Description
<code>ceil</code> (996)	Round to infinity
<code>floor</code> (1001)	Round to minus infinity
<code>frexp</code> (1003)	Return mantissa and exponent

63.7 Exponential and logarithmic functions

Table 63.5:

Name	Description
<code>intpower</code> (1007)	Raise float to integer power
<code>ldexp</code> (1008)	Calculate $2^x \times \text{float}$
<code>lnxp1</code> (1009)	calculate $\log(x+1)$
<code>log10</code> (1009)	calculate 10-base log
<code>log2</code> (1010)	calculate 2-base log
<code>logn</code> (1010)	calculate N-base log
<code>power</code> (1022)	raise float to arbitrary power

63.8 Hyperbolic functions

Table 63.6:

Name	Description
<code>arcosh</code> (993)	calculate reverse hyperbolic cosine
<code>arsinh</code> (995)	calculate reverse hyperbolic sine
<code>artanh</code> (995)	calculate reverse hyperbolic tangent
<code>cosh</code> (998)	calculate hyperbolic cosine
<code>sinh</code> (1029)	calculate hyperbolic sine
<code>tanh</code> (1034)	calculate hyperbolic tangent

63.9 Trigonometric functions

Table 63.7:

Name	Description
<code>arccos</code> (992)	calculate reverse cosine
<code>arcsin</code> (993)	calculate reverse sine
<code>arctan2</code> (994)	calculate reverse tangent
<code>cotan</code> (998)	calculate cotangent
<code>sincos</code> (1028)	calculate sine and cosine
<code>tan</code> (1033)	calculate tangent

63.10 Angle unit conversion

Routines to convert angles between different angle units.

Table 63.8:

Name	Description
<code>cycletorad</code> (999)	convert cycles to radians
<code>degtograd</code> (1000)	convert degrees to grads
<code>degtorad</code> (1000)	convert degrees to radians
<code>gradtodeg</code> (1004)	convert grads to degrees
<code>gradtorad</code> (1005)	convert grads to radians
<code>radto cycle</code> (1023)	convert radians to cycles
<code>radtodeg</code> (1023)	convert radians to degrees
<code>radto grad</code> (1024)	convert radians to grads

63.11 Min/max determination

Functions to determine the minimum or maximum of numbers:

Table 63.9:

Name	Description
<code>max</code> (1011)	Maximum of 2 values
<code>maxIntValue</code> (1011)	Maximum of an array of integer values
<code>maxvalue</code> (1012)	Maximum of an array of values
<code>min</code> (1015)	Minimum of 2 values
<code>minIntValue</code> (1015)	Minimum of an array of integer values
<code>minvalue</code> (1016)	Minimum of an array of values

63.12 Constants, types and variables

63.12.1 Constants

`EqualsValue = 0`

Values are the same

`GreaterThanValue = High(TValueRelationship)`

First values is greater than second value

`Infinity = 1.0 / 0.0`

Value is infinity

`LessThanValue = Low(TValueRelationship)`

First value is less than second value

`MaxFloat = 0`

Maximum value of float type

`MinFloat = 0`

Minimum value (closest to zero) of float type

`NaN = 0.0 / 0.0`

Value is Not a Number

`NegativeValue = Low(TValueSign)`

Value is negative

`NegInfinity = (- 1.0) / (0.0)`

Value is negative (minus) infinity

`PositiveValue = High(TValueSign)`

Value is positive

`ZeroValue = 0`

Value is zero

63.12.2 Types

`Float = MaxFloatType`

All calculations are done with the `Float` type which is the largest float type available for the current CPU. This allows to recompile the unit with a different float type to obtain a desired precision. The pointer type `PFloat` (991) is used in functions that accept an array of values of arbitrary length.

`PFloat = ^Float`

Pointer to `Float` (991) type.

`PInteger = ObjPas.PInteger`

Pointer to integer type

`TFPUException = system.TFPUException`

Type describing Floating Point processor exceptions.

`TFPUExceptionMask = system.TFPUExceptionMask`

Type to set the Floating Point Unit exception mask.

`TFPUPrecisionMode = system.TFPUPrecisionMode`

Type describing the default precision for the Floating Point processor.

`TFPURoundingMode = system.TFPURoundingMode`

Type describing the rounding mode for the Floating Point processor.

`TPaymentTime = (ptEndOfPeriod, ptStartOfPeriod)`

Table 63.10: Enumeration values for type `TPaymentTime`

Value	Explanation
<code>ptEndOfPeriod</code>	End of period.
<code>ptStartOfPeriod</code>	Start of period.

Type used in financial (interest) calculations.

`TRoundToRange = - 37..37`

`TRoundToRange` is the range of valid digits to be used in the `RoundTo` (1026) function.

`TValueRelationship = - 1..1`

Type to describe relational order between values

`TValueSign = - 1..1`

Type indicating sign of a value

63.13 Procedures and functions

63.13.1 ArcCos

Synopsis: Return inverse cosine

Declaration: `function ArcCos(x: Float) : Float`

Visibility: default

Description: `Arccos` returns the inverse cosine of its argument `x`. The argument `x` should lie between -1 and 1 (borders included).

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arcsin` ([993](#)), `arcosh` ([993](#)), `arsinh` ([995](#)), `artanh` ([995](#))

Listing: `./examples/mathex/ex1.pp`

Program `Example1`;

{ Program to demonstrate the arccos function. }

Uses `math`;

Procedure `WriteRadDeg(X : float)`;

begin

`WriteLn(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')`

end;

begin

`WriteRadDeg (arccos (1));`

`WriteRadDeg (arccos (sqrt (3)/2));`

`WriteRadDeg (arccos (sqrt (2)/2));`

`WriteRadDeg (arccos (1/2));`

`WriteRadDeg (arccos (0));`

`WriteRadDeg (arccos (-1));`

end.

63.13.2 ArcCosh

Synopsis: Return inverse hyperbolic cosine

Declaration: `function ArcCosH(x: Float) : Float`

Visibility: default

Description: `arccosh` returns the inverse hyperbolic cosine of its argument `x`.

This function is an alias for `arcosh` ([993](#)), provided for Delphi compatibility.

See also: `arcosh` ([993](#))

63.13.3 ArCosh

Synopsis: Return inverse hyperbolic cosine

Declaration: `function ArCosh(x: Float) : Float`

Visibility: default

Description: `Arcosh` returns the inverse hyperbolic cosine of its argument `x`. The argument `x` should be larger than 1. The `arccosh` variant of this function is supplied for Delphi compatibility.

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `cosh` (998), `sinh` (1029), `arcsin` (993), `arsinh` (995), `artanh` (995), `tanh` (1034)

Listing: `./examples/mathex/ex3.pp`

Program Example3;

{ Program to demonstrate the arcosh function. }

Uses math;

begin

WriteLn(`arcosh(1)`);

WriteLn(`arcosh(2)`);

end.

63.13.4 ArcSin

Synopsis: Return inverse sine

Declaration: `function ArcSin(x: Float) : Float`

Visibility: default

Description: `Arcsin` returns the inverse sine of its argument `x`. The argument `x` should lie between -1 and 1.

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arccos` (992), `arcosh` (993), `arsinh` (995), `artanh` (995)

Listing: `./examples/mathex/ex2.pp`

Program Example1;

{ Program to demonstrate the arcsin function. }

Uses math;

Procedure WriteRadDeg(X : float);

begin

WriteLn(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')

end;

begin

 WriteRadDeg (arcsin(1));

 WriteRadDeg (arcsin(**sqrt**(3)/2));

```

WriteRadDeg ( arcsin (sqrt (2)/2));
WriteRadDeg ( arcsin (1/2));
WriteRadDeg ( arcsin (0));
WriteRadDeg ( arcsin (-1));
end.

```

63.13.5 ArcSinH

Synopsis: Return inverse hyperbolic sine

Declaration: `function ArcSinH(x: Float) : Float`

Visibility: default

Description: `arcsinh` returns the inverse hyperbolic sine of its argument `x`.

This function is an alias for `arsinh` (995), provided for Delphi compatibility.

See also: `arsinh` (995)

63.13.6 ArcTan2

Synopsis: Return arctangent of (y/x)

Declaration: `function ArcTan2(y: Float; x: Float) : Float`

Visibility: default

Description: `arctan2` calculates `arctan(y/x)`, and returns an angle in the correct quadrant. The returned angle will be in the range $-\pi$ to π radians. The values of `x` and `y` must be between -2^{64} and 2^{64} , moreover `x` should be different from zero. On Intel systems this function is implemented with the native intel `fpatan` instruction.

See also: `arccos` (992), `arcosh` (993), `arsinh` (995), `artanh` (995)

Listing: `./examples/mathex/ex6.pp`

Program Example6;

{ Program to demonstrate the arctan2 function. }

Uses math;

Procedure WriteRadDeg(X : float);

begin

WriteLn(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')

end;

begin

WriteRadDeg (arctan2(2,1));

end.

63.13.7 ArcTanH

Synopsis: Return inverse hyperbolic tangent

Declaration: `function ArcTanH(x: Float) : Float`

Visibility: default

Description: `arsinh` returns the inverse hyperbolic tangent of its argument `x`.

This function is an alias for `artanh` (995), provided for Delphi compatibility.

See also: `artanh` (995)

63.13.8 ArSinH

Synopsis: Return inverse hyperbolic sine

Declaration: `function ArSinH(x: Float) : Float`

Visibility: default

Description: `arsinh` returns the inverse hyperbolic sine of its argument `x`. The `arscsinh` variant of this function is supplied for Delphi compatibility.

Errors: None.

See also: `arcosh` (993), `arccos` (992), `arcsin` (993), `artanh` (995)

Listing: `./examples/mathex/ex4.pp`

Program Example4;

{ Program to demonstrate the arsinh function. }

Uses math;

begin

WriteLn(`arsinh(0)`);

WriteLn(`arsinh(1)`);

end.

63.13.9 ArTanH

Synopsis: Return inverse hyperbolic tangent

Declaration: `function ArTanH(x: Float) : Float`

Visibility: default

Description: `artanh` returns the inverse hyperbolic tangent of its argument `x`, where `x` should lie in the interval `[-1,1]`, borders included. The `arctanh` variant of this function is supplied for Delphi compatibility.

Errors: In case `x` is not in the interval `[-1,1]`, an `EInvalidArgument` exception is raised.

See also: `arcosh` (993), `arccos` (992), `arcsin` (993), `artanh` (995)

Listing: `./examples/mathex/ex5.pp`

```

Program Example5;

{ Program to demonstrate the artanh function. }

Uses math;

begin
  WriteLn(artanh(0));
  WriteLn(artanh(0.5));
end.

```

63.13.10 Ceil

Synopsis: Return the lowest integer number greater than or equal to argument

Declaration: `function Ceil(x: Float) : Integer`

Visibility: default

Description: `Ceil` returns the lowest integer number greater than or equal to `x`. The absolute value of `x` should be less than `maxint`.

Errors: If the absolute value of `x` is larger than `maxint`, an overflow error will occur.

See also: `floor` ([1001](#))

Listing: `./examples/mathex/ex7.pp`

```

Program Example7;

{ Program to demonstrate the Ceil function. }

Uses math;

begin
  WriteLn(Ceil(-3.7)); // should be -3
  WriteLn(Ceil(3.7)); // should be 4
  WriteLn(Ceil(-4.0)); // should be -4
end.

```

63.13.11 Ceil64

Synopsis: Round to the nearest bigger int64 value

Declaration: `function Ceil64(x: Float) : Int64`

Visibility: default

Description: `Ceil64` rounds the value `X` to the nearest bigger int64 value. The result is always bigger than `X`.

Errors: None.

See also: `ceil` ([996](#)), `floor64` ([1002](#))

63.13.12 ClearExceptions

Synopsis: Clear Floating Point Unit exceptions

Declaration: `procedure ClearExceptions(RaisePending: Boolean)`

Visibility: default

Description: Clear Floating Point Unit exceptions

63.13.13 CompareValue

Synopsis: Compare 2 values

Declaration: `function CompareValue(const A: Integer; const B: Integer) : TValueRelationship`
`function CompareValue(const A: Int64; const B: Int64) : TValueRelationship`
`function CompareValue(const A: QWord; const B: QWord) : TValueRelationship`
`function CompareValue(const A: Single; const B: Single; delta: Single) : TValueRelationship`
`function CompareValue(const A: Double; const B: Double; delta: Double) : TValueRelationship`
`function CompareValue(const A: Extended; const B: Extended; delta: Extended) : TValueRelationship`

Visibility: default

Description: CompareValue compares 2 integer or floating point values A and B and returns one of the following values:

-1 if $A < B$

0 if $A = B$

1 if $A > B$

See also: TValueRelationship ([991](#))

63.13.14 Cosecant

Synopsis: Calculate cosecant

Declaration: `function Cosecant(x: Float) : Float`

Visibility: default

Description: cosecant calculates the cosecant ($1/\sin(x)$) of its argument x.

Errors: If 0 or 180 degrees is specified, an exception will be raised.

See also: secant ([1027](#))

63.13.15 Cosh

Synopsis: Return hyperbolic cosine

Declaration: `function CosH(x: Float) : Float`

Visibility: default

Description: `Cosh` returns the hyperbolic cosine of it's argument {x}.

Errors: None.

See also: `arcosh` (993), `sinh` (1029), `arsinh` (995)

Listing: `./examples/mathex/ex8.pp`

Program `Example8;`

{ Program to demonstrate the cosh function. }

Uses `math;`

begin

`WriteLn(Cosh(0));`

`WriteLn(Cosh(1));`

end.

63.13.16 Cot

Synopsis: Alias for `Cotan`

Declaration: `function Cot(x: Float) : Float`

Visibility: default

Description: `cot` is an alias for the `cotan` (998) function.

See also: `cotan` (998)

63.13.17 Cotan

Synopsis: Return cotangent

Declaration: `function Cotan(x: Float) : Float`

Visibility: default

Description: `Cotan` returns the cotangent of it's argument x. The argument x must be in radians. x should be different from zero.

Errors: If x is zero then a overflow error will occur.

See also: `tanh` (1034)

Listing: `./examples/mathex/ex9.pp`

Program Example9;

{ Program to demonstrate the cotan function. }

Uses math;

begin

writeln(cotan(**pi**/2));

Writeln(cotan(**pi**/3));

Writeln(cotan(**pi**/4));

end.

63.13.18 Csc

Synopsis: Alias for cosecant

Declaration: `function Csc(x: Float) : Float`

Visibility: default

Description: `csc` is an alias for the cosecant (997) function.

See also: cosecant (997)

63.13.19 CycleToRad

Synopsis: Convert cycle angle to radians angle

Declaration: `function CycleToRad(cycle: Float) : Float`

Visibility: default

Description: `Cycletorad` transforms it's argument `cycle` (an angle expressed in cycles) to radians. (1 cycle is 2π radians).

Errors: None.

See also: `degtograd` (1000), `degtorad` (1000), `radtodeg` (1023), `radtograd` (1024), `radto cycle` (1023)

Listing: ./examples/mathex/ex10.pp

Program Example10;

{ Program to demonstrate the cycletorad function. }

Uses math;

begin

writeln(**cos**(cycletorad(1/6))); *// Should print 1/2*

writeln(**cos**(cycletorad(1/8))); *// should be sqrt(2)/2*

end.

63.13.20 DegNormalize

Synopsis: Normalize an angle measured in degrees

Declaration: `function DegNormalize(deg: single) : single`
`function DegNormalize(deg: Double) : Double`
`function DegNormalize(deg: extended) : extended`

Visibility: default

Description: `DegNormalize` returns the angle `deg` as a positive angle between 0 and 360 degrees.

63.13.21 DegToGrad

Synopsis: Convert degree angle to grads angle

Declaration: `function DegToGrad(deg: Float) : Float`

Visibility: default

Description: `Degtograd` transforms it's argument `deg` (an angle in degrees) to grads. (90 degrees is 100 grad.)

Errors: None.

See also: `cycletorad` ([999](#)), `degtorad` ([1000](#)), `radtodeg` ([1023](#)), `radtograd` ([1024](#)), `radtcycle` ([1023](#))

Listing: `./examples/mathex/ex11.pp`

Program `Example11`;

{ Program to demonstrate the degto grad function. }

Uses `math`;

begin
`writeln(degto grad(90));`
`writeln(degto grad(180));`
`writeln(degto grad(270))`
end.

63.13.22 DegToRad

Synopsis: Convert degree angle to radians angle.

Declaration: `function DegToRad(deg: Float) : Float`

Visibility: default

Description: `Degtorad` converts it's argument `deg` (an angle in degrees) to radians. (pi radians is 180 degrees)

Errors: None.

See also: `cycletorad` ([999](#)), `degto grad` ([1000](#)), `radto deg` ([1023](#)), `radto grad` ([1024](#)), `radtcycle` ([1023](#))

Listing: `./examples/mathex/ex12.pp`

Program Example12;

{ Program to demonstrate the degtorad function. }

Uses math;

begin
 writeln(degtorad(45));
 writeln(degtorad(90));
 writeln(degtorad(180));
 writeln(degtorad(270));
 writeln(degtorad(360));
end.

63.13.23 DivMod

Synopsis: Return DIV and MOD of arguments

Declaration: procedure DivMod(Dividend: LongInt; Divisor: Word; var Result: Word;
 var Remainder: Word)
 procedure DivMod(Dividend: LongInt; Divisor: Word;
 var Result: SmallInt; var Remainder: SmallInt)
 procedure DivMod(Dividend: DWord; Divisor: DWord; var Result: DWord;
 var Remainder: DWord)
 procedure DivMod(Dividend: LongInt; Divisor: LongInt;
 var Result: LongInt; var Remainder: LongInt)

Visibility: default

Description: DivMod returns Dividend DIV Divisor in Result, and Dividend MOD Divisor in Remainder

63.13.24 EnsureRange

Synopsis: Change value so it fits in a specified range.

Declaration: function EnsureRange(const AValue: Integer; const AMin: Integer;
 const AMax: Integer) : Integer; Overload
 function EnsureRange(const AValue: Int64; const AMin: Int64;
 const AMax: Int64) : Int64; Overload
 function EnsureRange(const AValue: Double; const AMin: Double;
 const AMax: Double) : Double; Overload

Visibility: default

Description: EnsureRange returns Value if AValue is in the range AMin..AMax. It returns AMin if the value is less than AMin, or AMax if the value is larger than AMax.

See also: InRange ([1006](#))

63.13.25 Floor

Synopsis: Return the largest integer smaller than or equal to argument

Declaration: function Floor(x: Float) : Integer

Visibility: default

Description: `Floor` returns the largest integer smaller than or equal to `x`. The absolute value of `x` should be less than `maxint`.

Errors: If `x` is larger than `maxint`, an overflow will occur.

See also: [ceil \(996\)](#)

Listing: ./examples/mathex/ex13.pp

Program Example13;

```
{ Program to demonstrate the floor function. }
```

Uses `math`;

begin

```
WriteIn(Floor(-3.7)); // should be -4
```

```
WriteIn(Floor(3.7)); // should be 3
```

```
WriteIn(Floor(-4.0)); // should be -4
```

end .

63.13.26 Floor64

Synopsis: Round to the nearest smaller int64 value

Declaration: `function Floor64(x: Float) : Int64`

Visibility: default

Description: `Floor64` rounds the value `X` to the nearest smaller `int64` value. The result is always smaller than `X`.

Errors: None.

See also: floor ([1001](#)), ceil64 ([996](#))

63.13.27 FMod

Synopsis: Floatin point modulo

```
Declaration: function FMod(const a: Single; const b: Single) : Single; Overload
            function FMod(const a: Double; const b: Double) : Double; Overload
            function FMod(const a: Extended; const b: Extended) : Extended
                ; Overload
```

Visibility: default

Description: FMod is the floating-point equivalent of the modulo operation $a \bmod b$. It returns the result of $a - b * \text{Int}(a/b)$

Errors: b may not be zero, but no check is performed.

63.13.28 Frexp

Synopsis: Return mantissa and exponent.

Declaration: `procedure Frexp(X: Float; var Mantissa: Float; var Exponent: Integer)`

Visibility: default

Description: `Frexp` returns the mantissa and exponent of its argument `x` in mantissa and exponent.

Errors: None

Listing: `./examples/mathex/ex14.pp`

Program Example14;

{ Program to demonstrate the frexp function. }

Uses math;

Procedure dofexp(**Const** X : extended);

var man : extended;
 exp: longint;

begin
 man:=0;
 exp:=0;
 frexp(x,man,**exp**);
 write(x,' has ');
 WriteLn('mantissa ',man,' and exponent ',**exp**);
end;

begin
 // dofexp(1.00);
 dofexp(1.02e-1);
 dofexp(1.03e-2);
 dofexp(1.02e1);
 dofexp(1.03e2);
end.

63.13.29 FutureValue

Synopsis: Calculate the future value of an investment.

Declaration: `function FutureValue(ARate: Float; NPeriods: Integer; APayment: Float;
 APresentValue: Float; APaymentTime: TPaymentTime)
 : Float`

Visibility: default

Description: `FutureValue` calculates the future value of an investment (FV) in the cash flow formula (see Cash-FlowFunctions (986)) The function result is the future value of an investment of `APresentValue` (PV), where `APayment` (PMT) is invested for `NPeriods` (n) at the rate of `ARate` (q) per period.

The `APaymentTime` parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: `ptEndOfPeriod` must be used if payments are at the end of each period. If the payments are at the beginning of the periode, `ptStartOfPeriod` must be used.

See also: [InterestRate \(1006\)](#), [NumberOfPeriods \(1019\)](#), [Payment \(1020\)](#), [PresentValue \(1023\)](#), [TPaymentTime \(991\)](#), [CashFlowFunctions \(986\)](#)

63.13.30 GetExceptionMask

Synopsis: Get the Floating Point Unit exception mask.

Declaration: `function GetExceptionMask : TFPUExceptionMask`

Visibility: default

Description: Get the Floating Point Unit exception mask.

63.13.31 GetPrecisionMode

Synopsis: Return the Floating Point Unit precision mode.

Declaration: `function GetPrecisionMode : TFPUPrecisionMode`

Visibility: default

Description: Return the Floating Point Unit precision mode.

63.13.32 GetRoundMode

Synopsis: Return the Floating Point Unit rounding mode.

Declaration: `function GetRoundMode : TFPURoundingMode`

Visibility: default

Description: Return the Floating Point Unit rounding mode.

63.13.33 GradToDeg

Synopsis: Convert grads angle to degrees angle

Declaration: `function GradToDeg(grad: Float) : Float`

Visibility: default

Description: `Gradtodeg` converts its argument `grad` (an angle in grads) to degrees. (100 grad is 90 degrees)

Errors: None.

See also: [cycletorad \(999\)](#), [degtograd \(1000\)](#), [radtodeg \(1023\)](#), [radtograd \(1024\)](#), [radtcycle \(1023\)](#), [gradtorad \(1005\)](#)

Listing: `./examples/mathex/ex15.pp`

Program `Example15;`

{ Program to demonstrate the gradtodeg function. }

Uses `math;`

begin

```

writeln (gradtodeg (100));
writeln (gradtodeg (200));
writeln (gradtodeg (300));
end.

```

63.13.34 GradToRad

Synopsis: Convert grads angle to radians angle

Declaration: `function GradToRad(grad: Float) : Float`

Visibility: default

Description: `Gradtorad` converts its argument `grad` (an angle in grads) to radians. (200 grad is pi degrees).

Errors: None.

See also: `cycletorad` ([999](#)), `degtograd` ([1000](#)), `radtodeg` ([1023](#)), `radtograd` ([1024](#)), `radtocycle` ([1023](#)), `gradtodeg` ([1004](#))

Listing: `./examples/mathex/ex16.pp`

Program `Example16;`

```

{ Program to demonstrate the gradtorad function. }

```

Uses `math;`

```

begin
  writeln (gradtorad (100));
  writeln (gradtorad (200));
  writeln (gradtorad (300));
end.

```

63.13.35 Hypot

Synopsis: Return hypotenuse of triangle

Declaration: `function Hypot(x: Float; y: Float) : Float`

Visibility: default

Description: `Hypot` returns the hypotenuse of the triangle where the sides adjacent to the square angle have lengths `x` and `y`. The function uses Pythagoras' rule for this.

Errors: None.

Listing: `./examples/mathex/ex17.pp`

Program `Example17;`

```

{ Program to demonstrate the hypot function. }

```

Uses `math;`

```

begin
  WriteLn (hypot (3,4)); // should be 5
end.

```

63.13.36 IfThen

Synopsis: Return one of two values, depending on a boolean condition

Declaration:

```
function IfThen(val: Boolean; const iftrue: Integer;
               const iffalse: Integer) : Integer; Overload
function IfThen(val: Boolean; const iftrue: Int64; const iffalse: Int64)
               : Int64; Overload
function IfThen(val: Boolean; const iftrue: Double;
               const iffalse: Double) : Double; Overload
```

Visibility: default

Description: `ifthen` returns `iftrue` if `val` is `True`, and `iffalse` if `val` is `False`.

This function can be used in expressions.

63.13.37 InRange

Synopsis: Check whether value is in range.

Declaration:

```
function InRange(const AValue: Integer; const AMin: Integer;
                const AMax: Integer) : Boolean; Overload
function InRange(const AValue: Int64; const AMin: Int64;
                const AMax: Int64) : Boolean; Overload
function InRange(const AValue: Double; const AMin: Double;
                const AMax: Double) : Boolean; Overload
```

Visibility: default

Description: `InRange` returns `True` if `AValue` is in the range `AMin..AMax`. It returns `False` if `Value` lies outside the specified range.

See also: `EnsureRange` ([1001](#))

63.13.38 InterestRate

Synopsis: Calculate the interest rate value of an investment

Declaration:

```
function InterestRate(NPeriods: Integer; APayment: Float;
                    APresentValue: Float; AFutureValue: Float;
                    APaymentTime: TPaymentTime) : Float
```

Visibility: default

Description: `InterestRate` calculates the future value of an investment (q) in the cash flow formula (see [CashFlowFunctions](#) ([986](#))). The function result is the interest rate value in case of a future value `AFutureValue` for an investment of a start value `APresentValue` (PV), where `APayment` (PMT) is invested for `NPeriods` (n).

The `APaymentTime` parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: `ptEndOfPeriod` must be used if payments are at the end of each period. If the payments are at the beginning of the periode, `ptStartOfPeriod` must be used.

See also: `FutureValue` ([1003](#)), `NumberOfPeriods` ([1019](#)), `Payment` ([1020](#)), `PresentValue` ([1023](#)), `TPaymentTime` ([991](#)), [CashFlowFunctions](#) ([986](#))

63.13.39 IntPower

Synopsis: Return integer power.

Declaration: `function IntPower(base: Float; const exponent: Integer) : Float`

Visibility: default

Description: `Intpower` returns `base` to the power `exponent`, where `exponent` is an integer value.

Errors: If `base` is zero and the `exponent` is negative, then an overflow error will occur.

See also: `power` ([1022](#))

Listing: `./examples/mathex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the intpower function. }

Uses `math;`

Procedure `DoIntpower (X : extended; Pow : Integer);`

begin

`writeln(X:8:4, '^', Pow:2, ' = ', intpower(X, pow):8:4);`
end;

begin

`dointpower(0.0,0);`
`dointpower(1.0,0);`
`dointpower(2.0,5);`
`dointpower(4.0,3);`
`dointpower(2.0,-1);`
`dointpower(2.0,-2);`
`dointpower(-2.0,4);`
`dointpower(-4.0,3);`

end.

63.13.40 IsInfinite

Synopsis: Check whether value is infinite

Declaration: `function IsInfinite(const d: Single) : Boolean; Overload`
`function IsInfinite(const d: Double) : Boolean; Overload`
`function IsInfinite(const d: Extended) : Boolean; Overload`

Visibility: default

Description: `IsInfinite` returns `True` if the double `d` contains the infinite value.

See also: `IsZero` ([1008](#)), `IsInfinite` ([1007](#))

63.13.41 IsNan

Synopsis: Check whether value is Not a Number


```
Declaration: function IsNan(const d: Single) : Boolean; Overload
            function IsNan(const d: Double) : Boolean; Overload
            function IsNan(const d: Extended) : Boolean; Overload
```

Visibility: default

Description: `IsNaN` returns `True` if the double `d` contains Not A Number (a value which cannot be represented correctly in double format).

See also: [IsZero \(1008\)](#), [IsInfinite \(1007\)](#)

63.13.42 IsZero

Synopsis: Check whether value is zero

```

Declaration: function IsZero(const A: Single; Epsilon: Single) : Boolean;   Overload
            function IsZero(const A: Single) : Boolean;   Overload
            function IsZero(const A: Double; Epsilon: Double) : Boolean;   Overload
            function IsZero(const A: Double) : Boolean;   Overload
            function IsZero(const A: Extended; Epsilon: Extended) : Boolean
                ;   Overload
            function IsZero(const A: Extended) : Boolean;   Overload

```

Visibility: default

Description: IsZero checks whether the float value A is zero, up to a precision of Epsilon. It returns True if Abs(A) is less than Epsilon.

The default value for `Epsilon` depends on the type of the argument: it is 1E-4 for `Single`, 1E-12 for `Double` and 1E-16 for extended.

See also: [IsNan \(1007\)](#), [IsInfinite \(1007\)](#), [SameValue \(1026\)](#)

63.13.43 Ldexp

Synopsis: Return (2 to the power p) times x

Declaration: function Ldexp(x: Float; const p: Integer) : Float

Visibility: default

Description: `Ldexp` returns (2 to the power `p`) times `x`.

Errors: None.

See also: [lnxp1 \(1009\)](#), [log10 \(1009\)](#), [log2 \(1010\)](#), [logn \(1010\)](#)

Listing: ./examples/mathex/ex19.pp

Program Example19;

```
{ Program to demonstrate the Idexp function. }
```

Uses `math`;

```
begin
  writeln(ldexp(2,4):8:4);
  writeln(ldexp(0.5,3):8:4);
end.
```

63.13.44 LnXP1

Synopsis: Return natural logarithm of 1+X

Declaration: `function LnXP1(x: Float) : Float`

Visibility: default

Description: `Lnxp1` returns the natural logarithm of 1+X. The result is more precise for small values of x. x should be larger than -1.

Errors: If $x \leq -1$ then an `EInvalidArgument` exception will be raised.

See also: `ldexp` ([1008](#)), `log10` ([1009](#)), `log2` ([1010](#)), `logn` ([1010](#))

Listing: `./examples/mathex/ex20.pp`

Program `Example20`;

{ Program to demonstrate the lnxp1 function. }

Uses `math`;

```
begin
  writeln(lnxp1(0));
  writeln(lnxp1(0.5));
  writeln(lnxp1(1));
end.
```

63.13.45 Log10

Synopsis: Return 10-Based logarithm.

Declaration: `function Log10(x: Float) : Float`

Visibility: default

Description: `Log10` returns the 10-base logarithm of X.

Errors: If x is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` ([1008](#)), `lnxp1` ([1009](#)), `log2` ([1010](#)), `logn` ([1010](#))

Listing: `./examples/mathex/ex21.pp`

Program `Example21`;

{ Program to demonstrate the log10 function. }

Uses `math`;

```
begin
  Writeln(Log10(10):8:4);
  Writeln(Log10(100):8:4);
  Writeln(Log10(1000):8:4);
  Writeln(Log10(1):8:4);
  Writeln(Log10(0.1):8:4);
  Writeln(Log10(0.01):8:4);
  Writeln(Log10(0.001):8:4);
end.
```

63.13.46 Log2

Synopsis: Return 2-based logarithm

Declaration: `function Log2(x: Float) : Float`

Visibility: default

Description: `Log2` returns the 2-base logarithm of `X`.

Errors: If `x` is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (1008), `lnxp1` (1009), `log10` (1009), `logn` (1010)

Listing: `./examples/mathex/ex22.pp`

Program `Example22`;

{ Program to demonstrate the log2 function. }

Uses `math`;

begin

```

  WriteLn(Log2(2):8:4);
  WriteLn(Log2(4):8:4);
  WriteLn(Log2(8):8:4);
  WriteLn(Log2(1):8:4);
  WriteLn(Log2(0.5):8:4);
  WriteLn(Log2(0.25):8:4);
  WriteLn(Log2(0.125):8:4);

```

end.

63.13.47 LogN

Synopsis: Return N-based logarithm.

Declaration: `function LogN(n: Float; x: Float) : Float`

Visibility: default

Description: `Logn` returns the n-base logarithm of `X`.

Errors: If `x` is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (1008), `lnxp1` (1009), `log10` (1009), `log2` (1010)

Listing: `./examples/mathex/ex23.pp`

Program `Example23`;

{ Program to demonstrate the logn function. }

Uses `math`;

begin

```

  WriteLn(Logn(3,4):8:4);
  WriteLn(Logn(2,4):8:4);
  WriteLn(Logn(6,9):8:4);
  WriteLn(Logn(exp(1),exp(1)):8:4);

```

```

Writeln(Logn(0.5,1):8:4);
Writeln(Logn(0.25,3):8:4);
Writeln(Logn(0.125,5):8:4);
end.

```

63.13.48 Max

Synopsis: Return largest of 2 values

Declaration: `function Max(a: Integer; b: Integer) : Integer; Overload`
`function Max(a: Int64; b: Int64) : Int64; Overload`
`function Max(a: QWord; b: QWord) : QWord; Overload`
`function Max(a: Single; b: Single) : Single; Overload`
`function Max(a: Double; b: Double) : Double; Overload`
`function Max(a: Extended; b: Extended) : Extended; Overload`

Visibility: default

Description: `Max` returns the maximum of `Int1` and `Int2`.

Errors: None.

See also: `min` ([1015](#)), `maxIntValue` ([1011](#)), `maxvalue` ([1012](#))

Listing: ./examples/mathex/ex24.pp

Program Example24;

{ Program to demonstrate the max function. }

Uses math;

Var

A,B : Cardinal;

begin

A:=1;b:=2;

writeln(max(a,b));

end.

63.13.49 MaxIntValue

Synopsis: Return largest element in integer array

Declaration: `function MaxIntValue(const Data: Array of Integer) : Integer`

Visibility: default

Description: `MaxIntValue` returns the largest integer out of the `Data` array.

This function is provided for Delphi compatibility, use the `maxvalue` ([1012](#)) function instead.

Errors: None.

See also: `maxvalue` ([1012](#)), `minvalue` ([1016](#)), `minIntValue` ([1015](#))

Listing: ./examples/mathex/ex25.pp

```

Program Example25;

{ Program to demonstrate the MaxIntValue function. }

{ Make sure integer is 32 bit }
{$mode objfpc}

Uses math;

Type
  TExArray = Array[1..100] of Integer;

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=low(exarray) to high(exarray) do
    ExArray[I]:=Random(I)-Random(100);
  WriteLn(MaxIntValue(ExArray));
end.

```

63.13.50 MaxValue

Synopsis: Return largest value in array

Declaration:

```

function MaxValue(const data: Array of Single) : Single
function MaxValue(const data: PSingle; const N: Integer) : Single
function MaxValue(const data: Array of Double) : Double
function MaxValue(const data: PDouble; const N: Integer) : Double
function MaxValue(const data: Array of Extended) : Extended
function MaxValue(const data: PExtended; const N: Integer) : Extended
function MaxValue(const data: Array of Integer) : Integer
function MaxValue(const data: PInteger; const N: Integer) : Integer

```

Visibility: default

Description: Maxvalue returns the largest value in the data array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of N integer or float values.

Errors: None.

See also: [maxIntValue \(1011\)](#), [minvalue \(1016\)](#), [minIntValue \(1015\)](#)

Listing: ./examples/mathex/ex26.pp

```

program Example26;

{ Program to demonstrate the MaxValue function. }

{ Make sure integer is 32 bit }
{$mode objfpc}

uses math;

```

```

var i:1..100;
    f_array:array[1..100] of Float;
    i_array:array[1..100] of Integer;
    Pf_array:Pfloat;
    Pi_array:Pinteger;

begin
    randomize;

    Pf_array:=@f_array[1];
    Pi_array:=@i_array[1];

    for i:=low(f_array) to high(f_array) do
        f_array[i]:=(random-random)*100;
    for i:=low(i_array) to high(i_array) do
        i_array[i]:=random(1)-random(100);

    Writeln('Max Float      : ',MaxValue(f_array):8:4);
    Writeln('Max Float   (b) : ',MaxValue(Pf_array,100):8:4);
    Writeln('Max Integer   : ',MaxValue(i_array):8);
    Writeln('Max Integer (b) : ',MaxValue(Pi_array,100):8);
end.

```

63.13.51 Mean

Synopsis: Return mean value of array

Declaration: function Mean(const data: Array of Single) : Float
function Mean(const data: PSingle; const N: LongInt) : Float
function Mean(const data: Array of Double) : Float
function Mean(const data: PDouble; const N: LongInt) : Float
function Mean(const data: Array of Extended) : Float
function Mean(const data: PExtended; const N: LongInt) : Float
function Mean(const data: PInt64; const N: LongInt) : Float
function Mean(const data: Array of Int64) : Float
function Mean(const data: PInteger; const N: LongInt) : Float
function Mean(const data: Array of Integer) : Float

Visibility: default

Description: Mean returns the average value of data. The second form accepts a pointer to an array of N values.

Errors: None.

See also: meanandstddev ([1014](#)), momentskewkurtosis ([1017](#)), sum ([1030](#))

Listing: ./examples/mathex/ex27.pp

Program Example27;

```

{ Program to demonstrate the Mean function. }
{ @ should return typed pointer }
{$T+}
Uses math;

```

Type

```

TExArray = Array[1..100] of Float;

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I]:=(Random-Random)*100;
  Writeln ( 'Max      : ',MaxValue(ExArray):8:4);
  Writeln ( 'Min      : ',MinValue(ExArray):8:4);
  Writeln ( 'Mean     : ',Mean(ExArray):8:4);
  Writeln ( 'Mean (b) : ',Mean(PExtended(@ExArray[1]),100):8:4);
end.

```

63.13.52 MeanAndStdDev

Synopsis: Return mean and standard deviation of array

Declaration: `procedure MeanAndStdDev(const data: Array of Single; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: PSingle; const N: LongInt; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: Array of Double; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: PDouble; const N: LongInt; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: Array of Extended; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: PExtended; const N: LongInt; var mean: Float; var stddev: Float)`

Visibility: default

Description: `meanandstddev` calculates the mean and standard deviation of data and returns the result in `mean` and `stddev`, respectively. `Stddev` is zero if there is only one value. The second form accepts a pointer to an array of N values.

Errors: None.

See also: `mean` ([1013](#)), `sum` ([1030](#)), `sumofsquares` ([1031](#)), `momentskewkurtosis` ([1017](#))

Listing: `./examples/mathex/ex28.pp`

Program Example28;

```

{ Program to demonstrate the Meanandstddev function. }
{ @ should return typed pointer }
{$T+}

```

Uses math;

Type

```
TExArray = Array[1..100] of Extended;
```

Var

```

I : Integer;
ExArray : TExArray;
Mean,stddev : Extended;

begin
  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I]:=(Random-Random)*100;
  MeanAndStdDev(ExArray,Mean,StdDev);
  Writeln('Mean      : ',Mean:8:4);
  Writeln('StdDev     : ',StdDev:8:4);
  MeanAndStdDev(@ExArray[1],100,Mean,StdDev);
  Writeln('Mean      (b) : ',Mean:8:4);
  Writeln('StdDev     (b) : ',StdDev:8:4);
end.

```

63.13.53 Min

Synopsis: Return smallest of two values.

Declaration: function Min(a: Integer; b: Integer) : Integer; Overload
 function Min(a: Int64; b: Int64) : Int64; Overload
 function Min(a: QWord; b: QWord) : QWord; Overload
 function Min(a: Single; b: Single) : Single; Overload
 function Min(a: Double; b: Double) : Double; Overload
 function Min(a: Extended; b: Extended) : Extended; Overload

Visibility: default

Description: min returns the smallest value of Int1 and Int2;

Errors: None.

See also: max ([1011](#))

Listing: ./examples/mathex/ex29.pp

Program Example29;

{ Program to demonstrate the min function. }

Uses math;

Var

A,B : Cardinal;

begin

A:=1;b:=2;

 writeln(min(a,b));

end.

63.13.54 MinIntValue

Synopsis: Return smallest value in integer array

Declaration: function MinIntValue(const Data: Array of Integer) : Integer

Visibility: default

Description: `MinIntValue` returns the smallest value in the `Data` array.

This function is provided for Delphi compatibility, use `minvalue` instead.

Errors: None

See also: `minvalue` (1016), `maxIntValue` (1011), `maxvalue` (1012)

Listing: `./examples/mathex/ex30.pp`

Program `Example30`;

{ Program to demonstrate the MinIntValue function. }

{ Make sure integer is 32 bit }

{ \$mode objfpc }

Uses `math`;

Type

`TExArray = Array[1..100] of Integer;`

Var

`I : Integer;`

`ExArray : TExArray;`

begin

`Randomize;`

`for I:=low(ExArray) to high(ExArray) do`

`ExArray[I]:=Random(I)-Random(100);`

`WriteLn(MinIntValue(ExArray));`

end.

63.13.55 MinValue

Synopsis: Return smallest value in array

Declaration:

```
function MinValue(const data: Array of Single) : Single
function MinValue(const data: PSingle; const N: Integer) : Single
function MinValue(const data: Array of Double) : Double
function MinValue(const data: PDouble; const N: Integer) : Double
function MinValue(const data: Array of Extended) : Extended
function MinValue(const data: PExtended; const N: Integer) : Extended
function MinValue(const data: Array of Integer) : Integer
function MinValue(const Data: PInteger; const N: Integer) : Integer
```

Visibility: default

Description: `Minvalue` returns the smallest value in the `data` array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of `N` integer or float values.

Errors: None.

See also: `maxIntValue` (1011), `maxvalue` (1012), `minIntValue` (1015)

Listing: ./examples/mathex/ex31.pp

```

program Example31;

  { Program to demonstrate the MinValue function. }

  { Make sure integer is 32 bit }
  {$mode objfpc}

  uses math;

  var i:1..100;
      f_array:array[1..100] of Float;
      i_array:array[1..100] of Integer;
      Pf_array:Pfloat;
      Pi_array:Pinteger;

  begin
    randomize;

    Pf_array:=@f_array[1];
    Pi_array:=@i_array[1];

    for i:=low(f_array) to high(f_array) do
      f_array[i]:=(random-random)*100;
    for i:=low(i_array) to high(i_array) do
      i_array[i]:=random(1)-random(100);

    Writeln( 'Min Float      : ',MinValue(f_array):8:4);
    Writeln( 'Min Float   (b) : ',MinValue(Pf_array,100):8:4);
    Writeln( 'Min Integer   : ',MinValue(i_array):8);
    Writeln( 'Min Integer (b) : ',MinValue(Pi_array,100):8);
  end.

```

63.13.56 modulus(Float,Float):Float

Synopsis: Floating point modulo

Declaration: `operator mod(const a: Float; const b: Float) : Float`

Visibility: default

Description: Modulus is the floating-point equivalent of the modulo operation `a mod b`. It returns the result of

`a-b * Int(a/b)`

Errors: `b` may not be zero, but no check is performed.

See also: [FMod \(1002\)](#)

63.13.57 MomentSkewKurtosis

Synopsis: Return 4 first moments of distribution

Declaration: `procedure MomentSkewKurtosis(const data: Array of Single;`
 `out m1: Float; out m2: Float;`
 `out m3: Float; out m4: Float;`

```

                                out skew: Float; out kurtosis: Float)
procedure MomentSkewKurtosis(const data: PSingle; const N: Integer;
                                out m1: Float; out m2: Float;
                                out m3: Float; out m4: Float;
                                out skew: Float; out kurtosis: Float)
procedure MomentSkewKurtosis(const data: Array of Double;
                                out m1: Float; out m2: Float;
                                out m3: Float; out m4: Float;
                                out skew: Float; out kurtosis: Float)
procedure MomentSkewKurtosis(const data: PDouble; const N: Integer;
                                out m1: Float; out m2: Float;
                                out m3: Float; out m4: Float;
                                out skew: Float; out kurtosis: Float)
procedure MomentSkewKurtosis(const data: Array of Extended;
                                out m1: Float; out m2: Float;
                                out m3: Float; out m4: Float;
                                out skew: Float; out kurtosis: Float)
procedure MomentSkewKurtosis(const data: PExtended; const N: Integer;
                                out m1: Float; out m2: Float;
                                out m3: Float; out m4: Float;
                                out skew: Float; out kurtosis: Float)

```

Visibility: default

Description: `momentskewkurtosis` calculates the 4 first moments of the distribution of value in data and returns them in `m1,m2,m3` and `m4`, as well as the skew and kurtosis.

Errors: None.

See also: `mean` ([1013](#)), `meanandstddev` ([1014](#))

Listing: `./examples/mathex/ex32.pp`

```

program Example32;

{ Program to demonstrate the momentskewkurtosis function. }

uses math;

var distarray: array[1..1000] of float;
    l: longint;
    m1,m2,m3,m4,skew,kurtosis: float;

begin
    randomize;
    for l:=low(distarray) to high(distarray) do
        distarray[l]:=random;
    momentskewkurtosis(DistArray,m1,m2,m3,m4,skew,kurtosis);

    Writeln ('1st moment : ',m1:8:6);
    Writeln ('2nd moment : ',m2:8:6);
    Writeln ('3rd moment : ',m3:8:6);
    Writeln ('4th moment : ',m4:8:6);
    Writeln ('Skew      : ',skew:8:6);
    Writeln ('kurtosis   : ',kurtosis:8:6);
end.

```

63.13.58 Norm

Synopsis: Return Euclidean norm

Declaration: `function Norm(const data: Array of Single) : Float`
`function Norm(const data: PSingle; const N: Integer) : Float`
`function Norm(const data: Array of Double) : Float`
`function Norm(const data: PDouble; const N: Integer) : Float`
`function Norm(const data: Array of Extended) : Float`
`function Norm(const data: PExtended; const N: Integer) : Float`

Visibility: default

Description: `Norm` calculates the Euclidean norm of the array of data. This equals `sqrt (sumofsquares (data))`.
 The second form accepts a pointer to an array of N values.

Errors: None.

See also: `sumofsquares` ([1031](#))

Listing: `./examples/mathex/ex33.pp`

```
program Example33;

{ Program to demonstrate the norm function. }

uses math;

var v:array[1..10] of Float;
    l:1..10;

begin
  for l:=low(v) to high(v) do
    v[l]:=random;
  writeln (norm(v));
end.
```

63.13.59 NumberOfPeriods

Synopsis: Calculate the number of periods for an investment

Declaration: `function NumberOfPeriods(ARate: Float; APayment: Float;`
`APresentValue: Float; AFutureValue: Float;`
`APaymentTime: TPaymentTime) : Float`

Visibility: default

Description: `NumberOfPeriods` calculates the number of periods (n) needed to obtain future value of an investment in the cash flow formula (see `CashFlowFunctions` ([986](#))). The function result is the number of periods a payment `APayment` (PMT) must be paid in order to obtain a future value `AFutureValue` for an investment of a start value `APresentValue` (PV), where `APayment` (PMT) is invested at a rate `ARate` (q).

The `APaymentTime` parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: `ptEndOfPeriod` `NumberOfPeriods` must be used if payments are at the end of each period. If the payments are at the beginning of the periode, `ptStartOfPeriod` must be used.

See also: `FutureValue` ([1003](#)), `InterestRate` ([1006](#)), `Payment` ([1020](#)), `PresentValue` ([1023](#)), `TPaymentTime` ([991](#)), `CashFlowFunctions` ([986](#))

63.13.60 Payment

Synopsis: Calculate the payment for an investment

Declaration: `function Payment (ARate: Float; NPeriods: Integer; APresentValue: Float;
AFutureValue: Float; APaymentTime: TPaymentTime) : Float`

Visibility: default

Description: `Payment` calculates the amount that must be paid (PMT) during number of periods (n) needed to obtain future value of an investment in the cash flow formula (see `CashFlowFunctions` (986)). The function result is the amount (PMT) that must be paid in order to obtain a future value `AFutureValue` for an investment of a start value `APresentValue` (PV), where the amount must be paid `NPeriods` (PMT) and the interest rate is `ARate` (q).

The `APaymentTime` parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: `ptEndOfPeriod` `NumberOfPeriods` must be used if payments are at the end of each period. If the payments are at the beginning of the periode, `ptStartOfPeriod` must be used.

See also: `FutureValue` (1003), `InterestRate` (1006), `NumberOfPeriods` (1019), `PresentValue` (1023), `TPaymentTime` (991), `CashFlowFunctions` (986)

63.13.61 PopnStdDev

Synopsis: Return Population standard deviation

Declaration: `function PopnStdDev(const data: Array of Single) : Float
function PopnStdDev(const data: PSingle; const N: Integer) : Float
function PopnStdDev(const data: Array of Double) : Float
function PopnStdDev(const data: PDouble; const N: Integer) : Float
function PopnStdDev(const data: Array of Extended) : Float
function PopnStdDev(const data: PExtended; const N: Integer) : Float`

Visibility: default

Description: `Popnstddev` returns the square root of the population variance of the values in the `Data` array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of N values.

Errors: None.

See also: `popnvariance` (1021), `mean` (1013), `meanandstddev` (1014), `stddev` (1029), `momentskewkurtosis` (1017)

Listing: `./examples/mathex/ex35.pp`

Program `Example35;`

```
{ Program to demonstrate the PopnStdDev function. }
{ @ should return typed pointer }
{$T+}
```

Uses `Math;`

Type

`TExArray = Array[1..100] of Float;`

```

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I]:=(Random-Random)*100;
  Writeln ( 'Max           : ',MaxValue(ExArray):8:4);
  Writeln ( 'Min           : ',MinValue(ExArray):8:4);
  Writeln ( 'Pop. stddev.   : ',PopnStdDev(ExArray):8:4);
  Writeln ( 'Pop. stddev. (b) : ',PopnStdDev(@ExArray[1],100):8:4);
end.

```

63.13.62 PopnVariance

Synopsis: Return population variance

Declaration: `function PopnVariance(const data: PSingle; const N: Integer) : Float`
`function PopnVariance(const data: Array of Single) : Float`
`function PopnVariance(const data: PDouble; const N: Integer) : Float`
`function PopnVariance(const data: Array of Double) : Float`
`function PopnVariance(const data: PExtended; const N: Integer) : Float`
`function PopnVariance(const data: Array of Extended) : Float`

Visibility: default

Description: `Popnvariance` the population variance of the values in the `Data` array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of `N` values.

Errors: None.

See also: `popnstddev` ([1020](#)), `mean` ([1013](#)), `meanandstddev` ([1014](#)), `stddev` ([1029](#)), `momentskewkurtosis` ([1017](#))

Listing: `./examples/mathex/ex36.pp`

Program Example36;

```

{ Program to demonstrate the PopnVariance function. }
{ @ should return typed pointer }
{$T+}

```

Uses math;

```

Var
  I : Integer;
  ExArray : Array[1..100] of Float;

```

```

begin
  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I]:=(Random-Random)*100;
  Writeln ( 'Max           : ',MaxValue(ExArray):8:4);
  Writeln ( 'Min           : ',MinValue(ExArray):8:4);
  Writeln ( 'Pop. var.      : ',PopnVariance(ExArray):8:4);
  Writeln ( 'Pop. var. (b) : ',PopnVariance(@ExArray[1],100):8:4);
end.

```

63.13.63 Power

Synopsis: Return real power.

Declaration: `function Power(base: Float; exponent: Float) : Float`

Visibility: default

Description: `power` raises `base` to the power `power`. This is equivalent to `exp (power*ln (base))`. Therefore `base` should be non-negative.

Errors: Any number of floating point math exceptions may be raised, if they are not masked by `SetExceptionMask` (1027).

See also: `intpower` (1007)

Listing: `./examples/mathex/ex34.pp`

Program `Example34;`

{ Program to demonstrate the power function. }

Uses `Math;`

procedure `dopower(x,y : float);`

begin

`writeln(x:8:6, '^', y:8:6, ' = ', power(x,y):8:6)`

end;

begin

`dopower(2,2);`

`dopower(2,-2);`

`dopower(2,0.0);`

end.

63.13.64 power(Float,Float):Float

Synopsis: Raise base to the power exponent

Declaration: `operator *(bas: Float; expo: Float) : Float`

Visibility: default

Description: `Power` raises `base` to the power `exponent`, i.e., it calculates $\text{base}^{\text{exponent}}$.

63.13.65 power(Int64,Int64):Int64

Synopsis: Raise base to the power exponent

Declaration: `operator *(bas: Int64; expo: Int64) : Int64`

Visibility: default

Description: `Power` raises `base` to the power `exponent`, i.e., it calculates $\text{base}^{\text{exponent}}$.

63.13.66 PresentValue

Synopsis: Calculate the present value given the future value of an investment.

Declaration: `function PresentValue (ARate: Float; NPeriods: Integer; APayment: Float;
AFutureValue: Float; APaymentTime: TPaymentTime)
: Float`

Visibility: default

Description: `PresentValue` calculates the present (start) value of an investment (PV) in the cash flow formula (see `CashFlowFunctions` (986)) The function result is the start value of an investment, when the future value is `AFutureValue` (FV) and `APayment` (PMT) is invested for `NPeriods` (n) at the rate of `ARate` (q) per period.

The `APaymentTime` parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: `ptEndOfPeriod` must be used if payments are at the end of each period. If the payments are at the beginning of the periode, `ptStartOfPeriod` must be used.

See also: `FutureValue` (1003), `InterestRate` (1006), `NumberOfPeriods` (1019), `Payment` (1020), `TPaymentTime` (991), `CashFlowFunctions` (986)

63.13.67 RadToCycle

Synopsis: Convert radians angle to cycle angle

Declaration: `function RadToCycle (rad: Float) : Float`

Visibility: default

Description: `RadtoCycle` converts its argument `rad` (an angle expressed in radians) to an angle in cycles.
(1 cycle equals 2 pi radians)

Errors: None.

See also: `degtograd` (1000), `degtorad` (1000), `radtodeg` (1023), `radtoegrad` (1024), `cycletorad` (999)

Listing: `./examples/mathex/ex37.pp`

Program `Example37;`

{ Program to demonstrate the radtoCycle function. }

Uses `math;`

begin

`writeln (radtoCycle (2*pi):8:6);`

`writeln (radtoCycle (pi):8:6);`

`writeln (radtoCycle (pi/2):8:6);`

end.

63.13.68 RadToDeg

Synopsis: Convert radians angle to degrees angle

Declaration: `function RadToDeg (rad: Float) : Float`

Visibility: default

Description: `Radtodeg` converts its argument `rad` (an angle expressed in radians) to an angle in degrees. (180 degrees equals pi radians)

Errors: None.

See also: `degtograd` ([1000](#)), `degtorad` ([1000](#)), `radto cycle` ([1023](#)), `radto grad` ([1024](#)), `cycleto rad` ([999](#))

Listing: `./examples/mathex/ex38.pp`

Program `Example38`;

{ Program to demonstrate the radtodeg function. }

Uses `math`;

begin

`writeln (radtodeg (2*pi):8:6);`

`writeln (radtodeg (pi):8:6);`

`writeln (radtodeg (pi/2):8:6);`

end.

63.13.69 RadToGrad

Synopsis: Convert radians angle to grads angle

Declaration: `function RadToGrad(rad: Float) : Float`

Visibility: `default`

Description: `Radtodeg` converts its argument `rad` (an angle expressed in radians) to an angle in grads. (200 grads equals pi radians)

Errors: None.

See also: `degtograd` ([1000](#)), `degtorad` ([1000](#)), `radto cycle` ([1023](#)), `radto deg` ([1023](#)), `cycleto rad` ([999](#))

Listing: `./examples/mathex/ex39.pp`

Program `Example39`;

{ Program to demonstrate the radto grad function. }

Uses `math`;

begin

`writeln (radto grad (2*pi):8:6);`

`writeln (radto grad (pi):8:6);`

`writeln (radto grad (pi/2):8:6);`

end.

63.13.70 RandG

Synopsis: Return gaussian distributed random number.

Declaration: `function RandG(mean: Float; stddev: Float) : Float`

Visibility: `default`

Description: `randg` returns a random number which - when produced in large quantities - has a Gaussian distribution with mean `mean` and standarddeviation `stddev`.

Errors: None.

See also: [mean \(1013\)](#), [stddev \(1029\)](#), [meanandstddev \(1014\)](#)

Listing: ./examples/mathex/ex40.pp

Program Example40 :

```
{ Program to demonstrate the randg function. }
```

Uses Math :

Var

```

I : Integer;
ExArray : Array[1..10000] of Float;
Mean, stddev : Float;

```

begin

```

Randomize;
for i:=low(ExArray) to high(ExArray) do
  ExArray[i]:=Randg(1,0.2);
MeanAndStdDev(ExArray,Mean,StdDev);
Writeln('Mean      : ',Mean:8:4);
Writeln('StdDev    : ',StdDev:8:4);

```

end.

63.13.71 RandomFrom

Synopsis: Return a random element of an array of numbers

```
Declaration: function RandomFrom(const AValues: Array of Double) : Double; Overload
              function RandomFrom(const AValues: Array of Integer) : Integer
                          ; Overload
              function RandomFrom(const AValues: Array of Int64) : Int64; Overload
```

Visibility: default

Description: RandomFrom returns a random element from the array AValues. The return value has the same type as the type of the array elements.

See also: `#rtl.system.Random` (1521), `RandomRange` (1025)

63.13.72 RandomRange

Synopsis: Return a random number in a range

```
Declaration: function RandomRange(const aFrom: Integer; const aTo: Integer) : Integer
            function RandomRange(const aFrom: Int64; const aTo: Int64) : Int64
```

Visibility: default

Description: RandomRange returns a random value in the range AFrom to ATo. AFrom and ATo do not need to be in increasing order. The upper border is not included in the generated value, but the lower border is.

See also: `#rtl.system.Random` (1521), `RandomFrom` (1025)

63.13.73 RoundTo

Synopsis: Round to the specified number of digits

Declaration:

```
function RoundTo(const AValue: Double; const Digits: TRoundToRange)
    : Double
function RoundTo(const AValue: Extended; const Digits: TRoundToRange)
    : Extended
function RoundTo(const AValue: Single; const Digits: TRoundToRange)
    : Single
```

Visibility: default

Description: RoundTo rounds the specified float AValue to the specified number of digits and returns the result. This result is accurate to "10 to the power Digits". It uses the standard Round function for this.

Errors: An exception may occur if the value AValue is not inside a valid integer (or Int64) range.

See also: TRoundToRange ([991](#)), SimpleRoundTo ([1028](#)), SetRoundMode ([1027](#)), TFPURoundingMode ([991](#))

63.13.74 SameValue

Synopsis: Check whether 2 float values are the same

Declaration:

```
function SameValue(const A: Extended; const B: Extended) : Boolean
    ; Overload
function SameValue(const A: Double; const B: Double) : Boolean
    ; Overload
function SameValue(const A: Single; const B: Single) : Boolean
    ; Overload
function SameValue(const A: Extended; const B: Extended;
    Epsilon: Extended) : Boolean; Overload
function SameValue(const A: Double; const B: Double; Epsilon: Double)
    : Boolean; Overload
function SameValue(const A: Single; const B: Single; Epsilon: Single)
    : Boolean; Overload
```

Visibility: default

Description: SameValue returns True if the floating-point values A and B are the same, i.e. whether the absolute value of their difference is smaller than Epsilon. If their difference is larger, then False is returned.

If unspecified, the default value for Epsilon is 0.0.

See also: MinFloat ([990](#)), IsZero ([1008](#))

63.13.75 Sec

Synopsis: Alias for secant

Declaration:

```
function Sec(x: Float) : Float
```

Visibility: default

Description: sec is an alias for the secant ([1027](#)) function.

See also: secant ([1027](#))

63.13.76 Secant

Synopsis: Calculate secant

Declaration: `function Secant (x: Float) : Float`

Visibility: default

Description: `Secant` calculates the secant ($1/\cos(x)$) of its argument `x`.

Errors: If 90 or 270 degrees is specified, an exception will be raised.

See also: cosecant ([997](#))

63.13.77 SetExceptionMask

Synopsis: Set the Floating Point Unit exception mask.

Declaration: `function SetExceptionMask(const Mask: TFPUExceptionMask)
: TFPUExceptionMask`

Visibility: default

Description: Set the Floating Point Unit exception mask.

63.13.78 SetPrecisionMode

Synopsis: Set the Floating Point Unit precision mode.

Declaration: `function SetPrecisionMode(const Precision: TFPUPrecisionMode)
: TFPUPrecisionMode`

Visibility: default

Description: Set the Floating Point Unit precision mode.

63.13.79 SetRoundMode

Synopsis: Set the Floating Point Unit rounding mode.

Declaration: `function SetRoundMode(const RoundMode: TFPURoundingMode)
: TFPURoundingMode`

Visibility: default

Description: `SetRoundMode` sets the floating point unit rounding mode. It also returns the previous rounding mode.

rmNearestRound to nearest integer

rmDownRound to biggest integer smaller than value.

rmUpRound to smallest integer larger than value

rmTruncate Cut off fractional part

See also: `GetRoundMode` ([1004](#)), `TFPURoundingMode` ([991](#))

63.13.80 Sign

Synopsis: Return sign of argument

Declaration: `function Sign(const AValue: Integer) : TValueSign; Overload`
`function Sign(const AValue: Int64) : TValueSign; Overload`
`function Sign(const AValue: Single) : TValueSign; Overload`
`function Sign(const AValue: Double) : TValueSign; Overload`
`function Sign(const AValue: Extended) : TValueSign; Overload`

Visibility: default

Description: `Sign` returns the sign of it's argument, which can be an Integer, 64 bit integer, or a double. The returned value is an integer which is -1, 0 or 1, and can be used to do further calculations with.

63.13.81 SimpleRoundTo

Synopsis: Round to the specified number of digits (rounding up if needed)

Declaration: `function SimpleRoundTo(const AValue: Single;`
`const Digits: TRoundToRange) : Single`
`function SimpleRoundTo(const AValue: Double;`
`const Digits: TRoundToRange) : Double`
`function SimpleRoundTo(const AValue: Extended;`
`const Digits: TRoundToRange) : Extended`

Visibility: default

Description: `SimpleRoundTo` rounds the specified float `AValue` to the specified number of digits using symmetric arithmetic rounding (rounding up for positive or down for negative) and returns the result. This result is accurate to "10 to the power `Digits`". It uses the standard `Round` function for this.

Errors: An exception may occur if the value `AValue` is not inside a valid integer (or `Int64`) range.

See also: `TRoundToRange` ([991](#)), `RoundTo` ([1026](#))

63.13.82 SinCos

Synopsis: Return sine and cosine of argument

Declaration: `procedure SinCos(theta: single; out sinus: single; out cosinus: single)`
`procedure SinCos(theta: Double; out sinus: Double; out cosinus: Double)`
`procedure SinCos(theta: extended; out sinus: extended;`
`out cosinus: extended)`

Visibility: default

Description: `SinCos` calculates the sine and cosine of the angle `theta`, and returns the result in `sinus` and `cosinus`.

On Intel hardware, This calculation will be faster than making 2 calls to calculate the sine and cosine separately.

Errors: None.

See also: `arcsin` ([993](#)), `arccos` ([992](#))

Listing: `./examples/mathex/ex41.pp`

```

Program Example41;

{ Program to demonstrate the sincos function. }

Uses math;

Procedure dosincos(Angle : Float);

Var
    Sine , Cosine : Float;

begin
    sincos (angle , sine , cosine );
    Write( 'Angle : ', Angle : 8:6);
    Write( ' Sine : ', sine : 8:6);
    Write( ' Cosine : ', cosine : 8:6);
end;

begin
    dosincos(pi);
    dosincos(pi/2);
    dosincos(pi/3);
    dosincos(pi/4);
    dosincos(pi/6);
end.

```

63.13.83 SinH

Synopsis: Return hyperbolic sine

Declaration: `function SinH(x: Float) : Float`

Visibility: default

Description: `Sinh` returns the hyperbolic sine of its argument `x`.

See also: `cosh` ([998](#)), `arsinh` ([995](#)), `tanh` ([1034](#)), `artanh` ([995](#))

Listing: `./examples/mathex/ex42.pp`

```

Program Example42;

{ Program to demonstrate the sinh function. }

Uses math;

begin
    writeln(sinh(0));
    writeln(sinh(1));
    writeln(sinh(-1));
end.

```

63.13.84 StdDev

Synopsis: Return standard deviation of data

Declaration: `function StdDev(const data: Array of Single) : Float`
`function StdDev(const data: PSingle; const N: Integer) : Float`
`function StdDev(const data: Array of Double) : Float`
`function StdDev(const data: PDouble; const N: Integer) : Float`
`function StdDev(const data: Array of Extended) : Float`
`function StdDev(const data: PExtended; const N: Integer) : Float`

Visibility: default

Description: Stddev returns the standard deviation of the values in Data. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: [mean \(1013\)](#), [meanandstddev \(1014\)](#), [variance \(1035\)](#), [totalvariance \(1034\)](#)

Listing: ./examples/mathex/ex43.pp

Program Example40;

```
{ Program to demonstrate the stddev function. }
{ @ should return typed pointer }
{$T+}
```

Uses Math;

Var

```
l : Integer;
ExArray : Array[1..10000] of Float;
```

begin

```
  Randomize;
```

```
  for l:=low(ExArray) to high(ExArray) do
```

```
    ExArray[l]:=Randg(1,0.2);
```

```
  WriteIn('StdDev      : ',StdDev(ExArray):8:4);
```

```
  WriteIn('StdDev (b) : ',StdDev(@ExArray[1],10000):8:4);
```

```
end.
```

63.13.85 Sum

Synopsis: Return sum of values

Declaration: `function Sum(const data: Array of Single) : Float`
`function Sum(const data: PSingle; const N: LongInt) : Float`
`function Sum(const data: Array of Double) : Float`
`function Sum(const data: PDouble; const N: LongInt) : Float`
`function Sum(const data: Array of Extended) : Float`
`function Sum(const data: PExtended; const N: LongInt) : Float`

Visibility: default

Description: Sum returns the sum of the values in the data array.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: `sumofsquares` ([1031](#)), `sumsandsquares` ([1032](#)), `totalvariance` ([1034](#)), `variance` ([1035](#))

Listing: `./examples/mathex/ex44.pp`

Program `Example44`;

```
{ Program to demonstrate the Sum function. }
{ @ should return typed pointer }
{$T+}
```

Uses `math`;

Var

```
l : 1..100;
ExArray : Array[1..100] of Float;
```

begin

Randomize;

```
for l:=low(ExArray) to high(ExArray) do
```

```
  ExArray[l]:=(Random-Random)*100;
```

```
  WriteIn ( 'Max      : ',MaxValue(ExArray):8:4);
```

```
  WriteIn ( 'Min      : ',MinValue(ExArray):8:4);
```

```
  WriteIn ( 'Sum      : ',Sum(ExArray):8:4);
```

```
  WriteIn ( 'Sum (b) : ',Sum(@ExArray[1],100):8:4);
```

end.

63.13.86 SumInt

Synopsis: Return the sum of an array of integers

Declaration:

```
function SumInt(const data: PInt64; const N: LongInt) : Int64
function SumInt(const data: Array of Int64) : Int64
function SumInt(const data: PInteger; const N: LongInt) : Int64
function SumInt(const data: Array of Integer) : Int64
```

Visibility: default

Description: `SumInt` returns the sum of the N integers in the Data array, where this can be an open array or a pointer to an array.

Errors: An overflow may occur.

63.13.87 SumOfSquares

Synopsis: Return sum of squares of values

Declaration:

```
function SumOfSquares(const data: Array of Single) : Float
function SumOfSquares(const data: PSingle; const N: Integer) : Float
function SumOfSquares(const data: Array of Double) : Float
function SumOfSquares(const data: PDouble; const N: Integer) : Float
function SumOfSquares(const data: Array of Extended) : Float
function SumOfSquares(const data: PExtended; const N: Integer) : Float
```

Visibility: default

Description: `sumofsquares` returns the sum of the squares of the values in the data array.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: [sum \(1030\)](#), [sumsandsquares \(1032\)](#), [totalvariance \(1034\)](#), [variance \(1035\)](#)

Listing: ./examples/mathex/ex45.pp

Program Example45;

```
{ Program to demonstrate the SumOfSquares function. }
{ @ should return typed pointer }
{$T+}
```

Uses math;

Var

```
  I : 1..100;
  ExArray : Array[1..100] of Float;
```

begin

```
  Randomize;
```

```
  for I:=low(ExArray) to high(ExArray) do
```

```
    ExArray[I]:= (Random-Random)*100;
```

```
  Writeln( 'Max           : ',MaxValue(ExArray):8:4);
```

```
  Writeln( 'Min           : ',MinValue(ExArray):8:4);
```

```
  Writeln( 'Sum squares    : ',SumOfSquares(ExArray):8:4);
```

```
  Writeln( 'Sum squares (b) : ',SumOfSquares(@ExArray[1],100):8:4);
```

```
end.
```

63.13.88 SumsAndSquares

Synopsis: Return sum and sum of squares of values.

Declaration:

```
procedure SumsAndSquares(const data: Array of Single; var sum: Float;
                        var sumofsquares: Float)
procedure SumsAndSquares(const data: PSingle; const N: Integer;
                        var sum: Float; var sumofsquares: Float)
procedure SumsAndSquares(const data: Array of Double; var sum: Float;
                        var sumofsquares: Float)
procedure SumsAndSquares(const data: PDouble; const N: Integer;
                        var sum: Float; var sumofsquares: Float)
procedure SumsAndSquares(const data: Array of Extended; var sum: Float;
                        var sumofsquares: Float)
procedure SumsAndSquares(const data: PExtended; const N: Integer;
                        var sum: Float; var sumofsquares: Float)
```

Visibility: default

Description: sumsandsquares calculates the sum of the values and the sum of the squares of the values in the data array and returns the results in sum and sumofsquares.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: [sum \(1030\)](#), [sumofsquares \(1031\)](#), [totalvariance \(1034\)](#), [variance \(1035\)](#)

Listing: ./examples/mathex/ex46.pp

Program Example45;

```
{ Program to demonstrate the SumOfSquares function. }
{ @ should return typed pointer }
{$T+}
```

Uses math;

Var

```
l : 1..100;
ExArray : Array[1..100] of Float;
s,ss : float;
```

begin

Randomize;

```
for l:=low(ExArray) to high(ExArray) do
```

```
  ExArray[l]:= (Random-Random)*100;
```

```
WriteIn ( 'Max           : ',MaxValue(ExArray):8:4);
```

```
WriteIn ( 'Min           : ',MinValue(ExArray):8:4);
```

```
SumsAndSquares(ExArray,S,SS);
```

```
WriteIn ( 'Sum           : ',S:8:4);
```

```
WriteIn ( 'Sum squares   : ',SS:8:4);
```

```
SumsAndSquares(@ExArray[1],100,S,SS);
```

```
WriteIn ( 'Sum (b)       : ',S:8:4);
```

```
WriteIn ( 'Sum squares (b) : ',SS:8:4);
```

end.

63.13.89 Tan

Synopsis: Return tangent

Declaration: `function Tan(x: Float) : Float`

Visibility: default

Description: Tan returns the tangent of x. The argument x must be in radians.

Errors: If x (normalized) is pi/2 or 3pi/2 then an overflow will occur.

See also: tanh ([1034](#)), arcsin ([993](#)), sincos ([1028](#)), arccos ([992](#))

Listing: ./examples/mathex/ex47.pp

Program Example47;

```
{ Program to demonstrate the Tan function. }
```

Uses math;

Procedure DoTan(Angle : Float);

begin

```
Write ( 'Angle : ',RadToDeg(Angle):8:6);
```

```
WriteIn ( 'Tangent : ',Tan(Angle):8:6);
```

end;

begin

```

DoTan(0);
DoTan(Pi);
DoTan(Pi/3);
DoTan(Pi/4);
DoTan(Pi/6);
end.

```

63.13.90 TanH

Synopsis: Return hyperbolic tangent

Declaration: `function TanH(x: Float) : Float`

Visibility: default

Description: Tanh returns the hyperbolic tangent of x.

Errors: None.

See also: [arcsin \(993\)](#), [sincos \(1028\)](#), [arccos \(992\)](#)

Listing: ./examples/mathex/ex48.pp

Program Example48;

{ Program to demonstrate the Tanh function. }

Uses math;

```

begin
  writeln(tanh(0));
  writeln(tanh(1));
  writeln(tanh(-1));
end.

```

63.13.91 TotalVariance

Synopsis: Return total variance of values

Declaration: `function TotalVariance(const data: Array of Single) : Float`
`function TotalVariance(const data: PSingle; const N: Integer) : Float`
`function TotalVariance(const data: Array of Double) : Float`
`function TotalVariance(const data: PDouble; const N: Integer) : Float`
`function TotalVariance(const data: Array of Extended) : Float`
`function TotalVariance(const data: PExtended; const N: Integer) : Float`

Visibility: default

Description: TotalVariance returns the total variance of the values in the data array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: [variance \(1035\)](#), [stddev \(1029\)](#), [mean \(1013\)](#)

Listing: ./examples/mathex/ex49.pp

Program Example49;

```
{ Program to demonstrate the TotalVariance function. }
{ @ should return typed pointer }
{$T+}
```

Uses math;

Type

TExArray = **Array**[1..100] of Float;

Var

I : Integer;
ExArray : TExArray;
TV : float;

begin

```
Randomize;
for I:=1 to 100 do
  ExArray[I]:=(Random-Random)*100;
TV:=TotalVariance(ExArray);
WriteLn('Total variance      : ',TV:8:4);
TV:=TotalVariance(@ExArray[1],100);
WriteLn('Total Variance (b) : ',TV:8:4);
```

end.

63.13.92 Variance

Synopsis: Return variance of values

Declaration:

```
function Variance(const data: Array of Single) : Float
function Variance(const data: PSingle; const N: Integer) : Float
function Variance(const data: Array of Double) : Float
function Variance(const data: PDouble; const N: Integer) : Float
function Variance(const data: Array of Extended) : Float
function Variance(const data: PExtended; const N: Integer) : Float
```

Visibility: default

Description: Variance returns the variance of the values in the data array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: totalvariance ([1034](#)), stddev ([1029](#)), mean ([1013](#))

Listing: ./examples/mathex/ex50.pp

Program Example50;

```
{ Program to demonstrate the Variance function. }
{ @ should return typed pointer }
{$T+}
```

Uses math;

Var

```

I : 1..100;
ExArray : Array[1..100] of Float;
V : float;

```

begin

```

  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I] := (Random-Random)*100;
  V:=Variance(ExArray);
  WriteLn( 'Variance      : ',V:8:4);
  V:=Variance(@ExArray[1],100);
  WriteLn( 'Variance (b) : ',V:8:4);

```

end.

Listing: ./examples/mathex/ex51.pp

Program Example51;

```

{
  Program to demonstrate the Variance function.
  It demonstrates the absence of large errors in the calculation.
}

```

Uses math;

const

```

  Size = 1000000;
```

var

```

dataS: array of Single;
dataD: array of Double;
dataE: array of Extended;
i,n: longint;

```

begin

```

  WriteLn( 'Each run should return a value near unity. ');
  WriteLn( 'Single: ');
  SetLength( dataS, Size );
  for n := 1 to 4 do
    begin
      for i := 0 to Size - 1 do
        begin
          dataS[i] := 10000000 + RandG(0,1);
        end;
      WriteLn( Math.Variance( dataS ):5:3 );
    end;

```

```

  WriteLn( 'Double: ');
  SetLength( dataD, Size );
  for n := 1 to 4 do
    begin
      for i := 0 to Size - 1 do
        begin
          dataD[i] := 10000000000000000 + RandG(0,1);
        end;
      WriteLn( Math.Variance( dataD ):5:3 );
    end;

```

```
end;  
  
WriteLn('Extended: ');  
SetLength( dataE, Size );  
for n := 1 to 4 do  
begin  
  for i := 0 to Size - 1 do  
  begin  
    dataE[i] := 1000000000000000000 + RandG(0,1);  
  end;  
  WriteLn( Math.Variance( dataE ):5:3 );  
end;  
end.
```

63.14 EInvalidArgument

63.14.1 Description

Exception raised when invalid arguments are passed to a function.

Chapter 64

Reference for unit 'matrix'

64.1 Used units

Table 64.1: Used units by unit 'matrix'

Name	Page
System	1339

64.2 Overview

The unit `matrix` is a unit that provides objects for the common two, three and four dimensional vectors matrices. These vectors and matrices are very common in computer graphics and are often implemented from scratch by programmers while every implementation provides exactly the same functionality.

It makes therefore sense to provide this functionality in the runtime library. This eliminates the need for programmers to reinvent the wheel and also allows libraries that use matrix operations to become more compatible.

The matrix unit does not provide n-dimensional matrices. The functionality needs of a general matrix unit varies from application to application; one can think of reduced memory usage tricks for matrices that only have data around the diagonal etc., desire for parallelization etc. etc. It is believed that programmers that do use n-dimensional matrices would not necessarily benefit from such a unit in the runtime library.

Design goals:

- Provide common dimensions, two three and four.
- Provide multiple floating point precisions, single, double, extended.
- Simple trivial binary representation; it is possible to typecast vectors into other implementations that use the same trivial representation.
- No dynamic memory management in the background. It must be possible to write expressions like `matrix A * B * C` without worrying about memory management.

Design decisions:

- Class object model is ruled out. The objects object model, without virtual methods, is suitable.
- Operator overloading is a good way to allow programmers to write matrix expressions.
- 3 dimensions * 3 precision means 9 vector and 9 matrix objects. Macro's have been used in the source to take care of this.

64.3 Constants, types and variables

64.3.1 Types

```
Tmatrix2_double_data = Array[0..1,0..1] of Double
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix2_extended_data = Array[0..1,0..1] of extended
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix2_single_data = Array[0..1,0..1] of single
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix3_double_data = Array[0..2,0..2] of Double
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix3_extended_data = Array[0..2,0..2] of extended
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix3_single_data = Array[0..2,0..2] of single
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.


```
Tmatrix4_double_data = Array[0..3,0..3] of Double
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_extended_data = Array[0..3,0..3] of extended
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_single_data = Array[0..3,0..3] of single
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_double_data = Array[0..1] of Double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_extended_data = Array[0..1] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_single_data = Array[0..1] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_double_data = Array[0..2] of Double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_extended_data = Array[0..2] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_single_data = Array[0..2] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_double_data = Array[0..3] of Double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_extended_data = Array[0..3] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_single_data = Array[0..3] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

64.4 Procedures and functions

64.4.1 add(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Add scalar to two-dimensional double precision matrix

Declaration: `operator +(const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.2 add(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double

Synopsis: Add two two-dimensional double precision matrices together.

Declaration: `operator +(const m1: Tmatrix2_double; const m2: Tmatrix2_double)
: Tmatrix2_double`

Visibility: default

Description: This operator allows you to add two two-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.3 add(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Add scalar to two-dimensional extended precision matrix

Declaration: `operator +(const m: Tmatrix2_extended; const x: extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.4 add(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended

Synopsis: Add two two-dimensional extended precision matrices together.

Declaration: `operator +(const m1: Tmatrix2_extended; const m2: Tmatrix2_extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to add two two-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.5 add(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Add scalar to two-dimensional single precision matrix

Declaration: `operator +(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.6 add(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single

Synopsis: Add two two-dimensional single precision matrices together.

Declaration: `operator +(const m1: Tmatrix2_single; const m2: Tmatrix2_single)
: Tmatrix2_single`

Visibility: default

Description: This operator allows you to add two two-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.7 add(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Add scalar to three-dimensional double precision matrix

Declaration: `operator +(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.8 add(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double

Synopsis: Add two three-dimensional double precision matrices together.

Declaration: `operator +(const m1: Tmatrix3_double; const m2: Tmatrix3_double)
: Tmatrix3_double`

Visibility: default

Description: This operator allows you to add two three-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.9 add(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Add scalar to three-dimensional extended precision matrix

Declaration: `operator +(const m: Tmatrix3_extended; const x: extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.10 add(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended

Synopsis: Add two three-dimensional extended precision matrices together.

Declaration: `operator +(const m1: Tmatrix3_extended; const m2: Tmatrix3_extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to add two three-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.11 add(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Add scalar to three-dimensional single precision matrix

Declaration: `operator +(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.12 add(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single

Synopsis: Add two three-dimensional single precision matrices together.

Declaration: `operator +(const m1: Tmatrix3_single; const m2: Tmatrix3_single)
: Tmatrix3_single`

Visibility: default

Description: This operator allows you to add two three-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.13 add(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Add scalar to four-dimensional double precision matrix

Declaration: `operator +(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.14 add(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double

Synopsis: Add two four-dimensional double precision matrices together.

Declaration: `operator +(const m1: Tmatrix4_double; const m2: Tmatrix4_double)
: Tmatrix4_double`

Visibility: default

Description: This operator allows you to add two four-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.15 add(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Add scalar to four-dimensional extended precision matrix

Declaration: `operator +(const m: Tmatrix4_extended; const x: extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.16 add(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended

Synopsis: Add two four-dimensional extended precision matrices together.

Declaration: `operator +(const m1: Tmatrix4_extended; const m2: Tmatrix4_extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to add two four-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.17 add(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Add scalar to four-dimensional single precision matrix

Declaration: `operator +(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.18 add(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single

Synopsis: Add two four-dimensional single precision matrices together.

Declaration: `operator +(const m1: Tmatrix4_single; const m2: Tmatrix4_single)
: Tmatrix4_single`

Visibility: default

Description: This operator allows you to add two four-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.19 add(Tvector2_double,Double):Tvector2_double

Synopsis: Add scalar to two-dimensional double precision vector

Declaration: `operator +(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.20 add(Tvector2_double,Tvector2_double):Tvector2_double

Synopsis: Add two-dimensional double precision vectors together

Declaration: `operator +(const x: Tvector2_double; const y: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.21 add(Tvector2_extended,extended):Tvector2_extended

Synopsis: Add scalar to two-dimensional extended precision vector

Declaration: `operator +(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.22 add(Tvector2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Add two-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector2_extended; const y: Tvector2_extended)
: Tvector2_extended`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.23 add(Tvector2_single,single):Tvector2_single

Synopsis: Add scalar to two-dimensional single precision vector

Declaration: `operator +(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.24 add(Tvector2_single,Tvector2_single):Tvector2_single

Synopsis: Add two-dimensional single precision vectors together

Declaration: `operator +(const x: Tvector2_single; const y: Tvector2_single)
: Tvector2_single`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.25 add(Tvector3_double,Double):Tvector3_double

Synopsis: Add scalar to three-dimensional double precision vector

Declaration: `operator +(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.26 add(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Add three-dimensional double precision vectors together

Declaration: `operator +(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.27 add(Tvector3_extended,extended):Tvector3_extended

Synopsis: Add scalar to three-dimensional extended precision vector

Declaration: `operator +(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.28 add(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Add three-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.29 add(Tvector3_single,single):Tvector3_single

Synopsis: Add scalar to three-dimensional single precision vector

Declaration: `operator +(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.30 add(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Add three-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.31 add(Tvector4_double,Double):Tvector4_double

Synopsis: Add scalar to four-dimensional double precision vector

Declaration: `operator +(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.32 add(Tvector4_double,Tvector4_double):Tvector4_double

Synopsis: Add four-dimensional double precision vectors together

Declaration: `operator +(const x: Tvector4_double; const y: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.33 add(Tvector4_extended,extended):Tvector4_extended

Synopsis: Add scalar to four-dimensional extended precision vector

Declaration: `operator +(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.34 add(Tvector4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Add four-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector4_extended; const y: Tvector4_extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.35 add(Tvector4_single,single):Tvector4_single

Synopsis: Add scalar to four-dimensional single precision vector

Declaration: `operator +(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.36 add(Tvector4_single,Tvector4_single):Tvector4_single

Synopsis: Add four-dimensional single precision vectors together

Declaration: `operator +(const x: Tvector4_single; const y: Tvector4_single) : Tvector4_single`

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.37 assign(Tmatrix2_double):Tmatrix2_extended

Synopsis: Allow assignment of two-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected.

64.4.38 assign(Tmatrix2_double):Tmatrix2_single

Synopsis: Allow assignment of two-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. Some accuracy is lost because of the conversion.

64.4.39 assign(Tmatrix2_double):Tmatrix3_double

Synopsis: Allow assignment of two-dimensional double precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.40 assign(Tmatrix2_double):Tmatrix3_extended

Synopsis: Allow assignment of two-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.41 assign(Tmatrix2_double):Tmatrix3_single

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.42 assign(Tmatrix2_double):Tmatrix4_double

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.43 **assign(Tmatrix2_double):Tmatrix4_extended**

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.44 **assign(Tmatrix2_double):Tmatrix4_single**

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0 and some precision is lost because of the conversion.

64.4.45 **assign(Tmatrix2_extended):Tmatrix2_double**

Synopsis: Allow assignment of two-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a two-dimensional two with extended precision values wherever a two-dimensional matrix with double precision is expected. Some accuracy is lost because of the conversion.

64.4.46 **assign(Tmatrix2_extended):Tmatrix2_single**

Synopsis: Allow assignment of two-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. Some accuracy is lost because of the conversion.

64.4.47 assign(Tmatrix2_extended):Tmatrix3_double

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.48 assign(Tmatrix2_extended):Tmatrix3_extended

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.49 assign(Tmatrix2_extended):Tmatrix3_single

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.50 assign(Tmatrix2_extended):Tmatrix4_double

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.51 assign(Tmatrix2_extended):Tmatrix4_extended

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0.

64.4.52 assign(Tmatrix2_extended):Tmatrix4_single

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0 and some precision is lost because of the conversion.

64.4.53 assign(Tmatrix2_single):Tmatrix2_double

Synopsis: Allow assignment of two-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected.

64.4.54 assign(Tmatrix2_single):Tmatrix2_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected.

64.4.55 assign(Tmatrix2_single):Tmatrix3_double

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.56 assign(Tmatrix2_single):Tmatrix3_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.57 assign(Tmatrix2_single):Tmatrix3_single

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0.

64.4.58 assign(Tmatrix2_single):Tmatrix4_double

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.59 assign(Tmatrix2_single):Tmatrix4_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.60 assign(Tmatrix2_single):Tmatrix4_single

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0.

64.4.61 assign(Tmatrix3_double):Tmatrix2_double

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.62 assign(Tmatrix3_double):Tmatrix2_extended

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.63 assign(Tmatrix3_double):Tmatrix2_single

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some accuracy is lost because of the conversion.

64.4.64 assign(Tmatrix3_double):Tmatrix3_extended

Synopsis: Allow assignment of three-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected.

64.4.65 assign(Tmatrix3_double):Tmatrix3_single

Synopsis: Allow assignment of three-dimensional double precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a three-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.66 **assign(Tmatrix3_double):Tmatrix4_double**

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with double precision is expected.

64.4.67 **assign(Tmatrix3_double):Tmatrix4_extended**

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.68 **assign(Tmatrix3_double):Tmatrix4_single**

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.69 **assign(Tmatrix3_extended):Tmatrix2_double**

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away and some accuracy is lost because of the conversion.

64.4.70 assign(Tmatrix3_extended):Tmatrix2_extended

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.71 assign(Tmatrix3_extended):Tmatrix2_single

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

64.4.72 assign(Tmatrix3_extended):Tmatrix3_double

Synopsis: Allow assignment of three-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. Some precision is lost because of the conversion.

64.4.73 assign(Tmatrix3_extended):Tmatrix3_single

Synopsis: Allow assignment of three-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.74 assign(Tmatrix3_extended):Tmatrix4_double

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected. Some precision is lost because of the conversion.

64.4.75 assign(Tmatrix3_extended):Tmatrix4_extended

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.76 assign(Tmatrix3_extended):Tmatrix4_single

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.77 assign(Tmatrix3_single):Tmatrix2_double

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.78 assign(Tmatrix3_single):Tmatrix2_extended

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.79 **assign(Tmatrix3_single):Tmatrix2_single**

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.80 **assign(Tmatrix3_single):Tmatrix3_double**

Synopsis: Allow assignment of three-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected.

64.4.81 **assign(Tmatrix3_single):Tmatrix3_extended**

Synopsis: Allow assignment of three-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected.

64.4.82 **assign(Tmatrix3_single):Tmatrix4_double**

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected.

64.4.83 assign(Tmatrix3_single):Tmatrix4_extended

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.84 assign(Tmatrix3_single):Tmatrix4_single

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected.

64.4.85 assign(Tmatrix4_double):Tmatrix2_double

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.86 assign(Tmatrix4_double):Tmatrix2_extended

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.87 assign(Tmatrix4_double):Tmatrix2_single

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

64.4.88 assign(Tmatrix4_double):Tmatrix3_double

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.89 assign(Tmatrix4_double):Tmatrix3_extended

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.90 assign(Tmatrix4_double):Tmatrix3_single

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

64.4.91 assign(Tmatrix4_double):Tmatrix4_extended

Synopsis: Allow assignment of four-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.92 assign(Tmatrix4_double):Tmatrix4_single

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.93 **assign(Tmatrix4_extended):Tmatrix2_double**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

64.4.94 **assign(Tmatrix4_extended):Tmatrix2_extended**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.95 **assign(Tmatrix4_extended):Tmatrix2_single**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

64.4.96 **assign(Tmatrix4_extended):Tmatrix3_double**

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.97 assign(Tmatrix4_extended):Tmatrix3_extended

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.98 assign(Tmatrix4_extended):Tmatrix3_single

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

64.4.99 assign(Tmatrix4_extended):Tmatrix4_double

Synopsis: Allow assignment of four-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected.

64.4.100 assign(Tmatrix4_extended):Tmatrix4_single

Synopsis: Allow assignment of four-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.101 assign(Tmatrix4_single):Tmatrix2_double

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.102 **assign(Tmatrix4_single):Tmatrix2_extended**

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.103 **assign(Tmatrix4_single):Tmatrix2_single**

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.104 **assign(Tmatrix4_single):Tmatrix3_double**

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.105 **assign(Tmatrix4_single):Tmatrix3_extended**

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.106 assign(Tmatrix4_single):Tmatrix3_single

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.107 assign(Tmatrix4_single):Tmatrix4_double

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected.

64.4.108 assign(Tmatrix4_single):Tmatrix4_extended

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.109 assign(Tvector2_double):Tvector2_extended

Synopsis: Allow assignment of double precision vector to extended precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever an extended precision vector is expected.

64.4.110 assign(Tvector2_double):Tvector2_single

Synopsis: Allow assignment of double precision vector to single precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever a single precision vector is expected, at the cost of loosing some precision.

64.4.111 assign(Tvector2_double):Tvector3_double

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

64.4.112 assign(Tvector2_double):Tvector3_extended

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

64.4.113 assign(Tvector2_double):Tvector3_single

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

64.4.114 assign(Tvector2_double):Tvector4_double

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

64.4.115 assign(Tvector2_double):Tvector4_extended

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

64.4.116 `assign(Tvector2_double):Tvector4_single`

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

64.4.117 `assign(Tvector2_extended):Tvector2_double`

Synopsis: Allow assignment of extended precision vector to double precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a double precision vector is expected, at the cost of loosing some precision.

64.4.118 `assign(Tvector2_extended):Tvector2_single`

Synopsis: Allow assignment of extended precision vector to single precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a single precision vector is expected, at the cost of loosing some precision.

64.4.119 `assign(Tvector2_extended):Tvector3_double`

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

64.4.120 assign(Tvector2_extended):Tvector3_extended

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

64.4.121 assign(Tvector2_extended):Tvector3_single

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

64.4.122 assign(Tvector2_extended):Tvector4_double

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

64.4.123 assign(Tvector2_extended):Tvector4_extended

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

64.4.124 assign(Tvector2_extended):Tvector4_single

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

64.4.125 assign(Tvector2_single):Tvector2_double

Synopsis: Allow assignment of single precision vector to double precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever a double precision vector is expected.

64.4.126 assign(Tvector2_single):Tvector2_extended

Synopsis: Allow assignment of single precision vector to extended precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever an extended precision vector is expected.

64.4.127 assign(Tvector2_single):Tvector3_double

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

64.4.128 assign(Tvector2_single):Tvector3_extended

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

64.4.129 assign(Tvector2_single):Tvector3_single

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The third dimension is set to 0.0.

64.4.130 assign(Tvector2_single):Tvector4_double

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

64.4.131 assign(Tvector2_single):Tvector4_extended

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

64.4.132 assign(Tvector2_single):Tvector4_single

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The third and fourth dimensions are set to 0.0.

64.4.133 assign(Tvector3_double):Tvector2_double

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

64.4.134 assign(Tvector3_double):Tvector2_extended

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

64.4.135 assign(Tvector3_double):Tvector2_single

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

64.4.136 assign(Tvector3_double):Tvector3_extended

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected.

64.4.137 assign(Tvector3_double):Tvector3_single

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some precision is lost because of the conversion.

64.4.138 **assign(Tvector3_double):Tvector4_double**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

64.4.139 **assign(Tvector3_double):Tvector4_extended**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

64.4.140 **assign(Tvector3_double):Tvector4_single**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some precision is lost because of the conversion.

64.4.141 **assign(Tvector3_extended):Tvector2_double**

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

64.4.142 assign(Tvector3_extended):Tvector2_extended

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

64.4.143 assign(Tvector3_extended):Tvector2_single

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

64.4.144 assign(Tvector3_extended):Tvector3_double

Synopsis: Allow assignment of three-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

64.4.145 assign(Tvector3_extended):Tvector3_single

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

64.4.146 assign(Tvector3_extended):Tvector4_double

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

64.4.147 assign(Tvector3_extended):Tvector4_extended

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

64.4.148 assign(Tvector3_extended):Tvector4_single

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

64.4.149 assign(Tvector3_single):Tvector2_double

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

64.4.150 assign(Tvector3_single):Tvector2_extended

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

64.4.151 **assign(Tvector3_single):Tvector2_single**

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away.

64.4.152 **assign(Tvector3_single):Tvector3_double**

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected.

64.4.153 **assign(Tvector3_single):Tvector3_extended**

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected.

64.4.154 **assign(Tvector3_single):Tvector4_double**

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

64.4.155 assign(Tvector3_single):Tvector4_extended

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

64.4.156 assign(Tvector3_single):Tvector4_single

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0.

64.4.157 assign(Tvector4_double):Tvector2_double

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

64.4.158 assign(Tvector4_double):Tvector2_extended

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

64.4.159 assign(Tvector4_double):Tvector2_single

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

64.4.160 **assign(Tvector4_double):Tvector3_double**

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

64.4.161 **assign(Tvector4_double):Tvector3_extended**

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

64.4.162 **assign(Tvector4_double):Tvector3_single**

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

64.4.163 **assign(Tvector4_double):Tvector4_extended**

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected.

64.4.164 assign(Tvector4_double):Tvector4_single

Synopsis: Allow assignment of four-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

64.4.165 assign(Tvector4_extended):Tvector2_double

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

64.4.166 assign(Tvector4_extended):Tvector2_extended

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

64.4.167 assign(Tvector4_extended):Tvector2_single

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

64.4.168 assign(Tvector4_extended):Tvector3_double

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

64.4.169 assign(Tvector4_extended):Tvector3_extended

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimensions are thrown away.

64.4.170 assign(Tvector4_extended):Tvector3_single

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

64.4.171 assign(Tvector4_extended):Tvector4_double

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion.

64.4.172 assign(Tvector4_extended):Tvector4_single

Synopsis: Allow assignment of four-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

64.4.173 assign(Tvector4_single):Tvector2_double

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

64.4.174 assign(Tvector4_single):Tvector2_extended

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

64.4.175 assign(Tvector4_single):Tvector2_single

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away.

64.4.176 assign(Tvector4_single):Tvector3_double

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

64.4.177 assign(Tvector4_single):Tvector3_extended

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

64.4.178 assign(Tvector4_single):Tvector3_single

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away.

64.4.179 assign(Tvector4_single):Tvector4_double

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected.

64.4.180 assign(Tvector4_single):Tvector4_extended

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected.

64.4.181 divide(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.182 divide(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix2_extended; const x: extended) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.183 divide(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.184 divide(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.185 divide(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix3_extended; const x: extended) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.186 divide(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.187 divide(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.188 divide(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix4_extended; const x: extended) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.189 divide(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.190 divide(Tvector2_double,Double):Tvector2_double

Synopsis: Divide a two-dimensional double precision vector by a scalar

Declaration: `operator /(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.191 divide(Tvector2_extended,extended):Tvector2_extended

Synopsis: Divide a two-dimensional extended precision vector by a scalar

Declaration: `operator /(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.192 divide(Tvector2_single,single):Tvector2_single

Synopsis: Divide a two-dimensional single precision vector by a scalar

Declaration: `operator /(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.193 divide(Tvector3_double,Double):Tvector3_double

Synopsis: Divide a three-dimensional double precision vector by a scalar

Declaration: `operator /(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.194 divide(Tvector3_extended,extended):Tvector3_extended

Synopsis: Divide a three-dimensional extended precision vector by a scalar

Declaration: `operator /(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.195 divide(Tvector3_single,single):Tvector3_single

Synopsis: Divide a three-dimensional single precision vector by a scalar

Declaration: `operator /(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.196 divide(Tvector4_double,Double):Tvector4_double

Synopsis: Divide a four-dimensional double precision vector by a scalar

Declaration: `operator /(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.197 divide(Tvector4_extended,extended):Tvector4_extended

Synopsis: Divide a four-dimensional extended precision vector by a scalar

Declaration: `operator /(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.198 divide(Tvector4_single,single):Tvector4_single

Synopsis: Divide a four-dimensional single precision vector by a scalar

Declaration: `operator /(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.199 multiply(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Multiply a two-dimensional double precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.200 multiply(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double

Synopsis: Give product of two two-dimensional double precision matrices

Declaration: `operator *(const m1: Tmatrix2_double; const m2: Tmatrix2_double)
: Tmatrix2_double`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.201 multiply(Tmatrix2_double,Tvector2_double):Tvector2_double

Synopsis: Give product of a two-dimensional double precision matrix and vector

Declaration: `operator *(const m: Tmatrix2_double; const v: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator allows you to multiply a two-dimensional double precision matrices with a two dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.202 multiply(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Multiply a two-dimensional extended precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix2_extended; const x: extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.203 multiply(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended

Synopsis: Give product of two two-dimensional extended precision matrices

Declaration: `operator *(const m1: Tmatrix2_extended; const m2: Tmatrix2_extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.204 multiply(Tmatrix2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Give product of a two-dimensional extended precision matrix and vector

Declaration: `operator *(const m: Tmatrix2_extended; const v: Tvector2_extended)
: Tvector2_extended`

Visibility: default

Description: This operator allows you to multiply a two-dimensional extended precision matrices with a two dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.205 multiply(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Multiply a two-dimensional single precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.206 multiply(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single

Synopsis: Give product of two two-dimensional single precision matrices

Declaration: `operator *(const m1: Tmatrix2_single; const m2: Tmatrix2_single)
: Tmatrix2_single`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.207 multiply(Tmatrix2_single,Tvector2_single):Tvector2_single

Synopsis: Give product of a two-dimensional single precision matrix and vector

Declaration: `operator *(const m: Tmatrix2_single; const v: Tvector2_single)
: Tvector2_single`

Visibility: default

Description: This operator allows you to multiply a two-dimensional single precision matrices with a two dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.208 multiply(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Multiply a three-dimensional double precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.209 multiply(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double

Synopsis: Give product of two three-dimensional double precision matrices

Declaration: `operator *(const m1: Tmatrix3_double; const m2: Tmatrix3_double)
: Tmatrix3_double`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.210 multiply(Tmatrix3_double,Tvector3_double):Tvector3_double

Synopsis: Give product of a three-dimensional double precision matrix and vector

Declaration: `operator *(const m: Tmatrix3_double; const v: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator allows you to multiply a three-dimensional double precision matrices with a three dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.211 multiply(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Multiply a three-dimensional extended precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix3_extended; const x: extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.212 multiply(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended

Synopsis: Give product of two three-dimensional extended precision matrices

Declaration: `operator *(const m1: Tmatrix3_extended; const m2: Tmatrix3_extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.213 multiply(Tmatrix3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Give product of a three-dimensional extended precision matrix and vector

Declaration: `operator *(const m: Tmatrix3_extended; const v: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator allows you to multiply a three-dimensional extended precision matrices with a three dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.214 multiply(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Multiply a three-dimensional single precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.215 multiply(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single

Synopsis: Give product of two three-dimensional single precision matrices

Declaration: `operator *(const m1: Tmatrix3_single; const m2: Tmatrix3_single)
: Tmatrix3_single`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.216 multiply(Tmatrix3_single,Tvector3_single):Tvector3_single

Synopsis: Give product of a three-dimensional single precision matrix and vector

Declaration: `operator *(const m: Tmatrix3_single; const v: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator allows you to multiply a three-dimensional single precision matrices with a three dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.217 multiply(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Multiply a four-dimensional double precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.218 multiply(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double

Synopsis: Give product of two four-dimensional double precision matrices

Declaration: `operator *(const m1: Tmatrix4_double; const m2: Tmatrix4_double)
: Tmatrix4_double`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.219 multiply(Tmatrix4_double,Tvector4_double):Tvector4_double

Synopsis: Give product of a four-dimensional double precision matrix and vector

Declaration: `operator *(const m: Tmatrix4_double; const v: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator allows you to multiply a four-dimensional double precision matrices with a four dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.220 multiply(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Multiply a four-dimensional extended precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix4_extended; const x: extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.221 multiply(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended

Synopsis: Give product of two four-dimensional extended precision matrices

Declaration: `operator *(const m1: Tmatrix4_extended; const m2: Tmatrix4_extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.222 multiply(Tmatrix4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Give product of a four-dimensional extended precision matrix and vector

Declaration: `operator *(const m: Tmatrix4_extended; const v: Tvector4_extended)
: Tvector4_extended`

Visibility: default

Description: This operator allows you to multiply a four-dimensional extended precision matrices with a four dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.223 multiply(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Multiply a four-dimensional single precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.224 multiply(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single

Synopsis: Give product of two four-dimensional single precision matrices

Declaration: `operator *(const m1: Tmatrix4_single; const m2: Tmatrix4_single)
: Tmatrix4_single`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.225 multiply(Tmatrix4_single,Tvector4_single):Tvector4_single

Synopsis: Give product of a four-dimensional single precision matrix and vector

Declaration: `operator *(const m: Tmatrix4_single; const v: Tvector4_single)
: Tvector4_single`

Visibility: default

Description: This operator allows you to multiply a four-dimensional single precision matrices with a four dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.226 multiply(Tvector2_double,Double):Tvector2_double

Synopsis: Multiply a two-dimensional double precision vector by a scalar

Declaration: `operator *(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.227 multiply(Tvector2_double,Tvector2_double):Tvector2_double

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector2_double; const y: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.228 multiply(Tvector2_extended,extended):Tvector2_extended

Synopsis: Multiply a two-dimensional extended precision vector by a scalar

Declaration: `operator *(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.229 multiply(Tvector2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector2_extended; const y: Tvector2_extended) : Tvector2_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.230 multiply(Tvector2_single,single):Tvector2_single

Synopsis: Multiply a two-dimensional single precision vector by a scalar

Declaration: `operator *(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.231 multiply(Tvector2_single,Tvector2_single):Tvector2_single

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector2_single; const y: Tvector2_single) : Tvector2_single`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.232 multiply(Tvector3_double,Double):Tvector3_double

Synopsis: Multiply a three-dimensional double precision vector by a scalar

Declaration: `operator *(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.233 multiply(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.234 multiply(Tvector3_extended,extended):Tvector3_extended

Synopsis: Multiply a three-dimensional extended precision vector by a scalar

Declaration: `operator *(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.235 multiply(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.236 multiply(Tvector3_single,single):Tvector3_single

Synopsis: Multiply a three-dimensional single precision vector by a scalar

Declaration: `operator *(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.237 multiply(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.238 multiply(Tvector4_double,Double):Tvector4_double

Synopsis: Multiply a four-dimensional double precision vector by a scalar

Declaration: `operator *(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.239 multiply(Tvector4_double,Tvector4_double):Tvector4_double

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector4_double; const y: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.240 multiply(Tvector4_extended,extended):Tvector4_extended

Synopsis: Multiply a four-dimensional extended precision vector by a scalar

Declaration: `operator *(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.241 multiply(Tvector4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector4_extended; const y: Tvector4_extended)
: Tvector4_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.242 multiply(Tvector4_single,single):Tvector4_single

Synopsis: Multiply a four-dimensional single precision vector by a scalar

Declaration: `operator *(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.243 multiply(Tvector4_single,Tvector4_single):Tvector4_single

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector4_single; const y: Tvector4_single)
: Tvector4_single`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.244 negative(Tmatrix2_double):Tmatrix2_double

Synopsis: Negate two-dimensional double precision matrix.

Declaration: `operator -(const m1: Tmatrix2_double) : Tmatrix2_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.245 negative(Tmatrix2_extended):Tmatrix2_extended

Synopsis: Negate two-dimensional extended precision matrix.

Declaration: `operator -(const m1: Tmatrix2_extended) : Tmatrix2_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.246 negative(Tmatrix2_single):Tmatrix2_single

Synopsis: Negate two-dimensional single precision matrix.

Declaration: `operator -(const m1: Tmatrix2_single) : Tmatrix2_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.247 negative(Tmatrix3_double):Tmatrix3_double

Synopsis: Negate three-dimensional double precision matrix.

Declaration: `operator -(const m1: Tmatrix3_double) : Tmatrix3_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.248 negative(Tmatrix3_extended):Tmatrix3_extended

Synopsis: Negate three-dimensional extended precision matrix.

Declaration: `operator -(const m1: Tmatrix3_extended) : Tmatrix3_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.249 negative(Tmatrix3_single):Tmatrix3_single

Synopsis: Negate three-dimensional single precision matrix.

Declaration: `operator -(const m1: Tmatrix3_single) : Tmatrix3_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.250 negative(Tmatrix4_double):Tmatrix4_double

Synopsis: Negate four-dimensional double precision matrix.

Declaration: `operator -(const m1: Tmatrix4_double) : Tmatrix4_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.251 negative(Tmatrix4_extended):Tmatrix4_extended

Synopsis: Negate four-dimensional extended precision matrix.

Declaration: `operator -(const m1: Tmatrix4_extended) : Tmatrix4_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.252 negative(Tmatrix4_single):Tmatrix4_single

Synopsis: Negate four-dimensional single precision matrix.

Declaration: `operator -(const m1: Tmatrix4_single) : Tmatrix4_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.253 negative(Tvector2_double):Tvector2_double

Synopsis: Negate two-dimensional vector.

Declaration: `operator -(const x: Tvector2_double) : Tvector2_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.254 negative(Tvector2_extended):Tvector2_extended

Synopsis: Negate two-dimensional vector.

Declaration: `operator -(const x: Tvector2_extended) : Tvector2_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.255 negative(Tvector2_single):Tvector2_single

Synopsis: Negate two-dimensional vector.

Declaration: `operator -(const x: Tvector2_single) : Tvector2_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.256 negative(Tvector3_double):Tvector3_double

Synopsis: Negate three-dimensional vector.

Declaration: `operator -(const x: Tvector3_double) : Tvector3_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.257 negative(Tvector3_extended):Tvector3_extended

Synopsis: Negate three-dimensional vector.

Declaration: `operator -(const x: Tvector3_extended) : Tvector3_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.258 negative(Tvector3_single):Tvector3_single

Synopsis: Negate three-dimensional vector.

Declaration: `operator -(const x: Tvector3_single) : Tvector3_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.259 negative(Tvector4_double):Tvector4_double

Synopsis: Negate four-dimensional vector.

Declaration: `operator -(const x: Tvector4_double) : Tvector4_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.260 negative(Tvector4_extended):Tvector4_extended

Synopsis: Negate four-dimensional vector.

Declaration: `operator -(const x: Tvector4_extended) : Tvector4_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.261 negative(Tvector4_single):Tvector4_single

Synopsis: Negate four-dimensional vector.

Declaration: `operator -(const x: Tvector4_single) : Tvector4_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.262 power(Tvector2_double,Tvector2_double):Double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector2_double; const y: Tvector2_double) : Double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.263 power(Tvector2_extended,Tvector2_extended):extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector2_extended; const y: Tvector2_extended)
: extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.264 power(Tvector2_single,Tvector2_single):single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector2_single; const y: Tvector2_single) : single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.265 power(Tvector3_double,Tvector3_double):Double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector3_double; const y: Tvector3_double) : Double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.266 power(Tvector3_extended,Tvector3_extended):extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector3_extended; const y: Tvector3_extended)
: extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.267 power(Tvector3_single,Tvector3_single):single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector3_single; const y: Tvector3_single) : single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.268 power(Tvector4_double,Tvector4_double):Double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector4_double; const y: Tvector4_double) : Double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.269 power(Tvector4_extended,Tvector4_extended):extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector4_extended; const y: Tvector4_extended)
: extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.270 power(Tvector4_single,Tvector4_single):single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector4_single; const y: Tvector4_single) : single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.271 subtract(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Subtract scalar to two-dimensional double precision matrix

Declaration: `operator - (const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.272 subtract(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double

Synopsis: Subtract a two-dimensional double precision matrix from another.

Declaration: `operator - (const m1: Tmatrix2_double; const m2: Tmatrix2_double)
: Tmatrix2_double`

Visibility: default

Description: This operator allows you to subtract a two-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.273 subtract(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Add scalar to two-dimensional extended precision matrix

Declaration: `operator - (const m: Tmatrix2_extended; const x: extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.274 subtract(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended

Synopsis: Subtract a two-dimensional extended precision matrix from another.

Declaration: `operator - (const m1: Tmatrix2_extended; const m2: Tmatrix2_extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to subtract a two-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.275 subtract(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Subtract scalar to two-dimensional single precision matrix

Declaration: `operator -(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.276 subtract(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single

Synopsis: Subtract a two-dimensional single precision matrix from another.

Declaration: `operator -(const m1: Tmatrix2_single; const m2: Tmatrix2_single)
: Tmatrix2_single`

Visibility: default

Description: This operator allows you to subtract a two-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.277 subtract(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Add scalar to three-dimensional double precision matrix

Declaration: `operator -(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.278 subtract(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double

Synopsis: Subtract a three-dimensional double precision matrix from another.

Declaration: `operator -(const m1: Tmatrix3_double; const m2: Tmatrix3_double)
: Tmatrix3_double`

Visibility: default

Description: This operator allows you to subtract a three-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.279 subtract(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Add scalar to three-dimensional extended precision matrix

Declaration: `operator -(const m: Tmatrix3_extended; const x: extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.280 subtract(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended

Synopsis: Subtract a three-dimensional extended precision matrix from another.

Declaration: `operator -(const m1: Tmatrix3_extended; const m2: Tmatrix3_extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to subtract a three-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.281 subtract(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Add scalar to three-dimensional single precision matrix

Declaration: `operator -(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.282 subtract(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single

Synopsis: Subtract a three-dimensional single precision matrix from another.

Declaration: `operator -(const m1: Tmatrix3_single; const m2: Tmatrix3_single)
: Tmatrix3_single`

Visibility: default

Description: This operator allows you to subtract a three-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.283 subtract(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Add scalar to four-dimensional double precision matrix

Declaration: `operator -(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.284 subtract(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double

Synopsis: Subtract a four-dimensional double precision matrix from another.

Declaration: `operator -(const m1: Tmatrix4_double; const m2: Tmatrix4_double)
: Tmatrix4_double`

Visibility: default

Description: This operator allows you to subtract a four-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.285 subtract(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Add scalar to four-dimensional extended precision matrix

Declaration: `operator -(const m: Tmatrix4_extended; const x: extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.286 subtract(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended

Synopsis: Subtract a four-dimensional extended precision matrix from another.

Declaration: `operator -(const m1: Tmatrix4_extended; const m2: Tmatrix4_extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to subtract a four-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.287 subtract(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Add scalar to four-dimensional single precision matrix

Declaration: `operator -(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.288 subtract(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single

Synopsis: Subtract a four-dimensional single precision matrix from another.

Declaration: `operator -(const m1: Tmatrix4_single; const m2: Tmatrix4_single)
: Tmatrix4_single`

Visibility: default

Description: This operator allows you to subtract a four-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.289 subtract(Tvector2_double,Double):Tvector2_double

Synopsis: Subtract scalar from two-dimensional double precision vector

Declaration: `operator -(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.290 subtract(Tvector2_double,Tvector2_double):Tvector2_double

Synopsis: Subtract two-dimensional double precision vectors from each other

Declaration: `operator -(const x: Tvector2_double; const y: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.291 subtract(Tvector2_extended,extended):Tvector2_extended

Synopsis: Subtract scalar from two-dimensional extended precision vector

Declaration: `operator -(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.292 subtract(Tvector2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Subtract two-dimensional extended precision vectors from each other

Declaration: `operator -(const x: Tvector2_extended; const y: Tvector2_extended)
: Tvector2_extended`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.293 subtract(Tvector2_single,single):Tvector2_single

Synopsis: Subtract scalar from two-dimensional single precision vector

Declaration: `operator -(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.294 subtract(Tvector2_single,Tvector2_single):Tvector2_single

Synopsis: Subtract two-dimensional single precision vectors from each other

Declaration: `operator -(const x: Tvector2_single; const y: Tvector2_single)
: Tvector2_single`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.295 subtract(Tvector3_double,Double):Tvector3_double

Synopsis: Subtract scalar from three-dimensional double precision vector

Declaration: `operator -(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.296 subtract(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Subtract three-dimensional double precision vectors from each other

Declaration: `operator -(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.297 subtract(Tvector3_extended,extended):Tvector3_extended

Synopsis: Subtract scalar from three-dimensional extended precision vector

Declaration: `operator -(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.298 subtract(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Subtract three-dimensional extended precision vectors from each other

Declaration: `operator -(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.299 subtract(Tvector3_single,single):Tvector3_single

Synopsis: Subtract scalar from three-dimensional single precision vector

Declaration: `operator -(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.300 subtract(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Subtract three-dimensional single precision vectors from each other

Declaration: `operator -(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.301 subtract(Tvector4_double,Double):Tvector4_double

Synopsis: Subtract scalar from four-dimensional double precision vector

Declaration: `operator -(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.302 subtract(Tvector4_double,Tvector4_double):Tvector4_double

Synopsis: Subtract four-dimensional double precision vectors from each other

Declaration: `operator -(const x: Tvector4_double; const y: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.303 subtract(Tvector4_extended,extended):Tvector4_extended

Synopsis: Subtract scalar from four-dimensional extended precision vector

Declaration: `operator -(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.304 subtract(Tvector4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Subtract four-dimensional extended precision vectors from each other

Declaration: `operator -(const x: Tvector4_extended; const y: Tvector4_extended)
: Tvector4_extended`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.305 subtract(Tvector4_single,single):Tvector4_single

Synopsis: Subtract scalar from four-dimensional single precision vector

Declaration: `operator -(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.306 subtract(Tvector4_single,Tvector4_single):Tvector4_single

Synopsis: Subtract four-dimensional single precision vectors from each other

Declaration: `operator -(const x: Tvector4_single; const y: Tvector4_single)
: Tvector4_single`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.307 symmetricaldifference(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator ><(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

64.4.308 symmetricaldifference(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator ><(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

64.4.309 symmetricaldifference(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator ><(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

64.5 Tmatrix2_double**64.5.1 Description**

The `Tmatrix2_double` object provides a matrix of 2*2 double precision scalars.

64.5.2 Method overview

Page	Method	Description
1108	<code>determinant</code>	Calculates the determinant of the matrix.
1108	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1108	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1108	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1107	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1107	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1109	<code>inverse</code>	Calculates the inverse of the matrix.
1108	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1108	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1109	<code>transpose</code>	Returns the transposition of the matrix.

64.5.3 Tmatrix2_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.5.4 Tmatrix2_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.5.5 Tmatrix2_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: Double; ab: Double; ba: Double; bb: Double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.5.6 Tmatrix2_double.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

64.5.7 Tmatrix2_double.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.5.8 Tmatrix2_double.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.5.9 Tmatrix2_double.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.5.10 Tmatrix2_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : Double`

Visibility: default

Description: Returns the determinant of the matrix.

64.5.11 Tmatrix2_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: Double) : Tmatrix2_double`

Visibility: default

Description: `Tmatrix2_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.5.12 Tmatrix2_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.6 Tmatrix2_extended

64.6.1 Description

The `Tmatrix2_extended` object provides a matrix of 2*2 extended precision scalars.

64.6.2 Method overview

Page	Method	Description
1111	<code>determinant</code>	Calculates the determinant of the matrix.
1110	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1110	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1110	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1110	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1109	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1111	<code>inverse</code>	Calculates the inverse of the matrix.
1110	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1110	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1111	<code>transpose</code>	Returns the transposition of the matrix.

64.6.3 Tmatrix2_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.6.4 Tmatrix2_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.6.5 Tmatrix2_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ba: extended; bb: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.6.6 Tmatrix2_extended.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.6.7 Tmatrix2_extended.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.6.8 Tmatrix2_extended.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.6.9 Tmatrix2_extended.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.6.10 Tmatrix2_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

64.6.11 Tmatrix2_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: extended) : Tmatrix2_extended`

Visibility: default

Description: `Tmatrix2_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.6.12 Tmatrix2_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.7 Tmatrix2_single

64.7.1 Description

The `Tmatrix2_single` object provides a matrix of 2*2 single precision scalars.

64.7.2 Method overview

Page	Method	Description
1113	<code>determinant</code>	Calculates the determinant of the matrix.
1112	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1112	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1112	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1112	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1112	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1113	<code>inverse</code>	Calculates the inverse of the matrix.
1112	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1113	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1113	<code>transpose</code>	Returns the transposition of the matrix.

64.7.3 Tmatrix2_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.7.4 Tmatrix2_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.7.5 Tmatrix2_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single; ab: single; ba: single; bb: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.7.6 Tmatrix2_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.7.7 Tmatrix2_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.7.8 Tmatrix2_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.7.9 Tmatrix2_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.7.10 Tmatrix2_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

64.7.11 Tmatrix2_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A: Tmatrix2_single) : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.7.12 Tmatrix2_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.8 Tmatrix3_double

64.8.1 Description

The `Tmatrix3_double` object provides a matrix of 3*3 double precision scalars.

64.8.2 Method overview

Page	Method	Description
1115	<code>determinant</code>	Calculates the determinant of the matrix.
1114	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1115	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1114	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1114	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1114	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1115	<code>inverse</code>	Calculates the inverse of the matrix.
1115	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1115	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1115	<code>transpose</code>	Returns the transposition of the matrix.

64.8.3 Tmatrix3_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.8.4 Tmatrix3_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.8.5 Tmatrix3_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: Double; ab: Double; ac: Double; ba: Double; bb: Double; bc: Double; ca: Double; cb: Double; cc: Double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.8.6 Tmatrix3_double.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.8.7 Tmatrix3_double.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.8.8 Tmatrix3_double.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.8.9 Tmatrix3_double.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.8.10 Tmatrix3_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : Double`

Visibility: default

Description: Returns the determinant of the matrix.

64.8.11 Tmatrix3_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A_determinant: Double) : Tmatrix3_double`

Visibility: default

Description: `Tmatrix3_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.8.12 Tmatrix3_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the *x* and *y* coordinates of the values swapped.

64.9 Tmatrix3_extended

64.9.1 Description

The `Tmatrix3_extended` object provides a matrix of 3*3 extended precision scalars.

64.9.2 Method overview

Page	Method	Description
1117	<code>determinant</code>	Calculates the determinant of the matrix.
1117	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1117	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1116	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1116	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1116	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1117	<code>inverse</code>	Calculates the inverse of the matrix.
1117	<code>set_column</code>	Sets r-th column of the matrix with a vector.
1117	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1118	<code>transpose</code>	Returns the transposition of the matrix.

64.9.3 Tmatrix3_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.9.4 Tmatrix3_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.9.5 Tmatrix3_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ac: extended;
ba: extended; bb: extended; bc: extended; ca: extended;
cb: extended; cc: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.9.6 Tmatrix3_extended.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

64.9.7 Tmatrix3_extended.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.9.8 Tmatrix3_extended.set_column

Synopsis: Sets *r*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.9.9 Tmatrix3_extended.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.9.10 Tmatrix3_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

64.9.11 Tmatrix3_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: extended) : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix3_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.9.12 Tmatrix3_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.10 Tmatrix3_single

64.10.1 Description

The `Tmatrix3_single` object provides a matrix of 3*3 single precision scalars.

64.10.2 Method overview

Page	Method	Description
1120	<code>determinant</code>	Calculates the determinant of the matrix.
1119	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1119	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1119	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1118	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1118	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1120	<code>inverse</code>	Calculates the inverse of the matrix.
1119	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1119	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1120	<code>transpose</code>	Returns the transposition of the matrix.

64.10.3 Tmatrix3_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.10.4 Tmatrix3_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.10.5 Tmatrix3_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single; ab: single; ac: single; ba: single;
bb: single; bc: single; ca: single; cb: single;
cc: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.10.6 Tmatrix3_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.10.7 Tmatrix3_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.10.8 Tmatrix3_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.10.9 Tmatrix3_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.10.10 Tmatrix3_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

64.10.11 Tmatrix3_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: single) : Tmatrix3_single`

Visibility: default

Description: `Tmatrix3_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.10.12 Tmatrix3_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.11 Tmatrix4_double**64.11.1 Description**

The `Tmatrix4_double` object provides a matrix of 4*4 double precision scalars.

64.11.2 Method overview

Page	Method	Description
1122	<code>determinant</code>	Calculates the determinant of the matrix.
1121	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1121	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1121	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1121	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1121	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1122	<code>inverse</code>	Calculates the inverse of the matrix.
1122	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1122	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1122	<code>transpose</code>	Returns the transposition of the matrix.

64.11.3 Tmatrix4_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.11.4 Tmatrix4_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.11.5 Tmatrix4_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: Double; ab: Double; ac: Double; ad: Double;
ba: Double; bb: Double; bc: Double; bd: Double;
ca: Double; cb: Double; cc: Double; cd: Double;
da: Double; db: Double; dc: Double; dd: Double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.11.6 Tmatrix4_double.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.11.7 Tmatrix4_double.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_double`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.11.8 Tmatrix4_double.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.11.9 Tmatrix4_double.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.11.10 Tmatrix4_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : Double`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

64.11.11 Tmatrix4_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: Double) : Tmatrix4_double`

Visibility: default

Description: Tmatrix4_double.inverse returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

64.11.12 Tmatrix4_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_double`

Visibility: default

Description: Tmatrix2_double.transpose returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.12 Tmatrix4_extended

64.12.1 Description

The `Tmatrix4_extended` object provides a matrix of 4*4 extended precision scalars.

64.12.2 Method overview

Page	Method	Description
1124	<code>determinant</code>	Calculates the determinant of the matrix.
1124	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1124	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1123	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1123	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1123	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1125	<code>inverse</code>	Calculates the inverse of the matrix.
1124	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1124	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1125	<code>transpose</code>	Returns the transposition of the matrix.

64.12.3 Tmatrix4_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.12.4 Tmatrix4_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.12.5 Tmatrix4_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ac: extended;
ad: extended; ba: extended; bb: extended; bc: extended;
bd: extended; ca: extended; cb: extended; cc: extended;
cd: extended; da: extended; db: extended; dc: extended;
dd: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.12.6 Tmatrix4_extended.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

64.12.7 Tmatrix4_extended.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.12.8 Tmatrix4_extended.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.12.9 Tmatrix4_extended.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.12.10 Tmatrix4_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

64.12.11 Tmatrix4_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: extended) : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix4_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

64.12.12 Tmatrix4_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.13 Tmatrix4_single

64.13.1 Description

The `Tmatrix4_single` object provides a matrix of 4*4 single precision scalars.

64.13.2 Method overview

Page	Method	Description
1127	<code>determinant</code>	Calculates the determinant of the matrix.
1126	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1126	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1126	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1126	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1125	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1127	<code>inverse</code>	Calculates the inverse of the matrix.
1126	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1127	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1127	<code>transpose</code>	Returns the transposition of the matrix.

64.13.3 Tmatrix4_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.13.4 Tmatrix4_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.13.5 Tmatrix4_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single; ab: single; ac: single; ad: single;
ba: single; bb: single; bc: single; bd: single;
ca: single; cb: single; cc: single; cd: single;
da: single; db: single; dc: single; dd: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.13.6 Tmatrix4_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.13.7 Tmatrix4_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.13.8 Tmatrix4_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.13.9 Tmatrix4_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.13.10 Tmatrix4_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

64.13.11 Tmatrix4_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: single) : Tmatrix4_single`

Visibility: default

Description: `Tmatrix4_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

64.13.12 Tmatrix4_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.14 Tvector2_double**64.14.1 Description**

The `Tvector2_double` object provides a vector of two double precision scalars.

64.14.2 Method overview

Page	Method	Description
1128	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1128	<code>init_one</code>	Initializes the vector and sets its elements to one
1128	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1128	<code>length</code>	Calculates the length of the vector.
1128	<code>squared_length</code>	Calculates the squared length of the vector.

64.14.3 Tvector2_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.14.4 Tvector2_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.14.5 Tvector2_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: Double; b: Double)`

Visibility: default

64.14.6 Tvector2_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function &length : Double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([1128](#)) if you are able to, as it is faster.

64.14.7 Tvector2_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : Double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

64.15 Tvector2_extended

64.15.1 Description

The `Tvector2_extended` object provides a vector of two extended precision scalars.

64.15.2 Method overview

Page	Method	Description
1129	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1129	<code>init_one</code>	Initializes the vector and sets its elements to one
1129	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1129	<code>length</code>	Calculates the length of the vector.
1130	<code>squared_length</code>	Calculates the squared length of the vector.

64.15.3 Tvector2_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.15.4 Tvector2_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.15.5 Tvector2_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended; b: extended)`

Visibility: default

64.15.6 Tvector2_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function &length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([1130](#)) if you are able to, as it is faster.

64.15.7 Tvector2_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

64.16 Tvector2_single

64.16.1 Description

The `Tvector2_single` object provides a vector of two single precision scalars.

64.16.2 Method overview

Page	Method	Description
1130	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1130	<code>init_one</code>	Initializes the vector and sets its elements to one
1130	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1131	<code>length</code>	Calculates the length of the vector.
1131	<code>squared_length</code>	Calculates the squared length of the vector.

64.16.3 Tvector2_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.16.4 Tvector2_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.16.5 Tvector2_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single; b: single)`

Visibility: default

64.16.6 Tvector2_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function &length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` (1131) if you are able to, as it is faster.

64.16.7 Tvector2_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

64.17 Tvector3_double

64.17.1 Description

The `Tvector3_double` object provides a vector of three double precision scalars.

64.17.2 Method overview

Page	Method	Description
1132	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1131	<code>init_one</code>	Initializes the vector and sets its elements to one
1131	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1132	<code>length</code>	Calculates the length of the vector.
1132	<code>squared_length</code>	Calculates the squared length of the vector.

64.17.3 Tvector3_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.17.4 Tvector3_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.17.5 Tvector3_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: Double; b: Double; c: Double)`

Visibility: default

64.17.6 Tvector3_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function &length : Double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` ([1132](#)) if you are able to, as it is faster.

64.17.7 Tvector3_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : Double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

64.18 Tvector3_extended

64.18.1 Description

The `Tvector3_extended` object provides a vector of three extended precision scalars.

64.18.2 Method overview

Page	Method	Description
1133	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1133	<code>init_one</code>	Initializes the vector and sets its elements to one
1132	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1133	<code>length</code>	Calculates the length of the vector.
1133	<code>squared_length</code>	Calculates the squared length of the vector.

64.18.3 Tvector3_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.18.4 Tvector3_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.18.5 Tvector3_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended; b: extended; c: extended)`

Visibility: default

64.18.6 Tvector3_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function &length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` (1133) if you are able to, as it is faster.

64.18.7 Tvector3_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

64.19 Tvector3_single

64.19.1 Description

The `Tvector3_single` object provides a vector of three single precision scalars.

64.19.2 Method overview

Page	Method	Description
1134	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1134	<code>init_one</code>	Initializes the vector and sets its elements to one
1134	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1134	<code>length</code>	Calculates the length of the vector.
1134	<code>squared_length</code>	Calculates the squared length of the vector.

64.19.3 Tvector3_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.19.4 Tvector3_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.19.5 Tvector3_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single; b: single; c: single)`

Visibility: default

64.19.6 Tvector3_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function &length : single`

Visibility: default

Description: Calculate the length of the vector: $\text{length} = \sqrt{\text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2}$. Try to use `squared_length` ([1134](#)) if you are able to, as it is faster.

64.19.7 Tvector3_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: $\text{squared_length} = \text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2$.

64.20 Tvector4_double**64.20.1 Description**

The `Tvector4_double` object provides a vector of four double precision scalars.

64.20.2 Method overview

Page	Method	Description
1135	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1135	<code>init_one</code>	Initializes the vector and sets its elements to one
1135	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1135	<code>length</code>	Calculates the length of the vector.
1135	<code>squared_length</code>	Calculates the squared length of the vector.

64.20.3 Tvector4_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.20.4 Tvector4_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.20.5 Tvector4_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: Double; b: Double; c: Double; d: Double)`

Visibility: default

64.20.6 Tvector4_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function &length : Double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([1135](#)) if you are able to, as it is faster.

64.20.7 Tvector4_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : Double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

64.21 Tvector4_extended

64.21.1 Description

The `Tvector4_extended` object provides a vector of four extended precision scalars.

64.21.2 Method overview

Page	Method	Description
1136	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1136	<code>init_one</code>	Initializes the vector and sets its elements to one
1136	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1136	<code>length</code>	Calculates the length of the vector.
1137	<code>squared_length</code>	Calculates the squared length of the vector.

64.21.3 Tvector4_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.21.4 Tvector4_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.21.5 Tvector4_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended; b: extended; c: extended; d: extended)`

Visibility: default

64.21.6 Tvector4_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function &length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([1137](#)) if you are able to, as it is faster.

64.21.7 Tvector4_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

64.22 Tvector4_single

64.22.1 Description

The `Tvector4_single` object provides a vector of four single precision scalars.

64.22.2 Method overview

Page	Method	Description
1137	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1137	<code>init_one</code>	Initializes the vector and sets its elements to one
1137	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1138	<code>length</code>	Calculates the length of the vector.
1138	<code>squared_length</code>	Calculates the squared length of the vector.

64.22.3 Tvector4_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.22.4 Tvector4_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.22.5 Tvector4_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single; b: single; c: single; d: single)`

Visibility: default

64.22.6 Tvector4_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function &length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([1138](#)) if you are able to, as it is faster.

64.22.7 Tvector4_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

Chapter 65

Reference for unit 'mmx'

65.1 Used units

Table 65.1: Used units by unit 'mmx'

Name	Page
System	1339

65.2 Overview

This document describes the MMX unit. This unit allows you to use the MMX capabilities of the Free Pascal compiler. It was written by Florian Klaempfl for the I386 processor. It should work on all platforms that use the Intel processor.

65.3 Constants, types and variables

65.3.1 Constants

```
is_amd_3d_cpu : Boolean = False
```

The `is_amd_3d_cpu` initialized constant allows you to determine if the computer has the AMD 3D extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_dsp_cpu : Boolean = False
```

The `is_amd_3d_dsp_cpu` initialized constant allows you to determine if the computer has the AMD 3D DSP extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_mmx_cpu : Boolean = False
```

The `is_amd_3d_mmx_cpu` initialized constant allows you to determine if the computer has the AMD 3D MMX extensions. It is set correctly in the unit's initialization code.

```
is_mmx_cpu : Boolean = False
```

The `is_mmx_cpu` initialized constant allows you to determine if the computer has MMX extensions. It is set correctly in the unit's initialization code.

```
is_sse2_cpu : Boolean = False
```

The `is_sse2_cpu` initialized constant allows you to determine if the computer has the SSE2 extensions. It is set correctly in the unit's initialization code.

```
is_sse_cpu : Boolean = False
```

The `is_sse_cpu` initialized constant allows you to determine if the computer has the SSE extensions. It is set correctly in the unit's initialization code.

65.3.2 Types

```
pmmxbyte = ^tmmxbyte
```

Pointer to `tmmxbyte` (1140) array type

```
pmmxcardinal = ^tmmxcardinal
```

Pointer to `tmmxcardinal` (1140) array type

```
pmmxinteger = ^tmmxinteger
```

Pointer to `tmmxinteger` (1141) array type

```
pmmxlongint = ^tmmxlongint
```

Pointer to `tmmxlongint` (1141) array type

```
pmmxshortint = ^tmmxshortint
```

Pointer to `tmmxshortint` (1141) array type

```
pmmxsingle = ^tmmxsingle
```

Pointer to `tmmxsingle` (1141) array type

```
pmmxword = ^tmmxword
```

Pointer to `tmmxword` (1141) array type

```
tmmxbyte = Array[0..7] of Byte
```

Array of bytes, 64 bits in size

```
tmmxcardinal = Array[0..1] of Cardinal
```

Array of cardinals, 64 bits in size

```
tmmxinteger = Array[0..3] of Integer
```

Array of integers, 64 bits in size

```
tmmxlongint = Array[0..1] of LongInt
```

Array of longint, 64 bits in size

```
tmmxshortint = Array[0..7] of ShortInt
```

Array of shortints, 64 bits in size

```
tmmxsingle = Array[0..1] of single
```

Array of singles, 64 bits in size

```
tmmxword = Array[0..3] of Word
```

Array of words, 64 bits in size

65.4 Procedures and functions

65.4.1 emms

Synopsis: Reset floating point registers

Declaration: `procedure emms`

Visibility: `default`

Description: `Emms` sets all floating point registers to empty. This procedure must be called after you have used any MMX instructions, if you want to use floating point arithmetic. If you just want to move floating point data around, it isn't necessary to call this function, the compiler doesn't use the FPU registers when moving data. Only when doing calculations, you should use this function. The following code demonstrates this:

```
Program MMXDemo;
uses mmx;
var
  d : double;
  a : array[0..10000] of double;
  i : longint;
begin
  d:=1.0;
{$mmx+}
  { floating point data is used, but we do _no_ arithmetic }
  for i:=0 to 10000 do
    a[i]:=d; { this is done with 64 bit moves }
{$mmx-}
  emms; { clear fpu }
  { now we can do floating point arithmetic again }
end.
```

See also: `femms` ([1142](#))

65.4.2 femms

Synopsis: Reset floating point registers - AMD version

Declaration: `procedure femms`

Visibility: `default`

Description: `femms` executes the `femms` assembler instruction for AMD processors. it is not supported by all assemblers, hence it is coded as byte codes.

See also: `emms` ([1141](#))

Chapter 66

Reference for unit 'Mouse'

66.1 Used units

Table 66.1: Used units by unit 'Mouse'

Name	Page
System	1339

66.2 Overview

The `Mouse` unit implements a platform independent mouse handling interface. It is implemented identically on all platforms supported by Free Pascal and can be enhanced with custom drivers, should this be needed. It is intended to be used only in text-based screens, for instance in conjunction with the keyboard and video unit. No support for graphical screens is implemented, and there are (currently) no plans to implement this.

66.3 Writing a custom mouse driver

The `mouse` unit has support for adding a custom mouse driver. This can be used to add support for mice not supported by the standard Free Pascal driver, but also to enhance an existing driver for instance to log mouse events or to implement a record and playback function.

The following unit shows how a mouse driver can be enhanced by adding some logging capabilities to the driver.

Listing: `./examples/mouseex/logmouse.pp`

```
unit logmouse ;
```

```
interface
```

```
Procedure StartMouseLogging ;
```

```
Procedure StopMouseLogging ;
```

```
Function IsMouseLogging : Boolean ;
```

```
Procedure SetMouseLogFileName ( FileName : String ) ;
```


implementation

```
uses sysutils ,Mouse;
```

var

```
  NewMouseDriver ,
  OldMouseDriver : TMouseDriver;
  Active ,Logging : Boolean;
  LogFileName : String;
  MouseLog : Text;
```

```
Function TimeStamp : String;
```

begin

```
  TimeStamp:=FormatDateTime( 'hh:nn:ss ',Time());
end;
```

```
Procedure StartMouseLogging;
```

begin

```
  Logging:=True;
  WriteLn(MouseLog,'Start logging mouse events at: ',TimeStamp);
end;
```

```
Procedure StopMouseLogging;
```

begin

```
  WriteLn(MouseLog,'Stop logging mouse events at: ',TimeStamp);
  Logging:=False;
end;
```

```
Function IsMouseLogging : Boolean;
```

begin

```
  IsMouseLogging:=Logging;
end;
```

```
Procedure LogGetMouseEvent(Var Event : TMouseEvent);
```

Var

```
  M : TMouseEvent;
```

begin

```
  OldMouseDriver.GetMouseEvent(M);
  If Logging then
  begin
    Write(MouseLog,TimeStamp,': Mouse ');
    With M do
    begin
      Case Action of
        MouseActionDown : Write(MouseLog,'down');
        MouseActionUp : Write(MouseLog,'up');
        MouseActionMove : Write(MouseLog,'move');
      end;
    Write(MouseLog,' event at ',X,', ',Y);
    If (Buttons<>0) then
    begin
```

```

        Write(MouseLog, ' for buttons: ');
        If (Buttons and MouseLeftbutton)<>0 then
            Write(MouseLog, 'Left ');
        If (Buttons and MouseRightbutton)<>0 then
            Write(MouseLog, 'Right ');
        If (Buttons and MouseMiddlebutton)<>0 then
            Write(MouseLog, 'Middle ');
        end;
        WriteLn(MouseLog);
    end;
end;

Procedure LogInitMouse;

begin
    OldMouseDriver.InitDriver();
    Assign(MouseLog, logFileName);
    Rewrite(MouseLog);
    Active := True;
    StartMouseLogging;
end;

Procedure LogDoneMouse;

begin
    StopMouseLogging;
    Close(MouseLog);
    Active := False;
    OldMouseDriver.DoneDriver();
end;

Procedure SetMouseLogFileName(FileName : String);

begin
    If Not Active then
        LogFileName := FileName;
    end;

Initialization
    GetMouseDriver(OldMouseDriver);
    NewMouseDriver := OldMouseDriver;
    NewMouseDriver.GetMouseEvent := @LogGetMouseEvent;
    NewMouseDriver.InitDriver := @LogInitMouse;
    NewMouseDriver.DoneDriver := @LogDoneMouse;
    LogFileName := 'Mouse.log';
    Logging := False;
    SetMouseDriver(NewMouseDriver);
end.

```

66.4 Constants, types and variables

66.4.1 Constants

```
errMouseBase = 1030
```

Base for mouse error codes.

```
errMouseInitError = errMouseBase + 0
```

Mouse initialization error

```
errMouseNotImplemented = errMouseBase + 1
```

Mouse driver not implemented.

```
MouseActionDown = $0001
```

Mouse button down event signal.

```
MouseActionMove = $0004
```

Mouse cursor move event signal.

```
MouseActionUp = $0002
```

Mouse button up event signal.

```
MouseButton4 = $08
```

4th mouse button event

```
MouseButton5 = $10
```

5th mouse button event

```
MouseEventBufSize = 16
```

The mouse unit has a mechanism to buffer mouse events. This constant defines the size of the event buffer.

```
MouseLeftButton = $01
```

Left mouse button event.

```
MouseMiddleButton = $04
```

Middle mouse button event.

```
MouseRightButton = $02
```

Right mouse button event.

66.4.2 Types

```
PMouseEvent = ^TMouseEvent
```

Pointer to TMouseEvent ([1154](#)) record.

66.4.3 Variables

MouseButtons : Byte

This variable keeps track of the last known mouse button state. Do not use.

MouseIntFlag : Byte

This variable keeps track of the last known internal mouse state. Do not use.

MouseWhereX : Word

This variable keeps track of the last known cursor position. Do not use.

MouseWhereY : Word

This variable keeps track of the last known cursor position. Do not use.

66.5 Procedures and functions

66.5.1 DetectMouse

Synopsis: Detect the presence of a mouse.

Declaration: `function DetectMouse : Byte`

Visibility: default

Description: `DetectMouse` detects whether a mouse is attached to the system or not. If there is no mouse, then zero is returned. If a mouse is attached, then the number of mouse buttons is returned.

This function should be called after the mouse driver was initialized.

Errors: None.

See also: `InitMouse` ([1151](#)), `DoneMouse` ([1148](#))

Listing: `./examples/mouseex/ex1.pp`

Program `Example1`;

{ Program to demonstrate the DetectMouse function. }

Uses `mouse`;

Var

Buttons : Byte;

begin

InitMouse;

Buttons:=DetectMouse;

If Buttons=0 **then**

 WriteLn('No mouse present.')

else

 WriteLn('Found mouse with ',Buttons,' buttons.');

DoneMouse;

end.

66.5.2 DoneMouse

Synopsis: Deinitialize mouse driver.

Declaration: `procedure DoneMouse`

Visibility: `default`

Description: `DoneMouse` De-initializes the mouse driver. It cleans up any memory allocated when the mouse was initialized, or removes possible mouse hooks from memory. The mouse functions will not work after `DoneMouse` was called. If `DoneMouse` is called a second time, it will exit at once. `InitMouse` should be called before `DoneMouse` can be called again.

For an example, see most other mouse functions.

Errors: None.

See also: `DetectMouse` ([1147](#)), `InitMouse` ([1151](#))

66.5.3 GetMouseButtons

Synopsis: Get the state of the mouse buttons

Declaration: `function GetMouseButtons : Word`

Visibility: `default`

Description: `GetMouseButtons` returns the current button state of the mouse, i.e. it returns a or-ed combination of the following constants:

MouseLeftButton When the left mouse button is held down.

MouseRightButton When the right mouse button is held down.

MouseMiddleButton When the middle mouse button is held down.

Errors: None.

See also: `GetMouseEvent` ([1149](#)), `GetMouseX` ([1149](#)), `GetMouseY` ([1150](#))

Listing: `./examples/mouseex/ex2.pp`

Program `Example2`;

{ Program to demonstrate the GetMouseButtons function. }

Uses `mouse`;

begin

`InitMouse`;

`WriteLn`('Press right mouse button to exit program');

While (`GetMouseButtons`<>`MouseRightButton`) **do** ;

`DoneMouse`;

end.

66.5.4 GetMouseDriver

Synopsis: Get a copy of the currently active mouse driver.

Declaration: `procedure GetMouseDriver (var Driver: TMouseDriver)`

Visibility: default

Description: `GetMouseDriver` returns the currently set mouse driver. It can be used to retrieve the current mouse driver, and override certain callbacks.

A more detailed explanation about getting and setting mouse drivers can be found in `mousedrv` (1143).

For an example, see the section on writing a custom mouse driver, `mousedrv` (1143)

Errors: None.

See also: `SetMouseDriver` (1152)

66.5.5 GetMouseEvent

Synopsis: Get next mouse event from the queue.

Declaration: `procedure GetMouseEvent (var MouseEvent: TMouseEvent)`

Visibility: default

Description: `GetMouseEvent` returns the next mouse event (a movement, button press or button release), and waits for one if none is available in the queue.

Some mouse drivers can implement a mouse event queue which can hold multiple events till they are fetched. Others don't, and in that case, a one-event queue is implemented for use with `PollMouseEvent` (1151).

Errors: None.

See also: `GetMouseButtons` (1148), `GetMouseX` (1149), `GetMouseY` (1150)

66.5.6 GetMouseX

Synopsis: Query the current horizontal position of the mouse cursor.

Declaration: `function GetMouseX : Word`

Visibility: default

Description: `GetMouseX` returns the current X position of the mouse. X is measured in characters, starting at 0 for the left side of the screen.

Errors: None.

See also: `GetMouseButtons` (1148), `GetMouseEvent` (1149), `GetMouseY` (1150)

Listing: `./examples/mouseex/ex4.pp`

Program `Example4;`

{ Program to demonstrate the GetMouseX, GetMouseY functions. }

Uses `mouse;`

```

Var
  X,Y : Word;

begin
  InitMouse;
  Writeln ('Move mouse cursor to square 10,10 to end');
  Repeat
    X:=GetMouseX;
    Y:=GetMouseY;
    Writeln ('X,Y= (',X,' ',',',Y,' ')');
  Until (X=9) and (Y=9);
  DoneMouse;
end.

```

66.5.7 GetMouseY

Synopsis: Query the current vertical position of the mouse cursor.

Declaration: `function GetMouseY : Word`

Visibility: default

Description: `GetMouseY` returns the current Y position of the mouse. Y is measured in characters, starting at 0 for the top of the screen.

For an example, see `GetMouseX` ([1149](#))

Errors: None.

See also: `GetMouseButtons` ([1148](#)), `GetMouseEvent` ([1149](#)), `GetMouseX` ([1149](#))

66.5.8 HideMouse

Synopsis: Hide the mouse cursor.

Declaration: `procedure HideMouse`

Visibility: default

Description: `HideMouse` hides the mouse cursor. This may or may not be implemented on all systems, and depends on the driver.

Errors: None.

See also: `ShowMouse` ([1153](#))

Listing: `./examples/mouseex/ex5.pp`

Program Example5;

{ Program to demonstrate the HideMouse function. }

Uses mouse;

Var

Event : TMouseEvent;
Visible : Boolean;

```

begin
  InitMouse;
  ShowMouse;
  Visible:=True;
  WriteLn('Press left mouse button to hide/show, right button quits');
  Repeat
    GetMouseEvent(Event);
    With Event do
      If (Buttons=MouseLeftbutton) and
        (Action=MouseDown) then
        begin
          If Visible then
            HideMouse
          else
            ShowMouse;
            Visible:=Not Visible;
          end;
        Until (Event.Buttons=MouseRightButton) and
          (Event.Action=MouseDown);
      DoneMouse;
    end.

```

66.5.9 InitMouse

Synopsis: Initialize the FPC mouse driver.

Declaration: `procedure InitMouse`

Visibility: default

Description: `InitMouse` initializes the mouse driver. This will allocate any data structures needed for the mouse to function. All mouse functions can be used after a call to `InitMouse`.

A call to `InitMouse` must always be followed by a call to `DoneMouse` (1148) at program exit. Failing to do so may leave the mouse in an unusable state, or may result in memory leaks.

For an example, see most other functions.

Errors: None.

See also: `DoneMouse` (1148), `DetectMouse` (1147)

66.5.10 PollMouseEvent

Synopsis: Query next mouse event. Do not wait if none available.

Declaration: `function PollMouseEvent (var MouseEvent: TMouseEvent) : Boolean`

Visibility: default

Description: `PollMouseEvent` checks whether a mouse event is available, and returns it in `MouseEvent` if one is found. The function result is `True` in that case. If no mouse event is pending, the function result is `False`, and the contents of `MouseEvent` is undefined.

Note that after a call to `PollMouseEvent`, the event should still be removed from the mouse event queue with a call to `GetMouseEvent`.

Errors: None.

See also: `GetMouseEvent` (1149), `PutMouseEvent` (1152)

66.5.11 PutMouseEvent

Synopsis: Put a mouse event in the event queue.

Declaration: `procedure PutMouseEvent (const MouseEvent: TMouseEvent)`

Visibility: default

Description: `PutMouseEvent` adds `MouseEvent` to the input queue. The next call to `GetMouseEvent` (1149) or `PollMouseEvent` will then return `MouseEvent`.

Please note that depending on the implementation the mouse event queue can hold only one value.

Errors: None.

See also: `GetMouseEvent` (1149), `PollMouseEvent` (1151)

66.5.12 SetMouseDriver

Synopsis: Set a new mouse driver.

Declaration: `procedure SetMouseDriver (const Driver: TMouseDriver)`

Visibility: default

Description: `SetMouseDriver` sets the mouse driver to `Driver`. This function should be called before `InitMouse` (1151) is called, or after `DoneMouse` is called. If it is called after the mouse has been initialized, it does nothing.

For more information on setting the mouse driver, `mousedrv` (1143).

For an example, see `mousedrv` (1143)

See also: `InitMouse` (1151), `DoneMouse` (1148), `GetMouseDriver` (1149)

66.5.13 SetMouseXY

Synopsis: Set the mouse cursor position.

Declaration: `procedure SetMouseXY (x: Word; y: Word)`

Visibility: default

Description: `SetMouseXY` places the mouse cursor on `X`, `Y`. `X` and `Y` are zero based character coordinates: 0, 0 is the top-left corner of the screen, and the position is in character cells (i.e. not in pixels).

Errors: None.

See also: `GetMouseX` (1149), `GetMouseY` (1150)

Listing: `./examples/mouseex/ex7.pp`

Program `Example7`;

{ Program to demonstrate the SetMouseXY function. }

Uses `mouse`;

begin

`InitMouse`;

`WriteLn`('Click right mouse button to quit.');

```

SetMouseXY(40,12);
Repeat
  WriteLn(GetMouseX, ', ', GetMouseY);
  If (GetMouseX>70) then
    SetMouseXY(10,GetMouseY);
  If (GetMouseY>20) then
    SetMouseXY(GetMouseX,5);
  Until (GetMouseButtons=MouseRightButton);
DoneMouse;
end.

```

66.5.14 ShowMouse

Synopsis: Show the mouse cursor.

Declaration: `procedure ShowMouse`

Visibility: `default`

Description: `ShowMouse` shows the mouse cursor if it was previously hidden. The capability to hide or show the mouse cursor depends on the driver.

For an example, see `HideMouse` ([1150](#))

Errors: None.

See also: `HideMouse` ([1150](#))

66.6 TMouseDriver

```

TMouseDriver = record
  UseDefaultQueue : Boolean;
  InitDriver :
  procedure;
  DoneDriver : procedure;
  DetectMouse : function : Byte
  ;
  ShowMouse : procedure;
  HideMouse : procedure;
  GetMouseX :
  function : Word;
  GetMouseY : function : Word;
  GetMouseButtons
  : function : Word;
  SetMouseXY : procedure(x: Word; y: Word);
  GetMouseEvent : procedure(var MouseEvent: TMouseEvent);
  PollMouseEvent
  : function(var MouseEvent: TMouseEvent) : Boolean;
  PutMouseEvent
  : procedure(const MouseEvent: TMouseEvent);
end

```

The `TMouseDriver` record is used to implement a mouse driver in the `SetMouseDriver` ([1152](#)) function. Its fields must be filled in before calling the `SetMouseDriver` ([1152](#)) function.

66.7 TMouseEvent

```
TMouseEvent = packed record
  buttons : Word;
  x : Word;
  y : Word
;
  Action : Word;
end
```

The `TMouseEvent` is the central type of the mouse unit, it is used to describe all mouse events.

The `Buttons` field describes which buttons were down when the event occurred. The `x`, `y` fields describe where the event occurred on the screen. The `Action` describes what action was going on when the event occurred. The `Buttons` and `Action` field can be examined using the constants defined in the unit interface.

Chapter 67

Reference for unit 'Objects'

67.1 Used units

Table 67.1: Used units by unit 'Objects'

Name	Page
System	1339

67.2 Overview

This document documents the `objects` unit. The unit was implemented by many people, and was mainly taken from the FreeVision sources. It has been ported to all supported platforms.

The methods and fields that are in a `Private` part of an object declaration have been left out of this documentation.

67.3 Constants, types and variables

67.3.1 Constants

`coIndexError = - 1`

Collection list error: Index out of range

`coOverflow = - 2`

Collection list error: Overflow

`DefaultTPCompatible : Boolean = False`

`DefaultTPCompatible` is used to initialize `tstream.tpcompatible` (??).

`MaxBytes = 128 * 1024 * 128`

Maximum data size (in bytes)

```
MaxCollectionSize = MaxBytes div SizeOf(Pointer)
```

Maximum collection size (in items)

```
MaxPtrs = MaxBytes div SizeOf(Pointer)
```

Maximum data size (in pointers)

```
MaxReadBytes = $7fffffff
```

Maximum data that can be read from a stream (not used)

```
MaxTPCompatibleCollectionSize = 65520 div 4
```

Maximum collection size (in items, same value as in TP)

```
MaxWords = MaxBytes div SizeOf(Word)
```

Maximum data size (in words)

```
RCollection : TStreamRec = (ObjType: 50; VmtLink: Ofs(^ TypeOf(TCollection
)); Load: @ TCollection.Load; Store: @ TCollection.Store; Next: Nil
)
```

Default stream record for the TCollection ([1172](#)) object.

```
RStrCollection : TStreamRec = (ObjType: 69; VmtLink: Ofs(^ TypeOf
(TStrCollection)); Load: @ TStrCollection.Load; Store: @ TStrCollection
.Store; Next: Nil)
```

Default stream record for the TStrCollection ([1212](#)) object.

```
RStringCollection : TStreamRec = (ObjType: 51; VmtLink: Ofs(^ TypeOf
(TStringCollection)); Load: @ TStringCollection.Load; Store: @ TStringCollection
.Store; Next: Nil)
```

Default stream record for the TStringCollection ([1222](#)) object.

```
RStringList : TStreamRec = (ObjType: 52; VmtLink: Ofs(^ TypeOf(TStringList
)); Load: @ TStringList.Load; Store: Nil; Next: Nil)
```

Default stream record for the TStringList ([1224](#)) object.

```
RStrListMaker : TStreamRec = (ObjType: 52; VmtLink: Ofs(^ TypeOf(TStrListMaker
)); Load: Nil; Store: @ TStrListMaker.Store; Next: Nil)
```

Default stream record for the TStrListMaker ([1226](#)) object.

```
stCreate = $3C00
```

Stream initialization mode: Create new file

`stError = - 1`

Stream error codes: Access error

`stGetError = - 5`

Stream error codes: Get object error

`stInitError = - 2`

Stream error codes: Initialize error

`stOk = 0`

Stream error codes: No error

`stOpen = $3D02`

Stream initialization mode: Read/write access

`stOpenError = - 8`

Stream error codes: Error opening stream

`stOpenRead = $3D00`

Stream initialization mode: Read access only

`stOpenWrite = $3D01`

Stream initialization mode: Write access only

`stPutError = - 6`

Stream error codes: Put object error

`stReadError = - 3`

Stream error codes: Stream read error

`StreamError : CodePointer = Nil`

Pointer to default stream error handler.

`stSeekError = - 7`

Stream error codes: Seek error in stream

`stWriteError = - 4`

Stream error codes: Stream write error

`vmtHeaderSize = 8`

Size of the VMT header in an object (not used).

67.3.2 Types

`AsciiZ = Array[0..255] of Char`

Filename - null terminated array of characters.

`FNameStr = String`

Filename - shortstring version.

`PBufStream = ^TBufStream`

Pointer to `TBufStream` (1168) object.

`PByteArray = ^TByteArray`

Pointer to `TByteArray` (1160)

`PCharSet = ^TCharSet`

Pointer to `TCharSet` (1160).

`PCollection = ^TCollection`

Pointer to `TCollection` (1172) object.

`PDosStream = ^TDosStream`

Pointer to `TDosStream` (1187) object.

`PItemList = ^TItemList`

Pointer to `TItemList` (1160) object.

`PMemoryStream = ^TMemoryStream`

Pointer to `TMemoryStream` (1192) object.

`PObject = ^TObject`

Pointer to `TObject` (1194) object.

`PPoint = ^TPoint`

Pointer to `TPoint` (1196) record.

`PPointerArray = ^TPointerArray`

Pointer to `TPointerArray` (1160)

`PRect = ^TRect`

Pointer to TRect (1196) object.

PResourceCollection = ^TResourceCollection

Pointer to TResourceCollection (1202) object.

PResourceFile = ^TResourceFile

Pointer to TResourceFile (1203) object.

PSortedCollection = ^TSortedCollection

Pointer to TSortedCollection (1206) object.

PStrCollection = ^TStrCollection

Pointer to TStrCollection (1212) object.

PStream = ^TStream

Pointer type to TStream (1214)

PStreamRec = ^TStreamRec

Pointer to TStreamRec (1168)

PStrIndex = ^TStrIndex

Pointer to TStrIndex (1160) array.

PString = PShortString

Pointer to a shortstring.

PStringCollection = ^TStringCollection

Pointer to TStringCollection (1222) object.

PStringList = ^TStringList

Pointer to TStringList (1224) object.

PStrListMaker = ^TStrListMaker

Pointer to TStrListMaker (1226) object.

PUnSortedStrCollection = ^TUnSortedStrCollection

Pointer to TUnSortedStrCollection (1227) object.

PWordArray = ^TWordArray

Pointer to TWordArray ([1160](#))

`Sw_Integer = LongInt`

Alias for longint

`Sw_Word = Cardinal`

Alias for Cardinal

`TByteArray = Array[0..MaxBytes-1] of Byte`

Array with maximum allowed number of bytes.

`TCharSet = Set of Char`

Generic set of characters type.

`TItemList = Array[0..MaxCollectionSize-1] of Pointer`

Pointer array type used in a TCollection ([1172](#))

`TPointerArray = Array[0..MaxPtrs-1] of Pointer`

Array with maximum allowed number of pointers

`TStrIndex = Array[0..9999] of TStrIndexRec`

Pointer array type used in a TStringList ([1224](#))

`TWordArray = Array[0..MaxWords-1] of Word`

Array with maximum allowed number of words.

67.3.3 Variables

`invalidhandle : THandle`

Value for invalid handle. Initial value for file stream handles or when the stream is closed.

67.4 Procedures and functions

67.4.1 Abstract

Synopsis: Abstract error handler.

Declaration: `procedure Abstract`

Visibility: default

Description: When implementing abstract methods, do not declare them as `abstract`. Instead, define them simply as `virtual`. In the implementation of such abstract methods, call the `Abstract` procedure. This allows explicit control of what happens when an abstract method is called.

The current implementation of `Abstract` terminates the program with a run-time error 211.

Errors: None.

67.4.2 CallPointerConstructor

Synopsis: Call a constructor with a pointer argument.

Declaration: `function CallPointerConstructor(Ctor: CodePointer; Obj: pointer;
VMT: pointer; Param1: pointer) : pointer`

Visibility: default

Description: `CallVoidConstructor` calls the constructor of an object. `Ctor` is the address of the constructor, `Obj` is a pointer to the instance. If it is `Nil`, then a new instance is allocated. `VMT` is a pointer to the object's VMT. `Param1` is passed to the constructor. The return value is a pointer to the instance.

Note that this can only be used on constructors that require a pointer as the sole argument. It can also be used to call a constructor with a single argument by reference.

Errors: If the constructor expects other arguments than a pointer, the stack may be corrupted.

See also: `CallVoidConstructor` (1162), `CallPointerMethod` (1161), `CallVoidLocal` (1162), `CallPointerLocal` (1161), `CallVoidMethodLocal` (1163), `CallPointerMethodLocal` (1162)

67.4.3 CallPointerLocal

Synopsis: Call a local nested function with a pointer argument

Declaration: `function CallPointerLocal(Func: CodePointer; Frame: Pointer;
Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping function. It passes `Param1` to the local function.

Errors: If the local function expects other parameters than a pointer, the stack may become corrupted.

See also: `CallPointerMethod` (1161), `CallVoidMethod` (1163), `CallVoidLocal` (1162), `CallVoidMethodLocal` (1163), `CallPointerMethodLocal` (1162), `CallVoidConstructor` (1162), `CallPointerConstructor` (1161)

67.4.4 CallPointerMethod

Synopsis: Call a method with a single pointer argument

Declaration: `function CallPointerMethod(Method: CodePointer; Obj: pointer;
Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerMethod` calls the method with address `Method` for instance `Obj`. It passes `Param1` to the method as the single argument. It returns a pointer to the instance.

Errors: If the method expects other parameters than a single pointer, the stack may become corrupted.

See also: `CallVoidMethod` (1163), `CallVoidLocal` (1162), `CallPointerLocal` (1161), `CallVoidMethodLocal` (1163), `CallPointerMethodLocal` (1162), `CallVoidConstructor` (1162), `CallPointerConstructor` (1161)

67.4.5 CallPointerMethodLocal

Synopsis: Call a local procedure of a method with a pointer argument

Declaration: `function CallPointerMethodLocal(Func: CodePointer; Frame: Pointer;
Obj: pointer; Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerMethodLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping method. It passes `Param1` to the local function.

Errors: If the local function expects other parameters than a pointer, the stack may become corrupted.

See also: `CallPointerMethod` (1161), `CallVoidMethod` (1163), `CallPointerLocal` (1161), `CallVoidLocal` (1162), `CallVoidMethodLocal` (1163), `CallVoidConstructor` (1162), `CallPointerConstructor` (1161)

67.4.6 CallVoidConstructor

Synopsis: Call a constructor with no arguments

Declaration: `function CallVoidConstructor(Ctor: CodePointer; Obj: pointer;
VMT: pointer) : pointer`

Visibility: default

Description: `CallVoidConstructor` calls the constructor of an object. `Ctor` is the address of the constructor, `Obj` is a pointer to the instance. If it is `Nil`, then a new instance is allocated. `VMT` is a pointer to the object's VMT. The return value is a pointer to the instance.

Note that this can only be used on constructors that require no arguments.

Errors: If the constructor expects arguments, the stack may be corrupted.

See also: `CallPointerConstructor` (1161), `CallPointerMethod` (1161), `CallVoidLocal` (1162), `CallPointerLocal` (1161), `CallVoidMethodLocal` (1163), `CallPointerMethodLocal` (1162)

67.4.7 CallVoidLocal

Synopsis: Call a local nested procedure.

Declaration: `function CallVoidLocal(Func: CodePointer; Frame: Pointer) : pointer`

Visibility: default

Description: `CallVoidLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping function.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` (1161), `CallVoidMethod` (1163), `CallPointerLocal` (1161), `CallVoidMethodLocal` (1163), `CallPointerMethodLocal` (1162), `CallVoidConstructor` (1162), `CallPointerConstructor` (1161)

67.4.8 CallVoidMethod

Synopsis: Call an object method

Declaration: `function CallVoidMethod(Method: CodePointer; Obj: pointer) : pointer`

Visibility: default

Description: `CallVoidMethod` calls the method with address `Method` for instance `Obj`. It returns a pointer to the instance.

Errors: If the method expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` ([1161](#)), `CallVoidLocal` ([1162](#)), `CallPointerLocal` ([1161](#)), `CallVoidMethodLocal` ([1163](#)), `CallPointerMethodLocal` ([1162](#)), `CallVoidConstructor` ([1162](#)), `CallPointerConstructor` ([1161](#))

67.4.9 CallVoidMethodLocal

Synopsis: Call a local procedure of a method

Declaration: `function CallVoidMethodLocal(Func: CodePointer; Frame: Pointer; Obj: pointer) : pointer`

Visibility: default

Description: `CallVoidMethodLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping method.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` ([1161](#)), `CallVoidMethod` ([1163](#)), `CallPointerLocal` ([1161](#)), `CallVoidLocal` ([1162](#)), `CallPointerMethodLocal` ([1162](#)), `CallVoidConstructor` ([1162](#)), `CallPointerConstructor` ([1161](#))

67.4.10 DisposeStr

Synopsis: Dispose of a shortstring which was allocated on the heap.

Declaration: `procedure DisposeStr(P: PString)`

Visibility: default

Description: `DisposeStr` removes a dynamically allocated string from the heap.

For an example, see `NewStr` ([1164](#)).

Errors: None.

See also: `NewStr` ([1164](#)), `SetStr` ([1167](#))

67.4.11 LongDiv

Synopsis: Overflow safe divide

Declaration: `function LongDiv(X: LongInt; Y: Integer) : Integer`

Visibility: default

Description: `LongDiv` divides `X` by `Y`. The result is of type `Integer` instead of type `Longint`, as you would get normally.

Errors: If Y is zero, a run-time error will be generated.

See also: LongMul ([1164](#))

67.4.12 LongMul

Synopsis: Overflow safe multiply.

Declaration: `function LongMul(X: Integer; Y: Integer) : LongInt`

Visibility: default

Description: LongMul multiplies X with Y. The result is of type LongInt. This avoids possible overflow errors you would normally get when multiplying X and Y that are too big.

Errors: None.

See also: LongDiv ([1163](#))

67.4.13 NewStr

Synopsis: Allocate a copy of a shortstring on the heap.

Declaration: `function NewStr(const S: string) : PString`

Visibility: default

Description: NewStr makes a copy of the string S on the heap, and returns a pointer to this copy. If the string is empty then Nil is returned.

The allocated memory is not based on the declared size of the string passed to NewStr, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: DisposeStr ([1163](#)), SetStr ([1167](#))

Listing: ./examples/objectex/ex40.pp

```

Program ex40;

{ Program to demonstrate the NewStr function }

Uses Objects;

Var S : String;
    P : PString;

begin
  S := 'Some really cute string';
  P := NewStr(S);
  If P^ <> S then
    Writeln ('Oh-oh... Something is wrong !!');
  DisposeStr(P);
end.

```

67.4.14 RegisterObjects

Synopsis: Register standard objects.

Declaration: `procedure RegisterObjects`

Visibility: `default`

Description: `RegisterObjects` registers the following objects for streaming:

1. `TCollection`, see `TCollection` (1172).
2. `TStringCollection`, see `TStringCollection` (1222).
3. `TStrCollection`, see `TStrCollection` (1212).

Errors: None.

See also: `RegisterType` (1165)

67.4.15 RegisterType

Synopsis: Register new object for streaming.

Declaration: `procedure RegisterType (var S: TStreamRec)`

Visibility: `default`

Description: `RegisterType` registers a new type for streaming. An object cannot be streamed unless it has been registered first. The stream record `S` needs to have the following fields set:

ObjType: `Sw_Word` This should be a unique identifier. Each possible type should have it's own identifier.

VmtLink: `pointer` This should contain a pointer to the VMT (Virtual Method Table) of the object you try to register.

Load : `Pointer` is a pointer to a method that initializes an instance of that object, and reads the initial values from a stream. This method should accept as it's sole argument a `PStream` type variable.

Store: `Pointer` is a pointer to a method that stores an instance of the object to a stream. This method should accept as it's sole argument a `PStream` type variable.

The VMT of the object can be retrieved with the following expression:

```
VmtLink: ofs (TypeOf (MyType) ^) ;
```

Errors: In case of error (if a object with the same `ObjType`) is already registered), run-time error 212 occurs.

Listing: `./examples/objectex/myobject.pp`

```
Unit MyObject;
```

```
Interface
```

```
Uses Objects;
```

```
Type
```

```

PMyObject = ^TMyObject;
TMyObject = Object(TObject)
  Field : Longint;
  Constructor Init;
  Constructor Load (Var Stream : TStream);
  Destructor Done;
  Procedure Store (Var Stream : TStream);
  Function GetField : Longint;
  Procedure SetField (Value : Longint);
end;

```

Implementation

```

Constructor TMyobject.Init;

begin
  Inherited Init;
  Field := -1;
end;

Constructor TMyobject.Load (Var Stream : TStream);

begin
  Stream.Read(Field, Sizeof(Field));
end;

Destructor TMyObject.Done;

begin
end;

Function TMyObject.GetField : Longint;

begin
  GetField := Field;
end;

Procedure TMyObject.SetField (Value : Longint);

begin
  Field := Value;
end;

Procedure TMyObject.Store (Var Stream : TStream);

begin
  Stream.Write(Field, SizeOf(Field));
end;

Const MyObjectRec : TStreamRec = (
  Objtype : 666;
  vmtlink : Ofs(TypeOf(TMyObject)^);
  Load : @TMyObject.Load;
  Store : @TMyObject.Store;
);

begin
  RegisterObjects;

```

```

    RegisterType (MyObjectRec);
end.

```

67.4.16 SetStr

Synopsis: Allocate a copy of a shortstring on the heap.

Declaration: `procedure SetStr(var p: PString; const s: string)`

Visibility: default

Description: `SetStr` makes a copy of the string `S` on the heap and returns the pointer to this copy in `P`. If `P` pointed to another string (i.e. was not `Nil`, the memory is released first. Contrary to `NewStr` ([1164](#)), if the string is empty then a pointer to an empty string is returned.

The allocated memory is not based on the declared size of the string passed to `NewStr`, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: `DisposeStr` ([1163](#)), `NewStr` ([1164](#))

67.5 LongRec

```

LongRec = packed record
    Hi : Word;
    Lo : Word;
end

```

Record describing a longint (in Words)

67.6 PtrRec

```

PtrRec = packed record
    Ofs : Word;
    Seg : Word;
end

```

Record describing a pointer to a memory location.

67.7 TStreamRec

```

TStreamRec = packed record
    ObjType : Sw_Word;
    VmtLink : pointer
;
    Load : CodePointer;
    Store : CodePointer;

```



```

    Next : PStreamRec
;
end

```

TStreamRec is used by the `Objects` unit streaming mechanism: when an object is registered, a TStreamRec record is added to a list of records. This list is used when objects need to be streamed from/streamed to a stream. It contains all the information needed to stream the object.

67.8 TStrIndexRec

```

TStrIndexRec = packed record
    Key : Sw_Word;
    Count : Word;
    Offset
    : Word;
end

```

Record type used in a TStringList ([1224](#)) to store the strings

67.9 WordRec

```

WordRec = packed record
    Hi : Byte;
    Lo : Byte;
end

```

Record describing a Word (in bytes)

67.10 TBufStream

67.10.1 Description

Bufstream implements a buffered file stream. That is, all data written to the stream is written to memory first. Only when the buffer is full, or on explicit request, the data is written to disk.

Also, when reading from the stream, first the buffer is checked if there is any unread data in it. If so, this is read first. If not the buffer is filled again, and then the data is read from the buffer.

The size of the buffer is fixed and is set when constructing the file.

This is useful if you need heavy throughput for your stream, because it speeds up operations.

67.10.2 Method overview

Page	Method	Description
1170	Close	Flush data and Close the file.
1169	Done	Close the file and cleans up the instance.
1170	Flush	FLush data from buffer, and write it to stream.
1169	Init	Initialize an instance of <code>TBufStream</code> and open the file.
1171	Open	Open the file if it is closed.
1172	Read	Read data from the file to a buffer in memory.
1171	Seek	Set current position in file.
1171	Truncate	Flush buffer, and truncate the file at current position.
1172	Write	Write data to the file from a buffer in memory.

67.10.3 TBufStream.Init

Synopsis: Initialize an instance of `TBufStream` and open the file.

Declaration: `constructor Init (FileName: FNameStr; Mode: Word; Size: Word)`

Visibility: default

Description: `Init` instantiates an instance of `TBufStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

stCreateCreates a new file.

stOpenReadRead access only.

stOpenWriteWrite access only.

stOpenRead and write access.

The `Size` parameter determines the size of the buffer that will be created. It should be different from zero.

For an example see `TBufStream.Flush` ([1170](#)).

Errors: On error, `Status` is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Init` ([1188](#)), `TBufStream.Done` ([1169](#))

67.10.4 TBufStream.Done

Synopsis: Close the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` flushes and closes the file if it was open and cleans up the instance of `TBufStream`.

For an example see `TBufStream.Flush` ([1170](#)).

Errors: None.

See also: `TDosStream.Done` ([1188](#)), `TBufStream.Init` ([1169](#)), `TBufStream.Close` ([1170](#))

67.10.5 TBufStream.Close

Synopsis: Flush data and Close the file.

Declaration: `procedure Close; Virtual`

Visibility: default

Description: `Close` flushes and closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` (1169) it does not clean up the instance of `TBufStream`

For an example see `TBufStream.Flush` (1170).

Errors: None.

See also: `TStream.Close` (1218), `TBufStream.Init` (1169), `TBufStream.Done` (1169)

67.10.6 TBufStream.Flush

Synopsis: FLush data from buffer, and write it to stream.

Declaration: `procedure Flush; Virtual`

Visibility: default

Description: When the stream is in write mode, the contents of the buffer are written to disk, and the buffer position is set to zero. When the stream is in read mode, the buffer position is set to zero.

Errors: Write errors may occur if the file was in write mode. see `Write` (1172) for more info on the errors.

See also: `TStream.Close` (1218), `TBufStream.Init` (1169), `TBufStream.Done` (1169)

Listing: `./examples/objectex/ex15.pp`

Program `ex15;`

{ Program to demonstrate the TStream.Flush method }

Uses `Objects;`

Var `L : String;`
 `P : PString;`
 `S : PBufStream; { Only one with Flush implemented. }`

begin

```
L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PBufStream, Init('test.dat', stcreate, 100));
WriteLn ('Writing "', L, '" to stream with handle ', S^.Handle);
S^.WriteStr(@L);
{ At this moment, there is no data on disk yet. }
S^.Flush;
{ Now there is. }
S^.WriteStr(@L);
{ Close calls flush first }
S^.Close;
WriteLn ('Closed stream. File handle is ', S^.Handle);
S^.Open (stOpenRead);
P:=S^.ReadStr;
L:=P^;
```

```

DisposeStr(P);
WriteLn ('Read "',L,'" from stream with handle ',S^.Handle);
S^.Close;
Dispose (S,Done);
end.

```

67.10.7 TBufStream.Truncate

Synopsis: Flush buffer, and truncate the file at current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: If the status of the stream is `stOK`, then `Truncate` tries to flush the buffer, and then truncates the stream size to the current file position.

For an example, see `TDosStream.Truncate` ([1189](#)).

Errors: Errors can be those of `Flush` ([1170](#)) or `TDosStream.Truncate` ([1189](#)).

See also: `TStream.Truncate` ([1219](#)), `TDosStream.Truncate` ([1189](#)), `TStream.GetSize` ([1216](#))

67.10.8 TBufStream.Seek

Synopsis: Set current position in file.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

For an example, see `TStream.Seek` ([1220](#));

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` ([1220](#)), `TStream.GetPos` ([1216](#))

67.10.9 TBufStream.Open

Synopsis: Open the file if it is closed.

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` ([1170](#)) call.

For an example, see `TDosStream.Open` ([1190](#)).

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` ([1218](#)), `TBufStream.Close` ([1170](#))

67.10.10 TBufStream.Read

Synopsis: Read data from the file to a buffer in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

`Read` will first try to read the data from the stream's internal buffer. If insufficient data is available, the buffer will be filled before continuing to read. This process is repeated until all needed data has been read.

For an example, see `TStream.Read` ([1221](#)).

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: `TStream.Read` ([1221](#)), `TBufStream.Write` ([1172](#))

67.10.11 TBufStream.Write

Synopsis: Write data to the file from a buffer in memory.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Write` will write `Count` bytes from `Buf` and place them in the stream.

`Write` will first try to write the data to the stream's internal buffer. When the internal buffer is full, then the contents will be written to disk. This process is repeated until all data has been written.

For an example, see `TStream.Read` ([1221](#)).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` ([1221](#)), `TBufStream.Read` ([1172](#))

67.11 TCollection

67.11.1 Description

The `TCollection` object manages a collection of pointers or objects. It also provides a series of methods to manipulate these pointers or objects.

Whether or not objects are used depends on the kind of calls you use. All kinds come in 2 flavors, one for objects, one for pointers.

67.11.2 Method overview

Page	Method	Description
1174	<code>At</code>	Return the item at a certain index.
1183	<code>AtDelete</code>	Delete item at certain position.
1182	<code>AtFree</code>	Free an item at the indicates position, calling it's destructor.
1186	<code>AtInsert</code>	Insert an element at a certain position in the collection.
1185	<code>AtPut</code>	Set collection item, overwriting an existing value.
1181	<code>Delete</code>	Delete an item from the collection, but does not destroy it.
1180	<code>DeleteAll</code>	Delete all elements from the collection. Objects are not destroyed.
1174	<code>Done</code>	Clean up collection, release all memory.
1185	<code>Error</code>	Set error code.
1177	<code>FirstThat</code>	Return first item which matches a test.
1184	<code>ForEach</code>	Execute procedure for each item in the list.
1180	<code>Free</code>	Free item from collection, calling it's destructor.
1179	<code>FreeAll</code>	Release all objects from the collection.
1183	<code>FreeItem</code>	Destroy a non-nil item.
1176	<code>GetItem</code>	Read one item off the stream.
1175	<code>IndexOf</code>	Find the position of a certain item.
1173	<code>Init</code>	Instantiate a new collection.
1181	<code>Insert</code>	Insert a new item in the collection at the end.
1176	<code>LastThat</code>	Return last item which matches a test.
1173	<code>Load</code>	Initialize a new collection and load collection from a stream.
1178	<code>Pack</code>	Remove all <code>>Nil</code> pointers from the collection.
1187	<code>PutItem</code>	Put one item on the stream
1185	<code>SetLimit</code>	Set maximum number of elements in the collection.
1187	<code>Store</code>	Write collection to a stream.

67.11.3 TCollection.Init

Synopsis: Instantiate a new collection.

Declaration: `constructor Init (ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` initializes a new instance of a collection. It sets the (initial) maximum number of items in the collection to `ALimit`. `ADelta` is the increase size : The number of memory places that will be allocated in case `ALimit` is reached, and another element is added to the collection.

For an example, see `TCollection.ForEach` ([1184](#)).

Errors: None.

See also: `TCollection.Load` ([1173](#)), `TCollection.Done` ([1174](#))

67.11.4 TCollection.Load

Synopsis: Initialize a new collection and load collection from a stream.

Declaration: `constructor Load (var S: TStream)`

Visibility: default

Description: `Load` initializes a new instance of a collection. It reads from stream `S` the item count, the item limit count, and the increase size. After that, it reads the specified number of items from the stream.

Errors: Errors returned can be those of `GetItem` ([1176](#)).

See also: `TCollection.Init` ([1173](#)), `TCollection.GetItem` ([1176](#)), `TCollection.Done` ([1174](#))

Listing: `./examples/objectex/ex22.pp`

```

Program ex22;

{ Program to demonstrate the TCollection.Load method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I : Longint;
    S : PMemoryStream;

begin
  C:=New(PCollection, Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(100-I);
      C^.Insert(M);
    end;
    WriteLn ('Inserted ', C^.Count, ' objects ');
  S:=New(PMemoryStream, Init(1000,10));
  C^.Store(S^);
  C^.FreeAll;
  // Dispose(C, Done);
  S^.Seek(0);
  C^.Load(S^);
  WriteLn ('Read ', C^.Count, ' objects from stream. ');
  Dispose(S, Done);
  Dispose(C, Done);
end.
```

67.11.5 TCollection.Done

Synopsis: Clean up collection, release all memory.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done` frees all objects in the collection, and then releases all memory occupied by the instance.

For an example, see `TCollection.ForEach` ([1184](#)).

Errors: None.

See also: `TCollection.Init` ([1173](#)), `TCollection.FreeAll` ([1179](#))

67.11.6 TCollection.At

Synopsis: Return the item at a certain index.

Declaration: `function At(Index: Sw_Integer) : Pointer`

Visibility: default

Description: `At` returns the item at position `Index`.

Errors: If `Index` is less than zero or larger than the number of items in the collection, see `TCollection.Error` is called with `coIndexError` and `Index` as arguments, resulting in a run-time error.

See also: `TCollection.Insert` ([1181](#))

Listing: `./examples/objectex/ex23.pp`

Program `ex23`;

{ Program to demonstrate the TCollection.At method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

begin

`C:=New(PCollection, Init(100,10));`

For `I:=1 to 100 do`

begin

`M:=New(PMyObject, Init);`

`M^.SetField(100-I);`

`C^.Insert(M);`

end;

For `I:=0 to C^.Count-1 do`

begin

`M:=C^.At(I);`

`Writeln('Object ',i,' has field : ',M^.GetField);`

end;

`C^.FreeAll;`

`Dispose(C, Done);`

end.

67.11.7 TCollection.IndexOf

Synopsis: Find the position of a certain item.

Declaration: `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `IndexOf` returns the index of `Item` in the collection. If `Item` isn't present in the collection, -1 is returned.

Errors: If the item is not present, -1 is returned.

See also: `TCollection.At` ([1174](#)), `TCollection.GetItem` ([1176](#)), `TCollection.Insert` ([1181](#))

Listing: `./examples/objectex/ex24.pp`

Program `ex24`;

{ Program to demonstrate the TCollection.IndexOf method }

Uses Objects, MyObject; { For TMyObject definition and registration }

```

Var C : PCollection;
      M, Keep : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New( PCollection , Init(100,10));
  Keep:=Nil;
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      If Random<0.1 then
        Keep:=M;
      C^.Insert(M);
    end;
  If Keep=Nil then
    begin
      Writeln('Please run again. No object selected');
      Halt(1);
    end;
  Writeln('Selected object has field : ', Keep^.GetField);
  Write('Selected object has index : ', C^.IndexOf(Keep));
  Writeln(' should match it's field. ');
  C^.FreeAll;
  Dispose(C, Done);
end.

```

67.11.8 TCollection.GetItem

Synopsis: Read one item off the stream.

Declaration: function GetItem(var S: TStream) : Pointer; Virtual

Visibility: default

Description: GetItem reads a single item off the stream S, and returns a pointer to this item. This method is used internally by the Load method, and should not be used directly.

Errors: Possible errors are the ones from TStream.Get ([1214](#)).

See also: TStream.Get ([1214](#)), TCollection.Store ([1187](#))

67.11.9 TCollection.LastThat

Synopsis: Return last item which matches a test.

Declaration: function LastThat(Test: CodePointer) : Pointer

Visibility: default

Description: This function returns the last item in the collection for which Test returns a non-nil result. Test is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: `TCollection.FirstThat` ([1177](#))

Listing: `./examples/objectex/ex25.pp`

```

Program ex21;

{ Program to demonstrate the TCollection.Foreach method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I : Longint;

Function CheckField (Dummy: Pointer; P : PMyObject) : Longint;

begin
    If P^.GetField < 56 then
        CheckField := 1
    else
        CheckField := 0;
    end;

begin
    C := New(PCollection, Init(100, 10));
    For I := 1 to 100 do
        begin
            M := New(PMyObject, Init);
            M^.SetField(I);
            C^.Insert(M);
        end;
    Writeln ('Inserted ', C^.Count, ' objects');
    Writeln ('Last one for which Field < 56 has index (should be 54) : ',
        C^.IndexOf(C^.LastThat(@CheckField)));
    C^.FreeAll;
    Dispose(C, Done);
end.
```

67.11.10 TCollection.FirstThat

Synopsis: Return first item which matches a test.

Declaration: `function FirstThat (Test: CodePointer) : Pointer`

Visibility: default

Description: This function returns the first item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: `TCollection.LastThat` ([1176](#))

Listing: `./examples/objectex/ex26.pp`

```

Program ex21;

{ Program to demonstrate the TCollection.FirstThat method }
```

```

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

Function CheckField (Dummy: Pointer; P : PMyObject) : Longint;

begin
  If P^.GetField > 56 then
    Checkfield := 1
  else
    CheckField := 0;
end;

begin
  C := New(PCollection, Init(100, 10));
  For I := 1 to 100 do
    begin
      M := New(PMyObject, Init);
      M^.SetField(I);
      C^.Insert(M);
    end;
  Writeln ('Inserted ', C^.Count, ' objects ');
  Writeln ('first one for which Field > 56 has index (should be 56) : ',
    C^.IndexOf(C^.FirstThat(@CheckField)));
  C^.FreeAll;
  Dispose(C, Done);
end.

```

67.11.11 TCollection.Pack

Synopsis: Remove all >Nil pointers from the collection.

Declaration: `procedure Pack`

Visibility: default

Description: Pack removes all Nil pointers from the collection, and adjusts Count to reflect this change. No memory is freed as a result of this call. In order to free any memory, you can call SetLimit with an argument of Count after a call to Pack.

Errors: None.

See also: TCollection.SetLimit ([1185](#))

Listing: ./examples/objectex/ex26.pp

Program ex21;

{ Program to demonstrate the TCollection.FirstThat method }

Uses Objects, MyObject; { For TMyObject definition and registration }

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

```

```

Function CheckField (Dummy: Pointer;P : PMyObject) : Longint;

begin
  If P^.GetField>56 then
    Checkfield:=1
  else
    CheckField:=0;
end;

begin
  C:=New(PCollection , Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init );
      M^.SetField(I);
      C^.Insert(M);
    end;
  WriteLn ( 'Inserted ',C^.Count,' objects ');
  WriteLn ( 'first one for which Field>56 has index (should be 56) : ',
    C^.IndexOf(C^.FirstThat(@CheckField)));
  C^.FreeAll;
  Dispose(C,Done);
end.

```

67.11.12 TCollection.FreeAll

Synopsis: Release all objects from the collection.

Declaration: `procedure FreeAll`

Visibility: default

Description: `FreeAll` calls the destructor of each object in the collection. It doesn't release any memory occupied by the collection itself, but it does set `Count` to zero.

See also: `TCollection.DeleteAll` ([1180](#)), `TCollection.FreeItem` ([1183](#))

Listing: `./examples/objectex/ex28.pp`

Program ex28;

{ Program to demonstrate the TCollection.FreeAll method }

Uses Objects,MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
 M : PMyObject;
 I : Longint;

begin
 Randomize;
 C:=**New**(PCollection , Init(120,10));
 For I:=1 **to** 100 **do**
 begin
 M:=**New**(PMyObject, Init);
 M^.SetField(I-1);
 C^.Insert(M);
 end

```

    end;
    Writeln ('Added 100 Items. ');
    C^.FreeAll;
    Writeln ('Freed all objects. ');
    Dispose(C,Done);
end.

```

67.11.13 TCollection.DeleteAll

Synopsis: Delete all elements from the collection. Objects are not destroyed.

Declaration: `procedure DeleteAll`

Visibility: default

Description: `DeleteAll` deletes all elements from the collection. It just sets the `Count` variable to zero. Contrary to `FreeAll` (1179), `DeleteAll` doesn't call the destructor of the objects.

Errors: None.

See also: `TCollection.FreeAll` (1179), `TCollection.Delete` (1181)

Listing: `./examples/objectex/ex29.pp`

Program `ex29`;

```

{
  Program to demonstrate the TCollection.DeleteAll method
  Compare with example 28, where FreeAll is used.
}

```

Uses `Objects, MyObject`; { For *TMyObject* definition and registration }

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

```

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  Writeln ('Added 100 Items. ');
  C^.DeleteAll;
  Writeln ('Deleted all objects. ');
  Dispose(C,Done);
end.

```

67.11.14 TCollection.Free

Synopsis: Free item from collection, calling it's destructor.

Declaration: `procedure Free(Item: Pointer)`

Visibility: default

Description: `Free` Deletes `Item` from the collection, and calls the destructor `Done` of the object.

Errors: If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

See also: `TCollection.FreeItem` ([1183](#))

Listing: `./examples/objectex/ex30.pp`

Program `ex30`;

{ Program to demonstrate the TCollection.Free method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

begin
 Randomize;
 `C:=New(PCollection, Init(120,10));`
 For `I:=1 to 100 do`
 begin
 `M:=New(PMyObject, Init);`
 `M^.SetField(I-1);`
 `C^.Insert(M);`
 end;
 WriteLn ('Added 100 Items. ');
 With `C^ do`
 While `Count>0 do Free(At(Count-1));`
 WriteLn ('Freed all objects. ');
 Dispose(`C, Done`);
end.

67.11.15 TCollection.Insert

Synopsis: Insert a new item in the collection at the end.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts `Item` in the collection. `TCollection` inserts this item at the end, but descendent objects may insert it at another place.

Errors: None.

See also: `TCollection.AtInsert` ([1186](#)), `TCollection.AtPut` ([1185](#))

67.11.16 TCollection.Delete

Synopsis: Delete an item from the collection, but does not destroy it.

Declaration: `procedure Delete(Item: Pointer)`

Visibility: default

Description: `Delete` deletes `Item` from the collection. It doesn't call the item's destructor, though. For this the `Free` (1180) call is provided.

Errors: If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

See also: `TCollection.AtDelete` (1183), `TCollection.Free` (1180)

Listing: ./examples/objectex/ex31.pp

```

Program ex31;

{ Program to demonstrate the TCollection.Delete method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  Writeln ('Added 100 Items. ');
  With C^ do
    While Count>0 do Delete(At(Count-1));
  Writeln ('Freed all objects ');
  Dispose(C, Done);
end.
```

67.11.17 TCollection.AtFree

Synopsis: Free an item at the indicates position, calling it's destructor.

Declaration: `procedure AtFree(Index: Sw_Integer)`

Visibility: default

Description: `AtFree` deletes the item at position `Index` in the collection, and calls the item's destructor if it is not `Nil`.

Errors: If `Index` isn't valid then `Error` (1185) is called with `CoIndexError`.

See also: `TCollection.Free` (1180), `TCollection.AtDelete` (1183)

Listing: ./examples/objectex/ex32.pp

```

Program ex32;

{ Program to demonstrate the TCollection.AtFree method }
```

Uses Objects, MyObject; { For TMyObject definition and registration }

```
Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteLn ('Added 100 Items');
  With C^ do
    While Count>0 do AtFree(Count-1);
  WriteLn ('Freed all objects. ');
  Dispose(C, Done);
end.
```

67.11.18 TCollection.FreeItem

Synopsis: Destroy a non-nil item.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: FreeItem calls the destructor of Item if it is not nil.

Remark This function is used internally by the TCollection object, and should not be called directly.

Errors: None.

See also: TCollection.Free ([1180](#)), TCollection.AtFree ([1182](#))

67.11.19 TCollection.AtDelete

Synopsis: Delete item at certain position.

Declaration: `procedure AtDelete(Index: Sw_Integer)`

Visibility: default

Description: AtDelete deletes the pointer at position Index in the collection. It doesn't call the object's destructor.

Errors: If Index isn't valid then Error ([1185](#)) is called with CoIndexError.

See also: TCollection.Delete ([1181](#))

Listing: ./examples/objectex/ex33.pp

```

Program ex33;

{ Program to demonstrate the TCollection.Delete method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteLn ('Added 100 Items. ');
  With C^ do
    While Count>0 do Delete(Count-1);
  WriteLn ('Freed all objects. ');
  Dispose(C, Done);
end.

```

67.11.20 TCollection.ForEach

Synopsis: Execute procedure for each item in the list.

Declaration: `procedure ForEach(Action: CodePointer)`

Visibility: default

Description: `ForEach` calls `Action` for each element in the collection, and passes the element as an argument to `Action`.

`Action` is a procedural type variable that accepts a pointer as an argument.

Errors: None.

See also: `TCollection.FirstThat` ([1177](#)), `TCollection.LastThat` ([1176](#))

Listing: `./examples/objectex/ex21.pp`

```

Program ex21;

{ Program to demonstrate the TCollection.ForEach method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

begin

```

```

    WriteLn ( 'Field : ', P^.GetField );
end;

begin
  C:=New( PCollection , Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(100-I);
      C^.Insert(M);
    end;
    WriteLn ( 'Inserted ', C^.Count, ' objects ');
  C^.ForEach( @PrintField );
  C^.FreeAll;
  Dispose(C, Done);
end.

```

67.11.21 TCollection.SetLimit

Synopsis: Set maximum number of elements in the collection.

Declaration: `procedure SetLimit(ALimit: Sw_Integer); Virtual`

Visibility: default

Description: `SetLimit` sets the maximum number of elements in the collection. `ALimit` must not be less than `Count`, and should not be larger than `MaxCollectionSize`

For an example, see Pack ([1178](#)).

Errors: None.

See also: `TCollection.Init` ([1173](#))

67.11.22 TCollection.Error

Synopsis: Set error code.

Declaration: `procedure Error(Code: Integer; Info: Integer); Virtual`

Visibility: default

Description: `Error` is called by the various `TCollection` methods in case of an error condition. The default behaviour is to make a call to `RunError` with an error of `212-Code`.

This method can be overridden by descendent objects to implement a different error-handling.

See also: `Abstract` ([1160](#))

67.11.23 TCollection.AtPut

Synopsis: Set collection item, overwriting an existing value.

Declaration: `procedure AtPut(Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtPut` sets the element at position `Index` in the collection to `Item`. Any previous value is overwritten.

For an example, see `Pack` (1178).

Errors: If `Index` isn't valid then `Error` (1185) is called with `CoIndexError`.

67.11.24 TCollection.AtInsert

Synopsis: Insert an element at a certain position in the collection.

Declaration: `procedure AtInsert(Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtInsert` inserts `Item` in the collection at position `Index`, shifting all elements by one position. In case the current limit is reached, the collection will try to expand with a call to `SetLimit`

Errors: If `Index` isn't valid then `Error` (1185) is called with `CoIndexError`. If the collection fails to expand, then `coOverflow` is passed to `Error`.

See also: `TCollection.Insert` (1181)

Listing: `./examples/objectex/ex34.pp`

Program `ex34`;

{ Program to demonstrate the TCollection.AtInsert method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
`M` : `PMMyObject`;
`I` : `Longint`;

Procedure `PrintField` (`Dummy`: `Pointer`; `P` : `PMMyObject`);

begin
`Writeln` ('Field : ', `P`^.`GetField`);
end;

begin
`Randomize`;
`C`:=`New`(`PCollection`, `Init`(120,10));
`Writeln` ('Inserting 100 records at random places.');

For `I`:=1 **to** 100 **do**
`begin`
`M`:=`New`(`PMMyObject`, `Init`);
`M`^.`SetField`(`I`-1);
If `I`=1 **then**
`C`^.`Insert`(`M`)
else
With `C` **do**
`AtInsert`(`Random`(`Count`), `M`);
end;
`Writeln` ('Values : ');
`C`^.`Foreach`(`@PrintField`);
`Dispose`(`C`, `Done`);
end.

67.11.25 TCollection.Store

Synopsis: Write collection to a stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by writing the current `Count`, `Limit` and `Delta` to the stream, and then writing each item to the stream.

The contents of the stream are then suitable for instantiating another collection with `Load` ([1173](#)).

For an example, see `TCollection.Load` ([1173](#)).

Errors: Errors returned are those by `TStream.Put` ([1219](#)).

See also: `TCollection.Load` ([1173](#)), `TCollection.PutItem` ([1187](#))

67.11.26 TCollection.PutItem

Synopsis: Put one item on the stream

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to stream `S`. This method is used internally by the `TCollection` object, and should not be called directly.

Errors: Errors are those returned by `TStream.Put` ([1219](#)).

See also: `Store` ([1187](#)), `GetItem` ([1176](#))

67.12 TDosStream

67.12.1 Description

`TDosStream` is a stream that stores its contents in a file. it overrides a couple of methods of `TStream` ([1214](#)) for this.

In addition to the fields inherited from `TStream` (see `TStream` ([1214](#))), there are some extra fields, that describe the file. (mainly the name and the OS file handle)

No buffering in memory is done when using `TDosStream`. All data are written directly to the file. For a stream that buffers in memory, see `TBufStream` ([1168](#)).

67.12.2 Method overview

Page	Method	Description
1188	<code>Close</code>	Close the file.
1188	<code>Done</code>	Closes the file and cleans up the instance.
1188	<code>Init</code>	Instantiate a new instance of <code>TDosStream</code> .
1190	<code>Open</code>	Open the file stream
1191	<code>Read</code>	Read data from the stream to a buffer.
1189	<code>Seek</code>	Set file position.
1189	<code>Truncate</code>	Truncate the file on the current position.
1191	<code>Write</code>	Write data from a buffer to the stream.

67.12.3 TDosStream.Init

Synopsis: Instantiate a new instance of TDosStream.

Declaration: `constructor Init (FileName: FNameStr; Mode: Word)`

Visibility: default

Description: `Init` instantiates an instance of `TDosStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

stCreateCreates a new file.

stOpenReadRead access only.

stOpenWriteWrite access only.

stOpenRead and write access.

For an example, see `TDosStream.Truncate` ([1189](#)).

Errors: On error, `Status` (??) is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Done` ([1188](#))

67.12.4 TDosStream.Done

Synopsis: Closes the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` closes the file if it was open and cleans up the instance of `TDosStream`.
for an example, see e.g. `TDosStream.Truncate` ([1189](#)).

Errors: None.

See also: `TDosStream.Init` ([1188](#)), `TDosStream.Close` ([1188](#))

67.12.5 TDosStream.Close

Synopsis: Close the file.

Declaration: `procedure Close; Virtual`

Visibility: default

Description: `Close` closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` ([1188](#)) it does not clean up the instance of `TDosStream`

For an example, see `TDosStream.Open` ([1190](#)).

Errors: None.

See also: `TStream.Close` ([1218](#)), `TDosStream.Init` ([1188](#)), `TDosStream.Done` ([1188](#))

67.12.6 TDosStream.Truncate

Synopsis: Truncate the file on the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: `default`

Description: If the status of the stream is `stOK`, then `Truncate` tries to truncate the stream size to the current file position.

Errors: If an error occurs, the stream's status is set to `stError` and `ErrorInfo` is set to the OS error code.

See also: `TStream.Truncate` ([1219](#)), `TStream.GetSize` ([1216](#))

Listing: `./examples/objectex/ex16.pp`

Program `ex16;`

{ Program to demonstrate the TStream.Truncate method }

Uses `Objects;`

Var `L : String;`
 `P : PString;`
 `S : PDosStream; { Only one with Truncate implemented. }`

begin

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PDosStream, Init('test.dat', stcreate));
Writeln ('Writing "', L, '" to stream with handle ', S^.Handle);
S^.WriteStr(@L);
S^.WriteStr(@L);
{ Close calls flush first }
S^.Close;
S^.Open (stOpen);
Writeln ('Size of stream is : ', S^.GetSize);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
Writeln ('Read "', L, '" from stream with handle ', S^.Handle);
S^.Truncate;
Writeln ('Truncated stream. Size is : ', S^.GetSize);
S^.Close;
Dispose (S, Done);

```

end.

67.12.7 TDosStream.Seek

Synopsis: Set file position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: `default`

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` ([1220](#)), `TStream.GetPos` ([1216](#))

Listing: `./examples/objectex/ex17.pp`

Program `ex17`;

{ Program to demonstrate the TStream.Seek method }

Uses `Objects`;

Var `L : String`;
 `Marker : Word`;
 `P : PString`;
 `S : PDosStream`;

begin
 `L := 'Some constant string';`
 { Buffer size of 100 }
 `S := New(PDosStream, Init('test.dat', stcreate));`
 `WriteLn ('Writing "', L, '" to stream.');`
 `S^.WriteStr(@L);`
 `Marker := S^.GetPos;`
 `WriteLn ('Set marker at ', Marker);`
 `L := 'Some other constant String';`
 `WriteLn ('Writing "', L, '" to stream.');`
 `S^.WriteStr(@L);`
 `S^.Close;`
 `S^.Open(stOpenRead);`
 `WriteLn ('Size of stream is : ', S^.GetSize);`
 `WriteLn ('Seeking to marker');`
 `S^.Seek(Marker);`
 `P := S^.ReadStr;`
 `L := P^;`
 `DisposeStr(P);`
 `WriteLn ('Read "', L, '" from stream.');`
 `S^.Close;`
 `Dispose(S, Done);`
end.

67.12.8 TDosStream.Open

Synopsis: Open the file stream

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` ([1188](#)) call.

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` ([1218](#)), `TDosStream.Close` ([1188](#))

Listing: ./examples/objectex/ex14.pp

```

Program ex14;

{ Program to demonstrate the TStream.Close method }

Uses Objects;

Var L : String;
    P : PString;
    S : PDosStream; { Only one with Close implemented. }

begin
    L:= 'Some constant string';
    S:=New(PDosStream, Init('test.dat', stcreate));
    WriteIn ('Writing "', L, '" to stream with handle ', S^.Handle);
    S^.WriteStr(@L);
    S^.Close;
    WriteIn ('Closed stream. File handle is ', S^.Handle);
    S^.Open (stOpenRead);
    P:=S^.ReadStr;
    L:=P^;
    DisposeStr(P);
    WriteIn ('Read "', L, '" from stream with handle ', S^.Handle);
    S^.Close;
    Dispose (S, Done);
end.

```

67.12.9 TDosStream.Read

Synopsis: Read data from the stream to a buffer.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is stOK then Read will read Count bytes from the stream and place them in Buf.

For an example, see TStream.Read ([1221](#)).

Errors: In case of an error, Status is set to StReadError, and ErrorInfo gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: TStream.Read ([1221](#)), TDosStream.Write ([1191](#))

67.12.10 TDosStream.Write

Synopsis: Write data from a buffer to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is stOK then Write will write Count bytes from Buf and place them in the stream.

For an example, see TStream.Read ([1221](#)).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` ([1221](#)), `TDosStream.Read` ([1191](#))

67.13 TMemoryStream

67.13.1 Description

The `TMemoryStream` object implements a stream that stores it's data in memory. The data is stored on the heap, with the possibility to specify the maximum amount of data, and the size of the memory blocks being used.

See also: `TStream` ([1214](#))

67.13.2 Method overview

Page	Method	Description
1192	<code>Done</code>	Clean up memory and destroy the object instance.
1192	<code>Init</code>	Initialize memory stream, reserves memory for stream data.
1193	<code>Read</code>	Read data from the stream to a location in memory.
1193	<code>Truncate</code>	Set the stream size to the current position.
1194	<code>Write</code>	Write data to the stream.

67.13.3 TMemoryStream.Init

Synopsis: Initialize memory stream, reserves memory for stream data.

Declaration: constructor `Init(ALimit: LongInt; ABlockSize: Word)`

Visibility: default

Description: `Init` instantiates a new `TMemoryStream` object. The `memorystreamobject` will initially allocate at least `ALimit` bytes memory, divided into memory blocks of size `ABlockSize`. The number of blocks needed to get to `ALimit` bytes is rounded up.

By default, the number of blocks is 1, and the size of a block is 8192. This is selected if you specify 0 as the `blocksize`.

For an example, see e.g `TStream.CopyFrom` ([1222](#)).

Errors: If the stream cannot allocate the initial memory needed for the memory blocks, then the stream's status is set to `stInitError`.

See also: `TMemoryStream.Done` ([1192](#))

67.13.4 TMemoryStream.Done

Synopsis: Clean up memory and destroy the object instance.

Declaration: destructor `Done; Virtual`

Visibility: default

Description: `Done` releases the memory blocks used by the stream, and then cleans up the memory used by the stream object itself.

For an example, see e.g `TStream.CopyFrom` ([1222](#)).

Errors: None.

See also: `TMemoryStream.Init` ([1192](#))

67.13.5 TMemoryStream.Truncate

Synopsis: Set the stream size to the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: `Truncate` sets the size of the memory stream equal to the current position. It de-allocates any memory-blocks that are no longer needed, so that the new size of the stream is the current position in the stream, rounded up to the first multiple of the stream blocksize.

Errors: If an error occurs during memory de-allocation, the stream's status is set to `stError`

See also: `TStream.Truncate` ([1219](#))

Listing: `./examples/objectex/ex20.pp`

Program `ex20;`

{ Program to demonstrate the TMemoryStream.Truncate method }

Uses `Objects;`

Var `L : String;`
 `P : PString;`
 `S : PMemoryStream;`
 `I : Longint;`

begin
 `L := 'Some constant string';`
 { Buffer size of 100 }
 `S := New(PMemoryStream, Init(1000,100));`
 `Writeln ('Writing 100 times "',L,'" to stream.');`
 For `I := 1 to 100 do`
 `S^.WriteStr(@L);`
 `Writeln ('Finished.');`
 `S^.Seek(100);`
 `S^.Truncate;`
 `Writeln ('Truncated at byte 100.');`
 `Dispose (S,Done);`
 `Writeln ('Finished.');`
end.

67.13.6 TMemoryStream.Read

Synopsis: Read data from the stream to a location in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: `Read` reads `Count` bytes from the stream to `Buf`. It updates the position of the stream.

For an example, see `TStream.Read` ([1221](#)).

Errors: If there is not enough data available, no data is read, and the stream's status is set to `stReadError`.

See also: `TStream.Read` ([1221](#)), `TMemoryStream.Write` ([1194](#))

67.13.7 TMemoryStream.Write

Synopsis: Write data to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Write copies `Count` bytes from `Buf` to the stream. It updates the position of the stream.

If not enough memory is available to hold the extra `Count` bytes, then the stream will try to expand, by allocating as much blocks with size `BlkSize` (as specified in the constructor call `Init` ([1192](#))) as needed.

For an example, see `TStream.Read` ([1221](#)).

Errors: If the stream cannot allocate more memory, then the status is set to `stWriteError`

See also: `TStream.Write` ([1221](#)), `TMemoryStream.Read` ([1193](#))

67.14 TObject

67.14.1 Description

This type serves as the basic object for all other objects in the `Objects` unit.

67.14.2 Method overview

Page	Method	Description
1195	<code>Done</code>	Destroy an object.
1195	<code>Free</code>	Destroy an object and release all memory.
1194	<code>Init</code>	Construct (initialize) a new object
1195	<code>Is_Object</code>	Check whether a pointer points to an object.

67.14.3 TObject.Init

Synopsis: Construct (initialize) a new object

Declaration: `constructor Init`

Visibility: default

Description: Instantiates a new object of type `TObject`. It fills the instance up with `Zero` bytes.

For an example, see `Free` ([1195](#))

Errors: None.

See also: `TObject.Free` ([1195](#)), `TObject.Done` ([1195](#))

67.14.4 TObject.Free

Synopsis: Destroy an object and release all memory.

Declaration: `procedure Free`

Visibility: `default`

Description: `Free` calls the destructor of the object, and releases the memory occupied by the instance of the object.

Errors: No checking is performed to see whether `self` is `nil` and whether the object is indeed allocated on the heap.

See also: `TObject.Init` ([1194](#)), `TObject.Done` ([1195](#))

Listing: `./examples/objectex/ex7.pp`

```

program ex7;

  { Program to demonstrate the TObject.Free call }

Uses Objects;

Var O : PObject;

begin
  // Allocate memory for object.
  O:=New(PObject, Init);
  // Free memory of object.
  O^.free;
end.

```

67.14.5 TObject.Is_Object

Synopsis: Check whether a pointer points to an object.

Declaration: `function Is_Object(P: Pointer) : Boolean`

Visibility: `default`

Description: `Is_Object` returns `True` if the pointer `P` points to an instance of a `TObject` descendent, it returns `false` otherwise.

67.14.6 TObject.Done

Synopsis: Destroy an object.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done`, the destructor of `TObject` does nothing. It is mainly intended to be used in the `TObject.Free` ([1195](#)) method.

The destructor `Done` does not free the memory occupied by the object.

Errors: None.

See also: TObject.Free ([1195](#)), TObject.Init ([1194](#))

Listing: ./examples/objectex/ex8.pp

```

program ex8;

{ Program to demonstrate the TObject.Done call }

Uses Objects;

Var O : PObject;

begin
    // Allocate memory for object.
    O:=New(PObject, Init);
    O^.Done;
end.
```

67.15 TPoint

67.15.1 Description

Record describing a point in a 2 dimensional plane.

67.16 TRect

67.16.1 Description

Describes a rectangular region in a plane.

67.16.2 Method overview

Page	Method	Description
1201	Assign	Set rectangle corners.
1198	Contains	Determine if a point is inside the rectangle
1198	Copy	Copy cornerpoints from another rectangle.
1196	Empty	Is the surface of the rectangle zero
1197	Equals	Do the corners of the rectangles match
1201	Grow	Expand rectangle with certain size.
1199	Intersect	Reduce rectangle to intersection with another rectangle
1200	Move	Move rectangle along a vector.
1199	Union	Enlarges rectangle to encompass another rectangle.

67.16.3 TRect.Empty

Synopsis: Is the surface of the rectangle zero

Declaration: function Empty : Boolean

Visibility: default

Description: Empty returns True if the rectangle defined by the corner points A, B has zero or negative surface.

Errors: None.

See also: TRect.Equals ([1197](#)), TRect.Contains ([1198](#))

Listing: ./examples/objectex/ex1.pp

```

Program ex1;

{ Program to demonstrate TRect.Empty }

Uses objects;

Var ARect,BRect : TRect;
    P : TPoint;

begin
  With ARect.A do
    begin
      X:=10;
      Y:=10;
    end;
  With ARect.B do
    begin
      X:=20;
      Y:=20;
    end;
  { Offset B by (5,5) }
  With BRect.A do
    begin
      X:=15;
      Y:=15;
    end;
  With BRect.B do
    begin
      X:=25;
      Y:=25;
    end;
  { Point }
  With P do
    begin
      X:=15;
      Y:=15;
    end;
  Writeln ( 'A empty : ',ARect.Empty);
  Writeln ( 'B empty : ',BRect.Empty);
  Writeln ( 'A Equals B : ',ARect.Equals(BRect));
  Writeln ( 'A Contains (15,15) : ',ARect.Contains(P));
end.
```

67.16.4 TRect.Equals

Synopsis: Do the corners of the rectangles match

Declaration: `function Equals(R: TRect) : Boolean`

Visibility: default

Description: `Equals` returns `True` if the rectangle has the same corner points `A, B` as the rectangle `R`, and `False` otherwise.

For an example, see `TRect.Empty` (1196)

Errors: None.

See also: `TRect.Empty` (1196), `TRect.Contains` (1198)

67.16.5 TRect.Contains

Synopsis: Determine if a point is inside the rectangle

Declaration: `function Contains(P: TPoint) : Boolean`

Visibility: default

Description: `Contains` returns `True` if the point `P` is contained in the rectangle (including borders), `False` otherwise.

Errors: None.

See also: `TRect.Intersect` (1199), `TRect.Equals` (1197)

67.16.6 TRect.Copy

Synopsis: Copy cornerpoints from another rectangle.

Declaration: `procedure Copy(R: TRect)`

Visibility: default

Description: Assigns the rectangle `R` to the object. After the call to `Copy`, the rectangle `R` has been copied to the object that invoked `Copy`.

Errors: None.

See also: `TRect.Assign` (1201)

Listing: `./examples/objectex/ex2.pp`

Program `ex2`;

{ Program to demonstrate TRect.Copy }

Uses `objects`;

Var `ARect, BRect, CRect : TRect`;

begin

`ARect.Assign(10,10,20,20);`

`BRect.Assign(15,15,25,25);`

`CRect.Copy(ARect);`

If `ARect.Equals(CRect)` **Then**

Writeln ('ARect equals CRect')

Else

Writeln ('ARect does not equal CRect !');

end.

67.16.7 TRect.Union

Synopsis: Enlarges rectangle to encompass another rectangle.

Declaration: `procedure Union(R: TRect)`

Visibility: default

Description: `Union` enlarges the current rectangle so that it becomes the union of the current rectangle with the rectangle `R`.

Errors: None.

See also: `TRect.Intersect` ([1199](#))

Listing: `./examples/objectex/ex3.pp`

Program `ex3;`

{ Program to demonstrate TRect.Union }

Uses `objects;`

Var `ARect, BRect, CRect : TRect;`

begin

`ARect.Assign(10,10,20,20);`

`BRect.Assign(15,15,25,25);`

{ CRect is union of ARect and BRect }

`CRect.Assign(10,10,25,25);`

{ Calculate it explicitly }

`ARect.Union(BRect);`

If `ARect.Equals(CRect)` **Then**

`Writeln ('ARect equals CRect')`

Else

`Writeln ('ARect does not equal CRect !');`

end.

67.16.8 TRect.Intersect

Synopsis: Reduce rectangle to intersection with another rectangle

Declaration: `procedure Intersect(R: TRect)`

Visibility: default

Description: `Intersect` makes the intersection of the current rectangle with `R`. If the intersection is empty, then the rectangle is set to the empty rectangle at coordinate (0,0).

Errors: None.

See also: `TRect.Union` ([1199](#))

Listing: `./examples/objectex/ex4.pp`

```

Program ex4;

{ Program to demonstrate TRect.Intersect }

Uses objects;

Var ARect,BRect,CRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  { CRect is intersection of ARect and BRect }
  CRect.Assign(15,15,20,20);
  { Calculate it explicitly }
  ARect.Intersect(BRect);
  If ARect.Equals(CRect) Then
    Writeln ('ARect equals CRect')
  Else
    Writeln ('ARect does not equal CRect !');
  BRect.Assign(25,25,30,30);
  ARect.Intersect(BRect);
  If ARect.Empty Then
    Writeln ('ARect is empty');
end.

```

67.16.9 TRect.Move

Synopsis: Move rectangle along a vector.

Declaration: `procedure Move(ADX: Sw_Integer; ADY: Sw_Integer)`

Visibility: default

Description: `Move` moves the current rectangle along a vector with components (ADX, ADY). It adds ADX to the X-coordinate of both corner points, and ADY to both end points.

Errors: None.

See also: `TRect.Grow` ([1201](#))

Listing: ./examples/objectex/ex5.pp

```

Program ex5;

{ Program to demonstrate TRect.Move }

Uses objects;

Var ARect,BRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  ARect.Move(5,5);
  // Brect should be where new ARect is.
  BRect.Assign(15,15,25,25);

```

```

If ARect.Equals(BRect) Then
  Writeln ('ARect equals BRect')
Else
  Writeln ('ARect does not equal BRect !');
end.

```

67.16.10 TRect.Grow

Synopsis: Expand rectangle with certain size.

Declaration: `procedure Grow(ADX: Sw_Integer; ADY: Sw_Integer)`

Visibility: default

Description: `Grow` expands the rectangle with an amount `ADX` in the X direction (both on the left and right side of the rectangle, thus adding a length $2*ADX$ to the width of the rectangle), and an amount `ADY` in the Y direction (both on the top and the bottom side of the rectangle, adding a length $2*ADY$ to the height of the rectangle).

`ADX` and `ADY` can be negative. If the resulting rectangle is empty, it is set to the empty rectangle at `(0,0)`.

Errors: None.

See also: `TRect.Move` ([1200](#))

Listing: `./examples/objectex/ex6.pp`

Program `ex6`;

{ Program to demonstrate TRect.Grow }

Uses `objects`;

Var `ARect,BRect : TRect`;

begin

`ARect.Assign(10,10,20,20);`

`ARect.Grow(5,5);`

// Brect should be where new ARect is.

`BRect.Assign(5,5,25,25);`

If `ARect.Equals(BRect)` **Then**

`Writeln ('ARect equals BRect')`

Else

`Writeln ('ARect does not equal BRect !');`

end.

67.16.11 TRect.Assign

Synopsis: Set rectangle corners.

Declaration: `procedure Assign(XA: Sw_Integer; YA: Sw_Integer; XB: Sw_Integer; YB: Sw_Integer)`

Visibility: default

Description: Assign sets the corner points of the rectangle to (XA, YA) and (Xb, Yb).

For an example, see TRect.Copy ([1198](#)).

Errors: None.

See also: TRect.Copy ([1198](#))

67.17 TResourceCollection

67.17.1 Description

A TResourceCollection manages a collection of resource names. It stores the position and the size of a resource, as well as the name of the resource. It stores these items in records that look like this:

```
TYPE
  TResourceItem = packed RECORD
    Posn: LongInt;
    Size: LongInt;
    Key : String;
  End;
  PResourceItem = ^TResourceItem;
```

It overrides some methods of TStringCollection in order to accomplish this.

Remark Remark that the TResourceCollection manages the names of the resources and their associated positions and sizes, it doesn't manage the resources themselves.

67.17.2 Method overview

Page	Method	Description
1203	FreeItem	Release memory occupied by item.
1203	GetItem	Read an item from the stream.
1202	KeyOf	Return the key of an item in the collection.
1203	PutItem	Write an item to the stream.

67.17.3 TResourceCollection.KeyOf

Synopsis: Return the key of an item in the collection.

Declaration: function KeyOf(Item: Pointer) : Pointer; Virtual

Visibility: default

Description: KeyOf returns the key of an item in the collection. For resources, the key is a pointer to the string with the resource name.

Errors: None.

See also: TStringCollection.Compare ([1223](#))

67.17.4 TResourceCollection.GetItem

Synopsis: Read an item from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a resource item from the stream `S`. It reads the position, size and name from the stream, in that order. It DOES NOT read the resource itself from the stream.

The resulting item is not inserted in the collection. This call is mainly for internal use by the `TCollection.Load (1173)` method.

Errors: Errors returned are those by `TStream.Read (1221)`

See also: `TCollection.Load (1173)`, `TStream.Read (1221)`

67.17.5 TResourceCollection.FreeItem

Synopsis: Release memory occupied by item.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `FreeItem` releases the memory occupied by `Item`. It de-allocates the name, and then the resource item record.

It does NOT remove the item from the collection.

Errors: None.

See also: `TCollection.FreeItem (1183)`

67.17.6 TResourceCollection.PutItem

Synopsis: Write an item to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to the stream `S`. It does this by writing the position and size and name of the resource item to the stream.

This method is used primarily by the `Store (1187)` method.

Errors: Errors returned are those by `TStream.Write (1221)`.

See also: `TCollection.Store (1187)`

67.18 TResourceFile

67.18.1 Description

`TResourceFile (1203)` represents the resources in a binary file image.

67.18.2 Method overview

Page	Method	Description
1204	Count	Number of resources in the file
1206	Delete	Delete a resource from the file
1204	Done	Destroy the instance and remove it from memory.
1205	Flush	Writes the resources to the stream.
1205	Get	Return a resource by key name.
1204	Init	Instantiate a new instance.
1205	KeyAt	Return the key of the item at a certain position.
1206	Put	Set a resource by key name.
1205	SwitchTo	Write resources to a new stream.

67.18.3 TResourceFile.Init

Synopsis: Instantiate a new instance.

Declaration: `constructor Init (AStream: PStream)`

Visibility: default

Description: `Init` instantiates a new instance of a `TResourceFile` object. If `AStream` is not nil then it is considered as a stream describing an executable image on disk.

`Init` will try to position the stream on the start of the resources section, and read all resources from the stream.

Errors: None.

See also: `TResourceFile.Done` ([1204](#))

67.18.4 TResourceFile.Done

Synopsis: Destroy the instance and remove it from memory.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` cleans up the instance of the `TResourceFile` Object. If `Stream` was specified at initialization, then `Stream` is disposed of too.

Errors: None.

See also: `TResourceFile.Init` ([1204](#))

67.18.5 TResourceFile.Count

Synopsis: Number of resources in the file

Declaration: `function Count : Sw_Integer`

Visibility: default

Description: `Count` returns the number of resources. If no resources were read, zero is returned.

Errors: None.

See also: `TResourceFile.Init` ([1204](#))

67.18.6 TResourceFile.KeyAt

Synopsis: Return the key of the item at a certain position.

Declaration: `function KeyAt (I: Sw_Integer) : string`

Visibility: default

Description: `KeyAt` returns the key (the name) of the `I`-th resource.

Errors: In case `I` is invalid, `TCollection.Error` will be executed.

See also: `TResourceFile.Get` ([1205](#))

67.18.7 TResourceFile.Get

Synopsis: Return a resource by key name.

Declaration: `function Get (Key: string) : PObject`

Visibility: default

Description: `Get` returns a pointer to a instance of a resource identified by `Key`. If `Key` cannot be found in the list of resources, then `Nil` is returned.

Errors: Errors returned may be those by `TStream.Get`

67.18.8 TResourceFile.SwitchTo

Synopsis: Write resources to a new stream.

Declaration: `function SwitchTo (AStream: PStream; Pack: Boolean) : PStream`

Visibility: default

Description: `SwitchTo` switches to a new stream to hold the resources in. `AStream` will be the new stream after the call to `SwitchTo`.

If `Pack` is true, then all the known resources will be copied from the current stream to the new stream (`AStream`). If `Pack` is False, then only the current resource is copied.

The return value is the value of the original stream: `Stream`.

The `Modified` flag is set as a consequence of this call.

Errors: Errors returned can be those of `TStream.Read` ([1221](#)) and `TStream.Write` ([1221](#)).

See also: `TResourceFile.Flush` ([1205](#))

67.18.9 TResourceFile.Flush

Synopsis: Writes the resources to the stream.

Declaration: `procedure Flush`

Visibility: default

Description: If the `Modified` flag is set to `True`, then `Flush` writes the resources to the stream `Stream`. It sets the `Modified` flag to true after that.

Errors: Errors can be those by `TStream.Seek` ([1220](#)) and `TStream.Write` ([1221](#)).

See also: `TResourceFile.SwitchTo` ([1205](#))

67.18.10 TResourceFile.Delete

Synopsis: Delete a resource from the file

Declaration: `procedure Delete(Key: string)`

Visibility: `default`

Description: `Delete` deletes the resource identified by `Key` from the collection. It sets the `Modified` flag to `true`.

Errors: `None`.

See also: `TResourceFile.Flush` ([1205](#))

67.18.11 TResourceFile.Put

Synopsis: Set a resource by key name.

Declaration: `procedure Put(Item: PObject; Key: string)`

Visibility: `default`

Description: `Put` sets the resource identified by `Key` to `Item`. If no such resource exists, a new one is created. The item is written to the stream.

Errors: Errors returned may be those by `TStream.Put` ([1219](#)) and `TStream.Seek`

See also: `Get` ([1205](#))

67.19 TSortedCollection

67.19.1 Description

`TSortedCollection` is an abstract class, implementing a sorted collection. You should never use an instance of `TSortedCollection` directly, instead you should declare a descendent type, and override the `Compare` ([1208](#)) method.

Because the collection is ordered, `TSortedCollection` overrides some `TCollection` methods, to provide faster routines for lookup.

The `Compare` ([1208](#)) method decides how elements in the collection should be ordered. Since `TCollection` has no way of knowing how to order pointers, you must override the compare method.

Additionally, `TCollection` provides a means to filter out duplicates. if you set `Duplicates` to `False` (the default) then duplicates will not be allowed.

The example below defines a descendent of `TSortedCollection` which is used in the examples.

67.19.2 Method overview

Page	Method	Description
1208	Compare	Compare two items in the collection.
1208	IndexOf	Return index of an item in the collection.
1207	Init	Instantiates a new instance of a <code>TSortedCollection</code>
1210	Insert	Insert new item in collection.
1207	KeyOf	Return the key of an item
1207	Load	Instantiates a new instance of a <code>TSortedCollection</code> and loads it from stream.
1209	Search	Search for item with given key.
1211	Store	Write the collection to the stream.

67.19.3 TSortedCollection.Init

Synopsis: Instantiates a new instance of a `TSortedCollection`

Declaration: `constructor Init(ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` calls the inherited constructor (see `TCollection.Init` ([1173](#))) and sets the `Duplicates` flag to false.

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

Errors: None.

See also: `TSortedCollection.Load` ([1207](#)), `TCollection.Done` ([1174](#))

67.19.4 TSortedCollection.Load

Synopsis: Instantiates a new instance of a `TSortedCollection` and loads it from stream.

Declaration: `constructor Load(var S: TStream)`

Visibility: default

Description: `Load` calls the inherited constructor (see `TCollection.Load` ([1173](#))) and reads the `Duplicates` flag from the stream..

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

For an example, see `TCollection.Load` ([1173](#)).

Errors: None.

See also: `TSortedCollection.Init` ([1207](#)), `TCollection.Done` ([1174](#))

67.19.5 TSortedCollection.KeyOf

Synopsis: Return the key of an item

Declaration: `function KeyOf(Item: Pointer) : Pointer; Virtual`

Visibility: default

Description: `KeyOf` returns the key associated with `Item`. `TSortedCollection` returns the item itself as the key, descendent objects can override this method to calculate a (unique) key based on the item passed (such as hash values).

`Keys` are used to sort the objects, they are used to search and sort the items in the collection. If descendent types override this method then it allows possibly for faster search/sort methods based on keys rather than on the objects themselves.

Errors: None.

See also: `TSortedCollection.IndexOf` ([1208](#)), `TSortedCollection.Compare` ([1208](#))

67.19.6 `TSortedCollection.IndexOf`

Synopsis: Return index of an item in the collection.

Declaration: `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `IndexOf` returns the index of `Item` in the collection. It searches for the object based on it's key. If duplicates are allowed, then it returns the index of last object that matches `Item`.

In case `Item` is not found in the collection, -1 is returned.

For an example, see `TCollection.IndexOf` ([1175](#))

Errors: None.

See also: `TSortedCollection.Search` ([1209](#)), `TSortedCollection.Compare` ([1208](#))

67.19.7 `TSortedCollection.Compare`

Synopsis: Compare two items in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `Compare` is an abstract method that should be overridden by descendent objects in order to compare two items in the collection. This method is used in the `Search` ([1209](#)) method and in the `Insert` ([1210](#)) method to determine the ordering of the objects.

The function should compare the two keys of items and return the following function results:

Result < 0 If `Key1` is logically before `Key2` (`Key1 < Key2`)

Result = 0 If `Key1` and `Key2` are equal. (`Key1 = Key2`)

Result > 0 If `Key1` is logically after `Key2` (`Key1 > Key2`)

Errors: An 'abstract run-time error' will be generated if you call `TSortedCollection.Compare` directly.

See also: `TSortedCollection.IndexOf` ([1208](#)), `TSortedCollection.Search` ([1209](#))

Listing: `./examples/objectex/mysortc.pp`

Unit MySortC;

Interface

Uses Objects;

Type

```

PMySortedCollection = ^TMySortedCollection;
TMySortedCollection = Object(TSortedCollection)
    Function Compare (Key1,Key2 : Pointer): Sw_integer; virtual;
    end;

```

Implementation

Uses MyObject;

Function TMySortedCollection.Compare (Key1,Key2 : Pointer) :sw_integer;

begin

```

    Compare:=PMyobject(Key1)^.GetField - PMyObject(Key2)^.GetField;

```

end;

end.

67.19.8 TSortedCollection.Search

Synopsis: Search for item with given key.

Declaration: `function Search(Key: Pointer; var Index: Sw_Integer) : Boolean; Virtual`

Visibility: default

Description: Search looks for the item with key Key and returns the position of the item (if present) in the collection in Index.

Instead of a linear search as TCollection does, TSortedCollection uses a binary search based on the keys of the objects. It uses the Compare (1208) function to implement this search.

If the item is found, Search returns True, otherwise False is returned.

Errors: None.

See also: TCollection.IndexOf (1175)

Listing: ./examples/objectex/ex36.pp

Program ex36;

{ Program to demonstrate the TSortedCollection.Insert method }

Uses Objects, MyObject, MySortC;

{ For TMyObject, TMySortedCollection definition and registration }

Var C : PSortedCollection;

 M : PMyObject;

 I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

```

begin
  Writeln ( 'Field : ', P^.GetField );
end;

begin
  Randomize;
  C:=New( PMySortedCollection, Init(120,10));
  C^.Duplicates:=True;
  Writeln ( 'Inserting 100 records at random places.' );
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(Random(100));
      C^.Insert(M)
    end;
  M:=New(PMyObject, Init);
  Repeat;
    Write ( 'Value to search for (-1 stops) : ' );
    read ( I );
    If I<>-1 then
      begin
        M^.SetField(i);
        If Not C^.Search (M,I) then
          Writeln ( 'No such value found' )
        else
          begin
            Write ( 'Value ', PMyObject(C^.At(I))^ .GetField );
            Writeln ( ' present at position ', I );
          end;
        end;
      Until I=-1;
      Dispose (M, Done );
      Dispose (C, Done );
  end.

```

67.19.9 TSortedCollection.Insert

Synopsis: Insert new item in collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts an item in the collection at the correct position, such that the collection is ordered at all times. You should never use `Atinsert` (1186), since then the collection ordering is not guaranteed.

If `Item` is already present in the collection, and `Duplicates` is `False`, the item will not be inserted.

Errors: None.

See also: `TCollection.AtInsert` (1186)

Listing: `./examples/objectex/ex35.pp`

```

Program ex35;

{ Program to demonstrate the TSortedCollection.Insert method }

Uses Objects, MyObject, MySortC;
      { For TMyObject, TMySortedCollection definition and registration }

Var C : PSortedCollection;
      M : PMyObject;
      I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

begin
  WriteLn ( 'Field : ', P^.GetField );
end;

begin
  Randomize;
  C:=New( PMySortedCollection, Init(120,10));
  WriteLn ( 'Inserting 100 records at random places.' );
  For I:=1 to 100 do
    begin
      M:=New( PMyObject, Init );
      M^.SetField( Random(100));
      C^.Insert( M )
    end;
  WriteLn ( 'Values : ' );
  C^.Foreach( @PrintField );
  Dispose( C, Done );
end.

```

67.19.10 TSortedCollection.Store

Synopsis: Write the collection to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by calling the inherited `TCollection.Store` ([1187](#)), and then writing the `Duplicates` flag to the stream.

After a `Store`, the collection can be loaded from the stream with the constructor `Load` ([1207](#))

For an example, see `TCollection.Load` ([1173](#)).

Errors: Errors can be those of `TStream.Put` ([1219](#)).

See also: `TSortedCollection.Load` ([1207](#))

67.20 TStrCollection

67.20.1 Description

The `TStrCollection` object manages a sorted collection of null-terminated strings (pchar strings). To this end, it overrides the `Compare` (1208) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

67.20.2 Method overview

Page	Method	Description
1212	<code>Compare</code>	Compare two strings in the collection.
1213	<code>FreeItem</code>	Free null-terminated string from the collection.
1213	<code>GetItem</code>	Read a null-terminated string from the stream.
1213	<code>PutItem</code>	Write a null-terminated string to the stream.

67.20.3 TStrCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStrCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns

-1 if the first string is alphabetically earlier than the second string.

0 if the two strings are equal.

1 if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` (1208)

Listing: `./examples/objectex/ex38.pp`

Program `ex38;`

{ Program to demonstrate the TStrCollection.Compare method }

Uses `Objects, Strings;`

Var `C : PStrCollection;`

`S : String;`

`I : longint;`

`P : Pchar;`

begin

`Randomize;`

`C:=New(PStrCollection, Init(120,10));`

`C^.Duplicates:=True; { Duplicates allowed }`

`WriteLn('Inserting 100 records at random places.');`

For `I:=1 to 100 do`

`begin`

`Str(Random(100),S);`

```

S:= 'String with value '+S;
P:= StrAlloc (Length(S)+1);
C^.Insert(StrPCopy(P,S));
end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(I),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',I);
    Dispose(C,Done);
  end.

```

67.20.4 TStrCollection.GetItem

Synopsis: Read a null-terminated string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a null-terminated string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.StrRead` ([1215](#)).

See also: `TStrCollection.PutItem` ([1213](#))

67.20.5 TStrCollection.FreeItem

Synopsis: Free null-terminated string from the collection.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStrCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` ([1183](#))

67.20.6 TStrCollection.PutItem

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.StrWrite` ([1220](#)).

See also: `TStrCollection.GetItem` ([1213](#))

67.21 TStream

67.21.1 Description

The `TStream` object is the ancestor for all streaming objects, i.e. objects that have the capability to store and retrieve data.

It defines a number of methods that are common to all objects that implement streaming, many of them are virtual, and are only implemented in the descendent types.

Programs should not instantiate objects of type `TStream` directly, but instead instantiate a descendant type, such as `TDosStream`, `TMemoryStream`.

See also: `PStream` ([1159](#)), `TDosStream` ([1187](#)), `TMemoryStream` ([1192](#))

67.21.2 Method overview

Page	Method	Description
1218	<code>Close</code>	Close the stream
1222	<code>CopyFrom</code>	Copy data from another stream.
1220	<code>Error</code>	Set stream status
1219	<code>Flush</code>	Flush the stream data from the buffer, if any.
1214	<code>Get</code>	Read an object definition from the stream.
1216	<code>GetPos</code>	Return current position in the stream
1216	<code>GetSize</code>	Return the size of the stream.
1214	<code>Init</code>	Constructor for <code>TStream</code> instance
1218	<code>Open</code>	Open the stream
1219	<code>Put</code>	Write an object to the stream.
1221	<code>Read</code>	Read data from stream to buffer.
1217	<code>ReadStr</code>	Read a shortstring from the stream.
1218	<code>Reset</code>	Reset the stream
1220	<code>Seek</code>	Set stream position.
1215	<code>StrRead</code>	Read a null-terminated string from the stream.
1220	<code>StrWrite</code>	Write a null-terminated string to the stream.
1219	<code>Truncate</code>	Truncate the stream size on current position.
1221	<code>Write</code>	Write a number of bytes to the stream.
1220	<code>WriteStr</code>	Write a pascal string to the stream.

67.21.3 TStream.Init

Synopsis: Constructor for `TStream` instance

Declaration: `constructor Init`

Visibility: `default`

Description: `Init` initializes a `TStream` instance. Descendent streams should always call the inherited `Init`.

67.21.4 TStream.Get

Synopsis: Read an object definition from the stream.

Declaration: `function Get : PObject`

Visibility: `default`

Description: `Get` reads an object definition from a stream, and returns a pointer to an instance of this object.

Errors: On error, `TStream.Status` (??) is set, and `NIL` is returned.

See also: `TStream.Put` ([1219](#))

Listing: `./examples/objectex/ex9.pp`

Program `ex9`;

{ Program to demonstrate TStream.Get and TStream.Put }

Uses `Objects, MyObject`; *{ Definition and registration of TMyObject }*

Var `Obj : PMyObject`;
 `S : PStream`;

begin

```

Obj:=New(PMyObject, Init);
Obj^.SetField($1111);
WriteLn ('Field value : ', Obj^.GetField);
{ Since Stream is an abstract type, we instantiate a TMemoryStream }
S:=New(PMemoryStream, Init(100,10));
S^.Put(Obj);
WriteLn ('Disposing object');
S^.Seek(0);
Dispose(Obj, Done);
WriteLn ('Reading object');
Obj:=PMyObject(S^.Get);
WriteLn ('Field Value : ', Obj^.GetField);
Dispose(Obj, Done);

```

end.

67.21.5 TStream.StrRead

Synopsis: Read a null-terminated string from the stream.

Declaration: `function StrRead : PChar`

Visibility: `default`

Description: `StrRead` reads a string from the stream, allocates memory for it, and returns a pointer to a null-terminated copy of the string on the heap.

Errors: On error, `Nil` is returned.

See also: `TStream.StrWrite` ([1220](#)), `TStream.ReadStr` ([1217](#))

Listing: `./examples/objectex/ex10.pp`

Program `ex10`;

```

{
Program to demonstrate the TStream.StrRead TStream.StrWrite functions
}

```

Uses `objects`;

```

Var P : PChar;
      S : PStream;

begin
  P:= 'Constant Pchar string';
  Writeln ('Writing to stream : "',P,'"');
  S:=New(PMemoryStream, Init(100,10));
  S^.StrWrite(P);
  S^.Seek(0);
  P:= Nil;
  P:=S^.StrRead;
  Dispose (S,Done);
  Writeln ('Read from stream : "',P,'"');
  Freemem(P, Strlen(P)+1);
end.

```

67.21.6 TStream.GetPos

Synopsis: Return current position in the stream

Declaration: `function GetPos : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk`, `GetPos` returns the current position in the stream. Otherwise it returns `-1`

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` ([1220](#)), `TStream.GetSize` ([1216](#))

Listing: `./examples/objectex/ex11.pp`

```

Program ex11;

{ Program to demonstrate the TStream.GetPos function }

Uses objects;

Var L : String;
      S : PStream;

begin
  L:= 'Some kind of string';
  S:=New(PMemoryStream, Init(100,10));
  Writeln ('Stream position before write : ',S^.GetPos);
  S^.WriteStr(@L);
  Writeln ('Stream position after write : ',S^.GetPos);
  Dispose(S,Done);
end.

```

67.21.7 TStream.GetSize

Synopsis: Return the size of the stream.

Declaration: `function GetSize : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk` then `GetSize` returns the size of the stream, otherwise it returns `-1`.

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` ([1220](#)), `TStream.GetPos` ([1216](#))

Listing: `./examples/objectex/ex12.pp`

```
Program ex12;

{ Program to demonstrate the TStream.GetSize function }

Uses objects;

Var L : String;
    S : PStream;

begin
  L := 'Some kind of string';
  S := New(PMemoryStream, Init(100,10));
  WriteLn ('Stream size before write: ', S^.GetSize);
  S^.WriteStr(@L);
  WriteLn ('Stream size after write: ', S^.GetSize);
  Dispose(S, Done);
end.
```

67.21.8 TStream.ReadStr

Synopsis: Read a shortstring from the stream.

Declaration: `function ReadStr : PString`

Visibility: default

Description: `ReadStr` reads a string from the stream, copies it to the heap and returns a pointer to this copy. The string is saved as a pascal string, and hence is NOT null terminated.

Errors: On error (e.g. not enough memory), `Nil` is returned.

See also: `TStream.StrRead` ([1215](#))

Listing: `./examples/objectex/ex13.pp`

```
Program ex13;

{
  Program to demonstrate the TStream.ReadStr TStream.WriteStr functions
}

Uses objects;

Var P : PString;
    L : String;
    S : PStream;

begin
```

```

L:= 'Constant string line';
WriteIn ('Writing to stream : "',L,'"');
S:=New(PMemoryStream, Init(100,10));
S^.WriteStr(@L);
S^.Seek(0);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
DisPose (S,Done);
WriteIn ('Read from stream : "',L,'"');
end.

```

67.21.9 TStream.Open

Synopsis: Open the stream

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: `Open` is an abstract method, that should be overridden by descendent objects. Since opening a stream depends on the stream's type this is not surprising.

For an example, see `TDosStream.Open` ([1190](#)).

Errors: None.

See also: `TStream.Close` ([1218](#)), `TStream.Reset` ([1218](#))

67.21.10 TStream.Close

Synopsis: Close the stream

Declaration: `procedure Close; Virtual`

Visibility: default

Description: `Close` is an abstract method, that should be overridden by descendent objects. Since Closing a stream depends on the stream's type this is not surprising.

for an example, see `TDosStream.Open` ([1190](#)).

Errors: None.

See also: `TStream.Open` ([1218](#)), `TStream.Reset` ([1218](#))

67.21.11 TStream.Reset

Synopsis: Reset the stream

Declaration: `procedure Reset`

Visibility: default

Description: `Reset` sets the stream's status to 0, as well as the `ErrorInfo`

Errors: None.

See also: `TStream.Open` ([1218](#)), `TStream.Close` ([1218](#))

67.21.12 TStream.Flush

Synopsis: Flush the stream data from the buffer, if any.

Declaration: `procedure Flush; Virtual`

Visibility: default

Description: `Flush` is an abstract method that should be overridden by descendent objects. It serves to enable the programmer to tell streams that implement a buffer to clear the buffer.

for an example, see `TBufStream.Flush` ([1170](#)).

Errors: None.

See also: `TStream.Truncate` ([1219](#))

67.21.13 TStream.Truncate

Synopsis: Truncate the stream size on current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: `Truncate` is an abstract procedure that should be overridden by descendent objects. It serves to enable the programmer to truncate the size of the stream to the current file position.

For an example, see `TDosStream.Truncate` ([1189](#)).

Errors: None.

See also: `TStream.Seek` ([1220](#))

67.21.14 TStream.Put

Synopsis: Write an object to the stream.

Declaration: `procedure Put (P: PObject)`

Visibility: default

Description: `Put` writes the object pointed to by `P`. `P` should be non-nil. The object type must have been registered with `RegisterType` ([1165](#)).

After the object has been written, it can be read again with `Get` ([1214](#)).

For an example, see `TStream.Get` ([1214](#));

Errors: No check is done whether `P` is `Nil` or not. Passing `Nil` will cause a run-time error 216 to be generated. If the object has not been registered, the status of the stream will be set to `stPutError`.

See also: `TStream.Get` ([1214](#))

67.21.15 TStream.StrWrite

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure StrWrite(P: PChar)`

Visibility: default

Description: `StrWrite` writes the null-terminated string `P` to the stream. `P` can only be 65355 bytes long.

For an example, see `TStream.StrRead` ([1215](#)).

Errors: None.

See also: `TStream.WriteString` ([1220](#)), `TStream.StrRead` ([1215](#)), `TStream.ReadStr` ([1217](#))

67.21.16 TStream.WriteString

Synopsis: Write a pascal string to the stream.

Declaration: `procedure WriteStr(P: PString)`

Visibility: default

Description: `StrWrite` writes the pascal string pointed to by `P` to the stream.

For an example, see `TStream.ReadStr` ([1217](#)).

Errors: None.

See also: `TStream.StrWrite` ([1220](#)), `TStream.StrRead` ([1215](#)), `TStream.ReadStr` ([1217](#))

67.21.17 TStream.Seek

Synopsis: Set stream position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: `Seek` sets the position to `Pos`. This position is counted from the beginning, and is zero based. (i.e. `seek(0)` sets the position pointer on the first byte of the stream)

For an example, see `TDosStream.Seek` ([1189](#)).

Errors: If `Pos` is larger than the stream size, `Status` is set to `StSeekError`.

See also: `TStream.GetPos` ([1216](#)), `TStream.GetSize` ([1216](#))

67.21.18 TStream.Error

Synopsis: Set stream status

Declaration: `procedure Error(Code: Integer; Info: Integer); Virtual`

Visibility: default

Description: `Error` sets the stream's status to `Code` and `ErrorInfo` to `Info`. If the `StreamError` procedural variable is set, `Error` executes it, passing `Self` as an argument.

This method should not be called directly from a program. It is intended to be used in descendent objects.

Errors: None.

67.21.19 TStream.Read

Synopsis: Read data from stream to buffer.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Read is an abstract method that should be overridden by descendent objects.

Read reads Count bytes from the stream into Buf. It updates the position pointer, increasing it's value with Count. Buf must be large enough to contain Count bytes.

Errors: No checking is done to see if Buf is large enough to contain Count bytes.

See also: TStream.Write (1221), TStream.ReadStr (1217), TStream.StrRead (1215)

Listing: ./examples/objectex/ex18.pp

```

program ex18;

{ Program to demonstrate the TStream.Read method }

Uses Objects;

Var Buf1, Buf2 : Array[1..1000] of Byte;
    I : longint;
    S : PMemoryStream;

begin
    For I:=1 to 1000 do
        Buf1[I]:=Random(1000);
    Buf2:=Buf1;
    S:=New(PMemoryStream, Init(100,10));
    S^.Write(Buf1, SizeOf(Buf1));
    S^.Seek(0);
    For I:=1 to 1000 do
        Buf1[I]:=0;
    S^.Read(Buf1, SizeOf(Buf1));
    For I:=1 to 1000 do
        If Buf1[I]<>Buf2[I] then
            WriteLn('Buffer differs at position ',I);
    Dispose(S,Done);
end.

```

67.21.20 TStream.Write

Synopsis: Write a number of bytes to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Write is an abstract method that should be overridden by descendent objects.

Write writes Count bytes to the stream from Buf. It updates the position pointer, increasing it's value with Count.

For an example, see TStream.Read (1221).

Errors: No checking is done to see if Buf actually contains Count bytes.

See also: TStream.Read (1221), TStream.WriteString (1220), TStream.StrWrite (1220)

67.21.21 TStream.CopyFrom

Synopsis: Copy data from another stream.

Declaration: `procedure CopyFrom(var S: TStream; Count: LongInt)`

Visibility: default

Description: `CopyFrom` reads `Count` bytes from stream `S` and stores them in the current stream. It uses the `Read` (1221) method to read the data, and the `Write` (1221) method to write in the current stream.

Errors: None.

See also: `Read` (1221), `Write` (1221)

Listing: `./examples/objectex/ex19.pp`

Program `ex19;`

{ Program to demonstrate the TStream.CopyFrom function }

Uses `objects;`

Var `P : PString;`
 `L : String;`
 `S1,S2 : PStream;`

begin
 `L:= 'Constant string line';`
 `Writeln ('Writing to stream 1 : "',L,'"');`
 `S1:=New(PMemoryStream, Init(100,10));`
 `S2:=New(PMemoryStream, Init(100,10));`
 `S1^.WriteStr(@L);`
 `S1^.Seek(0);`
 `Writeln ('Copying contents of stream 1 to stream 2');`
 `S2^.Copyfrom(S1^,S1^.GetSize);`
 `S2^.Seek(0);`
 `P:=S2^.ReadStr;`
 `L:=P^;`
 `DisposeStr(P);`
 `Dispose (S1,Done);`
 `Dispose (S2,Done);`
 `Writeln ('Read from stream 2 : "',L,'"');`
end.

67.22 TStringCollection**67.22.1 Description**

The `TStringCollection` object manages a sorted collection of pascal strings. To this end, it overrides the `Compare` (1208) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

67.22.2 Method overview

Page	Method	Description
1223	Compare	Compare two strings in the collection.
1224	FreeItem	Dispose a string in the collection from memory.
1223	GetItem	Get string from the stream.
1224	PutItem	Write a string to the stream.

67.22.3 TStringCollection.GetItem

Synopsis: Get string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.ReadStr` ([1217](#)).

See also: `TStringCollection.PutItem` ([1224](#))

67.22.4 TStringCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStringCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns the following results:

-1 if the first string is alphabetically earlier than the second string.

0 if the two strings are equal.

1 if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` ([1208](#))

Listing: `./examples/objectex/ex37.pp`

```

Program ex37;

{ Program to demonstrate the TStringCollection.Compare method }

Uses Objects;

Var C : PStringCollection;
    S : String;
    I : longint;

begin
    Randomize;

```

```

C:=New(PStringCollection, Init(120,10));
C^.Duplicates:=True; { Duplicates allowed }
WriteLn ('Inserting 100 records at random places. ');
For I:=1 to 100 do
  begin
    Str(Random(100),S);
    S:='String with value '+S;
    C^.Insert(NewStr(S));
  end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(i),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',i);
Dispose(C,Done);
end.

```

67.22.5 TStringCollection.FreeItem

Synopsis: Dispose a string in the collection from memory.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStringCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` ([1183](#))

67.22.6 TStringCollection.PutItem

Synopsis: Write a string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.WriteString` ([1220](#)).

See also: `TStringCollection.GetItem` ([1223](#))

67.23 TStringList

67.23.1 Description

A `TStringList` object can be used to read a collection of strings stored in a stream. If you register this object with the `RegisterType` ([1165](#)) function, you cannot register the `TStrListMaker` object.

67.23.2 Method overview

Page	Method	Description
1225	Done	Clean up the instance
1225	Get	Return a string by key name
1225	Load	Load stringlist from stream.

67.23.3 TStringList.Load

Synopsis: Load stringlist from stream.

Declaration: `constructor Load(var S: TStream)`

Visibility: default

Description: The `Load` constructor reads the `TStringList` object from the stream `S`. It also reads the descriptions of the strings from the stream. The string descriptions are stored as an array of `TStrIndexrec` records, where each record describes a string on the stream. These records are kept in memory.

Errors: If an error occurs, a stream error is triggered.

See also: `TStringList.Done` ([1225](#))

67.23.4 TStringList.Done

Synopsis: Clean up the instance

Declaration: `destructor Done; Virtual`

Visibility: default

Description: The `Done` destructor frees the memory occupied by the string descriptions, and destroys the object.

Errors: None.

See also: `Load` ([1225](#)), `TObject.Done` ([1195](#))

67.23.5 TStringList.Get

Synopsis: Return a string by key name

Declaration: `function Get(Key: Sw_Word) : string`

Visibility: default

Description: `Get` reads the string with key `Key` from the list of strings on the stream, and returns this string. If there is no string with such a key, an empty string is returned.

Errors: If no string with key `Key` is found, an empty string is returned. A stream error may result if the stream doesn't contain the needed strings.

See also: `TStrListMaker.Put` ([1226](#))

67.24 TStrListMaker

67.24.1 Description

The `TStrListMaker` object can be used to generate a stream with strings, which can be read with the `TStringList` object. If you register this object with the `RegisterType` (1165) function, you cannot register the `TStringList` object.

67.24.2 Method overview

Page	Method	Description
1226	<code>Done</code>	Clean up the instance and free all related memory.
1226	<code>Init</code>	Instantiate a new instance of <code>TStrListMaker</code>
1226	<code>Put</code>	Add a new string to the list with associated key.
1227	<code>Store</code>	Write the strings to the stream.

67.24.3 TStrListMaker.Init

Synopsis: Instantiate a new instance of `TStrListMaker`

Declaration: `constructor Init (AStrSize: Sw_Word; AIndexSize: Sw_Word)`

Visibility: default

Description: The `Init` constructor creates a new instance of the `TstrListMaker` object. It allocates `AStrSize` bytes on the heap to hold all the strings you wish to store. It also allocates enough room for `AIndexSize` key description entries (of the type `TStrIndexrec`).

`AStrSize` must be large enough to contain all the strings you wish to store. If not enough memory is allocated, other memory will be overwritten. The same is true for `AIndexSize` : maximally `AIndexSize` strings can be written to the stream.

Errors: None.

See also: `TObject.Init` (1194), `TStrListMaker.Done` (1226)

67.24.4 TStrListMaker.Done

Synopsis: Clean up the instance and free all related memory.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: The `Done` destructor de-allocates the memory for the index description records and the string data, and then destroys the object.

Errors: None.

See also: `TObject.Done` (1195), `TStrListMaker.Init` (1226)

67.24.5 TStrListMaker.Put

Synopsis: Add a new string to the list with associated key.

Declaration: `procedure Put (Key: Sw_Word; S: string)`

Visibility: default

Description: `Put` adds the string `S` with key `Key` to the collection of strings. This action doesn't write the string to a stream. To write the strings to the stream, see the `Store` ([1227](#)) method.

Errors: None.

See also: `TStrListMaker.Store` ([1227](#))

67.24.6 TStrListMaker.Store

Synopsis: Write the strings to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection of strings to the stream `S`. The collection can then be read with the `TStringList` object.

Errors: A stream error may occur when writing the strings to the stream.

See also: `TStringList.Load` ([1225](#)), `TStrListMaker.Put` ([1226](#))

67.25 TUnSortedStrCollection

67.25.1 Description

The `TUnSortedStrCollection` object manages an unsorted list of strings. To this end, it overrides the `TSortedCollection.Insert` ([1210](#)) method to add strings at the end of the collection, rather than in the alphabetically correct position.

Take care, the `Search` ([1209](#)) and `IndexOf` ([1175](#)) methods will not work on an unsorted string collection.

67.25.2 Method overview

Page	Method	Description
1227	<code>Insert</code>	Insert a new string in the collection.

67.25.3 TUnSortedStrCollection.Insert

Synopsis: Insert a new string in the collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts a string at the end of the collection, instead of on its alphabetical place, resulting in an unsorted collection of strings.

Errors: None.

See also: `TCollection.Insert` ([1181](#))

Listing: `./examples/objectex/ex39.pp`

```
Program ex39;  
  
{ Program to demonstrate the TUnsortedStrCollection.Insert method }  
  
Uses Objects, Strings;  
  
Var C : PUnsortedStrCollection;  
      S : String;  
      I : longint;  
      P : Pchar;  
  
begin  
  Randomize;  
  C:=New(PUnsortedStrCollection, Init(120,10));  
  Writeln ('Inserting 100 records at random places. ');  
  For I:=1 to 100 do  
    begin  
      Str(Random(100),S);  
      S:='String with value '+S;  
      C^.Insert(NewStr(S));  
    end;  
  For I:=0 to 99 do  
    Writeln (I:2, ': ', PString(C^.At(i))^ );  
  Dispose(C,Done);  
end.
```

Chapter 68

Reference for unit 'objpas'

68.1 Used units

Table 68.1: Used units by unit 'objpas'

Name	Page
System	1339

68.2 Overview

The `objpas` unit is meant for compatibility with Object Pascal as implemented by Delphi. The unit is loaded automatically by the Free Pascal compiler whenever the `Delphi` or `objfpc` mode is entered, either through the command line switches `-Sd` or `-Sh` or with the `{ $MODE DELPHI }` or `{ $MODE OBJFPC }` directives.

It redefines some basic pascal types, introduces some functions for compatibility with Delphi's system unit, and introduces some methods for the management of the resource string tables.

68.3 Constants, types and variables

68.3.1 Constants

`MaxInt = MaxLongint`

Maximum value for Integer ([1230](#)) type.

68.3.2 Types

`FixedInt = Int32`

`FixedInt` is provided for Delphi compatibility.

`FixedUInt = UInt32`

FixedUInt is provided for Delphi compatibility.

Integer = LongInt

In OBJPAS mode and in DELPHI mode, an Integer has a size of 32 bit. In TP or regular FPC mode, an integer is 16 bit.

IntegerArray = Array[0..\$effffff] of Integer

Generic array of integer (1230)

PInteger = ^Integer

Pointer to Integer (1230) type.

PIntegerArray = ^IntegerArray

Pointer to TIntegerArray (1230) type.

PointerArray = Array[0..512*1024*1024-2] of Pointer

Generic Array of pointers.

PPointerArray = ^PointerArray

Pointer to PointerArray (1230)

PString = PAnsiString

Pointer to ansistring type.

TEndian = (Little, Big)

Table 68.2: Enumeration values for type TEndian

Value	Explanation
Big	Big endian byte order
Little	Little endian byte order

TEndian describes the endianness of a computer architecture.

TIntegerArray = IntegerArray

Alias for IntegerArray (1230)

TPointerArray = PointerArray

Alias for PointerArray (1230)

Chapter 69

Reference for unit 'ports'

69.1 Used units

Table 69.1: Used units by unit 'ports'

Name	Page
System	1339

69.2 Overview

The ports unit implements the `port` constructs found in Turbo Pascal. It uses classes and default array properties to do this.

The unit exists on Linux, OS/2 and Dos. It is implemented only for compatibility with Turbo Pascal. Its usage is discouraged, because using ports is not portable programming, and the operating system may not even allow it (for instance Windows).

Under Linux, your program must be run as root, or the `IOPerm` call must be set in order to set appropriate permissions on the port access.

69.3 Constants, types and variables

69.3.1 Variables

```
port : tport
```

Default instance of type `TPort` ([1232](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
port[221]:=12;
```

Will result in the integer 12 being written to port 221, if port is defined as a variable of type `tport`

```
portb : tport
```


Default instance of type `TPort` ([1232](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portb[221]:=12;
```

Will result in the byte 12 being written to port 221, if port is defined as a variable of type `tport`

```
portl : tportl
```

Default instance of type `TPortL` ([1233](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portl[221]:=12;
```

Will result in the longint 12 being written to port 221, if port is defined as a variable of type `tport`

```
portw : tportw
```

Default instance of type `TPortW` ([1233](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portw[221]:=12;
```

Will result in the word 12 being written to port 221, if port is defined as a variable of type `tport`

69.4 tport

69.4.1 Description

The `TPort` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

See also: `port` ([1231](#)), `TPortW` ([1233](#)), `TPortL` ([1233](#))

69.4.2 Property overview

Page	Properties	Access	Description
1232	pp	rw	Access integer-sized port by port number

69.4.3 tport.pp

Synopsis: Access integer-sized port by port number

Declaration: `Property pp[w: Word]: Byte; default`

Visibility: `public`

Access: `Read,Write`

Description: Access integer-sized port by port number

69.5 tporth

69.5.1 Description

The `TPorth` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

See also: `portw` ([1232](#)), `TPort` ([1232](#)), `TPorth` ([1233](#))

69.5.2 Property overview

Page	Properties	Access	Description
1233	pp	rw	Access Longint-sized port by port number

69.5.3 tporth.pp

Synopsis: Access Longint-sized port by port number

Declaration: `Property pp[w: Word]: LongInt; default`

Visibility: public

Access: Read,Write

Description: Access Longint-sized port by port number

69.6 portw

69.6.1 Description

The `TPortW` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

See also: `portw` ([1232](#)), `TPort` ([1232](#)), `TPorth` ([1233](#))

69.6.2 Property overview

Page	Properties	Access	Description
1233	pp	rw	Access word-sized port by port number

69.6.3 portw.pp

Synopsis: Access word-sized port by port number

Declaration: `Property pp[w: Word]: Word; default`

Visibility: public

Access: Read,Write

Description: Access word-sized port by port number

Chapter 70

Reference for unit 'printer'

70.1 Used units

Table 70.1: Used units by unit 'printer'

Name	Page
System	1339

70.2 Overview

This chapter describes the `printer` unit for Free Pascal. It was written for DOS by Florian Klaempfl, and it was written for Linux by Michael Van Canneyt, and has been ported to Windows and OS/2 as well. Its basic functionality is the same for all supported systems, although there are minor differences on Linux and UNIX.

70.3 Constants, types and variables

70.3.1 Variables

`Lst` : `text`

`Lst` is the standard printing device.

On Linux, `Lst` is set up using `AssignLst('/tmp/PID.lst')`.

70.4 Procedures and functions

70.4.1 AssignLst

Synopsis: Assign text file to printing device

Declaration: `procedure AssignLst (var F: text; ToFile: string)`

Visibility: default

Description: `AssignLst` assigns to `F` a printing device - *UNIX only*. `ToFile` is a string with the following form:

- `'|filename options'`: This sets up a pipe with the program filename, with the given options, such as in the `popen()` call.
- `'filename'`: Prints to file filename. Filename can contain the string 'PID' (No Quotes), which will be replaced by the PID of your program. When closing `lst`, the file will be sent to `lpr` and deleted. (`lpr` should be in `PATH`)
- `{'filename|'}`: Same as previous, only the file is *not* sent to `lpr`, nor is it deleted. (useful for opening `/dev/printer` or for later printing)

See also: `lst` ([1234](#))

Listing: `./examples/printex/printex.pp`

```

program testprn;

uses printer;

var i : integer;
    f : text;

begin
  writeln ('Test of printer unit');
  writeln ('Writing to lst...');
  for i:=1 to 80 do writeln (lst, 'This is line ', i, '.' #13);
  close (lst);
  writeln ('Done. ');
  { $ifdef Unix }
  writeln ('Writing to pipe...');
  assignlst (f, '|/usr/bin/lpr -m');
  rewrite (f);
  for i:=1 to 80 do writeln (f, 'This is line ', i, '.' #13);
  close (f);
  writeln ('Done. ')
  { $endif }
end.

```

70.4.2 InitPrinter

Synopsis: Initialize the printer

Declaration: `procedure InitPrinter(const PrinterName: string)`

Visibility: default

Description: Initialize the printer

70.4.3 IsLstAvailable

Synopsis: Determine whether printer is available.

Declaration: `function IsLstAvailable : Boolean`

Visibility: default

Description: Determine whether printer is available.

Chapter 71

Reference for unit 'sharemem'

71.1 Used units

Table 71.1: Used units by unit 'sharemem'

Name	Page
System	1339

71.2 Overview

`sharemem` implements a shared memory manager. Including this unit will replace the standard memory manager with a memory manager which uses shared memory. This means the memory allocated by this unit can be managed by a program and a DLL if they both use the shared memory manager: it allows, amongst other things, to pass ansistrings or Unicode strings from a program to a DLL and vice versa.

This unit does not implement any routines: all actions to replace the memory manager are performed in the initialization section of the unit. The unit should be placed as the first unit in a program or DLL's uses section, memory corruption may occur if the unit is not placed first.

This unit requires the `fpcmemdll.dll` library to be distributed with both program and dll that use this unit. This DLL is distributed with the windows Free Pascal distribution.

Chapter 72

Reference for unit 'Sockets'

72.1 Used units

Table 72.1: Used units by unit 'Sockets'

Name	Page
BaseUnix	141
System	1339
unixtype	2127

72.2 Overview

This document describes the SOCKETS unit for Free Pascal. it was written for Linux by Michael Van Canneyt, and ported to Windows by Florian Klaempfl.

72.3 Constants, types and variables

72.3.1 Constants

`AF_ALG` = 38

Address family: Algorithm sockets

`AF_APPLETALK` = 5

Address family Appletalk DDP

`AF_ASH` = 18

Address family: Ash

`AF_ATMPVC` = 8

Address family: ATM PVCs

AF_ATMSVC = 20

Address family: ATM SVCs

AF_AX25 = 3

Address family Amateur Radio AX.25

AF_BLUETOOTH = 31

Address family: Bluetooth sockets

AF_BRIDGE = 7

Address family Multiprotocol bridge

AF_CAIF = 37

Address family: CAIF (Application CPU interface) sockets

AF_CAN = 29

Address family: CAN (Controller Area Network) sockets

AF_DECnet = 12

Address family: Reserved for DECnet project.

AF_ECONET = 19

Address family: Acorn Econet

AF_IB = 27

Address family: IB (Infiniband) sockets

AF_IEEE802154 = 36

Address family: IEEE802154 sockets

AF_INET = 2

Address family Internet IP Protocol

AF_INET6 = 10

Address family IP version 6

AF_IPX = 4

Address family Novell IPX

AF_IRDA = 23

Address family: IRDA sockets

AF_ISDN = 34

Address family: ?

AF_IUCV = 32

Address family: IUCV (Inter User Communication Vehicle) sockets

AF_KCM = 41

Address family: KCM (Kernel Connection Multiplexor) sockets

AF_KEY = 15

Address family: PF_KEY key management API

AF_LLC = 26

Address family: Linux LLC

AF_LOCAL = 1

Address family: Unix socket

AF_MAX = 45

Address family Maximum value

AF_MPLS = 28

Address family: MPLS (Multiprotocol Label Switching) sockets

AF_NETBEUI = 13

Address family: Reserved for 802.2LLC project

AF_NETLINK = 16

Address family: ?

AF_NETROM = 6

Address family Amateur radio NetROM

AF_NFC = 39

Address family: NFC (Near Field Communication) sockets

AF_PACKET = 17

Address family: Packet family

AF_PHONET = 35

Address family: Phonet sockets

AF_PPPOX = 24

Address family: PPPoX sockets

AF_QIPCRTR = 42

Address family: QIPCRTR (Qualcomm IPC Router) sockets

AF_RDS = 21

Address Family: RDS (Reliable Datagram Sockets) sockets

AF_ROSE = 11

Address family: Amateur Radio X.25 PLP

AF_ROUTE = AF_NETLINK

Address family: Alias to emulate 4.4BSD.

AF_RXRPC = 33

Address family: RxRPC sockets

AF_SECURITY = 14

Address family: Security callback pseudo AF

AF_SMC = 43

Address family: SMC (Shared Memory Communication) sockets

AF_SNA = 22

Address family: Linux SNA project

AF_TIPC = 30

Address family: TIPC sockets

AF_UNIX = 1

Address family Unix domain sockets

`AF_UNSPEC = 0`

Address family Not specified

`AF_VSOCK = 40`

Address family: VSOCK (hypervisor) sockets

`AF_WANPIPE = 25`

Address family: Wanpipe API Sockets

`AF_X25 = 9`

Address family Reserved for X.25 project

`AF_XDP = 44`

Address family: XDP (Express Data Path) sockets

`EsockADDRINUSE = ESysEADDRINUSE`

`EsockADDRINUSE` is the error reported by `fpBind` ([1273](#)) when the socket is already in use.

`EsockEACCESS = ESysEAcces`

Access forbidden error

`EsockEBADF = EsysEBADF`

Alias: bad file descriptor

`EsockEFAULT = EsysEFAULT`

Alias: an error occurred

`EsockEINTR = EsysEINTR`

Alias : operation interrupted

`EsockEINVAL = EsysEINVAL`

Alias: Invalid value specified

`EsockEMFILE = ESysEmfile`

Error code ?

`EsockEMSGSIZE = ESysEMsgSize`

Wrong message size error

`EsockENOBUFS = ESysENoBufs`

No buffer space available error

`EsockENOTCONN = ESysENotConn`

Not connected error

`EsockENOTSOCK = ESysENotSock`

File descriptor is not a socket error

`EsockEPROTONOSUPPORT = ESysEProtoNoSupport`

Protocol not supported error

`EsockEWOULDBLOCK = ESysEWouldBlock`

Operation would block error

`INADDR_ANY = CARDINAL(0)`

A bitmask matching any IP address on the local machine.

`INADDR_NONE = CARDINAL($FFFFFFFF)`

A bitmask matching no valid IP address

`IPPROTO_AH = 51`

authentication header.

`IPPROTO_COMP = 108`

Compression Header Protocol.

`IPPROTO_DSTOPTS = 60`

IPv6 destination options.

`IPPROTO_EGP = 8`

Exterior Gateway Protocol.

`IPPROTO_ENCAP = 98`

Encapsulation Header.

`IPPROTO_ESP = 50`

encapsulating security payload.

IPPROTO_FRAGMENT = 44

IPv6 fragmentation header.

IPPROTO_GRE = 47

General Routing Encapsulation.

IPPROTO_HOPOPTS = 0

IPv6 Hop-by-Hop options.

IPPROTO_ICMP = 1

Internet Control Message Protocol.

IPPROTO_ICMPV6 = 58

ICMPv6.

IPPROTO_IDP = 22

XNS IDP protocol.

IPPROTO_IGMP = 2

Internet Group Management Protocol.

IPPROTO_IP = 0

Dummy protocol for TCP.

IPPROTO_IPIP = 4

IPIP tunnels (older KA9Q tunnels use 94).

IPPROTO_IPV6 = 41

IPv6 header.

IPPROTO_MAX = 255

Maximum value for IPPROTO options

IPPROTO_MTP = 92

Multicast Transport Protocol.

IPPROTO_NONE = 59

IPv6 no next header.

IPPROTO_PIM = 103

Protocol Independent Multicast.

IPPROTO_PUP = 12

PUP protocol.

IPPROTO_RAW = 255

Raw IP packets.

IPPROTO_ROUTING = 43

IPv6 routing header.

IPPROTO_RSVP = 46

Reservation Protocol.

IPPROTO_SCTP = 132

Stream Control Transmission Protocol.

IPPROTO_TCP = 6

Transmission Control Protocol.

IPPROTO_TP = 29

SO Transport Protocol Class 4.

IPPROTO_UDP = 17

User Datagram Protocol.

IPV6_ADDRFORM = 1

Change the IPV6 address into a different address family. Deprecated

IPV6_ADD_MEMBERSHIP = IPV6_JOIN_GROUP

Undocumented Getsockopt option ?

IPV6_AUTHHDR = 10

GetSockOpt/SetSockopt: Deliver authentication header messages

IPV6_CHECKSUM = 7

Undocumented Getsockopt option ?

IPV6_DROP_MEMBERSHIP = IPV6_LEAVE_GROUP

Undocumented Getsockopt option ?

IPV6_DSTOPTS = 4

Deliver destination option control messages

IPV6_HOPLIMIT = 8

Deliver an integer containing the HOP count

IPV6_HOPOPTS = 3

Deliver hop option control messages

IPV6_IPSEC_POLICY = 34

Undocumented Getsockopt option ?

IPV6_JOIN_ANYCAST = 27

Undocumented Getsockopt option ?

IPV6_JOIN_GROUP = 20

GetSockOpt/SetSockopt: Control membership (join group) in multicast groups

IPV6_LEAVE_ANYCAST = 28

Undocumented Getsockopt option ?

IPV6_LEAVE_GROUP = 21

GetSockOpt/SetSockopt: Control membership (leave group) in multicast groups

IPV6_MTU = 24

GetSockOpt/SetSockopt: Get/Set the MTU for the socket

IPV6_MTU_DISCOVER = 23

GetSockOpt/SetSockopt: Get/Set Control path MTU Discovery on the socket

IPV6_MULTICAST_HOPS = 18

GetSockOpt/SetSockopt: Get/Set the multicast hop limit.

IPV6_MULTICAST_IF = 17

GetSockOpt/SetSockopt: Get/Set device for multicast packages on the socket.

IPV6_MULTICAST_LOOP = 19

GetSockOpt/SetSockopt: Control whether socket sees multicast packages that it has sent itself

IPV6_NEXTHOP = 9

sendmsg: set next hop for IPV6 datagram

IPV6_PKTINFO = 2

Change delivery options for incoming IPV6 datagrams

IPV6_PKTOPTIONS = 6

Undocumented Getsockopt option ?

IPV6_PMTUDISC_DO = 2

Always DF.

IPV6_PMTUDISC_DONT = 0

Never send DF frames.

IPV6_PMTUDISC_WANT = 1

Use per route hints.

IPV6_RECVERR = 25

GetSockOpt/SetSockopt: Control receiving of asynchronous error options

IPV6_ROUTER_ALERT = 22

GetSockOpt/SetSockopt: Get/Set Pass all forwarded packets containing router alert option

IPV6_RTHDR = 5

Deliver routing header control messages

IPV6_RTHDR_LOOSE = 0

Hop doesn't need to be neighbour.

IPV6_RTHDR_STRICT = 1

Hop must be a neighbour.

IPV6_RTHDR_TYPE_0 = 0

IPv6 Routing header type 0.

IPV6_RXDSTOPTS = IPV6_DSTOPTS

Undocumented Getsockopt option ?

IPV6_RXHOPOPTS = IPV6_HOPOPTS

Undocumented Getsockopt option ?

IPV6_RXSRCRT = IPV6_RTHDR

Undocumented Getsockopt option ?

IPV6_UNICAST_HOPS = 16

GetSockOpt/SetSockopt: Get/Set unicast hop limit

IPV6_V6ONLY = 26

GetSockOpt/SetSockopt: Handle IPV6 connections only

IPV6_XFRM_POLICY = 35

Undocumented Getsockopt option ?

IPX_TYPE = 1

IPX type

IP_ADD_MEMBERSHIP = 35

add an IP group membership

IP_ADD_SOURCE_MEMBERSHIP = 39

join source group

IP_BLOCK_SOURCE = 38

block data from source

IP_DEFAULT_MULTICAST_LOOP = 1

Undocumented ?

IP_DEFAULT_MULTICAST_TTL = 1

Undocumented ?

IP_DROP_MEMBERSHIP = 36

drop an IP group membership

IP_DROP_SOURCE_MEMBERSHIP = 40

leave source group

IP_HDRINCL = 3

Header is included with data.

IP_MAX_MEMBERSHIPS = 20

Maximum group memberships for multicast messages

IP_MSFILTER = 41

Undocumented ?

IP_MTU_DISCOVER = 10

Undocumented ?

IP_MULTICAST_IF = 32

set/get IP multicast i/f

IP_MULTICAST_LOOP = 34

set/get IP multicast loopback

IP_MULTICAST_TTL = 33

set/get IP multicast ttl

IP_OPTIONS = 4

IP per-packet options.

IP_PKTINFO = 8

Undocumented ?

IP_PKTOPTIONS = 9

Undocumented ?

IP_PMTUDISC = 10

Undocumented ?

IP_PMTUDISC_DO = 2

Always DF.

IP_PMTUDISC_DONT = 0

Never send DF frames.

IP_PMTUDISC_WANT = 1

Use per route hints.

IP_RECVERR = 11

Undocumented ?

IP_RECVOPTS = 6

Receive all IP options w/datagram.

IP_RECVRETOPTS = IP_RETOPTS

Receive IP options for response.

IP_RECVTOS = 13

Undocumented ?

IP_RECVTTL = 12

Undocumented ?

IP_RETOPTS = 7

Set/get IP per-packet options.

IP_ROUTER_ALERT = 5

Undocumented ?

IP_TOS = 1

IP type of service and precedence.

IP_TTL = 2

IP time to live.

IP_UNBLOCK_SOURCE = 37

unblock data from source

MCAST_BLOCK_SOURCE = 43

block from given group

MCAST_EXCLUDE = 0

Undocumented ?

MCAST_INCLUDE = 1

Undocumented ?

MCAST_JOIN_GROUP = 42

join any-source group

MCAST_JOIN_SOURCE_GROUP = 46

join source-spec group

MCAST_LEAVE_GROUP = 45

leave any-source group

MCAST_LEAVE_SOURCE_GROUP = 47

leave source-spec group

MCAST_MSFILTER = 48

Undocumented ?

MCAST_UNBLOCK_SOURCE = 44

unblock from given group

MSG_BATCH = \$00040000

sendmmsg: more messages coming

MSG_CMSG_CLOEXEC = \$40000000

Set close_on_exec for file descriptor received through SCM_RIGHTS

MSG_CMSG_COMPAT = \$0

This message needs 32 bit fixups

MSG_CONFIRM = \$00000800

Send flags: Conform connection

MSG_CTRUNC = \$00000008

Receive flags: Control Data was discarded (buffer too small)

MSG_DONTROUTE = \$00000004

Send flags: don't use gateway

MSG_DONTWAIT = \$00000040

Receive flags: Non-blocking operation request.

MSG_EOF = MSG_FIN

Alias for MSG_FIN

MSG_EOR = \$00000080

Receive flags: End of record

MSG_ERRQUEUE = \$00002000

Receive flags: ?

MSG_FASTOPEN = \$20000000

Send data in TCP SYN

MSG_FIN = \$00000200

Receive flags: ?

MSG_MORE = \$00008000

Receive flags: ?

MSG_NOSIGNAL = \$00004000

Receive flags: Suppress SIG_PIPE signal.

MSG_NO_SHARED_FRAGS = \$00080000

sendpage internal : page frags are not shared

MSG_OOB = \$00000001

Receive flags: receive out-of-band data.

MSG_PEEK = \$00000002

Receive flags: peek at data, don't remove from buffer.

MSG_PROBE = MSG_PROXY

Do not send. Only probe path f.e. for MTU

MSG_PROXY = \$00000010

Receive flags: ?

MSG_RST = \$00001000

Receive flags: ?

MSG_SENDPAGE_DECRYPTED = \$00100000

sendpage() internal : page may carry plain text and require encryption

MSG_SENDPAGE_NOPOLICY = \$00010000

sendpage internal : do not apply policy

MSG_SENDPAGE_NOTLAST = \$00020000

sendpage internal : not the last page

MSG_SYN = \$00000400

Receive flags: ?

MSG_TRUNC = \$00000020

Receive flags: packet Data was discarded (buffer too small)

MSG_TRYHARD = MSG_DONTROUTE

Receive flags: ?

MSG_WAITALL = \$00000100

Receive flags: Wait till operation completed.

MSG_WAITFORONE = \$00010000

recvmsg(): block until 1+ packets avail

MSG_ZEROCOPY = \$04000000

Use user data in kernel path

NoAddress : in_addr = (s_addr: 0)

Constant indicating invalid (no) network address.

NoAddress6 : in6_addr = (u6_addr16: (0, 0, 0, 0, 0, 0, 0, 0, 0, 0))

Constant indicating invalid (no) IPV6 network address.

NoNet : in_addr = (s_addr: 0)

Constant indicating invalid (no) network address.

NoNet6 : in6_addr = (u6_addr16: (0, 0, 0, 0, 0, 0, 0, 0))

Constant indicating invalid (no) IPV6 network address.

PF_ALG = AF_ALG

Protocol family: Algorithm sockets

PF_APPLETALK = AF_APPLETALK

Protocol family: Appletalk DDP

PF_ASH = AF_ASH

Protocol family: Ash

PF_ATMPVC = AF_ATMPVC

Protocol family: ATM PVCs

PF_ATMSVC = AF_ATMSVC

Protocol family: ATM SVCs

PF_AX25 = AF_AX25

Protocol family: Amateur Radio AX.25

PF_BLUETOOTH = AF_BLUETOOTH

Protocol family: Bluetooth sockets

PF_BRIDGE = AF_BRIDGE

Protocol family: Multiprotocol bridge

PF_CAIF = AF_CAIF

Protocol family: CAIF (Application CPU interface) sockets

PF_CAN = AF_CAN

Protocol family: CAN (Controller Area Network) sockets

PF_DECnet = AF_DECnet

Protocol Family: DECNET project

PF_ECONET = AF_ECONET

Protocol family: Acorn Econet

PF_IB = AF_IB

Protocol family: IB (InfiniBand) sockets

PF_IEEE802154 = AF_IEEE802154

Protocol family: IEEE802154 sockets

PF_INET = AF_INET

Protocol family: Internet IP Protocol

PF_INET6 = AF_INET6

Protocol family: IP version 6

PF_IPX = AF_IPX

Protocol family: Novell IPX

PF_IRDA = AF_IRDA

Protocol family: IRDA sockets

PF_ISDN = AF_ISDN

Protocol Family: ?

PF_IUCV = AF_IUCV

Protocol family: IUCV (Inter User Communication Vehicle) sockets

PF_KCM = AF_KCM

Protocol family: KCM (Kernel Connection Multiplexor) sockets

PF_KEY = AF_KEY

Protocol family: Key management API

PF_LLC = AF_LLC

Protocol family: Linux LLC

PF_LOCAL = AF_LOCAL

Protocol family: Unix socket

PF_MAX = AF_MAX

Protocol family: Maximum value

PF_MPLS = AF_MPLS

Protocol family: MPLS (Multiprotocol Label Switching

PF_NETBEUI = AF_NETBEUI

Protocol family: Reserved for 802.2LLC project

PF_NETLINK = AF_NETLINK

Protocol family: ?

PF_NETROM = AF_NETROM

Protocol family:Amateur radio NetROM

PF_NFC = AF_NFC

Protocol family: NFC (Near Field Communication) sockets

PF_PACKET = AF_PACKET

Protocol family: Packet family

PF_PHONET = AF_PHONET

Protocol family: RxRPC sockets

PF_PPPOX = AF_PPPOX

Protocol family: PPPoX sockets

PF_QIPCRTR = AF_QIPCRTR

Protocol family: IPCRTR (Qualcomm IPC Router) sockets

PF_RDS = AF_RDS

Protocol family: RDS (Reliable Datagram Sockets) sockets

PF_ROSE = AF_ROSE

Protocol family: Amateur Radio X.25 PLP

PF_ROUTE = AF_ROUTE

Protocol Family: ?

PF_RXRPC = AF_RXRPC

Protocol family: RxRPC sockets

PF_SECURITY = AF_SECURITY

Protocol family: Security callback pseudo PF

PF_SMC = AF_SMC

Protocol family: SMC (Shared Memory Communication) sockets

PF_SNA = AF_SNA

Protocol Family: Linux SNA project

PF_TIPC = AF_TIPC

Protocol family: TIPC sockets

PF_UNIX = AF_UNIX

Protocol family: Unix domain sockets

PF_UNSPEC = AF_UNSPEC

Protocol family: Unspecified

PF_VSOCK = AF_VSOCK

Protocol family: VSOCK (hypervisor) sockets

PF_WANPIPE = AF_WANPIPE

Protocol family: Wanpipe API Sockets

PF_X25 = AF_X25

Protocol family: Reserved for X.25 project

PF_XDP = AF_XDP

Protocol family: XDP (Express Data Path) sockets

SCM_CREDENTIALS = \$02

socket control messages : credentials

SCM_RIGHTS = \$01

socket control messages : access rights

SCM_SECURITY = 03

socket control messages : security label

SCM_SRCRT = IPV6_RXSRCRT

Undocumented Getsockopt option ?

SCM_TIMESTAMP = SO_TIMESTAMP

Socket option: ?

SHUT_RD = 0

Shutdown read part of full duplex socket

SHUT_RDWR = 2

Shutdown read and write part of full duplex socket

SHUT_WR = 1

Shutdown write part of full duplex socket

SOCK_DGRAM = 2

Type of socket: datagram (conn.less) socket (UDP)

SOCK_MAXADDRLLEN = 255

Maximum socket address length for Bind ([1269](#)) call.

SOCK_RAW = 3

Type of socket: raw socket

SOCK_RDM = 4

Type of socket: reliably-delivered message

SOCK_SEQPACKET = 5

Type of socket: sequential packet socket

SOCK_STREAM = 1

Type of socket: stream (connection) type socket (TCP)

SOL_AAL = 265

Socket level: AAL

SOL_ALG = 279

Socket level: Algorithm socket

SOL_ATALK = 258

Socket level: Apple talk

SOL_ATM = 264

Socket level: ATM

SOL_AX25 = 257

Socket level: AX25

SOL_BLUETOOTH = 274

Socket level: BlueTooth

SOL_CAIF = 278

Socket level: CAIF (Application CPU interface)

SOL_DCCP = 269

Socket level: DCCP

SOL_DECNET = 261

Socket level: DECnet

SOL_ICMPV6 = 58

Socket level values for IPv6: ICMPV6

SOL_IP = 0

Undocumented ?

SOL_IPV6 = 41

Socket level values for IPv6: IPV6

SOL_IPX = 256

Socket level: IPX

SOL_IRDA = 266

Socket level: IRDA

SOL_IUCV = 277

Socket level: IUCV (Inter User Communication Vehicle)

SOL_KCM = 281

Socket level: KCM (Kernel Connection Multiplexor) sockets

SOL_LLC = 268

Socket level: LLC

SOL_NETBEUI = 267

Socket level: NETBEUI

SOL_NETLINK = 270

Socket level: NETLink

SOL_NETROM = 259

Socket level: Net ROM

SOL_NFC = 280

Socket level: NFC (Near Field Communication) socket

SOL_PACKET = 263

Socket level: Packet

SOL_PNPIPE = 275

Socket level: PNPIPE

SOL_PPPOL2TP = 273

Socket level: PPPOL2TP

SOL_RAW = 255

Socket level: raw socket

SOL_RDS = 276

Socket level: RDS (Reliable Datagram Socket)

SOL_ROSE = 260

Socket level: ROSE

SOL_RXRPC = 272

Socket level: RxRPC

SOL_SCTP = 132

Socket level: SCTP

SOL_SOCKET = 1

Socket option level: Socket level

SOL_TCP = 6

Socket level: TCP

SOL_TIPC = 271

Socket level: TIPC

SOL_TLS = 282

Socket level: TLS

SOL_UDP = 17

Socket level: UDP

SOL_UDPLITE = 136

Socket level: UDP Lite

SOL_X25 = 262

Socket level: X25

SOL_XDP = 283

Socket level: XDP (Express Data Path) sockets

SOMAXCONN = 4096

Maximum queue length specifiable by listen.

SO_ACCEPTCONN = 30

Socket option: ?

SO_ATTACH_FILTER = 26

Socket option: ?

SO_BINDTODEVICE = 25

Socket option: ?

SO_BROADCAST = 6

Socket option: Broadcast

SO_BSDCOMPAT = 14

Socket option: ?

SO_DEBUG = 1

Socket option level: debug

SO_DETACH_FILTER = 27

Socket option: ?

SO_DONTROUTE = 5

Socket option: Don't route

SO_ERROR = 4

Socket option: Error

SO_KEEPAIVE = 9

Socket option: keep alive

SO_LINGER = 13

Socket option: ?

SO_NO_CHECK = 11

Socket option: ?

SO_OOBINLINE = 10

Socket option: ?

SO_PASSCRED = 16

Socket option: ?

SO_PEERCREC = 17

Socket option: ?

SO_PEERNAME = 28

Socket option: ?

SO_PRIORITY = 12

Socket option: ?

SO_RCVBUF = 8

Socket option: receive buffer

SO_RCVLOWAT = 18

Socket option: ?

SO_RCVTIMEO = 20

Socket option: ?

SO_REUSEADDR = 2

Socket option: Reuse address

SO_REUSEPORT = 15

Socket Option : reuse port

SO_SECURITY_AUTHENTICATION = 22

Socket option: ?

SO_SECURITY_ENCRYPTION_NETWORK = 24

Socket option: ?

SO_SECURITY_ENCRYPTION_TRANSPORT = 23

Socket option: ?

SO_SNDBUF = 7

Socket option: Send buffer

SO_SNDLOWAT = 19

Socket option: ?

SO_SNDTIMEO = 21

Socket option: ?

SO_TIMESTAMP = 29

Socket option: ?

SO_TYPE = 3

Socket option: Type

S_IN = 0

Input socket in socket pair.

S_OUT = 1

Output socket in socket pair

TCP_CONGESTION = 13

Get/set the congestion-control algorithm for this socket

TCP_CORK = 3

Get/Set CORK algorithm: Send only complete packets

TCP_DEFER_ACCEPT = 9

Get/Set deferred accept on server socket

TCP_INFO = 11

Get TCP connection information (Linux only)

TCP_KEEPCNT = 6

Get/Set retry count for unacknowledged KEEPALIVE transmissions.

TCP_KEEPIDL = 4

Get/Set inactivity interval between KEEPALIVE transmissions.

TCP_KEEPINTVL = 5

Get/Set retry interval for unacknowledged KEEPALIVE transmissions.

TCP_LINGER2 = 8

Get/Set Linger2 flag

TCP_MAXSEG = 2

Get/Set Maximum segment size

TCP_MD5SIG = 14

Get/Set TCP MD5 signature option

TCP_NODELAY = 1

Get/Set No delay flag: disable Nagle algorithm

TCP_QUICKACK = 12

Get/Set quick ACK packet option.

TCP_SYNCNT = 7

Get/Set number of SYN packets to send before giving up on connection establishment

TCP_WINDOW_CLAMP = 10

Get/Set maximum packet size

UDP_CORK = 1

Get/Set UDP CORK algorithm on datagram sockets

UDP_ENCAP = 100

Get/Set UDP encapsulation flag for IPSec datagram sockets

UDP_ENCAP_ESPINUDP = 2

? Undocumented datagram option, IPSec related

UDP_ENCAP_ESPINUDP_NON_IKE = 1

? Undocumented datagram option, IPSec related

UDP_ENCAP_L2TPINUDP = 3

? Undocumented datagram option, IPSec related

72.3.2 Types

```
in6_addr = packed record
case Byte of
0: (
  u6_addr8 : Array[0..15
  ] of Byte;
);
1: (
  u6_addr16 : Array[0..7] of Word;
);
```

```

2: (
  u6_addr32
  : Array[0..3] of Cardinal;
);
3: (
  s6_addr8 : Array[0..15] of ShortInt
  ;
);
4: (
  s6_addr : Array[0..15] of ShortInt;
);
5: (
  s6_addr16
  : Array[0..7] of SmallInt;
);
6: (
  s6_addr32 : Array[0..3] of LongInt
  ;
);
end

```

Record used to describe a general IPV6 address.

```

in_addr = packed record
case Boolean of
True: (
  s_addr : cuint32
  ;
);
False: (
  s_bytes : packed Array[1..4] of Byte;
);
end

```

General inet socket address.

PIn6Addr = pin6_addr

Pointer to in6_addr ([1265](#)) type.

pin6_addr = ^in6_addr

Pointer to Tin6_addr ([1267](#))

PInAddr = pin_addr

Alias for pin_addr ([1266](#))

PInetSockAddr = psockaddr_in

Pointer to sockaddr_in ([1286](#))

PInetSockAddr6 = psockaddr_in6

Pointer to `sockaddr_in6` (1286) type

```
pin_addr = ^in_addr
```

Pointer to `in_addr` (1265) record.

```
plinger = ^linger
```

Pointer to `linger` (1286) type.

```
psockaddr = ^sockaddr
```

Pointer to `TSockAddr` (1267)

```
PSockAddr6 = ^TSockAddr6
```

`PSockAddr6` is a pointer to a record of type `TSockAddr6` (1267).

```
psockaddr_in = ^sockaddr_in
```

Pointer to `sockaddr_in` (1286)

```
psockaddr_in6 = ^sockaddr_in6
```

Pointer to `sockaddr_in6` (1286)

```
psockaddr_un = ^sockaddr_un
```

Pointer to `sockaddr_un` (1287) type.

```
Pucred = ^ucred
```

`Pucred` is a pointer to `ucred` (1287)

```
sa_family_t = cushort
```

Address family type

```
sockaddr = packed record
case Integer of
0: (
  sa_family : sa_family_t
  ;
  sa_data : packed Array[0..13] of cuint8;
);
1: (
  sin_family
  : sa_family_t;
  sin_port : cushort;
  sin_addr : in_addr;
  sin_zero
  : packed Array[0..7] of cuint8;
);
end
```

`sockaddr` is used to store a general socket address for the `FPBind` (1273), `FPRecv` (1277) and `FPSend` (1278) calls.

`TIn6Addr = in6_addr`

Alias for `in6_addr` (1265) type.

`Tin6_addr = in6_addr`

Alias for `sockaddr_in6` (1286)

`TInAddr = in_addr`

Alias for `in_addr` (1265) record type.

`TInetSockAddr = sockaddr_in`

Alias for `sockaddr_in` (1286)

`TInetSockAddr6 = sockaddr_in6`

Alias for `sockaddr_in6` (1286)

`TIn_addr = in_addr`

Alias for `in_addr` (1265) record type.

`TLinger = linger`

Alias for `linger` (1286)

`TSockAddr = sockaddr`

`TSockAddr6 = sockaddr_in6`

`TSockAddr6` is an alias for `sockaddr6_in` (1237)

`TSockArray = Array[1..2] of LongInt`

Type returned by the `FPSocketPair` (1280) call.

`Tsocket = LongInt`

Alias for easy kylix porting

`TSockLen = BaseUnix.TSocklen`

The actual type of `TSockLen` depends on the platform.

`TSockPairArray = Array[0..1] of LongInt`

Array of sockets, used in `FPSocketPair` (1280) call.

72.4 Procedures and functions

72.4.1 Accept

Synopsis: Accept a connection from a socket (deprecated).

Declaration:

```
function Accept(Sock: LongInt; var addr: TInetSockAddr;
               var SockIn: File; var SockOut: File) : Boolean
function Accept(Sock: LongInt; var addr: TInetSockAddr;
               var SockIn: text; var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: string; var SockIn: text;
               var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: string; var SockIn: File;
               var SockOut: File) : Boolean
```

Visibility: default

Description: `Accept` accepts a connection from a socket `Sock`, which was listening for a connection. If a connection is accepted, a file descriptor is returned. On error `-1` is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The `Accept` call fills the address of the connecting entity in `Addr`, and sets its length in `AddrLen`. `Addr` should be pointing to enough space, and `AddrLen` should be set to the amount of space available, prior to the call.

The alternate forms of the `Accept` (1268) command, with the `Text` or `File` parameters are equivalent to subsequently calling the regular `Accept` (1268) function and the `Sock2Text` (1284) or `Sock2File` (1283) functions. These functions return `True` if successful, `False` otherwise.

Errors: On error, `-1` is returned, and errors are reported in `SocketError`, and include the following:

ESockEBADF (1241) The socket descriptor is invalid.

ESockENOTSOCK (1242) The descriptor is not a socket.

SYS_EOPNOTSUPP The socket type doesn't support the `Listen` operation.

ESockEFAULT (1241) `Addr` points outside your address space.

ESockEWOULDBLOCK (1242) The requested operation would block the process.

See also: `FPListen` (1277), `Connect` (1270), `FPConnect` (1273), `FPBind` (1273)

Listing: `./examples/sockex/socksvr.pp`

Program server;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
{$mode fpc}
uses Sockets;
```

Var

```
  FromName : string;
  Buffer    : string[255];
  S         : Longint;
  Sin, Sout : Text;
  SAddr     : TInetSockAddr;
```

```

procedure perror (const S:string);
begin
  writeln (S, SocketError);
  halt(100);
end;

begin
  S:=fpSocket (AF_INET, SOCK_STREAM, 0);
  if SocketError<>0 then
    Perror ('Server : Socket : ');
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(5000);
  SAddr.sin_addr.s_addr:=0;
  if fpBind(S, @SAddr, sizeof(saddr))=-1 then
    Perror ('Server : Bind : ');
  if fpListen (S, 1)=-1 then
    Perror ('Server : Listen : ');
  writeln('Waiting for Connect from Client, run now sock_cli in an other tty');
  if Accept(S, FromName, Sin, Sout) then
    Perror ('Server : Accept : '+fromname);
  Reset(Sin);
  ReWrite(Sout);
  writeln(Sout, 'Message From Server');
  Flush(Sout);
  while not eof(sin) do
    begin
      Readln(Sin, Buffer);
      writeln('Server : read : ', buffer);
    end;
end.

```

72.4.2 Bind

Synopsis: Alias for fpBind.

Declaration: `function Bind(Socket: LongInt; const addr: string) : Boolean`

Visibility: default

Description: Bind is an alias for fpBind ([1273](#)) which binds to either a socket struct (Addr) or a string indicating a UNIX socket file (UNIX socket).

This function is deprecated, use fpBind instead.

See also: FPBind ([1273](#))

72.4.3 CloseSocket

Synopsis: Closes a socket handle.

Declaration: `function CloseSocket(Socket: LongInt) : LongInt`

Visibility: default

Description: CloseSocket closes a socket handle. It returns 0 if the socket was closed successfully, -1 if it failed.

Errors: On error, -1 is returned.

See also: `FPocket` ([1280](#))

72.4.4 Connect

Synopsis: Open a connection to a server socket (deprecated).

Declaration:

```
function Connect(Sock: LongInt; const addr: TInetSockAddr;
                 var SockIn: text; var SockOut: text) : Boolean
function Connect(Sock: LongInt; const addr: TInetSockAddr;
                 var SockIn: File; var SockOut: File) : Boolean
function Connect(Sock: LongInt; const addr: string; var SockIn: text;
                 var SockOut: text) : Boolean
function Connect(Sock: LongInt; const addr: string; var SockIn: File;
                 var SockOut: File) : Boolean
```

Visibility: default

Description: `Connect` opens a connection to a peer, whose address is described by `Addr`. `AddrLen` contains the length of the address. The type of `Addr` depends on the kind of connection you're trying to make, but is generally one of `TSockAddr` or `TUnixSockAddr`.

The forms of the `Connect` ([1270](#)) command with the `Text` or `File` arguments are equivalent to subsequently calling the regular `Connect` function and the `Sock2Text` ([1284](#)) or `Sock2File` ([1283](#)) functions. These functions return `True` if success full, `False` otherwise.

The `Connect` function returns a file descriptor if the call was success full, -1 in case of error.

Errors: On error, -1 is returned and errors are reported in `SocketError`.

See also: `FPListen` ([1277](#)), `FPBind` ([1273](#)), `Accept` ([1268](#)), `FPAccept` ([1272](#))

Listing: `./examples/sockex/sockcli.pp`

Program Client;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Client Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

uses Sockets;

```
procedure PError(const S : string);
begin
  writeln(S, SocketError);
  halt(100);
end;
```

```
Var
  SAddr   : TInetSockAddr;
  Buffer   : string [255];
  S        : Longint;
  Sin, Sout : Text;
  i        : integer;
```

```

begin
  S:=fpSocket (AF_INET,SOCK_STREAM,0);
  if s=-1 then
    Perror('Client : Socket : ');
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(5000);
  { localhost : 127.0.0.1 in network order }
  SAddr.sin_addr.s_addr:=HostToNet((127 shl 24) or 1);
  if not Connect (S,SAddr,Sin,Sout) then
    Perror('Client : Connect : ');
  Reset(Sin);
  Rewrite(Sout);
  Buffer:='This is a textstring sent by the Client.';
  for i:=1 to 10 do
    Writeln(Sout,Buffer);
  Flush(Sout);
  Readln(Sin,Buffer);
  Writeln(Buffer);
  Close(sout);
end.

```

Listing: ./examples/sockex/pfinger.pp

```

program pfinger;

uses sockets,errors;

Var
  Addr : TInetSockAddr;
  S : Longint;
  Sin,Sout : Text;
  Line : string;

begin
  Addr.sin_family:=AF_INET;
  { port 79 in network order }
  Addr.sin_port:=79 shl 8;
  { localhost : 127.0.0.1 in network order }
  Addr.sin_addr.s_addr:=((1 shl 24) or 127);
  S:=fpSocket(AF_INET,SOCK_STREAM,0);
  If Not Connect (S,Addr,Sin,Sout) Then
    begin
      Writeln ('Couldn't connect to localhost');
      Writeln ('Socket error : ',strerror(SocketError));
      halt(1);
    end;
  rewrite (sout);
  reset(sin);
  writeln (sout,paramstr(1));
  flush(sout);
  while not eof(sin) do
    begin
      readln (Sin,line);
      writeln (line);
    end;
  fpShutdown(s,2);
  close (sin);
  close (sout);

```

end.

72.4.5 fpaccept

Synopsis: Accept a connection from a socket.

Declaration: `function fpaccept(s: cint; addrx: psockaddr; addrlen: pSockLen) : cint`

Visibility: default

Description: `Accept` accepts a connection from a socket `S`, which was listening for a connection. If a connection is accepted, a file descriptor is returned (positive number). On error `-1` is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The `Accept` call fills the address of the connecting entity in `Addrx`, and sets its length in `Addrlen`. `Addrx` should be pointing to enough space, and `Addrlen` should be set to the amount of space available, prior to the call.

Errors: On error, `-1` is returned, and errors are reported in `SocketError`, and include the following:

ESockEBADF (1241)The socket descriptor is invalid.

ESockENOTSOCK (1242)The descriptor is not a socket.

SYS_EOPNOTSUPPThe socket type doesn't support the `Listen` operation.

ESockEFAULT (1241)`Addr` points outside your address space.

ESockEWOULDBLOCK (1242)The requested operation would block the process.

See also: `fpListen` (1277), `fpConnect` (1273), `fpBind` (1273)

Listing: `./examples/sockex/socksvr.pp`

Program `server;`

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
{$mode fpc}
uses Sockets;
```

Var

```
  FromName : string;
  Buffer    : string[255];
  S         : Longint;
  Sin, Sout : Text;
  SAddr     : TInetSockAddr;
```

```
procedure perror (const S:string);
begin
  writeln (S, SocketError);
  halt(100);
end;
```

begin

```
  S:=fpSocket (AF_INET, SOCK_STREAM, 0);
  if SocketError<>0 then
```

```

    PError ('Server : Socket : ');
    SAddr.sin_family:=AF_INET;
    { port 50000 in network order }
    SAddr.sin_port:=htons(5000);
    SAddr.sin_addr.s_addr:=0;
    if fpBind(S,@SAddr,sizeof(saddr))=-1 then
        PError ('Server : Bind : ');
    if fpListen (S,1)=-1 then
        PError ('Server : Listen : ');
    Writeln('Waiting for Connect from Client , run now sock_cli in an other tty');
    if Accept(S,FromName,Sin,Sout) then
        PError ('Server : Accept : '+fromname);
    Reset(Sin);
    Rewrite(Sout);
    Writeln(Sout, 'Message From Server');
    Flush(SOut);
    while not eof(sin) do
    begin
        Readln(Sin, Buffer);
        Writeln('Server : read : ',buffer);
    end;
end.
```

72.4.6 fpbind

Synopsis: Bind a socket to an address.

Declaration: `function fpbind(s: cint; addrx: psockaddr; addrlen: TSocketLen) : cint`

Visibility: default

Description: `fpBind` binds the socket `s` to address `Addrx`. `Addrx` has length `Addrlen`. The function returns 0 if the call was successful, -1 if not.

Errors: Errors are returned in `SocketError` and include the following:

ESockEBADF (1241)The socket descriptor is invalid.

ESockEINVAL (1241)The socket is already bound to an address,

ESockEACCESS (1241)Address is protected and you don't have permission to open it.

More errors can be found in the Unix man pages.

See also: `FPSocket (1280)`

72.4.7 fpconnect

Synopsis: Open a connection to a server socket.

Declaration: `function fpconnect(s: cint; name: psockaddr; namelen: TSocketLen) : cint`

Visibility: default

Description: `fpConnect` uses the socket `s` to open a connection to a peer, whose address is described by `Name`. `NameLen` contains the length of the address. The type of `Name` depends on the kind of connection you are trying to make, but is generally one of `TSocketAddr` or `TUnixSocketAddr`.

The `fpConnect` function returns zero if the call was success full, -1 in case of error.

Errors: On error, -1 is returned and errors are reported in `SocketError`.

See also: `fpListen` ([1277](#)), `fpBind` ([1273](#)), `fpAccept` ([1272](#))

Listing: ./examples/sockex/sockcli.pp

Program Client;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Client Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

uses Sockets;

```
procedure PError(const S : string);
begin
  writeln(S, SocketError);
  halt(100);
end;
```

Var

```
SAddr    : TInetSockAddr;
Buffer    : string [255];
S         : Longint;
Sin, Sout : Text;
i         : integer;
```

begin

```
S:=fpSocket (AF_INET, SOCK_STREAM, 0);
if s=-1 then
  PError('Client : Socket : ');
SAddr.sin_family:=AF_INET;
{ port 50000 in network order }
SAddr.sin_port:=htons(5000);
{ localhost : 127.0.0.1 in network order }
SAddr.sin_addr.s_addr:=HostToNet((127 shl 24) or 1);
if not Connect (S, SAddr, Sin, Sout) then
  PError('Client : Connect : ');
Reset(Sin);
ReWrite(Sout);
Buffer:='This is a textstring sent by the Client.';
for i:=1 to 10 do
  Writeln(Sout, Buffer);
Flush(Sout);
Readln(Sin, Buffer);
WriteLn(Buffer);
Close(sout);
```

end.

Listing: ./examples/sockex/pfinger.pp

program pfinger;

uses sockets, errors;

Var

```

Addr : TInetSockAddr;
S : Longint;
Sin, Sout : Text;
Line : string;

begin
  Addr.sin_family:=AF_INET;
  { port 79 in network order }
  Addr.sin_port:=79 shl 8;
  { localhost : 127.0.0.1 in network order }
  Addr.sin_addr.s_addr:=((1 shl 24) or 127);
  S:=fpSocket(AF_INET,SOCK_STREAM,0);
  If Not Connect (S,ADDR,SIN,SOUT) Then
    begin
      Writeln ('Couldn't connect to localhost');
      Writeln ('Socket error : ',strerror(SocketError));
      halt(1);
    end;
  rewrite (sout);
  reset(sin);
  writeln (sout,paramstr(1));
  flush(sout);
  while not eof(sin) do
    begin
      readln (Sin,line);
      writeln (line);
    end;
  fpShutdown(s,2);
  close (sin);
  close (sout);
end.

```

72.4.8 fpgetpeername

Synopsis: Return the name (address) of the connected peer.

Declaration: function fpgetpeername(s: cint; name: psockaddr; namelen: pSockLen)
: cint

Visibility: default

Description: fpGetPeerName returns the name of the entity connected to the specified socket S. The Socket must be connected for this call to work.

Name should point to enough space to store the name, the amount of space pointed to should be set in Namelen. When the function returns successfully, Name will be filled with the name, and Name will be set to the length of Name.

Errors: Errors are reported in SocketError, and include the following:

ESockEBADF (1241)The socket descriptor is invalid.

ESockENOBUFS (1242)The system doesn't have enough buffers to perform the operation.

ESockENOTSOCK (1242)The descriptor is not a socket.

ESockEFAULT (1241)Addr points outside your address space.

ESockENOTCONN (1242)The socket isn't connected.

See also: fpConnect (1273), fpSocket (1280)

72.4.9 fpgetsockname

Synopsis: Return name of socket.

Declaration: `function fpgetsockname(s: cint; name: psockaddr; namelen: pSockLen)
: cint`

Visibility: default

Description: `fpGetSockName` returns the current name of the specified socket `S`. `Name` should point to enough space to store the name, the amount of space pointed to should be set in `Namelen`. When the function returns successfully, `Name` will be filled with the name, and `Namelen` will be set to the length of `Name`.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1241)The socket descriptor is invalid.

ESockENOBUFS (1242)The system doesn't have enough buffers to perform the operation.

ESockENOTSOCK (1242)The descriptor is not a socket.

ESockEFAULT (1241)`Addr` points outside your address space.

See also: `fpBind` (1273)

72.4.10 fpgetsockopt

Synopsis: Get current socket options

Declaration: `function fpgetsockopt(s: cint; level: cint; optname: cint;
optval: pointer; optlen: pSockLen) : cint`

Visibility: default

Description: `fpGetSockOpt` gets the connection option `optname`, for socket `S`. The socket may be obtained from different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKETFrom the socket itself.

XXXset `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

The options are stored in the memory location pointed to by `optval`. `optlen` should point to the initial length of `optval`, and on return will contain the actual length of the stored data.

On success, 0 is returned. On Error, -1 is returned.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1241)The socket descriptor is invalid.

ESockENOTSOCK (1242)The descriptor is not a socket.

ESockEFAULT (1241)`OptVal` points outside your address space.

See also: `fpSetSockOpt` (1279)

72.4.11 fplisten

Synopsis: Listen for connections on a socket.

Declaration: `function fplisten(s: cint; backlog: cint) : cint`

Visibility: default

Description: `fpListen` listens for up to `backlog` connections from socket `S`. The socket `S` must be of type `SOCK_STREAM` or `Sock_SEQPACKET`.

The function returns 0 if a connection was accepted, -1 if an error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1241)The socket descriptor is invalid.

ESockENOTSOCK (1242)The descriptor is not a socket.

SYS_EOPNOTSUPPThe socket type doesn't support the `Listen` operation.

See also: `fpSocket` (1280), `fpBind` (1273), `fpConnect` (1273)

72.4.12 fprecv

Synopsis: Receive data on socket

Declaration: `function fprecv(s: cint; buf: pointer; len: size_t; flags: cint)
: ssize_t`

Visibility: default

Description: `fpRecv` reads at most `len` bytes from socket `S` into address `buf`. The socket must be in a connected state. `Flags` can be one of the following:

1Process out-of band data.

4Bypass routing, use a direct interface.

??Wait for full request or report an error.

The functions returns the number of bytes actually read from the socket, or -1 if a detectable error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1241)The socket descriptor is invalid.

ESockENOTCONN (1242)The socket isn't connected.

ESockENOTSOCK (1242)The descriptor is not a socket.

ESockEFAULT (1241)The address is outside your address space.

ESockEMSGSIZE (1241)The message cannot be sent atomically.

ESockEWOULDBLOCK (1242)The requested operation would block the process.

ESockENOBUFS (1242)The system doesn't have enough free buffers available.

See also: `FPSend` (1278)

72.4.13 fprecvfrom

Synopsis: Receive data from an unconnected socket

Declaration: `function fprecvfrom(s: cint; buf: pointer; len: size_t; flags: cint;
from: psockaddr; fromlen: pSockLen) : ssize_t`

Visibility: default

Description: `fpRecvFrom` receives data in buffer `Buf` with maximum length `Len` from socket `S`. Receipt is controlled by options in `Flags`. The location pointed to by `from` will be filled with the address from the sender, and its length will be stored in `fromlen`. The function returns the number of bytes received, or -1 on error. `AddrLen`.

Errors: On error, -1 is returned.

See also: `fpSocket` ([1280](#)), `frecv` ([1277](#))

72.4.14 fpsend

Synopsis: Send data through socket

Declaration: `function fpsend(s: cint; msg: pointer; len: size_t; flags: cint)
: ssize_t`

Visibility: default

Description: `fpSend` sends `Len` bytes starting from address `Msg` to socket `S`. `S` must be in a connected state. Options can be passed in `Flags`.

The function returns the number of bytes sent, or -1 if a detectable error occurred.

`Flags` can be one of the following:

1Process out-of band data.

4Bypass routing, use a direct interface.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF ([1241](#))The socket descriptor is invalid.

ESockENOTSOCK ([1242](#))The descriptor is not a socket.

ESockEFAULT ([1241](#))The address is outside your address space.

ESockEMSGSIZE ([1241](#))The message cannot be sent atomically.

ESockEWOULDBLOCK ([1242](#))The requested operation would block the process.

ESockENOBUFS ([1242](#))The system doesn't have enough free buffers available.

See also: `fpRecv` ([1277](#))

72.4.15 fpsendto

Synopsis: Send data through an unconnected socket to an address.

Declaration: `function fpsendto(s: cint; msg: pointer; len: size_t; flags: cint;
tox: psockaddr; tolen: TSockLen) : ssize_t`

Visibility: default

Description: `fpSendTo` sends data from buffer `Msg` with length `len` through socket `S` with options `Flags`. The data is sent to address `tox`, which has length `toLen`

Errors: On error, -1 is returned.

See also: `fpSocket` (1280), `fpSend` (1278), `fpRecvFrom` (1278)

72.4.16 `fpsetsockopt`

Synopsis: Set socket options.

Declaration: `function fpsetsockopt(s: cint; level: cint; optname: cint; optval: pointer; optlen: TSocketLen) : cint`

Visibility: default

Description: `fpSetSockOpt` sets the connection options for socket `S`. The socket may be manipulated at different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKETTo manipulate the socket itself.

XXXset `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

The actual option is stored in a buffer pointed to by `optval`, with length `optlen`.

For more information on this call, refer to the UNIX manual page `setsockopt`

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1241)The socket descriptor is invalid.

ESockENOTSOCK (1242)The descriptor is not a socket.

ESockEFAULT (1241)`OptVal` points outside your address space.

See also: `fpGetSockOpt` (1276)

72.4.17 `fpshutdown`

Synopsis: Close one end of full duplex connection.

Declaration: `function fpshutdown(s: cint; how: cint) : cint`

Visibility: default

Description: `fpShutDown` closes one end of a full duplex socket connection, described by `S`. The parameter `How` determines how the connection will be shut down, and can be one of the following:

0Further receives are disallowed.

1Further sends are disallowed.

2Sending nor receiving are allowed.

On success, the function returns 0, on error -1 is returned.

Errors: `SocketError` is used to report errors, and includes the following:

ESockEBADF (1241)The socket descriptor is invalid.

ESockENOTCONN (1242)The socket isn't connected.

ESockENOTSOCK (1242)The descriptor is not a socket.

See also: `fpSocket` (1280), `fpConnect` (1273)

72.4.18 `fpsocket`

Synopsis: Create new socket

Declaration: `function fpsocket(domain: cint; xtype: cint; protocol: cint) : cint`

Visibility: default

Description: `fpSocket` creates a new socket in domain `Domain`, from type `xType` using protocol `Protocol`. The Domain, Socket type and Protocol can be specified using predefined constants (see the section on constants for available constants) If successful, the function returns a socket descriptor, which can be passed to a subsequent `fpBind` (1273) call. If unsuccessfully, the function returns -1.
for an example, see `Accept` (1268).

Errors: Errors are returned in `SocketError`, and include the following:

ESockEPROTONOSUPPORT (1242) The protocol type or the specified protocol is not supported within this domain.

ESockEMFILE (1241) The per-process descriptor table is full.

SYS_ENFILE The system file table is full.

ESockEACCESS (1241) Permission to create a socket of the specified type and/or protocol is denied.

ESockENOBUFS (1242) Insufficient buffer space is available. The socket cannot be created until sufficient resources are freed.

See also: `FPSocketPair` (1280)

72.4.19 `fpsocketpair`

Synopsis: Create socket pair.

Declaration: `function fpsocketpair(d: cint; xtype: cint; protocol: cint; sv: puint) : cint`

Visibility: default

Description: `fpSocketPair` creates 2 sockets in domain `D`, from type `xType` and using protocol `Protocol`. The pair is returned in `sv`, and they are indistinguishable. The function returns -1 upon error and 0 upon success.

Errors: Errors are reported in `SocketError`, and are the same as in `FPSocket` (1280)

See also: `Str2UnixSockAddr` (1284)

72.4.20 `HostAddrToStr`

Synopsis: Convert a host address to a string.

Declaration: `function HostAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr` converts the host address in `Entry` to a string representation in human-readable form (a dotted quad).

Basically, it is the same as `NetAddrToStr` (1282), but with the bytes in correct order.

See also: `NetAddrToStr` (1282), `StrToHostAddr` (1284), `StrToNetAddr` (1285)

72.4.21 HostAddrToStr6

Synopsis: Convert a IPV6 host address to a string representation.

Declaration: `function HostAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr6` converts the IPV6 host address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` (1282), but with the bytes in correct order.

See also: `NetAddrToStr` (1282), `StrToHostAddr` (1284), `StrToNetAddr` (1285), `StrToHostAddr6` (1285)

72.4.22 HostToNet

Synopsis: Convert a host address to a network address

Declaration: `function HostToNet(Host: in_addr) : in_addr`
`function HostToNet(Host: LongInt) : LongInt`

Visibility: default

Description: `HostToNet` converts a host address to a network address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `NetToHost` (1282), `NToHS` (1283), `HToNS` (1281), `ShortHostToNet` (1283), `ShortNetToHost` (1283)

72.4.23 htonl

Synopsis: Convert long integer from host ordered to network ordered

Declaration: `function htonl(host: Cardinal) : Cardinal; Overload`

Visibility: default

Description: `htonl` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htons` (1281), `ntohl` (1282), `ntohs` (1283)

72.4.24 htons

Synopsis: Convert short integer from host ordered to network ordered

Declaration: `function htons(host: Word) : Word`

Visibility: default

Description: `htons` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htonl` (1281), `ntohl` (1282), `ntohs` (1283)

72.4.25 NetAddrToStr

Synopsis: Convert a network address to a string.

Declaration: `function NetAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr` converts the network address in `Entry` to a string representation in human-readable form (a dotted quad).

See also: `HostAddrToStr` ([1280](#)), `StrToNetAddr` ([1285](#)), `StrToHostAddr` ([1284](#))

72.4.26 NetAddrToStr6

Synopsis: Convert a IPV6 network address to a string.

Declaration: `function NetAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr6` converts the IPV6 network address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` ([1282](#)), but with the bytes in correct order.

See also: `NetAddrToStr` ([1282](#)), `StrToHostAddr` ([1284](#)), `StrToNetAddr` ([1285](#)), `StrToHostAddr6` ([1285](#))

72.4.27 NetToHost

Synopsis: Convert a network address to a host address.

Declaration: `function NetToHost(Net: in_addr) : in_addr`
`function NetToHost(Net: LongInt) : LongInt`

Visibility: default

Description: `NetToHost` converts a network address to a host address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `HostToNet` ([1281](#)), `NToHS` ([1283](#)), `HToNS` ([1281](#)), `ShortHostToNet` ([1283](#)), `ShortNetToHost` ([1283](#))

72.4.28 NToHI

Synopsis: Convert long integer from network ordered to host ordered

Declaration: `function NToHI(Net: Cardinal) : Cardinal; Overload`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` ([1281](#)), `htons` ([1281](#)), `ntohs` ([1283](#))

72.4.29 NToHs

Synopsis: Convert short integer from network ordered to host ordered

Declaration: `function NToHs (Net: Word) : Word`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` ([1281](#)), `htons` ([1281](#)), `ntohl` ([1282](#))

72.4.30 ShortHostToNet

Synopsis: Convert a host port number to a network port number

Declaration: `function ShortHostToNet (Host: Word) : Word`

Visibility: default

Description: `ShortHostToNet` converts a host port number to a network port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` ([1283](#)), `HostToNet` ([1281](#)), `NToHS` ([1283](#)), `HToNS` ([1281](#))

72.4.31 ShortNetToHost

Synopsis: Convert a network port number to a host port number

Declaration: `function ShortNetToHost (Net: Word) : Word`

Visibility: default

Description: `ShortNetToHost` converts a network port number to a host port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` ([1283](#)), `HostToNet` ([1281](#)), `NToHS` ([1283](#)), `HToNS` ([1281](#))

72.4.32 Sock2File

Synopsis: Convert socket to untyped file descriptors

Declaration: `procedure Sock2File (Sock: LongInt; var SockIn: File; var SockOut: File)`

Visibility: default

Description: `Sock2File` transforms a socket `Sock` into 2 Pascal file descriptors of type `File`, one for reading from the socket (`SockIn`), one for writing to the socket (`SockOut`).

Errors: None.

See also: `FPSocket` ([1280](#)), `Sock2Text` ([1284](#))

72.4.33 Sock2Text

Synopsis: Convert socket to text file descriptors

Declaration: `procedure Sock2Text (Sock: LongInt; var SockIn: Text; var SockOut: Text)`

Visibility: default

Description: `Sock2Text` transforms a socket `Sock` into 2 Pascal file descriptors of type `Text`, one for reading from the socket (`SockIn`), one for writing to the socket (`SockOut`).

Errors: None.

See also: `FPSocket` ([1280](#)), `Sock2File` ([1283](#))

72.4.34 socketerror

Synopsis: Contains the error code for the last socket operation.

Declaration: `function socketerror : cint`

Visibility: default

Description: `SocketError` contains the error code for the last socket operation. It can be examined to return the last socket error.

72.4.35 Str2UnixSockAddr

Synopsis: Convert path to `TUnixSockAddr` ([1287](#))

Declaration: `procedure Str2UnixSockAddr(const addr: string; var t: TUnixSockAddr; var len: LongInt)`

Visibility: default

Description: `Str2UnixSockAddr` transforms a Unix socket address in a string to a `TUnixSockAddr` structure which can be passed to the `Bind` ([1269](#)) call.

Errors: None.

See also: `FPSocket` ([1280](#)), `FPBind` ([1273](#))

72.4.36 StrToHostAddr

Synopsis: Convert a string to a host address.

Declaration: `function StrToHostAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToHostAddr` converts the string representation in `IP` to a host address and returns the host address.

Errors: On error, the host address is filled with zeroes.

See also: `NetAddrToStr` ([1282](#)), `HostAddrToStr` ([1280](#)), `StrToNetAddr` ([1285](#))

72.4.37 StrToHostAddr6

Synopsis: Convert a string to a IPV6 host address.

Declaration: `function StrToHostAddr6(IP: AnsiString) : Tin6_addr`

Visibility: default

Description: `StrToHostAddr6` converts the string representation in `IP` to a IPV6 host address and returns the host address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1282](#)), `HostAddrToStr6` ([1281](#)), `StrToHostAddr` ([1284](#))

72.4.38 StrToNetAddr

Synopsis: Convert a string to a network address.

Declaration: `function StrToNetAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToNetAddr` converts the string representation in `IP` to a network address and returns the network address.

Errors: On error, the network address is filled with zeroes.

See also: `NetAddrToStr` ([1282](#)), `HostAddrToStr` ([1280](#)), `StrToHostAddr` ([1284](#))

72.4.39 StrToNetAddr6

Synopsis: Convert a string to a IPV6 network address

Declaration: `function StrToNetAddr6(IP: AnsiString) : Tin6_addr`

Visibility: default

Description: `StrToNetAddr6` converts the string representation in `IP` to a IPV6 network address and returns the network address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1282](#)), `HostAddrToStr6` ([1281](#)), `StrToHostAddr6` ([1285](#))

72.4.40 TryStrToHostAddr

Synopsis: Try to convert a string to an IPV4 address

Declaration: `function TryStrToHostAddr(IP: AnsiString; out ip4: in_addr) : Boolean`

Visibility: default

Description: `TryStrToHostAddr` attempts to convert `IP` to an IPV4 address. If successful it returns the address in `ip4` and returns `True`. If unsuccessful it returns `False`.

See also: `StrToHostAddr` ([1284](#)), `TryStrToHostAddr6` ([1286](#))

72.4.41 TryStrToHostAddr6

Synopsis: Try to convert a string to an IPV6 address

Declaration: `function TryStrToHostAddr6(IP: AnsiString; out ip6: in6_addr) : Boolean`

Visibility: default

Description: `TryStrToHostAddr` attempts to convert IP to an IPV6 address. If successful it returns the address in `ip6` and returns `True`. If unsuccessful it returns `False`.

See also: `StrToHostAddr6` ([1285](#)), `TryStrToHostAddr` ([1285](#))

72.5 linger

```
linger = packed record
  l_onoff : cint;
  l_linger : cint;
end
```

This record is used in the `fpsetsockopt` ([1279](#)) call to specify linger options.

72.6 sockaddr_in

```
sockaddr_in = packed record
  sin_family : sa_family_t;
  sin_port
  : cushort;
  sin_addr : in_addr;
  xpad : Array[0..7] of Char;
end
```

`sockaddr_in` is used to store a INET socket address for the `FPBind` ([1273](#)), `FPRecv` ([1277](#)) and `FPSend` ([1278](#)) calls.

72.7 sockaddr_in6

```
sockaddr_in6 = packed record
  sin6_family : sa_family_t;
  sin6_port
  : cuint16;
  sin6_flowinfo : cuint32;
  sin6_addr : in6_addr;
  sin6_scope_id
  : cuint32;
end
```

Alias for `sockaddr_in6` ([1286](#))

72.8 sockaddr_un

```
sockaddr_un = packed record
  sun_family : sa_family_t;
  sun_path
    : Array[0..107] of Char;
end
```

`sockaddr_un` is used to store a UNIX socket address for the `FPBind` (1273), `FPRecv` (1277) and `FPSend` (1278) calls.

72.9 TUnixSockAddr

```
TUnixSockAddr = packed record
  family : sa_family_t;
  path : Array
    [0..107] of Char;
end
```

Alias for `sockaddr_un` (1287)

72.10 ucred

```
ucred = record
  pid : cuint32;
  uid : cuint32;
  gid : cuint32;
end
```

`ucred` is used for socket control messages with type `SCM_CREDENTIALS`.

pid Process ID

uid User ID

gid Group ID

Chapter 73

Reference for unit 'Strings'

73.1 Used units

Table 73.1: Used units by unit 'Strings'

Name	Page
System	1339

73.2 Overview

This chapter describes the `STRINGS` unit for Free Pascal. This unit is system independent, and therefore works on all supported platforms.

73.3 Procedures and functions

73.3.1 `stralloc`

Synopsis: Allocate memory for a new null-terminated string on the heap

Declaration: `function stralloc(L: SizeInt) : PChar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Errors: If there is not enough memory, a run-time error occurs.

See also: `StrNew` ([1297](#)), `StrPCopy` ([1298](#))

73.3.2 `strcat`

Synopsis: Concatenate 2 null-terminated strings.

Declaration: `function strcat(dest: PChar; source: PChar) : PChar`

Visibility: default

Description: Attaches Source to Dest and returns Dest.

Errors: No length checking is performed.

See also: StrLCat ([1293](#))

Listing: ./examples/stringex/ex11.pp

Program Example11;

Uses strings;

{ Program to demonstrate the StrCat function. }

Const P1 : PChar = 'This is a PChar String.';

Var P2 : PChar;

begin

P2:=StrAlloc (StrLen(P1)*2+1);

StrMove (P2,P1,StrLen(P1)+1); { P2=P1 }

StrCat (P2,P1); { Append P2 once more }

WriteLn ('P2 : ',P2);

StrDispose(P2);

end.

73.3.3 strcmp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: function strcmp(str1: PChar; str2: PChar) : SizeInt

Visibility: default

Description: Compares the null-terminated strings S1 and S2. The result is

- A negative SizeInt when S1<S2.
- 0 when S1=S2.
- A positive SizeInt when S1>S2.

For an example, see StrLComp ([1294](#)).

Errors: None.

See also: StrLComp ([1294](#)), StrIComp ([1292](#)), StrLComp ([1295](#))

73.3.4 strcpy

Synopsis: Copy a null-terminated string

Declaration: function strcpy(dest: PChar; source: PChar) : PChar; Overload

Visibility: default

Description: Copy the null terminated string in Source to Dest, and returns a pointer to Dest. Dest needs enough room to contain Source, i.e. StrLen(Source)+1 bytes.

Errors: No length checking is performed.

See also: StrPCopy ([1298](#)), StrLCopy ([1294](#)), StrECopy ([1291](#))

Listing: ./examples/stringex/ex4.pp

```

Program Example4;

Uses strings;

{ Program to demonstrate the StrCopy function. }

Const P : PChar = 'This is a PCHAR string.';

var PP : PChar;

begin
  PP:=StrAlloc (StrLen(P)+1);
  StrCopy (PP,P);
  If StrComp (PP,P)<>0 then
    Writeln ( 'Oh-oh problems... ' )
  else
    Writeln ( 'All is well : PP=',PP);
  StrDispose(PP);
end.

```

73.3.5 strdispose

Synopsis: disposes of a null-terminated string on the heap

Declaration: `procedure strdispose(p: PChar)`

Visibility: default

Description: Removes the string in P from the heap and releases the memory.

Errors: None.

See also: StrNew ([1297](#))

Listing: ./examples/stringex/ex17.pp

```

Program Example17;

Uses strings;

{ Program to demonstrate the StrDispose function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin
  P2:=StrNew (P1);
  Writeln ( 'P2 : ',P2);
  StrDispose(P2);
end.

```

73.3.6 strecopy

Synopsis: Copy a null-terminated string, return a pointer to the end.

Declaration: `function strecopy(dest: PChar; source: PChar) : PChar`

Visibility: default

Description: Copies the Null-terminated string in `Source` to `Dest`, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

Errors: No length checking is performed.

See also: `StrLCopy` ([1294](#)), `StrCopy` ([1289](#))

Listing: `./examples/stringex/ex6.pp`

Program `Example6;`

Uses `strings;`

{ Program to demonstrate the StrECopy function. }

Const `P : PChar = 'This is a PCHAR string.';`

Var `PP : PChar;`

begin

`PP:= StrAlloc (StrLen(P)+1);`

`If Longint(StrECopy(PP,P)) - Longint(PP) <> StrLen(P) then`

`Writeln('Something is wrong here !')`

`else`

`Writeln ('PP= ',PP);`

`StrDispose(PP);`

end.

73.3.7 strend

Synopsis: Return a pointer to the end of a null-terminated string

Declaration: `function strend(p: PChar) : PChar`

Visibility: default

Description: Returns a pointer to the end of `P`. (i.e. to the terminating null-character.

Errors: None.

See also: `StrLen` ([1295](#))

Listing: `./examples/stringex/ex7.pp`

Program `Example6;`

Uses `strings;`

{ Program to demonstrate the StrEnd function. }

Const `P : PChar = 'This is a PCHAR string.';`

```

begin
  If Longint(StrEnd(P)) - Longint(P) <> StrLen(P) then
    Writeln('Something is wrong here !')
  else
    Writeln('All is well..');
end.

```

73.3.8 stricmp

Synopsis: Compare 2 null-terminated strings, case insensitive.

Declaration: `function stricmp(str1: PChar; str2: PChar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings S1 and S2, ignoring case. The result is

- A negative `SizeInt` when $S1 < S2$.
- 0 when $S1 = S2$.
- A positive `SizeInt` when $S1 > S2$.

Errors: None.

See also: `StrLComp` ([1294](#)), `StrComp` ([1289](#)), `StrLComp` ([1295](#))

Listing: `./examples/stringex/ex8.pp`

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

```

Const P1 : PChar = 'This is the first string.';
      P2 : PChar = 'This is the second string.';

```

Var L : Longint;

```

begin
  Write('P1 and P2 are ');
  If StrComp(P1,P2) <> 0 then write('NOT ');
  write('equal. The first ');
  L:=1;
  While StrLComp(P1,P2,L)=0 do inc(L);
  dec(L);
  Writeln(L,' characters are the same. ');
end.

```

73.3.9 stripos

Synopsis: Return the position of a substring in a string, case insensitive.

Declaration: `function stripos(str1: PChar; str2: PChar) : PChar`

Visibility: default

Description: `strpos` returns the position of `str2` in `str1`. It searches in a case-insensitive manner, and if it finds a match, it returns a pointer to the location of the match. If no match is found, `Nil` is returned.

Errors: No checks are done on the validity of the pointers, and the pointers are assumed to point to a properly null-terminated string. If either of these conditions are not met, a run-time error may follow.

See also: `strscan` ([1293](#)), `strpos` ([1299](#))

73.3.10 `strscan`

Synopsis: Scan a string for a character, case-insensitive

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: `strscan` does the same as `strscan` ([1300](#)) but compares the characters case-insensitively. It returns a pointer to the first occurrence of the character `c` in the null-terminated string `p`, or `Nil` if `c` is not present in the string.

See also: `strscan` ([1300](#)), `strrscan` ([1299](#))

73.3.11 `strlcat`

Synopsis: Concatenate 2 null-terminated strings, with length boundary.

Declaration: `function strlcat(dest: PChar; source: PChar; l: SizeInt) : PChar`

Visibility: default

Description: Adds `L` characters from `Source` to `Dest`, and adds a terminating null-character. Returns `Dest`.

Errors: None.

See also: `StrCat` ([1288](#))

Listing: `./examples/stringex/ex12.pp`

Program `Example12;`

Uses `strings;`

{ Program to demonstrate the StrLCat function. }

Const `P1 : PChar = '1234567890';`

Var `P2 : PChar;`

begin

`P2:= StrAlloc (StrLen(P1)*2+1);`

`P2^:=#0; { Zero length }`

`StrCat (P2,P1);`

`StrLCat (P2,P1,5);`

`WriteLn ('P2 = ',P2);`

`StrDispose(P2)`

end.

73.3.12 strlcomp

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: `function strlcomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2. The result is

- A negative `SizeInt` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `SizeInt` when `S1>S2`.

Errors: None.

See also: `StrComp` ([1289](#)), `StrIComp` ([1292](#)), `StrLComp` ([1295](#))

Listing: `./examples/stringex/ex8.pp`

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

Const P1 : PChar = 'This is the first string.';
P2 : PChar = 'This is the second string.';

Var L : Longint;

begin

Write ('P1 and P2 are ');
If **StrComp** (P1,P2)<>0 **then write** ('NOT ');
write ('equal. The first ');
L:=1;
While **StrLComp**(P1,P2,L)=0 **do inc** (L);
dec(L);
WriteLn (L,' characters are the same.');

end.

73.3.13 strlcopy

Synopsis: Copy a null-terminated string, limited in length.

Declaration: `function strlcopy(dest: PChar; source: PChar; maxlen: SizeInt) : PChar`
; Overload

Visibility: default

Description: Copies MaxLen characters from Source to Dest, and makes Dest a null terminated string.

Errors: No length checking is performed.

See also: `StrCopy` ([1289](#)), `StrECopy` ([1291](#))

Listing: `./examples/stringex/ex5.pp`

```

Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin
  PP:= StrAlloc(11);
  WriteLn ('First 10 characters of P : ',StrLCopy (PP,P,10));
  StrDispose(PP);
end.

```

73.3.14 strlen

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: PChar) : SizeInt`

Visibility: default

Description: Returns the length of the null-terminated string P. If P equals Nil, then zero (0) is returned.

Errors: None.

See also: StrNew ([1297](#))

Listing: ./examples/stringex/ex1.pp

```

Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }

Const P : PChar = 'This is a constant pchar string';

begin
  WriteLn ('P          : ',p);
  WriteLn ('length(P) : ',StrLen(P));
end.

```

73.3.15 strlicomp

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2, ignoring case. The result is

- A negative `SizeInt` when $S1 < S2$.
- 0 when $S1 = S2$.
- A positive `SizeInt` when $S1 > S2$.

For an example, see `StrIComp` ([1292](#))

Errors: None.

See also: `StrLComp` ([1294](#)), `StrComp` ([1289](#)), `StrIComp` ([1292](#))

73.3.16 `strlower`

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: PChar) : PChar`

Visibility: default

Description: Converts `P` to an all-lowercase string. Returns `P`.

Errors: None.

See also: `StrUpper` ([1300](#))

Listing: `./examples/stringex/ex14.pp`

Program `Example14`;

Uses `strings`;

{ Program to demonstrate the StrLower and StrUpper functions. }

Const

`P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';`
`P2 : PChar = 'this is a lowercase string';`

begin

`P1 := StrNew(P1);`
`P2 := strNew(P2);`
`WriteLn ('Uppercase : ', StrUpper(P2));`
`StrLower(P1);`
`WriteLn ('Lowercase : ', P1);`
`StrDispose(P1);`
`StrDispose(P2);`

end.

73.3.17 `strmove`

Synopsis: Move a null-terminated string to new location.

Declaration: `function strmove(dest: PChar; source: PChar; l: SizeInt) : PChar`

Visibility: default

Description: Copies `MaxLen` characters from `Source` to `Dest`. No terminating null-character is copied. Returns `Dest`

Errors: None.

See also: StrLCopy ([1294](#)), StrCopy ([1289](#))

Listing: ./examples/stringex/ex10.pp

Program Example10;

Uses strings;

{ Program to demonstrate the StrMove function. }

Const P1 : PCHAR = 'This is a pchar string.';

Var P2 : Pchar;

begin

 P2:= StrAlloc (StrLen(P1)+1);

StrMove (P2,P1,StrLen(P1)+1); { P2:=P1 }

Writeln ('P2 = ',P2);

StrDispose(P2);

end.

73.3.18 strnew

Synopsis: Allocate room for new null-terminated string.

Declaration: function strnew(p: PChar) : PChar

Visibility: default

Description: Copies P to the Heap, and returns a pointer to the copy.

Errors: Returns Nil if no memory was available for the copy.

See also: StrCopy ([1289](#)), StrDispose ([1290](#))

Listing: ./examples/stringex/ex16.pp

Program Example16;

Uses strings;

{ Program to demonstrate the StrNew function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin

 P2:=StrNew (P1);

If P1=P2 **then**

writeln ('This can''t be happening... ')

else

writeln ('P2 : ',P2);

StrDispose(P2);

end.

73.3.19 strpas

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: `function strpas(p: PChar) : shortstring`

Visibility: default

Description: Converts a null terminated string in P to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

See also: StrPCopy ([1298](#))

Listing: ./examples/stringex/ex3.pp

Program Example3;

Uses strings;

{ Program to demonstrate the StrPas function. }

Const P : PChar = 'This is a PCHAR string';

var S : **string**;

begin

 S:=StrPas (P);

 WriteLn ('S : ',S);

end.

73.3.20 strcpy

Synopsis: Copy a pascal string to a null-terminated string

Declaration: `function strcpy(d: PChar; const s: string) : PChar`

Visibility: default

Description: Converts the Pascal string in S to a Null-terminated string, and copies it to D. D needs enough room to contain the string Source, i.e. Length(S)+1 bytes.

Errors: No length checking is performed.

See also: StrPas ([1298](#))

Listing: ./examples/stringex/ex2.pp

Program Example2;

Uses strings;

{ Program to demonstrate the StrPCopy function. }

Const S = 'This is a normal string.';

Var P : Pchar;

```

begin
  p:= StrAlloc (length(S)+1);
  if StrPCopy (P,S)<>P then
    Writeln ('This is impossible !!')
  else
    writeln (P);
    StrDispose(P);
end.

```

73.3.21 strpos

Synopsis: Search for a null-terminated substring in a null-terminated string

Declaration: `function strpos(str1: PChar; str2: PChar) : PChar`

Visibility: default

Description: Returns a pointer to the first occurrence of S2 in S1. If S2 does not occur in S1, returns Nil.

Errors: None.

See also: StrScan ([1300](#)), StrRScan ([1300](#))

Listing: ./examples/stringex/ex15.pp

Program Example15;

Uses strings;

{ Program to demonstrate the StrPos function. }

Const P : PChar = 'This is a PChar string.';
 S : PChar = 'is';

begin
 Writeln ('Position of ''is'' in P : ',sizeint(**StrPos**(P,S))-sizeint(P));
end.

73.3.22 strriscan

Synopsis: Scan a string reversely for a character, case-insensitive

Declaration: `function strriscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: `strriscan` does the same as `strrscan` ([1300](#)) but compares the characters case-insensitively. It returns a pointer to the last occurrence of the character `c` in the null-terminated string `p`, or Nil if `c` is not present in the string.

See also: `strrscan` ([1300](#)), `striscan` ([1293](#))

73.3.23 strscan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

For an example, see StrScan ([1300](#)).

Errors: None.

See also: StrScan ([1300](#)), StrPos ([1299](#))

73.3.24 strscan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: StrRScan ([1300](#)), StrPos ([1299](#))

Listing: ./examples/stringex/ex13.pp

Program Example13;

Uses strings;

{ Program to demonstrate the StrScan and StrRScan functions. }

Const P : PChar = 'This is a PCHAR string.';
 S : Char = 's' ;

begin

WriteLn ('P, starting from first 's' : ', **StrScan**(P,s));

WriteLn ('P, starting from last 's' : ', **StrRScan**(P,s));

end.

73.3.25 strupper

Synopsis: Convert null-terminated string to all-uppercase

Declaration: `function strupper(p: PChar) : PChar`

Visibility: default

Description: Converts P to an all-uppercase string. Returns P.

For an example, see StrLower ([1296](#))

Errors: None.

See also: StrLower ([1296](#))

Chapter 74

Reference for unit 'StrUtils'

74.1 Used units

Table 74.1: Used units by unit 'StrUtils'

Name	Page
System	1339
sysutils	1615
Types	1934

74.2 Constants, types and variables

74.2.1 Resource strings

```
SErrAmountStrings =  
    'Amount of search and replace strings don''t match'
```

Error message used in stringsreplace function

```
SInvalidRomanNumeral = '%s is not a valid Roman numeral'
```

Error string shown in exception raised when invalid roman numeral is encountered

74.2.2 Constants

```
AnsiResemblesProc : TCompareTextProc = @ SoundexProc
```

This procedural variable is standard set to SoundexProc ([1332](#)) but can be overridden with a user-defined algorithm. This algorithm should return `True` if `AText` resembles `AOtherText`, or `False` otherwise. The standard routine compares the soundexes of the two strings and returns `True` if they are equal.

```
Brackets = ['(', ')', '[', ']', '{', '}']
```

Set of characters that contain all possible bracket characters

```
DigitChars = ['0'..'9']
```

Set of digit characters

```
ResemblesProc : TCompareTextProc = @ SoundexProc
```

`ResemblesProc` is a procedure variable which can be set to compare 2 string. It is similar to `AnsiResemblesProc` (1301), and by default is set to the `SoundExProc` (1332) function.

```
StdSwitchChars = ['-','/']
```

Standard characters for the `SwitchChars` argument of `GetCmdLineArg` (1317).

```
StdWordDelims = [#0..' ', ',', '.', ';', '/', '\', ':', "'", '"',
  , '`'] + Brackets
```

Standard word delimiter values.

```
WordDelimiters : Set of Char = [#0..#255] - ['a'..'z', 'A'..'Z', '1'
  ..'9', '0']
```

Standard word delimiters, used in the `SearchBuf` (1330) call.

74.2.3 Types

```
SizeIntArray = Array of SizeInt
```

`SizeIntArray` is an auxiliary type used in `StringReplace` (1334)

```
TCompareTextProc = function(const AText: string; const AOther: string
  )
  : Boolean
```

Function prototype for comparing two string in `AnsiResemblesText` (1308)

```
TRawByteStringArray = Array of RawByteString
```

`TRawByteStringArray` defines a dynamic array of `RawByteString`. It is used in the `RawByteString` version of the `SplitCommandLine` (1333) function.

```
TRomanConversionStrictness = (rcsStrict,rcsRelaxed,rcsDontCare)
```

Table 74.2: Enumeration values for type `TRomanConversionStrictness`

Value	Explanation
<code>rcsDontCare</code>	Do not check correctness
<code>rcsRelaxed</code>	Like <code>rcsStrict</code> but allow more than 3 consecutive identical letters.
<code>rcsStrict</code>	Only accept correct roman numerals.

`TRomanConversionStrictness` is an enumerated type that can be used to decide how to react to invalid roman numerals.

rcsStrict Strict adherence to roman numerals. Up to 3 consecutive identical letters. No negative numbers. Ordering must be correct.

rcsRelaxed Same as `rcsStrict` but allow more than 3 consecutive identical letters.

rcsDontCare Do not check validity at all

`TSoundexIntLength = 1..8`

Range of allowed integer soundex lengths.

`TSoundexLength = 1..MaxInt`

Range of allowed soundex lengths.

`TStringReplaceAlgorithm = (sraDefault, sraManySmall, sraBoyerMoore)`

Table 74.3: Enumeration values for type `TStringReplaceAlgorithm`

Value	Explanation
<code>sraBoyerMoore</code>	Use a Boyer-Moore search algorithm
<code>sraDefault</code>	Use the <code>sysutils</code> algorithm, which does a straightforward linear search and replace
<code>sraManySmall</code>	Use an approach which is suitable for a string with many occurrences of the same small text

`TStringReplaceAlgorithm` enumerates the available algorithms to `StringReplace` ([1334](#))

sraDefault Use the `sysutils` algorithm, which does a straightforward linear search and replace

sraManySmall Use an approach which is suitable for a string with many occurrences of the same small text

sraBoyerMoore Use a Boyer-Moore search algorithm

Depending on the kind of data that is being treated, one or the other of these algorithms may produce faster results.

`TStringSeachOption = TStringSearchOption`

There is a typo error in the original Borland `StrUtils` unit. This type just refers to the correct `TStringSearchOption` ([1303](#)) and is provided for compatibility only.

`TStringSearchOption = (soDown, soMatchCase, soWholeWord)`

Table 74.4: Enumeration values for type `TStringSearchOption`

Value	Explanation
<code>soDown</code>	Search in down direction.
<code>soMatchCase</code>	Match case
<code>soWholeWord</code>	Search whole words only.

Possible options for `SearchBuf` ([1330](#)) call.

TStringSearchOptions = Set of TStringSearchOption

Set of options for SearchBuf ([1330](#)) call.

TUnicodeStringArray = Array of UnicodeString

TUnicodeStringArray defines a dynamic array of UnicodeString. It is used in the UnicodeString version of the SplitCommandLine ([1333](#)) function.

74.3 Procedures and functions

74.3.1 AddChar

Synopsis: Add characters to the left of a string till a certain length

Declaration: `function AddChar(C: Char; const S: string; N: Integer) : string`

Visibility: default

Description: AddChar adds characters (C) to the left of S till the length N is reached, and returns the resulting string. If the length of S is already equal to or larger than N, then no characters are added. The resulting string can be thought of as a right-aligned version of S, with length N.

Errors: None

See also: AddCharR ([1304](#)), PadLeft ([1324](#)), PadRight ([1325](#)), PadCenter ([1324](#))

74.3.2 AddCharR

Synopsis: Add chars at the end of a string till it reaches a certain length

Declaration: `function AddCharR(C: Char; const S: string; N: Integer) : string`

Visibility: default

Description: AddCharR adds characters (C) to the right of S till the length N is reached, and returns the resulting string. If the length of S is already equal to or larger than N, then no characters are added. The resulting string can be thought of as a left-aligned version of S, with length N.

Errors: None

See also: AddChar ([1304](#))

74.3.3 AnsiContainsStr

Synopsis: Checks whether a string contains a given substring

Declaration: `function AnsiContainsStr(const AText: string; const ASubText: string)
: Boolean`

Visibility: default

Description: AnsiContainsString checks whether AText contains ASubText, and returns True if this is the case, or returns False otherwise. The search is performed case-sensitive.

Errors: None

See also: AnsiContainsText ([1305](#)), AnsiEndsStr ([1305](#)), AnsiIndexStr ([1305](#)), AnsiStartsStr ([1309](#))

74.3.4 AnsiContainsText

Synopsis: Check whether a string contains a certain substring, ignoring case.

Declaration: `function AnsiContainsText(const AText: string; const ASubText: string)
: Boolean`

Visibility: default

Description: `AnsiContainsString` checks whether `AText` contains `ASubText`, and returns `True` if this is the case, or returns `False` otherwise. The search is performed case-insensitive.

See also: `AnsiContainsStr` ([1304](#)), `AnsiEndsText` ([1305](#)), `AnsiIndexText` ([1306](#)), `AnsiStartsText` ([1309](#))

74.3.5 AnsiEndsStr

Synopsis: Check whether a string ends with a certain substring

Declaration: `function AnsiEndsStr(const ASubText: string; const AText: string)
: Boolean`

Visibility: default

Description: `AnsiEndsStr` checks `AText` to see whether it ends with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-sensitive. Basically, it checks whether the position of `ASubText` equals the length of `AText` minus the length of `ASubText` plus one.

Errors: None.

See also: `AnsiEndsText` ([1305](#)), `AnsiStartsStr` ([1309](#)), `AnsiIndexStr` ([1305](#)), `AnsiContainsStr` ([1304](#))

74.3.6 AnsiEndsText

Synopsis: Check whether a string ends with a certain substring, ignoring case.

Declaration: `function AnsiEndsText(const ASubText: string; const AText: string)
: Boolean`

Visibility: default

Description: `AnsiEndsStr` checks `AText` to see whether it ends with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-insensitive. Basically, it checks whether the position of `ASubText` equals the length of `AText` minus the length of `ASubText` plus one.

Errors: None

See also: `AnsiStartsText` ([1309](#)), `AnsiEndsStr` ([1305](#)), `AnsiIndexText` ([1306](#)), `AnsiContainsText` ([1305](#))

74.3.7 AnsiIndexStr

Synopsis: Searches, observing case, for a string in an array of strings.

Declaration: `function AnsiIndexStr(const AText: string;
const AValues: Array of string) : Integer`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, the corresponding index (zero-based) in the `AValues` array is returned. If no match is found, -1 is returned. The strings are matched observing case.

Errors: None.

See also: `AnsiIndexText` (1306), `AnsiMatchStr` (1306), `AnsiMatchText` (1307)

74.3.8 `AnsiIndexText`

Synopsis: Searches, case insensitive, for a string in an array of strings.

Declaration: `function AnsiIndexText(const AText: string;
const AValues: Array of string) : Integer`

Visibility: default

Description: `AnsiIndexText` matches `AText` against each string in `AValues`. If a match is found, the corresponding index (zero-based) in the `AValues` array is returned. If no match is found, -1 is returned. The strings are matched ignoring case.

Errors: None

See also: `AnsiIndexStr` (1305), `AnsiMatchStr` (1306), `IndexStr` (1319), `MatchStr` (1322), `AnsiMatchText` (1307)

74.3.9 `AnsiLeftStr`

Synopsis: Copies a number of characters starting at the left of a string

Declaration: `function AnsiLeftStr(const AText: AnsiString; const ACount: SizeInt)
: AnsiString`

Visibility: default

Description: `AnsiLeftStr` returns the `ACount` leftmost characters from `AText`. If `ACount` is larger than the length of `AText`, only as much characters as available in `AText` will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes. This function corresponds to the Visual Basic `LeftStr` function.

Errors: None.

See also: `AnsiMidStr` (1307), `AnsiRightStr` (1309), `LeftStr` (1321), `RightStr` (1328), `MidStr` (1323), `LeftBStr` (1321), `RightBStr` (1328), `MidBStr` (1322)

74.3.10 `AnsiMatchStr`

Synopsis: Check whether a string occurs in an array of strings, observing case.

Declaration: `function AnsiMatchStr(const AText: string;
const AValues: Array of string) : Boolean`

Visibility: default

Description: `AnsiMatchStr` matches `AText` against each string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched observing case.

This function simply calls `AnsiIndexStr` (1305) and checks whether it returns -1 or not.

74.3.11 AnsiMatchText

Synopsis: Check whether a string occurs in an array of strings, disregarding case.

Declaration: `function AnsiMatchText(const AText: string;
const AValues: Array of string) : Boolean`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched ignoring case.

This function simply calls `AnsiIndexText` (1306) and checks whether it returns -1 or not.

74.3.12 AnsiMidStr

Synopsis: Returns a number of characters copied from a given location in a string

Declaration: `function AnsiMidStr(const AText: AnsiString; const AStart: SizeInt;
const ACount: SizeInt) : AnsiString`

Visibility: default

Description: `AnsiMidStr` returns `ACount` characters from `AText`, starting at position `AStart`. If `AStart+ACount` is larger than the length of `AText`, only as much characters as available in `AText` (starting from `AStart`) will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes.

This function corresponds to the Visual Basic `MidStr` function.

Errors: None

See also: `AnsiLeftStr` (1306), `AnsiRightStr` (1309), `LeftStr` (1321), `RightStr` (1328), `MidStr` (1323), `LeftBStr` (1321), `RightBStr` (1328), `MidBStr` (1322)

74.3.13 AnsiProperCase

Synopsis: Pretty-Print a string: make lowercase and capitalize first letters of words

Declaration: `function AnsiProperCase(const S: string; const WordDelims: TSysCharSet)
: string`

Visibility: default

Description: `AnsiProperCase` converts `S` to an all lowercase string, but capitalizes the first letter of every word in the string, and returns the resulting string. When searching for words, the characters in `WordDelimiters` are used to determine the boundaries of words. The constant `StdWordDelims` (1302) can be used for this.

74.3.14 AnsiReplaceStr

Synopsis: Search and replace all occurrences of a string, case sensitive.

Declaration: `function AnsiReplaceStr(const AText: string; const AFromText: string;
const AToText: string) : string`

Visibility: default

Description: `AnsiReplaceString` searches `AText` for all occurrences of the string `AFromText` and replaces them with `AToText`, and returns the resulting string. The search is performed observing case.

Errors: None.

See also: `AnsiReplaceText` ([1308](#)), `SearchBuf` ([1330](#))

74.3.15 `AnsiReplaceText`

Synopsis: Search and replace all occurrences of a string, case insensitive.

Declaration: `function AnsiReplaceText(const AText: string; const AFromText: string; const AToText: string) : string`

Visibility: default

Description: `AnsiReplaceString` searches `AText` for all occurrences of the string `AFromText` and replaces them with `AToText`, and returns the resulting string. The search is performed ignoring case.

Errors: None.

See also: `AnsiReplaceStr` ([1307](#)), `SearchBuf` ([1330](#))

74.3.16 `AnsiResemblesText`

Synopsis: Check whether 2 strings resemble each other.

Declaration: `function AnsiResemblesText(const AText: string; const AOther: string) : Boolean`

Visibility: default

Description: `AnsiResemblesText` will check whether `AnsiResemblesProc` ([1301](#)) is set. If it is not set, `False` is returned. If it is set, `AText` and `AOtherText` are passed to it and its result is returned.

Errors: None.

See also: `AnsiResemblesProc` ([1301](#)), `SoundexProc` ([1332](#))

74.3.17 `AnsiReverseString`

Synopsis: Reverse the letters in a string.

Declaration: `function AnsiReverseString(const AText: AnsiString) : AnsiString`

Visibility: default

Description: `AnsiReverseString` returns a string with all characters of `AText` in reverse order. if the result of this function equals `AText`, `AText` is called an anagram.

Errors: None.

74.3.18 AnsiRightStr

Synopsis: Copies a number of characters starting at the right of a string

Declaration: `function AnsiRightStr(const AText: AnsiString; const ACount: SizeInt)
: AnsiString`

Visibility: default

Description: `AnsiLeftStr` returns the `ACount` rightmost characters from `AText`. If `ACount` is larger than the length of `AText`, only as much characters as available in `AText` will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes.

This function corresponds to the Visual Basic `RightStr` function.

Errors: None.

See also: `AnsiLeftStr` (1306), `AnsiMidStr` (1307), `LeftStr` (1321), `RightStr` (1328), `MidStr` (1323), `LeftBStr` (1321), `RightBStr` (1328), `MidBStr` (1322)

74.3.19 AnsiStartsStr

Synopsis: Check whether a string starts with a given substring, observing case

Declaration: `function AnsiStartsStr(const ASubText: string; const AText: string)
: Boolean`

Visibility: default

Description: `AnsiStartsStr` checks `AText` to see whether it starts with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-sensitive. Basically, it checks whether the position of `ASubText` equals 1.

See also: `AnsiEndsStr` (1305), `AnsiStartsStr` (1309), `AnsiIndexStr` (1305), `AnsiContainsStr` (1304)

74.3.20 AnsiStartsText

Synopsis: Check whether a string starts with a given substring, ignoring case

Declaration: `function AnsiStartsText(const ASubText: string; const AText: string)
: Boolean`

Visibility: default

Description: `AnsiStartsText` checks `AText` to see whether it starts with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-insensitive. Basically, it checks whether the position of `ASubText` equals 1.

Errors: None.

See also: `AnsiEndsText` (1305), `AnsiStartsStr` (1309), `AnsiIndexText` (1306), `AnsiContainsText` (1305)

74.3.21 BinToHex

Synopsis: Convert a binary buffer to a hexadecimal string

Declaration:

```

procedure BinToHex(const BinBuffer: TBytes; BinBufOffset: Integer;
    var HexBuffer: TBytes; HexBufOffset: Integer;
    Count: Integer); Overload
procedure BinToHex(BinValue: Pointer; HexValue: PWideChar;
    BinBufSize: Integer); Overload
procedure BinToHex(const BinValue; HexValue: PWideChar;
    BinBufSize: Integer); Overload
procedure BinToHex(BinValue: PAnsiChar; HexValue: PAnsiChar;
    BinBufSize: Integer); Overload
procedure BinToHex(BinValue: PAnsiChar; HexValue: PWideChar;
    BinBufSize: Integer); Overload
procedure BinToHex(const BinValue; HexValue: PAnsiChar;
    BinBufSize: Integer); Overload
procedure BinToHex(BinValue: Pointer; HexValue: PAnsiChar;
    BinBufSize: Integer); Overload

```

Visibility: default

Description: `BinToHex` converts the byte values in `BinValue` to a string consisting of 2-character hexadecimal strings in `HexValue`. `BufSize` specifies the length of `BinValue`, which means that `HexValue` must have size $2 * \text{BufSize}$.

For example a buffer containing the byte values 255 and 0 will be converted to FF00.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `HexToBin` ([1318](#))

74.3.22 ContainsStr

Synopsis: Check whether one text contains another (case sensitive)

Declaration:

```

function ContainsStr(const AText: string; const ASubText: string)
    : Boolean

```

Visibility: default

Description: `ContainsStr` is an alias for `AnsiContainsStr` ([1304](#))

See also: `AnsiContainsStr` ([1304](#))

74.3.23 ContainsText

Synopsis: Check whether one text contains another (case insensitive)

Declaration:

```

function ContainsText(const AText: string; const ASubText: string)
    : Boolean

```

Visibility: default

Description: `ContainsText` is an alias for `AnsiContainsText` ([1305](#))

See also: `AnsiContainsText` ([1305](#))

74.3.24 Copy2Space

Synopsis: Returns all characters in a string till the first space character (not included).

Declaration: `function Copy2Space(const S: string) : string`

Visibility: default

Description: `Copy2Space` determines the position of the first space in the string `S` and returns all characters up to this position. The space character itself is not included in the result string. The string `S` is left untouched. If there is no space in `S`, then the whole string `S` is returned.

This function simply calls `Copy2Symb` (1311) with the space (ASCII code 32) as the symbol argument.

Errors: None.

See also: `Copy2Symb` (1311), `Copy2SpaceDel` (1311)

74.3.25 Copy2SpaceDel

Synopsis: Deletes and returns all characters in a string till the first space character (not included).

Declaration: `function Copy2SpaceDel(var S: string) : string`

Visibility: default

Description: `Copy2SpaceDel` determines the position of the first space in the string `S` and returns all characters up to this position. The space character itself is not included in the result string. All returned characters, including the space, are deleted from the string `S`, after which it is right-trimmed. If there is no space in `S`, then the whole string `S` is returned, and `S` itself is emptied.

This function simply calls `Copy2SymbDel` (1312) with the space (ASCII code 32) as the symbol argument.

Errors: None.

See also: `Copy2SymbDel` (1312), `Copy2Space` (1311)

74.3.26 Copy2Symb

Synopsis: Returns all characters in a string till a given character (not included).

Declaration: `function Copy2Symb(const S: string; Symb: Char) : string`

Visibility: default

Description: `Copy2Symb` determines the position of the first occurrence of `Symb` in the string `S` and returns all characters up to this position. The `Symb` character itself is not included in the result string. The string `S` is left untouched. If `Symb` does not appear in `S`, then the whole of `S` is returned.

Errors: None.

See also: `Copy2Space` (1311), `Copy2SymbDel` (1312)

74.3.27 Copy2SymbDel

Synopsis: Deletes and returns all characters in a string till a given character (not included).

Declaration: `function Copy2SymbDel(var S: string; Symb: Char) : string`

Visibility: default

Description: `Copy2SymbDel` determines the position of the first occurrence of `Symb` in the string `S` and returns all characters up to this position. The `Symb` character itself is not included in the result string. All returned characters and the `Symb` character, are deleted from the string `S`, after which it is right-trimmed. If `Symb` does not appear in `S`, then the whole of `S` is returned, and `S` itself is emptied.

Errors: None.

See also: `Copy2SpaceDel` ([1311](#)), `Copy2Symb` ([1311](#))

74.3.28 Dec2Numb

Synopsis: Convert a decimal number to a string representation, using given a base.

Declaration: `function Dec2Numb(N: LongInt; Len: Byte; Base: Byte) : string`

Visibility: default

Description: `Dec2Numb` converts `N` to its representation using base `Base`. `N` must be a positive integer. The resulting string is left-padded with zeroes till it has length `Len`. `Base` must be in the range 2-36 to be meaningful, but no checking on this is performed.

Errors: If `Base` is out of range, the resulting string will contain unreadable (non-alphanumeric) characters.

See also: `Hex2Dec` ([1318](#)), `IntToBin` ([1320](#)), `intToRoman` ([1320](#)), `RomanToInt` ([1329](#))

74.3.29 DecodeSoundexInt

Synopsis: Decodes the integer representation of a soundex code and returns the original soundex code.

Declaration: `function DecodeSoundexInt(AValue: Integer) : string`

Visibility: default

Description: `DecodeSoundexInt` converts the integer value `AValue` to a soundex string. It performs the reverse operation of the `SoundexInt` ([1331](#)) function. The result is the soundex string corresponding to `AValue`.

Errors: None.

See also: `SoundexInt` ([1331](#)), `DecodeSoundexWord` ([1312](#)), `Soundex` ([1331](#))

74.3.30 DecodeSoundexWord

Synopsis: Decodes the word-sized representation of a soundex code and returns the original soundex code.

Declaration: `function DecodeSoundexWord(AValue: Word) : string`

Visibility: default

Description: `DecodeSoundexWord` converts the integer value `AValue` to a soundex string. It performs the reverse operation of the `SoundexWord` ([1332](#)) function. The result is the soundex string corresponding to `AValue`.

Errors: None.

See also: SoundexInt ([1331](#)), DecodeSoundexInt ([1312](#)), Soundex ([1331](#))

74.3.31 DelChars

Synopsis: Delete all occurrences of a given character from a string.

Declaration: `function DelChars(const S: string; Chr: Char) : string`
`function DelChars(const S: string; Chars: TSysCharSet) : string`

Visibility: default

Description: DelChars returns a copy of S with all Chr characters removed from it.

Errors: None.

See also: DelSpace ([1313](#)), DelSpace1 ([1313](#))

74.3.32 DelSpace

Synopsis: Delete all occurrences of a space from a string.

Declaration: `function DelSpace(const S: string) : string`

Visibility: default

Description: DelSpace returns a copy of S with all spaces (ASCII code 32) removed from it.

Errors: None.

See also: DelChars ([1313](#)), DelSpace1 ([1313](#))

74.3.33 DelSpace1

Synopsis: Reduces sequences of space characters to 1 space character.

Declaration: `function DelSpace1(const S: string) : string`

Visibility: default

Description: DelSpace1 returns a copy of S with all sequences of spaces reduced to 1 space.

Errors: None.

See also: DelChars ([1313](#)), DelSpace ([1313](#))

74.3.34 DupeString

Synopsis: Creates and concatenates N copies of a string

Declaration: `function DupeString(const AText: string; ACount: Integer) : string`

Visibility: default

Description: DupeString returns a string consisting of ACount concatenations of AText. Thus

```
DupeString('1234567890', 3);
```

will produce a string

```
'123456789012345678901234567890'
```

Errors: None.

74.3.35 EndsStr

Synopsis: Check whether one string ends with another

Declaration: `function EndsStr(const ASubText: string; const AText: string) : Boolean`

Visibility: default

Description: `StartsText` checks whether `aText` ends with `aSubText` and returns `True` if it does. i.e. it returns `true` if the last characters of `aText` are `aSubText`. It follows that the length of `aText` must be at least the length of `aSubText`. The comparison is made case-sensitive. If you wish to compare case-insensitively, use `EndsText` (1314) instead.

See also: `AnsiEndsStr` (1305), `EndsText` (1314), `StartsText` (1334)

74.3.36 EndsText

Synopsis: Check whether one text ends with another

Declaration: `function EndsText(const ASubText: string; const AText: string) : Boolean`

Visibility: default

Description: `StartsText` checks whether `aText` ends with `aSubText` and returns `True` if it does. i.e. it returns `true` if the last characters of `aText` are `aSubText`. It follows that the length of `aText` must be at least the length of `aSubText`. The comparison is made case-insensitive. If you wish to compare case-sensitively, use `EndsStr` (1314) instead.

See also: `AnsiEndsStr` (1305), `EndsStr` (1314), `StartsText` (1334)

74.3.37 ExtractDelimited

Synopsis: Extract the N-th delimited part from a string.

Declaration: `function ExtractDelimited(N: Integer; const S: string;
const Delims: TSysCharSet) : string`

Visibility: default

Description: `ExtractDelimited` extracts the N-th part from the string `S`. The set of characters in `Delims` are used to mark part boundaries. When a delimiter is encountered, a new part is started and the old part is ended. Another way of stating this is that any (possibly empty) series of characters not in `Delims`, situated between 2 characters in `Delims`, it is considered as piece of a part. This means that if 2 delimiter characters appear next to each other, there is an empty part between it. If an N-th part cannot be found, an empty string is returned. However, unlike `ExtractWord` (1315), an empty string is a valid return value, i.e. a part can be empty.

The predefined constant `StdWordDelims` (1302) can be used for the `Delims` argument. The predefined constant `Brackets` (1301) would be better suited the `Delims` argument e.g. in case factors in a mathematical expression are searched.

Errors: None.

See also: `ExtractSubStr` (1315), `ExtractWord` (1315), `ExtractWordPos` (1315)

74.3.38 ExtractSubstr

Synopsis: Extract a word from a string, starting at a given position in the string.

Declaration: `function ExtractSubstr(const S: string; var Pos: Integer;
const Delims: TSysCharSet) : string`

Visibility: default

Description: `ExtractSubStr` returns all characters from `S` starting at position `Pos` till the first character in `Delims`, or till the end of `S` is reached. The delimiter character is not included in the result. `Pos` is then updated to point to the next first non-delimiter character in `S`. If `Pos` is larger than the Length of `S`, an empty string is returned.

The predefined constant `StdWordDelims` (1302) can be used for the `Delims` argument.

Errors: None.

See also: `ExtractDelimited` (1314), `ExtractWord` (1315), `ExtractWordPos` (1315)

74.3.39 ExtractWord

Synopsis: Extract the N-th word out of a string.

Declaration: `function ExtractWord(N: Integer; const S: string;
const WordDelims: TSysCharSet) : string`

Visibility: default

Description: `ExtractWord` extracts the N-th word from the string `S`. The set of characters in `WordDelims` are used to mark word boundaries. A word is defined as any non-empty sequence of characters which are not present in `WordDelims`: if a character is not in `WordDelims`, it is considered as part of a word. If an N-th word cannot be found, an empty string is returned.

Unlike `ExtractDelimited` (1314), an empty string is not a valid return value, i.e. is not a word. If an empty string is returned, the index `N` was out of range.

The predefined constant `StdWordDelims` (1302) can be used for the `WordDelims` argument.

Errors: None.

See also: `ExtractWordPos` (1315), `ExtractSubStr` (1315), `ExtractDelimited` (1314), `IsWordPresent` (1321), `WordCount` (1337), `WordPosition` (1337)

74.3.40 ExtractWordPos

Synopsis: Extract a word from a string, and return the position where it was located in the string.

Declaration: `function ExtractWordPos(N: Integer; const S: string;
const WordDelims: TSysCharSet; out Pos: Integer)
: string`

Visibility: default

Description: `ExtractWordPos` extracts the N-th word from the string `S` and returns the position of this word in `Pos`. The set of characters in `WordDelims` are used to mark word boundaries. A word is defined as any non-empty sequence of characters which are not present in `WordDelims`: if a character is not in `WordDelims`, it is considered as part of a word. If an N-th word cannot be found, an empty string is returned and `Pos` is zero.

Unlike `ExtractDelimited` (1314), an empty string is not a valid return value, i.e. is not a word. If an empty string is returned, the index `N` was out of range.

The predefined constant `StdWordDelims` (1302) can be used for the `WordDelims` argument.

Errors: None.

See also: `ExtractWord` (1315), `ExtractSubStr` (1315), `IsWordPresent` (1321), `WordCount` (1337), `WordPosition` (1337)

74.3.41 FindMatchesBoyerMooreCaseInsensitive

Synopsis: Find case-insensitive matches of a string using a Boyer-Moore algorithm

Declaration:

```
function FindMatchesBoyerMooreCaseInsensitive(const S: PChar;
                                             const OldPattern: PChar;
                                             const SSize: SizeInt;
                                             const OldPatternSize: SizeInt;
                                             out aMatches: SizeIntArray;
                                             const aMatchAll: Boolean)
                                             : Boolean

function FindMatchesBoyerMooreCaseInsensitive(const S: string;
                                             const OldPattern: string;
                                             out aMatches: SizeIntArray;
                                             const aMatchAll: Boolean)
                                             : Boolean
```

Visibility: default

Description: `FindMatchesBoyerMooreCaseInsensitive` finds occurrences of `OldPattern` (with length `OldPatternSize`) in `S` (with length `SSize`). The search is performed case-insensitively, and all (zero based) positions are reported in `aMatches`. If `aMatchAll` is `True`, all positions will be reported. If `aMatchAll` is `False`, only the first position is reported.

Errors: None.

See also: `FindMatchesBoyerMooreCaseSensitive` (1316), `StringReplace` (1334)

74.3.42 FindMatchesBoyerMooreCaseSensitive

Synopsis: Find case-sensitive matches of a string using a Boyer-Moore algorithm

Declaration:

```
function FindMatchesBoyerMooreCaseSensitive(const S: PChar;
                                             const OldPattern: PChar;
                                             const SSize: SizeInt;
                                             const OldPatternSize: SizeInt;
                                             out aMatches: SizeIntArray;
                                             const aMatchAll: Boolean)
                                             : Boolean

function FindMatchesBoyerMooreCaseSensitive(const S: string;
                                             const OldPattern: string;
                                             out aMatches: SizeIntArray;
                                             const aMatchAll: Boolean)
                                             : Boolean
```

Visibility: default

Description: `FindMatchesBoyerMooreCaseSensitive` finds occurrences of `OldPattern` (with length `OldPatternSize`) in `S` (with length `SSize`). The search is performed case-sensitively, and all (zero based) positions are reported in `aMatches`. If `aMatchAll` is `True`, all positions will be reported. If `aMatchAll` is `False`, only the first position is reported.

Errors: None.

See also: `FindMatchesBoyerMooreCaseInsensitive` ([1316](#)), `StringReplace` ([1334](#))

74.3.43 FindPart

Synopsis: Search for a substring in a string, using wildcards.

Declaration: `function FindPart(const HelpWilds: string; const InputStr: string)
: SizeInt`

Visibility: default

Description: `FindPart` searches the string `InputStr` and returns the first string that matches the wildcards specification in `HelpWilds`. If no match is found, an empty string is returned. Currently, the only valid wildcards is the "?" character.

Errors: None.

See also: `SearchBuf` ([1330](#))

74.3.44 GetCmdLineArg

Synopsis: Returns the command-line argument following the given switch.

Declaration: `function GetCmdLineArg(const Switch: string; SwitchChars: TSysCharSet)
: string`

Visibility: default

Description: `GetCmdLineArg` returns the value for the `Switch` option on the command-line, if any is given. Command-line arguments are considered switches if they start with one of the characters in the `SwitchChars` set. The value is the command-line argument following the switch command-line argument.

Gnu-style (long) Options of the form `switch=value` are not supported.

The `StdSwitchChars` ([1302](#)) constant can be used as value for the `SwitchChars` parameter.

Errors: The `GetCmdLineArg` does not check whether the value of the option does not start with a switch character. i.e.

```
myprogram -option1 -option2
```

will result in "-option2" as the result of the `GetCmdLineArg` call for `option1`.

See also: `StdSwitchChars` ([1302](#))

74.3.45 Hex2Dec

Synopsis: Converts a hexadecimal string to a decimal value

Declaration: `function Hex2Dec(const S: string) : LongInt`

Visibility: default

Description: `Hex2Dec` converts the hexadecimal value in the string `S` to its decimal value. Unlike the standard `Val` or `StrToInt` functions, there need not be a `$` sign in front of the hexadecimal value to indicate that it is indeed a hexadecimal value.

Errors: If `S` does not contain a valid hexadecimal value, an `EConvertError` exception will be raised.

See also: `Dec2Numb` ([1312](#)), `IntToBin` ([1320](#)), `intToRoman` ([1320](#)), `RomanToInt` ([1329](#))

74.3.46 Hex2Dec64

Synopsis: Convert hexadecimal value to 64-bit integer

Declaration: `function Hex2Dec64(const S: string) : Int64`

Visibility: default

Description: `Hex2Dec64` converts the hexadecimal number in `S` to a 64-bit value and returns the result. It is equivalent to `StrToInt('$'+S)`.

See also: `Hex2Dec` ([1318](#))

74.3.47 HexToBin

Synopsis: Convert a hexadecimal string to a binary buffer

Declaration: `function HexToBin(HexValue: PChar; BinValue: PChar; BinBufSize: Integer) : Integer`

Visibility: default

Description: `HexToBin` scans the hexadecimal string representation in `HexValue` and transforms every 2 character hexadecimal number to a byte and stores it in `BinValue`. The buffer size is the size of the binary buffer. Scanning will stop if the size of the binary buffer is reached or when an invalid character is encountered. The return value is the number of stored bytes.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `BinToHex` ([1309](#))

74.3.48 IfThen

Synopsis: Returns one of two strings, depending on a boolean expression

Declaration: `function IfThen(AValue: Boolean; const ATrue: string; const AFalse: string) : string; Overload`

Visibility: default

Description: `IfThen` returns `ATrue` if `AValue` is `True`, and returns `AFalse` if `AValue` is `false`.

Errors: None.

See also: `AnsiMatchStr` ([1306](#)), `AnsiMatchText` ([1307](#))

74.3.49 in(string,):Boolean

Synopsis: Check presence of string in an array of strings

Declaration: `operator in(const AText: string; const AValues: Array of string)
: Boolean`

Visibility: default

Description: This is the (string) operator equivalent of `IndexStr` ([1319](#))

See also: `IndexStr` ([1319](#))

74.3.50 in(UnicodeString,):Boolean

Synopsis: Check presence of string in an array of strings

Declaration: `operator in(const AText: UnicodeString;
const AValues: Array of UnicodeString) : Boolean`

Visibility: default

Description: This is the (unicode string) operator equivalent of `IndexStr` ([1319](#))

See also: `IndexStr` ([1319](#))

74.3.51 IndexStr

Synopsis: Searches, observing case, for a string in an array of strings.

Declaration: `function IndexStr(const AText: UnicodeString;
const AValues: Array of UnicodeString) : Integer
function IndexStr(const AText: string; const AValues: Array of string)
: Integer`

Visibility: default

Description: `IndexStr` matches `AText` against each Unicode string in `AValues`. If a match is found, the corresponding index (zero-based) in the `AValues` array is returned. If no match is found, -1 is returned. The strings are matched observing case.

Errors: None.

See also: `AnsiIndexText` ([1306](#)), `MatchStr` ([1322](#)), `AnsiIndexStr` ([1305](#))

74.3.52 IndexText

Synopsis: Index of text in a list of values

Declaration: `function IndexText(const AText: string; const AValues: Array of string)
: Integer
function IndexText(const AText: UnicodeString;
const AValues: Array of UnicodeString) : Integer`

Visibility: default

Description: `IndexText` returns the index of the string in the array `aValues` that matches `aText`, and -1 otherwise. The comparison is done case insensitively. If you wish to compare case sensitively, use `IndexStr` ([1319](#)) instead.

See also: `IndexStr` ([1319](#)), `MatchText` ([1322](#)), `AnsiIndexText` ([1306](#))

74.3.53 IntToBin

Synopsis: Converts an integer to a binary string representation, inserting spaces at fixed locations.

Declaration:

```
function IntToBin(Value: LongInt; Digits: Integer; Spaces: Integer)
                : string
function IntToBin(Value: LongInt; Digits: Integer) : string
function intToBin(Value: Int64; Digits: Integer) : string
```

Visibility: default

Description: `IntToBin` converts `Value` to a string with its binary (base 2) representation. The resulting string contains `Digits` digits, with spaces inserted every `Spaces` digits. `Spaces` equal to zero yields a result without spacing. If `Digits` is larger than 32, it is truncated to 32.

See also: `Hex2Dec` ([1318](#)), `IntToRoman` ([1320](#))

74.3.54 IntToRoman

Synopsis: Represent an integer with roman numerals

Declaration:

```
function IntToRoman(Value: LongInt) : string
```

Visibility: default

Description: `IntToRoman` converts `Value` to a string with the Roman representation of `Value`. Number up to 1 million can be represented this way.

Errors: None.

See also: `RomanToInt` ([1329](#)), `Hex2Dec` ([1318](#)), `IntToBin` ([1320](#))

74.3.55 IsEmptyStr

Synopsis: Check whether a string is empty, disregarding whitespace characters

Declaration:

```
function IsEmptyStr(const S: string; const EmptyChars: TSysCharSet)
                : Boolean
```

Visibility: default

Description: `IsEmptyStr` returns `True` if the string `S` only contains characters whitespace characters, all characters in `EmptyChars` are considered whitespace characters. If a character not present in `EmptyChars` is found in `S`, `False` is returned.

Errors: None.

See also: `IsWild` ([1320](#)), `FindPart` ([1317](#)), `IsWordPresent` ([1321](#))

74.3.56 IsWild

Synopsis: Check whether a string matches a wildcard search expression.

Declaration:

```
function IsWild(InputStr: string; Wilds: string; IgnoreCase: Boolean)
                : Boolean
```

Visibility: default

Description: `IsWild` checks `InputStr` for the presence of the `Wilds` string. `Wilds` may contain "?" and "*" wildcard characters, which have their usual meaning: "*" matches any series of characters, possibly empty. "?" matches any single character. The function returns `True` if a string is found that matches `Wilds`, `False` otherwise.

If `IgnoreCase` is `True`, the non-wildcard characters are matched case insensitively. If it is `False`, case is observed when searching.

Errors: None.

See also: `SearchBuf` (1330), `FindPart` (1317)

74.3.57 IsWordPresent

Synopsis: Check for the presence of a word in a string.

Declaration: `function IsWordPresent(const W: string; const S: string;
const WordDelims: TSysCharSet) : Boolean`

Visibility: default

Description: `IsWordPresent` checks for the presence of the word `W` in the string `S`. Words are delimited by the characters found in `WordDelims`. The function returns `True` if a match is found, `False` otherwise. The search is performed case sensitive.

This function is equivalent to the `SearchBuf` (1330) function with the `soWholeWords` option specified.

Errors: None.

See also: `SearchBuf` (1330)

74.3.58 LeftBStr

Synopsis: Copies Count characters starting at the left of a string.

Declaration: `function LeftBStr(const AText: AnsiString; const AByteCount: SizeInt)
: AnsiString`

Visibility: default

Description: `LeftBStr` returns a string containing the leftmost `AByteCount` bytes from the string `AText`. If `AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned.

Errors: None.

See also: `LeftStr` (1321), `AnsiLeftStr` (1306), `RightBStr` (1328), `MidBStr` (1322)

74.3.59 LeftStr

Synopsis: Copies Count characters starting at the left of a string.

Declaration: `function LeftStr(const AText: AnsiString; const ACount: SizeInt)
: AnsiString
function LeftStr(const AText: WideString; const ACount: SizeInt)
: WideString`

Visibility: default

Description: `LeftStr` returns a string containing the leftmost `ACount` characters from the string `AText` . If `ACount` is larger than the length (in characters) of `AText` , only as many characters as available are returned.

Errors: None.

See also: `LeftBStr` ([1321](#)), `AnsiLeftStr` ([1306](#)), `RightStr` ([1328](#)), `MidStr` ([1323](#))

74.3.60 MatchStr

Synopsis: Check whether a string occurs in an array of strings, observing case.

Declaration:

```
function MatchStr(const AText: UnicodeString;
                  const AValues: Array of UnicodeString) : Boolean
function MatchStr(const AText: string; const AValues: Array of string)
                  : Boolean
```

Visibility: default

Description: `MatchStr` matches `AText` against each Unicode string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched observing case.

This function simply calls `IndexStr` ([1319](#)) and checks whether it returns -1 or not.

74.3.61 MatchText

Synopsis: Check if a string is in a list of values

Declaration:

```
function MatchText(const AText: string; const AValues: Array of string)
                  : Boolean
function MatchText(const AText: UnicodeString;
                  const AValues: Array of UnicodeString) : Boolean
```

Visibility: default

Description: `MatchText` returns `True` if `aText` equals one of the strings in `aValues`. The comparison is done case insensitively. If you wish to compare case sensitively, use `MatchStr` ([1322](#)) instead.

See also: `MatchStr` ([1322](#)), `AnsiMatchText` ([1307](#)), `IndexText` ([1319](#))

74.3.62 MidBStr

Synopsis: Copies a number of characters starting at a given position in a string.

Declaration:

```
function MidBStr(const AText: AnsiString; const AByteStart: SizeInt;
                 const AByteCount: SizeInt) : AnsiString
```

Visibility: default

Description: `MidBStr` returns a string containing the first `AByteCount` bytes from the string `AText` starting at position `AByteStart`. If `AByteStart+AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned. If `AByteStart` is less than 1 or larger than the length of `AText`, then no characters are returned.

Errors: None.

See also: `LeftBStr` ([1321](#)), `AnsiMidStr` ([1307](#)), `RightBStr` ([1328](#)), `MidStr` ([1323](#))

74.3.63 MidStr

Synopsis: Copies a number of characters starting at a given position in a string.

Declaration:

```
function MidStr(const AText: AnsiString; const AStart: SizeInt;
               const ACount: SizeInt) : AnsiString
function MidStr(const AText: WideString; const AStart: SizeInt;
               const ACount: SizeInt) : WideString
```

Visibility: default

Description: `MidStr` returns a string containing the first `ACount` bytes from the string `AText` starting at position `AStart`. If `AStart+ACount` is larger than the length (in characters) of `AText`, only as many characters as available are returned. If `AStart` is less than 1 or larger than the length of `AText`, then no characters are returned.

This function is equivalent to the standard `Copy` function, and is provided for completeness only.

Errors: None.

See also: `LeftStr` ([1321](#)), `AnsiMidStr` ([1307](#)), `RightStr` ([1328](#)), `MidBStr` ([1322](#))

74.3.64 NaturalCompareText

Synopsis: Compare using natural sort

Declaration:

```
function NaturalCompareText(const S1: string; const S2: string)
                           : Integer
function NaturalCompareText(const Str1: string; const Str2: string;
                           const ADecSeparator: Char;
                           const AThousandSeparator: Char) : Integer
```

Visibility: default

Description: `NaturalCompareText` will compare 2 strings and return one of the following values:

- 1 If `S1` comes before `S2`
- 0 If `S1` equals `S2`
- 1 If `S1` comes after `S2`

When `S1` and `S2` are integer or floating point values, the actual values are compared. Thus '12' will come after '2'. If either of the values is not a valid integer or floating point values, the strings are compared case insensitively as texts using `CompareText` ([1670](#))

A decimal separator and thousands separator can optionally be specified in `ADecSeparator`, `AThousandSeparator`. If none are specified, the defaults from the system unit will be used.

See also: `CompareText` ([1301](#))

74.3.65 NPos

Synopsis: Returns the position of the N-th occurrence of a substring in a string.

Declaration:

```
function NPos(const C: string; S: string; N: Integer) : SizeInt
```

Visibility: default

Description: `NPos` checks `S` for the position of the N-th occurrence of `C`. If `C` occurs less than `N` times in `S`, or does not occur in `S` at all, 0 is returned. If `N` is less than 1, zero is returned.

Errors: None.

See also: [WordPosition \(1337\)](#), [FindPart \(1317\)](#)

74.3.66 Numb2Dec

Synopsis: Converts a string representation of a number to its numerical value, given a certain base.

Declaration: `function Numb2Dec(S: string; Base: Byte) : LongInt`

Visibility: default

Description: `Numb2Dec` converts the number in string `S` to a decimal value. It assumes the number is represented using `Base` as the base. No checking is performed to see whether `S` contains a valid number using base `Base`.

Errors: None.

See also: [Hex2Dec \(1318\)](#), [Numb2USA \(1324\)](#)

74.3.67 Numb2USA

Synopsis: Insert thousand separators.

Declaration: `function Numb2USA(const S: string) : string`

Visibility: default

Description: `Numb2USA` inserts thousand separators in the string `S` at the places where they are supposed to be, i.e. every 3 digits. The string `S` should contain a valid integer number, i.e. no digital number. No checking on this is done.

Errors: None.

74.3.68 PadCenter

Synopsis: Pad the string to a certain length, so the string is centered.

Declaration: `function PadCenter(const S: string; Len: SizeInt) : string`

Visibility: default

Description: `PadCenter` add spaces to the left and right of the string `S` till the result reaches length `Len`. If the number of spaces to add is odd, then the extra space will be added at the end. If the string `S` has length equal to or larger than `Len`, no spaces are added, and the string `S` is returned as-is.

Errors: None.

See also: [PadLeft \(1324\)](#), [PadRight \(1325\)](#), [AddChar \(1304\)](#), [AddCharR \(1304\)](#)

74.3.69 PadLeft

Synopsis: Add spaces to the left of a string till a certain length is reached.

Declaration: `function PadLeft(const S: string; N: Integer) : string`

Visibility: default

Description: `PadLeft` add spaces to the left of the string `S` till the result reaches length `Len`. If the string `S` has length equal to or larger than `Len`, no spaces are added, and the string `S` is returned as-is. The resulting string is `S`, right-justified on length `Len`.

Errors: None.

See also: `PadLeft` ([1324](#)), `PadCenter` ([1324](#)), `AddChar` ([1304](#)), `AddCharR` ([1304](#))

74.3.70 `PadRight`

Synopsis: Add spaces to the right of a string till a certain length is reached.

Declaration: `function PadRight(const S: string; N: Integer) : string`

Visibility: default

Description: `PadRight` add spaces to the right of the string `S` till the result reaches length `Len`. If the string `S` has length equal to or larger than `Len`, no spaces are added, and the string `S` is returned as-is. The resulting string is `S`, left-justified on length `Len`.

Errors: None.

See also: `PadLeft` ([1324](#)), `PadCenter` ([1324](#)), `AddChar` ([1304](#)), `AddCharR` ([1304](#))

74.3.71 `PosEx`

Synopsis: Search for the occurrence of a character in a string, starting at a certain position.

Declaration: `function PosEx(const SubStr: string; const S: string; Offset: SizeUInt) : SizeInt`
`function PosEx(const SubStr: string; const S: string) : SizeInt`
`function PosEx(c: Char; const S: string; Offset: SizeUInt) : SizeInt`
`function PosEx(const SubStr: UnicodeString; const S: UnicodeString; Offset: SizeUInt) : SizeInt`
`function PosEx(c: WideChar; const S: UnicodeString; Offset: SizeUInt) : SizeInt`
`function PosEx(const SubStr: UnicodeString; const S: UnicodeString) : SizeInt`

Visibility: default

Description: `PosEx` returns the position of the first occurrence of the character `C` or the substring `SubStr` in the string `S`, starting the search at position `Offset` (default 1). If `C` or `SubStr` does not occur in `S` after the given `Offset`, zero is returned. The position `Offset` is also searched.

Errors: None.

See also: `NPos` ([1323](#)), `AnsiContainsText` ([1305](#)), `AnsiContainsStr` ([1304](#))

74.3.72 `PosSet`

Synopsis: Return the position in a string of any character out of a set of characters

Declaration: `function PosSet(const c: TSysCharSet; const s: ansistring) : SizeInt`
`function PosSet(const c: string; const s: ansistring) : SizeInt`

Visibility: default

Description: `PosSet` returns the position in `s` of the first found character which is in the set `c`. If none of the characters in `c` is found in `s`, then 0 is returned.

Errors: None.

See also: `PosEx` ([1325](#)), `PosSetEx` ([1326](#)), `#rtl.system.pos` ([1518](#)), `RPosEx` ([1330](#))

74.3.73 PosSetEx

Synopsis: Return the position in a string of any character out of a set of characters, starting at a certain position

Declaration:

```
function PosSetEx(const c: TSysCharSet; const s: ansistring;
                  count: Integer) : SizeInt
function PosSetEx(const c: string; const s: ansistring; count: Integer)
                  : SizeInt
```

Visibility: default

Description: `PosSetEx` returns the position in `s` of the first found character which is in the set `c`, and starts searching at character position `Count`. If none of the characters in `c` is found in `s`, then 0 is returned.

Errors: None.

See also: `PosEx` ([1325](#)), `PosSet` ([1325](#)), `#rtl.system.pos` ([1518](#)), `RPosEx` ([1330](#))

74.3.74 RandomFrom

Synopsis: Choose a random string from an array of strings.

Declaration:

```
function RandomFrom(const AValues: Array of string) : string; Overload
```

Visibility: default

Description: `RandomFrom` picks at random a valid index in the array `AValues` and returns the string at that position in the array.

Errors: None.

See also: `AnsiMatchStr` ([1306](#)), `AnsiMatchText` ([1307](#))

74.3.75 Removeleadingchars

Synopsis: Remove any leading characters in a set from a string

Declaration:

```
procedure Removeleadingchars(var S: AnsiString; const CSet: TSysCharSet)
```

Visibility: default

Description: `Removeleadingchars` removes any starting characters from `S` that appear in the set `CSet`. It stops removing characters as soon as a character not in `CSet` is encountered. This is similar in behaviour to `TrimLeft` ([1779](#)) which used whitespace as the set.

Errors: None.

See also: `TrimLeft` ([1779](#)), `RemoveTrailingChars` ([1327](#)), `RemovePadChars` ([1327](#)), `TrimLeftSet` ([1336](#))

74.3.76 RemovePadChars

Synopsis: Remove any trailing or leading characters in a set from a string

Declaration: `procedure RemovePadChars(var S: AnsiString; const CSet: TSysCharSet)`

Visibility: default

Description: `RemovePadChars` removes any leading trailing characters from `S` that appear in the set `CSet`, i.e. it starts with the last character and works its way to the start of the string, and it stops removing characters as soon as a character not in `CSet` is encountered. Then the same procedure is repeated starting from the beginning of the string. This is similar in behaviour to `Trim` (1779) which used whitespace as the set.

Errors: None.

See also: `Trim` (1779), `RemoveLeadingChars` (1326), `RemoveTrailingChars` (1327), `TrimSet` (1336), `TrimLeftSet` (1336), `TrimRightSet` (1336)

74.3.77 RemoveTrailingChars

Synopsis: Remove any trailing characters in a set from a string

Declaration: `procedure RemoveTrailingChars(var S: AnsiString;
const CSet: TSysCharSet)`

Visibility: default

Description: `RemoveTrailingChars` removes any trailing characters from `S` that appear in the set `CSet`, i.e. it starts with the last character and works its way to the start of the string. It stops removing characters as soon as a character not in `CSet` is encountered. This is similar in behaviour to `TrimRight` (1780) which used whitespace as the set.

See also: `TrimRight` (1779), `RemoveLeadingChars` (1326), `TrimRightSet` (1336)

74.3.78 ReplaceStr

Synopsis: Replace strings case-sensitively

Declaration: `function ReplaceStr(const AText: string; const AFromText: string;
const AToText: string) : string`

Visibility: default

Description: `ReplaceStr` is a utility function that scans `AText` and replaces all occurrences of `AFromText` with `AToText` and returns the resulting string. It simply calls `StringReplace` (1755) with the appropriate options.

See also: `StringReplace` (1755), `ReplaceText` (1327)

74.3.79 ReplaceText

Synopsis: Replace strings case-insensitively

Declaration: `function ReplaceText(const AText: string; const AFromText: string;
const AToText: string) : string`

Visibility: default

Description: `ReplaceText` is a utility function that scans `AText` and replaces all occurrences of `AFromText` (case insensitive) with `AToText` and returns the resulting string. It simply calls `StringReplace` (1755) with the appropriate options.

See also: `StringReplace` (1755), `ReplaceText` (1327)

74.3.80 ResemblesText

Synopsis: Check whether 2 strings resemble each other

Declaration: `function ResemblesText(const AText: string; const AOther: string)
: Boolean`

Visibility: default

Description: `ResemblesText` is an alias for `AnsiResemblesText` (1308)

See also: `AnsiResemblesText` (1308)

74.3.81 ReverseString

Synopsis: Reverse characters in a string

Declaration: `function ReverseString(const AText: string) : string`

Visibility: default

Description: `ReverseString` returns a string, made up of the characters in string `AText`, in reverse order.

Errors: None.

See also: `RandomFrom` (1326)

74.3.82 RightBStr

Synopsis: Copy a given number of characters (bytes), counting from the right of a string.

Declaration: `function RightBStr(const AText: AnsiString; const AByteCount: SizeInt)
: AnsiString`

Visibility: default

Description: `RightBStr` returns a string containing the rightmost `AByteCount` bytes from the string `AText`. If `AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned.

Errors: None.

See also: `LeftBStr` (1321), `AnsiRightStr` (1309), `RightStr` (1328), `MidBStr` (1322)

74.3.83 RightStr

Synopsis: Copy a given number of characters, counting from the right of a string.

Declaration: `function RightStr(const AText: AnsiString; const ACount: SizeInt)
: AnsiString
function RightStr(const AText: WideString; const ACount: SizeInt)
: WideString`

Visibility: default

Description: `RightStr` returns a string containing the rightmost `ACount` characters from the string `AText`. If `ACount` is larger than the length (in characters) of `AText`, only as many characters as available are returned.

Errors: None.

See also: `LeftStr` ([1321](#)), `AnsiRightStr` ([1309](#)), `RightBStr` ([1328](#)), `MidStr` ([1323](#))

74.3.84 RomanToInt

Synopsis: Convert a string with a Roman number to its decimal value.

Declaration: `function RomanToInt(const S: string; Strictness: TRomanConversionStrictness) : LongInt`

Visibility: default

Description: `RomanToInt` returns the decimal equivalent of the Roman numerals in the string `S`. Invalid characters are dropped from `S`. A negative numeral is supported as well. The level of error checking is determined by the `strictness` parameter, the values are described in the type `TRomanConversionStrictness` ([1302](#)).

Errors: On error, a `EConvertError` ([1301](#)) exception is raised.

See also: `TRomanConversionStrictness` ([1302](#)), `IntToRoman` ([1320](#)), `Hex2Dec` ([1318](#)), `Numb2Dec` ([1324](#))

74.3.85 RomanToIntDef

Synopsis: Convert a roman numeral to an integer value

Declaration: `function RomanToIntDef(const S: string; const ADefault: LongInt; Strictness: TRomanConversionStrictness) : LongInt`

Visibility: default

Description: `RomanToInt` converts the roman numeral in `S` to an integer and returns the integer value. The strictness of the conversion algorithm is determined by `Strictness`. If the conversion fails, `ADefault` is returned.

See also: `TRomanConversionStrictness` ([1302](#)), `TryRomanToInt` ([1336](#)), `RomanToInt` ([1329](#)), `IntToRoman` ([1320](#))

74.3.86 RPos

Synopsis: Find last occurrence of substring or character in a string

Declaration: `function RPos(c: Char; const S: AnsiString) : SizeInt; Overload`
`function RPos(c: UnicodeChar; const S: UnicodeString) : SizeInt`
`; Overload`
`function RPos(const Substr: AnsiString; const Source: AnsiString)`
`: SizeInt; Overload`
`function RPos(const Substr: UnicodeString; const Source: UnicodeString)`
`: SizeInt; Overload`

Visibility: default

Description: `RPos` looks in `S` for the character `C` or the string `SubStr`. It starts looking at the end of the string, and searches towards the beginning of the string. If a match is found, it returns the position of the match.

See also: `RPosEx` ([1330](#))

74.3.87 RPosEx

Synopsis: Find last occurrence substring or character in a string, starting at a certain position

Declaration:

```
function RPosEx(C: Char; const S: AnsiString; offs: Cardinal) : SizeInt
    ; Overload
function RPosEx(C: UnicodeChar; const S: UnicodeString; offs: Cardinal)
    : SizeInt; Overload
function RPosEx(const Substr: AnsiString; const Source: AnsiString;
    offs: Cardinal) : SizeInt; Overload
function RPosEx(const Substr: UnicodeString;
    const Source: UnicodeString; offs: Cardinal) : SizeInt
    ; Overload
```

Visibility: default

Description: `RPos` looks in `S` for the character `C` or the string `SubStr`. It starts looking at position `Offs` (counted from the start of the string), and searches towards the beginning of the string. If a match is found, it returns the position of the match.

See also: `RPos` ([1329](#))

74.3.88 SearchBuf

Synopsis: Search a buffer for a certain string.

Declaration:

```
function SearchBuf(Buf: PChar; BufLen: SizeInt; SelStart: SizeInt;
    SelLength: SizeInt; SearchString: string;
    Options: TStringSearchOptions) : PChar
function SearchBuf(Buf: PChar; BufLen: SizeInt; SelStart: SizeInt;
    SelLength: SizeInt; SearchString: string) : PChar
```

Visibility: default

Description: `SearchBuf` searches the buffer `Buf` for the occurrence of `SearchString`. At most `BufLen` characters are searched, and the search is started at `SelStart+SelLength`. If a match is found, a pointer to the position of the match is returned. The parameter `Options` ([1303](#)) specifies how the search is conducted. It is a set of the following options:

Table 74.5:

Option	Effect
<code>soDown</code>	Searches forward, starting at the end of the selection. Default is searching up
<code>soMatchCase</code>	Observe case when searching. Default is to ignore case.
<code>soWholeWord</code>	Match only whole words. Default also returns parts of words

The standard constant `WordDelimiters` ([1302](#)) is used to mark the boundaries of words.

The `SelStart` parameter is zero based.

Errors: Buflen must be the real length of the string, no checking on this is performed.

See also: FindPart ([1317](#)), ExtractWord ([1315](#)), ExtractWordPos ([1315](#)), ExtractSubStr ([1315](#)), IsWordPresent ([1321](#))

74.3.89 Soundex

Synopsis: Compute the soundex of a string

Declaration: `function Soundex(const AText: string; ALength: TSoundexLength) : string`
`function Soundex(const AText: string) : string`

Visibility: default

Description: Soundex computes a soundex code for AText. The resulting code will at most have ALength characters. The soundex code is computed according to the US system of soundex computing, which may result in inaccurate results in other languages.

Note that AText may not contain null characters.

Errors: None.

See also: SoundexCompare ([1331](#)), SoundexInt ([1331](#)), SoundexProc ([1332](#)), SoundexWord ([1332](#)), SoundexSimilar ([1332](#))

74.3.90 SoundexCompare

Synopsis: Compare soundex values of 2 strings.

Declaration: `function SoundexCompare(const AText: string; const AOther: string;`
`ALength: TSoundexLength) : Integer`
`function SoundexCompare(const AText: string; const AOther: string)`
`: Integer`

Visibility: default

Description: SoundexCompare computes the soundex codes of AText and AOther and feeds these to CompareText. It will return -1 if the soundex code of AText is less than the soundex code of AOther, 0 if they are equal, and 1 if the code of AOther is larger than the code of AText.

Errors: None.

See also: Soundex ([1331](#)), SoundexInt ([1331](#)), SoundexProc ([1332](#)), SoundexWord ([1332](#)), SoundexSimilar ([1332](#))

74.3.91 SoundexInt

Synopsis: Soundex value as an integer.

Declaration: `function SoundexInt(const AText: string; ALength: TSoundexIntLength)`
`: Integer`
`function SoundexInt(const AText: string) : Integer`

Visibility: default

Description: SoundexInt computes the Soundex ([1331](#)) code (with length ALength, default 4) of AText, and converts the code to an integer value.

Errors: None.

See also: [Soundex \(1331\)](#), [SoundexCompare \(1331\)](#), [SoundexProc \(1332\)](#), [SoundexWord \(1332\)](#), [SoundexSimilar \(1332\)](#)

74.3.92 SoundexProc

Synopsis: Default `AnsiResemblesText` implementation.

Declaration: `function SoundexProc(const AText: string; const AOther: string)
: Boolean`

Visibility: default

Description: `SoundexProc` is the standard implementation for the `AnsiResemblesText (1308)` procedure: By default, `AnsiResemblesProc` is set to this function. It compares the soundex codes of `AOther` and `AText` and returns `True` if they are equal, or `False` if they are not.

Errors: None.

See also: [Soundex \(1331\)](#), [SoundexCompare \(1331\)](#), [SoundexInt \(1331\)](#), [SoundexWord \(1332\)](#), [SoundexSimilar \(1332\)](#)

74.3.93 SoundexSimilar

Synopsis: Check whether 2 strings have equal soundex values

Declaration: `function SoundexSimilar(const AText: string; const AOther: string;
ALength: TSoundexLength) : Boolean
function SoundexSimilar(const AText: string; const AOther: string)
: Boolean`

Visibility: default

Description: `SoundexSimilar` returns `True` if the soundex codes (with length `ALength`) of `AText` and `AOther` are equal, and `False` if they are not.

Errors: None.

See also: [Soundex \(1331\)](#), [SoundexCompare \(1331\)](#), [SoundexInt \(1331\)](#), [SoundexProc \(1332\)](#), [SoundexWord \(1332\)](#), [Soundex \(1331\)](#)

74.3.94 SoundexWord

Synopsis: Calculate a word-sized soundex value

Declaration: `function SoundexWord(const AText: string) : Word`

Visibility: default

Description: `SoundexInt` computes the [Soundex \(1331\)](#) code (with length 4) of `AText`, and converts the code to a word-sized value.

`AText` may not contain null characters.

Errors: None.

See also: [Soundex \(1331\)](#), [SoundexCompare \(1331\)](#), [SoundexInt \(1331\)](#), [SoundexProc \(1332\)](#), [SoundexSimilar \(1332\)](#)

74.3.95 SplitCommandLine

Synopsis: Split commandline in a series of separate arguments

Declaration: `function SplitCommandLine(S: RawByteString) : TRawByteStringArray`
`function SplitCommandLine(S: UnicodeString) : TUnicodeStringArray`

Visibility: default

Description: `SplitCommandLine` parses `S` into words separated by whitespace, and returns a list of separate words (command-line arguments): When parsing it takes into account quoting with single (') or double quote (") characters: a word that contains whitespace can be enclosed in a quote character and will be considered a single word.

You can call this function with a `UnicodeString` or a `RawByteString`, the resulting array will have the same type of elements.

for example:

```
first "second argument" 'third argument'
```

Will result in an array of 3 elements

- first
- second argument
- thirs argument

See also: `TRawByteStringArray` ([1302](#)), `TUnicodeStringArray` ([1304](#))

74.3.96 SplitString

Synopsis: Split a string in words

Declaration: `function SplitString(const S: string; const Delimiters: string)`
`: TStringDynArray`

Visibility: default

Description: `SplitString` will split the string (`S`) using the characters in `Delimiters` as separator characters. The result contains all words separated by one of the characters in `Delimiters`.

This function is a simplified wrapper around `TStringHelper.Split` ([1301](#)).

See also: `TStringHelper.Split` ([1301](#))

74.3.97 StartsStr

Synopsis: Check whether one string starts with another

Declaration: `function StartsStr(const ASubText: string; const AText: string)`
`: Boolean`

Visibility: default

Description: `StartsText` checks whether `aText` starts with `aSubText` and returns `True` if it does. i.e. it returns true if the first characters of `aText` are `aSubText`. It follows that the length of `aText` must be at least the length of `aSubText`. The comparison is made case-sensitive. If you wish to compare case-insensitively, use `StartsText` ([1334](#)) instead.

See also: `AnsiStartsStr` ([1309](#)), `EndsStr` ([1314](#)), `StartsText` ([1334](#))

74.3.98 StartsText

Synopsis: Check whether one text starts with another

Declaration: `function StartsText(const ASubText: string; const AText: string)
: Boolean`

Visibility: default

Description: `StartsText` checks whether `aText` starts with `aSubText` and returns `True` if it does. i.e. it returns `true` if the first characters of `aText` are `aSubText`. It follows that the length of `aText` must be at least the length of `aSubText`. The comparison is made case-insensitive. If you wish to compare case-sensitively, use `StartsStr` (1333) instead.

See also: `AnsiStartsText` (1309), `EndsText` (1314), `StartsStr` (1333)

74.3.99 StringReplace

Synopsis: Optimized search-and-replace algorithm

Declaration: `function StringReplace(const S: string; const OldPattern: string;
const NewPattern: string; Flags: TReplaceFlags;
out aCount: Integer;
Algorithm: TStringReplaceAlgorithm) : string
; Overload
function StringReplace(const S: string; const OldPattern: string;
const NewPattern: string; Flags: TReplaceFlags;
Algorithm: TStringReplaceAlgorithm) : string
; Overload
function StringReplace(const S: UnicodeString;
const OldPattern: UnicodeString;
const NewPattern: UnicodeString;
Flags: TReplaceFlags) : UnicodeString; Overload
function StringReplace(const S: WideString;
const OldPattern: WideString;
const NewPattern: WideString;
Flags: TReplaceFlags) : WideString; Overload`

Visibility: default

Description: `StringReplace` replaces one or all occurrences of `OldPattern` with `NewPattern` in the string `S`. The behaviour is controlled by `Flags` and the search mechanism may be optimized using `Algorithm`. A list of possible algorithms is specified in `TStringReplaceAlgorithm` (1303).

For `ansistrings`, this is an optimized version of the `SysUtils.StringReplace` (1755) algorithm. For `widestrings` or `unicodestrings`, the algorithm parameter is ignored and the default mechanism in `sysutils` is always used.

Errors: None.

See also: `SysUtils.StringReplace` (1755), `TStringReplaceAlgorithm` (1303)

74.3.100 StringsReplace

Synopsis: Replace occurrences of a set of strings to another set of strings

Declaration: `function StringsReplace(const S: string; OldPattern: Array of string;
NewPattern: Array of string;
Flags: TReplaceFlags) : string`

Visibility: default

Description: `StringsReplace` scans `S` for the occurrence of one of the strings in `OldPattern` and replaces it with the corresponding string in `NewPattern`. It takes into account `Flags`, which has the same meaning as in `StringReplace` ([1755](#)).

Corresponding strings are matched by location: the `N`-th string in `OldPattern` is replaced by the `N`-th string in `NewPattern`. Note that this means that the number of strings in both arrays must be the same.

Errors: If the number of strings in both arrays is different, then an exception is raised.

See also: `StringReplace` ([1755](#)), `TReplaceFlags` ([1639](#))

74.3.101 StuffString

Synopsis: Replace part of a string with another string.

Declaration: `function StuffString(const AText: string; AStart: Cardinal;
ALength: Cardinal; const ASubText: string) : string`

Visibility: default

Description: `StuffString` returns a copy of `AText` with the segment starting at `AStart` with length `ALength`, replaced with the string `ASubText`. Basically it deletes the segment of `Atext` and inserts the new text in it's place.

Errors: No checking on the validity of the `AStart` and `ALength` parameters is done. Providing invalid values may result in access violation errors.

See also: `FindPart` ([1317](#)), `DelChars` ([1313](#)), `DelSpace` ([1313](#)), `ExtractSubStr` ([1315](#)), `DupeString` ([1313](#))

74.3.102 Tab2Space

Synopsis: Convert tab characters to a number of spaces

Declaration: `function Tab2Space(const S: string; Numb: Byte) : string`

Visibility: default

Description: `Tab2Space` returns a copy of `S` with all tab characters (ASCII character 9) converted to `Numb` spaces.

Errors: None.

See also: `StuffString` ([1335](#)), `FindPart` ([1317](#)), `ExtractWord` ([1315](#)), `DelChars` ([1313](#)), `DelSpace` ([1313](#)), `DelSpace1` ([1313](#)), `DupeString` ([1313](#))

74.3.103 TrimLeftSet

Synopsis: Remove any leading characters in a set from a string and returns the result

Declaration: `function TrimLeftSet(const S: string; const CSet: TSysCharSet) : string`

Visibility: default

Description: `TrimLeftSet` performs the same action as `RemoveLeadingChars` (1326), but returns the resulting string.

Errors: None.

See also: [TrimLeft \(1779\)](#), [RemoveLeadingChars \(1326\)](#), [RemoveTrailingChars \(1327\)](#), [RemovePadChars \(1327\)](#), [TrimSet \(1336\)](#), [TrimRightSet \(1336\)](#)

74.3.104 TrimRightSet

Synopsis: Remove any trailing characters in a set from a string and returns the result

Declaration: `function TrimRightSet(const S: string; const CSet: TSysCharSet) : string`

Visibility: default

Description: `TrimLeftSet` performs the same action as `RemoveTrailingChars` ([1327](#)), but returns the resulting string.

Errors: None.

See also: [TrimRight \(1780\)](#), [RemoveLeadingChars \(1326\)](#), [RemoveTrailingChars \(1327\)](#), [RemovePadChars \(1327\)](#), [TrimSet \(1336\)](#), [TrimLeftSet \(1336\)](#)

74.3.105 TrimSet

Synopsis: Remove any leading or trailing characters in a set from a string and returns the result

Declaration: `function TrimSet(const S: string; const CSet: TSysCharSet) : string`

Visibility: default

Description: `TrimSet` performs the same action as `RemovePadChars` (1327), but returns the resulting string.

Errors: None.

See also: [Trim \(1779\)](#), [RemoveLeadingChars \(1326\)](#), [RemoveTrailingChars \(1327\)](#), [RemovePadChars \(1327\)](#), [TrimRightSet \(1336\)](#), [TrimLeftSet \(1336\)](#)

74.3.106 TryRomanToInt

Synopsis: Try to convert a roman numeral to an integer value.

```
Declaration: function TryRomanToInt(S: string; out N: LongInt;
                                     Strictness: TRomanConversionStrictness) : Boolean
```

Visibility: default

Description: `TryRomanToInt` will try to convert the roman numeral in `S` to an integer and returns the integer value in `N`. The strictness of the conversion algorithm is determined by `Strictness`. If the conversion succeeds, then `True` is returned, or else `False`.

See also: TRomanConversionStrictness (1302), RomanToIntDef (1329), RomanToInt (1329), IntToRoman (1320)

74.3.107 WordCount

Synopsis: Count the number of words in a string.

Declaration: `function WordCount(const S: string; const WordDelims: TSysCharSet)
: SizeInt`

Visibility: default

Description: `WordCount` returns the number of words in the string `S`. A word is a non-empty string of characters bounded by one of the characters in `WordDelims`.

The predefined `StdWordDelims` (1302) constant can be used for the `WordDelims` argument.

Errors: None.

See also: `WordPosition` (1337), `StdWordDelims` (1302), `ExtractWord` (1315), `ExtractWordPos` (1315)

74.3.108 WordPosition

Synopsis: Search position of Nth word in a string.

Declaration: `function WordPosition(const N: Integer; const S: string;
const WordDelims: TSysCharSet) : SizeInt`

Visibility: default

Description: `WordPosition` returns the position (in characters) of the N-th word in the string `S`. A word is a non-empty string of characters bounded by one of the characters in `WordDelims`. If `N` is out of range, zero is returned.

The predefined `StdWordDelims` (1302) constant can be used for the `WordDelims` argument.

Errors: None

See also: `WordCount` (1337), `StdWordDelims` (1302), `ExtractWord` (1315), `ExtractWordPos` (1315)

74.3.109 XorDecode

Synopsis: Decode a string encoded with `XorEncode` (1338)

Declaration: `function XorDecode(const Key: string; const Source: string) : string`

Visibility: default

Description: `XorDecode` decodes `Source` and returns the original string that was encrypted using `XorEncode` (1338) with key `Key`. If a different key is used than the key used to encode the string, the result will be unreadable.

Errors: If the string `Source` is not a valid `XorEncode` result (e.g. contains non-numerical characters), then a `EConversionError` exception will be raised.

See also: `XorEncode` (1338), `XorString` (1338)

74.3.110 XorEncode

Synopsis: Encode a string by XOR-ing its characters using characters of a given key, representing the result as hex values.

Declaration: `function XorEncode(const Key: string; const Source: string) : string`

Visibility: default

Description: `XorEncode` encodes the string `Source` by XOR-ing each character in `Source` with the corresponding character in `Key` (repeating `Key` as often as necessary) and representing the resulting ASCII code as a hexadecimal number (of length 2). The result is therefore twice as long as the original string, and every 2 bytes represent an ASCII code.

Feeding the resulting string with the same key `Key` to the `XorDecode` (1337) function will result in the original `Source` string.

This function can be used e.g. to trivially encode a password in a configuration file.

Errors: None.

See also: `XorDecode` (1337), `XorString` (1338), `Hex2Dec` (1318)

74.3.111 XorString

Synopsis: Encode a string by XOR-ing its characters using characters of a given key.

Declaration: `function XorString(const Key: ShortString; const Src: ShortString)
: ShortString`

Visibility: default

Description: `XorString` encodes the string `Src` by XOR-ing each character in `Source` with the corresponding character in `Key`, repeating `Key` as often as necessary. The resulting string may contain unreadable characters and may even contain null characters. For this reason it may be a better idea to use the `XorEncode` (1338) function instead, which will representing each resulting ASCII code as a hexadecimal number (of length 2).

Feeding the result again to `XorString` with the same `Key`, will result in the original string `Src`.

Errors: None.

See also: `XorEncode` (1338), `XorDecode` (1337)

Chapter 75

Reference for unit 'System'

75.1 Overview

The system unit contains the standard supported functions of Free Pascal. It is the same for all platforms. Basically it is the same as the system unit provided with Borland or Turbo Pascal.

Functions are listed in alphabetical order. Arguments of functions or procedures that are optional are put between square brackets.

The predefined constants and variables are listed in the first section. The second section contains an overview of all functions, grouped by functionality, and the last section contains the supported functions and procedures.

75.2 Unicode and codepage support

The system unit works with Short-, Ansi-, and UnicodeString routines for all string related operations.

Ansistrings are code-page aware, which means that code page information is associated with them. For most routines, the support for converting these code pages is natural. For some routines, care must be taken when converting from codepage-aware strings to widestring.

The codepage conversion support is influenced by the following variables:

Table 75.1:

Name	Description
DefaultSystemCodePage (1419)	Actual code page to use when CP_ACP (1346) is encountered
DefaultUnicodeCodePage (1419)	Code page for new Unicode strings
DefaultFileSystemCodePage (1418)	Codepage to use when sending strings to single-byte OS file system routines.
DefaultRTLFileSystemCodePage (1418)	Codepage to use when receiving strings from single-byte OS file system routines.

The windows code page identifiers are used. There are 3 special codepage identifiers:

Table 75.2:

Name	Description
CP_ACP (1346)	Currently set default system codepage
CP_OEMCP (1346)	OEM (console) code page (only on windows)
CP_NONE (1346)	Indicates absence of code page information for a string
DefaultRTLFileSystemCodePage (1418)	

The following routines may perform code page conversions:

Table 75.3:

Name	Description
LowerCase (1509)	Return lowercase version of a string.
UpCase (1567)	Convert a string to all uppercase.
GetDir (1477)	Return the current directory
MkDir (1510)	Create a new directory.
ChDir (1440)	Change current working directory.
RmDir (1529)	Remove directory when empty.
Assign (1427)	Assign a name to a file
Erase (1462)	Delete a file from disk
Rename (1526)	Rename file on disk
Read (1522)	Read from a text file into variable
ReadLn (1523)	Read from a text file into variable and goto next line
Write (1574)	Write variable to a text file or standard output
WriteLn (1575)	Write variable to a text file or standard output and append newline
ReadStr (1524)	Read variables from a string
WriteStr (1576)	Write variables to a string
Insert (1496)	Insert one string or dynamic array in another.
Copy (1449)	Copy part of a string.
Delete (1453)	Delete elements (characters) from a string or dynamic array.
SetString (1543)	Set length of a string and copy buffer.

All these routines exist also in Unicode versions.

Note that for conversion of codepages and Unicode strings, a Unicode manager must be present. On windows, the system is used for this. On Unix, one of the fpwdestring or cwstring units must be used.

75.3 Miscellaneous functions

Functions that do not belong in one of the other categories.

Table 75.4:

Name	Description
Assert (1427)	Conditionally abort program with error
Break (1436)	Abort current loop
Continue (1448)	Next cycle in current loop
Exclude (1463)	Exclude an element from a set
Exit (1464)	Exit current function or procedure
Include (1489)	Include an element into a set
LongJump (1508)	Jump to execution point
Ord (1515)	Return ordinal value of enumerated type
Pred (1519)	Return previous value of ordinal type
SetJump (1539)	Mark execution point for jump
SizeOf (1547)	Return size of variable or type
Succ (1555)	Return next value of ordinal type

75.4 Operating System functions

Functions that are connected to the operating system.

Table 75.5:

Name	Description
Chdir (1440)	Change working directory
Getdir (1477)	Return current working directory
Halt (1484)	Halt program execution
Paramcount (1516)	Number of parameters with which program was called
Paramstr (1517)	Retrieve parameters with which program was called
Mkdir (1510)	Make a directory
Rmdir (1529)	Remove a directory
Runerror (1534)	Abort program execution with error condition

75.5 String handling

All things connected to string handling.

Table 75.6:

Name	Description
BinStr (1434)	Construct binary representation of integer
Chr (1441)	Convert ASCII code to character
Concat (1447)	Concatenate two strings
Copy (1449)	Copy part of a string
Delete (1453)	Delete part of a string
HexStr (1485)	Construct hexadecimal representation of integer
Insert (1496)	Insert one string in another
Length (1503)	Return length of string
Lowercase (1509)	Convert string to all-lowercase
OctStr (1513)	Construct octal representation of integer
Pos (1518)	Calculate position of one string in another
SetLength (1540)	Set length of a string
SetString (1543)	Set contents and length of a string or dynamic array
Str (1551)	Convert number to string representation
StringOfChar (1553)	Create string consisting of a number of characters
Ucase (1567)	Convert string to all-uppercase
Val (1570)	Convert string to number

75.6 Mathematical routines

Functions connected to calculating and converting numbers.

Table 75.7:

Name	Description
Abs (1422)	Calculate absolute value
Arctan (1426)	Calculate inverse tangent
Cos (1450)	Calculate cosine of angle
Dec (1451)	Decrease value of variable
Exp (1466)	Exponentiate
Frac (1474)	Return fractional part of floating point value
Hi (1485)	Return high byte/word of value
Inc (1488)	Increase value of variable
Int (1496)	Calculate integer part of floating point value
Ln (1505)	Calculate logarithm
Lo (1505)	Return low byte/word of value
Odd (1514)	Is a value odd or even ?
Pi (1517)	Return the value of pi
Random (1521)	Generate random number
Randomize (1522)	Initialize random number generator
Round (1532)	Round floating point value to nearest integer number
Sin (1547)	Calculate sine of angle
Sqr (1549)	Calculate the square of a value
Sqrt (1550)	Calculate the square root of a value
Swap (1556)	Swap high and low bytes/words of a variable
Trunc (1562)	Truncate a floating point value

75.7 Memory management functions

Functions concerning memory issues.

Table 75.8:

Name	Description
Addr (1424)	Return address of variable
Assigned (1432)	Check if a pointer is valid
CompareByte (1442)	Compare 2 memory buffers byte per byte
CompareChar (1443)	Compare 2 memory buffers byte per byte
CompareDWord (1445)	Compare 2 memory buffers byte per byte
CompareWord (1446)	Compare 2 memory buffers byte per byte
CSeg (1451)	Return code segment
Dispose (1454)	Free dynamically allocated memory
DSeg (1456)	Return data segment
FillByte (1468)	Fill memory region with 8-bit pattern
FillChar (1469)	Fill memory region with certain character
FillDWord (1470)	Fill memory region with 32-bit pattern
FillQWord (??)	Fill memory region with 64-bit pattern
FillWord (1470)	Fill memory region with 16-bit pattern
Freemem (1475)	Release allocated memory
Getmem (1478)	Allocate new memory
GetMemoryManager (1479)	Return current memory manager
High (1486)	Return highest index of open array or enumerated
IndexByte (1489)	Find byte-sized value in a memory range
IndexChar (1490)	Find char-sized value in a memory range
IndexDWord (1491)	Find DWord-sized (32-bit) value in a memory range
IndexQWord (1492)	Find QWord-sized value in a memory range
IndexWord (1492)	Find word-sized value in a memory range
IsMemoryManagerSet (1502)	Is the memory manager set
MemSize (1510)	Get size of allocation
Low (1508)	Return lowest index of open array or enumerated
Move (1510)	Move data from one location in memory to another
MoveChar0 (1511)	Move data till first zero character
New (1512)	Dynamically allocate memory for variable
Ofs (1514)	Return offset of variable
Ptr (1520)	Combine segment and offset to pointer
ReAllocMem (1525)	Resize a memory block on the heap
Seg (1538)	Return segment
SetMemoryManager (1541)	Set a memory manager
Sptr (1549)	Return current stack pointer
SSeg (1550)	Return stack segment register value

75.8 File handling functions

Functions concerning input and output from and to file.

Table 75.9:

Name	Description
Append (1425)	Open a file in append mode
Assign (1427)	Assign a name to a file
Blockread (1435)	Read data from a file into memory
Blockwrite (1436)	Write data from memory to a file
Close (1441)	Close a file
Eof (1460)	Check for end of file
Eoln (1461)	Check for end of line
Erase (1462)	Delete file from disk
Filepos (1467)	Position in file
Filesize (1468)	Size of file
Flush (1473)	Write file buffers to disk
IOresult (1500)	Return result of last file IO operation
Read (1522)	Read from file into variable
Readln (1523)	Read from file into variable and goto next line
Rename (1526)	Rename file on disk
Reset (1527)	Open file for reading
Rewrite (1528)	Open file for writing
Seek (1536)	Set file position
SeekEof (1536)	Set file position to end of file
SeekEoln (1537)	Set file position to end of line
SetTextBuf (1543)	Set size of file buffer
Truncate (1562)	Truncate the file at position
Write (1574)	Write variable to file
WriteLn (1575)	Write variable to file and append newline

75.9 Run-Time Error behaviour

The system unit handles errors by default by generating a run-time error, and halting the program with an exit code equal to the run-time error number.

This behaviour changes when the SysUtils (1615) unit is used. In that case, all run-time errors are converted to exceptions: most run-time errors have their own exception class.

If these exceptions are caught, the program code decides what to do with it. If the exception is not caught, the program will exit through the default exception handler.

When the system unit documentation refers to run-time errors, the above should be kept in mind.

75.10 Constants, types and variables

75.10.1 Constants

```
AbstractErrorProc : TAbstractErrorProc = Nil
```

If set, the `AbstractErrorProc` constant is used when an abstract error occurs. If it is not set, then the standard error handling is done: A stack dump is performed, and the program exits with error code 211.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

```
AllFilesMask = '*'
```

AllFilesMask is the wildcard that can be used to return all files in a directory. Do not assume that this is '*' or '*.*' based on the platform only. The actual value on DOS/Windows based systems can be influenced by e.g. LFNSupport ([1361](#)).

```
AllowDirectorySeparators : Set of Char = ['\','/']
```

AllowDirectorySeparators is the set of characters which are considered directory separators by the RTL units. By default, this is set to the most common directory separators: forward slash and backslash, so routines will work in a cross-platform manner, no matter which character was used:

```
AllowDirectorySeparators : set of char = ['\','/'];
```

If a more strict behaviour is desired, then AllowDirectorySeparators can be set to the only character allowed on the current operating system, and all RTL routines that handle filenames (splitting filenames, extracting parts of the filename and so on) will use that character only.

```
AllowDriveSeparators : Set of Char = []
```

AllowDriveSeparators are the characters which are considered to separate the drive part from the directory part in a filename. This will be an empty set on systems that do not support drive letters. Other systems (Dos, Windows and OS/2) will have the colon (:) character as the only member of this set.

```
AssertErrorProc : TAssertErrorProc = @ SysAssert
```

If set, the AssertErrorProc constant is used when an assert error occurs. If it is not set, then the standard assert error handling is performed:

- The assertion error message is printed.
- The location of the assertion is printed.
- a stack dump is printed.
- The program exits with error code 227.

The SysUtils unit sets this procedure and raises an exception in its handler.

```
BacktraceStrFunc : TBacktraceStrFunc = @ SysBacktraceStr
```

This handler is called to get a standard format for the backtrace routine.

```
CatchAllExceptions = PtrInt(- 1)
```

Mask indicating all exception kinds

```
cExceptionFrame = 1
```

cExceptionFrame indicates an except frame.

```
cFinalizeFrame = 2
```

`cFinalizeFrame` indicates a finally frame.

`CP_ACP` = 0

`CP_ACP` is the default Windows codepage identifier.

`CP_ASCII` = 20127

`CP_ASCII` is the Windows ASCII encoding codepage identifier.

`CP_NONE` = \$FFFF

`CP_NONE` is used when no code page information is available.

`CP_OEMCP` = 1

`CP_ACP` is the default Windows OEM (MS-DOS) codepage identifier.

`CP_UTF16` = 1200

`CP_UTF16` is the default Windows Unicode codepage identifier (little endian).

`CP_UTF16BE` = 1201

`CP_UTF16BE` is the Windows Unicode codepage identifier (big endian).

`CP_UTF7` = 65000

`CP_UTF7` is the Windows Unicode 7-Bit encoding codepage identifier.

`CP_UTF8` = 65001

`CP_UTF8` is the Windows Unicode 8-Bit encoding codepage identifier.

`CtrlZMarksEOF` : Boolean = False

`CtrlZMarksEOF` indicates whether on this system, an CTRL-Z character (ordinal 26) in a file marks the end of the file. This is False on most systems apart from DOS and Windows.

To get DOS/Windows-compatible behaviour, this constant can be set to True

`Default8087CW` : Word = \$1332

`DefaultMXCSR` : DWord = \$1900

`DefaultStackSize` = 4 * 1024 * 1024

Default size for a new thread's stack (4MiB by default).

`DefaultTextLineBreakStyle` : TTextLineBreakStyle = tlbsLF

`DefaultTextLineBreakStyle` contains the default OS setting for the `TTextLineBreakStyle` (1403) type. It is initialized by the system unit, and is used to determine the default line ending when writing to text files.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
DirectorySeparator = '/'
```

`DirectorySeparator` is the character used by the current operating system to separate directory parts in a pathname. This constant is system dependent, and should not be set.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
DriveSeparator = ''
```

On systems that support drive letters, the `DriveSeparator` constant denotes the character that separates the drive indicator from the directory part in a filename path.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
ErrorAddr : CodePointer = Nil
```

Address where the last error occurred.

```
ErrorCode : Word = 0
```

Last error code.

```
ErrorProc : TErrorProc = Nil
```

If set, the `ErrorProc` constant is used when a run-time error occurs. If it is not set, then the standard error handling is done: a stack dump is performed, and the program exits with the indicated error code.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

```
ExceptClsProc : Pointer = Nil
```

`ExceptClsProc` is used in SEH (Structured Exception Support) to convert OS exception information to FPC exception classes when filtering exceptions. It is set e.g. by the `sysutils` unit. If it is not set, the exception is not handled.

```
ExceptObjProc : Pointer = Nil
```

`ExceptObjProc` is used in SEH (Structured Exception Support) to convert OS exception information to FPC exceptions. It is set e.g. by the `sysutils` unit. If it is not set, a run-time error results when OS exceptions are intercepted.

```
ExceptProc : TExceptProc = Nil
```

This constant points to the current exception handling procedure. This routine is called when an unhandled exception occurs, i.e. an exception that is not stopped by a except block.

If the handler is not set, the RTL will emit a run-time error 217 when an unhandler exception occurs.

It is set by the sysutils (1615) unit.

```
ExitProc : CodePointer = Nil
```

Exit procedure pointer.

```
ExtensionSeparator = '.'
```

ExtensionSeparator is the character which separates the filename from the file extension. On all current platforms, this is the . (dot) character. All RTL filename handling routines use this constant.

```
E_NOINTERFACE = hresult($80004002)
```

Interface call result: Error: not an interface

```
E_NOTIMPL = hresult($80004001)
```

Interface call result: Interface not implemented

```
E_UNEXPECTED = hresult($8000FFFF)
```

Interface call result: Unexpected error

```
FileMode : Byte = 2
```

FileMode determines how untyped files are opened for reading with Reset (1527). It can have the following values:

0 open file readonly

1 open file write only

2 open file read/write

```
FileNameCasePreserving : Boolean = True
```

FileNameCasePreserving is True if case of letters in file and directory entries is preserved and may be later retrieved exactly as supplied when creating or renaming these entries. Note that this may depend on the file system: Unix operating systems that access a DOS or Windows partition will have this constant set to true, but when writing to the DOS partition, all letters may be automatically converted to uppercase.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
FileNameCaseSensitive : Boolean = True
```

`FileNameCaseSensitive` is `True` if case is important when using filenames on the current OS. In this case, the OS will treat files with different cased names as different files. Note that this may depend on the file system: Unix operating systems that access a DOS or Windows partition will have this constant set to true, but when writing to the DOS partition, the casing is ignored.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`filerecnamelength` = 255

`filerecnamelength` is the maximum filename size for untyped files.

`float_flag_denormal` = `exDenormalized`

IEC/IEEE floating-point exception flag: ?

`float_flag_divbyzero` = `exZeroDivide`

IEC/IEEE floating-point exception flag: Division by zero error

`float_flag_inexact` = `exPrecision`

IEC/IEEE floating-point exception flag: ?

`float_flag_invalid` = `exInvalidOp`

IEC/IEEE floating-point exception flag: Invalid operation error

`float_flag_overflow` = `exOverflow`

IEC/IEEE floating-point exception flag: Overflow error

`float_flag_underflow` = `exUnderflow`

IEC/IEEE floating-point exception flag: Underflow error

`float_round_down` = `rmDown`

Round down

`float_round_nearest_even` = `rmNearest`

Round to nearest even number

`float_round_to_zero` = `rmTruncate`

Round in the direction of zero (down for positive, up for negative)

`float_round_up` = `rmUp`

Round up

`fmAppend = $D7B4`

File mode: File is open for writing, appending to the end.

`fmClosed = $D7B0`

File mode: File is closed.

`fmInOut = $D7B3`

File mode: File is open for reading and writing.

`fmInput = $D7B1`

File mode: File is open for reading.

`fmOutput = $D7B2`

File mode: File is open for writing.

`FPC_EXCEPTION = 1`

`FPC_EXCEPTION` is a constant describing a type of exception.

`fpc_in_abs_long = 64`

Internal ABS function

`fpc_in_abs_real = 127`

FPC compiler internal procedure index: `abs` (real)

`fpc_in_addr_x = 42`

FPC compiler internal procedure index: `addr`

`fpc_in_aligned_x = 80`

FPC compiler internal procedure index: `aligned`

`fpc_in_and_assign_x_y = 86`

`fpc_in_arctan_real = 130`

FPC compiler internal procedure index: `arctan` (real)

`fpc_in_assert_x_y = 41`

FPC compiler internal procedure index: `assert`

fpc_in_assigned_x = 19

FPC compiler internal procedure index: assigned

fpc_in_bitsizeof_x = 61

FPC compiler internal procedure index: bitsizeof

fpc_in_box_x = 77

FPC compiler internal procedure index: box

fpc_in_break = 39

FPC compiler internal procedure index: break

fpc_in_bsf_x = 74

FPC compiler internal procedure index: bsf_x

fpc_in_bsr_x = 75

FPC compiler internal procedure index: bsr_x

fpc_in_chr_byte = 7

FPC compiler internal procedure index: chr

fpc_in_concat_x = 18

FPC compiler internal procedure index: concat

fpc_in_const_abs = 101

FPC compiler internal procedure index: abs

fpc_in_const_odd = 102

FPC compiler internal procedure index: sqr

fpc_in_const_ptr = 103

FPC compiler internal procedure index: sqr

fpc_in_const_sqr = 100

FPC compiler internal procedure index: sqr

fpc_in_const_swap_long = 105

FPC compiler internal procedure index: swap (long)

fpc_in_const_swap_qword = 108

FPC compiler internal procedure index: swap (qword)

fpc_in_const_swap_word = 104

FPC compiler internal procedure index: swap (word)

fpc_in_continue = 40

FPC compiler internal procedure index: continue

fpc_in_copy_x = 49

FPC compiler internal procedure index: copy

fpc_in_cos_real = 125

FPC compiler internal procedure index: cos (real)

fpc_in_cpu_first = 10000

fpc_in_cycle = 52

FPC compiler internal procedure index: cycle

fpc_in_dec_x = 36

FPC compiler internal procedure index: dec

fpc_in_default_x = 76

FPC compiler internal procedure index: default

fpc_in_delete_x_y_z = 83

fpc_in_dispose_x = 47

FPC compiler internal procedure index: dispose

fpc_in_exclude_x_y = 38

FPC compiler internal procedure index: exclude

fpc_in_exit = 48

FPC compiler internal procedure index: exit

fpc_in_exp_real = 124

FPC internal compiler routine: in_exp_real

fpc_in_faraddr_x = 97

fpc_in_fillchar_x = 55

FPC internal compiler routine: in_fillchar_x

fpc_in_finalize_x = 45

FPC compiler internal procedure index: finalize

fpc_in_fma_double = 134

FPC compiler internal procedure index: fma (double)

fpc_in_fma_extended = 135

FPC compiler internal procedure index: fma (extended)

fpc_in_fma_float128 = 136

FPC compiler internal procedure index: fma (float 128)

fpc_in_fma_single = 133

FPC compiler internal procedure index: fma (single)

fpc_in_frac_real = 122

FPC internal compiler routine: in_frac_real

fpc_in_get_caller_addr = 57

FPC internal compiler routine: in_get_caller_addr

fpc_in_get_caller_frame = 58

FPC internal compiler routine: in_get_caller_frame

fpc_in_get_frame = 56

FPC internal compiler routine: in_get_frame

fpc_in_high_x = 28

FPC compiler internal procedure index: high

fpc_in_hi_long = 4

FPC compiler internal procedure index: hi (long)

`fpc_in_hi_qword = 107`

FPC compiler internal procedure index: hi (qword)

`fpc_in_hi_word = 2`

FPC compiler internal procedure index: hi (word)

`fpc_in_include_x_y = 37`

FPC compiler internal procedure index: include

`fpc_in_inc_x = 35`

FPC compiler internal procedure index: inc

`fpc_in_initialize_x = 50`

FPC compiler internal procedure index: initialize

`fpc_in_insert_x_y_z = 82`

`fpc_in_int_real = 123`

FPC internal compiler routine: in_int_real

`fpc_in_leave = 51`

FPC compiler internal procedure index: leave

`fpc_in_length_string = 6`

FPC compiler internal procedure index: length

`fpc_in_ln_real = 131`

FPC compiler internal procedure index: ln (real)

`fpc_in_low_x = 27`

FPC compiler internal procedure index: low

`fpc_in_lo_long = 3`

FPC compiler internal procedure index: lo (long)

`fpc_in_lo_qword = 106`

FPC compiler internal procedure index: lo (qword)

`fpc_in_lo_word = 1`

FPC compiler internal procedure index: lo (word)

`fpc_in_mmx_pcmpeqb = 200`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpeqd = 202`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpeqw = 201`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpgtb = 203`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpgtd = 205`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpgtw = 204`

FPC compiler internal procedure index: MMX

`fpc_in_move_x = 54`

FPC internal compiler routine: in_move_x

`fpc_in_neg_assign_x = 94`

`fpc_in_new_x = 46`

FPC compiler internal procedure index: new

`fpc_in_not_assign_x = 95`

`fpc_in_ofs_x = 21`

FPC compiler internal procedure index: ofs

`fpc_in_ord_x = 5`

FPC compiler internal procedure index: ord

fpc_in_or_assign_x_y = 87

fpc_in_pack_x_y_z = 59

FPC compiler internal procedure index: pack

fpc_in_pi_real = 126

FPC internal compiler routine: in_pi_real

fpc_in_popcnt_x = 79

FPC compiler internal procedure index: popcnt

fpc_in_pred_x = 30

FPC compiler internal procedure index: pred

fpc_in_prefetch_var = 109

FPC compiler internal procedure index: prefetch

fpc_in_readln_x = 17

FPC compiler internal procedure index: readln

fpc_in_readstr_x = 63

Internal read string procedure

fpc_in_read_x = 16

FPC compiler internal procedure index: read

fpc_in_reset_typedfile = 32

FPC compiler internal procedure index: reset

fpc_in_reset_typedfile_name = 84

fpc_in_reset_x = 25

FPC compiler internal procedure index: reset

fpc_in_rewrite_typedfile = 33

FPC compiler internal procedure index: rewrite

fpc_in_rewrite_typedfile_name = 85

fpc_in_rewrite_x = 26

FPC compiler internal procedure index: rewrite

fpc_in_rol_assign_x_y = 92

fpc_in_rol_x = 67

fpc_in_rol_x_x = 68

fpc_in_ror_assign_x_y = 93

fpc_in_ror_x = 65

fpc_in_ror_x_x = 66

fpc_in_round_real = 121

FPC internal compiler routine: in_round_real

fpc_in_sar_assign_x_y = 89

fpc_in_sar_x = 73

FPC compiler internal procedure index: sar_x

fpc_in_sar_x_y = 72

FPC compiler internal procedure index: sar_x_y

fpc_in_seg_x = 29

FPC compiler internal procedure index: seg

fpc_in_setlength_x = 44

FPC compiler internal procedure index: setlength

fpc_in_setstring_x_y_z = 81

FPC compiler internal procedure index: setstring

fpc_in_settextbuf_file_x = 34

FPC compiler internal procedure index: settextbuf

fpc_in_shl_assign_x_y = 90

fpc_in_shr_assign_x_y = 91

fpc_in_sin_real = 132

FPC compiler internal procedure index: sin (real)

fpc_in_sizeof_x = 22

FPC compiler internal procedure index: sizeof

fpc_in_slice = 53

FPC internal compiler routine: in_slice

fpc_in_sqrt_real = 129

FPC compiler internal procedure index: sqrt (real)

fpc_in_sqr_real = 128

FPC compiler internal procedure index: sqr (real)

fpc_in_str_x_string = 20

FPC compiler internal procedure index: str

fpc_in_succ_x = 31

FPC compiler internal procedure index: succ

fpc_in_trunc_real = 120

FPC internal compiler routine: in_trunc_real

fpc_in_typeinfo_x = 43

FPC compiler internal procedure index: typeinfo

fpc_in_typeof_x = 23

FPC compiler internal procedure index: typeof

fpc_in_unbox_x_y = 78

FPC compiler internal procedure index: unbox

fpc_in_unpack_x_y_z = 60

FPC compiler internal procedure index: unpack

`fpc_in_val_x = 24`

FPC compiler internal procedure index: val

`fpc_in_writeln_x = 15`

FPC compiler internal procedure index: writeln

`fpc_in_writestr_x = 62`

Internal write string procedure

`fpc_in_write_x = 14`

FPC compiler internal procedure index: write

`fpc_in_x86_cli = fpc_in_cpu_first + 6`

`fpc_in_x86_get_cs = fpc_in_cpu_first + 8`

`fpc_in_x86_get_ds = fpc_in_cpu_first + 10`

`fpc_in_x86_get_es = fpc_in_cpu_first + 11`

`fpc_in_x86_get_fs = fpc_in_cpu_first + 12`

`fpc_in_x86_get_gs = fpc_in_cpu_first + 13`

`fpc_in_x86_get_ss = fpc_in_cpu_first + 9`

`fpc_in_x86_inportb = fpc_in_cpu_first`

`fpc_in_x86_inportl = fpc_in_cpu_first + 2`

`fpc_in_x86_inportw = fpc_in_cpu_first + 1`

`fpc_in_x86_outportb = fpc_in_cpu_first + 3`

`fpc_in_x86_outportl = fpc_in_cpu_first + 5`

`fpc_in_x86_outportw = fpc_in_cpu_first + 4`

`fpc_in_x86_sti = fpc_in_cpu_first + 7`

`fpc_in_xor_assign_x_y = 88`

`fpc_objc_encode_x = 71`

`fpc_objc_protocol_x = 70`

`fpc_objc_selector_x = 69`

`growheapsize1 : PtrUInt = 256 * 1024`

Grow rate for block less than 256 Kb.

`growheapsize2 : PtrUInt = 1024 * 1024`

Grow rate for block larger than 256 Kb.

`growheapsize_small : PtrUInt = 32 * 1024`

Fixed size small blocks grow rate

`has_mmx_support : Boolean = False`

CPU has mmx support

`has_sse2_support : Boolean = False`

CPU has sse2 support?

`has_sse3_support : Boolean = False`

CPU has sse3 support?

`has_sse_support : Boolean = False`

CPU has SSE support ?

`InitProc : CodePointer = Nil`

`InitProc` is a routine that can be called after all units were initialized. It can be set by units to execute code that can be initialized after all units were initialized.

Remark When setting the value of `InitProc`, the previous value should always be saved, and called when the installed initialization routine has finished executing.

```
IOBJECTINSTANCE : TGUID =
  '{D91C9AF4-3C93-420F-A303-BF5BA82BFD23}'
```

`IOBJECTINSTANCE` is an internal GUID, which should not be used in end-user code. It is used in the `as` operator.

```
ISMULTITHREAD : longbool = False
```

Indicates whether more than one thread is running in the application.

```
LFNSUPPORT = True
```

`LFNSUPPORT` determines whether the current OS supports long file names, i.e. filenames that are not of the form 8.3 as on ancient DOS systems. If the value of this constant is `True` then long filenames are supported. If it is false, then not.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
LINEENDING = #10
```

`LINEENDING` is a constant which contains the current line-ending character. This character is system dependent, and is initialized by the system. It should not be set.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
MAXEXITCODE = 255
```

`MAXEXITCODE` is the maximum value for the `Halt` ([1484](#)) call.

```
MAXINT = maxsmallint
```

Maximum integer value.

```
MAXKEPTOSCHUNKS : DWord = 4
```

`MAXKEPTOSCHUNKS` tells the heap manager how many free chunks of OS-allocated memory it should keep in memory. When freeing memory, it can happen that a memory block obtained from the OS is completely free. If more than `MAXKEPTOSCHUNKS` such blocks are free, then the heap manager will return them to the OS, to reduce memory requirements.

```
MAXLONGINT = $7fffffff
```

Maximum longint value.

```
MAXPATHLEN = 4096
```

This constant is system dependent.

```
MAXSINTVALUE = High(ValSInt)
```

Maximum String-size value.

```
MaxSmallint = 32767
```

Maximum smallint value.

```
MaxUIntValue = High(ValUInt)
```

Maximum unsigned integer value.

```
Max_Frame_Dump : Word = 8
```

Maximum number of frames to show in error frame dump.

```
ModuleIsCpp : Boolean = False
```

ModuleIsCpp is always false for FPC programs, it is provided for Delphi compatibility only.

```
ModuleIsLib : Boolean = False
```

ModuleIsLib is set by the compiler when linking a library, program or package, and determines whether the current module is a library (or package) (True) or program (False).

```
ModuleIsPackage : Boolean = False
```

ModuleIsLib is set by the compiler when linking a library, program or package, and determines whether the current module is a package (True) or a library or program (False).

```
NilHandle = TLibHandle(0)
```

Correctly typed Nil handle - returned on error by LoadLibrary ([1506](#))

```
PathSeparator = ':'
```

PathSeparator is the character used commonly on the current operating system to separate paths in a list of paths, such as the PATH environment variable.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
RaiseMaxFrameCount : LongInt = 16
```

Maximum number of frames to include in TExceptObject ([1392](#))

```
RaiseProc : TExceptProc = Nil
```

Procedure to raise an exception.

```
RT_ACCELERATOR = MAKEINTRESOURCE(9)
```

Constant identifying an accelerator resource

```
RT_ANICURSOR = MAKEINTRESOURCE(21)
```

This constant can be used to specify a resource of type "animated cursor".

`RT_ANIICON = MAKEINTRESOURCE (22)`

This constant can be used to specify a resource of type "animated icon".

`RT_BITMAP = MAKEINTRESOURCE (2)`

Constant identifying a bitmap resource

`RT_CURSOR = MAKEINTRESOURCE (1)`

Constant identifying a cursor resource

`RT_DIALOG = MAKEINTRESOURCE (5)`

Constant identifying a dialog resource

`RT_FONT = MAKEINTRESOURCE (8)`

Constant identifying a font resource

`RT_FONTDIR = MAKEINTRESOURCE (7)`

Constant identifying a font directory resource

`RT_GROUP_CURSOR = MAKEINTRESOURCE (12)`

Constant identifying a group cursor resource

`RT_GROUP_ICON = MAKEINTRESOURCE (14)`

Constant identifying a group icon resource

`RT_HTML = MAKEINTRESOURCE (23)`

This constant can be used to specify a resource of type "HTML data".

`RT_ICON = MAKEINTRESOURCE (3)`

Constant identifying an icon resource

`RT_MANIFEST = MAKEINTRESOURCE (24)`

This constant can be used to specify a resource of type "Manifest".

`RT_MENU = MAKEINTRESOURCE (4)`

Constant identifying a menu resource

`RT_MESSAGE_TABLE = MAKEINTRESOURCE (11)`

Constant identifying a message data resource

```
RT_RCDATA = MAKEINTRESOURCE(10)
```

Constant identifying a binary data resource

```
RT_STRING = MAKEINTRESOURCE(6)
```

Constant identifying a string table resource

```
RT_VERSION = MAKEINTRESOURCE(16)
```

Constant identifying a version info resource

```
RuntimeErrorExitCodes : Array[TRuntimeError] of Byte = (0, 203, 204
, 200, 201, 215, 207, 200, 205, 206, 219, 216, 218, 217, 202, 220
, 221, 222, 223, 224, 225, 227, 212, 228, 229, 233, 234, 235, 236
)
```

This array is used by the [Error \(1463\)](#) routine to convert a [TRuntimeError \(1400\)](#) enumeration type to a process exit code.

```
SafeCallErrorProc : TSafeCallErrorProc = Nil
```

`SafeCallErrorProc` is a Handler called in case of a safecall calling convention error. `Error` is the error number (passed by the Windows operating system) and `Addr` is the address where the error occurred.

```
SharedSuffix = 'so'
```

Shared library suffix for the current platform

```
sLineBreak = LineEnding
```

`sLineBreak` is an alias for [LineEnding \(1361\)](#) and is supplied for Delphi compatibility.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
StackError : Boolean = False
```

Indicate whether there was a stack error.

```
StdErrorHandle = 2
```

Value of the OS handle for the standard error-output file.

```
StdInputHandle = 0
```

Value of the OS handle for the standard input file.

```
StdOutputHandle = 1
```

Value of the OS handle for the standard output file.

`S_FALSE = 1`

Interface call result: Not OK

`S_OK = 0`

Interface call result: OK

`Test8086 : Byte = 2`

This constant will only exist on Intel CPU platforms.

`Test8087 : Byte = 3`

This constant will only exist on Intel CPU platforms.

`TextRecBufSize = 256`

`TextRecBufSize` is the default buffer size for text files. The actual buffer can be set to another size using `SetTextBuf` ([1543](#)).

`TextRecNameLength = 256`

`TextRecNameLength` is the maximum filename size for text files.

`ThreadingAlreadyUsed : Boolean = False`

Internal constant for the threading system. Don't use.

`tkAnsiChar = tkChar`

`tkAnsiChar` is an alias for `TTypeKind.tkChar` ([1405](#))

`tkAnsiString = tkAString`

`tkAnsiString` is an alias for `TTypeKind.tkAString` ([1405](#))

`tkShortString = tkSString`

`tkShortString` is an alias for `TTypeKind.tkSString` ([1405](#))

`tkUnicodeString = tkUString`

`tkUnicodeString` is an alias for `TTypeKind.tkUString` ([1405](#))

`tkWideChar = tkWChar`

`tkWideChar` is an alias for `TTypeKind.tkUChar` ([1405](#))

`tkWideString = tkWString`

`tkWideString` is an alias for `TTypeKind.tkWString` ([1405](#))

`UnixGetModuleByAddrHook` : `procedure(addr: pointer; var baseaddr: pointer
; var filename: string) = Nil`

`UnixGetModuleByAddrHook` is used on Unix systems to retrieve a module name based on an address. It is used in the `exeinfo` ([725](#)) unit to map addresses to module (programs or library) names.

`UnusedHandle = - 1`

Value indicating an unused file handle (as reported by the OS).

`VarAddRefProc` : `procedure(var v: tvardata) = Nil`

Callback to increase reference count of a variant.

`varAny = $101`

Variant type: Any

`varArray = $2000`

Variant type: variant Array

`varBoolean = 11`

Variant type: Boolean type

`varByRef = $4000`

Variant type: By reference

`varByte = 17`

Variant type: Byte (8 bit)

`VarClearProc` : `procedure(var v: tvardata) = Nil`

Callback to clear a variant.

`VarCopyProc` : `procedure(var d: tvardata; const s: tvardata) = Nil`

Callback to copy a variant

`varCurrency = 6`

Variant type: Currency

`varDate = 7`

Variant type: Date

`varDecimal = 14`

Variant type: Decimal (BCD)

`varDispatch = 9`

Variant type: dispatch interface

`varDouble = 5`

Variant type: Double float

`varEmpty = 0`

Variant type: Empty variant

`varError = 10`

Variant type: Error type

`varInt64 = 20`

Variant type: Integer (64-Bit)

`varInteger = 3`

Variant type: Integer (32-bit)

`varLongWord = 19`

Variant type: Word (32 bit)

`varNull = 1`

Variant type: Null ([1513](#)) variant

`varOleStr = 8`

Variant type: OLE string (widestring)

`varQWord = 21`

Variant type: Word (64-bit)

`varRecord = 36`

Record variant type

`varShortInt = 16`

Variant type: Shortint (16 bit)

varSingle = 4

Variant type: Single float

varSmallInt = 2

Variant type: smallint (8 bit)

varStrArg = \$48

Variant type: String

varString = \$100

Variant type: String

```
VarToLStrProc : procedure(var d: AnsiString; const s: tvardata) =
    Nil
```

Callback to convert a variant to a ansistring.

```
VarToWStrProc : procedure(var d: WideString; const s: tvardata) =
    Nil
```

Callback to convert a variant to a widestring.

varTypeMask = \$fff

Variant type: Mask to extract type

varUInt64 = varQWord

varuint64 denotes an unsigned 64-bit value in a variant. It is one of the values found in the VType field of the variant record tvardata ([1411](#)).

varUnknown = 13

Variant type: Unknown

varUStrArg = \$49

varustrarg denotes a Unicode string argument in DispInvoke call. It will be converted to varustring in a variant.

varUString = \$102

varustring denotes a Unicode string value in a variant. It is one of the values found in the VType field of the variant record tvardata ([1411](#)).

`varVariant = 12`

Variant type: Variant (arrays only)

`varWord = 18`

Variant type: Word (16 bit)

`varWord64 = varQWord`

Variant type: Word (64-bit)

`vmtAfterConstruction = vmtMethodStart + sizeof(codepointer) * 5`

VMt Layout: ?

`vmtAutoTable = vmtParent + sizeof(pointer) * 7`

VMt layout: ?

`vmtBeforeDestruction = vmtMethodStart + sizeof(codepointer) * 6`

VMt Layout: ?

`vmtClassName = vmtParent + sizeof(pointer)`

VMt Layout: location of class name.

`vmtDefaultHandler = vmtMethodStart + sizeof(codepointer) * 4`

VMt Layout: ?

`vmtDefaultHandlerStr = vmtMethodStart + sizeof(codepointer) * 7`

VMt Layout: ?

`vmtDestroy = vmtMethodStart`

VMt Layout: Location of destructor pointer.

`vmtDispatch = vmtMethodStart + sizeof(codepointer) * 8`

`vmtDispatch` is the offset from the VMT start, in bytes to the dispatch table for a class. The dispatch table is used when dispatching messages in `TObject.Dispatch` ([1602](#))

`vmtDispatchStr = vmtMethodStart + sizeof(codepointer) * 9`

`vmtDispatchStr` is the offset from the VMT start, in bytes to the dispatch table for a class. The dispatch table is used when dispatching messages in `TObject.DispatchStr` ([1603](#))

`vmtDynamicTable = vmtParent + sizeof(pointer) * 2`

VMT Layout: location of dynamic methods table.

```
vmtEquals = vmtMethodStart + sizeof(codepointer) * 10
```

vmtEquals contains the offset from the VMT start, of the location of the TObj.Equals (1605) method pointer.

```
vmtFieldTable = vmtParent + sizeof(pointer) * 4
```

VMT Layout: Location of fields table.

```
vmtFreeInstance = vmtMethodStart + sizeof(codepointer) * 2
```

VMT Layout: location of FreeInstance method.

```
vmtGetHashCode = vmtMethodStart + sizeof(codepointer) * 11
```

vmtGetHashCode contains the offset from the VMT start, of the location of the TObj.GetHashCode (1605) method pointer.

```
vmtInitTable = vmtParent + sizeof(pointer) * 6
```

VMT Layout: ?

```
vmtInstanceSize = 0
```

VMT Layout: Location of class instance size in VMT

```
vmtIntfTable = vmtParent + sizeof(pointer) * 8
```

VMT layout: Interface table

```
vmtMethodStart = vmtParent + sizeof(pointer) * 10
```

VMT layout: start of method table.

```
vmtMethodTable = vmtParent + sizeof(pointer) * 3
```

VMT Layout: Method table start.

```
vmtMsgStrPtr = vmtParent + sizeof(pointer) * 9
```

VMT layout: message strings table.

```
vmtNewInstance = vmtMethodStart + sizeof(codepointer)
```

VMT Layout: location of NewInstance method.

```
vmtParent = sizeof(SizeInt) * 2
```

VMT Layout: location of pointer to parent VMT.

`vmtSafeCallException = vmtMethodStart + sizeof(codepointer) * 3`

VMT Layout: ?

`vmtToString = vmtMethodStart + sizeof(codepointer) * 12`

`vmtToString` contains the offset from the VMT start, of the location of the `TObject.ToString` (1606) method pointer.

`vmtTypeInfo = vmtParent + sizeof(pointer) * 5`

VMT Layout: Location of class type information.

`vtAnsiString = 11`

TVarRec type: Ansistring

`vtBoolean = 1`

TVarRec type: Boolean

`vtChar = 2`

TVarRec type: Char

`vtClass = 8`

TVarRec type: Class type

`vtCurrency = 12`

TVarRec type: Currency

`vtExtended = 3`

TVarRec type: Extended

`vtInt64 = 16`

TVarRec type: Int64 (signed 64-bit integer)

`vtInteger = 0`

TVarRec type: Integer

`vtInterface = 14`

TVarRec type: Interface

`vtObject = 7`

TVarRec type: Object instance

vtPChar = 6

TVarRec type: PChar

vtPointer = 5

TVarRec type: pointer

vtPWideChar = 10

TVarRec type: PWideChar

vtQWord = 17

TVarRec type: QWord (unsigned 64-bit integer)

vtString = 4

TVarRec type: String

vtUnicodeString = 18

vtUnicodeString denotes a Unicode string argument in the array of const. The TVarRec.VUnicodeString field will contain the actual value.

vtVariant = 13

TVarRec type: Variant

vtWideChar = 9

TVarRec type: Widechar

vtWideString = 15

TVarRec type: WideString

75.10.2 Types

AnsiChar = Char

Alias for 1-byte sized char.

Byte = 0..255

An unsigned 8-bits integer

Cardinal = LongWord

An unsigned 32-bits integer.

`Char = #0..#255`

`Char` is the basic ANSI character type, with a range of `[#0..#255]`.

`CodePointer = Pointer`

`CodePointer` is used in 8/16-bit targets to indicate pointers to code segments. On all other platforms this equals `Pointer`.

`CodePointer = Pointer`

`CodePointer` is used in 8/16-bit targets to indicate pointers to code segments. On all other platforms this equals `Pointer`.

`CodePtrInt = PtrInt`

`CodePtrInt` is a signed integer with the same size as `CodePointer` ([1373](#))

`CodePtrInt = PtrInt`

`CodePtrInt` is a signed integer with the same size as `CodePointer` ([1373](#))

`CodePtrUInt = PtrUInt`

`CodePtrUInt` is an unsigned integer with the same size as `CodePointer` ([1373](#))

`CodePtrUInt = PtrUInt`

`CodePtrUInt` is an unsigned integer with the same size as `CodePointer` ([1373](#))

`Comp = Int64`

`Comp` is a 64-bit floating point type. See the language reference for more details.

`DWord = LongWord`

An unsigned 32-bits integer

```
EnumResLangProc = function(ModuleHandle: TFPResourceHMODULE;
    ResourceType: PChar; ResourceName: PChar;
    IDLanguage: Word; lParam: PtrInt) :
    LongBool
```

`EnumResNameProcs` used in the `EnumResourceLanguages` ([1459](#)) call. It is called for all languages for a resource of the specified type and name, and is passed the `ModuleHandle`, `ResourceName`, `ResourceName` and `IDLanguage` values for each language encountered for the specified resource. Additionally, the `lParam` parameter from the `EnumResourceLanguages` is passed unaltered.

```
EnumResNameProc = function(ModuleHandle: TFPResourceHMODULE;
    ResourceType: PChar; ResourceName: PChar;
    lParam: PtrInt) : LongBool
```

EnumResNameProc is used in the EnumResourceNames (1460) call. It is called for all resources of the specified type, and is passed the ModuleHandle, ResourceType, ResourceName values for each resource encountered. Additionally, the lParam parameter from the EnumResourceNames is passed unaltered.

```
EnumResTypeProc = function(ModuleHandle: TFPResourceHMODULE;
    ResourceType: PChar; lParam: PtrInt)
    : LongBool
```

EnumResTypeProc is used in the EnumResourceTypes (1460) call. It is called for all resources, and is passed the ModuleHandle, ResourceType values for each resource encountered. Additionally, the lParam parameter from the EnumResourceTypes is passed unaltered.

```
FarPointer = Pointer
```

FarPointer is used in 8/16-bit targets to indicate far pointers (over segments). On all other platforms this equals Pointer.

```
FileRec = record
public
    Handle : THandle;
    Mode : LongInt;
    RecSize
    : SizeInt;
    _private : Array[1..3*SizeOf(SizeInt)+5*SizeOf(pointer
    )] of Byte;
    UserData : Array[1..32] of Byte;
    name : Array[0..filerecnamelength
    ] of TFileTextRecChar;
end
```

FileRec is the underlying type used in untyped files. It should be treated as opaque and never manipulated directly.

```
HGLOBAL = PtrUInt
```

This is an opaque type.

```
HMODULE = PtrUInt
```

This is an opaque type.

```
HRESULT = LongInt
```

32-Bit signed integer.

```
IInterface = IUnknown
```

`IInterface` is the basic interface from which all COM style interfaces descend.

`Int16 = SmallInt`

A signed 16-bits integer

`Int32 = LongInt`

A signed 32-bits integer

`Int64 = - 9223372036854775808..9223372036854775807`

`Int64` is a 64-bit, signed integer type, with range [-9223372036854775808..9223372036854775807].

`Int8 = ShortInt`

A signed 8-bits integer

`Integer = SmallInt`

The system unit defines `Integer` as a signed 16-bit integer. But when DELPHI or OBJFPC mode are active, then the `objpas` unit redefines `Integer` as a 32-bit integer.

Remark Note that due to the way the language modes are implemented, if you refer to `integer` with the fully qualified name `System.Integer`, you will still get a 16-bit integer.

`IntegerArray = Array[0..$ffffff] of Integer`

Generic array of integer.

`IntPtr = PtrInt`

A signed integer with the same size in bytes as pointer

```
jmp_buf = packed record
public
    ebx : LongInt;
    esi : LongInt;
    edi : LongInt;
    bp  : Pointer;
    sp  : Pointer;
    pc  : Pointer;
end
```

Record type to store processor information.

`Longint = - 2147483648..2147483647`

A signed 32-bits integer

`Longword = 0..4294967295`

The base 32-bit unsigned type. See the reference manual for more details

`MAKEINTRESOURCE = PChar`

Alias for the `PChar` (1377) type.

`MarshaledAString = PAnsiChar`

Alias for `PAnsiChar`

`MarshaledString = PWideChar`

Alias for `PWideChar`

`NativeInt = PtrInt`

`NativeInt` is defined for Delphi compatibility. It is a signed integer with the size of a pointer, so 32-bit on 32-bit platforms, 64-bit on 64-bit platforms. It is advisable to use unsigned variants of this type. See `PtrUInt` (1384) for details.

`NativeUInt = PtrUInt`

`NativeUInt` is defined for Delphi compatibility. It is an unsigned integer with the size of a pointer, so 32-bit on 32-bit platforms, 64-bit on 64-bit platforms.

`OpaquePointer = POpaqueData`

Type alias for `POpaqueData`

`PAnsiChar = PChar`

Alias for `PChar` (1377) type.

`PAnsiString = ^AnsiString`

Pointer to an `ansistring` type.

`PBoolean = ^Boolean`

Pointer to a `Boolean` type.

`PBoolean16 = ^Boolean16`

Pointer to `Boolean16` type.

`PBoolean32 = ^Boolean32`

Pointer to `Boolean32` type.

`PBoolean64 = ^Boolean64`

Pointer to Boolean64 type.

```
PBoolean8 = ^Boolean8
```

Pointer to Boolean8 type.

```
PByte = ^Byte
```

Pointer to byte (1372) type

```
PByteBool = ^ByteBool
```

Pointer to ByteBool type.

```
pcallldesc = ^tcallldesc
```

Pointer to TCallDesc (1388) record.

```
PCardinal = ^Cardinal
```

Pointer to Cardinal (1373) type

```
PChar = ^Char
```

Or the same as a pointer to an array of char. See the reference manual for more information about this type.

```
PClass = ^TClass
```

Pointer to TClass (1388)

```
PCodePointer = ^CodePointer
```

PCodePointer is a typed pointer to CodePointer (1373).

```
PCurrency = ^Currency
```

Pointer to currency type.

```
PDate = ^TDateTime
```

Pointer to a TDateTime (1389) type.

```
PDateTime = ^TDateTime
```

Pointer to TDateTime

```
PDispatch = ^IDispatch
```

Pointer to IDispatch (1588) interface type

`pdispdesc = ^tdispdesc`

Pointer to `tdispdesc` (1389) record

`PDouble = ^Double`

Pointer to double-sized float value.

`PDWord = ^DWord`

Pointer to `DWord` (1373) type

`pdynarrayindex = ^tdynarrayindex`

Pointer to `tdynarrayindex` (1390) type.

`pdynarraytypeinfo = ^tdynarraytypeinfo`

Pointer to `TDynArrayTypeInfo` (1390) type.

`PError = ^TError`

Pointer to an `Error` (1463) type.

`PEventState = pointer`

Pointer to `EventState`, which is an opaque type.

`PExceptAddr = ^TExceptAddr`

`PExceptAddr` is a pointer to `PExceptAddr` (1378)

`PExceptObject = ^TExceptObject`

Pointer to Exception handler procedural type `TExceptProc` (1392)

`PExtended = ^Extended`

Pointer to extended-sized float value.

`PFileTextRecChar = ^TFileTextRecChar`

`PFileTextRecChar` is a typed pointer to `TFileTextRecChar` (1392).

`PGuid = ^TGuid`

Pointer to `TGUID` (1395) type.

`PInt16 = PSmallInt`

Pointer to `Int16` (1375) type

`PInt32 = PLongint`

Pointer to Int32 (1375) type

`PInt64 = ^Int64`

Pointer to Int64 type

`PInt8 = PShortInt`

Pointer to Int8 (1375) type

`PInteger = ^Integer`

Pointer to integer (1375) type

`PIntegerArray = ^IntegerArray`

Pointer to IntegerArray (1375) type

`PInterface = PUnknown`

Pointer to IInterface (1375) interface

`pinterfaceentry = ^tinterfaceentry`

Pointer to tinterfaceentry (1583) record.

`pinterfacetable = ^tinterfacetable`

Pointer to tinterfacetable (1397) record.

`PIntPtr = PPtrInt`

Pointer to IntPtr (1375) type

`PJump_buf = ^jmp_buf`

Pointer to jmp_buf (1375) record

`PLongBool = ^LongBool`

Pointer to a LongBool type.

`PLongint = ^LongInt`

Pointer to Longint (1375) type

`PLongWord = ^LongWord`

Pointer to LongWord type

PMarshaledAString = ^PAnsiChar

Pointer to PWideChar

PMarshaledString = ^PWideChar

Pointer to PWideChar

PMemoryManager = ^TMemoryManager

Pointer to TMemoryManager (1397) record

PMethod = ^TMethod

Pointer to method

PMsgStrTable = ^TMsgStrTable

Pointer to array of TMsgStrTable (1398) records.

PNativeInt = ^NativeInt

Pointer to NativeInt (1376) type

PNativeUInt = ^NativeUInt

Pointer to NativeInt (1376) type

PointerArray = Array[0..512*1024*1024-2] of Pointer

Generic pointer array.

POleVariant = ^OleVariant

Pointer to OleVariant type.

POpaqueData = ^TOpaqueData

POpaqueData represents a pointer to data for which the internal structure must not be known. You can make type aliases from this pointer.

PPAnsiChar = PPChar

Alias for PPChar (1381) type.

PPByte = ^PByte

PPByte is a pointer to a PByte (1377) type.

PPChar = ^PChar

Pointer to an array of pointers to null-terminated strings.

```
PPCharArray = ^TPCharArray
```

Pointer to TPCharArray (1398) type.

```
PPCodePointer = ^PCodePointer
```

PPCodePointer is a typed pointer to PCodePointer (1377).

```
PPDispatch = ^PDispatch
```

Pointer to PDispatch (1377) pointer type

```
PPDouble = ^PDouble
```

PPDouble is a pointer to a PDouble (1378) type.

```
ppdynarraytypeinfo = ^pdynarraytypeinfo
```

Pointer to pdynarraytypeinfo

```
PPLongint = ^PLongint
```

PPLongint is a pointer to a PLongint (1379) type.

```
PPPointer = ^Pointer
```

Pointer to a pointer type.

```
PPPointerArray = ^PointerArray
```

Pointer to PointerArray (1380) type

```
PPPAansiChar = PPPChar
```

PPPAansiChar is a typed pointer to PPAnsichar (1380).

```
PPPChar = ^PPChar
```

PPPChar is a pointer to a PPChar (1381)

```
PPPPointer = ^PPPointer
```

Pointer to a PPointer (1381) type.

```
PPPWideChar = ^PPWideChar
```

PPPWideChar is a pointer to a PPWideChar (1382) type.

```
PPPtrInt = ^PtrInt
```

Pointer to `PtrInt` (1383) type.

```
PPtrUInt = ^PtrUInt
```

Pointer to unsigned integer of pointer size

```
PPUnknown = ^PUnknown
```

Pointer to untyped pointer

```
PPVmt = ^PVmt
```

Pointer to PVMT pointer.

```
PPWideChar = ^PWideChar
```

Pointer to link id="PWideChar"> type.

```
PQWord = ^QWord
```

Pointer to QWord type

```
PQWordBool = ^QWordBool
```

Pointer to QWordBool type.

```
PRawByteString = ^RawByteString
```

Pointer to RawByteString

```
PRTLCriticalSection = ^RTLCriticalSection
```

Pointer to `#rtl.system.RTLCriticalSection` (1400) type.

```
PRTLEvent = pointer
```

Pointer to RTLEvent, which is an opaque type.

```
PShortInt = ^ShortInt
```

Pointer to shortint (1386) type

```
PShortString = ^ShortString
```

Pointer to a shortstring type.

```
PSingle = ^Single
```

Pointer to single-sized float value.

```
PSizeInt = ^SizeInt
```

Pointer to a `SizeInt` (1386) type

```
PSizeUInt = ^SizeUInt
```

`PSizeUInt64` is a pointer to a `SizeUInt` (1387), an unsigned integer of architecture-dependent size.

```
PSmallInt = ^SmallInt
```

Pointer to `smallint` (1387) type

```
pstringmessagetable = ^TStringMessageTable
```

Pointer to `TStringMessageTable` (1402) record.

```
PText = ^Text
```

Pointer to text file.

```
PtrInt = Int64
```

`PtInt` is a signed integer type which has always the same size as a pointer. `PtInt` is considered harmful and should almost never be used in actual code, because pointers are normally unsigned. For example, consider the following code:

```
getmem(p, 2048);           {Assume the address of p becomes $7fffffff0.}
q:=pointer(pInt(p)+1024);  {Overflow error.}
writeln(q>p);             {Incorrect answer.}
```

`PtInt` might have a valid use when two pointers are subtracted from each other if it is unknown which pointer has the largest address. However, even in this case `pInt` causes trouble in case the distance is larger than `high(pInt)` and must be used with great care.

The introduction of the `pInt` type was a mistake. Please use `ptrint` (1384) instead.

```
PtrInt = LongInt
```

`PtInt` is a signed integer type which has always the same size as a pointer. `PtInt` is considered harmful and should almost never be used in actual code, because pointers are normally unsigned. For example, consider the following code:

```
getmem(p, 2048);           {Assume the address of p becomes $7fffffff0.}
q:=pointer(pInt(p)+1024);  {Overflow error.}
writeln(q>p);             {Incorrect answer.}
```

`PtInt` might have a valid use when two pointers are subtracted from each other if it is unknown which pointer has the largest address. However, even in this case `pInt` causes trouble in case the distance is larger than `high(pInt)` and must be used with great care.

The introduction of the `pInt` type was a mistake. Please use `ptrint` (1384) instead.

```
PtrUInt = QWord
```

`PtrUInt` is an unsigned integer type which has always the same size as a pointer. When using integers which will be cast to pointers and vice versa, use this type, never the regular `Cardinal` type.

`PtrUInt = DWord`

`PtrUInt` is an unsigned integer type which has always the same size as a pointer. When using integers which will be cast to pointers and vice versa, use this type, never the regular `Cardinal` type.

`PUCS2Char = PWideChar`

Pointer to UCS2Char (1416) character.

`PUCS4Char = ^UCS4Char`

Pointer to UCS4Char (1416)

`PUCS4CharArray = ^TUCS4CharArray`

Pointer to array of UCS4Char (1416) characters.

`PUInt16 = PWord`

Pointer to UInt16 (1416) type

`PUInt32 = PDWord`

Pointer to UInt32 (1416) type

`PUInt64 = ^UInt64`

`PUInt64` is a pointer to a `UInt64` (1416), an unsigned 64-bit integer.

`PUInt8 = PByte`

Pointer to UInt8 (1416) type

`PUIntPtr = PPtrUInt`

Pointer to UIntPtr (1416) type

`PUnicodeChar = ^UnicodeChar`

`PUnicodeChar` is a pointer to a Unicode character, just like `PChar` is a pointer to a Char an-sistring character.

`PUnicodeString = ^UnicodeString`

`PUnicodeString` is a pointer to a `UnicodeString` string.

`PUnknown = ^IUnknown`

Untyped pointer

`PUTF8Char = PAnsiChar`

Pointer to UTF8Char

`PUTF8String = ^UTF8String`

Pointer to UTF8String (1417)

`pvararray = ^tvararray`

Pointer to TVarArray (1408) type.

`pvararraybound = ^tvararraybound`

Pointer to tvararraybound (1408) type.

`pvararrayboundarray = ^tvararrayboundarray`

Pointer to tvararrayboundarray (1408) type.

`pvararraycoorarray = ^tvararraycoorarray`

Pointer to tvararraycoorarray (1408) type.

`pvardata = ^tvardata`

Pointer to TVarData (1411) record.

`PVariant = ^Variant`

Pointer to Variant type.

`pvariantmanager = ^tvariantmanager`

Pointer to TVariantManager (1413) record.

`PVarRec = ^TVarRec`

Pointer to TVarRec (1415) type.

`PVmt = ^TVmt`

Pointer to TVMT (1587) record

`PWideChar = ^WideChar`

Pointer to WChar (1417).

`PWideString = ^WideString`

Pointer to widestring type

`PWord = ^Word`

Pointer to word (1417) type

```
PWordBool = ^WordBool
```

Pointer to a WordBool type.

```
QWord = 0..18446744073709551615
```

QWord is a 64-bit, unsigned integer type, with range [0..18446744073709551615].

```
RawByteString = ansistring
```

RawByteString is a single-byte character string which does not have any codepage associated with it.

This means that assigning a single-byte character string to this kind of string will not change the codepage of the string.

Inversely, when assigning a RawByteString to a single-byte string, the codepage of the destination is simply set to the codepage of the rawbytestring: no codepage conversion happens, the reference count is simply increased.

```
Real = Double
```

Alias for real type

```
Real48 = Array[0..5] of Byte
```

TP compatible real type (6 bytes) definition

```
Shortint = - 128..127
```

A signed 8-bits integer

```
SizeInt = LongInt
```

SizeInt is used to describe sizes of structures in FPC using a signed integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

```
SizeInt = Int64
```

SizeInt is used to describe sizes of structures in FPC using a signed integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

```
SizeUInt = QWord
```

SizeUInt is used to describe sizes of structures in FPC using an unsigned integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`SizeUInt = DWord`

`SizeUInt` is used to describe sizes of structures in FPC using an unsigned integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`Smallint = - 32768..32767`

A signed 16-bits integer

`TAbstractErrorProc = procedure`

Abstract error handler procedural type.

`TAllocateThreadVarsHandler = procedure`

Threadvar allocation callback type for `TThreadManager` ([1404](#)).

`TAnsiChar = Char`

Alias for 1-byte sized char.

```
TAssertErrorProc = procedure(const msg: ShortString;
    const fname: ShortString; lineno: LongInt;
    erroraddr: pointer)
```

Assert error handler procedural type.

`TBacktraceStrFunc = function(Addr: CodePointer) : ShortString`

Type for formatting of backtrace dump.

```
TBasicEventCreateHandler = function(EventAttributes: Pointer;
    AManualReset: Boolean;
    InitialState: Boolean;
    const Name: ansistring)
    : PEventState
```

callback type for creating eventstate in `TThreadManager` ([1404](#)).

`TBasicEventHandler = procedure(state: PEventState)`

Generic callback type for handling eventstate in `TThreadManager` ([1404](#)).

```
TBasicEventWaitForHandler = function(timeout: Cardinal;
    state: PEventState) : LongInt
```

Wait for basic event callback type for `TThreadManager` ([1404](#)).

```
TBeginThreadHandler = function(sa: Pointer; stacksize: PtrUInt;
  ThreadFunction: TThreadFunc; p: pointer
  ;
                                creationFlags: DWord;
  var ThreadId: TThreadID) : TThreadID
```

Callback for thread start in TThreadManager (1404).

```
TBoundArray = Array of SizeInt
```

Dynamic array of integer.

```
tcalldesc = packed record
public
  calltype : Byte;
  argcount : Byte
  ;
  namedargcount : Byte;
  argtypes : Array[0..255] of Byte;
end
```

tcalldesc is used to encode the arguments to a dispatch call to an OLE dual interface. It is used on windows only. It describes the arguments to a call.

```
TClass = class of TObject
```

Class of TObject (1595).

```
TCompareOption = (coIgnoreCase)
```

Table 75.10: Enumeration values for type TCompareOption

Value	Explanation
coIgnoreCase	Ignore case (usually identical to coLingIgnoreCase)

TCompareOption indicates how 2 strings should be compared. This option is used in the WideString-Manager (1416) implementation when comparing 2 strings. The following options exist:

Ignore case linguistically (usually identical to coIgnoreCase)

Ignore diacritic characters

Ignore case (usually identical to coLingIgnoreCase)

Corresponding hiragana and katakana characters compare as equal.

Corresponding hiragana and katakana characters compare as equal.

Ignore nonspace characters (usually identical to coLingIgnoreDiacritic)

Ignore symbols and punctuation characters

Ignore half-width and full width characters (used in Chinese and Japanese)

Use linguistic rules for casing, instead of file system rules

Treat digits as numbers (20 before 120)

Handle punctuation as symbols

Not all platforms will support all possibilities.

`TCompareOptions = Set of TCompareOption`

`TCompareOptions` is simply a set of `TCompareOption` (1388) enumeration values.

`TCriticalSectionHandler = procedure (var cs)`

Generic callback type for critical section handling in `TThreadManager` (1404).

`TCriticalSectionHandlerTryEnter = function (var cs) : LongInt`

`TCriticalSectionHandlerTryEnter` is the function prototype for the `TryEnterCriticalSection` (1563) function, in the `TThreadManager` (1404) record's `TryEnterCriticalSection` field.

`TCtrlBreakHandler = function (CtrlBreak: Boolean) : Boolean`

`TCtrlBreakHandler` is the prototype for the CTRL-C handler. If `CtrlBreak` is `True` then Ctrl-Break was hit, otherwise CTRL-C was hit. The handlers should return `True` to signal that the key-combination was handled. If `False` is returned, then default handling will be used, which by default means an exception will be raised if the `sysutils` unit is used.

`TDate = TDateTime`

`TDate` is defined for Delphi compatibility. This type is deprecated, use `TDateTime` (1389) instead.

`TDateTime = Double`

Encoded Date-Time type.

```
tdispdesc = packed record
public
    dispid : LongInt;
    restype : Byte
    ;
    calldesc : tcalldesc;
end
```

`tcalldesc` is used to encode a dispatch call to an OLE dispatch interface. It is used on windows only. It describes the dispatch call call.

`tdynarrayindex = SizeInt`

A variable of type `tdynarrayindex` will always have the correct size, suitable for serving as an index in a dynamic array.

```
tdynarraytypeinfo = packed record
public
  kind : TTypeKind;
  namelen
    : Byte;
  elesize : SizeInt;
  eletype : ppdynarraytypeinfo;
  vartype
    : LongInt;
end
```

`tdynarraytypeinfo` describes the structure of a multi-dimensional dynamic array. It is used in the `DynArraySetLength` (1458) call.

```
TDynLibsManager = record
public
  LoadLibraryU : TLoadLibraryUHandler
  ;
  LoadLibraryA : TLoadLibraryAHandler;
  GetProcAddress : TGetProcAddressHandler
  ;
  GetProcAddressOrdinal : TGetProcAddressOrdinalHandler;
  UnloadLibrary
    : TUnloadLibraryHandler;
  GetLoadErrorStr : TGetLoadErrorStrHandler
  ;
end
```

`TDynLibsManager` contains all the callbacks needed to load and manage dynamic libraries. The system unit does not contain dynamic loading library support on all supported platforms. Like the unicode string support, heap support and thread support, support for loading dynamic libraries is pluggable. This record contains the necessary callbacks that the system unit needs to implement loading of dynamic libraries (needed for example for run-time package support).

Including the `dynlibs` (716) unit will enable support for dynamically loadable libraries on all platforms that support this.

```
TEndThreadHandler = procedure(ExitCode: DWord)
```

Callback for thread end in `TThreadManager` (1404).

```
TEntryInformation = record
public
  InitFinalTable : Pointer;
  ThreadvarTablesTable
    : Pointer;
  ResourceStringTables : Pointer;
  ResStrInitTables
    : Pointer;
  ResLocation : Pointer;
  PascalMain : procedure;
```

```

    valgrind_used
    : Boolean;
    OS : TEntryInformationOS;
end

```

TEntryInformation is used to initialize a Free Pascal program or library. Under normal circumstances, there should be no need to use this structure directly: it is used by the system unit and special linking units.

```

TEntryInformationOS = record
public
    argc : LongInt;
    argv : PPChar
    ;
    envp : PPChar;
    stkptr : pointer;
    stklen : SizeUInt;
    haltproc
    : procedure(e: LongInt);
end

```

TEntryInformationOS represents executable entry information for the current OS. This structure is OS dependent.

```
TErrors = LongInt
```

Error type, used in variants.

```
TErrorsProc = procedure(ErrNo: LongInt; Address: CodePointer;
    Frame: Pointer)
```

Standard error handler procedural type.

```
TErrorsAddr = record
public
    buf : PJump_buf;
    next : PErrorsAddr
    ;
    frametype : LongInt;
end

```

TErrorsAddr describes an exception frame on the exception address frame stack. It is used in structured stack exception handling.

```
TErrorsObject = record
public
    FObject : TObject;
    Addr : CodePointer
    ;
    Next : PErrorsObject;
    refcount : LongInt;
    Framecount : LongInt
    ;
    Frames : PCodePointer;
end

```


TExceptObject is the exception description record which is found on the exception stack.

```
TExceptProc = procedure (Obj: TObject; Addr: CodePointer;
    FrameCount: LongInt; Frame: PCodePointer)
```

Exception handler procedural type

```
TextBuf = Array[0..TextRecBufSize-1] of AnsiChar
```

TextBuf is a type for the default buffer used in TextRec (1392).

```
TextFile = Text
```

Alias for Text file type.

```
TextRec = record
public
    Handle : THandle;
    Mode : LongInt;
    bufsize
    : SizeInt;
    _private : SizeInt;
    bufpos : SizeInt;
    bufend : SizeInt
;
    bufptr : ^TextBuf;
    openfunc : CodePointer;
    inoutfunc : CodePointer
;
    flushfunc : CodePointer;
    closefunc : CodePointer;
    UserData
    : Array[1..32] of Byte;
    name : Array[0..textrecnamelength-1] of
    TFileTextRecChar;
    LineEnd : TLineEndStr;
    buffer : TextBuf;
end
```

TextRec is the underlying type used in text files. It should be treated as opaque and never manipulated directly.

```
TFileTextRecChar = UnicodeChar
```

TFileTextRecChar is the type of character used in TextRec (1392) or FileRec (1374) file types. It is an alias type, depending on platform and RTL compilation flags. No assumptions should be made on the actual character type.

```
TFloatSpecial = (fsZero, fsNZero, fsDenormal, fsNDenormal, fsPositive
,
    fsNegative, fsInf, fsNInf, fsNaN, fsInvalidOp)
```

Table 75.11: Enumeration values for type TFloatSpecial

Value	Explanation
fsDenormal	Denormal value
fsInf	Infinity
fsInvalidOp	Invalid operation
fsNaN	Not a number
fsNDenormal	Negative enormal value
fsNegative	Negative value
fsNInf	Negative infinity
fsNZero	Negative zero
fsPositive	Positive value
fsZero	Zero

TFloatSpecial enumerates a series of floating point value properties.

```
TFPCHeapStatus = record
public
  MaxHeapSize : PtrUInt;
  MaxHeapUsed
  : PtrUInt;
  CurrHeapSize : PtrUInt;
  CurrHeapUsed : PtrUInt;
  CurrHeapFree : PtrUInt;
end
```

TFPCHeapStatus describes the state of the FPC heap manager. This is not equivalent to the THeapStatus (1396) record defined by Delphi, which contains information not meaningful for the FPC heap manager. The heap status can be retrieved by the GetFPCHeapStatus (1478) call.

```
TFPResourceHandle = PtrUInt
```

TFPResourceHandle represents a handle to a binary resource and is used in the various resource calls. Its actual type and size may differ across platforms.

```
TFPResourceHGLOBAL = PtrUInt
```

TFPResourceHGLOBAL represents a handle to the global module containing a resource. It is used in the various resource calls. It is an opaque type: its actual type and size may differ across platforms.

```
TFPResourceHMODULE = PtrUInt
```

TFPResourceHMODULE represents a module (library, executable, other) in which a resource is located. It is used in the various resource calls. It is an opaque type: its actual type and size may differ across platforms.

```
TFPUException = (exInvalidOp, exDenormalized, exZeroDivide, exOverflow
,
exUnderflow, exPrecision)
```

Table 75.12: Enumeration values for type `TFPUException`

Value	Explanation
<code>exDenormalized</code>	
<code>exInvalidOp</code>	Invalid operation error
<code>exOverflow</code>	Float overflow error
<code>exPrecision</code>	Precision error
<code>exUnderflow</code>	Float underflow error
<code>exZeroDivide</code>	Division by zero error.

`TFPUException` describes what floating point errors raise exceptions. It has been moved here from the `Math` unit.

`TFPUExceptionMask` = Set of `TFPUException`

`TFPUExceptionMask` is a set of `TFPUException` constants

`TFPUPrecisionMode` = (`pmSingle`, `pmReserved`, `pmDouble`, `pmExtended`)

Table 75.13: Enumeration values for type `TFPUPrecisionMode`

Value	Explanation
<code>pmDouble</code>	Double-type precision
<code>pmExtended</code>	Extended-type precision
<code>pmReserved</code>	?
<code>pmSingle</code>	Single-type precision

`TFPUPrecisionMode` describes the possible default precisions for the software Floating Point math routines. It has been moved here from the `math` unit.

`TFPURoundingMode` = (`rmNearest`, `rmDown`, `rmUp`, `rmTruncate`)

Table 75.14: Enumeration values for type `TFPURoundingMode`

Value	Explanation
<code>rmDown</code>	Round to biggest integer smaller than value.
<code>rmNearest</code>	Round to nearest integer
<code>rmTruncate</code>	Cut off fractional part
<code>rmUp</code>	Round to smallest integer larger than value

`TFPURoundingMode` enumerates the possible values for software floating point math rounding. It has been moved here from the `math` unit.

`TGetCurrentThreadIdHandler` = function : `TThreadID`

Callback type for retrieving thread ID in `TThreadManager` (1404).

```
TGetLoadErrorStrHandler = function : string
```

TGetLoadErrorStrHandler is the type for the GetLoadErrorStr call using ansistring names in the TDynLibsManager (1390) dynamic library loading manager.

```
TGetProcAddressHandler = function(Lib: TLibHandle;
  const ProcName: AnsiString) : Pointer
```

TGetProcAddressHandler is the type for the GetProcAddress call using ansistring names in the TDynLibsManager (1390) dynamic library loading manager.

```
TGetProcAddressOrdinalHandler = function(Lib: TLibHandle;
  Ordinal: TOrdinalEntry)
  : Pointer
```

TGetProcAddressOrdinalHandler is the type for the GetProcAddressOrdinal call using ansistring names in the TDynLibsManager (1390) dynamic library loading manager.

```
TGuid = packed record
case Integer of
1: (
public
  Data1 : DWord
  ;
  Data2 : Word;
  Data3 : Word;
  Data4 : Array[0..7] of Byte;
);
2: (
public
  D1 : DWord;
  D2 : Word;
  D3 : Word;
  D4 : Array
    [0..7] of Byte;
);
3: (
public
  time_low : DWord;
  time_mid : Word
  ;
  time_hi_and_version : Word;
  clock_seq_hi_and_reserved : Byte
  ;
  clock_seq_low : Byte;
  node : Array[0..5] of Byte;
);
end
```

Standard GUID representation type.

```
THandle = LongInt
```

This type should be considered opaque. It is used to describe file and other handles.

```

THeapStatus = record
public
  TotalAddrSpace : Cardinal;
  TotalUncommitted
  : Cardinal;
  TotalCommitted : Cardinal;
  TotalAllocated : Cardinal
  ;
  TotalFree : Cardinal;
  FreeSmall : Cardinal;
  FreeBig : Cardinal
  ;
  Unused : Cardinal;
  Overhead : Cardinal;
  HeapErrorCode : Cardinal
  ;
end

```

THeapStatus is the record describing the current heap status. It is returned by the GetHeapStatus (1478) call.

```
TInitThreadVarHandler = procedure(var offset: DWord; size: DWord)
```

Threadvar initialization callback type for TThreadManager (1404).

```
TInterfacedClass = class of TInterfacedObject
```

TInterfacedClass is a descendent of

```

tinterfaceentrytype = (etStandard,etVirtualMethodResult,
  etStaticMethodResult,etFieldValue,
  etVirtualMethodClass,etStaticMethodClass,
  etFieldValueClass)

```

Table 75.15: Enumeration values for type tinterfaceentrytype

Value	Explanation
etFieldValue	Field value
etFieldValueClass	Interface provided by a class field
etStandard	Standard entry
etStaticMethodClass	Interface provided by a static class method
etStaticMethodResult	Static method
etVirtualMethodClass	Interface provided by a virtual class method
etVirtualMethodResult	Virtual method

This is an internal type for the compiler to encode calls to dispatch interfaces.

```
tinterfacetable = record
```

```

public
  EntryCount : SizeUInt;
  Entries
    : Array[0..0] of tinterfaceentry;
end

```

Record to store list of interfaces of a class.

```
TLibHandle = PtrInt
```

TLibHandle should be considered an opaque type. It is defined differently on various platforms. The definition shown here depends on the platform for which the documentation was generated.

```
TLineEndStr = string
```

TLineEndStr is an alias for the actual line ending string type, used in TextRec (1392). It should be treated as opaque.

```

TLoadLibraryAHandler = function(const Name: RawByteString) :
  TLibHandle

```

TLoadLibraryAHandler is the type for the loadlibrary call using ansistring names in the TDynLibsManager (1390) dynamic library loading manager.

```

TLoadLibraryUHandler = function(const Name: UnicodeString) :
  TLibHandle

```

TLoadLibraryUHandler is the type for the loadlibrary call using unicode names in the TDynLibsManager (1390) dynamic library loading manager.

```

TMemoryManager = record
public
  NeedLock : Boolean;
  Getmem : function
    (Size: PtrUInt) : Pointer;
  Freemem : function(p: pointer) : PtrUInt
  ;
  FreememSize : function(p: pointer; Size: PtrUInt) : PtrUInt;
  AllocMem : function(Size: PtrUInt) : Pointer;
  ReAllocMem : function
    (var p: pointer; Size: PtrUInt) : Pointer;
  MemSize : function(p
    : pointer) : PtrUInt;
  InitThread : procedure;
  DoneThread : procedure
  ;
  RelocateHeap : procedure;
  GetHeapStatus : function : THeapStatus
  ;
  GetFPCHeapStatus : function : TFPCHeapStatus;
end

```

TMemoryManager describes the memory manager. For more information about the memory manager, see the programmer's reference.

```
TMethod = record
public
  Code : CodePointer;
  Data : Pointer;
end
```

TMethod describes a general method pointer, and is used in Run-Time Type Information handling.

```
TMsgStrTable = record
public
  name : PShortString;
  method : CodePointer
;
end
```

Record used in string message handler table.

```
TOpaqueData = record
end
```

TOpaqueData represents data for which the internal structure must not be known. It is mostly useful for the pointer definition POpaqueData ([1380](#)).

```
TOrdinalEntry = SizeUInt
```

Ordinal of entry point (windows only)

```
packed TPCharArray = Array[0..(MaxLongintdivSizeOf(PChar))-1] of
  PChar
```

Array of PChar

```
TProcedure = procedure
```

Simple procedural type.

```
TReleaseThreadVarsHandler = procedure
```

Threadvar release callback type for TThreadManager ([1404](#)).

```
TRelocateThreadVarHandler = function(offset: DWord) : pointer
```

Threadvar relocation callback type for TThreadManager ([1404](#)).

```
TResourceHandle = PtrUInt
```

This is an opaque type.

```

TResourceManager = record
public
  HINSTANCEFunc : function : TFPResourceHMODULE
  ;
  EnumResourceTypesFunc : function(ModuleHandle: TFPResourceHMODULE
  ; EnumFunc: EnumResTypeProc;
    lParam: PtrInt) : LongBool
  ;
  EnumResourceNamesFunc : function(ModuleHandle: TFPResourceHMODULE
  ; ResourceType: PChar;
    EnumFunc: EnumResNameProc; lParam
  : PtrInt) : LongBool;
  EnumResourceLanguagesFunc : function(ModuleHandle
  : TFPResourceHMODULE; ResourceType: PChar;
    ResourceName
  : PChar; EnumFunc: EnumResLangProc; lParam: PtrInt)
  :
  LongBool;
  FindResourceFunc : function(ModuleHandle: TFPResourceHMODULE
  ; ResourceName: PChar;
    ResourceType: PChar) : TFPResourceHandle
  ;
  FindResourceExFunc : function(ModuleHandle: TFPResourceHMODULE
  ; ResourceType: PChar;
    ResourceName: PChar; Language:
  Word) : TFPResourceHandle;
  LoadResourceFunc : function(ModuleHandle
  : TFPResourceHMODULE; ResHandle: TFPResourceHandle)
  :
  TFPResourceHGLOBAL;
  SizeofResourceFunc : function(ModuleHandle
  : TFPResourceHMODULE; ResHandle: TFPResourceHandle)
  :
  LongWord;
  LockResourceFunc : function(ResData: TFPResourceHGLOBAL
  ) : Pointer;
  UnlockResourceFunc : function(ResData: TFPResourceHGLOBAL
  ) : LongBool;
  FreeResourceFunc : function(ResData: TFPResourceHGLOBAL
  ) : LongBool;
end

```

TResourceManager is the record describing the resource manager. Depending on the kind of resources (internal, external), another resource managing handler is installed by the system. The resource manager record is used by all resource handling functions to do the actual work: for each function in the API, a handler function is available. People wishing to implement their own resource manager, must implement all handler functions in their implementation.

As soon as resources are used, the compiler will install a resource manager, depending on the platform, this may be an internal or an external resource manager.

```
TRTLCREATEEventHandler = function : PRTLEvent
```

Callback type for creating a TRTLEvent type in TThreadManager ([1404](#)).

TRTLCriticalSection = Opaque type

TRTLCriticalSection represents a critical section (a mutex). This is an opaque type, it can differ from operating system to operating system. No assumptions should be made about it's structure or contents.

TRTLEventHandler = procedure (AEvent: PRTLEvent)

Generic TRTLEvent handling type for TThreadManager ([1404](#)).

TRTLEventHandlerTimeout = procedure (AEvent: PRTLEvent; timeout: LongInt
)

TRTLEvent timeout handling type for TThreadManager ([1404](#)).

trtlmethod = procedure of object

Callback type for synchronization event.

```
TRuntimeError = (reNone, reOutOfMemory, reInvalidPtr, reDivByZero,
  reRangeError, reIntOverflow, reInvalidOp, reZeroDivide
  ,
    reOverflow, reUnderflow, reInvalidCast, reAccessViolation
  ,
    rePrivInstruction, reControlBreak, reStackOverflow
  ,
    reVarTypeCast, reVarInvalidOp, reVarDispatch,
  reVarArrayCreate, reVarNotArray, reVarArrayBounds,
  reAssertionFailed, reExternalException, reIntfCastError
  ,
    reSafeCallError, reQuit, reCodesetConversion,
  reNoDynLibsSupport, reThreadError)
```

Table 75.16: Enumeration values for type TRuntimeError

Value	Explanation
reAccessViolation	Access Violation
reAssertionFailed	Assertion failed error
reCodesetConversion	Code set conversion error
reControlBreak	User pressed CTRL-C
reDivByZero	Division by zero error
reExternalException	An external exception occurred
reIntfCastError	Interface typecast error
reIntOverflow	Integer overflow error
reInvalidCast	Invalid (class) typecast error
reInvalidOp	Invalid operation error
reInvalidPtr	Invalid pointer error
reNoDynLibsSupport	Runtime error if no dynamic library support is available
reNone	No error
reOutOfMemory	Out of memory error
reOverflow	Overflow error
rePrivInstruction	Privileged instruction error
reQuit	Quit signal error
reRangeError	Range check error
reSafeCallError	Safecall (IDispInterface) error
reStackOverflow	Stack overflow error
reThreadError	Runtime error if no thread support is available
reUnderflow	Underflow error
reVarArrayBounds	Variant array bounds error
reVarArrayCreate	Variant array creation error
reVarDispatch	Variant Dispatch error.
reVarInvalidOp	Invalid variant operation error
reVarNotArray	Variant is not an array error.
reVarTypeCast	Invalid typecase from variant
reZeroDivide	Division by zero error

TRuntimeError is used in the Error (1463) procedure to indicate what kind of error should be reported.

```
TSafeCallErrorProc = procedure(error: HRESULT; addr: pointer)
```

Prototype of a safecall error handler routine. Error is the error number (passed by the Windows operating system) and Addr is the address where the error occurred.

```
TSemaphoreDestroyHandler = procedure(const sem: Pointer)
```

TSemaphoreDestroyHandler is the function prototype to destroy an existing semaphore, as returned by (ThreadManager.SemaphoreInit). It is used by the thread manager (ThreadManager.SemaphoreDest

```
TSemaphorePostHandler = procedure(const sem: Pointer)
```

TSemaphorePostHandler is the function prototype to post an event to the semaphore. It should handle a pointer as returned by the ThreadManager.SemaphoreInit procedure. it's used by the thread manager ThreadManager.SemaphorePost.

```
TSemaphoreWaitHandler = procedure(const sem: Pointer)
```

TSemaphoreWaitHandler is the function prototype to wait on an event on the semaphore (which should be posted to the semaphore with `ThreadManager.SemaphorePost`). It should handle a pointer as returned by the `ThreadManager.SemaphoreInit` procedure. it's used by the thread manager `ThreadManager.SemaphoreWait`.

```
TSempahoreInitHandler = function : Pointer
```

TSempahoreInitHandler is the function prototype for initializing a semaphore. It is used by the thread manager (`ThreadManager.SemaphoreInit`) to create semaphores. The function should return a pointer, usable by the other semaphore functions of the thread manager.

```
TStandardCodePageEnum = (scpAnsi, scpConsoleInput, scpConsoleOutput
,
                        scpFileSystemSingleByte)
```

Table 75.17: Enumeration values for type TStandardCodePageEnum

Value	Explanation
scpAnsi	Ansi codepage (CP_ACP)
scpConsoleInput	Console input codepage
scpConsoleOutput	Console output codepage
scpFileSystemSingleByte	File system single byte codepage.

TStandardCodePageEnum describes several types of standard used codepages, which can be queried by the unicode string manager `TUnicodeStringManager` ([1407](#)).

```
TStringMessageTable = record
public
    count : LongInt;
    msgstrtable
    : Array[0..0] of TMsgStrTable;
end
```

Record used to describe the string messages handled by a class. It consists of a count, followed by an array of `TMsgStrTable` ([1398](#)) records.

```
TSystemCodePage = Word
```

TSystemCodePage is a type used to indicate code pages. It should be treated as an opaque type.

```
TTextBuf = TextBuf
```

TTextBuf is an alias for TextBuf

```
TTextLineBreakStyle = (tlbsLF, tlbsCRLF, tlbsCR)
```

Table 75.18: Enumeration values for type TTextLineBreakStyle

Value	Explanation
tlbsCR	Carriage-return (#13, Mac-OS style)
tlbsCRLF	Carriage-return, line-feed (#13#30, Windows style)
tlbsLF	Line-feed only (#10, Unix style)

Text line break style. (end of line character)

```
TThreadFunc = function(parameter: pointer) : PtrInt
```

Thread function prototype

```
TThreadGetPriorityHandler = function(threadHandle: TThreadID) :
    LongInt
```

Callback type for thread priority getting in TThreadManager ([1404](#)).

```
TThreadHandler = function(threadHandle: TThreadID) : DWord
```

Generic thread handler callback for TThreadManager ([1404](#)).

```
TThreadID = PtrUInt
```

This is an opaque type, it can differ from operating system to operating system.

```
TThreadManager = record
public
    InitManager : function : Boolean
    ;
    DoneManager : function : Boolean;
    BeginThread : TBeginThreadHandler
    ;
    EndThread : TEndThreadHandler;
    SuspendThread : TThreadHandler
    ;
    ResumeThread : TThreadHandler;
    KillThread : TThreadHandler;
    CloseThread : TThreadHandler;
    ThreadSwitch : TThreadSwitchHandler
    ;
    WaitForThreadTerminate : TWaitForThreadTerminateHandler;
    ThreadSetPriority
    : TThreadSetPriorityHandler;
    ThreadGetPriority : TThreadGetPriorityHandler
    ;
    GetCurrentThreadId : TGetCurrentThreadIdHandler;
    SetThreadDebugNameA
    : TThreadSetThreadDebugNameHandlerA;
    SetThreadDebugNameU : TThreadSetThreadDebugNameHandlerU
    ;
```

```

InitCriticalSection : TCriticalSectionHandler;
DoneCriticalSection
: TCriticalSectionHandler;
EnterCriticalSection : TCriticalSectionHandler
;
TryEnterCriticalSection : TCriticalSectionHandlerTryEnter;
LeaveCriticalSection
: TCriticalSectionHandler;
InitThreadVar : TInitThreadVarHandler
;
RelocateThreadVar : TRelocateThreadVarHandler;
AllocateThreadVars
: TAllocateThreadVarsHandler;
ReleaseThreadVars : TReleaseThreadVarsHandler
;
BasicEventCreate : TBasicEventCreateHandler;
BasicEventDestroy
: TBasicEventHandler;
BasicEventResetEvent : TBasicEventHandler
;
BasicEventSetEvent : TBasicEventHandler;
BasicEventWaitFor
: TBasicEventWaitForHandler;
RTLEventCreate : TRTLCreateEventHandler
;
RTLEventDestroy : TRTLEventHandler;
RTLEventSetEvent : TRTLEventHandler
;
RTLEventResetEvent : TRTLEventHandler;
RTLEventWaitFor : TRTLEventHandler
;
RTLEventWaitForTimeout : TRTLEventHandlerTimeout;
end

```

`TThreadManager` is a record that contains all callbacks needed for the thread handling routines of the Free Pascal Run-Time Library. The thread manager can be set by the `SetThreadManager` ([1545](#)) procedure, and the current thread manager can be retrieved with the `GetThreadManager` ([1481](#)) procedure.

The Windows RTL will set the thread manager automatically to a system thread manager, based on the Windows threading routines. Unix operating systems provide a unit `cthreads` which implements threads based on the C library POSIX thread routines. It is not included by default, because it would make the system unit dependent on the C library.

For more information about thread programming, see the programmer's guide.

```

TThreadSetPriorityHandler = function(threadHandle: TThreadID;
  Prio: LongInt) : Boolean

```

Callback type for thread priority setting in `TThreadManager` ([1404](#)).

```

TThreadSetThreadDebugNameHandlerA = procedure(threadHandle: TThreadID
;
                                     const ThreadName
: AnsiString)

```

`TThreadSetThreadDebugNameHandlerA` is the type of the `TThreadManager` (1404)`SetThreadDebugNameA` method. It receives the thread ID in `threadHandle` and the name (as `AnsiString`) to apply in `ThreadName`.

```
TThreadSetThreadDebugNameHandlerU = procedure(threadHandle: TThreadID
;
                                     const ThreadName
: UnicodeString)
```

`TThreadSetThreadDebugNameHandlerU` is the type of the `TThreadManager` (1404)`SetThreadDebugNameU` method. It receives the thread ID in `threadHandle` and the name to apply (as `unicodeString`) in `ThreadName`.

```
TThreadSwitchHandler = procedure
```

Callback type for thread switch in `TThreadManager` (1404).

```
TTime = TDateTime
```

`TTime` is defined for Delphi compatibility. This type is deprecated, use `TDateTime` (1389) instead.

```
TTypeKind = (tkUnknown,tkInteger,tkChar,tkEnumeration,tkFloat,tkSet
,
            tkMethod,tkSString,tkLString,tkAString,tkWString,tkVariant
,
            tkArray,tkRecord,tkInterface,tkClass,tkObject,tkWChar
,
            tkBool,tkInt64,tkQWord,tkDynArray,tkInterfaceRaw,tkProcVar
,
            tkUString,tkUChar,tkHelper,tkFile,tkClassRef,tkPointer
)
```

Table 75.19: Enumeration values for type TTypeKind

Value	Explanation
tkArray	Array property.
tkAString	Ansistring property.
tkBool	Boolean property.
tkChar	Char property.
tkClass	Class property.
tkClassRef	Class reference type
tkDynArray	Dynamic array property.
tkEnumeration	Enumeration type property.
tkFile	File type
tkFloat	Float property.
tkHelper	Helper type
tkInt64	Int64 property.
tkInteger	Integer property.
tkInterface	Interface property.
tkInterfaceRaw	Raw interface property.
tkLString	Longstring property.
tkMethod	Method property.
tkObject	Object property.
tkPointer	Generic pointer type
tkProcVar	Procedural variable
tkQWord	QWord property.
tkRecord	Record property.
tkSet	Set property.
tkSString	Shortstring property.
tkUChar	Unicode character
tkUnknown	Unknown property type.
tkUString	Unicode string
tkVariant	Variant property.
tkWChar	Widechar property.
tkWString	Widestring property.

Type of a property or value.

```
TUCS4CharArray = Array[0..$efffffff] of UCS4Char
```

Array of UCS4Char (1416) characters.

```
TUnicodeStringManager = record
public
  Wide2AnsiMoveProc : procedure
    (source: PWideChar; var dest: RawByteString;
     cp: TSystemCodePage
    ; len: SizeInt);
  Ansi2WideMoveProc : procedure(source: PChar; cp
    : TSystemCodePage; var dest: widestring;
     len: SizeInt
    );
  UpperWideStringProc : function(const S: WideString) : WideString
    ;
```

```

LowerWideStringProc : function(const S: WideString) : WideString
;
CompareWideStringProc : function(const s1: WideString; const s2
: WideString;
    Options: TCompareOptions) : PtrInt;
CharLengthPCharProc
: function(const Str: PChar) : PtrInt;
CodePointLengthProc : function
(const Str: PChar; MaxLookAead: PtrInt) : PtrInt;
UpperAnsiStringProc
: function(const s: ansistring) : ansistring;
LowerAnsiStringProc
: function(const s: ansistring) : ansistring;
CompareStrAnsiStringProc
: function(const S1: ansistring; const S2: ansistring) : PtrInt;
CompareTextAnsiStringProc : function(const S1: ansistring; const
S2: ansistring) : PtrInt;
StrCompAnsiStringProc : function(S1:
PChar; S2: PChar) : PtrInt;
StrICompAnsiStringProc : function(S1
: PChar; S2: PChar) : PtrInt;
StrLCompAnsiStringProc : function
(S1: PChar; S2: PChar; MaxLen: PtrUInt) : PtrInt;
StrLICompAnsiStringProc
: function(S1: PChar; S2: PChar; MaxLen: PtrUInt) : PtrInt;
StrLowerAnsiStringProc
: function(Str: PChar) : PChar;
StrUpperAnsiStringProc : function
(Str: PChar) : PChar;
ThreadInitProc : procedure;
ThreadFiniProc
: procedure;
Unicode2AnsiMoveProc : procedure(source: PUnicodeChar
; var dest: RawByteString;
    cp: TSystemCodePage; len:
SizeInt);
Ansi2UnicodeMoveProc : procedure(source: PChar; cp: TSystemCodePage
; var dest: unicodestring;
    len: SizeInt);
UpperUnicodeStringProc
: function(const S: UnicodeString) : UnicodeString;
LowerUnicodeStringProc
: function(const S: UnicodeString) : UnicodeString;
CompareUnicodeStringProc
: function(const s1: UnicodeString; const s2: UnicodeString;
Options: TCompareOptions) : PtrInt;
GetStandardCodePageProc
: function(const stdcp: TStandardCodePageEnum) : TSystemCodePage
;
end

```

TUnicodeStringManager is currently the same as the TUnicodeStringManager (1407) manager record. It performs the same functions: converting Unicode strings to ansistrings and vice-versa, performing uppercase to lowercase transformations and comparing strings.


```
TUnloadLibraryHandler = function(Lib: TLibHandle) : Boolean
```

TUnloadLibraryHandler is the type for the UnloadLibrary call using anistring names in the TDynLibsManager (1390) dynamic library loading manager.

```
tvararray = record
public
  dimcount : Word;
  flags : Word;
  elementsize
  : LongInt;
  lockcount : LongInt;
  data : pointer;
  bounds : tvararrayboundarray
;
end
```

tvararray is a record describing a variant array. It contains some general data, followed by a number of TVarArrayBound (1408) records equal to the number of dimensions in the array (dimcount).

```
tvararraybound = record
public
  elementcount : LongInt;
  lowbound
  : LongInt;
end
```

tvararraybound is used to describe one dimension in a variant array.

```
tvararrayboundarray = Array[0..0] of tvararraybound
```

array of tvararraybound (1408) records.

```
tvararraycoorarray = Array[0..0] of LongInt
```

Array of variant array coordinates

```
tvardata = packed record
public
  vtype : tvartype;
case Integer of
  0: (
public
  res1 : Word;
case Integer of
  0: (
public
  res2 : Word
;
  res3 : Word;
case Word of
varsmallint: (
```

```
public
    vsmallint :
        SmallInt;
);
varinteger: (
public
    vinteger : LongInt;
);
varsingle
    : (
public
    vsingle : single;
);
vardouble: (
public
    vdouble :
        Double;
);
vardate: (
public
    vdate : TDateTime;
);
varcurrency
    : (
public
    vcurrency : currency;
);
varolestr: (
public
    volestr
        : PWideChar;
);
vardispatch: (
public
    vdispatch : pointer;
);
varerror
    : (
public
    verror : HRESULT;
);
varboolean: (
public
    vboolean
        : wordbool;
);
varunknown: (
public
    vunknown : pointer;
);
varustring
    : (
public
    vustring : pointer;
```

```
);
varshortint: (
public
    vshortint
    : ShortInt;
);
varbyte: (
public
    vbyte : Byte;
);
varword: (
public
    vword : Word;
);
varlongword: (
public
    vlongword : DWord;
);
varint64: (
public
    vint64 : Int64;
);
varqword: (
public
    vqword
    : QWord;
);
varword64: (
public
    vword64 : QWord;
);
varstring:
(
public
    vstring : pointer;
);
varany: (
public
    vany : pointer
    ;
);
vararray: (
public
    varray : pvararray;
);
varbyref: (
public
    vpointer : pointer;
);
varrecord: (
public
    vrecord : pointer
    ;
    precinfo : pointer;
```

```

);
);
1: (
public
    vlongs : Array[0..2] of
        LongInt;
);
);
1: (
public
    vwords : Array[0..6] of Word;
);
2:
(
public
    vbytes : Array[0..13] of Byte;
);
end

```

TVarData is a record representation of a variant. It contains the internal structure of a variant and is handled by the various variant handling routines.

```

tvariantmanager = record
public
    vartoint : function(const v: variant
    ) : LongInt;
    vartoint64 : function(const v: variant) : Int64;
    vartoword64 : function(const v: variant) : QWord;
    vartobool : function
    (const v: variant) : Boolean;
    vartoreal : function(const v: variant
    ) : extended;
    vartotdatetime : function(const v: variant) : TDateTime
    ;
    vartocurr : function(const v: variant) : currency;
    vartopstr
    : procedure(var s; const v: variant);
    vartolstr : procedure(var
    s: ansistring; const v: variant);
    vartowstr : procedure(var s:
    wideststring; const v: variant);
    vartointf : procedure(var intf:
    IInterface; const v: variant);
    vartodisp : procedure(var disp:
    IDispatch; const v: variant);
    vartodynarray : procedure(var dynarr
    : pointer; const v: variant; typeinfo: pointer);
    varfrombool : procedure
    (var dest: variant; const source: Boolean);
    varfromint : procedure
    (var dest: variant; const source: LongInt;
        const Range
    : LongInt);
    varfromint64 : procedure(var dest: variant; const source

```

```

: Int64);
varfromword64 : procedure(var dest: variant; const source
: QWord);
varfromreal : procedure(var dest: variant; const source
: extended);
varfromdatetime : procedure(var dest: Variant; const
source: TDateTime);
varfromcurr : procedure(var dest: Variant;
const source: Currency);
varfrompstr : procedure(var dest: variant
; const source: ShortString);
varfromlstr : procedure(var dest:
variant; const source: ansistring);
varfromwstr : procedure(var
dest: variant; const source: WideString);
varfromintf : procedure
(var dest: variant; const source: IInterface);
varfromdisp : procedure
(var dest: variant; const source: IDispatch);
varfromdynarray :
procedure(var dest: variant; const source: pointer; typeinfo: pointer
);
olevarfrompstr : procedure(var dest: olevariant; const source
: shortstring);
olevarfromlstr : procedure(var dest: olevariant
; const source: ansistring);
olevarfromvar : procedure(var dest
: olevariant; const source: variant);
olevarfromint : procedure
(var dest: olevariant; const source: Int64;
const range
: ShortInt);
varop : procedure(var left: variant; const right: variant
; opcode: tvarop);
cmpop : function(const left: variant; const right
: variant;
const opcode: tvarop) : Boolean;
varneg
: procedure(var v: variant);
varnot : procedure(var v: variant)
;
varinit : procedure(var v: variant);
varclear : procedure(var
v: variant);
varaddref : procedure(var v: variant);
varcopy
: procedure(var dest: variant; const source: variant);
varcast
: procedure(var dest: variant; const source: variant; vartype: LongInt
);
varcastole : procedure(var dest: variant; const source: variant
; vartype: LongInt);
dispinvoke : procedure(dest: pvardata; var
source: tvardata; calldesc: pcalldesc);

```

```

        params: pointer
    );
    vararrayredim : procedure(var a: variant; highbound: SizeInt
    );
    vararrayget : function(const a: variant; indexcount: SizeInt
    ; indices: PLongint)
        : variant;
    vararrayput : procedure
    (var a: variant; const value: variant; indexcount: SizeInt;
    indices: PLongint);
    writevariant : function(var t: text
    ; const v: variant; width: LongInt) : Pointer;
    write0Variant : function
    (var t: text; const v: Variant) : Pointer;
end

```

TVariantManager describes the variant manager as expected by the SetVariantManager (1546) call.

```

tvarop = (opadd,opsubtract,opmultiply,opdivide,opintdivide,opmodulus
,
        opshiftleft,opshiftright,opand,opor,opxor,opcompare,opnegate
,
        opnot,opcmpeq,opcmpne,opcmplt,opcmple,opcmpgt,opcmpge
,oppower)

```

Table 75.20: Enumeration values for type tvarop

Value	Explanation
opadd	Variant operation: Addition.
opand	Variant operation: Binary AND operation
opcmpeq	Variant operation: Compare equal.
opcmpge	Variant operation: Compare larger than or equal
opcmpgt	Variant operation: Compare larger than
opcmple	Variant operation: Compare less than or equal to
opcmplt	Variant operation: Compare less than.
opcmpne	Variant operation: Compare not equal
opcompare	Variant operation: Compare
opdivide	Variant operation: division
opintdivide	Variant operation: integer divide
opmodulus	Variant operation: Modulus
opmultiply	Variant operation: multiplication
opnegate	Variant operation: negation.
opnot	Variant operation: Binary NOT operation.
opor	Variant operation: Binary OR operation
oppower	Variant operation: Power
opshiftleft	Variant operation: Shift left
opshiftright	Variant operation: Shift right
opsubtract	Variant operation: Subtraction
opxor	Variant operation: binary XOR operation.

tvarop describes a variant operation. It is mainly used for the variant manager to implement the various conversions and mathematical operations on a variant.

```
TVarRec = record
case VType : SizeInt of
vtInteger: (
public
  VInteger
    : LongInt;
);
vtBoolean: (
public
  VBoolean : Boolean;
);
vtChar
  : (
public
  VChar : Char;
);
vtWideChar: (
public
  VWideChar : WideChar
  ;
);
vtExtended: (
public
  VExtended : PExtended;
);
vtString: (
  public
  VString : PShortString;
);
vtPointer: (
public
  VPointer
    : Pointer;
);
vtPChar: (
public
  VPChar : PAnsiChar;
);
vtObject
  : (
public
  VObject : TObject;
);
vtClass: (
public
  VClass : TClass
  ;
);
vtPWideChar: (
public
  VPWideChar : PWideChar;
```

```

);
vtAnsiString
  : (
public
  VAnsiString : Pointer;
);
vtCurrency: (
public
  VCurrency
  : PCurrency;
);
vtVariant: (
public
  VVariant : PVariant;
);
vtInterface
  : (
public
  VInterface : Pointer;
);
vtWideString: (
public
  VWideString
  : Pointer;
);
vtInt64: (
public
  VInt64 : PInt64;
);
vtUnicodeString
  : (
public
  VUnicodeString : Pointer;
);
vtQWord: (
public
  VQWord
  : PQWord;
);
end

```

TVarRec is a record generated by the compiler for each element in a array of const call. The procedure that receives the constant array receives an array of TVarRec elements, with lower bound zero and high bound equal to the number of elements in the array minus one (as returned by High(Args))

tvartype = Word

Type with size of variant type.

```

TWaitForThreadTerminateHandler = function(threadHandle: TThreadID
;
                                     TimeoutMs: LongInt)
: DWord

```


Callback type for thread termination in TThreadManager ([1404](#)).

TWideStringManager = TUnicodeStringManager

TWideStringManager contains the definition of the widestring manager.

UCS2Char = WideChar

UCS2 Unicode character.

UCS4Char =

UCS Unicode character (unsigned 32 bit word)

UCS4String = Array of UCS4Char

String of UCS4Char ([1416](#)) characters.

UInt16 = Word

An unsigned 16-bits integer

UInt32 = Cardinal

An unsigned 32-bits integer

UInt64 = QWord

Unsigned 64-bit integer

UInt8 = Byte

An unsigned 8-bits integer

UIntPtr = PtrUInt

Alias for PtrUInt ([1384](#)) type for compatibility with later Delphi versions.

UnicodeChar = WideChar

UnicodeChar is a single character from a UnicodeString. It equals WideChar in all respects.

UnicodeString = UnicodeString

UnicodeString is a string of WideChars. The main difference with WideString is that unicode-string is reference counted, and WideString is not reference counted on Windows.

UTF8Char = AnsiChar

UTF8Char is provided for completeness, a type alias for AnsiChar.

`UTF8String = ansistring`

UTF-8 Unicode (Ansi) string.

`ValReal = Extended`

`ValReal` is an alias for the largest available floating point type on the architecture the program runs on. On most processors, it should be one of `Double` or `Extended`.

`ValSInt = LongInt`

Integer with the same size as the return code of the `Val` (1570) function.

`ValSInt = Int64`

Integer with the same size as the return code of the `Val` (1570) function.

`ValUInt = Cardinal`

Integer with the same size as the return code of the `Val` (1570) function.

`ValUInt = QWord`

Integer with the same size as the return code of the `Val` (1570) function.

`WChar = WideChar`

Wide char (16-bit sized char)

`WideChar = #$0000..#$FFFF`

This type is the base unit for all two byte character types, like `UnicodeString` (1416) and `WideString` (1417)

`WideString = WideString`

`WideString` is an alias for `UnicodeString` on UNIX. On windows, it is a different type which has no reference counting.

`Word = 0..65535`

An unsigned 16-bits integer

75.10.3 Variables

`argc : LongInt; external 'operatingsystem_parameter_argc'`

`argc` contains the number of command-line arguments passed to the program by the OS. It is not available on all systems.

`argv : PPChar; external 'operatingsystem_parameter_argv'`

`argv` contains a pointer to a `nil`-terminated array of null-terminated strings, containing the command-line arguments passed to the program by the OS. It is not available on all systems.

`DefaultFileSystemCodePage` : `TSystemCodePage`

`DefaultFileSystemCodePage` determines the code page to which file/path names are translated before they are passed to OS API calls, if the RTL uses a single byte OS API for this purpose on the current platform.

This code page is also used for intermediate operations on file paths inside the RTL before making OS API calls.

This variable does not exist in Delphi, and has been introduced in FPC to make it possible to change the value of `DefaultSystemCodePage` without breaking RTL interfaces with the OS file system API calls.

The initial value of this variable depends on the platform:

- Windows: UTF-8, because the RTL uses UTF-16 OS API calls (so no data is lost in intermediate operations).
- OS X and iOS: UTF-8 (as defined by Apple)
- Unix (excluding OS X and iOS): equals `DefaultSystemCodePage` (1419). This is because the encoding of file names is undefined on Unix platforms: it is an untyped array of bytes that can be interpreted in any way; Specifically, it is not guaranteed to be valid UTF-8.
- Other platforms: same as `DefaultSystemCodePage` (1419).

The value of this variable may be changed using the `SetMultiByteFileSystemCodePage` (1541) procedure.

Remark The Unix/OS X/iOS settings only apply in case the `cwstring` widestring manager is installed, otherwise `DefaultFileSystemCodePage` will have the same value as `DefaultSystemCodePage` after program startup.

`DefaultRTLFileSystemCodePage` : `TSystemCodePage`

`DefaultRTLFileSystemCodePage` determines the code page to which file/path names are translated before they are returned from `RawByteString` (1386) file/path RTL routines.

Examples include the file/path names returned by the `RawByteString` versions of `SysUtils.FindFirst` (1339) and `GetDir` (1477).

The main reason for its existence is to enable the RTL to provide backward compatibility with earlier versions of FPC, as these always returned strings encoded in whatever the OS' single byte API used (normally `DefaultSystemCodePage` (1419)).

The initial value of this variable depends on the platform:

- Windows: `DefaultSystemCodePage`, for backward compatibility.
- OS X and iOS: UTF-8, for backward compatibility. It was already always UTF-8 in the past, since that's what the OS file APIs returned, and the data was never converted.
- Other Unixes: `DefaultSystemCodePage`, for the same reason as `DefaultFileSystemCodePage` (1418). Setting this to a different value than `DefaultFileSystemCodePage` is a bad idea on these platforms, since any code page conversion can corrupt these strings as their initial encoding is unknown.

- Other platforms: same as `DefaultSystemCodePage`.

The value of this variable can be set using the `SetMultiByteRTLFileSystemCodePage` (1542) call.

`DefaultSystemCodePage : TSystemCodePage`

`DefaultSystemCodePage` is used to determine how `CP_ACP` is interpreted; it is what the program considers to be the current system codepage.

It is initialized to the default system codepage.

- On windows, this is the result of the `GetACP` operating call, which returns the Windows ANSI code page.
- On iOS, this is UTF-8
- on other Unixes this will be based on the currently set `LANG` or `LC_CTYPE` environment variables. Normally this is UTF-8, but that is not guaranteed to be the case.
- For all other platforms it is set to `CP_ACP`, as these platforms currently do not support multiple code pages, and are hardcoded to use their OS-specific code page in all cases.

The `DefaultSystemCodePage` value may be set using `SetMultiByteConversionCodePage` (1541). That means that it is not a good idea to use its value to determine the real OS "default system code page".

Note that if you change `DefaultSystemCodePage`, you should call `TEncoding.FreeEncodings` to free the encodings that were created. They will be recreated with the correct (new) `DefaultSystemCodePage`.

`DefaultUnicodeCodePage : TSystemCodePage`

`DefaultUnicodeCodePage` is the unicode code page for a new unicode string. On most platforms, this is `CP_UTF16` (1346).

`DispCallByIDProc : CodePointer`

`VarDispProc` is called by the compiler if it needs to perform an interface call from a variant which contains a dispatch interface. For instance, the following call:

```
Var
  V : OleVariant;
begin
  (V as IWord).OpenDocument('c:\temp\mydoc.doc');
end;
```

where `IWord` is a dispatch interface is encoded by the compiler and passed to `DispCallByIDProc`. This pointer must be set by a routine that calls the OS COM handling routines.

`envp : PPChar; external 'operatingsystem_parameter_envp'`

`envp` contains a pointer to a nil-terminated array of null-terminated strings, containing the environment variables passed to the program by the OS. It is not available on all systems.

`ErrOutput : Text`

ErrOutput is provided for Delphi compatibility.

```
ExitCode : LongInt; public 'operatingsystem_result'
```

Exit code for the program, will be communicated to the OS on exit.

```
FirstDotAtFileNameStartIsExtension : Boolean = False
```

FirstDotAtFileNameStartIsExtension determines what happens if a filename starts with a dot (.) character. If True, then the whole file name will be treated as extension. If False, then the extension is empty.

```
InOutRes : Word
```

InOutRes contains the result of the last I/O operation using one of the file I/O routines. When I/O checks are enabled, this variable is checked and if it is nonzero, a runtime error is raised.

Although it is a variable for historical reasons, it is not meant to be written to by user code, outside of routines that implement some form of file I/O.

```
Input : Text
```

Standard input text file.

```
IsConsole : Boolean; public 'operatingsystem_isconsole' = False
```

True for console applications, False for GUI applications.

```
IsLibrary : Boolean; public 'operatingsystem_islibrary' = False
```

True if the current module is a library. Otherwise module is an executable

```
mem : Array[0..$7fffffff-1] of Byte
```

mem is an array of bytes, representing the computer's memory. This array is available only when compiling for the Dos Go32V2 target. It's use is not recommended, and it is not even available on other platforms.

```
meml : Array[0..($7fffffffdivsizeof(longint))-1] of LongInt
```

memw is an array of longints, representing the computer's memory as 32-bit signed integers. This array is available only when compiling for the Dos Go32V2 target. It's use is not recommended, and it is not even available on other platforms.

```
memw : Array[0..($7fffffffdivsizeof(word))-1] of Word
```

memw is an array of words, representing the computer's memory as 2-byte words. This array is available only when compiling for the Dos Go32V2 target. It's use is not recommended, and it is not even available on other platforms.

```
NoErrMsg : Boolean = Falseplatform
```

Unused, for Delphi compatibility

Output : Text

Standard output text file.

RandSeed : Cardinal

Seed for Random ([1521](#)) function.

ReturnNilIfGrowHeapFails : Boolean

ReturnNilIfGrowHeapFails describes what happens if there is no more memory available from the operating system. if set to True the memory manager will return Nil. If set to False then a run-time error will occur.

softfloat_exception_flags : TFPUEExceptionMask

Current soft float exception flags

softfloat_exception_mask : TFPUEExceptionMask

Current soft float exception mask

softfloat_rounding_mode : TFPURoundingMode

softfloat_rounding_mode determines how the software floating-point emulation routines do the rounding. The value can be one of the following:

float_round_nearest_even Round to nearest even number

float_round_down Round down

float_round_up Round up

float_round_to_zero Round in the direction of zero (down for positive, up for negative)

StackBottom : Pointer

Current stack bottom.

StackLength : SizeUInt

Maximum stack length.

StdErr : Text

Standard diagnostic output text file.

StdOut : Text

Alias for Output ([1421](#)).

ThreadID : TThreadID

Current Thread ID.

UTF8CompareLocale : TSystemCodePage

UTF8CompareLocale is currently present for Delphi compatibility only, it is not used in FPC code.

widestringmanager : TUnicodeStringManager

Contains the current widestring manager. Do not use directly.

WriteErrorsToStdErr : Boolean = True

WriteErrorsToStdErr can be set to True to write error messages (run-time errors, exceptions) to StdErr instead of to standard output. This is the default behaviour. When set to False, error message will be written to standard output.

75.11 Procedures and functions

75.11.1 Abs

Synopsis: Calculate absolute value

Declaration: `function Abs(l: LongInt) : LongInt`
`function Abs(l: Int64) : Int64`
`function Abs(d: ValReal) : ValReal`

Visibility: default

Description: Abs returns the absolute value of a variable. The result of the function has the same type as its argument, which can be any numerical type.

Errors: None.

See also: Round ([1532](#))

Listing: ./examples/refex/ex1.pp

Program Example1;

{ Program to demonstrate the Abs function. }

Var

`r : real;`
`i : integer;`

begin

`r:=abs(-1.0); { r:=1.0 }`
`i:=abs(-21); { i:=21 }`

end.

75.11.2 AbstractError

Synopsis: Generate an abstract error.

Declaration: `procedure AbstractError`

Visibility: default

Description: `AbstractError` generates an abstract error (run-time error 211). If the `AbstractErrorProc` ([1344](#)) constant is set, it will be called instead.

Errors: This routine causes a run-time error 211.

See also: `AbstractErrorProc` ([1344](#))

75.11.3 AcquireExceptionObject

Synopsis: Obtain a reference to the current exception object

Declaration: `function AcquireExceptionObject : Pointer`

Visibility: default

Description: `AcquireExceptionObject` returns the current exception object. It raises the reference count of the exception object, so it will not be freed. Calling this method is only valid within an except block.

The effect of this function is countered by re-raising an exception via `raise`;

To make sure that the exception object is released when it is no longer needed, `ReleaseExceptionObject` ([1526](#)) must be called when the reference is no longer needed.

Errors: If there is no current exception, a run-time error 231 will occur.

See also: `ReleaseExceptionObject` ([1526](#))

75.11.4 add(variant,variant):variant

Synopsis: Implement addition (+) operation on variants.

Declaration: `operator +(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the addition + operation is delegated to the variant manager with operation `opadd`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `-(variant, variant): variant` ([1339](#))

75.11.5 AddExitProc

Synopsis: Add an exit procedure to the exit procedure chain.

Declaration: `procedure AddExitProc(Proc: TProcedure)`

Visibility: default

Description: `AddExitProc` adds `Proc` to the exit procedure chain. At program exit, all procedures added in this way will be called in reverse order.

Errors: None.

See also: `ExitProc` ([1348](#))

75.11.6 Addr

Synopsis: Return address of a variable

Declaration: `function Addr(X: TAnytype) : Pointer`

Visibility: default

Description: `Addr` returns a pointer to its argument, which can be any type, or a function or procedure name. The returned pointer isn't typed. The same result can be obtained by the `@` operator, which can return a typed pointer (see the programmer's guide).

Errors: None

See also: `SizeOf` ([1547](#))

Listing: `./examples/refex/ex2.pp`

Program `Example2`;

{ Program to demonstrate the Addr function. }

Const `Zero : integer = 0;`

Var `p : pointer;`
`i : Integer;`

begin
`p:=Addr(p); { P points to itself }`
`p:=Addr(i); { P points to i }`
`p:=Addr(Zero); { P points to 'Zero' }`
end.

75.11.7 Align

Synopsis: Return aligned version of an address

Declaration: `function Align(Addr: PtrUInt; Alignment: PtrUInt) : PtrUInt`
`function Align(Addr: Pointer; Alignment: PtrUInt) : Pointer`

Visibility: default

Description: `Align` returns `Address`, aligned to `Alignment` bytes.

Errors: None.

75.11.8 AllocMem

Synopsis: Allocate and clear memory.

Declaration: `function AllocMem(Size: PtrUInt) : pointer`

Visibility: default

Description: `AllocMem` calls `getmem GetMem` (1478), and clears the allocated memory, i.e. the allocated memory is filled with `Size` zero bytes.

See also: `GetMem` (1478)

75.11.9 AnsiToUtf8

Synopsis: Convert ansi string to UTF-8 string

Declaration: `function AnsiToUtf8(const s: RawByteString) : RawByteString`

Visibility: default

Description: `AnsiToUtf8` converts the ansistring `S` to a UTF-8 format, that is, it converts the string from whatever codepage is currently in use, to UTF-8.

The current codepage is fetched from the system, if internationalization support is enabled. It can be UTF-8, in which case the function simply returns `S`.

Errors: None.

See also: `Utf8toAnsi` (1569)

75.11.10 Append

Synopsis: Open a file in append mode

Declaration: `procedure Append(var t: Text)`

Visibility: default

Description: `Append` opens an existing file in append mode. Any data written to `F` will be appended to the file. Only text files can be opened in append mode. After a call to `Append`, the file `F` becomes write-only. File sharing is not taken into account when calling `Append`.

Errors: If the file doesn't exist when appending, a run-time error will be generated. This behaviour has changed on Windows and Linux platforms, where in versions prior to 1.0.6, the file would be created in append mode.

See also: `Rewrite` (1528), `Close` (1441), `Reset` (1527)

Listing: `./examples/refex/ex3.pp`

Program `Example3`;

{ Program to demonstrate the Append function. }

Var `f` : text;

begin

 Assign (`f`, 'test.txt');

 Rewrite (`f`); *{ file is opened for write , and emptied }*

```

WriteIn (F, 'This is the first line of text.txt');
close (f);
Append(f);           { file is opened for write , but NOT emptied.
                       any text written to it is appended.}
WriteIn (f, 'This is the second line of text.txt');
close (f);
end.

```

75.11.11 ArcTan

Synopsis: Calculate inverse tangent

Declaration: `function ArcTan(d: ValReal) : ValReal`

Visibility: default

Description: `ArcTan` returns the Arctangent of X, which can be any Real type. The resulting angle is in radial units.

Errors: None

See also: `Sin` ([1547](#)), `Cos` ([1450](#))

Listing: `./examples/refex/ex4.pp`

```

Program Example4;

{ Program to demonstrate the ArcTan function. }

Var R : Real;

begin
  R:=ArcTan(0);      { R:=0 }
  R:=ArcTan(1)/pi;   { R:=0.25 }
end.

```

75.11.12 ArrayStringToPPchar

Synopsis: Convert an array of string to an array of null-terminated strings

Declaration: `function ArrayStringToPPchar(const S: Array of AnsiString;
 reserveentries: LongInt) : PPChar`

Visibility: default

Description: `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array S. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

Errors: If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([1554](#))

75.11.13 Assert

Synopsis: Check validity of a given condition.

Declaration: `procedure Assert (Expr: Boolean)`
`procedure Assert (Expr: Boolean; const Msg: string)`

Visibility: default

Description: With assertions on, `Assert` tests if `expr` is false, and if so, aborts the application with a Runtime error 227 and an optional error message in `msg`. If `expr` is true, program execution continues normally. If assertions are not enabled at compile time, this routine does nothing, and no code is generated for the `Assert` call. Enabling and disabling assertions at compile time is done via the `\$C` or `\$ASSERTIONS` compiler switches. These are local switches. The default behavior of the `assert` call can be changed by setting a new handler in the `AssertErrorProc` variable. `Sysutils` overrides the default handler to raise a `EAssertionFailed` exception.

Errors: None.

See also: `Halt` ([1484](#)), `Runerror` ([1534](#))

75.11.14 Assign

Synopsis: Assign a name to a file

Declaration: `procedure Assign(out f: File; const Name: ShortString)`
`procedure Assign(out f: File; const p: PAnsiChar)`
`procedure Assign(out f: File; const c: AnsiChar)`
`procedure Assign(out f: File; const Name: UnicodeString)`
`procedure Assign(out f: File; const Name: RawByteString)`
`procedure Assign(out f: TypedFile; const Name: shortstring)`
`procedure Assign(out f: TypedFile; const p: PAnsiChar)`
`procedure Assign(out f: TypedFile; const c: AnsiChar)`
`procedure Assign(out f: TypedFile; const Name: unicodestring)`
`procedure Assign(out f: TypedFile; const Name: RawByteString)`
`procedure Assign(out t: Text; const s: shortstring)`
`procedure Assign(out t: Text; const p: PAnsiChar)`
`procedure Assign(out t: Text; const c: AnsiChar)`
`procedure Assign(out t: Text; const s: unicodestring)`
`procedure Assign(out t: Text; const s: RawByteString)`

Visibility: default

Description: `Assign` assigns a name to `F`, which can be any file type. This call doesn't open the file, it just assigns a name to a file variable, and marks the file as closed.

Note that the filename (including path) can be only 255 characters long.

Errors: None.

See also: `Reset` ([1527](#)), `Rewrite` ([1528](#)), `Append` ([1425](#))

Listing: `./examples/refex/ex5.pp`

Program `Example5;`

{ Program to demonstrate the Assign function. }

Var `F : text;`

```

begin
  Assign (F, '');
  Rewrite (f);
  { The following can be put in any file by redirecting it
    from the command line. }
  Writeln (f, 'This goes to standard output !');
  Close (f);
  Assign (F, 'Test.txt');
  rewrite (f);
  writeln (f, 'This doesn't go to standard output !');
  close (f);
end.

```

75.11.15 assign(Comp):olevariant

Synopsis: Assign a comp-precision float to an ole-variant

Declaration: `operator :=(const source: Comp) : olevariant`

Visibility: default

75.11.16 assign(Comp):variant

Synopsis: Assign a comp-precision float to a variant

Declaration: `operator :=(const source: Comp) : variant`

Visibility: default

Description: The resulting variant is a double-precision value.

75.11.17 assign(extended):olevariant

Synopsis: Assign an extended-precision float to an ole-variant

Declaration: `operator :=(const source: extended) : olevariant`

Visibility: default

75.11.18 assign(extended):variant

Synopsis: Assign an extended-precision float to a variant

Declaration: `operator :=(const source: extended) : variant`

Visibility: default

Description: The resulting variant is a double-precision value

75.11.19 assign(NativeInt):variant

Declaration: `operator :=(const source: NativeInt) : variant`

Visibility: default

75.11.20 **assign(NativeUInt):variant**

Declaration: `operator :=(const source: NativeUInt) : variant`

Visibility: default

75.11.21 **assign(olevariant):Comp**

Synopsis: Assign an ole- variant to a comp-precision float

Declaration: `operator :=(const source: olevariant) : Comp`

Visibility: default

75.11.22 **assign(olevariant):extended**

Synopsis: Assign an ole- variant to an extended-precision float

Declaration: `operator :=(const source: olevariant) : extended`

Visibility: default

75.11.23 **assign(olevariant):Real**

Synopsis: Assign an ole- variant to a real-precision float

Declaration: `operator :=(const source: olevariant) : Real`

Visibility: default

75.11.24 **assign(olevariant):single**

Synopsis: Assign an ole- variant to a single-precision float

Declaration: `operator :=(const source: olevariant) : single`

Visibility: default

75.11.25 **assign(olevariant):UnicodeString**

Synopsis: Assign an ole-variant to a unicode string

Declaration: `operator :=(const source: olevariant) : UnicodeString`

Visibility: default

75.11.26 **assign(Real):olevariant**

Synopsis: Assign a real-precision float to an ole-variant

Declaration: `operator :=(const source: Real) : olevariant`

Visibility: default

75.11.27 **assign(Real):variant**

Synopsis: Assign a real-precision float to a variant

Declaration: `operator :=(const source: Real) : variant`

Visibility: default

Description: The resulting variant is a double-precision value.

75.11.28 **assign(Real48):extended**

Synopsis:

Declaration: `operator :=(b: Real48) : extended`

Visibility: default

75.11.29 **assign(single):olevariant**

Synopsis: Assign a single-precision float to an ole-variant

Declaration: `operator :=(const source: single) : olevariant`

Visibility: default

75.11.30 **assign(single):variant**

Synopsis: Assign a single-precision float to a variant

Declaration: `operator :=(const source: single) : variant`

Visibility: default

Description: The resulting variant is a double-precision value

75.11.31 **assign(UCS4String):variant**

Synopsis: Assign UCS4String to a variant, performing the necessary conversions

Declaration: `operator :=(const source: UCS4String) : variant`

Visibility: default

Description: The resulting variant is a widestring.

75.11.32 **assign(UnicodeString):olevariant**

Synopsis: Assign a unicodestring to an ole-variant

Declaration: `operator :=(const source: UnicodeString) : olevariant`

Visibility: default

75.11.33 **assign(UnicodeString):variant**

Synopsis: Assign UnicodeString to a variant, performing the necessary conversions

Declaration: `operator :=(const source: UnicodeString) : variant`

Visibility: default

Description: The resulting variant is a widestring.

75.11.34 **assign(UTF8String):variant**

Synopsis: Assign an UTF-8 string to a variant, performing the necessary conversions

Declaration: `operator :=(const source: UTF8String) : variant`

Visibility: default

Description: The resulting variant is a widestring.

75.11.35 **assign(variant):Comp**

Synopsis: Assign a variant to a comp-precision float

Declaration: `operator :=(const source: variant) : Comp`

Visibility: default

75.11.36 **assign(variant):extended**

Synopsis: Assign a variant to a extended-precision float

Declaration: `operator :=(const source: variant) : extended`

Visibility: default

75.11.37 **assign(variant):NativeInt**

Declaration: `operator :=(const source: variant) : NativeInt`

Visibility: default

75.11.38 **assign(variant):NativeUInt**

Declaration: `operator :=(const source: variant) : NativeUInt`

Visibility: default

75.11.39 **assign(variant):Real**

Synopsis: Assign a variant to a real-precision float

Declaration: `operator :=(const source: variant) : Real`

Visibility: default

75.11.40 assign(variant):single

Synopsis: Assign a variant to a single-precision float

Declaration: `operator :=(const source: variant) : single`

Visibility: default

75.11.41 assign(variant):unicodestring

Synopsis: Assign a variant to a unicodestring

Declaration: `operator :=(const source: variant) : unicodestring`

Visibility: default

75.11.42 assign(variant):UTF8String

Synopsis: Assign a variant to an UTF8String

Declaration: `operator :=(const source: variant) : UTF8String`

Visibility: default

75.11.43 Assigned

Synopsis: Check if a pointer is valid

Declaration: `function Assigned(P: Pointer) : Boolean`

Visibility: default

Description: `Assigned` returns `True` if `P` is non-nil and returns `False` if `P` is nil. The main use of `Assigned` is that Procedural variables, method variables and class-type variables also can be passed to `Assigned`.

Errors: None

See also: `New` ([1512](#))

Listing: `./examples/refex/ex96.pp`

Program `Example96`;

{ Program to demonstrate the Assigned function. }

Var `P : Pointer`;

begin

If Not Assigned(`P`) **then**

Writeln ('Pointer is initially NIL');

`P:=@P`;

If Not Assigned(`P`) **then**

Writeln ('Internal inconsistency')

else

Writeln ('All is well in FPC')

end.

75.11.44 BasicEventCreate

Synopsis: Obsolete. Don't use

Declaration: `function BasicEventCreate(EventAttributes: Pointer;
 AManualReset: Boolean; InitialState: Boolean;
 const Name: ansistring) : PEventState`

Visibility: default

Description: `BasicEventCreate` is obsolete, use `RTLEventCreate` ([1532](#)) instead.

See also: `RTLEventCreate` ([1532](#))

75.11.45 BasicEventDestroy

Synopsis: Obsolete. Don't use

Declaration: `procedure BasicEventDestroy(state: PEventState)`

Visibility: default

Description: `basiceventdestroy` is obsolete. Use `RTLEventDestroy` ([1533](#)) instead.

See also: `RTLEventDestroy` ([1533](#))

75.11.46 BasicEventResetEvent

Synopsis: Obsolete. Don't use

Declaration: `procedure BasicEventResetEvent(state: PEventState)`

Visibility: default

Description: `basiceventresetevent` is obsolete. Use `RTLEventResetEvent` ([1533](#)) instead.

See also: `RTLEventResetEvent` ([1533](#))

75.11.47 BasicEventSetEvent

Synopsis: Obsolete. Don't use

Declaration: `procedure BasicEventSetEvent(state: PEventState)`

Visibility: default

Description: `basiceventsetevent` is obsolete. Use `RTLEventSetEvent` ([1533](#)) instead.

See also: `RTLEventSetEvent` ([1533](#))

75.11.48 BasicEventWaitFor

Synopsis: Obsolete. Don't use

Declaration: `function BasicEventWaitFor(Timeout: Cardinal; state: PEventState)
 : LongInt`

Visibility: default

Description: `basiceventwaitfor` is obsolete. Use `RTLEventWaitFor` ([1534](#)) instead.

See also: `RTLEventWaitFor` ([1534](#))

75.11.49 BeginThread

Synopsis: Start a new thread.

Declaration: `function BeginThread(sa: Pointer; stacksize: SizeUInt; ThreadFunction: TThreadFunc; p: pointer; creationFlags: DWord; var ThreadId: TThreadID) : TThreadID`

`function BeginThread(ThreadFunction: TThreadFunc) : TThreadID`

`function BeginThread(ThreadFunction: TThreadFunc; p: pointer) : TThreadID`

`function BeginThread(ThreadFunction: TThreadFunc; p: pointer; var ThreadId: TThreadID) : TThreadID`

`function BeginThread(ThreadFunction: TThreadFunc; p: pointer; var ThreadId: TThreadID; const stacksize: SizeUInt) : TThreadID`

Visibility: default

Description: `BeginThread` starts a new thread and executes `ThreadFunction` in the new thread. If `P` is specified, then it is passed to `ThreadFunction`. If `ThreadId` is specified, it is filled with the thread ID of the newly started thread. If `StackSize` is specified, it is set as the stack size for the new thread. If none is specified, a default stack size of 4MiB is used.

The function returns the thread handle (or ID, on some other operating systems like Linux or OS/2) on success, or 0 if an error occurred. Note that the thread ID and handle are the same on Unix processes, and that the thread ID and thread handle are different on windows systems.

Errors: On error, the value "0" is returned.

See also: `EndThread` ([1458](#))

75.11.50 BEtoN

Synopsis: Convert Big Endian-ordered integer to Native-ordered integer

Declaration: `function BEtoN(const AValue: SmallInt) : SmallInt`

`function BEtoN(const AValue: Word) : Word`

`function BEtoN(const AValue: LongInt) : LongInt`

`function BEtoN(const AValue: DWord) : DWord`

`function BEtoN(const AValue: Int64) : Int64`

`function BEtoN(const AValue: QWord) : QWord`

Visibility: default

Description: `BETON` will rearrange the bytes in a Big-Endian number to the native order for the current processor. That is, for a big-endian processor, it will do nothing, and for a little-endian processor, it will invert the order of the bytes.

See also: `LEtoN` ([1504](#)), `NtoBE` ([1513](#)), `NtoLE` ([1513](#))

75.11.51 BinStr

Synopsis: Convert integer to string with binary representation.

Declaration: `function BinStr(Val: LongInt; cnt: Byte) : shortstring`

`function BinStr(Val: Int64; cnt: Byte) : shortstring`

`function BinStr(Val: QWord; cnt: Byte) : shortstring`

Visibility: default

Description: `BinStr` returns a string with the binary representation of `Value`. The string has at most `cnt` characters. (i.e. only the `cnt` rightmost bits are taken into account) To have a complete representation of any longint-type value, 32 bits are needed, i.e. `cnt=32`

Errors: None.

See also: `Str` ([1551](#)), `Val` ([1570](#)), `HexStr` ([1485](#)), `OctStr` ([1513](#))

Listing: `./examples/refex/ex82.pp`

```

Program example82;

{ Program to demonstrate the BinStr function }

Const Value = 45678;

Var I : longint;

begin
  For I:=8 to 20 do
    WriteLn ( BinStr(Value,I):20);
end.

```

75.11.52 BlockRead

Synopsis: Read data from an untyped file into memory

Declaration:

```

procedure BlockRead(var f: File; var Buf; count: Int64;
                    var Result: Int64)
procedure BlockRead(var f: File; var Buf; count: LongInt;
                    var Result: LongInt)
procedure BlockRead(var f: File; var Buf; count: Cardinal;
                    var Result: Cardinal)
procedure BlockRead(var f: File; var Buf; count: Word; var Result: Word)
procedure BlockRead(var f: File; var Buf; count: Word;
                    var Result: Integer)
procedure BlockRead(var f: File; var Buf; count: Int64)

```

Visibility: default

Description: `Blockread` reads `count` or less records from file `F`. A record is a block of bytes with size specified by the `Rewrite` ([1528](#)) or `Reset` ([1527](#)) statement. The result is placed in `Buffer`, which must contain enough room for `Count` records. The function cannot read partial records. If `Result` is specified, it contains the number of records actually read. If `Result` isn't specified, and less than `Count` records were read, a run-time error is generated. This behavior can be controlled by the `{SI}` switch.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Blockwrite` ([1436](#)), `Close` ([1441](#)), `Reset` ([1527](#)), `Assign` ([1427](#))

Listing: `./examples/refex/ex6.pp`

Program Example6;

{ Program to demonstrate the BlockRead and BlockWrite functions. }

```

Var Fin, fout : File;
      NumRead, NumWritten : Word;
      Buf : Array[1..2048] of byte;
      Total : Longint;

begin
  Assign (Fin, Paramstr(1));
  Assign (Fout, Paramstr(2));
  Reset (Fin, 1);
  Rewrite (Fout, 1);
  Total:=0;
  Repeat
    BlockRead (Fin, buf, Sizeof(buf), NumRead);
    BlockWrite (Fout, Buf, NumRead, NumWritten);
    inc(Total, NumWritten);
  Until (NumRead=0) or (NumWritten<>NumRead);
  Write ('Copied ', Total, ' bytes from file ', paramstr(1));
  Writeln (' to file ', paramstr(2));
  close(fin);
  close(fout);
end.

```

75.11.53 BlockWrite

Synopsis: Write data from memory to an untyped file

Declaration:

```

procedure BlockWrite(var f: File; const Buf; Count: Int64;
                     var Result: Int64)
procedure BlockWrite(var f: File; const Buf; Count: LongInt;
                     var Result: LongInt)
procedure BlockWrite(var f: File; const Buf; Count: Cardinal;
                     var Result: Cardinal)
procedure BlockWrite(var f: File; const Buf; Count: Word;
                     var Result: Word)
procedure BlockWrite(var f: File; const Buf; Count: Word;
                     var Result: Integer)
procedure BlockWrite(var f: File; const Buf; Count: LongInt)

```

Visibility: default

Description: BlockWrite writes count records from buffer to the file F. A record is a block of bytes with size specified by the Rewrite (1528) or Reset (1527) statement. If the records couldn't be written to disk, a run-time error is generated. This behavior can be controlled by the {\$I} switch.

Errors: Depending on the state of the {\$I} switch, a runtime error can be generated if there is an error. In the {\$I-} state, use IOResult to check for errors.

See also: Blockread (1435), Close (1441), Rewrite (1528), Assign (1427)

75.11.54 Break

Synopsis: Exit current loop construct.

Declaration: `procedure Break`

Visibility: `default`

Description: `Break` jumps to the statement following the end of the current repetitive statement. The code between the `Break` call and the end of the repetitive statement is skipped. The condition of the repetitive statement is NOT evaluated.

This can be used with `For`, `var{repeat}` and `While` statements.

Note that although `Break` is a compiler intrinsic (i.e. is treated specially) it is defined as a procedure in the system unit, and hence can be redefined.

Errors: None.

See also: [Continue \(1448\)](#), [Exit \(1464\)](#)

Listing: `./examples/refex/ex87.pp`

Program `Example87;`

{ Program to demonstrate the Break function. }

```

Var I : longint;

begin
  I:=0;
  While I<10 Do
    begin
      Inc(I);
      If I>5 Then
        Break;
      Writeln (i);
    end;
  I:=0;
  Repeat
    Inc(I);
    If I>5 Then
      Break;
    Writeln (i);
  Until I>=10;
  For I:=1 to 10 do
    begin
      If I>5 Then
        Break;
      Writeln (i);
    end;
end.

```

Listing: `./examples/refex/ex121.pp`

```

{
  Example 121:
  Continue, break and exit are system procedures.
  They can be redefined
}

```

procedure `continue;`

begin

```

    Writeln ( 'Continue ' );
end;

Procedure Exit ;

begin
    Writeln ( 'exit ' );
end;

Procedure Break ;

begin
    Writeln ( 'Break ' );
end;

begin
    Repeat
        Continue ;
        Break ;
        exit ;
    Until True ;
end.

```

75.11.55 BsfByte

Synopsis: Return the position of the rightmost set bit in an 8-bit value

Declaration: `function BsfByte(const AValue: Byte) : Byte`

Visibility: default

Description: `BsfByte` scans the byte `AValue`, starting at position 0 (rightmost position) and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsrByte` ([1439](#)), `BsfWord` ([1439](#)), `BsfDWord` ([1438](#)), `BsfQWord` ([1438](#))

75.11.56 BsfDWord

Synopsis: Return the position of the rightmost set bit in a 32-bit value

Declaration: `function BsfDWord(const AValue: DWord) : Cardinal`

Visibility: default

Description: `BsfDWord` scans the `DWord` `AValue`, starting at position 0 (rightmost position) , and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1438](#)), `BsfWord` ([1439](#)), `BsrDWord` ([1439](#)), `BsfQWord` ([1438](#))

75.11.57 BsfQWord

Synopsis: Return the position of the rightmost set bit in a 64-bit value

Declaration: `function BsfQWord(const AValue: QWord) : Cardinal`

Visibility: default

Description: `BsfQWord` scans the `QWord AValue`, starting at position 0 (rightmost position) , and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1438](#)), `BsfWord` ([1439](#)), `BsfDWord` ([1438](#)), `BsrQWord` ([1440](#))

75.11.58 BsfWord

Synopsis: Return the position of the rightmost set bit in a 16-bit value

Declaration: `function BsfWord(const AValue: Word) : Cardinal`

Visibility: default

Description: `BsfWord` scans the word `AValue`, starting at position 0 (rightmost position) , and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1438](#)), `BsrWord` ([1440](#)), `BsfDWord` ([1438](#)), `BsfQWord` ([1438](#))

75.11.59 BsrByte

Synopsis: Return the position of the leftmost set bit in an 8-bit value

Declaration: `function BsrByte(const AValue: Byte) : Byte`

Visibility: default

Description: `BsfByte` scans the byte `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1438](#)), `BsrWord` ([1440](#)), `BsrDWord` ([1439](#)), `BsrQWord` ([1440](#))

75.11.60 BsrDWord

Synopsis: Return the position of the leftmost set bit in a 32-bit value

Declaration: `function BsrDWord(const AValue: DWord) : Cardinal`

Visibility: default

Description: `BsrDWord` scans the `DWord AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsrByte` ([1439](#)), `BsrWord` ([1440](#)), `BsfDWord` ([1438](#)), `BsrQWord` ([1440](#))

75.11.61 BsrQWord

Synopsis: Return the position of the leftmost set bit in a 64-bit value

Declaration: `function BsrQWord(const AValue: QWord) : Cardinal`

Visibility: default

Description: `BsfQWord` scans the `QWord` `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1438](#)), `BsfWord` ([1439](#)), `BsfDWord` ([1438](#)), `BsrQWord` ([1440](#))

75.11.62 BsrWord

Synopsis: Return the position of the leftmost set bit in a 16-bit value

Declaration: `function BsrWord(const AValue: Word) : Cardinal`

Visibility: default

Description: `BsrWord` scans the word `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsrByte` ([1439](#)), `BsfWord` ([1439](#)), `BsrDWord` ([1439](#)), `BsrQWord` ([1440](#))

75.11.63 CaptureBacktrace

Synopsis: Return stack trace

Declaration: `function CaptureBacktrace(skipframes: SizeInt; count: SizeInt; frames: PCodePointer) : SizeInt`

Visibility: default

Description: `CaptureBacktrace` will fill the array pointed to by `frames` with the addresses of a backtrace. It will skip `skipframes` frames, and will write at most `count` addresses. Frames must point to enough memory to hold the stacktrace, which is `count*sizeof(codepointer)` bytes.

See also: `Get_pc_addr` ([1484](#)), `get_caller_stackinfo` ([1483](#)), `get_caller_addr` ([1482](#)), `get_caller_frame` ([1483](#))

75.11.64 ChDir

Synopsis: Change current working directory.

Declaration: `procedure ChDir(const s: shortstring); Overload`
`procedure ChDir(const s: RawByteString); Overload`
`procedure ChDir(const s: unicodestring); Overload`

Visibility: default

Description: `Chdir` changes the working directory of the process to `S`.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: Mkdir ([1510](#)), Rmdir ([1529](#))

Listing: ./examples/refex/ex7.pp

Program Example7;

{ Program to demonstrate the ChDir function. }

```
begin
  {$I-}
  ChDir (ParamStr(1));
  if IOresult <> 0 then
    Writeln ('Cannot change to directory : ', paramstr (1));
end.
```

75.11.65 Chr

Synopsis: Convert byte value to character value

Declaration: `function Chr(b: Byte) : Char`

Visibility: default

Description: Chr returns the character which has ASCII value X.

Historical note:

Originally, Pascal did not have typecasts and chr was a necessary function in order to do certain operations on ASCII values of characters. With the arrival of typecasting a generic approach became possible, making chr mostly obsolete. However, chr is not considered deprecated and remains in wide use today.

Errors: None.

See also: Ord ([1515](#)), Str ([1551](#))

Listing: ./examples/refex/ex8.pp

Program Example8;

{ Program to demonstrate the Chr function. }

```
begin
  Write (chr(10),chr(13)); { The same effect as Writeln; }
end.
```

75.11.66 Close

Synopsis: Close a file

Declaration: `procedure Close(var f: File)`
`procedure Close(var t: Text)`

Visibility: default

Description: Close flushes the buffer of the file F and closes F. After a call to Close, data can no longer be read from or written to F. To reopen a file closed with Close, it isn't necessary to assign the file again. A call to Reset ([1527](#)) or Rewrite ([1528](#)) is sufficient.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: Assign (1427), Reset (1527), Rewrite (1528), Flush (1473)

Listing: ./examples/refex/ex9.pp

Program Example9;

```
{ Program to demonstrate the Close function. }
```

```
Var F : text;
```

begin

```
Assign (f , 'Test.txt');
```

ReWrite (F);

```
WriteIn (F, 'Some text written to Test.txt');
```

```
close (f); { Flushes contents of buffer to disk,  
           closes the file. Omitting this may  
           cause data NOT to be written to disk.}
```

end .

75.11.67 CloseThread

Synopsis: Close a thread and free up resources used by the thread

Declaration: `function CloseThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `CloseThread` must be called on any thread started with `BeginThread` (1434). It must be called after the thread has ended (either by exiting the thread function or after calling `EndThread` (1458)).

Errors: If no threadmanager is installed, an exception may be raised or runtime error 232 may occur if no exceptions are used.

See also: [BeginThread \(1434\)](#), [EndThread \(1458\)](#)

75.11.68 CompareByte

Synopsis: Compare 2 memory buffers byte per byte

Declaration: `function CompareByte(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: CompareByte compares two memory regions buf1,buf2 on a byte-per-byte basis for a total of len bytes.

The function returns one of the following values:

less than 0 if buf1 and buf2 contain different bytes in the first len bytes, and the first such byte is smaller in buf1 than the byte at the same position in buf2.

0if the first `len` bytes in `buf1` and `buf2` are equal.

greater than 0 if buf1 and buf2 contain different bytes in the first len bytes, and the first such byte is larger in buf1 than the byte at the same position in buf2.

Errors: None.

See also: [CompareChar \(1443\)](#), [CompareChar0 \(1445\)](#), [CompareWord \(1446\)](#), [CompareDWord \(1445\)](#)

Listing: ./examples/refex/ex99.pp

Program Example99;

{ Program to demonstrate the CompareByte function. }

Const

 ArraySize = 100;
 HalfArraySize = ArraySize **Div** 2;

Var

 Buf1, Buf2 : **Array**[1..ArraySize] **of** byte;
 I : longint;

Procedure CheckPos(Len : Longint);

Begin

Write ('First ', Len, ' positions are ');
 if CompareByte(Buf1, Buf2, Len) <> 0 **then**
 Write ('NOT ');
 Writeln ('equal');
end;

begin

For I:=1 **to** ArraySize **do**
 begin
 Buf1[I]:=I;
 If I<=HalfArraySize **Then**
 Buf2[I]:=I
 else
 Buf2[I]:=HalfArraySize-I;
 end;
 CheckPos(HalfArraySize **div** 2);
 CheckPos(HalfArraySize);
 CheckPos(HalfArraySize+1);
 CheckPos(HalfArraySize + HalfArraySize **Div** 2);
end.

75.11.69 CompareChar

Synopsis: compare 2 memory buffers character per character

Declaration: `function CompareChar(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareChar` compares two memory regions `buf1`, `buf2` on a character-per-character basis for a total of `len` characters.

The `CompareChar0` variant compares `len` bytes, or until a zero character is found.

The function returns one of the following values:

-If buf1 and buf2 contain different characters in the first len positions, and the first such character is smaller in buf1 than the character at the same position in buf2.

0If the first len characters in buf1 and buf2 are equal.

1If buf1 and buf2 contain different characters in the first len positions, and the first such character is larger in buf1 than the character at the same position in buf2.

Errors: None.

See also: CompareByte (1442), CompareChar0 (1445), CompareWord (1446), CompareDWord (1445)

Listing: ./examples/refex/ex100.pp

Program Example100;

{ Program to demonstrate the CompareChar function. }

Const

 ArraySize = 100;
 HalfArraySize = ArraySize Div 2;

Var

 Buf1, Buf2 : **Array**[1..ArraySize] **of** char;
 I : longint;

Procedure CheckPos(Len : Longint);

Begin

Write('First ', Len, ' characters are ');
 if CompareChar(Buf1, Buf2, Len) <> 0 **then**
 Write('NOT ');
 Writeln('equal');
end;

Procedure CheckNullPos(Len : Longint);

Begin

Write('First ', Len, ' non-null characters are ');
 if CompareChar0(Buf1, Buf2, Len) <> 0 **then**
 Write('NOT ');
 Writeln('equal');
end;

begin

For I:=1 **to** ArraySize **do**
 begin
 Buf1[I] := **chr**(I);
 If I <= HalfArraySize **Then**
 Buf2[I] := **chr**(I)
 else
 Buf2[I] := **chr**(HalfArraySize - I);
 end;
 CheckPos(HalfArraySize Div 2);
 CheckPos(HalfArraySize);
 CheckPos(HalfArraySize + 1);
 CheckPos(HalfArraySize + HalfArraySize Div 2);
 For I:=1 **to** 4 **do**
 begin
 buf1[**Random**(ArraySize)+1] := **Chr**(0);

```

    buf2[Random(ArraySize)+1]:=Chr(0);
end;
Randomize;
CheckNullPos(HalfArraySize div 2);
CheckNullPos(HalfArraySize);
CheckNullPos(HalfArraySize+1);
CheckNullPos(HalfArraySize + HalfArraySize Div 2);
end.

```

75.11.70 CompareChar0

Synopsis: Compare two buffers character by character till a null-character is reached.

Declaration: `function CompareChar0(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareChar0` compares 2 buffers `buf1` and `buf2` for a maximum length of `len` or till a null character is reached in either buffer. The result depends on the contents of the buffers:

< 0 If `buf1` contains a character less than the corresponding character in `buf2`.
 0 If both buffers are equal
 > 0 If `buf1` contains a character greater than the corresponding character in `buf2`.

Errors: None.

See also: `CompareByte` ([1442](#)), `CompareChar` ([1443](#)), `CompareDWord` ([1445](#)), `CompareWord` ([1446](#))

75.11.71 CompareDWord

Synopsis: Compare 2 memory buffers DWord per DWord

Declaration: `function CompareDWord(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareDWord` compares two memory regions `buf1`, `buf2` on a DWord-per-DWord basis for a total of `len` DWords. (A DWord is 4 bytes).

The function returns one of the following values:

-1 if `buf1` and `buf2` contain different DWords in the first `len` DWords, and the first such DWord is smaller in `buf1` than the DWord at the same position in `buf2`.
 0 if the first `len` DWords in `buf1` and `buf2` are equal.
 1 if `buf1` and `buf2` contain different DWords in the first `len` DWords, and the first such DWord is larger in `buf1` than the DWord at the same position in `buf2`.

Errors: None.

See also: `CompareChar` ([1443](#)), `CompareByte` ([1442](#)), `CompareWord` ([1446](#))

Listing: `./examples/refex/ex101.pp`

```

Program Example101;

{ Program to demonstrate the CompareDWord function. }

Const
    ArraySize      = 100;
    HalfArraySize = ArraySize Div 2;

Var
    Buf1, Buf2 : Array[1..ArraySize] of Dword;
    I : longint;

    Procedure CheckPos(Len : Longint);

    Begin
        Write ('First ', Len, ' DWords are ');
        if CompareDWord(Buf1, Buf2, Len) <> 0 then
            Write ('NOT ');
            Writeln ('equal');
        end;

    begin
        For I:=1 to ArraySize do
            begin
                Buf1[I]:= I;
                If I<=HalfArraySize Then
                    Buf2[I]:= I
                else
                    Buf2[I]:= HalfArraySize-I;
                end;
            CheckPos(HalfArraySize div 2);
            CheckPos(HalfArraySize);
            CheckPos(HalfArraySize+1);
            CheckPos(HalfArraySize + HalfArraySize Div 2);
        end.

```

75.11.72 CompareWord

Synopsis: Compare 2 memory buffers word per word

Declaration: function CompareWord(const buf1; const buf2; len: SizeInt) : SizeInt

Visibility: default

Description: CompareWord compares two memory regions buf1, buf2 on a Word-per-Word basis for a total of len Words. (A Word is 2 bytes).

The function returns one of the following values:

- 1 if buf1 and buf2 contain different Words in the first len Words, and the first such Word is smaller in buf1 than the Word at the same position in buf2.
- 0 if the first len Words in buf1 and buf2 are equal.
- 1 if buf1 and buf2 contain different Words in the first len Words, and the first such Word is larger in buf1 than the Word at the same position in buf2.

Errors: None.

See also: [CompareChar \(1443\)](#), [CompareByte \(1442\)](#), [CompareDWord \(1445\)](#)

Listing: ./examples/refex/ex102.pp

Program Example102;

{ Program to demonstrate the CompareWord function. }

Const

 ArraySize = 100;
 HalfArraySize = ArraySize **Div** 2;

Var

 Buf1, Buf2 : **Array**[1..ArraySize] **of** Word;
 I : longint;

Procedure CheckPos(Len : Longint);

Begin

Write('First ', Len, ' words are ');
 if CompareWord(Buf1, Buf2, Len) <> 0 **then**
 Write('NOT ');
 Writeln('equal ');
 end;

begin

For I:=1 **to** ArraySize **do**
 begin
 Buf1[I]:= I;
 If I<=HalfArraySize **Then**
 Buf2[I]:= I
 else
 Buf2[I]:= HalfArraySize-I;
 end;
 CheckPos(HalfArraySize **div** 2);
 CheckPos(HalfArraySize);
 CheckPos(HalfArraySize+1);
 CheckPos(HalfArraySize + HalfArraySize **Div** 2);
 end.

75.11.73 Concat

Synopsis: Append one string or dynamic array to another.

Declaration: function Concat(const S1: string; const S2: string; const S3: string;
 const Sn: string) : string

Visibility: default

Description: Concat concatenates the strings S1,S2 etc. to one long string. The same operation can be performed with the + operation.

Concat can also be used to concatenate 2 dynamic arrays of any type, resulting in a new dynamic array containing all the elements of the dynamic arrays used in the call.

Errors: None.

See also: Copy ([1449](#)), Delete ([1453](#)), Insert ([1496](#)), Pos ([1518](#)), Length ([1503](#))

Listing: ./examples/refex/ex10.pp

Program Example10;

```
{ Program to demonstrate the Concat function. }
Var
  S : String;

begin
  S:=Concat('This can be done',' Easier ','with the + operator !');
end.
```

75.11.74 Continue

Synopsis: Continue with next loop cycle.

Declaration: procedure Continue

Visibility: default

Description: Continue jumps to the end of the current repetitive statement. The code between the Continue call and the end of the repetitive statement is skipped. The condition of the repetitive statement is then checked again.

This can be used with For, repeat and While statements.

Note that although Continue is a compiler intrinsic (i.e. is treated specially) it is defined as an identifier in the system unit, hence it can be redefined.

Errors: None.

See also: Break ([1436](#)), Exit ([1464](#))

Listing: ./examples/refex/ex86.pp

Program Example86;

```
{ Program to demonstrate the Continue function. }

Var I : longint;

begin
  I:=0;
  While I<10 Do
    begin
      Inc(I);
      If I<5 Then
        Continue;
      Writeln (i);
    end;
  I:=0;
  Repeat
    Inc(I);
    If I<5 Then
      Continue;
    Writeln (i);
  Until I>=10;
```

```

For i:=1 to 10 do
  begin
    If i<5 Then
      Continue;
    Writeln (i);
  end;
end.

```

Listing: ./examples/refex/ex121.pp

```

{
  Example 121:
  Continue, break and exit are system procedures.
  They can be redefined
}

procedure continue;

begin
  Writeln('Continue');
end;

Procedure Exit;

begin
  Writeln('exit');
end;

Procedure Break;

begin
  Writeln('Break');
end;

begin
  Repeat
    Continue;
    Break;
  exit;
  Until True;
end.

```

75.11.75 Copy

Synopsis: Copy part of a string.

Declaration: function Copy(S: AStringType; Index: SizeInt; Count: SizeInt) : string
 function Copy(A: DynArrayType; Index: SizeInt; Count: SizeInt)
 : DynArray

Visibility: default

Description: Copy returns a string which is a copy of the Count characters in S, starting at position Index. If Count is larger than the length of the string S, the result is truncated. If Index is larger than the length of the string S, then an empty string is returned. Index is 1-based.

For dynamic arrays, Copy returns a new dynamic array of the same type as the original one, and copies Count elements from the old array, starting at the position in Index.

The `Count` argument can be omitted. In that case, the string (or dynamic array) is copied from the position `Index` till the end of the string or array.

Errors: None.

See also: [Delete \(1453\)](#), [Insert \(1496\)](#), [Pos \(1518\)](#)

Listing: ./examples/refex/ex11.pp

Program Example11 ;

{ Program to demonstrate the Copy function. }

Var S,T : **String**;

begin

 T:= '1234567' ;

 S:=**Copy** (T,1,2); { S:= '12' }

 S:=**Copy** (T,4,2); { S:= '45' }

 S:=**Copy** (T,4,8); { S:= '4567' }

end.

75.11.76 CopyArray

Synopsis: Copy managed-type elements in array

Declaration: `procedure CopyArray(dest: Pointer; source: Pointer; typeInfo: Pointer; count: SizeInt)`

Visibility: default

Description: `CopyArray` copies `count` elements containing managed types from the array pointed to by `source` to the array pointed to by `dest`. For this, it uses the type information of the elements as specified in `typeinfo`.

Under normal circumstances, this procedure should not be used, it is called automatically by the compiler when an array-typed variables are assigned to each other.

See also: [InitializeArray \(1495\)](#), [FinalizeArray \(1471\)](#), [DynArraySize \(1458\)](#), [DynArrayClear \(1457\)](#), [DynArrayDim \(1457\)](#), [DynArrayBounds \(1457\)](#)

75.11.77 Cos

Synopsis: Calculate cosine of angle

Declaration: `function Cos(d: ValReal) : ValReal`

Visibility: default

Description: `Cos` returns the cosine of `X`, where `X` is an angle, in radians. If the absolute value of the argument is larger than $2\hat{6}3$, then the result is undefined.

Errors: None.

See also: [Arctan \(1426\)](#), [Sin \(1547\)](#)

Listing: ./examples/refex/ex12.pp

```

Program Example12;

{ Program to demonstrate the Cos function. }

Var R : Real;

begin
  R:=Cos(Pi);      { R:=-1 }
  R:=Cos(Pi/2);    { R:=0  }
  R:=Cos(0);       { R:=1  }
end.

```

75.11.78 CSeg

Synopsis: Return code segment

Declaration: `function CSeg : Word`

Visibility: default

Description: CSeg returns the Code segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32/64 bit compiler.

Errors: None.

See also: DSeg ([1456](#)), Seg ([1538](#)), OfS ([1514](#)), Ptr ([1520](#))

Listing: ./examples/refex/ex13.pp

```

Program Example13;

{ Program to demonstrate the CSeg function. }

var W : word;

begin
  W:=CSeg; {W:=0, provided for compatibility,
           FPC is 32 bit.}
end.

```

75.11.79 Dec

Synopsis: Decrease value of variable

Declaration: `procedure Dec(var X: TOrdinal)`
`procedure Dec(var X: TOrdinal; Decrement: TOrdinal)`

Visibility: default

Description: Dec decreases the value of X with Decrement. If Decrement isn't specified, then 1 is taken as a default.

Dec can be used on typed pointers: in that case it decreases the value with Decrement the size of the type the pointer points to. This works independently of the setting of the \$POINTERMATH directive.

Errors: A range check can occur, or an underflow error, if an attempt is made to decrease X below its minimum value.

See also: Inc ([1488](#))

Listing: ./examples/refex/ex14.pp

Program Example14;

{ Program to demonstrate the Dec function. }

Var

I : Integer;
L : Longint;
W : Word;
B : Byte;
Si : ShortInt;

begin

I:=1;
L:=2;
W:=3;
B:=4;
Si:=5;
Dec (i); { i:=0 }
Dec (L,2); { L:=0 }
Dec (W,2); { W:=1 }
Dec (B,-2); { B:=6 }
Dec (Si,0); { Si:=5 }

end.

75.11.80 Default

Synopsis: Return Default initialized value

Declaration: `function Default(const T: AnyType) : AnyType`

Visibility: default

Description: `Default` is a compiler intrinsic: it returns for every type T a default value. In essence, this is a block of memory that is zeroed out. It can be used to correctly initialize any type, and more importantly, a managed type. It also works using a generic type template.

This function cannot be used on any of the file types or complex types that contain a file type.

See also: `TypeInfo` ([1563](#)), `Initialize` ([1493](#)), `Finalize` ([1471](#))

75.11.81 DefaultAnsi2UnicodeMove

Synopsis: Standard widestring manager callback

Declaration: `procedure DefaultAnsi2UnicodeMove(source: PChar; cp: TSystemCodePage;
var dest: uncodestring; len: SizeInt)`

Visibility: default

Description: `DefaultAnsi2UnicodeMove` is the standard callback used for the widestring manager when an ansistring must be converted to a uncodestring. It simply copies over all characters from the ansistring to the uncodestring, no conversion whatsoever is performed.

75.11.82 DefaultAnsi2WideMove

Synopsis: Standard implementation of Ansi to Widestring conversion routine

Declaration: `procedure DefaultAnsi2WideMove(source: PChar; cp: TSystemCodePage;
var dest: widestring; len: SizeInt)`

Visibility: default

Description: `DefaultAnsi2WideMove` simply copies each character of the null-terminated ansi-string `Source` to the corresponding `WideChar` in `Dest`. At most `Len` characters will be copied.

Errors: None.

See also: `DefaultUnicode2AnsiMove` ([1453](#))

75.11.83 DefaultUnicode2AnsiMove

Synopsis: Standard widestring manager callback

Declaration: `procedure DefaultUnicode2AnsiMove(source: PUnicodeChar;
var dest: RawByteString;
cp: TSystemCodePage; len: SizeInt)`

Visibility: default

Description: `DefaultUnicode2AnsiMove` is the standard callback used for the widestring manager when a Unicode string must be converted to an ansistring. It replaces all words with value < 256 with their value as ASCII code.

Errors: None.

See also: `WidestringManager` ([1422](#))

75.11.84 Delete

Synopsis: Delete elements (characters) from a string or dynamic array.

Declaration: `procedure Delete(var S: string; const Index: Integer;
const Count: Integer)
procedure Delete(var A: DynArrayType; const Index: Integer;
const Count: Integer)`

Visibility: default

Description: `Delete` removes `Count` characters from string `S`, starting at position `Index`. `Index` is 1-based. All characters after the deleted characters are shifted `Count` positions to the left, and the length of the string is adjusted.

For dynamic arrays, `Delete` removes `Count` elements from the array `A`, starting at position `Index`. `Index` is 0-based. All elements after the deleted elements are shifted `Count` positions to the left, and the length of the array is adjusted.

If the sum of `Index` and `Count` exceeds the length of the string or array, `Delete` removes the end of the string or array, starting at `Index`.

If `Index` is less than 1 or greater than the length of the string or array, or if `Count` is negative or zero, `Delete` does nothing.

See also: `Copy` ([1449](#)), `Pos` ([1518](#)), `Insert` ([1496](#))

Listing: ./examples/refex/ex15.pp

```

Program Example15;

{ Program to demonstrate the Delete function. }

Var
  S : String;

begin
  S := 'This is not easy !';
  Delete (S,9,4); { S := 'This is easy !' }
end.

```

75.11.85 Dispose

Synopsis: Free dynamically allocated memory

Declaration: `procedure &Dispose(P: Pointer)`
`procedure &Dispose(P: TypedPointer; Des: TProcedure)`

Visibility: default

Description: The first form `Dispose` releases the memory allocated with a call to `New` (1512). The pointer `P` must be typed. The released memory is returned to the heap.

The second form of `Dispose` accepts as a first parameter a pointer to an object type, and as a second parameter the name of a destructor of this object. The destructor will be called, and the memory allocated for the object will be freed.

Errors: An runtime error will occur if the pointer doesn't point to a location in the heap.

See also: `New` (1512), `Getmem` (1478), `Freemem` (1475)

Listing: ./examples/refex/ex16.pp

```

Program Example16;

{ Program to demonstrate the Dispose and New functions. }

Type SS = String[20];

  AnObj = Object
    I : integer;
    Constructor Init;
    Destructor Done;
    end;

Var
  P : ^SS;
  T : ^AnObj;

Constructor Anobj.Init;

begin
  WriteLn ('Initializing an instance of AnObj !');
end;

```

```

Destructor AnObj.Done;

begin
  WriteIn ('Destroying an instance of AnObj !');
end;

begin
  New (P);
  P^:= 'Hello , World !';
  Dispose (P);
  { P is undefined from here on !}
  New(T, Init);
  T^.i:=0;
  Dispose (T, Done);
end.

```

75.11.86 divide(variant,variant):variant

Synopsis: Implement division (/) operation on variants.

Declaration: `operator /(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the division / operation is delegated to the variant manager with operation `opDivide`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `*(variant, variant): variant` ([1339](#))

75.11.87 DoneCriticalSection

Synopsis: Clean up a critical section.

Declaration: `procedure DoneCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `DoneCriticalSection` cleans up the critical section CS. After a call to `DoneCriticalSection`, the critical section can no longer be used with `EnterCriticalSection` ([1459](#)) or `LeaveCriticalSection` ([1502](#)), unless it is again initialized with `InitCriticalSection` ([1493](#))

See also: `InitCriticalSection` ([1493](#)), `EnterCriticalSection` ([1459](#)), `LeaveCriticalSection` ([1502](#))

75.11.88 DoneThread

Synopsis: End the current thread

Declaration: `procedure DoneThread`

Visibility: default

Description: `DoneThread` should be used to end the current thread. It performs the necessary housekeeping before actually ending the thread. Using the operating system calls to end the thread may result in data corruption or memory leaks.

See also: `BeginThread` ([1434](#))

75.11.89 DSeg

Synopsis: Return data segment

Declaration: `function DSeg : Word`

Visibility: default

Description: `DSeg` returns the data segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32/64 bit compiler.

Errors: None.

See also: `CSeg` ([1451](#)), `Seg` ([1538](#)), `Ofs` ([1514](#)), `Ptr` ([1520](#))

Listing: `./examples/refex/ex17.pp`

Program `Example17;`

{ Program to demonstrate the DSeg function. }

Var

`W : Word;`

begin

`W:=DSeg; {W:=0, This function is provided for compatibility,
FPC is a 32 bit compiler.}`

end.

75.11.90 DumpExceptionBacktrace

Synopsis: Create backtrace

Declaration: `procedure DumpExceptionBacktrace(var f: text)`

Visibility: default

Description: `DumpExceptionBackTrace` writes a backtrace of the current exception to the file `f`. If no exception is currently being raised, nothing is written. As much frames as available are written. If debug info is available, then file names and line numbers will be written as well.

Errors: No check is done to see whether `f` is opened for writing.

See also: `dump_stack` ([1456](#))

75.11.91 Dump_Stack

Synopsis: Dump stack to the given text file.

Declaration: `procedure Dump_Stack(var f: text; fp: pointer; addr: CodePointer)`
`procedure Dump_Stack(var f: text; skipframes: LongInt)`

Visibility: default

Description: `Dump_Stack` prints a stack dump to the file `f`, with base frame pointer `bp`

Errors: The file `f` must be opened for writing or an error will occur.

See also: `get_caller_addr` ([1482](#)), `get_caller_frame` ([1483](#)), `get_frame` ([1483](#))

75.11.92 DynArrayBounds

Synopsis: Return the bounds of the dynamic array

Declaration: `function DynArrayBounds(a: Pointer; typeInfo: Pointer) : TBoundArray`

Visibility: default

Description: `DynArrayBounds` returns the bounds of all the dimensions of the dynamic array `a` with type information `typeInfo`.

The result is an array (zero-based) with the maximum valid index for each dimension in the array: the lower bound is not present in the result, it is always zero.

See also: `InitializeArray` (1495), `FinalizeArray` (1471), `CopyArray` (1450), `DynArraySize` (1458), `DynArrayClear` (1457), `DynArrayDim` (1457)

75.11.93 DynArrayClear

Synopsis: Clears a dynamic array

Declaration: `procedure DynArrayClear(var a: Pointer; typeInfo: Pointer)`

Visibility: default

Description: `DynArrayClear` clears the array (`a`) using its type info (`typeInfo`). It is equal to setting the length to zero.

See also: `InitializeArray` (1495), `FinalizeArray` (1471), `CopyArray` (1450), `DynArraySize` (1458), `DynArrayDim` (1457), `DynArrayBounds` (1457)

75.11.94 DynArrayDim

Synopsis: Return the number of dimensions in a dynamic array

Declaration: `function DynArrayDim(typeInfo: Pointer) : Integer`

Visibility: default

Description: `DynArrayDim` returns the number of dimensions in a dynamic array, using the type information (`typeInfo`) of the array.

See also: `InitializeArray` (1495), `FinalizeArray` (1471), `CopyArray` (1450), `DynArraySize` (1458), `DynArrayClear` (1457), `DynArrayBounds` (1457)

75.11.95 DynArrayIndex

Synopsis: Return pointer to indicated element

Declaration: `function DynArrayIndex(a: Pointer; const indices: Array of SizeInt; typeInfo: Pointer) : Pointer`

Visibility: default

Description: `DynArrayIndex` returns a pointer to the element indicated by `indices` in dynamic array `a` with type information `typeInfo`. The length of `indices` must equal the number of dimensions of the array (as returned by `DynArrayDim` (1457)).

Errors: No bounds checking is performed, it is therefor possible to get an access violation if one of the indexes is out of range.

See also: [InitializeArray \(1495\)](#), [FinalizeArray \(1471\)](#), [CopyArray \(1450\)](#), [DynArraySize \(1458\)](#), [DynArrayClear \(1457\)](#), [DynArrayBounds \(1457\)](#), [DynArrayDim \(1457\)](#), [IsDynArrayRectangular \(1501\)](#)

75.11.96 DynArraySetLength

Synopsis: Set the length of a dynamic array

Declaration: `procedure DynArraySetLength(var a: Pointer; typeInfo: Pointer;
dimCnt: SizeInt; lengthVec: PSizeInt)`

Visibility: default

Description: `DynArraySetLength` sets the length of the dynamic array `a` to the first `dimCnt` lengths specified in the array `lengthVec`. The dynamic array type is described in `typeInfo` which points to a record of type `TDynArrayTypeInfo` ([1390](#))

It should never be necessary to call this function directly, the standard `SetLength` ([1540](#)) function should be used instead.

Errors: If an invalid pointer is specified, an error may occur.

See also: `SetLength` ([1540](#)), `tdynarraytypeinfo` ([1390](#))

75.11.97 DynArraySize

Synopsis: Return length of dynamic array

Declaration: `function DynArraySize(a: pointer) : tdynarrayindex`

Visibility: default

Description: `DynArraySize` gets the number of elements in the array (`a`) the result is equal to `Length` ([1503](#)) for dynamic arrays.

See also: `InitializeArray` ([1495](#)), `FinalizeArray` ([1471](#)), `CopyArray` ([1450](#)), `DynArrayClear` ([1457](#)), `DynArrayDim` ([1457](#)), `DynArrayBounds` ([1457](#))

75.11.98 EmptyMethod

Synopsis: Empty method alias

Declaration: `procedure EmptyMethod`

Visibility: default

Description: `EmptyMethod` is meant for the compiler only. It should not be used directly.

75.11.99 EndThread

Synopsis: End the current thread.

Declaration: `procedure EndThread(ExitCode: DWord)
procedure EndThread`

Visibility: default

Description: `EndThread` ends the current thread. If `ExitCode` is supplied, it is returned as the exit code for the thread to a function waiting for the thread to terminate (`WaitForThreadTerminate` (1572)). If it is omitted, zero is used.

This function does not return.

See also: `WaitForThreadTerminate` (1572), `BeginThread` (1434)

75.11.100 EnterCriticalSection

Synopsis: Enter a critical section

Declaration: `procedure EnterCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `EnterCriticalSection` will suspend the current thread if another thread has currently entered the critical section. When the other thread has left the critical section (through `LeaveCriticalSection` (1502)), the current thread resumes execution. The result is that only 1 thread is executing code which is protected by a `EnterCriticalSection` and `LeaveCriticalSection` pair.

The critical section must have been initialized with `InitCriticalSection` (1493) prior to a call to `EnterCriticalSection`.

A call to `EnterCriticalSection` must always be matched by a call to `LeaveCriticalSection` (1502). To avoid problems, it is best to include the code to be execute in a `try...finally` block, as follows:

```
EnterCriticalSection(Section);
Try
    // Code to be protected goes here.
Finally
    LeaveCriticalSection(Section);
end;
```

For performance reasons it is best to limit the code between the entering and leaving of a critical section as short as possible.

See also: `InitCriticalSection` (1493), `DoneCriticalSection` (1455), `LeaveCriticalSection` (1502)

75.11.101 EnumResourceLanguages

Synopsis: Enumerate available languages for a resource of given type and name

Declaration: `function EnumResourceLanguages(ModuleHandle: TFPResourceHMODULE;
ResourceType: PChar; ResourceName: PChar;
EnumFunc: EnumResLangProc; lParam: PtrInt)
: LongBool`

Visibility: default

Description: `EnumResourceLanguages` enumerates the available languages for a resource of given `ResourceName` and type `ResourceType` in the module `ModuleHandle`. For each language available, it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource `ResourceType`, the name of the resource `ResourceName`, the language ID, and `lParam`. It returns `False` if no resources are available for the specified resource type and module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceTypes` (1460), `EnumResourceNames` (1460), `EnumResourceLanguages` (1459)

75.11.102 EnumResourceNames

Synopsis: Enumerate available resource names for a specified resource type

Declaration: `function EnumResourceNames (ModuleHandle: TFPResourceHMODULE;
ResourceType: PChar;
EnumFunc: EnumResNameProc; lParam: PtrInt)
: LongBool`

Visibility: default

Description: `EnumResourceNames` enumerates the names of all resources of type `ResourceType` in the module `ModuleHandle`. For each resource available it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource `ResourceType`, the name of the resource, and `lParam`. It returns `False` if no resources are available for the specified resource type and module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceTypes` (1460), `EnumResourceLanguages` (1459)

75.11.103 EnumResourceTypes

Synopsis: Enumerate available resource types

Declaration: `function EnumResourceTypes (ModuleHandle: TFPResourceHMODULE;
EnumFunc: EnumResTypeProc; lParam: PtrInt)
: LongBool`

Visibility: default

Description: `EnumResourceTypes` enumerates the types of all resources in the module `ModuleHandle`. For each resource available it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource, and `lParam`. It returns `False` if no resources are available for the specified module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceNames` (1460), `EnumResourceLanguages` (1459)

75.11.104 EOF

Synopsis: Check for end of file

Declaration: `function EOF (var f: File) : Boolean
function EOF (var t: Text) : Boolean
function EOF : Boolean`

Visibility: default

Description: `Eof` returns `True` if the file-pointer has reached the end of the file, or if the file is empty. In all other cases `Eof` returns `False`. If no file `F` is specified, standard input is assumed.

Note that calling this function may cause your program to wait: to determine whether you are at EOF, it is necessary to read data. If the file descriptor is not a real file (for instance for standard input or sockets), then this call may seem to hang the program while it is waiting for data to appear or for the file descriptor to be closed.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Eoln` ([1461](#)), `Assign` ([1427](#)), `Reset` ([1527](#)), `Rewrite` ([1528](#))

Listing: `./examples/refex/ex18.pp`

Program `Example18;`

```
{ Program to demonstrate the Eof function. }

Var T1,T2 : text;
      C : Char;

begin
  { Set file to read from. Empty means from standard input. }
  assign (t1,paramstr(1));
  reset (t1);
  { Set file to write to. Empty means to standard output. }
  assign (t2,paramstr(2));
  rewrite (t2);
  While not eof(t1) do
    begin
      read (t1,C);
      write (t2,C);
    end;
    Close (t1);
    Close (t2);
end.
```

75.11.105 EOLn

Synopsis: Check for end of line

Declaration: `function EOLn(var t: Text) : Boolean`
`function EOLn : Boolean`

Visibility: default

Description: `EoLn` returns `True` if the file pointer has reached the end of a line, which is demarcated by a line-feed character (ASCII value 10), or if the end of the file is reached. In all other cases `EoLn` returns `False`. If no file `F` is specified, standard input is assumed. It can only be used on files of type `Text`.

Errors: None.

See also: `Eof` ([1460](#)), `Assign` ([1427](#)), `Reset` ([1527](#)), `Rewrite` ([1528](#))

Listing: `./examples/refex/ex19.pp`

Program `Example19;`

```
{ Program to demonstrate the Eoln function. }

begin
  { This program waits for keyboard input. }
  { It will print True when an empty line is put in ,
    and false when you type a non-empty line.
    It will only stop when you press enter. }
```

```

    While not Eoln do
        Writeln (eoln);
    end.

```

75.11.106 equal(variant,variant):Boolean

Synopsis: Implement = (equality) operation on variants.

Declaration: `operator =(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the equality (=) operation is delegated to the variant manager with operation `opcmpeq`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator <(variant, variant): boolean ([1339](#))

75.11.107 Erase

Synopsis: Delete a file from disk

Declaration: `procedure Erase(var f: File)`
`procedure Erase(var t: Text)`

Visibility: default

Description: `Erase` removes an unopened file from disk. The file should be assigned with `Assign`, but not opened with `Reset` or `Rewrite`

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Assign` ([1427](#))

Listing: `./examples/refex/ex20.pp`

Program `Example20;`

{ Program to demonstrate the Erase function. }

Var `F : Text;`

begin

{ Create a file with a line of text in it }

`Assign (F, 'test.txt');`

`Rewrite (F);`

`Writeln (F, 'Try and find this when I'm finished !');`

`close (f);`

{ Now remove the file }

`Erase (f);`

end.

75.11.108 Error

Synopsis: Generate run-time error

Declaration: `procedure Error(RunTimeError: TRuntimeError)`

Visibility: default

Description: `Error` generates a run-time error with an exit code corresponding to `RunTimeError`. This function is implemented for Delphi compatibility, and is not used by the Free Pascal Run-Time Library.

See also: `RunError` ([1534](#)), `Halt` ([1484](#))

75.11.109 Exclude

Synopsis: Exclude element from a set if it is present.

Declaration: `procedure Exclude(var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Exclude` removes `E` from the set `S` if it is included in the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```
S:=S-[E];
Exclude(S,E);
```

Errors: If the type of the element `E` is not equal to the base type of the set `S`, the compiler will generate an error.

See also: `Include` ([1489](#))

Listing: `./examples/refex/ex111.pp`

```
program Example111;

{ Program to demonstrate the Include/Exclude functions }

Type
  TEnumA = (aOne,aTwo,aThree);
  TEnumAs = Set of TEnumA;

Var
  SA : TEnumAs;

Procedure PrintSet(S : TEnumAs);

var
  B : Boolean;

procedure DoEI(A : TEnumA; Desc : String);

begin
  If A in S then
    begin
      If B then
        Write(' ');
```



```

        B:=True;
        Write( Desc );
    end;
end;

begin
    Write( ' [ ' );
    B:=False;
    DoEl(aOne, 'aOne');
    DoEl(aTwo, 'aTwo');
    DoEl(aThree, 'aThree');
    WriteLn( ' ] ')
end;

begin
    SA:=[];
    Include(SA,aOne);
    PrintSet(SA);
    Include(SA,aThree);
    PrintSet(SA);
    Exclude(SA,aOne);
    PrintSet(SA);
    Exclude(SA,aTwo);
    PrintSet(SA);
    Exclude(SA,aThree);
    PrintSet(SA);
end.

```

75.11.110 Exit

Synopsis: Exit current subroutine.

Declaration: `procedure &Exit(const X: TAnyType)`
`procedure &Exit`

Visibility: default

Description: `Exit` exits the current subroutine, and returns control to the calling routine. If invoked in the main program routine, exit stops the program. The optional argument `X` allows to specify a return value, in the case `Exit` is invoked in a function. The function result will then be equal to `X`.

In Object Pascal or Delphi modes, if the `Exit` statement is surrounded by one or more `Try .. Finally` constructs, the `Finally` blocks are executed, which means that if the finally blocks are used to free resources, then these resources will also be freed when `Exit` is called.

Note that although `Exit` is a compiler intrinsic (i.e. is treated specially) it is defined as an identifier in the system unit, hence it can be redefined.

Errors: None.

See also: `Halt` ([1484](#))

Listing: `./examples/refex/ex21.pp`

Program Example21;

{ Program to demonstrate the Exit function. }

```

Procedure DoAnExit (Yes : Boolean);

{ This procedure demonstrates the normal Exit }

begin
  Writeln ('Hello from DoAnExit !');
  If Yes then
    begin
      Writeln ('Bailing out early. ');
      exit;
    end;
  Writeln ('Continuing to the end. ');
end;

Function Positive (Which : Integer) : Boolean;

{ This function demonstrates the extra FPC feature of Exit :
  You can specify a return value for the function }

begin
  if Which > 0 then
    exit (True)
  else
    exit (False);
end;

begin
  { This call will go to the end }
  DoAnExit (False);
  { This call will bail out early }
  DoAnExit (True);
  if Positive (-1) then
    Writeln ('The compiler is nuts, -1 is not positive. ')
  else
    Writeln ('The compiler is not so bad, -1 seems to be negative. ');
end.

```

Listing: ./examples/refex/ex121.pp

```

{
  Example 121:
  Continue, break and exit are system procedures.
  They can be redefined
}

procedure continue;

begin
  Writeln ('Continue ');
end;

Procedure Exit;

begin
  Writeln ('exit ');
end;

Procedure Break;

```

```

begin
  WriteLn ( 'Break ' );
end;

begin
  Repeat
    Continue;
  Break;
  exit;
  Until True;
end.

```

75.11.111 Exp

Synopsis: Exponentiate

Declaration: `function Exp(d: ValReal) : ValReal`

Visibility: default

Description: `Exp` returns the exponent of X, i.e. the number e to the power X.

Errors: None.

See also: `Ln` ([1505](#))

Listing: `./examples/refex/ex22.pp`

```

Program Example22;

{ Program to demonstrate the Exp function. }

begin
  WriteLn (Exp(1):8:2); { Should print 2.72 }
end.

```

75.11.112 Fail

Synopsis: Fail a constructor

Declaration: `procedure Fail`

Visibility: default

Description: `Fail` can be used in a constructor for an object or class. It will exit the constructor at once, and the memory allocated for the constructor is freed. This mean that for objects allocated with `New` ([1512](#)), the resulting pointer is `Nil` and for classes, the object instance will be `Nil`.

See also: `TypeOf` ([1564](#)), `New` ([1512](#)), `Initialize` ([1493](#)), `Finalize` ([1471](#))

Listing: `./examples/refex/ex116.pp`

```

program testfail;

{$mode objfpc}

```

Type

```

TMyClass = Class
  Constructor Create;
end;

Constructor TMyClass.Create;

begin
  Fail;
end;

var
  M : TMyClass;

begin
  M:=TMyClass.Create;
  WriteIn('M is nil : ',Not Assigned(M));
end.

```

75.11.113 FilePos

Synopsis: Get position in file

Declaration: `function FilePos(var f: File) : Int64`

Visibility: default

Description: `FilePos` returns the current record position of the file-pointer in file `F`. It cannot be invoked with a file of type `Text`. A compiler error will be generated if this is attempted. Untyped files have a default record size of 128, if the second parameter to `Reset` ([1527](#)) isn't specified.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Filesize` ([1468](#))

Listing: `./examples/refex/ex23.pp`

Program `Example23;`

```

{ Program to demonstrate the FilePos function. }

Var F : File of Longint;
    L,FP : longint;

begin
  { Fill a file with data :
    Each position contains the position ! }
  Assign (F, 'test.tmp');
  Rewrite (F);
  For L:=0 to 100 do
    begin
      FP:=FilePos(F);
      Write (F,FP);
    end;
  Close (F);
  Reset (F);
  { If all goes well, nothing is displayed here. }

```

```

While not (Eof(F)) do
  begin
    FP:=FilePos (F);
    Read (F,L);
    if L<>FP then
      Writeln ('Something wrong: Got ',l,' on pos ',FP);
    end;
    Close (F);
    Erase (f);
  end.

```

75.11.114 FileSize

Synopsis: Size of file

Declaration: `function FileSize(var f: File) : Int64`

Visibility: default

Description: `FileSize` returns the total number of records in file `F`. It cannot be invoked with a file of type `Text`. (under Linux and Unix, this also means that it cannot be invoked on pipes). If `F` is empty, 0 is returned. Untyped files have a default record size of 128, if the second parameter to `Reset` ([1527](#)) isn't specified.

Note that the file must be open for this function to return a result.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Filepos` ([1467](#))

Listing: `./examples/refex/ex24.pp`

Program `Example24`;

{ Program to demonstrate the FileSize function. }

```

Var F : File Of byte;
    L : File Of Longint;

```

```

begin
  Assign (F,paramstr(1));
  Reset (F);
  Writeln ('File size in bytes : ',FileSize(F));
  Close (F);
  Assign (L,paramstr (1));
  Reset (L);
  Writeln ('File size in Longints : ',FileSize(L));
  Close (f);
end.

```

75.11.115 FillByte

Synopsis: Fill memory region with 8-bit pattern

Declaration: `procedure FillByte(var x; count: SizeInt; value: Byte)`

Visibility: default

Description: `FillByte` fills the memory starting at `X` with `Count` bytes with value equal to `Value`. This is useful for quickly zeroing out a memory location. When the size of the memory location to be filled out is a multiple of 2 bytes, it is better to use `Fillword` (1470), and if it is a multiple of 4 bytes it is better to use `FillDWord` (1470), these routines are optimized for their respective sizes.

Errors: No checking on the size of `X` is done.

See also: `Fillchar` (1469), `FillDWord` (1470), `Fillword` (1470), `Move` (1510)

Listing: ./examples/refex/ex103.pp

Program Example103;

{ Program to demonstrate the FillByte function. }

```

Var S : String[10];
      I : Byte;

begin
  For i:=10 downto 0 do
    begin
      { Fill S with i bytes }
      FillByte (S,SizeOf(S),32);
      { Set Length }
      SetLength(S,I);
      Writeln (s,'*');
    end;
end.

```

75.11.116 FillChar

Synopsis: Fill memory region with certain character

Declaration: `procedure FillChar`(var x; count: `SizeInt`; Value: `Byte`)
 `procedure FillChar`(var x; count: `SizeInt`; Value: `Boolean`)
 `procedure FillChar`(var x; count: `SizeInt`; Value: `Char`)

Visibility: default

Description: `Fillchar` fills the memory starting at `X` with `Count` bytes or characters with value equal to `Value`.

Errors: No checking on the size of `X` is done.

See also: `Fillword` (1470), `Move` (1510), `FillByte` (1468), `FillDWord` (1470)

Listing: ./examples/refex/ex25.pp

Program Example25;

{ Program to demonstrate the FillChar function. }

```

Var S : String[10];
      I : Byte;

begin
  For i:=10 downto 0 do

```

```

begin
  { Fill S with i spaces }
  FillChar (S, SizeOf(S), ' ');
  { Set Length }
  SetLength(S, I);
  Writeln (s, '*');
end;
end.

```

75.11.117 FillDWord

Synopsis: Fill memory region with 32-bit pattern

Declaration: `procedure FillDWord(var x; count: SizeInt; value: DWord)`

Visibility: default

Description: `FillDWord` fills the memory starting at `X` with `Count` `DWords` with value equal to `Value`. A `DWord` is 4 bytes in size.

Errors: No checking on the size of `X` is done.

See also: `FillByte` ([1468](#)), `FillChar` ([1469](#)), `FillWord` ([1470](#)), `Move` ([1510](#))

Listing: `./examples/refex/ex104.pp`

Program `Example104`;

{ Program to demonstrate the FillDWord function. }

Const

`ArraySize = 1000;`

Var

`S : Array [1..ArraySize] of DWord;`
`I : longint;`

begin

`FillDWord(S, ArraySize, 0);`

For `I:=1 to ArraySize do`

If `S[I]<>0 then`

`Writeln('Position ', I, ' not zeroed out');`

end.

75.11.118 FillWord

Synopsis: Fill memory region with 16-bit pattern

Declaration: `procedure FillWord(var x; count: SizeInt; Value: Word)`

Visibility: default

Description: `FillWord` fills the memory starting at `X` with `Count` words with value equal to `Value`. A word is 2 bytes in size.

Errors: No checking on the size of `X` is done.

See also: [Fillchar \(1469\)](#), [Move \(1510\)](#)

Listing: ./examples/refex/ex76.pp

Program Example76;

{ Program to demonstrate the FillWord function. }

Var W : **Array**[1..100] **of** Word;

begin

{ Quick initialization of array W }

FillWord(W,100,0);

end.

75.11.119 Finalize

Synopsis: Finalize (clean up) memory block using RTTI

Declaration: `procedure Finalize(var T: TAnyType; ACount: SizeInt)`

Visibility: default

Description: `Finalize` is a compiler intrinsic: it cleans up (finalizes) a memory area T for any kind of managed variable. Finalizing means decreasing reference counts where necessary and generally zeroing out the memory area. It performs the opposite operation of `initialize` ([1493](#)).

The optional `ACount` parameter can be used to finalize an array of values.

For examples, see `initialize` ([1493](#)).

See also: `initialize` ([1493](#)), `Default` ([1452](#)), `TypeInfo` ([1563](#))

75.11.120 FinalizeArray

Synopsis: Finalize managed-type elements in array

Declaration: `procedure FinalizeArray(p: Pointer; typeInfo: Pointer; count: SizeInt)`

Visibility: default

Description: `FinalizeArray` dereferences and clears managed types in the array pointed to by p. For this, it uses the type information of the elements as specified in `typeinfo`.

Under normal circumstances, this procedure should not be used, it is called automatically by the compiler when an array-typed variable containing managed types goes out of scope.

See also: `InitializeArray` ([1495](#)), `CopyArray` ([1450](#)), `DynArraySize` ([1458](#)), `DynArrayClear` ([1457](#)), `DynArrayDim` ([1457](#)), `DynArrayBounds` ([1457](#))

75.11.121 FindResource

Synopsis: Locate a resource and return a handle to it.

Declaration: `function FindResource(ModuleHandle: TFPResourceHMODULE;
 ResourceName: PChar; ResourceType: PChar)
 : TFPResourceHandle`
`function FindResource(ModuleHandle: TFPResourceHMODULE;`


```

        const ResourceName: AnsiString;
        const ResourceType: AnsiString) : TFPResourceHandle
function FindResource(ModuleHandle: TFPResourceHMODULE;
        const ResourceName: AnsiString;
        ResourceType: PChar) : TFPResourceHandle
function FindResource(ModuleHandle: TFPResourceHMODULE;
        ResourceName: PChar;
        const ResourceType: AnsiString) : TFPResourceHandle

```

Visibility: default

Description: FindResource searches for a resource with name ResourceName and of type ResourceType in the executable or library identified by ModuleHandle. It returns a TResourceHandle which can be used to load the resource with LoadResource (1506).

Errors: None. In case the resource was not found, 0 is returned.

See also: FreeResource (1476), LoadResource (1506), SizeofResource (1548), LockResource (1507), UnlockResource (1567), FreeResource (1476)

75.11.122 FindResourceEx

Synopsis: Find a resource based on type, name, language

```

Declaration: function FindResourceEx(ModuleHandle: TFPResourceHMODULE;
        ResourceType: PChar; ResourceName: PChar;
        Language: Word) : TFPResourceHandle
function FindResourceEx(ModuleHandle: TFPResourceHMODULE;
        const ResourceType: AnsiString;
        const ResourceName: AnsiString; Language: Word)
        : TFPResourceHandle
function FindResourceEx(ModuleHandle: TFPResourceHMODULE;
        ResourceType: PChar;
        const ResourceName: AnsiString; Language: Word)
        : TFPResourceHandle
function FindResourceEx(ModuleHandle: TFPResourceHMODULE;
        const ResourceType: AnsiString;
        ResourceName: PChar; Language: Word)
        : TFPResourceHandle

```

Visibility: default

Description: FindResourceEx looks in module ModuleHandle for a resource of type ResourceType and name ResourceName with language ID Language. Both ResourceName and ResourceName can be specified as a null-terminated array of characters, or as an AnsiString.

If the requested language/sublanguage is not found, then the search is conducted

1. with only primary language.
2. with the neutral language (LANG_NEUTRAL)
3. with the English language

If none of these has returned a match, then the first available language is returned.

If a match is found, a handle to the resource is returned. If none is found, an empty handle (nil or 0) is returned.

Errors: None.

75.11.123 float_raise

Synopsis: Raise floating point exception

Declaration: `procedure float_raise(i: TFPUEException)`
`procedure float_raise(i: TFPUEExceptionMask)`

Visibility: default

Description: `float_raise` raises the floating point exceptions specified by `softfloat_exception_flags` (1421).

See also: `softfloat_exception_flags` (1421), `softfloat_exception_mask` (1421)

75.11.124 Flush

Synopsis: Write file buffers to disk

Declaration: `procedure Flush(var t: Text)`

Visibility: default

Description: `Flush` empties the internal buffer of an opened file `F` and writes the contents to disk. The file is **not** closed as a result of this call.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Close` (1441)

Listing: `./examples/refex/ex26.pp`

Program `Example26;`

{ Program to demonstrate the Flush function. }

Var `F : Text;`

begin

{ Assign F to standard output }

`Assign (F, '');`

Rewrite `(F);`

Writeln `(F, 'This line is written first, but appears later !');`

*{ At this point the text is in the internal pascal buffer,
and not yet written to standard output }*

Writeln `('This line appears first, but is written later !');`

*{ A writeln to 'output' always causes a flush – so this text is
written to screen }*

Flush `(f);`

{ At this point, the text written to F is written to screen. }

Write `(F, 'Finishing ');`

`Close (f);` *{ Closing a file always causes a flush first }*

Writeln `('off.');`

end.

75.11.125 FlushThread

Synopsis: Flush all standard files

Declaration: `procedure FlushThread`

Visibility: default

Description: `FlushThread` flushes any buffers from standard file descriptors such as standard input/output/error. It should normally not be called by user code, but is executed when a thread exits.

See also: `EndThread` ([1458](#))

75.11.126 FMADouble

Synopsis: Internal function, do not use

Declaration: `function FMADouble(d1: Double; d2: Double; d3: Double) : Double`

Visibility: default

75.11.127 FMAExtended

Synopsis: Internal function, do not use

Declaration: `function FMAExtended(e1: extended; e2: extended; e3: extended)
: extended`

Visibility: default

75.11.128 FMASingle

Synopsis: Internal function, do not use

Declaration: `function FMASingle(s1: single; s2: single; s3: single) : single`

Visibility: default

75.11.129 FPower10

Synopsis: Fast multiply with a power of 10

Declaration: `function FPower10(val: Extended; Power: LongInt) : Extended`

Visibility: default

Description: `FPower10` multiplies `val` with 10 to the power `Power`. It uses a fast algorithm to calculate the result.

75.11.130 Frac

Synopsis: Return fractional part of floating point value.

Declaration: `function Frac(d: ValReal) : ValReal`

Visibility: default

Description: `Frac` returns the non-integer part of `X`.

Errors: None.

See also: `Round` ([1532](#)), `Int` ([1496](#))

Listing: `./examples/refex/ex27.pp`

Program `Example27`;

{ Program to demonstrate the Frac function. }

Var `R` : `Real`;

begin

WriteLn (`Frac` (`123.456`):0:3); *{ Prints 0.456 }*

WriteLn (`Frac` (`-123.456`):0:3); *{ Prints -0.456 }*

end.

75.11.131 FreeLibrary

Synopsis: For compatibility with Delphi/Windows: Unload a library

Declaration: `function FreeLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

Description: `FreeLibrary` provides the same functionality as `UnloadLibrary` ([1566](#)), and is provided for compatibility with Delphi.

See also: `UnloadLibrary` ([1566](#))

75.11.132 Freemem

Synopsis: Release allocated memory

Declaration: `procedure Freemem(p: pointer; Size: PtrUInt)`
`function Freemem(p: pointer) : PtrUInt`

Visibility: default

Description: `Freemem` releases the memory occupied by the pointer `P`, of size `Count` (in bytes), and returns it to the heap. `P` should point to the memory allocated to a dynamic variable.

Errors: An error will occur when `P` doesn't point to the heap.

See also: `Getmem` ([1478](#)), `New` ([1512](#)), `Dispose` ([1454](#))

Listing: `./examples/refex/ex28.pp`

Program `Example28`;

{ Program to demonstrate the FreeMem and GetMem functions. }

Var `P` : `Pointer`;

`MM` : `Longint`;

begin

```

    { Get memory for P }
    GetMem (P,80);
    FillChar (P^,80,' ');
    FreeMem (P,80);
end.

```

75.11.133 Freememory

Synopsis: Alias for FreeMem ([1475](#))

Declaration: `procedure Freememory(p: pointer; Size: PtrUInt)`
`function Freememory(p: pointer) : PtrUInt`

Visibility: default

Description: `FreeMemory` is an alias for `FreeMem` ([1475](#)).

See also: `FreeMem` ([1475](#))

75.11.134 FreeResource

Synopsis: Free a loaded resource

Declaration: `function FreeResource(ResData: TFPResourceHGLOBAL) : LongBool`

Visibility: default

Description: `FreeResource` unloads the resource identified by `ResData` from memory. The resource must have been loaded by `LoadResource` ([1506](#)). It returns `True` if the operation was successful, `False` otherwise.

Errors: On error, `False` is returned.

See also: `FindResource` ([1471](#)), `LoadResource` ([1506](#)), `SizeofResource` ([1548](#)), `LockResource` ([1507](#)), `UnlockResource` ([1567](#)), `FreeResource` ([1476](#))

75.11.135 Get8087CW

Declaration: `function Get8087CW : Word`

Visibility: default

75.11.136 GetCPUCount

Synopsis: Return the number of cores on the system

Declaration: `function GetCPUCount : LongWord`

Visibility: default

Description: `GetCPUCount` returns the number of CPU cores on the system. Whether these are physically separate CPUs or cores on a single CPU is deliberately undefined.

See also: `CPUCount` ([1339](#))

75.11.137 GetCurrentThreadId

Synopsis: Return the id of the currently running thread.

Declaration: `function GetCurrentThreadId : TThreadId`

Visibility: default

Description: `GetCurrentThreadId` returns the ID of the currently running thread. It can be used in calls such as `KillThread` ([1502](#)) or `ThreadSetPriority` ([1561](#))

Errors: None.

See also: `KillThread` ([1502](#)), `ThreadSetPriority` ([1561](#))

75.11.138 GetDir

Synopsis: Return the current directory

Declaration: `procedure GetDir(drivenr: Byte; var dir: shortstring); Overload`
`procedure GetDir(drivenr: Byte; var dir: RawByteString); Overload`
`procedure GetDir(drivenr: Byte; var dir: unicodestring); Overload`

Visibility: default

Description: `Getdir` returns in `dir` the current directory on the drive `drivenr`, where {`drivenr`} is 1 for the first floppy drive, 3 for the first hard disk etc. A value of 0 returns the directory on the current disk. On Linux and Unix systems, `drivenr` is ignored, as there is only one directory tree.

Errors: An error is returned under dos, if the drive requested isn't ready.

See also: `Chdir` ([1440](#))

Listing: `./examples/refex/ex29.pp`

Program `Example29;`

{ Program to demonstrate the GetDir function. }

Var `S : String;`

begin

`GetDir (0,S);`

`Writeln ('Current directory is : ',S);`

end.

75.11.139 GetDynLibsManager

Synopsis: Return currently active dynamic library support handler

Declaration: `procedure GetDynLibsManager (var Manager: TDynLibsManager)`

Visibility: default

Description: `GetDynLibsManager` returns the currently active dynamic library support handler. This handler has normally been set by inclusion of the `#rtl.dynlibs` ([716](#)) unit.

See also: `#rtl.dynlibs` ([716](#)), `SetDynLibsManager` ([1539](#))

75.11.140 GetFPCHeapStatus

Synopsis: Return FPC heap manager status information

Declaration: `function GetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: Return FPC heap manager status information

75.11.141 GetHeapStatus

Synopsis: Return the memory manager heap status.

Declaration: `function GetHeapStatus : THeapStatus`

Visibility: default

75.11.142 GetLoadErrorStr

Synopsis: Return an error describing the last library loading error

Declaration: `function GetLoadErrorStr : string`

Visibility: default

Description: `GetLoadErrorStr` returns an error string describing the last library loading error. This function must be called before any other OS calls are performed.

Errors: None.

See also: `LoadLibrary` ([1506](#)), `SafeLoadLibrary` ([1534](#))

75.11.143 GetMem

Synopsis: Allocate new memory on the heap

Declaration: `procedure Getmem(out p: pointer; Size: PtrUInt)`
`function GetMem(size: PtrUInt) : pointer`

Visibility: default

Description: `Getmem` reserves `Size` bytes memory on the heap, and returns a pointer to this memory in `p`. What happens if no more memory is available, depends on the value of the variable `ReturnNilIfGrowHeapFails` ([1421](#)): if the variable is `True` then `Nil` is returned. If the variable is `False`, a run-time error is generated. The default value is `False`, so by default an error is generated.

The newly allocated memory is not initialized in any way, and may contain garbage data. It must be cleared with a call to `FillChar` ([1469](#)) or `FillWord` ([1470](#)).

For an example, see `Freemem` ([1475](#)).

Errors: None.

See also: `Freemem` ([1475](#)), `Dispose` ([1454](#)), `New` ([1512](#)), `returnnilifgrowheapfails` ([1421](#)), `MemSize` ([1510](#))

75.11.144 GetMemory

Synopsis: Alias for GetMem ([1478](#))

Declaration: `procedure Getmemory(out p: pointer; Size: PtrUInt)`
`function GetMemory(size: PtrUInt) : pointer`

Visibility: default

Description: Getmemory is an alias for GetMem ([1478](#)).

See also: GetMem ([1478](#))

75.11.145 GetMemoryManager

Synopsis: Return current memory manager

Declaration: `procedure GetMemoryManager(var MemMgr: TMemoryManager)`

Visibility: default

Description: GetMemoryManager stores the current Memory Manager record in MemMgr.

For an example, see the programmer's guide.

Errors: None.

See also: SetMemoryManager ([1541](#)), IsMemoryManagerSet ([1502](#))

75.11.146 GetMXCSR

Declaration: `function GetMXCSR : DWord`

Visibility: default

75.11.147 GetProcAddress

Synopsis: For compatibility with Delphi/Windows: Get the address of a procedure

Declaration: `function GetProcAddress(Lib: TLibHandle; const ProcName: AnsiString)`
`: Pointer`

Visibility: default

Description: GetProcAddress provides the same functionality as GetProcAddress ([1479](#)), and is provided for compatibility with Delphi.

75.11.148 GetProcAddress

Synopsis: Get the address of a procedure or symbol in a dynamic library.

Declaration: `function GetProcAddress(Lib: TLibHandle;`
`const ProcName: AnsiString) : Pointer`
`function GetProcAddress(Lib: TLibHandle; Ordinal: TOrdinalEntry)`
`: Pointer`

Visibility: default

Description: `GetProcAddress` returns a pointer to the location in memory of the symbol `ProcName` or ordinal value `Ordinal` in the dynamically loaded library specified by it's handle `lib`. If the symbol cannot be found or the handle is invalid, `Nil` is returned.

On Windows, only an exported procedure or function can be searched this way. On Unix platforms the location of any exported symbol can be retrieved this way.

Only windows and OS/2 support getting the address of a function using an ordinal value.

Errors: If the symbol cannot be found, `Nil` is returned.

See also: `LoadLibrary` ([1506](#)), `UnLoadLibrary` ([1566](#))

75.11.149 GetProcessID

Synopsis: Get the current process ID

Declaration: `function GetProcessID : SizeUInt`

Visibility: default

Description: `GetProcessID` returns the current process ID. The meaning of the return value of this call is system dependent.

Errors: None.

See also: `GetThreadID` ([1481](#))

75.11.150 GetResourceManager

Synopsis: Return the currently active resource manager

Declaration: `procedure GetResourceManager (var Manager: TResourceManager)`

Visibility: default

Description: `GetResourceManager` returns the currently active resource manager record in `Manager`. There is always an active resource manager record.

Errors: None.

See also: `TResourceManager` ([1399](#)), `SetResourceManager` ([1542](#))

75.11.151 GetSSECSR

Declaration: `function GetSSECSR : DWord`

Visibility: default

75.11.152 GetTextCodePage

Synopsis: Get the codepage used in a text file.

Declaration: `function GetTextCodePage (var T: Text) : TSystemCodePage`

Visibility: default

Description: `GetTextCodePage` returns the codepage that the text file `T` uses. All strings written to the file will be converted to the indicated codepage. By default, the codepage is set to `CP_ACP`.

Errors: None.

See also: [TextRec \(1392\)](#), [SetTextCodePage \(1544\)](#)

75.11.153 GetThreadID

Synopsis: Get the current Thread ID.

Declaration: `function GetThreadID : TThreadID`

Visibility: default

Description: `GetThreadID` returns the current process ID. The meaning of the return value of this call is system dependent.

See also: [GetProcessID \(1480\)](#)

75.11.154 GetThreadManager

Synopsis: Return the current thread manager

Declaration: `function GetThreadManager(var TM: TThreadManager) : Boolean`

Visibility: default

Description: `GetThreadManager` returns the currently used thread manager in TM.

For more information about thread programming, see the programmer's guide.

See also: [SetThreadManager \(1545\)](#), [TThreadManager \(1404\)](#)

75.11.155 GetTypeKind

Synopsis: Return type kind for a type

Declaration: `function GetTypeKind(const T: AnyType) : TTypeKind`

Visibility: default

Description: `GetTypeKind` is a compiler intrinsic: it returns the type kind for the type T. In difference with the [TypeInfo \(1563\)](#), if no type information was yet generated for the type, this statement will not ensure that the type information is available: the compiler knows the correct value, and will directly insert it into the code as a constant.

See also: [Default \(1452\)](#), [TypeInfo \(1563\)](#), [TypeOf \(1564\)](#), [Initialize \(1493\)](#), [Finalize \(1471\)](#)

75.11.156 GetUnicodeStringManager

Synopsis: Return a copy of the currently active UnicodeString manager.

Declaration: `procedure GetUnicodeStringManager(var Manager: TUnicodeStringManager)`

Visibility: default

Description: `GetUnicodeStringManager` returns a copy of the currently active Unicode string manager in `Old`

UnicodeStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `UnicodeStringManager` record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom unicodestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `SetUnicodeStringManager` (1545), `TUnicodeStringManager` (1407)

75.11.157 `GetVariantManager`

Synopsis: Return the current variant manager.

Declaration: `procedure GetVariantManager (var VarMgr: tvariantmanager)`

Visibility: default

Description: `GetVariantManager` returns the current variant manager in `varmgr`.

See also: `SetVariantManager` (1546)

75.11.158 `GetWideStringManager`

Synopsis: Return a copy of the currently active widestring manager.

Declaration: `procedure GetWideStringManager (var Manager: TUnicodeStringManager)`

Visibility: default

Description: `GetWideStringManager` returns a copy of the currently active heap manager in `Old`

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `WideString` manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `SetWideStringManager` (1546), `TWideStringManager` (1416)

75.11.159 `get_caller_addr`

Synopsis: Return the address of the caller.

Declaration: `function get_caller_addr (framebp: pointer; addr: CodePointer)
: CodePointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to address (the return address) of the caller of the routine which has as frame `framebp`.

See also: `get_frame` (1483), `get_caller_frame` (1483), `Dump_Stack` (1456)

75.11.160 `get_caller_frame`

Synopsis: Return the frame pointer of the caller

Declaration: `function get_caller_frame(framebp: pointer; addr: CodePointer) : pointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to the frame of the caller of the routine which has as frame `framebp`.

See also: `get_caller_addr` ([1482](#)), `get_frame` ([1483](#)), `Dump_Stack` ([1456](#))

75.11.161 `get_caller_stackinfo`

Synopsis: Return caller stack information

Declaration: `procedure get_caller_stackinfo(var framebp: pointer;
var addr: CodePointer)`

Visibility: default

Description: `get_caller_stackinfo` returns caller address in `addr` and frame base pointer in `framebp`.

See also: `CaptureBacktrace` ([1440](#)), `Get_pc_addr` ([1484](#)), `get_caller_addr` ([1482](#)), `get_caller_frame` ([1483](#))

75.11.162 `get_cmdline`

Synopsis: Return the command-line as a null-terminated string

Declaration: `function get_cmdline : PChar`

Visibility: default

Description: `get_cmdline` returns the complete command-line as a null-terminated string. It is not recommended to use this function, since it builds a complete value from the actual command-line arguments. Instead, `ParamCount` ([1516](#)) and `ParamStr` ([1517](#)) should be used.

See also: `ParamCount` ([1516](#)), `ParamStr` ([1517](#))

75.11.163 `get_frame`

Synopsis: Return the current frame

Declaration: `function get_frame : pointer`

Visibility: default

Description: `get_frame` returns a pointer to the current stack frame.

See also: `get_caller_addr` ([1482](#)), `get_caller_frame` ([1483](#))

75.11.164 Get_pc_addr

Synopsis: Get Program Counter address

Declaration: `function Get_pc_addr : CodePointer`

Visibility: default

Description: `Get_pc_addr` returns the program counter address (current execution address).

See also: `CaptureBacktrace` (1440), `get_caller_stackinfo` (1483), `get_caller_addr` (1482), `get_caller_frame` (1483)

75.11.165 greaterthan(variant,variant):Boolean

Synopsis: Implement > (greater than) operation on variants.

Declaration: `operator >(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the "greater than" comparison (>) operation is delegated to the variant manager with operation `opcmpgt`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator <(variant, variant): boolean` (1339)

75.11.166 greaterthanorequal(variant,variant):Boolean

Synopsis: Implement >= (greater than or equal) operation on variants.

Declaration: `operator >=(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the "greater than or equal" comparison (>=) operation is delegated to the variant manager with operation `opcmpge`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator <(variant, variant): boolean` (1339)

75.11.167 Halt

Synopsis: Stop program execution.

Declaration: `procedure Halt(errnum: LongInt)`
`procedure Halt`

Visibility: default

Description: `Halt` stops program execution and returns control to the calling program. The optional argument `Errnum` specifies an exit value. If omitted, zero is returned.

Note that this skips any try/finally (implicit or explicit) or try/except blocks, thus may result in memory leaks. Finalization sections of units will be executed.

Errors: None.

See also: [Exit \(1464\)](#)

Listing: ./examples/refex/ex30.pp

Program Example30;

```
{ Program to demonstrate the Halt function. }

begin
  Writeln ('Before Halt. ');
  Halt (1); { Stop with exit code 1 }
  Writeln ('After Halt doesn't get executed. ');
end.
```

75.11.168 HexStr

Synopsis: Convert integer value to string with hexadecimal representation.

Declaration:

```
function HexStr(Val: LongInt; cnt: Byte) : shortstring
function HexStr(Val: Int64; cnt: Byte) : shortstring
function HexStr(Val: QWord; cnt: Byte) : shortstring
function HexStr(Val: Pointer) : shortstring
```

Visibility: default

Description: HexStr returns a string with the hexadecimal representation of Value. The string has exactly cnt characters. (i.e. only the cnt rightmost nibbles are taken into account) To have a complete representation of a Longint-type value, 8 nibbles are needed, i.e. cnt=8.

Errors: None.

See also: [Str \(1551\)](#), [Val \(1570\)](#), [BinStr \(1434\)](#)

Listing: ./examples/refex/ex81.pp

Program example81;

```
{ Program to demonstrate the HexStr function }

Const Value = 45678;

Var I : longint;

begin
  For I:=1 to 10 do
    Writeln (HexStr(Value, I));
end.
```

75.11.169 Hi

Synopsis: Return high byte/word/nibble of value.

Declaration: `function Hi(b: Byte) : Byte`
`function Hi(i: Integer) : Byte`
`function Hi(w: Word) : Byte`
`function Hi(l: LongInt) : Word`
`function Hi(l: DWord) : Word`
`function Hi(i: Int64) : DWord`
`function Hi(q: QWord) : DWord`

Visibility: default

Description: `Hi` returns the high nibble, byte or word or longword from `X`, depending on the size of `X`.

Table 75.21:

Size	Return value
8	Byte, High nibble
16	Byte, High byte
32	Word, High word
64	Cardinal, High DWord

Note that in Delphi or TP, this function always treats its argument as if it was a `Word`, so the results may differ from FPC.

Errors: None.

See also: `Lo` ([1505](#))

Listing: `./examples/refex/ex31.pp`

```
Program Example31 ;

{ Program to demonstrate the Hi function. }

var
  L : Longint;
  W : Word;
  B : Byte;

begin
  L:=1 Shl 16;    { = $10000 }
  W:=1 Shl 8;     { = $100 }
  B:=1 Shl 4;     { = $10 }
  Writeln (Hi(L)); { Prints 1 }
  Writeln (Hi(W)); { Prints 1 }
  Writeln (Hi(B)); { Prints 1 }
end.
```

75.11.170 High

Synopsis: Return highest index of open array or enumerated

Declaration: `function High(Arg: TypeOrVariable) : TOrdinal`

Visibility: default

Description: The return value of `High` depends on it's argument:

- 1.If the argument is an ordinal type, `High` returns the highest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `High` returns the highest possible value of it's index. For dynamic arrays, it returns the same as `Length -1`, meaning that it reports -1 for empty arrays.
- 3.If the argument is an open array identifier in a function or procedure, then `High` returns the highest index of the array, as if the array has a zero-based index. If the array is empty, then -1 is returned.
- 4.If the argument is a set type then it returns the highest value of the underlying ordinal type.

The return type is always the same type as the type of the argument (This can lead to some nasty surprises !).

Errors: None.

See also: `Low` ([1508](#)), `Ord` ([1515](#)), `Pred` ([1519](#)), `Succ` ([1555](#))

Listing: ./examples/refex/ex80.pp

Program example80;

{ Example to demonstrate the High and Low functions. }

Type TEnum = (North , East , South , West);
 TRange = 14..55;
 TArray = **Array** [2..10] **of** Longint;

Function Average (Row : **Array of** Longint) : Real;

Var I : longint;
 Temp : Real;

begin
 Temp := Row[0];
 For I := 1 **to** **High**(Row) **do**
 Temp := Temp + Row[I];
 Average := Temp / (**High**(Row)+1);
end;

Var A : TEnum;
 B : TRange;
 C : TArray;
 I : longint;

begin
 Writeln ('TEnum goes from : ', **Ord**(**Low**(TEnum)), ' to ', **Ord**(**high**(TEnum)), '. ');
 Writeln ('A goes from : ', **Ord**(**Low**(A)), ' to ', **Ord**(**high**(A)), '. ');
 Writeln ('TRange goes from : ', **Ord**(**Low**(TRange)), ' to ', **Ord**(**high**(TRange)), '. ');
 Writeln ('B goes from : ', **Ord**(**Low**(B)), ' to ', **Ord**(**high**(B)), '. ');
 Writeln ('TArray index goes from : ', **Ord**(**Low**(TArray)), ' to ', **Ord**(**high**(TArray)), '. ');
 Writeln ('C index goes from : ', **Low**(C), ' to ', **high**(C), '. ');
 For I:=**Low**(C) **to** **High**(C) **do**
 C[I]:=I;
 Writeln ('Average : ', Average(c));
end;

```

    Write ('Type of return value is always same as type of argument:');
    Writeln(high(high(word)));
end.

```

75.11.171 HINSTANCE

Synopsis: Windows compatibility type for use in resources

Declaration: `function HINSTANCE : TFPResourceHMODULE`

Visibility: default

Description: This is an opaque type.

75.11.172 Inc

Synopsis: Increase value of integer variable

Declaration: `procedure Inc(var X: TOrdinal)`
`procedure Inc(var X: TOrdinal; Increment: TOrdinal)`

Visibility: default

Description: `Inc` increases the value of `X` with `Increment`. If `Increment` isn't specified, then 1 is taken as a default.

`Inc` can be used on typed pointers: in that case it increases the value with `Increment` the size of the type the pointer points to. This works independently of the setting of the `$POINTERMATH` directive.

Errors: If range checking is on, then A range check can occur, or an overflow error, when an attempt is made to increase `X` over its maximum value.

See also: `Dec` ([1451](#))

Listing: `./examples/refex/ex32.pp`

Program `Example32;`

{ Program to demonstrate the Inc function. }

Const

```

C : Cardinal  = 1;
L : Longint   = 1;
I : Integer   = 1;
W : Word      = 1;
B : Byte      = 1;
SI : ShortInt = 1;
CH : Char     = 'A';

```

begin

```

Inc (C);      { C:=2    }
Inc (L,5);    { L:=6    }
Inc (I,-3);   { I:=-2   }
Inc (W,3);    { W:=4    }
Inc (B,100);  { B:=101  }
Inc (SI,-3);  { SI:=-2  }
Inc (CH,1);   { ch:='B' }

```

end.

75.11.173 Include

Synopsis: Include element in set if it was not yet present.

Declaration: `procedure Include(var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Include` includes `E` in the set `S` if it is not yet part of the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```
S:=S+[E];
Include(S,E);
```

For an example, see `Exclude` ([1463](#))

Errors: If the type of the element `E` is not equal to the base type of the set `S`, the compiler will generate an error.

See also: `Exclude` ([1463](#))

75.11.174 IndexByte

Synopsis: Search for a byte in a memory range.

Declaration: `function IndexByte(const buf; len: SizeInt; b: Byte) : SizeInt`

Visibility: default

Description: `IndexByte` searches the memory at `buf` for maximally `len` positions for the byte `b` and returns it's position if it found one. If `b` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexChar` ([1490](#)), `IndexDWord` ([1491](#)), `IndexWord` ([1492](#)), `CompareByte` ([1442](#))

Listing: `./examples/refex/ex105.pp`

Program `Example105;`

{ Program to demonstrate the IndexByte function. }

Const

```
  ArraySize = 256;
  MaxValue = 256;
```

Var

```
  Buffer : Array[1..ArraySize] of Byte;
  I,J : longint;
  K : Byte;
```

begin

```
  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=Random(MaxValue);
  For I:=1 to 10 do
    begin
      K:=Random(MaxValue);
```

```

J:=IndexByte ( Buffer , ArraySize ,K);
if J=-1 then
  WriteLn('Value ',K,' was not found in buffer.')
else
  WriteLn('Found ',K,' at position ',J,' in buffer');
end;
end.

```

75.11.175 IndexChar

Synopsis: Search for a character in a memory range.

Declaration: `function IndexChar(const buf; len: SizeInt; b: Char) : SizeInt`

Visibility: default

Description: `IndexChar` searches the memory at `buf` for maximally `len` positions for the character `b` and returns it's position if it found one. If `b` is not found then -1 is returned. The position is zero-based. The `IndexChar0` variant stops looking if a null character is found, and returns -1 in that case.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1489](#)), `IndexDWord` ([1491](#)), `IndexWord` ([1492](#)), `CompareChar` ([1443](#))

Listing: `./examples/refex/ex108.pp`

Program `Example108`;

{ Program to demonstrate the IndexChar function. }

Const

```

  ArraySize = 1000;
  MaxValue = 26;

```

Var

```

  Buffer : Array[1..ArraySize] of Char;
  I,J : longint;
  K : Char;

```

begin

```

  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=chr(Ord('A')+Random(MaxValue));
  For I:=1 to 10 do
    begin
      K:=chr(Ord('A')+Random(MaxValue));
      J:=IndexChar(Buffer,ArraySize,K);
      if J=-1 then
        WriteLn('Value ',K,' was not found in buffer.')
      else
        WriteLn('Found ',K,' at position ',J,' in buffer');
      end;
    end;

```

end.

75.11.176 IndexChar0

Synopsis: Return index of a character in null-terminated array of char.

Declaration: `function IndexChar0(const buf; len: SizeInt; b: Char) : SizeInt`

Visibility: default

Description: `IndexChar0` returns the index of the character `b` in the null-terminated array `Buf`. At most `len` characters will be searched, or the null character if it is encountered first. If the character is not found, -1 is returned.

Errors: On error, -1 is returned.

See also: `IndexByte` ([1489](#)), `IndexChar` ([1490](#)), `IndexWord` ([1492](#)), `IndexDWord` ([1491](#)), `CompareChar0` ([1445](#))

75.11.177 IndexDWord

Synopsis: Search for a DWord value in a memory range.

Declaration: `function IndexDWord(const buf; len: SizeInt; b: DWord) : SizeInt`

Visibility: default

Description: `IndexDWord` searches the memory at `buf` for maximally `len` positions for the DWord `DW` and returns it's position if it found one. If `DW` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1489](#)), `IndexChar` ([1490](#)), `IndexWord` ([1492](#)), `CompareDWord` ([1445](#))

Listing: `./examples/refex/ex106.pp`

Program `Example106;`

{ Program to demonstrate the IndexDWord function. }

Const

`ArraySize = 1000;
 MaxValue = 1000;`

Var

`Buffer : Array[1..ArraySize] of DWord;
 I,J : longint;
 K : DWord;`

begin

`Randomize;
 For I:=1 To ArraySize do
 Buffer[I]:=Random(MaxValue);
 For I:=1 to 10 do
 begin
 K:=Random(MaxValue);
 J:=IndexDWord(Buffer , ArraySize ,K);
 if J=-1 then
 WriteLn('Value ',K, ' was not found in buffer.')
 else
 WriteLn('Found ',K, ' at position ',J, ' in buffer');
 end;`

`end.`

75.11.178 IndexQWord

Synopsis: Return the position of a QWord in a memory range

Declaration: `function IndexQWord(const buf; len: SizeInt; b: QWord) : SizeInt`

Visibility: default

Description: `IndexQWord` checks the first `len` qwords starting at `Buf`, and returns the position (zero-based) of `b`. If `b` does not appear in the first `len` qwords, then -1 is returned.

Note that the search is done on QWord boundaries, but that the address of `buf` need not be on a QWord boundary.

Errors: No check is done to see whether the indicated memory range is valid. If it is not, a run-error or exception may be triggered.

See also: `IndexDWord` ([1491](#))

75.11.179 Indexword

Synopsis: Search for a WORD value in a memory range.

Declaration: `function Indexword(const buf; len: SizeInt; b: Word) : SizeInt`

Visibility: default

Description: `IndexWord` searches the memory at `buf` for maximally `len` positions for the Word `W` and returns it's position if it found one. If `W` is not found then -1 is returned.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1489](#)), `IndexDWord` ([1491](#)), `IndexChar` ([1490](#)), `CompareWord` ([1446](#))

Listing: `./examples/refex/ex107.pp`

Program `Example107;`

{ Program to demonstrate the IndexWord function. }

Const

`ArraySize = 1000;`
`MaxValue = 1000;`

Var

`Buffer : Array[1..ArraySize] of Word;`
`I,J : longint;`
`K : Word;`

begin

`Randomize;`
`For I:=1 To ArraySize do`
`Buffer[I]:=Random(MaxValue);`
`For I:=1 to 10 do`
`begin`
`K:=Random(MaxValue);`
`J:=IndexWord(Buffer,ArraySize,K);`
`if J=-1 then`
`WriteLn('Value ',K,' was not found in buffer.')`
`else`

```

    WriteLn('Found ',K,' at position ',J,' in buffer');
  end;
end.

```

75.11.180 InitCriticalSection

Synopsis: Initialize a critical section

Declaration: `procedure InitCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `InitCriticalSection` initializes a critical section CS for use. Before using a critical section with `EnterCriticalSection` (1459) or `LeaveCriticalSection` (1502) the critical section should be initialized with `InitCriticalSection`.

When a critical section is no longer used, it should be disposed of with `DoneCriticalSection` (1455)

See also: `DoneCriticalSection` (1455), `EnterCriticalSection` (1459), `LeaveCriticalSection` (1502)

75.11.181 Initialize

Synopsis: Initialize memory block using RTTI

Declaration: `procedure Initialize(var T: TAnyType; ACount: SizeInt)`

Visibility: default

Description: `Initialize` is a compiler intrinsic: it initializes a memory area T for any kind of managed variable. Initializing means zeroing out the memory area. In this sense it is close in functionality to `Default` (1452), but `Default` requires an already initialized variable. It performs the opposite operation of `finalize` (1471), which should be used to clean up the memory block when it is no longer needed.

The optional `ACount` parameter can be used to initialize an array. It then specifies the number of elements in the array.

See also: `finalize` (1471), `Default` (1452), `TypeInfo` (1563)

Listing: `./examples/refex/ex117.pp`

```

{
  This example demonstrates the use of the Initialize and Finalize functions
  used to initialize (and clean up) any RTTI-enabled data not allocated with
  New or Create.
}

{$mode objfpc}
{$h+} // use ansistrings, they need to be initialized.
Type
  PData = ^TData;
  TData = record
    Street, City, Zip, Country, Tel: String;
    StreetNumber: Integer;
  end;

var
  Data: PData;

```

```

begin
    // Do not use New.
    GetMem(Data, SizeOf(TData));
    Try
        { Initialize the structure in memory, using Run-Time Type Information }
        Initialize(Data^);
        { Assign some string data to the ansistring contents.
          Note that this only works because the record was zeroed out by Initialize }
        Data^.Street := 'Sesame Street';
        Data^.City := 'Heaven';
        Data^.Zip := '7777777';
        Data^.Country := 'Spain';
        Data^.StreetNumber := 3;
    Finally
        { Clean up the record contents.
          Again, the structure of the record is detected through
          Run-time Type Information }
        Finalize(Data^);
        FreeMem(Data);
    end;
end.

```

Listing: ./examples/refex/ex118.pp

```

{
    This example demonstrates the use of the Initialize and Finalize functions
    used to initialize (and clean up) any RTTI-enabled data not allocated with
    New or Create.
}

{$mode objfpc}
{$h+} // use ansistrings, they need to be initialized.
Type
    PData = ^TData;
    TData = record
        Street, City, Zip, Country, Tel: String;
        StreetNumber : Integer;
    end;

var
    Data: PData;

begin
    // We use the fact that a pointer is also usable as an array.
    GetMem(Data, SizeOf(TData)*2);
    Try
        { Initialize the structure in memory, using Run-Time Type Information }
        Initialize(Data^, 2);
        { Assign some string data to the ansistring contents.
          Note that this only works because the record was zeroed out by Initialize }
        Data[0].Street := 'Sesame Street';
        Data[0].City := 'Heaven';
        Data[0].Zip := '7777777';
        Data[0].Country := 'Spain';
        Data[0].StreetNumber := 3;
        // Second, well known street
        Data[1].Street := 'Wall Street';
        Data[1].City := 'New York';
    end;
end.

```

```

    Data[1].Zip:= '10005';
    Data[1].Country:= 'USA';
    Data[1].StreetNumber:=11;
Finally
    { Clean up the record contents.
      Again, the structure of the record is detected through
      Run-time Type Information }
    Finalize(Data^);
    FreeMem(Data);
end;
end.

```

75.11.182 InitializeArray

Synopsis: Initialize managed-type elements in array

Declaration: `procedure InitializeArray(p: Pointer; typeInfo: Pointer; count: SizeInt)`

Visibility: default

Description: `InitializeArray` initializes managed types in the array pointed to by `p`. For this, it uses the type information of the elements as specified in `typeinfo`.

Under normal circumstances, this procedure should not be used, it is called automatically by the compiler when an array-typed variable is declared and the array contains elements with managed types.

See also: `FinalizeArray` ([1471](#)), `CopyArray` ([1450](#))

75.11.183 InitThread

Synopsis: Initialize a thread

Declaration: `procedure InitThread(stklen: SizeUInt)`

Visibility: default

Description: Do not use, this is used internally by the thread manager.

75.11.184 InitThreadVars

Synopsis: Initialize threadvars

Declaration: `procedure InitThreadVars(RelocProc: TRelocateThreadVarHandler)`

Visibility: default

Description: This routine should be called when threading is started. It is called by the compiler and should never be called manually, only from a thread manager.

Errors: None.

See also: `TThreadManager` ([1404](#))

75.11.185 Insert

Synopsis: Insert one string or dynamic array in another.

Declaration: `procedure Insert(const source: string; var S: string;
const Index: Integer)
procedure Insert(const source: DynArrayType; var S: DynArrayType;
const Index: Integer)`

Visibility: default

Description: `Insert` inserts string `Source` in string `S`, at position `Index`, shifting all characters after `Index` to the right. The resulting string is truncated at 255 characters, if needed. (i.e. for shortstrings)

`Index` is a 1-based index. if `Index` is less than 1, the insert of `Source` happens at the start of the string, as if the value 1 was specified.

If the value of `Index` is larger than the length of the string `S`, `Source` is appended to the string `S`.

For dynamic arrays, `Insert` inserts the elements of array `Source` in array `S`, at position `Index`, shifting all elements after `Index` to the right.

`Index` is a 0-based index. if `Index` is less than 0, the insert of `Source` happens at position 0.

If the value of `Index` is larger than the length of the array `S`, `Source` is appended to the array `S`.

Errors: None.

See also: `Delete` ([1453](#)), `Copy` ([1449](#)), `Pos` ([1518](#))

Listing: `./examples/refex/ex33.pp`

Program `Example33`;

{ Program to demonstrate the Insert function. }

Var `S : String`;

begin

`S := 'Free Pascal is difficult to use !';`

`Insert ('NOT ', S, pos('difficult', S));`

`writeln (s);`

end.

75.11.186 Int

Synopsis: Calculate integer part of floating point value.

Declaration: `function Int(d: ValReal) : ValReal`

Visibility: default

Description: `Int` returns the integer part of any Real `X`, as a Real.

Errors: None.

See also: `Frac` ([1474](#)), `Round` ([1532](#))

Listing: `./examples/refex/ex34.pp`

Program Example34;

```
{ Program to demonstrate the Int function. }

begin
  Writeln (Int(123.456):0:1); { Prints 123.0 }
  Writeln (Int(-123.456):0:1); { Prints -123.0 }
end.
```

75.11.187 intdivide(variant,variant):variant

Synopsis: Implement div (integer division) operation on variants.

Declaration: operator div(const op1: variant; const op2: variant) : variant

Visibility: default

Description: The implementation of the integer division Div operation is delegated to the variant manager with operation opintdivide.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator mod(variant, variant): variant ([1339](#))

75.11.188 InterlockedCompareExchange

Synopsis: Conditional exchange

Declaration: function InterlockedCompareExchange(var Target: LongInt;
 NewValue: LongInt;
 Comperand: LongInt) : LongInt
 function InterlockedCompareExchange(var Target: Pointer;
 NewValue: Pointer;
 Comperand: Pointer) : Pointer
 function InterlockedCompareExchange(var Target: Cardinal;
 NewValue: Cardinal;
 Comperand: Cardinal) : Cardinal

Visibility: default

Description: InterlockedCompareExchange does an compare-and-exchange operation on the specified values in a thread-safe way. The function compares Target and Comperand and exchanges Target with NewValue if Target and Comperand are equal. It returns the old value of Target. This is done in a thread-safe way, i.e., only one processor is accessing the Target variable at a time.

Errors: None.

See also: InterLockedDecrement ([1498](#)), InterLockedIncrement ([1500](#)), InterLockedExchange ([1498](#)), InterLockedExchangeAdd ([1499](#))

75.11.189 InterlockedCompareExchange64

Declaration: `function InterlockedCompareExchange64 (var Target: Int64;
 NewValue: Int64; Comperand: Int64)
 : Int64
 function InterlockedCompareExchange64 (var Target: QWord;
 NewValue: QWord; Comperand: QWord)
 : QWord`

Visibility: default

75.11.190 InterlockedCompareExchangePointer

Synopsis: Compare pointers in an atomic operation

Declaration: `function InterlockedCompareExchangePointer (var Target: Pointer;
 NewValue: Pointer;
 Comperand: Pointer) : Pointer`

Visibility: default

Description: `InterlockedCompareExchangePointer` compares `Comperand` with `Target`. if they are equal, replaces `Target` with `NewValue`. This is done in a single atomic operation.

See also: `InterlockedCompareExchange` ([1497](#))

75.11.191 InterlockedDecrement

Synopsis: Thread-safe decrement

Declaration: `function InterlockedDecrement (var Target: LongInt) : LongInt
 function InterlockedDecrement (var Target: Pointer) : Pointer
 function InterlockedDecrement (var Target: Cardinal) : Cardinal`

Visibility: default

Description: `InterLockedDecrement` decrements `Target` with 1 and returns the result. This is done in a thread-safe way. (i.e. only one processor is accessing the variable at a time).

Errors: None.

See also: `InterLockedIncrement` ([1500](#)), `InterLockedExchange` ([1498](#)), `InterLockedExchangeAdd` ([1499](#)), `InterlockedCompareExchange` ([1497](#))

75.11.192 InterlockedDecrement64

Declaration: `function InterlockedDecrement64 (var Target: Int64) : Int64
 function InterlockedDecrement64 (var Target: QWord) : QWord`

Visibility: default

75.11.193 InterlockedExchange

Synopsis: Exchange 2 integers in a thread-safe way

Declaration: `function InterlockedExchange(var Target: LongInt; Source: LongInt) : LongInt`
`function InterlockedExchange(var Target: Pointer; Source: Pointer) : Pointer`
`function InterlockedExchange(var Target: Cardinal; Source: Cardinal) : Cardinal`

Visibility: default

Description: `InterLockedExchange` stores `Source` in `Target` and returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

Errors: None.

See also: `InterLockedDecrement` ([1498](#)), `InterLockedIncrement` ([1500](#)), `InterLockedExchangeAdd` ([1499](#)), `InterlockedCompareExchange` ([1497](#))

75.11.194 InterlockedExchange64

Declaration: `function InterlockedExchange64(var Target: Int64; Source: Int64) : Int64`
`function InterlockedExchange64(var Target: QWord; Source: QWord) : QWord`

Visibility: default

75.11.195 InterlockedExchangeAdd

Synopsis: Thread-safe add and exchange of 2 values

Declaration: `function InterlockedExchangeAdd(var Target: LongInt; Source: LongInt) : LongInt`
`function InterlockedExchangeAdd(var Target: Pointer; Source: Pointer) : Pointer`
`function InterlockedExchangeAdd(var Target: Cardinal; Source: Cardinal) : Cardinal`

Visibility: default

Description: `InterLockedExchangeAdd` adds to `Target` the value of `Source` in a thread-safe way, and returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

Errors: None.

See also: `InterLockedDecrement` ([1498](#)), `InterLockedIncrement` ([1500](#)), `InterLockedExchange` ([1498](#)), `InterlockedCompareExchange` ([1497](#))

75.11.196 InterlockedExchangeAdd64

Declaration: `function InterlockedExchangeAdd64(var Target: Int64; Source: Int64) : Int64`
`function InterlockedExchangeAdd64(var Target: QWord; Source: QWord) : QWord`

Visibility: default

75.11.197 InterlockedIncrement

Synopsis: Thread-safe increment

Declaration: `function InterlockedIncrement (var Target: LongInt) : LongInt`
`function InterlockedIncrement (var Target: Pointer) : Pointer`
`function InterlockedIncrement (var Target: Cardinal) : Cardinal`

Visibility: default

Description: `InterLockedIncrement` increments `Target` with 1 and returns the result. This is done in a thread-safe way (i.e. only one processor is accessing the variable at a time).

Errors: None.

See also: `InterLockedDecrement` ([1498](#)), `InterLockedExchange` ([1498](#)), `InterLockedExchangeAdd` ([1499](#)), `InterlockedCompareExchange` ([1497](#))

75.11.198 InterlockedIncrement64

Declaration: `function InterlockedIncrement64 (var Target: Int64) : Int64`
`function InterlockedIncrement64 (var Target: QWord) : QWord`

Visibility: default

75.11.199 IOResult

Synopsis: Return result of last file IO operation

Declaration: `function IOResult : Word`

Visibility: default

Description: `IOresult` contains the result of any input/output call, when the `{\${i-}}` compiler directive is active, disabling IO checking. When the flag is read, it is reset to zero. If `IOresult` is zero, the operation completed successfully. If non-zero, an error occurred. The following errors can occur:

dos errors :

2File not found.

3Path not found.

4Too many open files.

5Access denied.

6Invalid file handle.

12Invalid file-access mode.

15Invalid disk number.

16Cannot remove current directory.

17Cannot rename across volumes.

I/O errors :

100Error when reading from disk.

101Error when writing to disk.

102File not assigned.

103File not open.

104File not opened for input.

105File not opened for output.

106Invalid number.

Fatal errors :

150Disk is write protected.

151Unknown device.

152Drive not ready.

153Unknown command.

154CRC check failed.

155Invalid drive specified..

156Seek error on disk.

157Invalid media type.

158Sector not found.

159Printer out of paper.

160Error when writing to device.

161Error when reading from device.

162Hardware failure.

Errors: None.

Listing: ./examples/refex/ex35.pp

Program Example35;

{ Program to demonstrate the IOResult function. }

Var F : text;

begin

Assign (f,paramstr(1));

{ \$i- }

Reset (f);

{ \$i+ }

If IOresult<>0 **then**

writeln ('File ',paramstr(1),' doesn't exist')

else

writeln ('File ',paramstr(1),' exists');

end.

75.11.200 IsDynArrayRectangular

Synopsis: Check whether all dimensions have the same size

Declaration: function IsDynArrayRectangular(a: Pointer; typeInfo: Pointer) : Boolean

Visibility: default

Description: IsDynArrayRectangular returns True if all dimensions of the dynamic array a with type information typinfo have the same bounds. It returns True if the array is empty.

See also: InitializeArray (1495), FinalizeArray (1471), CopyArray (1450), DynArraySize (1458), DynArrayClear (1457), DynArrayBounds (1457), DynArrayDim (1457)

75.11.201 IsMemoryManagerSet

Synopsis: Is the memory manager set

Declaration: `function IsMemoryManagerSet : Boolean`

Visibility: default

Description: `IsMemoryManagerSet` will return `True` if the memory manager has been set to another value than the system heap manager, it will return `False` otherwise.

Errors: None.

See also: `SetMemoryManager` ([1541](#)), `GetMemoryManager` ([1479](#))

75.11.202 Is_IntResource

Synopsis: Check whether a resource is an internal resource

Declaration: `function Is_IntResource(aStr: PChar) : Boolean`

Visibility: default

Description: `Is_IntResource` returns `True` if the resource type is internal (system predefined) resource or false if it is a user-defined resource type.

Errors: None.

75.11.203 KillThread

Synopsis: Kill a running thread

Declaration: `function KillThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `KillThread` causes a running thread to be aborted. The thread is identified by its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `WaitForThreadTerminate` ([1572](#)), `EndThread` ([1458](#)), `SuspendThread` ([1556](#))

75.11.204 LeaveCriticalSection

Synopsis: Leave a critical section

Declaration: `procedure LeaveCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `LeaveCriticalSection` signals that the current thread is exiting the critical section CS it has entered with `EnterCriticalSection` ([1459](#)).

The critical section must have been initialized with `InitCriticalSection` ([1493](#)) prior to a call to `EnterCriticalSection` and `LeaveCriticalSection`.

See also: `InitCriticalSection` ([1493](#)), `DoneCriticalSection` ([1455](#)), `EnterCriticalSection` ([1459](#))

75.11.205 leftshift(variant,variant):variant

Synopsis: Implement binary shl operation on variants.

Declaration: `operator shl(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the shl operation is delegated to the variant manager with operation opshiftright.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator shr(variant, variant): variant ([1339](#))

75.11.206 Length

Synopsis: Returns length of a string or array.

Declaration: `function &Length(S: AStringType) : SizeInt`
`function &Length(A: DynArrayType) : SizeInt`

Visibility: default

Description: Length returns the length of the string or array S, which is limited to 255 for shortstrings. If the string S is empty, 0 is returned.

Note: The length of the string S is stored in S[0] for shortstrings only. The Length function should always be used on ansistrings and widestrings.

For dynamic or static arrays, the function returns the number of elements in the array.

Length also supports arguments of type PChar and PWideChar, in which case it is identical to the StrLen and WStrLen functions, respectively. In this case, the function actually calculates the length of the null-terminated string, and its execution time is proportional to the string length because the terminating null character is searched through a linear scan.

Errors: None.

See also: Pos ([1518](#)), SetLength ([1540](#))

Listing: ./examples/refex/ex36.pp

Program Example36;

{ Program to demonstrate the Length function. }

type

somebytes = **array** [6..10] **of** byte;
 somewords = **array** [3..10] **of** word;

Var

S : **String**;
 I : **Integer**;
 bytes : somebytes;
 words : somewords;

begin

S:= '';
for i:=1 **to** 10 **do**

```

begin
S:=S+ '* ' ;
Writeln (Length(S):2, ' : ',s);
end;
Writeln ( 'Bytes : ',length(bytes));
Writeln ( 'Words : ',length(words));
end.

```

75.11.207 lessthan(variant,variant):Boolean

Synopsis: Implement < (less than) operation on variants.

Declaration: operator <(const op1: variant; const op2: variant) : Boolean

Visibility: default

Description: The implementation of the "less than" comparison (<) operation is delegated to the variant manager with operation opcmplt.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator >(variant, variant): boolean ([1339](#))

75.11.208 lessthanorequal(variant,variant):Boolean

Synopsis: Implement <= (less than or equal) operation on variants.

Declaration: operator <=(const op1: variant; const op2: variant) : Boolean

Visibility: default

Description: The implementation of the "less than or equal" comparison (<=) operation is delegated to the variant manager with operation opcmple.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator <(variant, variant): boolean ([1339](#))

75.11.209 LEtoN

Synopsis: Convert Little Endian-ordered integer to Native-ordered integer

Declaration: function LEtoN(const AValue: SmallInt) : SmallInt
function LEtoN(const AValue: Word) : Word
function LEtoN(const AValue: LongInt) : LongInt
function LEtoN(const AValue: DWord) : DWord
function LEtoN(const AValue: Int64) : Int64
function LEtoN(const AValue: QWord) : QWord

Visibility: default

Description: LEToN will rearrange the bytes in a Little-Endian number to the native order for the current processor. That is, for a little-endian processor, it will do nothing, and for a big-endian processor, it will invert the order of the bytes.

See also: BEtoN ([1434](#)), NtoBE ([1513](#)), NtoLE ([1513](#))

75.11.210 Ln

Synopsis: Calculate logarithm

Declaration: `function Ln(d: ValReal) : ValReal`

Visibility: default

Description: `Ln` returns the natural logarithm of the Real parameter X. X must be positive.

Errors: An run-time error will occur when X is negative.

See also: `Exp` ([1466](#))

Listing: `./examples/refex/ex37.pp`

Program `Example37;`

{ Program to demonstrate the Ln function. }

```
begin
  Writeln (Ln(1));      { Prints 0 }
  Writeln (Ln(Exp(1))); { Prints 1 }
end.
```

75.11.211 Lo

Synopsis: Return low nibble/byte/word of value.

Declaration: `function Lo(B: Byte) : Byte`
`function Lo(i: Integer) : Byte`
`function Lo(w: Word) : Byte`
`function Lo(l: LongInt) : Word`
`function Lo(l: DWord) : Word`
`function Lo(i: Int64) : DWord`
`function Lo(q: QWord) : DWord`

Visibility: default

Description: `Lo` returns the high nibble, byte or word or longword from X, depending on the size of X.

Table 75.22:

Size	Return value
8	Byte, low nibble
16	Byte, low byte
32	Word, low word
64	Cardinal, low DWord

Errors: None.

See also: `Ord` ([1515](#)), `Chr` ([1441](#)), `Hi` ([1485](#))

Listing: `./examples/refex/ex38.pp`

```

Program Example38;

{ Program to demonstrate the Lo function. }

Var L : Longint;
      W : Word;
      B : Byte;
begin
  L:=(1 Shl 16) + (1 Shl 4); { $10010 }
  WriteLn (Lo(L));           { Prints 16 }
  W:=(1 Shl 8) + (1 Shl 4); { $110 }
  WriteLn (Lo(W));           { Prints 16 }
  B:=$EF;
  WriteLn (Lo(B));           { Prints 15 }
end.

```

75.11.212 LoadLibrary

Synopsis: Load a dynamic library and return a handle to it.

Declaration: `function LoadLibrary(const Name: RawByteString) : TLibHandle`
`function LoadLibrary(const Name: UnicodeString) : TLibHandle`

Visibility: default

Description: `LoadLibrary` loads a dynamic library in file `Name` and returns a handle to it. If the library cannot be loaded, `NilHandle` ([1362](#)) is returned.

No assumptions should be made about the location of the loaded library if a relative pathname is specified. The behaviour is dependent on the platform. Therefore it is best to specify an absolute pathname if possible.

Errors: On error, `NilHandle` ([1362](#)) is returned.

See also: `UnloadLibrary` ([1566](#)), `GetProcAddress` ([1479](#))

75.11.213 LoadResource

Synopsis: Load a resource for use

Declaration: `function LoadResource(ModuleHandle: TFPResourceHMODULE;`
`ResHandle: TFPResourceHandle) : TFPResourceHGLOBAL`

Visibility: default

Description: `LoadResource` loads a resource identified by `ResHandle` from a module identified by `ModuleHandle` into memory. It returns a handle to the resource.

Loaded resources must be unloaded again using the `FreeResource` ([1476](#)) function.

Errors: On error, 0 is returned.

See also: `FindResource` ([1471](#)), `FreeResource` ([1476](#)), `SizeofResource` ([1548](#)), `LockResource` ([1507](#)), `UnlockResource` ([1567](#)), `FreeResource` ([1476](#))

75.11.214 LockResource

Synopsis: Lock a resource

Declaration: `function LockResource(ResData: TFPResourceHGLOBAL) : Pointer`

Visibility: default

Description: `LockResource` locks a resource previously loaded by `LoadResource` into memory. This means that any attempt to modify the resource will fail while it is locked. The function returns a pointer to the resource location in memory.

The resource can be freed again using the `UnlockResource` (1567) function.

Errors: if the function fails, `Nil` is returned.

See also: `FindResource` (1471), `FreeResource` (1476), `SizeofResource` (1548), `LoadResource` (1506), `UnlockResource` (1567), `FreeResource` (1476)

75.11.215 logicaland(variant,variant):variant

Synopsis: Implement logical/binary `and` operation on variants

Declaration: `operator and(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `and` operation is delegated to the variant manager with operation `opand`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator or(variant, variant): variant` (1339), `operator xor(variant, variant): variant` (1339), `operator not(variant): variant` (1339)

75.11.216 logicalnot(variant):variant

Synopsis: Implement logical/binary `not` operation on variants

Declaration: `operator not(const op: variant) : variant`

Visibility: default

Description: The implementation of the `not` operation is delegated to the variant manager with operation `opnot`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator and(variant, variant): variant` (1339), `operator or(variant, variant): variant` (1339), `operator xor(variant, variant): variant` (1339)

75.11.217 logicalor(variant,variant):variant

Synopsis: Implement logical/binary `or` operation on variants

Declaration: `operator or(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `or` operation is delegated to the variant manager with operation `opor`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `and`(variant, variant): variant ([1339](#)), operator `xor`(variant, variant): variant ([1339](#)), operator `not`(variant): variant ([1339](#))

75.11.218 `logicalxor(variant,variant):variant`

Synopsis: Implement logical/binary `xor` operation on variants

Declaration: `operator xor(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `xor` operation is delegated to the variant manager with operation `opxor`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `or`(variant, variant): variant ([1339](#)), operator `and`(variant, variant): variant ([1339](#)), operator `not`(variant): variant ([1339](#))

75.11.219 `longjmp`

Synopsis: Jump to address.

Declaration: `procedure longjmp(var S: jmp_buf; value: LongInt)`

Visibility: default

Description: `LongJump` jumps to the address in the `envjmp_buf`, and restores the registers that were stored in it at the corresponding `SetJump` ([1539](#)) call. In effect, program flow will continue at the `SetJump` call, which will return `value` instead of 0. If a `value` equal to zero is passed, it will be converted to 1 before passing it on. The call will not return, so it must be used with extreme care. This can be used for error recovery, for instance when a segmentation fault occurred.

For an example, see `SetJump` ([1539](#))

Errors: None.

See also: `SetJump` ([1539](#))

75.11.220 `Low`

Synopsis: Return lowest index of open array or enumerated

Declaration: `function Low(Arg: TypeOrVariable) : TOrdinal`

Visibility: default

Description: The return value of `Low` depends on it's argument:

- 1.If the argument is an ordinal type, `Low` returns the lowest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `Low` returns the lowest possible value of it's index.
- 3.If the argument is an open array identifier in a function or procedure, then `Low` returns the lowest element of the array, which is always zero.

4.If the argument is a set type then it returns the lowest value of the underlying ordinal type.

The return type is always the same type as the type of the argument.

for an example, see High ([1486](#)).

Errors: None.

See also: High ([1486](#)), Ord ([1515](#)), Pred ([1519](#)), Succ ([1555](#))

75.11.221 LowerCase

Synopsis: Return lowercase version of a string.

Declaration: `function LowerCase(const s: shortstring) : shortstring; Overload`
`function LowerCase(c: Char) : Char; Overload`
`function LowerCase(const s: ansistring) : ansistring`
`function LowerCase(const s: UnicodeString) : UnicodeString`
`function LowerCase(c: UnicodeChar) : UnicodeChar`

Visibility: default

Description: `Lowercase` returns the lowercase version of its argument `C`. If its argument is a string, then the complete string is converted to lowercase. The type of the returned value is the same as the type of the argument.

`Lowercase` does not change the number of characters (or bytes) in an `ansistring`.

Errors: None.

See also: `Uppcase` ([1567](#))

Listing: `./examples/refex/ex73.pp`

```

program Example73;

{ Program to demonstrate the Lowercase function. }

var c:char;

begin
  for c:= 'A' to 'Z' do
    write(lowercase(c));
    Writeln;
    Writeln(Lowercase( 'ABCDEFGHIJKLMNOPQRSTUVWXYZ' ));
end.
```

75.11.222 MakeLangID

Synopsis: Create a language ID

Declaration: `function MakeLangID(primary: Word; sub: Word) : Word`

Visibility: default

Description: `MakeLangID` creates a language ID from the `primary` and `sub` language IDs.

75.11.223 MemSize

Synopsis: Return the size of a memory block.

Declaration: `function MemSize(p: pointer) : PtrUInt`

Visibility: default

Description: `MemSize` returns the size of a memory block on the heap.

Errors: Passing an invalid pointer may lead to run-time errors (access violations).

See also: `GetMem` ([1478](#)), `FreeMem` ([1475](#))

75.11.224 MkDir

Synopsis: Create a new directory.

Declaration: `procedure MkDir(const s: shortstring); Overload`
`procedure MkDir(const s: RawByteString); Overload`
`procedure MkDir(const s: unicodestring); Overload`

Visibility: default

Description: `Mkdir` creates a new directory `S`.

For an example, see `Rmdir` ([1529](#)).

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Chdir` ([1440](#)), `Rmdir` ([1529](#))

75.11.225 modulus(variant,variant):variant

Synopsis: Implement `mod` (modulo) operation on variants.

Declaration: `operator mod(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the modulo `Mod` operation is delegated to the variant manager with operation `opModulus`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator div(variant, variant): variant` ([1339](#))

75.11.226 Move

Synopsis: Move data from one location in memory to another

Declaration: `procedure Move(const source; var dest; count: SizeInt)`

Visibility: default

Description: `Move` moves `Count` bytes from `Source` to `Dest`.

Errors: If either `Dest` or `Source` is outside the accessible memory for the process, then a run-time error will be generated.

See also: [Fillword \(1470\)](#), [Fillchar \(1469\)](#)

Listing: ./examples/refex/ex42.pp

Program Example42;

{ Program to demonstrate the Move function. }

Var S1,S2 : **String** [30];

begin

 S1:= 'Hello World !';

 S2:= 'Bye, bye !';

Move (S1,S2,**Sizeof**(S1));

Writeln (S2);

end.

75.11.227 MoveChar0

Synopsis: Move data till first zero character

Declaration: `procedure MoveChar0(const buf1; var buf2; len: SizeInt)`

Visibility: default

Description: `MoveChar0` moves `Count` bytes from `buf1` to `buf2`, and stops moving if a zero character is found.

Errors: No checking is done to see if `Count` stays within the memory allocated to the process.

See also: [Move \(1510\)](#)

Listing: ./examples/refex/ex109.pp

Program Example109;

{ Program to demonstrate the MoveChar0 function. }

Var

 Buf1,Buf2 : **Array**[1..80] **of** char;

 I : longint;

begin

Randomize;

For I:=**low**(buf1) **to** **high**(buf1) **do**

 Buf1[I]:= **chr**(**Random**(16)+**Ord**('A'));

Writeln ('Original buffer');

writeln (Buf1);

 Buf1[**Random**(80)+1]:= #0;

MoveChar0 (Buf1,Buf2,80);

Writeln ('Randomly zero-terminated Buffer');

Writeln (Buf2);

end.

75.11.228 multiply(variant,variant):variant

Synopsis: Implement multiplication (*) operation on variants.

Declaration: `operator *(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the multiplication * operation is delegated to the variant manager with operation `opMultiply`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `/(variant, variant): variant` ([1339](#))

75.11.229 negative(variant):variant

Synopsis: Implement - (unary minus, negation) operation on variants.

Declaration: `operator -(const op: variant) : variant`

Visibility: default

Description: The implementation of the unary minus (-) operation is delegated to the variant manager with operation `varNeg`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `-(variant, variant): variant` ([1339](#))

75.11.230 New

Synopsis: Dynamically allocate memory for variable

Declaration: `procedure &New(var P: Pointer)`
`procedure &New(var P: Pointer; Cons: TProcedure)`

Visibility: default

Description: `New` allocates a new instance of the type pointed to by `P`, and puts the address in `P`. If `P` is an object, then it is possible to specify the name of the constructor with which the instance will be created.

The newly allocated memory is not initialized in any way, and may contain garbage data. It must be cleared with a call to `FillChar` ([1469](#)) or `FillWord` ([1470](#)).

For an example, see `Dispose` ([1454](#)).

Errors: What happens if no more memory is available, depends on the value of the variable `ReturnNilIfGrowHeapfails` ([1421](#)): if the variable is `True` then `Nil` is returned. If the variable is `False`, a run-time error is generated.

See also: `Dispose` ([1454](#)), `Freemem` ([1475](#)), `Getmem` ([1478](#)), `ReturnNilIfGrowHeapfails` ([1421](#))

75.11.231 NtoBE

Synopsis: Convert Native-ordered integer to a Big Endian-ordered integer

Declaration: `function NtoBE(const AValue: SmallInt) : SmallInt`
`function NtoBE(const AValue: Word) : Word`
`function NtoBE(const AValue: LongInt) : LongInt`
`function NtoBE(const AValue: DWord) : DWord`
`function NtoBE(const AValue: Int64) : Int64`
`function NtoBE(const AValue: QWord) : QWord`

Visibility: default

Description: `NtoBE` will rearrange the bytes in a natively-ordered number to the Big-Endian order. That is, for a Little-Endian processor, it will invert the order of the bytes and for a big-endian processor, it will do nothing.

See also: `BEtoN` ([1434](#)), `LEtoN` ([1504](#)), `NtoLE` ([1513](#))

75.11.232 NtoLE

Synopsis: Convert Native-ordered integer to a Little Endian-ordered integer

Declaration: `function NtoLE(const AValue: SmallInt) : SmallInt`
`function NtoLE(const AValue: Word) : Word`
`function NtoLE(const AValue: LongInt) : LongInt`
`function NtoLE(const AValue: DWord) : DWord`
`function NtoLE(const AValue: Int64) : Int64`
`function NtoLE(const AValue: QWord) : QWord`

Visibility: default

Description: `NtoLE` will rearrange the bytes in a natively-ordered number to the little-Endian order. That is, for a Big-Endian processor, it will invert the order of the bytes and for a Little-Endian processor, it will do nothing.

See also: `BEtoN` ([1434](#)), `LEtoN` ([1504](#)), `NtoBE` ([1513](#))

75.11.233 Null

Synopsis: Null variant

Declaration: `function Null : Variant`

Visibility: default

75.11.234 OctStr

Synopsis: Convert integer to a string with octal representation.

Declaration: `function OctStr(Val: LongInt; cnt: Byte) : shortstring`
`function OctStr(Val: Int64; cnt: Byte) : shortstring`
`function OctStr(Val: QWord; cnt: Byte) : shortstring`

Visibility: default

Description: `OctStr` returns a string with the octal representation of `Value`. The string has exactly `cnt` characters.

Errors: None.

See also: Str ([1551](#)), Val ([1570](#)), BinStr ([1434](#)), HexStr ([1485](#))

Listing: ./examples/refex/ex112.pp

```

Program example112;

  { Program to demonstrate the OctStr function }

  Const Value = 45678;

  Var I : longint;

  begin
    For I:=1 to 10 do
      Writeln (OctStr(Value,I));
    For I:=1 to 16 do
      Writeln (OctStr(I,3));
  end.

```

75.11.235 Odd

Synopsis: Is a value odd or even ?

Declaration: `function Odd(l: LongInt) : Boolean`
`function Odd(l: LongWord) : Boolean`
`function Odd(l: Int64) : Boolean`
`function Odd(l: QWord) : Boolean`

Visibility: default

Description: Odd returns True if X is odd, or False otherwise.

Errors: None.

See also: Abs ([1422](#)), Ord ([1515](#))

Listing: ./examples/refex/ex43.pp

```

Program Example43;

  { Program to demonstrate the Odd function. }

  begin
    If Odd(1) Then
      Writeln ('Everything OK with 1 !');
    If Not Odd(2) Then
      Writeln ('Everything OK with 2 !');
  end.

```

75.11.236 Ofs

Synopsis: Return offset of a variable.

Declaration: `function Ofs(var X) : LongInt`

Visibility: default

Description: `Ofs` returns the offset of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always the complete address of the variable, since Free Pascal is a 32/64 bit compiler.

Errors: None.

See also: `DSeg` ([1456](#)), `CSeg` ([1451](#)), `Seg` ([1538](#)), `Ptr` ([1520](#))

Listing: ./examples/refex/ex44.pp

```
Program Example44;

{ Program to demonstrate the Ofs function. }

Var W : Pointer;

begin
  W:= Pointer(Ofs(W)); { W contains its own offset. }
end.
```

75.11.237 Ord

Synopsis: Return ordinal value of an ordinal type.

Declaration: `function Ord(X: TOrdinal) : LongInt`

Visibility: default

Description: `Ord` returns the Ordinal value of a ordinal-type variable X.

Historical note:

Originally, Pascal did not have typecasts and `ord` was a necessary function in order to do certain operations on non-integer ordinal types. With the arrival of typecasting a generic approach became possible, making `ord` mostly obsolete. However `ord` is not considered deprecated and remains in wide use today.

Errors: None.

See also: `Chr` ([1441](#)), `Succ` ([1555](#)), `Pred` ([1519](#)), `High` ([1486](#)), `Low` ([1508](#))

Listing: ./examples/refex/ex45.pp

```
Program Example45;

{ Program to demonstrate the Ord, Pred, Succ functions. }

Type
  TEnum = (Zero, One, Two, Three, Four);

Var
  X : Longint;
  Y : TEnum;

begin
  X:=125;
```

```

Writeln (Ord(X)); { Prints 125 }
X:=Pred(X);
Writeln (Ord(X)); { prints 124 }
Y:= One;
Writeln (Ord(y)); { Prints 1 }
Y:=Succ(Y);
Writeln (Ord(Y)); { Prints 2}
end.

```

75.11.238 Pack

Synopsis: Create packed array from normal array

Declaration: `procedure Pack(const A: UnpackedArrayType; StartIndex: TIndexType;
out Z: PackedArrayType)`

Visibility: default

Description: `Pack` will copy the elements of an unpacked array (A) to a packed array (Z). It will start the copy at the index denoted by `StartIndex`. The type of the index variable `StartIndex` must match the type of the index of A. The elements are always transferred to the beginning of the packed array Z. (i.e. it starts at `Low(Z)`).

Obviously, the type of the elements of the arrays A and Z must match.

See also: `unpack` ([1567](#))

75.11.239 ParamCount

Synopsis: Return number of command-line parameters passed to the program.

Declaration: `function ParamCount : LongInt`

Visibility: default

Description: `Paramcount` returns the number of command-line arguments. If no arguments were given to the running program, 0 is returned.

Errors: None.

See also: `Paramstr` ([1517](#))

Listing: `./examples/refex/ex46.pp`

Program Example46;

```

{ Program to demonstrate the ParamCount and ParamStr functions. }
Var
  I : Longint;

begin
  Writeln (paramstr(0), ' : Got ', ParamCount, ' command-line parameters: ');
  For i:=1 to ParamCount do
    Writeln (ParamStr (i));
end.

```

75.11.240 ParamStr

Synopsis: Return value of a command-line argument.

Declaration: `function ParamStr(L: LongInt) : string`

Visibility: default

Description: `ParamStr` returns the `L`-th command-line argument. `L` must be between 0 and `Paramcount`, these values included. The zeroth argument is the path and file name with which the program was started.

The command-line parameters will be truncated to a length of 255, even though the operating system may support bigger command-lines. The `Objpas` unit (used in `objfpc` or `delphi` mode) defines versions of `ParamStr` which return the full-length command-line arguments, using `ansistrings`.

In the interest of portability, the `ParamStr` function tries to behave the same on all operating systems: like the original `ParamStr` function in Turbo Pascal. This means even on Unix, `paramstr(0)` returns the full path to the program executable. A notable exception is Mac OS X, where the returned value depends on how the application was started. It may be that just the name of the application is returned (in case of a command-line launch), so it is best to avoid using it on that platform.

In general, it's a bad idea to rely on the location of the binary. Often, this goes against best OS practices. Configuration data should (or can) not be stored next to the binary, but on designated locations. What locations these are, is very much operating system dependent. Therefore, `ParamStr(0)` should be used with care.

For an example, see `Paramcount` ([1516](#)).

Errors: None.

See also: `Paramcount` ([1516](#))

75.11.241 Pi

Synopsis: Return the value of PI.

Declaration: `function Pi : ValReal`

Visibility: default

Description: `Pi` returns the value of Pi (3.1415926535897932385).

Errors: None.

See also: `Cos` ([1450](#)), `Sin` ([1547](#))

Listing: `./examples/refex/ex47.pp`

Program `Example47`;

{ Program to demonstrate the Pi function. }

```
begin
  Writeln (Pi);           {3.1415926}
  Writeln (Sin(Pi));
end.
```

75.11.242 PopCnt

Synopsis: Count number of set bits

Declaration: function PopCnt(const AValue: Byte) : Byte
 function PopCnt(const AValue: Word) : Word
 function PopCnt(const AValue: DWord) : DWord
 function PopCnt(const AValue: QWord) : QWord

Visibility: default

Description: PopCnt (population count) counts the number of set bits in AValue.

75.11.243 Pos

Synopsis: Search for substring in a string.

Declaration: function Pos(const substr: shortstring; const s: shortstring;
 Offset: SizeInt) : SizeInt
 function Pos(C: Char; const s: shortstring; Offset: SizeInt) : SizeInt
 function Pos(const Substr: ShortString; const Source: RawByteString;
 Offset: SizeInt) : SizeInt
 function Pos(const substr: shortstring; c: Char; Offset: SizeInt)
 : SizeInt
 function Pos(const Substr: RawByteString; const Source: RawByteString;
 Offset: SizeInt) : SizeInt
 function Pos(c: AnsiChar; const s: RawByteString; Offset: SizeInt)
 : SizeInt
 function Pos(const Substr: UnicodeString; const Source: UnicodeString;
 Offset: SizeInt) : SizeInt
 function Pos(c: Char; const s: UnicodeString; Offset: SizeInt) : SizeInt
 function Pos(c: UnicodeChar; const s: UnicodeString; Offset: SizeInt)
 : SizeInt
 function Pos(const c: RawByteString; const s: UnicodeString;
 Offset: SizeInt) : SizeInt
 function Pos(const c: UnicodeString; const s: RawByteString;
 Offset: SizeInt) : SizeInt
 function Pos(const c: ShortString; const s: UnicodeString;
 Offset: SizeInt) : SizeInt
 function Pos(const Substr: WideString; const Source: WideString;
 Offset: SizeInt) : SizeInt
 function Pos(c: Char; const s: WideString; Offset: SizeInt) : SizeInt
 function Pos(c: WideChar; const s: WideString; Offset: SizeInt)
 : SizeInt
 function Pos(c: WideChar; const s: RawByteString; Offset: SizeInt)
 : SizeInt
 function Pos(const c: RawByteString; const s: WideString;
 Offset: SizeInt) : SizeInt
 function Pos(const c: WideString; const s: RawByteString;
 Offset: SizeInt) : SizeInt
 function Pos(const c: ShortString; const s: WideString; Offset: SizeInt)
 : SizeInt
 function Pos(c: Char; const v: Variant) : SizeInt
 function Pos(s: ShortString; const v: Variant) : SizeInt
 function Pos(const a: AnsiString; const v: Variant) : SizeInt

```

function Pos(const w: WideString; const v: Variant) : SizeInt
function Pos(const w: UnicodeString; const v: Variant) : SizeInt
function Pos(const v: Variant; const c: Char) : SizeInt
function Pos(const v: Variant; const s: ShortString) : SizeInt
function Pos(const v: Variant; const a: AnsiString) : SizeInt
function Pos(const v: Variant; const w: WideString) : SizeInt
function Pos(const v: Variant; const w: UnicodeString) : SizeInt
function Pos(const v1: Variant; const v2: Variant) : SizeInt

```

Visibility: default

Description: Pos returns the index of Substr in S, if S contains Substr. In case Substr isn't found, 0 is returned. The search is case-sensitive.

Errors: None

See also: Length ([1503](#)), Copy ([1449](#)), Delete ([1453](#)), Insert ([1496](#))

Listing: ./examples/refex/ex48.pp

Program Example48;

{ Program to demonstrate the Pos function. }

Var

S : **String**;

begin

S:= 'The first space in this sentence is at position : ';

Writeln (S, pos(' ', S));

S:= 'The last letter of the alphabet doesn't appear in this sentence ';

If (Pos ('Z', S)=0) **and** (Pos ('z', S)=0) **then**

Writeln (S);

end.

75.11.244 power(variant,variant):variant

Synopsis: Implement power (**) operation on variants.

Declaration: operator ******(const op1: variant; const op2: variant) : variant

Visibility: default

Description: The implementation of the power ** operation is delegated to the variant manager with operation opPower.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator *(variant, variant): variant ([1339](#))

75.11.245 Pred

Synopsis: Return previous element for an ordinal type.

Declaration: function **Pred**(X: TOrdinal) : TOrdinal

Visibility: default

Description: `Pred` returns the element that precedes the element that was passed to it. If it is applied to the first value of the ordinal type, and the program was compiled with range checking on (`{ $R+ }`), then a run-time error will be generated.

For an example, see `Ord` (1515)

Errors: Run-time error 201 is generated when the result is out of range.

See also: `Ord` (1515), `Succ` (1555), `High` (1486), `Low` (1508)

75.11.246 Prefetch

Synopsis: Prefetch a memory location

Declaration: `procedure Prefetch(const mem)`

Visibility: default

Description: `Prefetch` can be used to optimize the CPU behaviour by already loading a memory location. It is mainly used as a hint for those processors that support it.

Errors: None.

75.11.247 Ptr

Synopsis: Combine segment and offset to pointer

Declaration: `function Ptr(sel: LongInt; off: LongInt) : FarPointer`

Visibility: default

Description: `Ptr` returns a pointer, pointing to the address specified by segment `Sel` and offset `Off`.

Remark

1. In the 32/64-bit flat-memory model supported by Free Pascal, this function is obsolete.
2. The returned address is simply the offset.

Errors: None.

See also: `Addr` (1424)

Listing: `./examples/refex/ex59.pp`

Program Example59;

{ Program to demonstrate the Ptr (compatibility) function. }

type pString = ^String;

Var P : pString;
S : String;

begin

S := 'Hello , World !';
P := pString(Ptr(Seg(S), Longint(Off(S))));
{ P now points to S ! }
Writeln (P^);

end.

75.11.248 RaiseList

Synopsis: List of currently raised exceptions.

Declaration: `function RaiseList : PExceptObject`

Visibility: default

Description: `RaiseList` returns a pointer to the list of currently raised exceptions (i.e. a pointer to the first exception block).

75.11.249 Random

Synopsis: Generate random number

Declaration: `function Random(l: LongInt) : LongInt`
`function Random(l: Int64) : Int64`
`function Random : extended`

Visibility: default

Description: `Random` returns a random number larger or equal to 0 and strictly less than L. For negative values of L the behaviour is undefined. If the argument L is omitted, a Real number between 0 and 1 is returned (0 included, 1 excluded).

Remark The Free Pascal implementation of the `Random` routine uses a Mersenne Twister algorithm to simulate randomness. This implementation has a better statistical distribution than for example a Linear Congruential generator algorithm, but is considerably slower than the latter. If speed is an issue, then alternate random number generators should be considered.

Note that the fact that a Mersenne Twister is used is an implementation detail, which can be changed at any point. The only guarantee `Random()` offers is that setting `randseed` to particular value will result in the same sequence of random numbers in a particular version the RTL. A newer version of the RTL may result in a different sequence for the same `randseed`.

Errors: None.

See also: [Randomize \(1522\)](#)

Listing: `./examples/refex/ex49.pp`

Program `Example49;`

{ Program to demonstrate the Random and Randomize functions. }

Var `I, Count, guess : Longint;`
`R : Real;`

begin

`Randomize; { This way we generate a new sequence every time`
`the program is run }`

`Count:=0;`

`For i:=1 to 1000 do`

`If Random>0.5 then inc(Count);`

`WriteLn ('Generated ',Count,' numbers > 0.5');`

`WriteLn ('out of 1000 generated numbers.');`

`count:=0;`

`For i:=1 to 5 do`

`begin`

`write ('Guess a number between 1 and 5 : ');`

```

    readln (Guess);
    If Guess=Random(5)+1 then inc(count);
    end;
    Writeln ('You guessed ',Count,' out of 5 correct. ');
end.

```

75.11.250 Randomize

Synopsis: Initialize random number generator

Declaration: `procedure Randomize`

Visibility: default

Description: `Randomize` initializes the random number generator of Free Pascal, by giving a value to `Randseed`, calculated with the system clock.

For an example, see `Random` ([1521](#)).

Errors: None.

See also: `Random` ([1521](#))

75.11.251 Read

Synopsis: Read from a text file into variable

Declaration: `procedure Read(var F: Text; Args: Arguments)`
`procedure Read(Args: Arguments)`

Visibility: default

Description: `Read` reads one or more values from a file `F`, and stores the result in `V1`, `V2`, etc.; If no file `F` is specified, then standard input is read. If `F` is of type `Text`, then the variables `V1`, `V2` etc. must be of type `Char`, `Integer`, `Real`, `String`. If `F` is a typed file, then each of the variables must be of the type specified in the declaration of `F`. Untyped files are not allowed as an argument.

In earlier versions of FPC, it was also allowed to read `Pchar` null-terminated strings, but this has been removed, since there is no buffer checking possible.

Errors: If no data is available, empty values are returned (0 for ordinal values, empty strings for string values)

See also: `Readln` ([1523](#)), `Blockread` ([1435](#)), `Write` ([1574](#)), `Blockwrite` ([1436](#))

Listing: `./examples/refex/ex50.pp`

Program `Example50`;

{ Program to demonstrate the Read(Ln) function. }

```

Var S : String;
    C : Char;
    F : File of char;

```

```

begin
    Assign (F, 'ex50.pp');
    Reset (F);

```

```

C:= 'A';
Writeln ('The characters before the first space in ex50.pp are : ');
While not Eof(f) and (C<>' ') do
  Begin
    Read (F,C);
    Write (C);
  end;
Writeln;
Close (F);
Writeln ('Type some words. An empty line ends the program. ');
repeat
  Readln (S);
until S='';
end.

```

75.11.252 ReadBarrier

Synopsis: Memory Read Barrier

Declaration: `procedure ReadBarrier`

Visibility: default

Description: `ReadBarrier` is a low-level instruction to force a read barrier in the CPU: all memory reads before the instruction will be finished before this instruction, before memory reads after the instruction occur.

See also: `ReadDependencyBarrier` ([1523](#)), `ReadWriteBarrier` ([1524](#)), `WriteBarrier` ([1575](#))

75.11.253 ReadDependencyBarrier

Synopsis: Memory Read Dependency Barrier

Declaration: `procedure ReadDependencyBarrier`

Visibility: default

Description: `ReadDependencyBarrier` is a low-level instruction to force a read barrier in the CPU: all memory reads (loads) depending on previous loads are separate from the ones following the instruction.

See also: `ReadBarrier` ([1523](#)), `ReadWriteBarrier` ([1524](#)), `WriteBarrier` ([1575](#))

75.11.254 ReadLn

Synopsis: Read from a text file into variable and goto next line

Declaration: `procedure ReadLn(var F: Text; Args: Arguments)`
`procedure ReadLn(Args: Arguments)`

Visibility: default

Description: `Read` reads one or more values from a file `F`, and stores the result in `V1`, `V2`, etc. After that it goes to the next line in the file. The end of the line is marked by any of the supported line ending styles, independent of the platform on which the code is running (supported line ending styles are CRLF, LF or CR). The end-of-line marker is not considered part of the line and is ignored.

If no file *F* is specified, then standard input is read. The variables *V1*, *V2* etc. must be of type *Char*, *Integer*, *Real*, *String* or *PChar*.

For an example, see [Read \(1522\)](#).

Errors: If no data is available, empty values are returned (0 for ordinal values, empty strings for string values)

See also: [Read \(1522\)](#), [Blockread \(1435\)](#), [Write \(1574\)](#), [Blockwrite \(1436\)](#)

75.11.255 ReadStr

Synopsis: Read variables from a string

Declaration: `procedure ReadStr(const S: string; Args: Arguments)`

Visibility: default

Description: `ReadStr` behaves like [Read \(1522\)](#), except that it reads its input from the string variable *S* instead of a file. Semantically, the `ReadStr` call is equivalent to writing the string to a file using the `Write` call, and then reading them into the various arguments *Arg* using the `Read` call from the same file:

```
var
  F : Text;
begin
  Rewrite(F);
  Write(F, S);
  Close(F);
  Reset(F);
  Read(F, Args);
  Close(F);
end;
```

Obviously, the `ReadStr` call does not use a temporary file.

`ReadStr` is defined in the ISO Extended Pascal standard. More information on the allowed arguments and the behaviour of the arguments can be found in the description of [Read \(1522\)](#).

See also: [Read \(1522\)](#), [WriteStr \(1576\)](#), [Write \(1574\)](#)

75.11.256 ReadWriteBarrier

Synopsis: Memory read/write barrier

Declaration: `procedure ReadWriteBarrier`

Visibility: default

Description: `ReadWriteBarrier` is a low-level instruction to force a read/write barrier in the CPU: both read (Loads) and write (stores) operations before and after the barrier are separate.

See also: [ReadBarrier \(1523\)](#), [ReadDependencyBarrier \(1523\)](#), [WriteBarrier \(1575\)](#)

75.11.257 Real2Double

Synopsis: Convert Turbo Pascal style real to double.

Declaration: `function Real2Double(r: Real48) : Double`

Visibility: default

Description: The `Real2Double` function converts a Turbo Pascal style real (6 bytes long) to a native Free Pascal double type. It can be used e.g. to read old binary TP files with FPC and convert them to Free Pascal binary files.

Note that the assignment operator has been overloaded so a `Real48` type can be assigned directly to a double or extended.

Errors: None.

Listing: `./examples/refex/ex110.pp`

```

program Example110;

{ Program to demonstrate the Real2Double function. }

Var
  i : integer;
  R : Real48;
  D : Double;
  E : Extended;
  F : File of Real48;

begin
  Assign(F, 'reals.dat');
  Reset(f);
  For i:=1 to 10 do
    begin
      Read(F,R);
      D:=Real2Double(R);
      WriteLn( 'Real ',i, ' : ',D);
      D:=R;
      WriteLn( 'Real (direct to double) ',i, ' : ',D);
      E:=R;
      WriteLn( 'Real (direct to Extended) ',i, ' : ',E);
    end;
  Close(f);
end.
```

75.11.258 ReAllocMem

Synopsis: Re-allocate memory on the heap

Declaration: `function ReAllocMem(var p: pointer; Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAllocMem` resizes the memory pointed to by `P` so it has size `Size`. The value of `P` may change during this operation. The contents of the memory pointed to by `P` (if any) will be copied to the new location, but may be truncated if the newly allocated memory block is smaller in size. If a larger block is allocated, only the used memory is initialized, extra memory will not be zeroed out.

Note that `P` may be `nil`, in that case the behaviour of `ReAllocMem` is equivalent to `Getmem`.

See also: [GetMem \(1478\)](#), [FreeMem \(1475\)](#)

75.11.259 ReAllocMemory

Synopsis: Alias for [ReAllocMem \(1525\)](#)

Declaration: `function ReAllocMemory(p: pointer; Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAllocMemory` is an alias for [ReAllocMem \(1525\)](#).

See also: [ReAllocMem \(1525\)](#)

75.11.260 ReleaseExceptionObject

Synopsis: Decrease the reference count of the current exception object.

Declaration: `procedure ReleaseExceptionObject`

Visibility: default

Description: `ReleaseExceptionObject` decreases the reference count of the current exception object. This should be called whenever a reference to the exception object was obtained via the [AcquireExceptionObject \(1423\)](#) call.

Calling this method is only valid within an except block.

Errors: If there is no current exception object, a run-time error 231 will occur.

See also: [AcquireExceptionObject \(1423\)](#)

75.11.261 Rename

Synopsis: Rename file on disk

Declaration: `procedure Rename(var f: File; const s: ShortString)`
`procedure Rename(var f: File; const p: PAnsiChar)`
`procedure Rename(var f: File; const c: AnsiChar)`
`procedure Rename(var f: File; const s: UnicodeString)`
`procedure Rename(var f: File; const s: RawByteString)`
`procedure Rename(var t: Text; const s: shortstring)`
`procedure Rename(var t: Text; const p: PAnsiChar)`
`procedure Rename(var t: Text; const c: AnsiChar)`
`procedure Rename(var t: Text; const s: unicodestring)`
`procedure Rename(var t: Text; const s: RawByteString)`

Visibility: default

Description: `Rename` changes the name of the assigned file `F` to `S`. `F` must be assigned, but not opened.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: [Erase \(1462\)](#)

Listing: `./examples/refex/ex77.pp`

Program Example77;

```
{ Program to demonstrate the Rename function. }
Var F : Text;

begin
    Assign (F,paramstr(1));
    Rename (F,paramstr(2));
end.
```

75.11.262 Reset

Synopsis: Open file for reading

Declaration: `procedure Reset(var f: File; l: LongInt)`
`procedure Reset(var f: File)`
`procedure Reset(var f: TypedFile)`
`procedure Reset(var t: Text)`

Visibility: default

Description: `Reset` opens a file `F` for reading. `F` can be any file type. If `F` is a text file, or refers to standard I/O (e.g. `”) then it is opened read-only, otherwise it is opened using the mode specified in filemode (1348).`

If `F` is an untyped file, the record size can be specified in the optional parameter `L`. A default value of 128 is used.

File sharing is not taken into account when calling `Reset`.

Note that the path can be only 255 characters long.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Rewrite` (1528), `Assign` (1427), `Close` (1441), `Append` (1425), `FileMode` (1348)

Listing: `./examples/refex/ex51.pp`

Program Example51;

```
{ Program to demonstrate the Reset function. }

Function FileExists (Name : String) : boolean;

Var F : File;

begin
    { $i- }
    Assign (F,Name);
    Reset (F);
    { $!+ }
    FileExists := (IOResult=0) and (Name<>' ');
    if FileExists then
        Close (f);
end;

begin
```

```

If FileExists (Paramstr(1)) then
  Writeln ('File found')
else
  Writeln ('File NOT found');
end.

```

75.11.263 ResumeThread

Synopsis: Resume a suspended thread.

Declaration: `function ResumeThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `ResumeThread` causes a suspended thread (using `SuspendThread` (1556)) to resume its execution. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `SuspendThread` (1556), `KillThread` (1502)

75.11.264 Rewrite

Synopsis: Open file for writing

Declaration: `procedure Rewrite(var f: File; l: LongInt)`
`procedure Rewrite(var f: File)`
`procedure Rewrite(var f: TypedFile)`
`procedure Rewrite(var t: Text)`

Visibility: default

Description: `Rewrite` opens a file `F` for writing. `F` can be any file type. If `F` is an untyped or typed file, then it is opened for reading and writing. If `F` is an untyped file, the record size can be specified in the optional parameter `L`. Default a value of 128 is used. if `Rewrite` finds a file with the same name as `F`, this file is truncated to length 0. If it doesn't find such a file, a new file is created.

Contrary to Turbo Pascal, Free Pascal opens the file with mode `fmoutput`. If it should be opened in `fminout` mode, an extra call to `Reset` (1527) is needed.

File sharing is not taken into account when calling `Rewrite`.

Note that the path can be only 255 characters long.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Reset` (1527), `Assign` (1427), `Close` (1441), `Flush` (1473), `Append` (1425)

Listing: `./examples/refex/ex52.pp`

Program Example52;

{ Program to demonstrate the Rewrite function. }

```

Var F : File;
    l : longint;

```

```

begin
  Assign (F, 'Test.tmp');
  { Create the file. Recordsize is 4 }
  Rewrite (F, Sizeof(l));
  For l:=1 to 10 do
    BlockWrite (F, l, 1);
  close (f);
  { F contains now a binary representation of
    10 longints going from 1 to 10 }
end.

```

75.11.265 rightshift(variant,variant):variant

Synopsis: Implement binary shr operation on variants.

Declaration: `operator shr(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the shr operation is delegated to the variant manager with operation opshiftright.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator shl(variant, variant): variant ([1339](#))

75.11.266 RmDir

Synopsis: Remove directory when empty.

Declaration: `procedure RmDir(const s: shortstring); Overload`
`procedure RmDir(const s: RawByteString); Overload`
`procedure RmDir(const s: unicodestring); Overload`

Visibility: default

Description: Rmdir removes the directory S.

Errors: Depending on the state of the {\$I} switch, a runtime error can be generated if there is an error. In the {\$I-} state, use IOResult to check for errors.

See also: Chdir ([1440](#)), Mkdir ([1510](#))

Listing: ./examples/refex/ex53.pp

Program Example53;

{ Program to demonstrate the Mkdir and Rmdir functions. }

Const D : **String**[8] = 'TEST.DIR';

Var S : **String**;

```

begin
  Writeln ('Making directory ',D);
  Mkdir (D);

```

```

WriteLn ('Changing directory to ',D);
ChDir (D);
GetDir (0,S);
WriteLn ('Current Directory is : ',S);
WRitLn ('Going back');
ChDir ('..');
WriteLn ('Removing directory ',D);
Rmdir (D);
end.

```

75.11.267 RolByte

Synopsis: Rotate bits of a byte value to the left

Declaration: `function RolByte(const AValue: Byte) : Byte`
`function RolByte(const AValue: Byte; const Dist: Byte) : Byte`

Visibility: default

Description: `RolByte` rotates the bits of the byte `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1531](#)), `RolWord` ([1531](#)), `RolDWord` ([1530](#)), `RolQWord` ([1530](#))

75.11.268 RolDWord

Synopsis: Rotate bits of a DWord (cardinal) value to the left

Declaration: `function RolDWord(const AValue: DWord) : DWord`
`function RolDWord(const AValue: DWord; const Dist: Byte) : DWord`

Visibility: default

Description: `RolDWord` rotates the bits of the DWord (cardinal) `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1530](#)), `RolWord` ([1531](#)), `RorDWord` ([1531](#)), `RolQWord` ([1530](#))

75.11.269 RolQWord

Synopsis: Rotate bits of a QWord (64-bit) value to the left

Declaration: `function RolQWord(const AValue: QWord) : QWord`
`function RolQWord(const AValue: QWord; const Dist: Byte) : QWord`

Visibility: default

Description: `RorQWord` rotates the bits of the QWord (64-bit) `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1530](#)), `RolWord` ([1531](#)), `RolDWord` ([1530](#)), `RorQWord` ([1531](#))

75.11.270 RolWord

Synopsis: Rotate bits of a word value to the left

Declaration: `function RolWord(const AValue: Word) : Word`
`function RolWord(const AValue: Word; const Dist: Byte) : Word`

Visibility: default

Description: `RolWord` rotates the bits of the word `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1530](#)), `RorWord` ([1532](#)), `RolDWord` ([1530](#)), `RolQWord` ([1530](#))

75.11.271 RorByte

Synopsis: Rotate bits of a byte value to the right

Declaration: `function RorByte(const AValue: Byte) : Byte`
`function RorByte(const AValue: Byte; const Dist: Byte) : Byte`

Visibility: default

Description: `RorByte` rotates the bits of the byte `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1530](#)), `RorWord` ([1532](#)), `RorDWord` ([1531](#)), `RorQWord` ([1531](#))

75.11.272 RorDWord

Synopsis: Rotate bits of a DWord (cardinal) value to the right

Declaration: `function RorDWord(const AValue: DWord) : DWord`
`function RorDWord(const AValue: DWord; const Dist: Byte) : DWord`

Visibility: default

Description: `RorDWord` rotates the bits of the DWord (cardinal) `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1531](#)), `RolDWord` ([1530](#)), `RorWord` ([1532](#)), `RorQWord` ([1531](#))

75.11.273 RorQWord

Synopsis: Rotate bits of a QWord (64-bit) value to the right

Declaration: `function RorQWord(const AValue: QWord) : QWord`
`function RorQWord(const AValue: QWord; const Dist: Byte) : QWord`

Visibility: default

Description: `RorQWord` rotates the bits of the QWord (64-bit) `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1531](#)), `RorWord` ([1532](#)), `RorDWord` ([1531](#)), `RolQWord` ([1530](#))

75.11.274 RorWord

Synopsis: Rotate bits of a word value to the right

Declaration: `function RorWord(const AValue: Word) : Word`
`function RorWord(const AValue: Word; const Dist: Byte) : Word`

Visibility: default

Description: `RorWord` rotates the bits of the word `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1531](#)), `RolWord` ([1531](#)), `RorDWord` ([1531](#)), `RorQWord` ([1531](#))

75.11.275 Round

Synopsis: Round floating point value to nearest integer number.

Declaration: `function Round(d: ValReal) : Int64`

Visibility: default

Description: `Round` rounds `X` to the closest integer, which may be bigger or smaller than `X`.

In the case of .5, the algorithm uses "banker's rounding": .5 values are always rounded towards the even number.

Errors: None.

See also: `Frac` ([1474](#)), `Int` ([1496](#)), `Trunc` ([1562](#))

Listing: `./examples/refex/ex54.pp`

Program `Example54;`

{ Program to demonstrate the Round function. }

```
begin
  Writeln (Round(1234.56)); { Prints 1235 }
  Writeln (Round(-1234.56)); { Prints -1235 }
  Writeln (Round(12.3456)); { Prints 12 }
  Writeln (Round(-12.3456)); { Prints -12 }
  Writeln (Round(2.5)); { Prints 2 (down) }
  Writeln (Round(3.5)); { Prints 4 (up) }
end.
```

75.11.276 RTLEventCreate

Synopsis: Create a new RTL event

Declaration: `function RTLEventCreate : PRTLEvent`

Visibility: default

Description: `RTLEventCreate` creates and initializes a new RTL event. RTL events are used to notify other threads that a certain condition is met, and to notify other threads of condition changes (conditional variables).

The function returns an initialized RTL event, which must be disposed of with `RTLEventdestroy` ([1533](#))

`RTLEvent` is used mainly for the `synchronize` method.

See also: `RTLEventDestroy` ([1533](#)), `RTLEventSetEvent` ([1533](#)), `RTLEventReSetEvent` ([1533](#)), `RTLEventWaitFor` ([1534](#))

75.11.277 RTLEventDestroy

Synopsis: Destroy a RTL Event

Declaration: `procedure RTLEventDestroy(state: PRTLEvent)`

Visibility: default

Description: `RTLeventdestroy` destroys the RTL event `State`. After a call to `RTLeventdestroy`, the `State` RTL event may no longer be used.

See also: `RTLEventCreate` ([1532](#)), `RTLEventResetEvent` ([1533](#)), `RTLEventSetEvent` ([1533](#))

75.11.278 RTLEventResetEvent

Synopsis: Reset an event

Declaration: `procedure RTLEventResetEvent(state: PRTLEvent)`

Visibility: default

Description: `RTLeventResetEvent` resets the event: this should be used to undo the signaled state of an event. Resetting an event that is not set (or was already reset) has no effect.

See also: `RTLEventCreate` ([1532](#)), `RTLEventDestroy` ([1533](#)), `RTLEventSetEvent` ([1533](#)), `RTLEventWaitFor` ([1534](#))

75.11.279 RTLEventSetEvent

Synopsis: Notify threads of the event.

Declaration: `procedure RTLEventSetEvent(state: PRTLEvent)`

Visibility: default

Description: `RTLeventSetEvent` notifies other threads which are listening, that the event has occurred.

See also: `RTLEventCreate` ([1532](#)), `RTLEventResetEvent` ([1533](#)), `RTLEventDestroy` ([1533](#)), `RTLEventWaitFor` ([1534](#))

75.11.280 RTLEventWaitFor

Synopsis: Wait for an event.

Declaration: `procedure RTLEventWaitFor(state: PRTLEvent)`
`procedure RTLEventWaitFor(state: PRTLEvent; timeout: LongInt)`

Visibility: default

Description: `RTLEventWaitFor` suspends the thread till the event occurs. The event will occur when another thread calls `RTLEventSetEvent` (1533) on `State`.

By default, the thread will be suspended indefinitely. However, if `TimeOut` is specified, then the thread will resume after timeout milliseconds have elapsed.

See also: `RTLEventCreate` (1532), `RTLEventDestroy` (1533), `RTLEventSetEvent` (1533), `RTLEventWaitFor` (1534)

75.11.281 RunError

Synopsis: Generate a run-time error.

Declaration: `procedure RunError(w: Word)`
`procedure RunError`

Visibility: default

Description: `RunError` stops the execution of the program, and generates a run-time error `ErrorCode`.

Errors: None.

See also: `Exit` (1464), `Halt` (1484)

Listing: `./examples/refex/ex55.pp`

Program `Example55`;

{ Program to demonstrate the RunError function. }

begin

{ The program will stop and emit a run-error 106 }

RunError (106);

end.

75.11.282 SafeLoadLibrary

Synopsis: Load a library safely

Declaration: `function SafeLoadLibrary(const Name: RawByteString) : TLibHandle`
`function SafeLoadLibrary(const Name: UnicodeString) : TLibHandle`

Visibility: default

Description: `SafeLoadLibrary` calls `LoadLibrary` (1506) but restores the current FPU control word and exception mask to their current value after the library was loaded, thus preventing the loaded library initialization code from modifying their current values.

See also: `LoadLibrary` (1506)

75.11.283 SarInt64

Synopsis: 64-bit Shift Arithmetic Right

Declaration: `function SarInt64(const AValue: Int64) : Int64`
`function SarInt64(const AValue: Int64; Shift: Byte) : Int64`

Visibility: default

Description: `SarInt64` performs an arithmetic right shift for `Shift` positions on a 64-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarShortInt` ([1535](#)), `SarSmallInt` ([1535](#)), `SarLongInt` ([1535](#))

75.11.284 SarLongint

Synopsis: 32-bit Shift Arithmetic Right

Declaration: `function SarLongint(const AValue: LongInt; const Shift: Byte) : LongInt`

Visibility: default

Description: `SarLongint` performs an arithmetic right shift for `Shift` positions on a 32-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarShortInt` ([1535](#)), `SarSmallInt` ([1535](#)), `SarInt64` ([1535](#))

75.11.285 SarShortint

Synopsis: 8-bit Shift Arithmetic Right

Declaration: `function SarShortint(const AValue: ShortInt; const Shift: Byte)`
`: ShortInt`

Visibility: default

Description: `SarShortint` performs an arithmetic right shift for `Shift` positions on an 8-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarSmallint` ([1535](#)), `SarLongint` ([1535](#)), `SarInt64` ([1535](#))

75.11.286 SarSmallint

Synopsis: 16-bit Shift Arithmetic Right

Declaration: `function SarSmallint(const AValue: SmallInt; const Shift: Byte)`
`: SmallInt`

Visibility: default

Description: `SarSmallint` performs an arithmetic right shift for `Shift` positions on an 16-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarShortint` ([1535](#)), `SarLongint` ([1535](#)), `SarInt64` ([1535](#))

75.11.287 Seek

Synopsis: Set file position

Declaration: `procedure Seek (var f: File; Pos: Int64)`

Visibility: default

Description: `Seek` sets the file-pointer for file `F` to record `Nr`. `Count`. The first record in a file has `Count=0`. `F` can be any file type, except `Text`. If `F` is an untyped file, with no record size specified in `Reset` (1527) or `Rewrite` (1528), 128 is assumed.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Eof` (1460), `SeekEof` (1536), `SeekEoln` (1537)

Listing: `./examples/refex/ex56.pp`

Program `Example56`;

```
{ Program to demonstrate the Seek function. }

Var
  F : File;
  I, J : longint;

begin
  { Create a file and fill it with data }
  Assign (F, 'test.tmp');
  Rewrite(F); { Create file }
  Close(f);
  FileMode:=2;
  ReSet (F, Sizeof(i)); { Opened read/write }
  For I:=0 to 10 do
    BlockWrite (F, I, 1);
  { Go Back to the beginning of the file }
  Seek(F, 0);
  For I:=0 to 10 do
    begin
      BlockRead (F, J, 1);
      If J<>I then
        Writeln ('Error: expected ', i, ', got ', j);
    end;
  Close (f);
end.
```

75.11.288 SeekEOF

Synopsis: Set file position to end of file

Declaration: `function SeekEOF (var t: Text) : Boolean`
`function SeekEOF : Boolean`

Visibility: default

Description: `SeekEof` returns `True` if the file-pointer is at the end of the file. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-file marker is reached.

If the end-of-file marker is reached, `True` is returned. Otherwise, `False` is returned.

If the parameter `F` is omitted, standard `Input` is assumed.

Remark The `SeekEOF` function can only be used on real textfiles: when assigning the file to other kinds of (virtual) text files, the function may fail, although it will perform a number of tests to guard against wrong usage.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1460](#)), `SeekEoln` ([1537](#)), `Seek` ([1536](#))

Listing: `./examples/refex/ex57.pp`

Program `Example57`;

```
{ Program to demonstrate the SeekEof function. }
Var C : Char;

begin
  { this will print all characters from standard input except
    Whitespace characters. }
  While Not SeekEof do
    begin
      Read (C);
      Write (C);
    end;
end.
```

75.11.289 SeekEOLn

Synopsis: Set file position to end of line

Declaration: `function SeekEOLn(var t: Text) : Boolean`
`function SeekEOLn : Boolean`

Visibility: `default`

Description: `SeekEoln` returns `True` if the file-pointer is at the end of the current line. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-line marker is reached. If the end-of-line marker is reached, `True` is returned. Otherwise, `False` is returned. The end-of-line marker is defined as `#10`, the `LineFeed` character. If the parameter `F` is omitted, standard `Input` is assumed.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1460](#)), `SeekEof` ([1536](#)), `Seek` ([1536](#))

Listing: `./examples/refex/ex58.pp`

Program `Example58`;

```
{ Program to demonstrate the SeekEoln function. }
Var
  C : Char;

begin
  { This will read the first line of standard output and print
    all characters except whitespace. }
```

```

While not SeekEoln do
  Begin
    Read (c);
    Write (c);
  end;
end.

```

75.11.290 Seg

Synopsis: Return segment

Declaration: `function Seg(var X) : LongInt`

Visibility: default

Description: `Seg` returns the segment of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always 0, since Free Pascal uses a flat 32/64 bit memory model. In such a memory model segments have no meaning.

Errors: None.

See also: `DSeg` ([1456](#)), `CSeg` ([1451](#)), `Ofs` ([1514](#)), `Ptr` ([1520](#))

Listing: `./examples/refex/ex60.pp`

Program `Example60`;

```

{ Program to demonstrate the Seg function. }
Var
  W : Word;

begin
  W:=Seg(W); { W contains its own Segment}
end.

```

75.11.291 Set8087CW

Declaration: `procedure Set8087CW(cw: Word)`

Visibility: default

75.11.292 SetCodePage

Synopsis: Set the codepage of a string

Declaration: `procedure SetCodePage(var s: RawByteString; CodePage: TSystemCodePage; Convert: Boolean)`

Visibility: default

Description: `SetCodePage` sets the codepage of a string `S` to `CodePage`. If `Convert` is `True` then the string will be transcoded to the new codepage. The resulting string will have reference count 1.

See also: `StringCodePage` ([1552](#))

75.11.293 SetDynLibsManager

Synopsis: Set a new handler for dynamic library support

Declaration: `procedure SetDynLibsManager(const &New: TDynLibsManager)`
`procedure SetDynLibsManager(const &New: TDynLibsManager;`
`var Old: TDynLibsManager)`

Visibility: default

Description: `SetDynLibsManager` sets the handler for dynamic library support to `New`. Optionally, it returns the currently active handler in `Old`.

This is the routine used by the `#rtl.dynlibs` (716) unit to set the default handler.

See also: `#rtl.dynlibs` (716), `GetDynLibsManager` (1477)

75.11.294 Setjmp

Synopsis: Save current execution point.

Declaration: `function Setjmp(var S: jmp_buf) : LongInt`

Visibility: default

Description: `SetJmp` fills `env` with the necessary data for a jump back to the point where it was called. It returns zero if called in this way. If the function returns nonzero, then it means that a call to `LongJump` (1508) with `env` as an argument was made somewhere in the program.

Errors: None.

See also: `LongJump` (1508)

Listing: `./examples/refex/ex79.pp`

```

program example79;

{ Program to demonstrate the setjmp, longjmp functions }

procedure dojmp(var env : jmp_buf; value : longint);

begin
    value:=2;
    Writeln ('Going to jump !');
    { This will return to the setjmp call,
      and return value instead of 0 }
    longjmp(env,value);
end;

var env : jmp_buf;

begin
    if setjmp(env)=0 then
        begin
            writeln ('Passed first time. ');
            dojmp(env,2);
        end
    else
        writeln ('Passed second time. ');
    end.

```

75.11.295 SetLength

Synopsis: Set length of a string or dynamic array.

Declaration: `procedure &SetLength(var S: AStringType; Len: SizeInt)`
`procedure &SetLength(var A: DynArrayType; Len: SizeInt)`

Visibility: default

Description: `SetLength` for strings sets the length of the string `S` to `Len`. `S` can be an ansistring, a short string or a widestring. For `ShortStrings`, `Len` can maximally be 255. For `AnsiStrings` it can have any value. For `AnsiString` strings, `SetLength` **must** be used to set the length of the string.

In the case of a dynamic array `A`, `SetLength` sets the number of elements. The elements are numbered from index 0, so the count runs from 0 to `Len-1`. If Zero is specified, the array is cleared and removed from memory.

In case the length is set to a smaller length than the current one, the elements 0-(`Len-1`) (or characters 1-`Len` in case of a string) are kept. The elements that fall outside the new length are finalized if the array element is a managed type.

In case the length is set to a larger length than the current one, the new elements are zeroed out for a dynamic array. For a string, the string is zero-terminated at the correct length.

Note that `SetLength` is governed by the Copy-On-Write principle for strings and dynamic arrays: the reference count after a call to `SetLength` will be 1 (except when the length is zero, then the array is removed from memory).

For multi-dimensional arrays, `SetLength` can be used to specify all dimensions at once:

```
Var
  arr : Array of Array of Integer;

begin
  SetLength(arr, 10, 20);
end;
```

This will create a dynamic array with 10 elements, where each element in itself is a dynamic array of 20 elements. `SetLength` will of course always create "rectangular" arrays: all elements will have the same size.

```
Var
  arr : Array of Integer;

begin
  SetLength(arr, 0);
end;
```

After this, `arr` is `Nil`.

Errors: None.

See also: `Length` ([1503](#))

Listing: `./examples/refex/ex85.pp`

Program `Example85;`

```
{ Program to demonstrate the SetLength function. }
```

```

Var S : String;

begin
  Setlength(S,100);
  FillChar(S[1],100,#32);
  WriteLn ('"',S,'"');
end.

```

75.11.296 SetMemoryManager

Synopsis: Set a memory manager

Declaration: `procedure SetMemoryManager(const MemMgr: TMemoryManager)`

Visibility: default

Description: `SetMemoryManager` sets the current memory manager record to `MemMgr`.

For an example, see the programmer's guide.

Errors: None.

See also: `GetMemoryManager` ([1479](#)), `IsMemoryManagerSet` ([1502](#))

75.11.297 SetMultiByteConversionCodePage

Synopsis: Set codepage for conversions from multi-byte strings to single-byte strings

Declaration: `procedure SetMultiByteConversionCodePage(CodePage: TSystemCodePage)`

Visibility: default

Description: `SetMultiByteConversionCodePage` sets `DefaultSystemCodePage` ([1419](#)) to `CodePage`.

The effect of this change is that the default codepage used to translate multi-byte (UTF-16) strings to single-byte codepage-aware strings changes, and code page conversions will be done to the new codepage.

Do not set `DefaultSystemCodePage` directly, as additional actions may need to be done when changing the code page.

When the `DefaultSystemCodePage` ([1419](#)) changes and you use the `TEncoding` classes, you must call `TEncoding.FreeEncodings` ([1838](#)) to regenerate the default encoding using the new code page.

See also: `DefaultSystemCodePage` ([1419](#)), `SetMultiByteFileSystemCodePage` ([1541](#)), `SetMultiByteRTLFileSystemCodePage` ([1542](#))

75.11.298 SetMultiByteFileSystemCodePage

Synopsis: Set codepage used when passing strings to OS single-byte file system APIs

Declaration: `procedure SetMultiByteFileSystemCodePage(CodePage: TSystemCodePage)`

Visibility: default

Description: `SetMultiByteFileSystemCodePage` sets the codepage used in single-byte OS file system APIs to `CodePage`. The effect of this change is that the default codepage used to translate multi-

byte (UTF-16) strings to single-byte codepage-aware strings used in File system APIs changes, and strings passed to the codepage-aware file system APIs will be passed using the new codepage.

This constant is not used if the file system API of the OS is multi-byte (such as on Windows).

Do not set `DefaultFileSystemCodePage` directly, as additional actions may need to be done when changing the code page.

See also: `DefaultFileSystemCodePage` ([1418](#)), `SetMultiByteConversionCodePage` ([1541](#)), `SetMultiByteRTL-FileSystemCodePage` ([1542](#))

75.11.299 SetMultiByteRTLFileSystemCodePage

Synopsis: Set codepage used when interpreting strings from OS single-byte file system APIs

Declaration: `procedure SetMultiByteRTLFileSystemCodePage(CodePage: TSystemCodePage)`

Visibility: default

Description: `SetMultiByteRTLFileSystemCodePage` sets the codepage used to interpreted strings returned by single-byte OS file system APIs to `CodePage`.

The effect of this change is that the default codepage used to translate single byte strings obtained from the OS to single-byte codepage-aware strings or multi-byte strings changes, and strings obtained from the codepage-aware file system APIs will be interpreted using the new codepage.

his constant is not used if the file system API of the OS is multi-byte (such as on Windows).

Do not set `DefaultRTLFileSystemCodePage` directly, as additional actions may need to be done when changing the code page.

See also: `SetMultiByteFileSystemCodePage` ([1541](#)), `SetMultiByteConversionCodePage` ([1541](#)), `SetMultiByteRTL-FileSystemCodePage` ([1542](#))

75.11.300 SetMXCSR

Declaration: `procedure SetMXCSR(w: DWord)`

Visibility: default

75.11.301 SetResourceManager

Synopsis: Set the resource manager

Declaration: `procedure SetResourceManager(const &New: TResourceManager)`

Visibility: default

Description: `SetResourceManager` sets the active resource manager to `Manager`. After a call to `SetResourceManager`, the functions in the `Manager` record will be used to handle resources.

Note that it is not supported to change resource managers on-the-fly: any resources or information about resources obtained should be discarded prior to a call to `SetResourceManager`. Typically, `SetResourceManager` should be called once, at program startup.

Errors: None.

See also: `TResourceManager` ([1399](#)), `GetResourceManager` ([1480](#))

75.11.302 SetSSECSR

Declaration: `procedure SetSSECSR(w: DWord)`

Visibility: default

75.11.303 SetString

Synopsis: Set length of a string and copy buffer.

Declaration: `procedure SetString(out S: AnsiString; Buf: PAnsiChar; Len: SizeInt)`
`procedure SetString(out S: AnsiString; Buf: PWideChar; Len: SizeInt)`
`procedure SetString(out S: Shortstring; Buf: PChar; Len: SizeInt)`
`procedure SetString(out S: UnicodeString; Buf: PUnicodeChar;`
`Len: SizeInt)`
`procedure SetString(out S: UnicodeString; Buf: PChar; Len: SizeInt)`
`procedure SetString(out S: WideString; Buf: PWideChar; Len: SizeInt)`
`procedure SetString(out S: WideString; Buf: PChar; Len: SizeInt)`

Visibility: default

Description: `SetString` sets the length of the string `S` to `Len` and if `Buf` is non-nil, copies `Len` characters from `Buf` into `S`. `S` can be an ansistring, a short string or a widestring. For `ShortStrings`, `Len` can maximally be 255.

Errors: None.

See also: `SetLength` ([1540](#))

75.11.304 SetTextBuf

Synopsis: Set size of text file internal buffer

Declaration: `procedure SetTextBuf(var f: Text; var Buf)`
`procedure SetTextBuf(var f: Text; var Buf; Size: SizeInt)`

Visibility: default

Description: `SetTextBuf` assigns an I/O buffer to a text file. The new buffer is located at `Buf` and is `Size` bytes long. If `Size` is omitted, then `SizeOf (Buf)` is assumed. The standard buffer of any text file is 128 bytes long. For heavy I/O operations this may prove too slow. The `SetTextBuf` procedure allows to set a bigger buffer for the I/O of the application, thus reducing the number of system calls, and thus reducing the load on the system resources. The maximum size of the newly assigned buffer is 65355 bytes.

Remark

- Never assign a new buffer to an opened file. A new buffer can be assigned immediately after a call to `Rewrite` ([1528](#)), `Reset` ([1527](#)) or `Append`, but not after the file was read from/written to. This may cause loss of data. If a new buffer must be assigned after read/write operations have been performed, the file should be flushed first. This will ensure that the current buffer is emptied.
- Take care that the assigned buffer is always valid. If a local variable is assigned as a buffer, then after the program exits the local program block, the buffer will no longer be valid, and stack problems may occur.

Errors: No checking on `Size` is done.

See also: `Assign` ([1427](#)), `Reset` ([1527](#)), `Rewrite` ([1528](#)), `Append` ([1425](#))

Listing: `./examples/refex/ex61.pp`

Program Example61;

{ Program to demonstrate the SetTextBuf function. }

Var

Fin, Fout : Text;
Ch : Char;
Bufin, Bufout : **Array**[1..10000] **of** byte;

begin

Assign (Fin, **paramstr**(1));
Reset (Fin);
Assign (Fout, **paramstr**(2));
Rewrite (Fout);
{ This is harmless before IO has begun }
{ Try this program again on a big file ,
after commenting out the following 2
lines and recompiling it. }
SetTextBuf (Fin, Bufin);
SetTextBuf (Fout, Bufout);
While not eof(Fin) **do**
 begin
 Read (Fin, ch);
 write (Fout, ch);
 end;
 Close (Fin);
 Close (Fout);

end.

75.11.305 SetTextCodePage

Synopsis: Set the codepage used in a text file.

Declaration: `procedure SetTextCodePage(var T: Text; CodePage: TSystemCodePage)`

Visibility: default

Description: `SetTextCodePage` sets the codepage that the text file T uses. All strings written to the file will be converted to the indicated codepage. By default, the codepage is set to CP_ACP.

Errors: None.

See also: `TextRec` ([1392](#)), `SetTextCodePage` ([1480](#))

75.11.306 SetTextLineEnding

Synopsis: Set the end-of-line character for the given text file.

Declaration: `procedure SetTextLineEnding(var f: Text; Ending: string)`

Visibility: default

Description: `SetTextLineEnding` sets the end-of-line character for the text file F to Ending. By default, this is the string indicated by `DefaultTextLineBreakStyle` ([1347](#)).

Errors: None.

See also: `DefaultTextLineBreakStyle` ([1347](#)), `TTextLineBreakStyle` ([1403](#))

75.11.307 SetThreadDebugName

Synopsis: Set the debug name for a thread.

Declaration:

```
procedure SetThreadDebugName(threadHandle: TThreadID;
                             const ThreadName: AnsiString)
procedure SetThreadDebugName(threadHandle: TThreadID;
                             const ThreadName: UnicodeString)
```

Visibility: default

Description: `SetThreadDebugName` can be used to set the name of a thread in a debugging context. A debugger can use this information to show the name instead of the thread ID, thus making debugging easier. The current platform's `TThreadManager` (1404) implementation must support this call.

Errors: This call does nothing on platforms that do not support threading.

See also: `GetCurrentThreadID` (1477), `TThreadManager` (1404)

75.11.308 SetThreadManager

Synopsis: Set the thread manager, optionally return the current thread manager.

Declaration:

```
function SetThreadManager(const NewTM: TThreadManager;
                          var OldTM: TThreadManager) : Boolean
function SetThreadManager(const NewTM: TThreadManager) : Boolean
```

Visibility: default

Description: `SetThreadManager` sets the thread manager to `NewTM`. If `OldTM` is given, `SetThreadManager` uses it to return the previously used thread manager.

The function returns `True` if the threadmanager was set successfully, `False` if an error occurred.

For more information about thread programming, see the programmer's guide.

Errors: If an error occurred cleaning up the previous manager, or an error occurred initializing the new manager, `False` is returned.

See also: `GetThreadManager` (1481), `TThreadManager` (1404)

75.11.309 SetUnicodeStringManager

Synopsis: Set the unicodestring manager

Declaration:

```
procedure SetUnicodeStringManager(const &New: TUnicodeStringManager)
procedure SetUnicodeStringManager(const &New: TUnicodeStringManager;
                                  var Old: TUnicodeStringManager)
```

Visibility: default

Description: `SetUnicodeStringManager` sets the current unicodestring manager to `New`. Optionally, it returns the currently active widestring manager in `Old`.

UnicodeStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a UnicodeString manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom unicodestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `TUnicodeStringManager` ([1407](#))

75.11.310 SetVariantManager

Synopsis: Set the current variant manager.

Declaration: `procedure SetVariantManager(const VarMgr: tvariantmanager)`

Visibility: default

Description: `SetVariantManager` sets the variant manager to `varmgr`.

See also: `GetVariantManager` ([1482](#))

75.11.311 SetWideStringManager

Synopsis: Set the widestring manager

Declaration: `procedure SetWideStringManager(const &New: TUnicodeStringManager)`
`procedure SetWideStringManager(const &New: TUnicodeStringManager;`
`var Old: TUnicodeStringManager)`

Visibility: default

Description: `SetWideStringManager` sets the current widestring manager to `New`. Optionally, it returns the currently active widestring manager in `Old`.

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `WideString` manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `TWideStringManager` ([1416](#))

75.11.312 ShortCompareText

Synopsis: Compare 2 shortstrings

Declaration: `function ShortCompareText(const S1: shortstring; const S2: shortstring)`
`: SizeInt`

Visibility: default

Description: `ShortCompareText` compares two shortstrings, `S1` and `S2`, and returns the following result:

`<0` if `S1 < S2`.

`0` if `S1 = S2`.

`>0` if `S1 > S2`.

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: `CompareText` ([1670](#))

75.11.313 Sin

Synopsis: Calculate sine of angle

Declaration: `function Sin(d: ValReal) : ValReal`

Visibility: default

Description: `Sin` returns the sine of its argument `X`, where `X` is an angle in radians. If the absolute value of the argument is larger than 2^{63} , then the result is undefined.

Errors: None.

See also: `Cos` ([1450](#)), `Pi` ([1517](#)), `Exp` ([1466](#)), `Ln` ([1505](#))

Listing: `./examples/refex/ex62.pp`

Program `Example62;`

```
{ Program to demonstrate the Sin function. }

begin
  WriteLn (Sin(Pi):0:1); { Prints 0.0 }
  WriteLn (Sin(Pi/2):0:1); { Prints 1.0 }
end.
```

75.11.314 SizeOf

Synopsis: Return size (in bytes) of a variable or type.

Declaration: `function SizeOf(X: TAnyType) : LongInt`

Visibility: default

Description: `SizeOf` returns the size, in bytes, of any variable or type-identifier.

Remark This isn't really a RTL function. Its result is calculated at compile-time, and hard-coded in the executable.

Errors: None.

See also: `Addr` ([1424](#)), `BitSizeOf` ([1339](#))

Listing: `./examples/refex/ex63.pp`

Program `Example63;`

```
{ Program to demonstrate the SizeOf function. }
Var
  I : Longint;
  S : String [10];

begin
  WriteLn (SizeOf(I)); { Prints 4 }
  WriteLn (SizeOf(S)); { Prints 11 }
end.
```

75.11.315 SizeofResource

Synopsis: Return the size of a particular resource

Declaration: `function SizeofResource (ModuleHandle: TFPResourceHMODULE;
ResHandle: TFPResourceHandle) : LongWord`

Visibility: default

Description: `SizeOfResource` returns the size of the resource identified by `ResHandle` in module identified by `ModuleHandle`. `ResHandle` should be obtained from a call to `LoadResource` ([1506](#))

Errors: In case of an error, 0 is returned.

See also: `FindResource` ([1471](#)), `FreeResource` ([1476](#)), `LoadResource` ([1506](#)), `LockResource` ([1507](#)), `UnlockResource` ([1567](#)), `FreeResource` ([1476](#))

75.11.316 Slice

Synopsis: Return part of an array

Declaration: `function Slice (const A: ArrayType; ACount: Integer) : ArrayType2`

Visibility: default

Description: `Slice` returns the first `ACount` elements from the array `A`. It returns an array with the same element type as `A`, but this array is not assignment compatible to any other array, and can therefor only be used in open array arguments to functions.

See also: `Length` ([1503](#)), `SetLength` ([1540](#))

Listing: `./examples/refex/ex113.pp`

Program `Example113;`

{ Program to demonstrate the Slice function. }

procedure `ShowArray (const A: array of Integer);`

var

`I: Integer;`

begin

`for I := Low(A) to High(A) do`

`WriteLn (I, ' : ', A[I]);`

end;

begin

`ShowArray (Slice ([1,2,3,4],2));`

end.

75.11.317 Space

Synopsis: Return a string of spaces

Declaration: `function Space (b: Byte) : shortstring`

Visibility: default

Description: `Space` returns a shortstring with length `B`, consisting of spaces.

See also: `StringOfChar` ([1553](#))

75.11.318 SPtr

Synopsis: Return current stack pointer

Declaration: `function SPtr : Pointer`

Visibility: default

Description: `Sptr` returns the current stack pointer.

Errors: None.

See also: `SSeg` ([1550](#))

Listing: `./examples/refex/ex64.pp`

```

program Example64;

  { Program to demonstrate the sptr function. }

  var p: ptnuint;

  begin
    p:=ofs(stackbottom); { P Contains now the current stack position. }
  end.

```

75.11.319 Sqr

Synopsis: Calculate the square of a value.

Declaration: `function Sqr(l: LongInt) : LongInt`
`function Sqr(l: Int64) : Int64`
`function Sqr(l: QWord) : QWord`
`function Sqr(d: ValReal) : ValReal`

Visibility: default

Description: `Sqr` returns the square of its argument X.

Errors: None.

See also: `Sqrt` ([1550](#)), `Ln` ([1505](#)), `Exp` ([1466](#))

Listing: `./examples/refex/ex65.pp`

```

Program Example65;

  { Program to demonstrate the Sqr function. }
  Var i : Integer;

  begin
    For i:=1 to 10 do
      writeln (Sqr(i):3);
  end.

```

75.11.320 Sqrt

Synopsis: Calculate the square root of a value

Declaration: `function Sqrt (d: ValReal) : ValReal`

Visibility: default

Description: `Sqrt` returns the square root of its argument `X`, which must be positive.

Errors: If `X` is negative, then a run-time error is generated.

See also: `Sqr` ([1549](#)), `Ln` ([1505](#)), `Exp` ([1466](#))

Listing: `./examples/refex/ex66.pp`

Program `Example66;`

{ Program to demonstrate the Sqrt function. }

```
begin
  WriteLn (Sqrt(4):0:3); { Prints 2.000 }
  WriteLn (Sqrt(2):0:3); { Prints 1.414 }
end.
```

75.11.321 SSeg

Synopsis: Return stack segment register value.

Declaration: `function SSeg : Word`

Visibility: default

Description: `SSeg` returns the Stack Segment. This function is only supported for compatibility reasons, as `Sptr` returns the correct contents of the stackpointer.

Errors: None.

See also: `Sptr` ([1549](#))

Listing: `./examples/refex/ex67.pp`

Program `Example67;`

{ Program to demonstrate the SSeg function. }

Var `W : Longint;`

```
begin
  W:=SSeg;
end.
```

75.11.322 StackTop

Synopsis: Top location of the stack.

Declaration: `function StackTop : Pointer`

Visibility: default

Description: `StackTop` contains the top of the stack for the current process. It is used to check the heap on some operating systems, and is set by the system unit initialization code. Do not use or modify this value.

See also: `StackBottom` ([1421](#)), `StackLength` ([1421](#))

75.11.323 Str

Synopsis: Convert a numerical or enumeration value to a string.

Declaration: `procedure Str(var X: TNumericType; var S: string)`

Visibility: default

Description: `Str` returns a string which represents the value of `X`. `X` can be any numerical or enumerated type. The actual declaration of `Str` is not according to pascal syntax, and should be

```
procedure Str(const X: TNumericType[:NumPlaces[:Decimals]];var S: String)
```

Where the optional `NumPlaces` and `Decimals` specifiers control the formatting of the string: `NumPlaces` gives the total width of the string, and `Decimals` the number of decimals after the decimal separator char.

`Str` can also be used to convert an enumerated type value to a string representation of the declared enumeration value. That means that the following will work:

```
Type
  TMyEnum = (One,Two);

Var
  S : String;
begin
  Str(One,S);
  Writeln(S);
end.
```

This will write `One` on the screen, which is consistent with the following - equivalent - program:

```
Type
  TMyEnum = (One,Two);

Var
  S : String;
  E : TMyEnum;
begin
  E:=One;
  Str(E,S);
  Writeln(S);
end.
```

For scoped enumerated types, only the value is written, which means the following program will have the same output:

75.11.325 StringElementSize

Synopsis: Get the character size of a string.

Declaration: `function StringElementSize(const S: RawByteString) : Word; Overload`
`function StringElementSize(const S: UnicodeString) : Word; Overload`

Visibility: default

Description: `StringCodePage` returns the character size of a string (S), regardless of the string type. It accesses the internal structures of the string to retrieve this information. For an empty string, `SizeOf(AnsiChar)` (normally 1) is returned.

See also: `StringCodePage` ([1552](#)), `StringRefCount` ([1553](#))

75.11.326 StringOfChar

Synopsis: Return a string consisting of 1 character repeated N times.

Declaration: `function StringOfChar(c: AnsiChar; l: SizeInt) : AnsiString`
`function StringOfChar(c: UnicodeChar; l: SizeInt) : UnicodeString`

Visibility: default

Description: `StringOfChar` creates a new String of length l and fills it with the character c.
 It is equivalent to the following calls:

```
SetLength(StringOfChar, l);
FillChar(Pointer(StringOfChar)^, Length(StringOfChar), c);
```

Errors: None.

See also: `SetLength` ([1540](#))

Listing: ./examples/refex/ex97.pp

Program Example97;

```
{ $H+ }

{ Program to demonstrate the StringOfChar function. }

Var S : String;

begin
  S:=StringOfChar(' ',40)+'Aligned at column 41.';
  Writeln(s);
end.
```

75.11.327 StringRefCount

Synopsis: Get the reference count of a string

Declaration: `function StringRefCount(const S: RawByteString) : SizeInt; Overload`
`function StringRefCount(const S: UnicodeString) : SizeInt; Overload`

Visibility: default

Description: `StringRefCount` returns the reference count of a string (`S`), regardless of the string type. It accesses the internal structures of the string to retrieve this information. For an empty string, 0 is returned.

See also: `StringCodePage` ([1552](#)), `StringElementSize` ([1553](#))

75.11.328 StringToPPChar

Synopsis: Split string in list of null-terminated strings

Declaration: `function StringToPPChar(var S: AnsiString; ReserveEntries: Integer) : PPChar`
`function StringToPPChar(S: PChar; ReserveEntries: Integer) : PPChar`

Visibility: default

Description: `StringToPPChar` splits the string `S` in words, replacing any whitespace with zero characters. It returns a pointer to an array of pchars that point to the first letters of the words in `S`. This array is terminated by a `Nil` pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of `PChar`; The caller is responsible for freeing this memory.

This function is only available on certain platforms.

Errors: None.

See also: `ArrayStringToPPchar` ([1426](#))

75.11.329 StringToUnicodeChar

Synopsis: Convert an ansistring to a null-terminated array of Unicode characters.

Declaration: `function StringToUnicodeChar(const Src: RawByteString; Dest: PUnicodeChar; DestSize: SizeInt) : PUnicodeChar`

Visibility: default

Description: `StringToUnicodeChar` converts the ansistring `S` to a unicodestring and places the result in `Dest`. The size of the memory location pointed to by `Dest` must be given in `DestSize`. If the result string is longer than the available size, the result string will be truncated.

The function always returns `Dest`.

Errors: No check is performed to see whether `Dest` points to a valid memory location.

See also: `UnicodeCharToString` ([1565](#)), `UnicodeCharLenToString` ([1564](#))

75.11.330 StringToWideChar

Synopsis: Convert a string to an array of widechars.

Declaration: `function StringToWideChar(const Src: RawByteString; Dest: PWideChar; DestSize: SizeInt) : PWideChar`

Visibility: default

Description: `StringToWideChar` converts a single-byte-character string `Src` to a null-terminated array of `WideChars`. The destination for this array is pointed to by `Dest`, and contains room for at least `DestSize` widechars.

Errors: No validity checking is performed on `Dest`.

See also: `WideCharToString` ([1573](#)), `WideCharToStrVar` ([1573](#)), `WideCharLenToStrVar` ([1573](#)), `WideCharLenToString` ([1572](#))

75.11.331 StrLen

Synopsis: Length of a null-terminated string.

Declaration: `function StrLen(p: PChar) : SizeInt`

Visibility: default

Description: Returns the length of the null-terminated string `P`.

Errors: None.

75.11.332 StrPas

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: `function StrPas(p: PChar) : shortstring`

Visibility: default

Description: Converts a null terminated string in `P` to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

75.11.333 subtract(variant,variant):variant

Synopsis: Implement subtraction (–) operation on variants.

Declaration: `operator -(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the subtraction – operation is delegated to the variant manager with operation `opSubtract`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator -(variant, variant): variant` ([1339](#))

75.11.334 Succ

Synopsis: Return next element of ordinal type.

Declaration: `function Succ(X: TOrdinal) : TOrdinal`

Visibility: default

Description: `Succ` returns the element that succeeds the element that was passed to it. If it is applied to the last value of the ordinal type, and the program was compiled with range checking on (`{ $R+ }`), then a run-time error will be generated.

for an example, see `Ord` ([1515](#)).

Errors: Run-time error 201 is generated when the result is out of range.

See also: `Ord` ([1515](#)), `Pred` ([1519](#)), `High` ([1486](#)), `Low` ([1508](#))

75.11.335 SuspendThread

Synopsis: Suspend a running thread.

Declaration: `function SuspendThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `SuspendThread` suspends a running thread. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `ResumeThread` ([1528](#)), `KillThread` ([1502](#))

75.11.336 Swap

Synopsis: Swap high and low bytes/words of a variable

Declaration: `function Swap(X: Word) : Word`
`function Swap(X: Integer) : Integer`
`function Swap(X: LongInt) : LongInt`
`function Swap(X: Cardinal) : Cardinal`
`function Swap(X: QWord) : QWord`
`function Swap(X: Int64) : Int64`

Visibility: default

Description: `Swap` swaps the high and low order bytes of `X` if `X` is of type `Word` or `Integer`, or swaps the high and low order words of `X` if `X` is of type `Longint` or `Cardinal`. The return type is the type of `X`

Errors: None.

See also: `Lo` ([1505](#)), `Hi` ([1485](#))

Listing: `./examples/refex/ex69.pp`

Program Example69;

{ Program to demonstrate the Swap function. }

Var `W : Word;`

`L : Longint;`

begin

`W := $1234;`

`W := Swap(W);`

`if W <> $3412 then`

```

    writeln ('Error when swapping word !');
    L:=$12345678;
    L:=Swap(L);
    if L<>$56781234 then
        writeln ('Error when swapping Longint !');
    end.

```

75.11.337 SwapEndian

Synopsis: Swap endianness of the argument

Declaration: function SwapEndian(const AValue: SmallInt) : SmallInt
 function SwapEndian(const AValue: Word) : Word
 function SwapEndian(const AValue: LongInt) : LongInt
 function SwapEndian(const AValue: DWord) : DWord
 function SwapEndian(const AValue: Int64) : Int64
 function SwapEndian(const AValue: QWord) : QWord

Visibility: default

Description: SwapEndian will swap the endianness of the bytes in its argument.

Errors: None.

See also: hi ([1485](#)), lo ([1505](#)), swap ([1556](#)), BEToN ([1434](#)), NToBE ([1513](#)), NToLE ([1513](#)), LEToN ([1504](#))

75.11.338 SysAllocMem

Synopsis: System memory manager: Allocate memory

Declaration: function SysAllocMem(size: PtrUInt) : Pointer

Visibility: default

Description: SysFreeSize is the system memory manager implementation for AllocMem ([1425](#))

See also: AllocMem ([1425](#))

75.11.339 SysAssert

Synopsis: Standard Assert failure implementation

Declaration: procedure SysAssert(const Msg: ShortString; const FName: ShortString;
 LineNo: LongInt; ErrorAddr: Pointer)

Visibility: default

Description: SysAssert is the standard implementation of the assertion failed code. It is the default value of the AssertErrorProc constant. It will print the assert message Msg together with the filename FName and linenumber LineNo to standard error output (StdErr) and will halt the program with exit code 227. The error address ErrorAddr is ignored.

See also: AssertErrorProc ([1345](#))

75.11.340 SysBacktraceStr

Synopsis: Format an address suitable for inclusion in a backtrace

Declaration: `function SysBacktraceStr(Addr: CodePointer) : ShortString`

Visibility: default

Description: `SysBackTraceStr` will create a string representation of the address `Addr`, suitable for inclusion in a stack backtrace.

Errors: None.

75.11.341 SysFlushStdIO

Synopsis: Flush all standard IO file descriptors

Declaration: `procedure SysFlushStdIO`

Visibility: default

Description: `SysFlushStdIO` calls `flush` ([1473](#)) on all standard file descriptors: `output` ([1421](#)), `stdout` ([1421](#)), `stderr` ([1421](#)), `erroutput` ([1420](#))

See also: `output` ([1421](#)), `stdout` ([1421](#)), `stderr` ([1421](#)), `erroutput` ([1420](#)), `flush` ([1473](#))

75.11.342 SysFreemem

Synopsis: System memory manager free routine.

Declaration: `function SysFreemem(p: pointer) : PtrUInt`

Visibility: default

Description: `SysFreeem` is the system memory manager implementation for `FreeMem` ([1475](#))

See also: `FreeMem` ([1475](#))

75.11.343 SysFreememSize

Synopsis: System memory manager free routine.

Declaration: `function SysFreememSize(p: pointer; Size: PtrUInt) : PtrUInt`

Visibility: default

Description: `SysFreeemSize` is the system memory manager implementation for `FreeMem` ([1475](#))

See also: `MemSize` ([1510](#))

75.11.344 SysGetFPCHeapStatus

Synopsis: Return the status of the FPC heapmanager

Declaration: `function SysGetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: `SysGetFPCHeapStatus` returns the status of the default FPC heapmanager. It is set as the default value of the corresponding `GetFPCHeapStatus` (1478) function.

Errors: None. The result of this function is bogus information if the current heapmanager is not the standard FPC heapmanager.

See also: `GetFPCHeapStatus` (1478)

75.11.345 **SysGetHeapStatus**

Synopsis: System implementation of `GetHeapStatus` (1478)

Declaration: `function SysGetHeapStatus : THeapStatus`

Visibility: default

Description: `SysGetHeapStatus` is the system implementation of the `GetHeapStatus` (1478) call.

See also: `GetHeapStatus` (1478)

75.11.346 **SysGetmem**

Synopsis: System memory manager memory allocator.

Declaration: `function SysGetmem(Size: PtrUInt) : Pointer`

Visibility: default

Description: `SysGetmem` is the system memory manager implementation for `GetMem` (1478)

See also: `GetMem` (1478), `GetMemory` (1479)

75.11.347 **SysInitExceptions**

Synopsis: Initialize exceptions.

Declaration: `procedure SysInitExceptions`

Visibility: default

Description: `SysInitExceptions` initializes the exception system. This procedure should never be called directly, it is taken care of by the RTL.

75.11.348 **SysInitFPU**

Synopsis: Initialize the FPU

Declaration: `procedure SysInitFPU`

Visibility: default

Description: `SysInitFPU` initializes (resets) the floating point unit, if one is available. It is called for instance when a new thread is started.

See also: `BeginThread` (1434)

75.11.349 SysInitStdIO

Synopsis: Initialize standard input and output.

Declaration: `procedure SysInitStdIO`

Visibility: default

Description: `SysInitStdIO` initializes the standard input and output files: Output (1421), Input (1420) and `StdErr` (1421). This routine is called by the initialization code of the system unit, there should be no need to call it directly.

75.11.350 SysMemSize

Synopsis: System memory manager: free size.

Declaration: `function SysMemSize(p: pointer) : PtrUInt`

Visibility: default

Description: `SysFreeMemSize` is the system memory manager implementation for `MemSize` (1510)

See also: `MemSize` (1510)

75.11.351 SysReAllocMem

Synopsis: System memory manager: Reallocate memory

Declaration: `function SysReAllocMem(var p: pointer; size: PtrUInt) : Pointer`

Visibility: default

Description: `SysReAllocMem` is a help routine for the system memory manager implementation for `ReAllocMem` (1525).

See also: `ReAllocMem` (1525)

75.11.352 SysResetFPU

Synopsis: Reset the floating point unit.

Declaration: `procedure SysResetFPU`

Visibility: default

Description: `SysResetFPU` resets the floating point unit. There should normally be no need to call this unit; the compiler itself takes care of this.

75.11.353 SysSetCtrlBreakHandler

Synopsis: System CTRL-C handler

Declaration: `function SysSetCtrlBreakHandler(Handler: TCtrlBreakHandler)
: TCtrlBreakHandler`

Visibility: default

Description: `SysSetCtrlBreakHandler` sets the CTRL-C handler to the `Handler` callback, and returns the previous value of the handler.

See also: `TCtrlBreakHandler` (1389)

75.11.354 SysTryResizeMem

Synopsis: System memory manager: attempt to resize memory.

Declaration: `function SysTryResizeMem(var p: pointer; size: PtrUInt) : Boolean`

Visibility: default

Description: `SysTryResizeMem` is a help routine for the system memory manager implementation for `ReAllocMem` ([1525](#)), `SysReAllocMem` ([1560](#))

See also: `SysReAllocMem` ([1560](#)), `ReAllocMem` ([1525](#))

75.11.355 ThreadGetPriority

Synopsis: Return the priority of a thread.

Declaration: `function ThreadGetPriority(threadHandle: TThreadID) : LongInt`

Visibility: default

Description: `ThreadGetPriority` returns the priority of thread `TThreadID` to `Prio`. The returned priority is a value between -15 and 15.

Errors: None.

See also: `ThreadSetPriority` ([1561](#))

75.11.356 ThreadSetPriority

Synopsis: Set the priority of a thread.

Declaration: `function ThreadSetPriority(threadHandle: TThreadID; Prio: LongInt) : Boolean`

Visibility: default

Description: `ThreadSetPriority` sets the priority of thread `TThreadID` to `Prio`. Priority is a value between -15 and 15.

Errors: None.

See also: `ThreadGetPriority` ([1561](#))

75.11.357 ThreadSwitch

Synopsis: Signal possibility of thread switch

Declaration: `procedure ThreadSwitch`

Visibility: default

Description: `ThreadSwitch` signals the operating system that the thread should be suspended and that another thread should be executed.

This call is a hint only, and may be ignored.

See also: `SuspendThread` ([1556](#)), `ResumeThread` ([1528](#)), `KillThread` ([1502](#))

75.11.358 ToSingleByteFileSystemEncodedFileName

Synopsis: Convert string to encoding for use in single-byte file system API

Declaration: `function ToSingleByteFileSystemEncodedFileName(const Str: UnicodeString)
: RawByteString
function ToSingleByteFileSystemEncodedFileName
(const arr: Array of WideChar)
: RawByteString
function ToSingleByteFileSystemEncodedFileName(const Str: RawByteString)
: RawByteString`

Visibility: default

Description: `ToSingleByteFileSystemEncodedFileName` converts the argument (`Str` or `Arr`) to a single-byte string, encoded using the codepage used by the single-byte file system API.

This routine is simply an auxiliary routine, which converts the argument to a single-byte string using `DefaultFileSystemCodePage` (1418) as a codepage.

See also: `DefaultFileSystemCodePage` (1418)

75.11.359 Trunc

Synopsis: Truncate a floating point value.

Declaration: `function Trunc(d: ValReal) : Int64`

Visibility: default

Description: `Trunc` returns the integer part of `X`, which is always smaller than (or equal to) `X` in absolute value.

Errors: None.

See also: `Frac` (1474), `Int` (1496), `Round` (1532)

Listing: `./examples/refex/ex70.pp`

Program `Example70;`

{ Program to demonstrate the Trunc function. }

```
begin
  Writeln (Trunc(123.456)); { Prints 123 }
  Writeln (Trunc(-123.456)); { Prints -123 }
  Writeln (Trunc(12.3456)); { Prints 12 }
  Writeln (Trunc(-12.3456)); { Prints -12 }
end.
```

75.11.360 Truncate

Synopsis: Truncate the file at position

Declaration: `procedure Truncate(var F: File)`

Visibility: default

Description: `Truncate` truncates the (opened) file `F` at the current file position.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: [Append \(1425\)](#), [Filepos \(1467\)](#), [Seek \(1536\)](#)

Listing: `./examples/refex/ex71.pp`

Program `Example71;`

```
{ Program to demonstrate the Truncate function. }

Var F : File of longint;
      I,L : Longint;

begin
  Assign (F, 'test.tmp');
  Rewrite (F);
  For I:=1 to 10 Do
    Write (F,I);
  Writeln ('Filesize before Truncate : ',FileSize(F));
  Close (f);
  Reset (F);
  Repeat
    Read (F,I);
  Until i=5;
  Truncate (F);
  Writeln ('Filesize after Truncate : ',FileSize(F));
  Close (f);
end.
```

75.11.361 TryEnterCriticalSection

Synopsis: Try entering a critical section

Declaration: `function TryEnterCriticalSection(var cs: TRTLCriticalSection) : LongInt`

Visibility: default

Description: `TryEnterCriticalSection` attempts to enter critical section `cs`. It returns at once. The return value is zero if another thread owns the critical section, or nonzero if the current thread already owns or successfully obtained the critical section.

75.11.362 TypeInfo

Synopsis: Return pointer to type information for type

Declaration: `function TypeInfo(const T: AnyType) : Pointer`

Visibility: default

Description: `TypeInfo` is a compiler intrinsic: it returns a pointer to the generated type information (RTTI) for the type `T`. If no type information was yet generated for the type, this statement will ensure that type information is available, i.e. the result is always non-nil.

See also: [Default \(1452\)](#), [TypeOf \(1564\)](#), [GetTypeKind \(1481\)](#), [Initialize \(1493\)](#), [Finalize \(1471\)](#)

75.11.363 **TypeOf**

Synopsis: Return pointer to VMT of an object

Declaration: `function TypeOf(T: TObjectType) : Pointer`

Visibility: default

Description: `TypeOf` is a compiler intrinsic: it returns a pointer to the VMT of the object type `T`.

See also: [Default \(1452\)](#), [TypeInfo \(1563\)](#), [GetTypeKind \(1481\)](#)

75.11.364 **UCS4StringToUnicodeString**

Synopsis: Convert a UCS-4 encoded string to a Unicode string

Declaration: `function UCS4StringToUnicodeString(const s: UCS4String) : UnicodeString`

Visibility: default

Description: `UCS4StringToUnicodeString` converts the UCS-4 encoded string `S` to a Unicode string and returns the resulting string.

This function requires the widestring manager.

See also: [UnicodeStringToUCS4String \(1566\)](#)

75.11.365 **UCS4StringToWideString**

Synopsis:

Declaration: `function UCS4StringToWideString(const s: UCS4String) : WideString`

Visibility: default

Description:

75.11.366 **Unassigned**

Synopsis: Unassigned variant.

Declaration: `function Unassigned : Variant`

Visibility: default

75.11.367 **UnicodeCharLenToString**

Synopsis: Convert a memory buffer with Unicode characters to a unicodestring

Declaration: `function UnicodeCharLenToString(S: PUnicodeChar; Len: SizeInt)
: UnicodeString`

Visibility: default

Description: `UnicodeCharLenToString` converts the Unicode characters in buffer `S` with at most `len` bytes length, to a unicodestring and returns the result.

This function requires the use of a widestring manager.

Errors: No checking is done to see if the pointer `S` or length `len` are valid.

See also: [StringToUnicodeChar \(1554\)](#), [UnicodeCharToString \(1565\)](#)

75.11.368 UnicodeCharLenToStrVar

Synopsis: Convert a memory buffer with Unicode characters to an ansistring

Declaration: `procedure UnicodeCharLenToStrVar(Src: PUnicodeChar; Len: SizeInt;
out Dest: UnicodeString)
procedure UnicodeCharLenToStrVar(Src: PUnicodeChar; Len: SizeInt;
out Dest: AnsiString)`

Visibility: default

Description: `UnicodeCharLenToString` converts the Unicode characters in buffer `S` with at most `len` bytes length, to an ansistring and returns the result in `Dest`

This function does the same as `UnicodeCharLenToString` (1564).

Errors: No checking is done to see if the pointer `S` or length `len` are valid.

See also: `StringToUnicodeChar` (1554), `UnicodeCharToString` (1565), `UnicodeCharLenToString` (1564), `UnicodeCharToStrVar` (1565)

75.11.369 UnicodeCharToString

Synopsis: Convert Unicode character to string

Declaration: `function UnicodeCharToString(S: PUnicodeChar) : UnicodeString`

Visibility: default

Description: `UnicodeCharToString` converts a null-word-terminated array of Unicode characters in `S` to a Unicode string value. It simply calls `UnicodeCharLenToString` (1564) with the length of the string `S`.

This function requires the use of a widestring manager.

Errors: No checking is done to see if the pointer `S` is valid.

See also: `StringToUnicodeChar` (1554), `UnicodeCharLenToString` (1564), `WidestringManager` (1422)

75.11.370 UnicodeCharToStrVar

Synopsis: Convert a null-terminated memory buffer with Unicode characters to an ansistring

Declaration: `procedure UnicodeCharToStrVar(S: PUnicodeChar; out Dest: AnsiString)`

Visibility: default

Description: `UnicodeCharLenToString` converts the Unicode characters in buffer `S` up to the first null word, to an ansistring and returns the result in `Dest`

This function does the same as `UnicodeCharToString` (1565).

Errors: No checking is done to see if the pointer `S` is valid.

See also: `StringToUnicodeChar` (1554), `UnicodeCharToString` (1565), `UnicodeCharLenToString` (1564), `UnicodeCharToString` (1565)

75.11.371 UnicodeStringToUCS4String

Synopsis: Convert a Unicode string to a UCS-4 string.

Declaration: `function UnicodeStringToUCS4String(const s: UnicodeString) : UCS4String`

Visibility: default

Description: `UnicodeStringToUCS4String` converts a Unicode string `S` to a UCS-4 encoded string, and returns the resulting string.

This function requires the widestring manager.

See also: `UCS4StringToUnicodeString` ([1564](#))

75.11.372 UnicodeToUtf8

Synopsis:

Declaration: `function UnicodeToUtf8(Dest: PChar; Source: PUnicodeChar;
MaxBytes: SizeInt) : SizeInt
function UnicodeToUtf8(Dest: PChar; MaxDestBytes: SizeUInt;
Source: PUnicodeChar; SourceChars: SizeUInt)
: SizeUInt`

Visibility: default

Description:

75.11.373 UniqueString

Synopsis: Make sure reference count of string is 1

Declaration: `procedure UniqueString(var S: RawByteString)
procedure UniqueString(var S: UnicodeString)
procedure UniqueString(var S: WideString)`

Visibility: default

Description: `UniqueString` ensures that the anstring `S` has reference count 1. It makes a copy of `S` if this is necessary, and returns the copy in `S`

Errors: None.

75.11.374 UnloadLibrary

Synopsis: Unload a previously loaded library

Declaration: `function UnloadLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

Description: `UnloadLibrary` unloads a previously loaded library (specified by the handle `lib`). The call returns `True` if successful, `False` otherwise.

Errors: On error, `False` is returned.

See also: `LoadLibrary` ([1506](#)), `GetProcAddress` ([1479](#))

75.11.375 UnlockResource

Synopsis: Unlock a previously locked resource

Declaration: `function UnlockResource(ResData: TFPResourceHGLOBAL) : LongBool`

Visibility: default

Description: `UnlockResource` unlocks a previously locked resource. Note that this function does not exist on windows, it's only needed on other platforms.

Errors: The function returns `False` if it failed.

See also: `FindResource` (1471), `FreeResource` (1476), `SizeofResource` (1548), `LoadResource` (1506), `lockResource` (1507), `FreeResource` (1476)

75.11.376 UnPack

Synopsis: Create unpacked array from packed array

Declaration: `procedure UnPack(const Z: PackedArrayType; out A: UnpackedArrayType; StartIndex: TIndexType)`

Visibility: default

Description: `UnPack` will copy the elements of a packed array (Z) to an unpacked array (A). All elements in Z are copied to A, starting at index `StartIndex` in A. The type of the index variable `StartIndex` must match the type of the index of A.

Obviously, the type of the elements of the arrays A and Z must match.

See also: `Pack` (1516)

75.11.377 UpCase

Synopsis: Convert a string to all uppercase.

Declaration: `function UpCase(const s: shortstring) : shortstring`
`function UpCase(c: Char) : Char`
`function UpCase(const s: ansistring) : ansistring`
`function UpCase(const s: UnicodeString) : UnicodeString`
`function UpCase(c: UnicodeChar) : UnicodeChar`
`function UpCase(const s: WideString) : WideString`

Visibility: default

Description: `UpCase` returns the uppercase version of its argument C. If its argument is a string, then the complete string is converted to uppercase. The type of the returned value is the same as the type of the argument.

`UpCase` does not change the number of characters in the string.

Errors: None.

See also: `Lowercase` (1509)

Listing: `./examples/refex/ex72.pp`

```

program Example72;

{ Program to demonstrate the upcase function. }

var c:char;

begin
  for c:='a' to 'z' do
    write(upcase(c));
  Writeln;
  { This doesn't work in TP, but it does in Free Pascal }
  Writeln(upcase('abcdefghijklmnopqrstuvwxyz'));
end.

```

75.11.378 Utf8CodePointLen

Synopsis: Length of an UTF-8 codepoint.

Declaration: `function Utf8CodePointLen(P: PAnsiChar; MaxLookAhead: SizeInt; IncludeCombiningDiacriticalMarks: Boolean) : SizeInt`

Visibility: default

Description: `Utf8CodePointLen` returns the length of the UTF-8 codepoint starting at the beginning of `P`. It will look at at most `MaxLookAhead` bytes to do create this codepoint. If `IncludeCombiningDiacriticalMarks` is true, combining diacritical marks trailing the first codepoint (which itself can also be such a mark) will be considered to be part of the codepoint.

If the function returns a value > 0 , then this is the number of bytes occupied by the codepoint and, if requested, the trailing combining diacritical marks. If the result $= 0$, this means that all bytes within the requested `MaxLookAhead` could be part of a single valid codepoint and, if requested, its trailing diacritical marks, but that the codepoint is incomplete and more bytes need to be looked at. If the result is < 0 , then the function determined that the codepoint was invalid after processing the number of bytes equal to the absolute value of the function result.

If `IncludeCombiningDiacriticalMarks` is True, then

- If the function processes all `MaxLookAhead` bytes, it will return the value `MaxLookAhead` rather than 0, even though in theory more combining diacritical marks might follow if more bytes would be looked at. Therefore, in order to ascertain that all combining diacritical marks are processed, pass all bytes at once to this function.
- If an invalid sequence is detected while processing a potential combining diacritical mark after a valid codepoint has been found already, the function will return the length of this valid codepoint (plus that of any preceding valid combining diacritical marks) as a positive value. The idea is that this invalid sequence at the end is by definition not a combining diacritical mark (since all of those are valid sequences) and hence should not render the preceding codepoint invalid.

Errors: None.

75.11.379 UTF8Decode

Synopsis: Convert an UTF-8 encoded ansistring to a unicodestring

Declaration: `function UTF8Decode(const s: RawByteString) : UnicodeString`

Visibility: default

Description: `UTF8Decode` converts the UTF-8 encoded ansistring `S` to a unicodestring and returns the resulting string. It calls the low-level `Utf8ToUnicode` (1570) function to do the actual work.

See also: `UTF8Encode` (1569), `Utf8ToAnsi` (1569), `SetWideStringManager` (1546), `Utf8ToUnicode` (1570)

75.11.380 UTF8Encode

Synopsis: Convert a widestring or unicodestring to an UTF-8 encoded ansistring

Declaration: `function UTF8Encode(const s: RawByteString) : RawByteString`
`function UTF8Encode(const s: UnicodeString) : RawByteString`
`function UTF8Encode(const s: WideString) : RawByteString`

Visibility: default

Description: `UTF8Encode` converts an ansistring or widestring `S` to the equivalent UTF-8 encoded Unicode string and returns this resulting string. It calls the low-level `UnicodeToUTF8` (1566) function to do the actual work.

The resulting string has code page `CP_UTF8`.

See also: `UTF8Decode` (1568), `Utf8ToAnsi` (1569), `UnicodeToUtf8` (1566), `SetWideStringManager` (1546)

75.11.381 Utf8ToAnsi

Synopsis: Convert a UTF-8 encoded Unicode string to an ansistring

Declaration: `function Utf8ToAnsi(const s: RawByteString) : RawByteString`

Visibility: default

Description: `Utf8ToAnsi` converts an utf8-encode Unicode string to an ansistring. It converts the string to a widestring and then converts the widestring to an ansistring.

For this function to work, a widestring manager must be installed.

See also: `UTF8Encode` (1569), `UTF8Decode` (1568), `SetWideStringManager` (1546)

75.11.382 UTF8ToString

Synopsis: Convert UTF8 to Unicode String

Declaration: `function UTF8ToString(const s: RawByteString) : UnicodeString`
`function UTF8ToString(const S: ShortString) : unicodestring`
`function UTF8ToString(const S: PAnsiChar) : unicodestring`
`function UTF8ToString(const S: Array of AnsiChar) : unicodestring`
`function UTF8ToString(const S: Array of Byte) : unicodestring`

Visibility: default

Description: `UTF8ToString` converts a UTF8 single byte string to a UTF16 encoded unicodestring. The source string `S` is interpreted as an array of UTF8 characters.

75.11.383 Utf8ToUnicode

Synopsis: Convert a buffer with UTF-8 characters to widestring characters

Declaration: `function Utf8ToUnicode(Dest: PUnicodeChar; Source: PChar;
MaxChars: SizeInt) : SizeInt
function Utf8ToUnicode(Dest: PUnicodeChar; MaxDestChars: SizeUInt;
Source: PChar; SourceBytes: SizeUInt) : SizeUInt`

Visibility: default

Description: `Utf8ToUnicode` converts the buffer in `Source` with a length of `SourceBytes` or for a maximum length of `MaxChars` (or `MaxDestChars`) widestring characters to the buffer pointed to by `Dest`.

The function returns the number of copied widestring characters.

Errors: On error, -1 is returned.

See also: `UTF8Encode` ([1569](#)), `UTF8Decode` ([1568](#)), `Utf8ToAnsi` ([1569](#)), `SetWideStringManager` ([1546](#))

75.11.384 Val

Synopsis: Calculate numerical/enumerated value of a string.

Declaration: `procedure Val(const S: string; var V; var Code: Word)`

Visibility: default

Description: `Val` converts the value represented in the string `S` to a numerical value or an enumerated value, and stores this value in the variable `V`, which can be of any integer type (signed or unsigned, sizes from 1 to 8 bytes), floating point type (of any supported size) or any enumerated type. If the conversion is not successful, then the parameter `Code` contains the index of the character in `S` which prevented the conversion. The string `S` is allowed to contain spaces in the beginning.

The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference. For enumerated values, the string must be the name of the enumerated value. The name is searched case insensitively.

The string can use various radices in addition to a decimal (radix 10) notation:

- \$, 0x or x can be used for hexadecimal notation. Allowed characters are 0 . . 9 and A . . F (case insensitive)
- & for octal notation. Allowed characters are 0 . . 7.
- % for binary notation. Allowed characters are 0 . . 1.

The conversion to enumerated exists only as of version 2.3.1 (or later) of the compiler.

Errors: If the conversion doesn't succeed, the value of `Code` indicates the position where the conversion went wrong. The value of `V` is then undefined.

See also: `Str` ([1551](#))

Listing: `./examples/refex/ex74.pp`

Program `Example74;`

```
{ Program to demonstrate the Val function. }
Var I, Code : Integer;
```

```

begin
  Val (ParamStr (1), I, Code);
  If Code<>0 then
    Writeln ('Error at position ', code, ' : ', Paramstr(1)[Code])
  else
    Writeln ('Value : ', I);
end.

```

75.11.385 VarArrayGet

Synopsis: Get a value from a single cell of a variant array

Declaration: `function VarArrayGet(const A: Variant; const Indices: Array of LongInt) : Variant`

Visibility: default

Description: `VarArrayGet` returns the value in the variant array `A` at the location indicated by `Indices`. Thus the statement

```
B:=VarArrayGet (A, [2,1]);
```

is equivalent to

```
B:=A[2,1];
```

The difference is that the previous is usable when the amount of indices is not known at compile time.

Errors: If the number of indices is wrong (or out of range) an exception may be raised.

See also: `VarArrayPut` ([1571](#))

75.11.386 VarArrayPut

Synopsis: Put a value in a single cell of a variant array

Declaration: `procedure VarArrayPut(var A: Variant; const Value: Variant; const Indices: Array of LongInt)`

Visibility: default

Description: `VarArrayPut` puts `Value` in the variant array `A` at the location indicated by `Indices`. Thus the statement

```
VarArrayPut (A,B, [2,1]);
```

is equivalent to

```
A[2,1]:=B;
```

The difference is that the previous is usable when the amount of indices is not known at compile time.

Errors: If the number of indices is wrong (or out of range) an exception may be raised.

See also: `VarArrayGet` ([1571](#))

75.11.387 VarArrayRedim

Synopsis: Redimension a variant array

Declaration: `procedure VarArrayRedim(var A: Variant; HighBound: SizeInt)`

Visibility: default

Description: `VarArrayRedim` re-sizes the first dimension of the variant array `A`, giving it a new high bound `HighBound`. Obviously, `A` must be a variant array for this function to work.

75.11.388 VarCast

Synopsis: Cast a variant to a certain type

Declaration: `procedure VarCast(var dest: variant; const source: variant;
vartype: LongInt)`

Visibility: default

Description: `VarCast` converts the variant in `Source` to the type indicated in `VarType` and returns the result in `dest`. The `VarType` must be one of the predefined `VarNNN` constants.

Errors: If the conversion is not possible because the value cannot be correctly casted, then a run-time error or an exception may occur.

75.11.389 WaitForThreadTerminate

Synopsis: Wait for a thread to terminate.

Declaration: `function WaitForThreadTerminate(threadHandle: TThreadID;
TimeoutMs: LongInt) : DWord`

Visibility: default

Description: `WaitForThreadTerminate` waits for a thread to finish its execution. The thread is identified by its handle or ID `threadHandle`. If the thread does not exit within `TimeoutMs` milliseconds, the function will return with an error value.

The function returns the exit code of the thread.

Not all platforms support the timeout parameter: the Unix platforms (with threads support based on `pthreads`) do not support timeout, and will wait indefinitely for the thread to exit.

See also: `EndThread` ([1458](#)), `KillThread` ([1502](#))

75.11.390 WideCharLenToString

Synopsis: Convert a length-limited array of widechar to an unicodestring

Declaration: `function WideCharLenToString(S: PWideChar; Len: SizeInt) : UnicodeString`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `S` to an unicodestring, and returns the unicodestring.

Errors: No validity checking is performed on `S`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` ([1554](#)), `WideCharToString` ([1573](#)), `WideCharToStrVar` ([1573](#)), `WideCharLenToStrVar` ([1573](#))

75.11.391 WideCharLenToStrVar

Synopsis: Convert a length-limited array of widechar to an ansistring

Declaration: `procedure WideCharLenToStrVar(Src: PWideChar; Len: SizeInt;
out Dest: UnicodeString)
procedure WideCharLenToStrVar(Src: PWideChar; Len: SizeInt;
out Dest: AnsiString)`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `Src` to an ansistring or Unicode string, and returns the resulting in `Dest`.

Errors: No validity checking is performed on `Src`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` (1554), `WideCharToString` (1573), `WideCharToStrVar` (1573), `WideCharLenToString` (1572)

75.11.392 WideCharToString

Synopsis: Convert a null-terminated array of widechar to an unicodestring

Declaration: `function WideCharToString(S: PWideChar) : UnicodeString`

Visibility: default

Description: `WideCharToString` converts the null-terminated widechar array `S` to an unicodestring, and returns the unicodestring.

Errors: No validity checking is performed on `Src`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: `StringToWideChar` (1554), `WideCharToStrVar` (1573), `WideCharLenToStrVar` (1573), `WideCharLenToString` (1572)

75.11.393 WideCharToStrVar

Synopsis: Convert a null-terminated array of widechar to an ansistring

Declaration: `procedure WideCharToStrVar(S: PWideChar; out Dest: UnicodeString)
procedure WideCharToStrVar(S: PWideChar; out Dest: AnsiString)`

Visibility: default

Description: `WideCharToString` converts the null-terminated widechar array `S` to an ansistring or Unicode string, and returns the resulting string in `Dest`.

Errors: No validity checking is performed on `S`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: `StringToWideChar` (1554), `WideCharToString` (1573), `WideCharLenToStrVar` (1573), `WideCharLenToString` (1572)

75.11.394 WideStringToUCS4String

Synopsis: Convert a widestring to a UCS-4 encoded string.

Declaration: `function WideStringToUCS4String(const s: WideString) : UCS4String`

Visibility: default

Description: Convert a widestring to a UCS-4 encoded string.

75.11.395 Write

Synopsis: Write variable to a text file or standard output

Declaration: `procedure Write(V1: Type1)`
`procedure Write(V1: Type1; V2: type2)`
`procedure Write(V1: Type1; V2: Type2; V3: Type3)`
`procedure Write(var F: Text; V1: Type1)`
`procedure Write(var F: Text; V1: Type1; V2: type2)`
`procedure Write(var F: Text; V1: Type1; V2: Type2; V3: Type3)`

Visibility: default

Description: `Write` writes the contents of the variables `V1`, `V2`, `V3` etc. to the file `F`. `F` can be a typed file, or a `Text` file. If `F` is a typed file, then the variables `V1`, `V2` etc. must be of the same type as the type in the declaration of `F`. Untyped files are not allowed.

The `Write` command accepts an arbitrary number of arguments. The `V1`, `V2`, `V3` in the declaration here are in fact just samples, the actual number may be much higher. The types of arguments (`Type1` etc.) are limited to the following types:

- Any character type.
- Any string type (including `pchar`).
- Any ordinal type (integer, enumerated).
- The `Int64` and `QWord` type.
- Any floating-point type (such as `double`, `single`, `extended`).

If the parameter `F` is omitted, standard output is assumed. If `F` is of type `Text`, then the necessary conversions are done such that the output of the variables is in human-readable format. This conversion is done for all numerical types. Strings are printed exactly as they are in memory, as well as `PChar` types.

The format of the numerical conversions can be influenced through the following modifiers: `OutputVariable: NumChars [: Decimals]` This will print the value of `OutputVariable` with a minimum of `NumChars` characters, from which `Decimals` are reserved for the decimals. If the number cannot be represented with `NumChars` characters, `NumChars` will be increased, until the representation fits. If the representation requires less than `NumChars` characters then the output is filled up with spaces, to the left of the generated string, thus resulting in a right-aligned representation. If no formatting is specified, then the number is written using its natural length, with nothing in front of it if it's positive, and a minus sign if it's negative. Real numbers are, by default, written in scientific notation.

Remark When writing string variables, no codepage conversions are done. The string is copied as-is to the file descriptor. In particular, for console output, it is the programmer's responsibility to make sure that the codepage of the string matches the codepage of the console.

Remark Note that on MS Windows GUI applications do not have a standard output by default: Standard file descriptors are available only when the

`{ $APPPTYPE CONSOLE }`

directive is present in the program file.

Errors: If an error occurs, a run-time error is generated. This behavior can be controlled with the `{ $I }` switch.

See also: [WriteLn \(1575\)](#), [Read \(1522\)](#), [ReadLn \(1523\)](#), [Blockwrite \(1436\)](#)

75.11.396 WriteBarrier

Synopsis: Memory write barrier

Declaration: `procedure WriteBarrier`

Visibility: default

Description: `WriteBarrier` is a low-level instruction to force a write barrier in the CPU: write (store) operations before and after the barrier are separate.

See also: [ReadBarrier \(1523\)](#), [ReadDependencyBarrier \(1523\)](#), [ReadWriteBarrier \(1524\)](#)

75.11.397 WriteLn

Synopsis: Write variable to a text file or standard output and append newline

Declaration: `procedure WriteLn(V1: Type1)`
`procedure WriteLn(V1: Type1; V2: type2)`
`procedure WriteLn(V1: Type1; V2: Type2; V3: Type3)`
`procedure WriteLn(var F: Text; V1: Type1)`
`procedure WriteLn(var F: Text; V1: Type1; V2: type2)`
`procedure WriteLn(var F: Text; V1: Type1; V2: Type2; V3: Type3)`

Visibility: default

Description: `WriteLn` does the same as [Write \(1574\)](#) for text files, and emits a Carriage Return - LineFeed character pair after that. If the parameter `F` is omitted, standard output is assumed. If no variables are specified, a newline character sequence is emitted, resulting in a new line in the file `F`.

Remark The newline character is determined by the [slinebreak \(1364\)](#) constant.

Remark When writing string variables, no codepage conversions are done. The string is copied as-is to the file descriptor. In particular, for console output, it is the programmer's responsibility to make sure that the codepage of the string matches the codepage of the console.

More details can be found in the [Write \(1574\)](#) description.

Errors: If an error occurs, a run-time error is generated. This behavior can be controlled with the `{ $I }` switch.

See also: [Write \(1574\)](#), [Read \(1522\)](#), [ReadLn \(1523\)](#), [Blockwrite \(1436\)](#), [slinebreak \(1364\)](#)

Listing: `./examples/refex/ex75.pp`

Program `Example75;`

{ Program to demonstrate the Write(ln) function. }

Var


```

F : File of Longint;
L : Longint;

begin
  Write ('This is on the first line ! '); { No CR/LF pair! }
  Writeln ('And this too...');
  Writeln ('But this is already on the second line ...');
  Assign (f, 'test.tmp');
  Rewrite (f);
  For L:=1 to 10 do
    write (F,L); { No writeln allowed here ! }
  Close (f);
end.

```

75.11.398 WriteStr

Synopsis: Write variables to a string

Declaration: `procedure WriteStr(out S: string; Args: Arguments)`

Visibility: default

Description: `WriteStr` behaves like `Write` ([1574](#)), except that it stores its output in the string variable `S` instead of a file. Semantically, the `WriteStr` call is equivalent to writing the arguments to a file using the `Write` call, and then reading them into `S` using the `Read` call from the same file:

```

var
  F : Text;
begin
  Rewrite (F);
  Write (F, Args);
  Close (F);
  Reset (F);
  Read (F, S);
  Close (F);
end;

```

Obviously, the `WriteStr` call does not use a temporary file.

`WriteStr` is defined in the ISO Extended Pascal standard. More information on the allowed arguments and the possible formatting can be found in the description of `Write` ([1574](#)).

See also: `Write` ([1574](#)), `ReadStr` ([1524](#)), `Read` ([1522](#))

75.12 TDoubleRec

```

TDoubleRec = packed record
private
  Bias = $3FF;
  function GetExp
    : QWord;
  procedure SetExp(e: QWord);
  function GetSign : Boolean
    ;

```

```

    procedure SetSign(s: Boolean);
    function GetFrac : QWord;
    procedure
      SetFrac(e: QWord);
public
  function Mantissa(IncludeHiddenBit: Boolean
  ) : QWord;
  function Fraction : ValReal;
  function Exponent : LongInt
  ;
  property Sign : Boolean;
  property Exp : QWord;
  property Frac
  : QWord;
  function SpecialType : TFloatSpecial;
  procedure BuildUp
  (const _Sign: Boolean; const _Mantissa: QWord;
  const _Exponent: LongInt);
case Byte of
0: (
public
  Bytes : Array
  [0..7] of Byte;
);
1: (
public
  Words : Array[0..3] of Word;
);
2
  : (
public
  Data : QWord;
);
3: (
public
  Value : Double;
);
end

```

TDoubleRec models the memory layout of a double value when using software floating point math.

75.12.1 Method overview

Page	Method	Description
1579	BuildUp	Build a double value
1578	Exponent	Exponent of the floating point value
1578	Fraction	Fraction of the floating point value
1578	Mantissa	Mantissa of the floating point value
1578	SpecialType	Is the floating point value special ?

75.12.2 Property overview

Page	Properties	Access	Description
1579	Exp	rw	Exponent bitpattern representation
1579	Frac	rw	Fractional part of double
1579	Sign	rw	Sign of the floating point value

75.12.3 TDoubleRec.Mantissa

Synopsis: Mantissa of the floating point value

Declaration: `function Mantissa(IncludeHiddenBit: Boolean) : QWord`

Visibility: public

Description: `Mantissa` returns the Mantissa part (significand bitpattern without hidden bit) of the floating point value.

See also: `TDoubleRec.Fraction` ([1578](#)), `TDoubleRec.Exponent` ([1578](#)), `TDoubleRec.SpecialType` ([1578](#))

75.12.4 TDoubleRec.Fraction

Synopsis: Fraction of the floating point value

Declaration: `function Fraction : ValReal`

Visibility: public

Description: `Fraction` returns the fraction (value after decimal) of the floating point value.

See also: `TDoubleRec.Mantissa` ([1578](#)), `TDoubleRec.Exponent` ([1578](#)), `TDoubleRec.SpecialType` ([1578](#))

75.12.5 TDoubleRec.Exponent

Synopsis: Exponent of the floating point value

Declaration: `function Exponent : LongInt`

Visibility: public

Description: `Exponent` returns the exponent (X in $m \times 2^X$ representation) of the floating point value.

See also: `TDoubleRec.Fraction` ([1578](#)), `TDoubleRec.Mantissa` ([1578](#)), `TDoubleRec.SpecialType` ([1578](#))

75.12.6 TDoubleRec.SpecialType

Synopsis: Is the floating point value special ?

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` returns special characteristics of the floating point value, if any. See `TFloatSpecial` ([1393](#)) for an explanation of the various special values.

See also: `TDoubleRec.Fraction` ([1578](#)), `TDoubleRec.Mantissa` ([1578](#)), `TDoubleRec.Exponent` ([1578](#)), `TFloatSpecial` ([1393](#))

75.12.7 TDoubleRec.BuildUp

Synopsis: Build a double value

Declaration: `procedure BuildUp(const _Sign: Boolean; const _Mantissa: QWord;
const _Exponent: LongInt)`

Visibility: public

Description: Buildup will build a double value from the given _Sign, _Mantissa and _Exponent.

See also: TDoubleRec.Mantissa ([1578](#)), TDoubleRec.Sign ([1579](#)), TDoubleRec.Exp ([1579](#))

75.12.8 TDoubleRec.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

75.12.9 TDoubleRec.Exp

Synopsis: Exponent bitpattern representation

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: Exp returns the internal bit representation of the exponent of the floating point value.

See also: TDoubleRec.Sign ([1579](#)), TDoubleRec.Exponent ([1578](#))

75.12.10 TDoubleRec.Frac

Synopsis: Fractional part of double

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: Frac is the fractional part of the Double. This is the bit pattern representing the fractional part including the preceding 1. (The mantissa is that bit pattern without the preceding 1)

See also: Frac ([1474](#))

75.13 TExtended80Rec

```

TExtended80Rec = packed record
private
    Bias = $3FFF;
    function
        GetExp : QWord;
    procedure SetExp(e: QWord);
    function GetSign
        : Boolean;
    procedure SetSign(s: Boolean);
public
    function Mantissa
        (IncludeHiddenBit: Boolean) : QWord;
    function Fraction : Extended
    ;
    function Exponent : LongInt;
    property Sign : Boolean;
    property
        Exp : QWord;
    function SpecialType : TFloatSpecial;
    procedure
        BuildUp(const _Sign: Boolean; const _Mantissa: QWord;
            const _Exponent: LongInt);
case Byte of
0: (
public
    Bytes
        : Array[0..9] of Byte;
);
1: (
public
    Words : Array[0..4] of Word
    ;
);
2: (
public
    _Exp : Word;
    Frac : QWord;
);
3: (
public
    Value
        : Extended;
);
end

```

TExtended80Rec models the memory layout of an extended value when using software floating point math.

75.13.1 Method overview

Page	Method	Description
1582	BuildUp	
1581	Exponent	Exponent of the floating point value
1581	Fraction	Fraction of the floating point value
1581	Mantissa	Mantissa of the floating point value
1582	SpecialType	Is the floating point value special ?

75.13.2 Property overview

Page	Properties	Access	Description
1582	Exp	rw	Exponent representation
1582	Sign	rw	Sign of the floating point value

75.13.3 TExtended80Rec.Mantissa

Synopsis: Mantissa of the floating point value

Declaration: `function Mantissa(IncludeHiddenBit: Boolean) : QWord`

Visibility: public

Description: `Mantissa` returns the Mantissa part (bit pattern of the significand, skipping the hidden bit) of the floating point value.

See also: `TExtended80Rec.Fraction` ([1581](#)), `TExtended80Rec.Exponent` ([1581](#)), `TExtended80Rec.SpecialType` ([1582](#))

75.13.4 TExtended80Rec.Fraction

Synopsis: Fraction of the floating point value

Declaration: `function Fraction : Extended`

Visibility: public

Description: `Fraction` returns the fraction (value after decimal) of the floating point value.

See also: `TExtended80Rec.Mantissa` ([1581](#)), `TExtended80Rec.Exponent` ([1581](#)), `TExtended80Rec.SpecialType` ([1582](#))

75.13.5 TExtended80Rec.Exponent

Synopsis: Exponent of the floating point value

Declaration: `function Exponent : LongInt`

Visibility: public

Description: `Exponent` returns the exponent (the X in the $m \cdot 2^X$ representation) of the floating point value.

See also: `TExtended80Rec.Fraction` ([1581](#)), `TExtended80Rec.Mantissa` ([1581](#)), `TExtended80Rec.SpecialType` ([1582](#))

75.13.6 TExtended80Rec.SpecialType

Synopsis: Is the floating point value special ?

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` returns special characteristics of the floating point value, if any. See `TFloatSpecial` (1393) for an explanation of the various special values.

See also: `TExtended80Rec.Fraction` (1581), `TExtended80Rec.Mantissa` (1581), `TExtended80Rec.Exponent` (1581), `TFloatSpecial` (1393)

75.13.7 TExtended80Rec.BuildUp

Declaration: `procedure BuildUp(const _Sign: Boolean; const _Mantissa: QWord;
const _Exponent: LongInt)`

Visibility: public

75.13.8 TExtended80Rec.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

75.13.9 TExtended80Rec.Exp

Synopsis: Exponent representation

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exponent` returns the internal bit representation of the exponent of the floating point value.

See also: `TExtended80Rec.Sign` (1582), `TExtended80Rec.Exponent` (1581)

75.14 tinterfaceentry

```

tinterfaceentry = record
private
    function GetIID : PGuid;
    function
        GetIIDStr : PShortString;
public
    property IID : PGuid;
    property
        IIDStr : PShortString;

```

```

IIDRef : ^PGuid;
VTable : Pointer;
case
  Integer of
1: (
public
  IOffset : SizeUInt;
);
2: (
public
  IOffsetAsCodePtr
  : CodePointer;
  IIDStrRef : ^PShortString;
  IType : tinterfaceentrytype
  ;
);
end

```

`tinterfaceentry` is used to store the list of Interfaces of a class. This list is stored as an array of `tinterfaceentry` records.

75.14.1 Property overview

Page	Properties	Access	Description
1583	IID	r	Unique GUID for this interface.
1583	IIDStr	r	Pointer to GUID string. Always assigned for COM.

75.14.2 `tinterfaceentry.IID`

Synopsis: Unique GUID for this interface.

Declaration: `Property IID : PGuid`

Visibility: `public`

Access: Read

75.14.3 `tinterfaceentry.IIDStr`

Synopsis: Pointer to GUID string. Always assigned for COM.

Declaration: `Property IIDStr : PShortString`

Visibility: `public`

Access: Read

75.15 TSingleRec

```

TSingleRec = packed record
private
  Bias = $7F;
  function GetExp

```



```

    : QWord;
    procedure SetExp(e: QWord);
    function GetSign : Boolean
    ;
    procedure SetSign(s: Boolean);
    function GetFrac : QWord;
    procedure
    SetFrac(e: QWord);
public
    function Mantissa(IncludeHiddenBit: Boolean
    ) : QWord;
    function Fraction : ValReal;
    function Exponent : LongInt
    ;
    property Sign : Boolean;
    property Exp : QWord;
    property Frac
    : QWord;
    function SpecialType : TFloatSpecial;
    procedure BuildUp
    (const _Sign: Boolean; const _Mantissa: QWord;
    const _Exponent: LongInt);
case Byte of
0: (
public
    Bytes : Array
    [0..3] of Byte;
);
1: (
public
    Words : Array[0..1] of Word;
);
2
    : (
public
    Data : DWord;
);
3: (
public
    Value : Single;
);
end

```

TsingleRec models the memory layout of a double value when using software floating point math.

75.15.1 Method overview

Page	Method	Description
1586	BuildUp	
1585	Exponent	Exponent of the floating point value
1585	Fraction	Fraction of the floating point value
1585	Mantissa	Mantissa of the floating point value
1585	SpecialType	Is the floating point value special ?

75.15.2 Property overview

Page	Properties	Access	Description
1586	Exp	rw	Exponent bitpattern representation
1586	Frac	rw	Fractional part of single
1586	Sign	rw	Sign of the floating point value

75.15.3 TSingleRec.Mantissa

Synopsis: Mantissa of the floating point value

Declaration: `function Mantissa(IncludeHiddenBit: Boolean) : QWord`

Visibility: public

Description: `Mantissa` returns the Mantissa part (significand bitpattern without hidden bit) of the floating point value.

See also: `TSingleRec.Fraction` ([1585](#)), `TSingleRec.Exponent` ([1585](#)), `TSingleRec.SpecialType` ([1585](#))

75.15.4 TSingleRec.Fraction

Synopsis: Fraction of the floating point value

Declaration: `function Fraction : ValReal`

Visibility: public

Description: `Fraction` returns the fraction (after decimal) of the floating point value.

See also: `TSingleRec.Mantissa` ([1585](#)), `TSingleRec.Exponent` ([1585](#)), `TSingleRec.SpecialType` ([1585](#))

75.15.5 TSingleRec.Exponent

Synopsis: Exponent of the floating point value

Declaration: `function Exponent : LongInt`

Visibility: public

Description: `Exponent` returns the exponent (X in $m \times 2^X$ representation) of the floating point value.

See also: `TSingleRec.Fraction` ([1585](#)), `TSingleRec.Mantissa` ([1585](#)), `TSingleRec.SpecialType` ([1585](#))

75.15.6 TSingleRec.SpecialType

Synopsis: Is the floating point value special ?

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` returns special characteristics of the floating point value, if any. See `TFloatSpecial` ([1393](#)) for an explanation of the various special values.

See also: `TSingleRec.Fraction` ([1585](#)), `TSingleRec.Mantissa` ([1585](#)), `TSingleRec.Exponent` ([1585](#)), `TFloatSpecial` ([1393](#))

75.15.7 TSingleRec.BuildUp

Declaration: `procedure BuildUp(const _Sign: Boolean; const _Mantissa: QWord;
const _Exponent: LongInt)`

Visibility: public

75.15.8 TSingleRec.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

75.15.9 TSingleRec.Exp

Synopsis: Exponent bitpattern representation

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` returns the internal bit representation of the exponent of the floating point value.

See also: `TSingleRec.Sign` ([1586](#)), `TSingleRec.Exponent` ([1585](#))

75.15.10 TSingleRec.Frac

Synopsis: Fractional part of single

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: `Frac` is the fractional part of the `Single`. This is the bit pattern representing the fractional part including the preceding 1. (The mantissa is that bit pattern without the preceding 1)

See also: `Frac` ([1474](#))

75.16 TVmt

```
TVmt = record
public
  vInstanceSize : SizeInt;
  vInstanceSize2
  : SizeInt;
  vParentRef : PPVmt;
  vClassName : PShortString;
  vDynamicTable
```

```

: Pointer;
vMethodTable : Pointer;
vFieldTable : Pointer;
vTypeInfo
: Pointer;
vInitTable : Pointer;
vAutoTable : Pointer;
vIntfTable
: pinterfacetable;
vMsgStrPtr : pstringmessagetable;
vDestroy
: CodePointer;
vNewInstance : CodePointer;
vFreeInstance : CodePointer
;
vSafeCallException : CodePointer;
vDefaultHandler : CodePointer
;
vAfterConstruction : CodePointer;
vBeforeDestruction : CodePointer
;
vDefaultHandlerStr : CodePointer;
vDispatch : CodePointer;
vDispatchStr : CodePointer;
vEquals : CodePointer;
vGetHashCode
: CodePointer;
vToString : CodePointer;
private
function GetvParent
: PVmt;
public
property vParent : PVmt;
end

```

TVMT is a record describing the VMT of a class. It's various fields represent the available information in the VMT, as far as it is common to all classes.

75.16.1 Property overview

Page	Properties	Access	Description
1587	vParent	r	Pointer to parent VMT

75.16.2 TVmt.vParent

Synopsis: Pointer to parent VMT

Declaration: Property vParent : PVmt

Visibility: public

Access: Read

75.17 IDispatch

75.17.1 Description

IDispatch is the pascal definition of the Windows Dispatch interface definition.

See also: IUnknown ([1591](#))

75.17.2 Method overview

Page	Method	Description
1588	GetIDsOfNames	Return IDs of named procedures
1588	GetTypeInfo	Return type information about properties
1588	GetTypeInfoCount	Return number of properties.
1588	Invoke	Invoke a dispatch method

75.17.3 IDispatch.GetTypeInfoCount

Synopsis: Return number of properties.

Declaration: `function GetTypeInfoCount(out count: LongInt) : HRESULT`

Visibility: default

75.17.4 IDispatch.GetTypeInfo

Synopsis: Return type information about properties

Declaration: `function GetTypeInfo(Index: LongInt; LocaleID: LongInt; out TypeInfo) : HRESULT`

Visibility: default

75.17.5 IDispatch.GetIDsOfNames

Synopsis: Return IDs of named procedures

Declaration: `function GetIDsOfNames(const iid: TGuid; names: Pointer; NameCount: LongInt; LocaleID: LongInt; DispIDs: Pointer) : HRESULT`

Visibility: default

Description: Return the ID of a procedure.

75.17.6 IDispatch.Invoke

Synopsis: Invoke a dispatch method

Declaration: `function Invoke(DispID: LongInt; const iid: TGuid; LocaleID: LongInt; Flags: Word; var params; VarResult: pointer; ExcepInfo: pointer; ArgErr: pointer) : HRESULT`

Visibility: default

75.18 IEnumerable

75.18.1 Description

`IEnumerable` can be used to get an enumerator from a class. If a class implements `IEnumerable`, it can return an enumerator interface `IEnumerator` ([1589](#)).

See also: `IEnumerator` ([1589](#))

75.18.2 Method overview

Page	Method	Description
1589	<code>GetEnumerator</code>	Return an enumerator interface for this class

75.18.3 IEnumerable.GetEnumerator

Synopsis: Return an enumerator interface for this class

Declaration: `function GetEnumerator : IEnumerator`

Visibility: default

Description: `GetEnumerator` returns a new `IEnumerator` ([1589](#)) interface for this class. This is called by the compiler whenever a `for in` loop is encountered in the source code to retrieve the enumerator instance.

See also: `IEnumerator` ([1589](#))

75.19 IEnumerator

75.19.1 Description

`IEnumerator` is the interface needed by the `For ... in ...` language construct, when operating on classes. It contains all methods that the compiler needs to implement a loop.

A `for in` loop like the following:

```
For O in MyObject do
  begin
    // do things
  end;
```

is treated by the compiler as equivalent to the following code:

```
Var
  I : IEnumerator;
  O : TObject;

begin
  I:=MyObject.GetEnumerator;
  While I.MoveNext do
    begin
      O:=I.GetCurrent;
      // Do things
```

```

    end;
end.
```

Any class that implements the `IEnumerable` interface must be able to return an `IEnumerator` instance for the compiler to use in a `For in` loop.

See also: `IEnumerable` ([1589](#))

75.19.2 Method overview

Page	Method	Description
1590	<code>GetCurrent</code>	Returns the current element in the iteration cycle
1590	<code>MoveNext</code>	Move to the next value
1591	<code>Reset</code>	Reset the pointer

75.19.3 Property overview

Page	Properties	Access	Description
1591	<code>Current</code>	<code>r</code>	Return the current item

75.19.4 `IEnumerator.GetCurrent`

Synopsis: Returns the current element in the iteration cycle

Declaration: `function GetCurrent : TObject`

Visibility: `default`

Description: `getCurrent` should return the object instance representing the current value in the `for in` loop. `GetCurrent` will always be called immediately after `IEnumerator.MoveNext` ([1590](#)) returned `True`.

Remark The actual return type of the interface should not necessarily be `TObject`, it can be any type. The compiler will check the actual return type with the type of the loop variable, and they should match.

See also: `IEnumerator.MoveNext` ([1590](#)), `IEnumerator.Reset` ([1591](#))

75.19.5 `IEnumerator.MoveNext`

Synopsis: Move to the next value

Declaration: `function MoveNext : Boolean`

Visibility: `default`

Description: `MoveNext` should move the current item pointer to the next available item. It should return `True` if an item is available, `False` if no more items are available. The first time it is called It will be called at the beginning of the `for` loop, so it should position the enumerator on the first value (if there is one). After `MoveNext` has returned `True`, `IEnumerator.GetCurrent` ([1590](#)) will be called to retrieve the item.

See also: `IEnumerator.Reset` ([1591](#)), `IEnumerator.GetCurrent` ([1590](#))

75.19.6 IEnumerator.Reset

Synopsis: Reset the pointer

Declaration: `procedure Reset`

Visibility: `default`

Description: `Reset` can be implemented to put the pointer at the start of the list. It is not mandatory to implement this method, the compiler does not use it.

See also: `IEnumerator.GetCurrent` ([1590](#)), `IEnumerator.MoveNext` ([1590](#))

75.19.7 IEnumerator.Current

Synopsis: Return the current item

Declaration: `Property Current : TObject`

Visibility: `default`

Access: `Read`

Description: `Current` simply is the redefinition of `IEnumerator.GetCurrent` ([1590](#)) as a property. It is read-only.

See also: `IEnumerator.GetCurrent` ([1590](#)), `IEnumerator.MoveNext` ([1590](#))

75.20 IInvokable

75.20.1 Description

`IInvokable` is a descendent of `IInterface` ([1375](#)), compiled in the `{ $M+ }` state, so Run-Time Type Information (RTTI) is generated for it.

See also: `IDispatch` ([1588](#)), `IInterface` ([1375](#))

75.21 IUnknown

75.21.1 Description

`IUnknown` is defined by windows. It's the basic interface which all COM objects must implement. The definition does not contain any code.

See also: `IInterface` ([1375](#)), `IDispatch` ([1588](#)), `IInvokable` ([1591](#))

75.21.2 Method overview

Page	Method	Description
1592	<code>_AddRef</code>	Increase reference count of the interface
1592	<code>QueryInterface</code>	Return pointer to VMT table of interface
1592	<code>_Release</code>	Decrease reference count of the interface

75.21.3 IUnknown.QueryInterface

Synopsis: Return pointer to VMT table of interface

Declaration: `function QueryInterface(const iid: TGuid; out obj) : LongInt`

Visibility: default

75.21.4 IUnknown._AddRef

Synopsis: Increase reference count of the interface

Declaration: `function _AddRef : LongInt`

Visibility: default

See also: `IUnknown._Release` ([1592](#))

75.21.5 IUnknown._Release

Synopsis: Decrease reference count of the interface

Declaration: `function _Release : LongInt`

Visibility: default

See also: `IUnknown._AddRef` ([1592](#))

75.22 TAggregatedObject

75.22.1 Description

`TAggregatedObject` implements an object whose lifetime is governed by an external object (or interface). It does not implement the `IUnknown` interface by itself, but delegates all methods to the controller object, as exposed in the `Controller` ([1593](#)) property. In effect, the reference count of the aggregated object is the same as that of its controller, and additionally, all interfaces of the controller are exposed by the aggregated object.

Note that the aggregated object maintains a non-counted reference to the controller.

Aggregated objects should be used when using delegation to implement reference counted objects: the delegated interfaces can be implemented safely by `TAggregatedObject` descendents.

See also: `Create` ([1593](#)), `Controller` ([1593](#))

75.22.2 Method overview

Page	Method	Description
1593	<code>Create</code>	Create a new instance of <code>TAggregatedObject</code>

75.22.3 Property overview

Page	Properties	Access	Description
1593	<code>Controller</code>	<code>r</code>	Controlling instance

75.22.4 TAggregatedObject.Create

Synopsis: Create a new instance of TAggregatedObject

Declaration: `constructor Create(const aController: IUnknown)`

Visibility: public

Description: Create creates a new instance of TAggregatedObject on the heap, and stores a reference to aController, so it can be exposed in the Controller ([1593](#)) property.

Errors: If not enough memory is present on the heap, an exception will be raised. If the aController is Nil, exceptions will occur when any of the TAggregatedObject methods (actually, the IUnknown methods) are used.

See also: Controller ([1593](#))

75.22.5 TAggregatedObject.Controller

Synopsis: Controlling instance

Declaration: `Property Controller : IUnknown`

Visibility: public

Access: Read

Description: Controller exposes the controlling object, with all interfaces it has.

The value of the controller is set when the TAggregatedObject instance is created.

See also: TAggregatedObject.Create ([1593](#))

75.23 TContainedObject

75.23.1 Description

TContainedObject is the base class for contained objects, i.e. objects that do not implement a reference counting mechanism themselves, but are owned by some other object which handles the reference counting mechanism. It implements the IUnknown interface and, more specifically, the QueryInterface method of IUnknown.

See also: IInterface ([1375](#))

75.23.2 Interfaces overview

Page	Interfaces	Description
1375	IInterface	Basic interface for all COM based interfaces

75.24 TInterfacedObject

75.24.1 Description

TInterfacedObject is a descendent of TObject ([1595](#)) which implements the IUnknown ([1591](#)) interface. It can be used as a base class for all classes which need reference counting.

See also: IUnknown ([1591](#)), TObject ([1595](#))

75.24.2 Interfaces overview

Page	Interfaces	Description
1591	IUnknown	Basic interface for all COM-based interfaces

75.24.3 Method overview

Page	Method	Description
1594	AfterConstruction	Handle reference count properly.
1594	BeforeDestruction	Check reference count.
1594	destroy	Destroy interfaced object
1595	NewInstance	Create a new instance

75.24.4 Property overview

Page	Properties	Access	Description
1595	RefCount	r	Return the current reference count

75.24.5 TInterfacedObject.destroy

Synopsis: Destroy interfaced object

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: `Destroy` overrides the default destructor to clean up: it explicitly sets all counters to zero.

See also: `IUnknown._Release` ([1592](#))

75.24.6 TInterfacedObject.AfterConstruction

Synopsis: Handle reference count properly.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` overrides the basic method in `TObject` and adds some additional reference count handling.

Errors: None.

See also: `BeforeDestruction` ([1594](#))

75.24.7 TInterfacedObject.BeforeDestruction

Synopsis: Check reference count.

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `AfterConstruction` overrides the basic method in `TObject` and adds a reference count check: if the reference count is not zero, an error occurs.

Errors: A runtime-error 204 will be generated if the reference count is nonzero when the object is destroyed.

See also: `AfterConstruction` ([1594](#))

75.24.8 TInterfacedObject.NewInstance

Synopsis: Create a new instance

Declaration: `class function NewInstance : TObject; Override`

Visibility: `public`

Description: `NewInstance` initializes a new instance of `TInterfacedObject` ([1593](#))

Errors: None.

75.24.9 TInterfacedObject.RefCount

Synopsis: Return the current reference count

Declaration: `Property RefCount : LongInt`

Visibility: `public`

Access: `Read`

Description: `RefCount` returns the current reference count. This reference count cannot be manipulated, except through the methods of `IUnknown` ([1591](#)). When it reaches zero, the class instance is destroyed.

See also: `IUnknown` ([1591](#))

75.25 TObject

75.25.1 Description

`TObject` is the parent root class for all classes in Object Pascal. If a class has no parent class explicitly declared, it is dependent on `TObject`. `TObject` introduces class methods that deal with the class' type information, and contains all necessary methods to create an instance at runtime, and to dispatch messages to the correct method (both string and integer messages).

See also: `TClass` ([1388](#))

75.25.2 Method overview

Page	Method	Description
1602	<code>AfterConstruction</code>	Method called after the constructor was called.
1602	<code>BeforeDestruction</code>	Method called before the destructor is called.
1599	<code>ClassInfo</code>	Return a pointer to the type information for this class.
1599	<code>ClassName</code>	Return the current class name.
1600	<code>ClassNameIs</code>	Check whether the class name equals the given name.
1600	<code>ClassParent</code>	Return the parent class.
1599	<code>ClassType</code>	Return a "class of" pointer for the current class
1599	<code>CleanupInstance</code>	Finalize the class instance.
1596	<code>Create</code>	<code>TObject</code> Constructor
1598	<code>DefaultHandler</code>	Default handler for integer message handlers.
1602	<code>DefaultHandlerStr</code>	Default handler for string messages.
1597	<code>Destroy</code>	<code>TObject</code> destructor.
1602	<code>Dispatch</code>	Dispatch an integer message
1603	<code>DispatchStr</code>	Dispatch a string message.
1605	<code>Equals</code>	Check if two objects are equal.
1601	<code>FieldAddress</code>	Return the address of a field.
1598	<code>Free</code>	Check for <code>Nil</code> and call destructor.
1597	<code>FreeInstance</code>	Clean up instance and free the memory reserved for the instance.
1605	<code>GetHashCode</code>	Return a hash code for the object
1603	<code>GetInterface</code>	Return a reference to an interface
1603	<code>GetInterfaceByStr</code>	Return an interface based on its GUID
1604	<code>GetInterfaceEntry</code>	Return the interface table entry by GUID
1604	<code>GetInterfaceEntryByStr</code>	Return the interface table entry by string
1604	<code>GetInterfaceTable</code>	Return a pointer to the table of implemented interfaces for a class
1604	<code>GetInterfaceWeak</code>	Get a reference to an interface, not increasing the reference count
1600	<code>InheritsFrom</code>	Check whether class is an ancestor.
1598	<code>InitInstance</code>	Initialize a new class instance.
1600	<code>InstanceSize</code>	Return the size of an instance.
1601	<code>MethodAddress</code>	Return the address of a method
1601	<code>MethodName</code>	Return the name of a method.
1597	<code>newinstance</code>	Allocate memory on the heap for a new instance
1605	<code>QualifiedClassName</code>	Fully qualified classname
1598	<code>SafeCallException</code>	Handle exception object
1601	<code>StringMessageTable</code>	Return a pointer to the string message table.
1606	<code>ToString</code>	Return a string representation for the object
1605	<code>UnitName</code>	Unit name

75.25.3 TObject.Create

Synopsis: `TObject` Constructor

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of `TObject`. Currently it does nothing (except allocating memory for the new instance).

Note that allocating the memory for the object instance happens in hidden code generated as part of every constructor, not only in `TObject.Create`. The hidden code calls `NewInstance` ([1597](#)).

See also: [Destroy \(1597\)](#)

75.25.4 TObject.Destroy

Synopsis: TObject destructor.

Declaration: `destructor Destroy; Virtual`

Visibility: `public`

Description: `Destroy` is the destructor of `TObject`. It will clean up the memory assigned to the instance. Descendent classes should override `destroy` if they want to do additional clean-up. No other destructor should be implemented.

It is bad programming practice to call `Destroy` directly. It is better to call the [Free \(1598\)](#) method, because that one will check first if `Self` is different from `Nil`.

To clean up an instance and reset the reference to the instance, it is best to use the [FreeAndNil \(1723\)](#) function.

See also: [Create \(1596\)](#), [Free \(1598\)](#)

75.25.5 TObject.newinstance

Synopsis: Allocate memory on the heap for a new instance

Declaration: `class function newInstance : TObject; Virtual`

Visibility: `public`

Description: `NewInstance` allocates memory on the heap for a new instance of the current class. If the memory was allocated, the class will be initialized by a call to [InitInstance \(1598\)](#). The function returns the newly initialized instance.

This method can be overridden to implement e.g. object pooling. Note that the method is responsible for correctly initializing the object, i.e. zeroing out the new instance.

Errors: If not enough memory is available, a `Nil` pointer may be returned, or an exception may be raised.

See also: [Create \(1596\)](#), [InitInstance \(1598\)](#), [InstanceSize \(1600\)](#), [FreeInstance \(1597\)](#)

75.25.6 TObject.FreeInstance

Synopsis: Clean up instance and free the memory reserved for the instance.

Declaration: `procedure FreeInstance; Virtual`

Visibility: `public`

Description: `FreeInstance` cleans up an instance of the current class, and releases the heap memory occupied by the class instance.

See also: [Destroy \(1597\)](#), [InitInstance \(1598\)](#), [NewInstance \(1597\)](#)

75.25.7 TObject.SafeCallException

Synopsis: Handle exception object

Declaration: `function SafeCallException(exceptobject: TObject;
exceptaddr: CodePointer) : HRESULT; Virtual`

Visibility: public

Description: `SafeCallException` should be overridden to handle exceptions in a method marked with the `savecall` directive. The implementation in `TObject` simply returns zero.

75.25.8 TObject.DefaultHandler

Synopsis: Default handler for integer message handlers.

Declaration: `procedure DefaultHandler(var message); Virtual`

Visibility: public

Description: `DefaultHandler` is the default handler for messages. If a message has an unknown message ID (i.e. does not appear in the table with integer message handlers), then it will be passed to `DefaultHandler` by the `Dispatch` (1602) method.

See also: `Dispatch` (1602), `DefaultHandlerStr` (1602)

75.25.9 TObject.Free

Synopsis: Check for `Nil` and call destructor.

Declaration: `procedure Free`

Visibility: public

Description: `Free` will check the `Self` pointer and calls `Destroy` (1597) if it is different from `Nil`. This is a safer method than calling `Destroy` directly. If a reference to the object must be reset as well (a recommended technique), then the function `FreeAndNil` (1723) should be called.

Errors: None.

See also: `Destroy` (1597), `FreeAndNil` (1723)

75.25.10 TObject.InitInstance

Synopsis: Initialize a new class instance.

Declaration: `class function InitInstance(instance: pointer) : TObject`

Visibility: public

Description: `InitInstance` initializes the memory pointer to by `Instance`. This means that the VMT is initialized, and the interface pointers are set up correctly. The function returns the newly initialized instance.

See also: `NewInstance` (1597), `Create` (1596)

75.25.11 TObject.CleanupInstance

Synopsis: Finalize the class instance.

Declaration: `procedure CleanupInstance`

Visibility: `public`

Description: `CleanUpInstance` finalizes the instance, i.e. takes care of all reference counted objects, by decreasing their reference count by 1, and freeing them if their count reaches zero.

Normally, `CleanupInstance` should never be called, it is called automatically when the object is freed with it's constructor.

Errors: None.

See also: `Destroy` ([1597](#)), `Free` ([1598](#)), `InitInstance` ([1598](#))

75.25.12 TObject.ClassType

Synopsis: Return a "class of" pointer for the current class

Declaration: `class function ClassType : TClass`

Visibility: `public`

Description: `ClassType` returns a `TClass` ([1388](#)) class type reference for the current class.

See also: `TClass` ([1388](#)), `ClassInfo` ([1599](#)), `ClassName` ([1599](#))

75.25.13 TObject.ClassInfo

Synopsis: Return a pointer to the type information for this class.

Declaration: `class function ClassInfo : pointer`

Visibility: `public`

Description: `ClassInfo` returns a pointer to the type information for this class. This pointer can be used in the various type information routines.

75.25.14 TObject.ClassName

Synopsis: Return the current class name.

Declaration: `class function ClassName : shortstring`

Visibility: `public`

Description: `ClassName` returns the class name for the current class. To check for the class name, you can use the `ClassNameIs` ([1600](#)) class method.

Errors: None.

See also: `ClassInfo` ([1599](#)), `ClassType` ([1599](#)), `ClassNameIs` ([1600](#))

75.25.15 TObject.ClassNameIs

Synopsis: Check whether the class name equals the given name.

Declaration: `class function ClassNameIs(const name: string) : Boolean`

Visibility: public

Description: `ClassNameIs` checks whether `Name` equals the class name. It takes of case sensitivity.

See also: `ClassInfo` ([1599](#)), `ClassType` ([1599](#)), `ClassName` ([1599](#))

75.25.16 TObject.ClassParent

Synopsis: Return the parent class.

Declaration: `class function ClassParent : TClass`

Visibility: public

Description: `ClassParent` returns the class of the parent class of the current class. This is always different from `Nil`, except for `TObject`.

Errors: None.

See also: `ClassInfo` ([1599](#)), `ClassType` ([1599](#)), `ClassNameIs` ([1599](#))

75.25.17 TObject.InstanceSize

Synopsis: Return the size of an instance.

Declaration: `class function InstanceSize : SizeInt`

Visibility: public

Description: `InstanceSize` returns the number of bytes an instance takes in memory. This is Just the memory occupied by the class structure, and does not take into account any additional memory that might be allocated by the constructor of the class.

Errors: None.

See also: `InitInstance` ([1598](#)), `ClassName` ([1599](#)), `ClassInfo` ([1599](#)), `ClassType` ([1599](#))

75.25.18 TObject.InheritsFrom

Synopsis: Check whether class is an ancestor.

Declaration: `class function InheritsFrom(aclass: TClass) : Boolean`

Visibility: public

Description: `InheritsFrom` returns `True` if `AClass` is an ancestor class from the current class, and returns `false` if it is not.

See also: `ClassName` ([1599](#)), `ClassInfo` ([1599](#)), `ClassType` ([1599](#)), `TClass` ([1388](#))

75.25.19 TObject.StringMessageTable

Synopsis: Return a pointer to the string message table.

Declaration: `class function StringMessageTable : pstringmessagetable`

Visibility: public

Description: `StringMessageTable` returns a pointer to the string message table, which can be used to look up methods for dispatching a string message. It is used by the `DispatchStr` (1603) method.

Errors: If there are no string message handlers, nil is returned.

See also: `DispatchStr` (1603), `Dispatch` (1602)

75.25.20 TObject.MethodAddress

Synopsis: Return the address of a method

Declaration: `class function MethodAddress(const name: shortstring) : CodePointer`

Visibility: public

Description: `MethodAddress` returns the address of a method, searching the method by its name. The `Name` parameter specifies which method should be taken. The search is conducted in a case-insensitive manner.

Errors: If no matching method is found, `Nil` is returned.

See also: `MethodName` (1601), `FieldAddress` (1601)

75.25.21 TObject.MethodName

Synopsis: Return the name of a method.

Declaration: `class function MethodName(address: CodePointer) : shortstring`

Visibility: public

Description: `MethodName` searches the VMT for a method with the specified address and returns the name of the method.

Errors: If no method with the matching address is found, an empty string is returned.

See also: `MethodAddress` (1601), `FieldAddress` (1601)

75.25.22 TObject.FieldAddress

Synopsis: Return the address of a field.

Declaration: `function FieldAddress(const name: shortstring) : pointer`

Visibility: public

Description: `FieldAddress` returns the address of the field with name `name`. The address is the address of the field in the current class instance.

Errors: If no field with the specified name is found, `Nil` is returned.

See also: `MethodAddress` (1601), `MethodName` (1601)

75.25.23 TObject.AfterConstruction

Synopsis: Method called after the constructor was called.

Declaration: `procedure AfterConstruction; Virtual`

Visibility: `public`

Description: `AfterConstruction` is a method called after the constructor was called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed after the constructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `BeforeDestruction` ([1602](#)), `Create` ([1596](#))

75.25.24 TObject.BeforeDestruction

Synopsis: Method called before the destructor is called.

Declaration: `procedure BeforeDestruction; Virtual`

Visibility: `public`

Description: `BeforeDestruction` is a method called before the destructor is called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed before the destructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `AfterConstruction` ([1602](#)), `Destroy` ([1597](#)), `Free` ([1598](#))

75.25.25 TObject.DefaultHandlerStr

Synopsis: Default handler for string messages.

Declaration: `procedure DefaultHandlerStr(var message); Virtual`

Visibility: `public`

Description: `DefaultHandlerStr` is called for string messages which have no handler associated with them in the string message handler table. The implementation of `DefaultHandlerStr` in `TObject` does nothing and must be overridden by descendent classes to provide specific message handling behaviour.

See also: `DispatchStr` ([1603](#)), `Dispatch` ([1602](#)), `DefaultHandler` ([1598](#))

75.25.26 TObject.Dispatch

Synopsis: Dispatch an integer message

Declaration: `procedure Dispatch(var message); Virtual`

Visibility: `public`

Description: `Dispatch` looks in the message handler table for a handler that handles `message`. The message is identified by the first dword (cardinal) in the message structure.

If no matching message handler is found, the message is passed to the `DefaultHandler` (1598) method, which can be overridden by descendent classes to add custom handling of messages.

See also: `DispatchStr` (1603), `DefaultHandler` (1598)

75.25.27 TObject.DispatchStr

Synopsis: Dispatch a string message.

Declaration: `procedure DispatchStr(var message); Virtual`

Visibility: public

Description: `DispatchStr` extracts the message identifier from `Message` and checks the message handler table to see if a handler for the message is found, and calls the handler, passing along the message. If no handler is found, the default `DefaultHandlerStr` (1602) is called.

Errors: None.

See also: `DefaultHandlerStr` (1602), `Dispatch` (1602), `DefaultHandler` (1598)

75.25.28 TObject.GetInterface

Synopsis: Return a reference to an interface

Declaration: `function GetInterface(const iid: TGuid; out obj) : Boolean`
`function GetInterface(const iidstr: shortstring; out obj) : Boolean`

Visibility: public

Description: `GetInterface` scans the interface tables and returns a reference to the interface `iid`. The reference is stored in `Obj` which should be an interface reference. It returns `True` if the interface was found, `False` if not.

The reference count of the interface is increased by this call.

Errors: If no interface was found, `False` is returned.

See also: `GetInterfaceByStr` (1603)

75.25.29 TObject.GetInterfaceByStr

Synopsis: Return an interface based on its GUID

Declaration: `function GetInterfaceByStr(const iidstr: shortstring; out obj) : Boolean`

Visibility: public

Description: `GetInterfaceByStr` returns in `obj` a pointer to the interface identified by `iidstr`. The function returns `True` if the interface is indeed implemented by the class, or `False` otherwise.

The `iidstr` is the unique GUID by which the interface was declared.

Errors: The function returns false if the requested interface is not implemented.

See also: `TObject.GetInterfaceEntry` (1604), `TObject.GetInterfaceEntryByStr` (1604)

75.25.30 TObject.GetInterfaceWeak

Synopsis: Get a reference to an interface, not increasing the reference count

Declaration: `function GetInterfaceWeak(const iid: TGuid; out obj) : Boolean`

Visibility: public

Description: `GetInterfaceWeak` performs the same function as `GetInterface` (1603), but unlike the latter, it will not increase the reference count of the interface.

See also: `TObject.GetInterface` (1603)

75.25.31 TObject.GetInterfaceEntry

Synopsis: Return the interface table entry by GUID

Declaration: `class function GetInterfaceEntry(const iid: TGuid) : pinterfaceentry`

Visibility: public

Description: `GetInterfaceEntry` returns the internal interface table entry for the interface identified by `iid` (the GUID used in the declaration of the interface). If the interface is not implemented by the class, the function returns `Nil`.

See also: `TObject.GetInterfaceByStr` (1603), `TObject.GetInterfaceEntryByStr` (1604)

75.25.32 TObject.GetInterfaceEntryByStr

Synopsis: Return the interface table entry by string

Declaration: `class function GetInterfaceEntryByStr(const iidstr: shortstring)
: pinterfaceentry`

Visibility: public

Description: `GetInterfaceEntryByStr` returns the internal interface table entry for the interface identified by `iidstr` (A string representation of the GUID used in the declaration of the interface). If the interface is not implemented by the class, the function returns `Nil`.

See also: `TObject.GetInterfaceByStr` (1603), `TObject.GetInterfaceEntry` (1604)

75.25.33 TObject.GetInterfaceTable

Synopsis: Return a pointer to the table of implemented interfaces for a class

Declaration: `class function GetInterfaceTable : pinterfacetable`

Visibility: public

Description: `GetInterfaceTable` returns a pointer to the internal table of implemented interfaces for a class. The result will always point to a valid address, if the class implements no interfaces the `EntryCount` field of the interface table will be zero.

See also: `TObject.GetInterfaceByStr` (1603), `TObject.GetInterfaceEntry` (1604)

75.25.34 TObject.UnitName

Synopsis: Unit name

Declaration: `class function UnitName : ansistring`

Visibility: public

Description: `UnitName` returns the unit name in which the class was defined. The name is obtained from the class definition data the compiler generates for each class.

75.25.35 TObject.QualifiedClassName

Synopsis: Fully qualified classname

Declaration: `class function QualifiedClassName : ansistring`

Visibility: public

Description: `QualifiedClassName` is the classname `TObject.ClassName` (1599) prepended with the unit name `TObject.UnitName` (1605) of the unit in which the class is defined. As such, this is a unique name for each class in the program.

See also: `TObject.ClassName` (1599), `TObject.UnitName` (1605)

75.25.36 TObject.Equals

Synopsis: Check if two objects are equal.

Declaration: `function Equals (Obj: TObject) : Boolean; Virtual`

Visibility: public

Description: `Equals` returns `True` if the object instance pointer (`Self`) equals the instance pointer `Obj`.
Descendent classes can override to check properties etc. in case the instance pointers are different.

See also: `TObject.GetHashCode` (1605), `TObject.ToString` (1606)

75.25.37 TObject.GetHashCode

Synopsis: Return a hash code for the object

Declaration: `function GetHashCode : PtrInt; Virtual`

Visibility: public

Description: `GetHashCode` should return a hash code for the object. By default, the numerical (integer) address of `Self` is returned.

Descendent classes can use this to generate better suitable values to be used in a hash table.

See also: `TObject.ToString` (1606), `TObject.Equals` (1605)

75.25.38 **TObject.ToString**

Synopsis: Return a string representation for the object

Declaration: `function ToString : ansistring; Virtual`

Visibility: `public`

Description: `ToString` returns by default the class name of the object. It is useful during sending of debug messages.

Descendent classes can override this method to give a better description of the object than just the class name.

See also: `TObject.GetHashCode` ([1605](#)), `TObject.Equals` ([1605](#))

Chapter 76

Reference for unit 'System.UITypes'

76.1 Used units

Table 76.1: Used units by unit 'System.UITypes'

Name	Page
System	1339

76.2 Constants, types and variables

76.2.1 Constants

```
ModalResultStr : Array[mrNone..mrLast] of shortstring = ('mrNone'  
    , 'mrOk', 'mrCancel', 'mrAbort', 'mrRetry', 'mrIgnore', 'mrYes', 'mrNo'  
    , 'mrAll', 'mrNoToAll', 'mrYesToAll', 'mrClose')
```

```
mrAbort = mrNone + 3
```

```
mrAll = mrNone + 8
```

```
mrCancel = mrNone + 2
```

```
mrClose = mrNone + 11
```

```
mrIgnore = mrNone + 5
```

```
mrLast = mrClose
```

```
mrNo = mrNone + 7
```


mrNone = 0

mrNoToAll = mrNone + 9

mrOK = mrNone + 1

mrRetry = mrNone + 4

mrYes = mrNone + 6

mrYesToAll = mrNone + 10

76.2.2 Types

PAlphaColor = ^TAlphaColor

PColor = ^TColor

PColorRef = ^TColorRef

PModalResult = ^TModalResult

TAlphaColor = Cardinal

TColor = - \$7FFFFFFF - 1..\$7FFFFFFF

TColorRef = Cardinal

TColors = TColorRec

TModalResult = (Integer)..(Integer)

TMsgDlgBtn = (mbYes,mbNo,mbOK,mbCancel,mbAbort,mbRetry,mbIgnore,mbAll
,
 mbNoToAll,mbYesToAll,mbHelp,mbClose)

Table 76.2: Enumeration values for type TMsgDlgBtn

Value	Explanation
mbAbort	
mbAll	
mbCancel	
mbClose	
mbHelp	
mbIgnore	
mbNo	
mbNoToAll	
mbOK	
mbRetry	
mbYes	
mbYesToAll	

```
TMsgDlgButtons = Set of TMsgDlgBtn
```

```
TMsgDlgType = (mtWarning, mtError, mtInformation, mtConfirmation, mtCustom
)
```

Table 76.3: Enumeration values for type TMsgDlgType

Value	Explanation
mtConfirmation	
mtCustom	
mtError	
mtInformation	
mtWarning	

76.3 TColorRec

```
TColorRec = record
public
  TColorRec.class operator :=(AColor: TColor
) : TColorRec;
  TColorRec.class operator :=(AColor: TColorRec) :
  TColor;
  AliceBlue = TColor($FFF8F0);
  AntiqueWhite = TColor($D7EBFA
);
  Aqua = TColor($FFFF00);
  Aquamarine = TColor($D4FF7F);
  Azure
= TColor($FFFFFF0);
  Beige = TColor($DCF5F5);
  Bisque = TColor(
$C4E4FF);
```

```
Black = TColor($000000);
BlanchedAlmond = TColor($CDEBFF
);
Blue = TColor($FF0000);
BlueViolet = TColor($E22B8A);
Brown
= TColor($2A2AA5);
BurlyWood = TColor($87B8DE);
CadetBlue = TColor
($A09E5F);
Chartreuse = TColor($00FF7F);
Chocolate = TColor($1E69D2
);
Coral = TColor($507FFF);
CornflowerBlue = TColor($ED9564);
Cornsilk = TColor($DCF8FF);
Crimson = TColor($3C14DC);
Cyan
= TColor($FFFF00);
DarkBlue = TColor($8B0000);
DarkCyan = TColor
($8B8B00);
DarkGoldenRod = TColor($0B86B8);
DarkGray = TColor
($A9A9A9);
DarkGreen = TColor($006400);
DarkGrey = TColor($A9A9A9
);
DarkKhaki = TColor($6BB7BD);
DarkMagenta = TColor($8B008B)
;
DarkOliveGreen = TColor($2F6B55);
DarkOrange = TColor($008CFF
);
DarkOrchid = TColor($CC3299);
DarkRed = TColor($00008B);
DarkSalmon = TColor($7A96E9);
DarkSeaGreen = TColor($8FBC8F);
DarkSlateBlue = TColor($8B3D48);
DarkSlateGray = TColor($4F4F2F
);
DarkSlateGrey = TColor($4F4F2F);
DarkTurquoise = TColor($D1CE00
);
DarkViolet = TColor($D30094);
DeepPink = TColor($9314FF);
DeepSkyBlue = TColor($FFBF00);
DimGray = TColor($696969);
DimGrey
= TColor($696969);
DodgerBlue = TColor($FF901E);
FireBrick =
TColor($2222B2);
FloralWhite = TColor($F0FAFF);
```

```

ForestGreen
= TColor($228B22);
Fuchsia = TColor($FF00FF);
Gainsboro = TColor
($DCDCDC);
GhostWhite = TColor($FFF8F8);
Gold = TColor($00D7FF
);
GoldenRod = TColor($20A5DA);
Gray = TColor($808080);
Green
= TColor($008000);
GreenYellow = TColor($2FFFAD);
Grey = TColor
($808080);
HoneyDew = TColor($F0FFF0);
HotPink = TColor($B469FF
);
IndianRed = TColor($5C5CCD);
Indigo = TColor($82004B);
Ivory
= TColor($F0FFFF);
Khaki = TColor($8CE6F0);
Lavender = TColor
($FAE6E6);
LavenderBlush = TColor($F5F0FF);
LawnGreen = TColor
($00FC7C);
LemonChiffon = TColor($CDFAFF);
LightBlue = TColor
($E6D8AD);
LightCoral = TColor($8080F0);
LightCyan = TColor($FFFFE0
);
LightGoldenRodYellow = TColor($D2FAFA);
LightGray = TColor
($D3D3D3);
LightGreen = TColor($90EE90);
LightGrey = TColor($D3D3D3
);
LightPink = TColor($C1B6FF);
LightSalmon = TColor($7AA0FF)
;
LightSeaGreen = TColor($AAB220);
LightSkyBlue = TColor($FACE87
);
LightSlateGray = TColor($998877);
LightSlateGrey = TColor(
$998877);
LightSteelBlue = TColor($DEC4B0);
LightYellow = TColor
($E0FFFF);
Lime = TColor($00FF00);
LimeGreen = TColor($32CD32

```

```
);
Linen = TColor($E6F0FA);
Magenta = TColor($FF00FF);
Maroon
= TColor($000080);
MediumAquaMarine = TColor($AACD66);
MediumBlue
= TColor($CD0000);
MediumOrchid = TColor($D355BA);
MediumPurple
= TColor($DB7093);
MediumSeaGreen = TColor($71B33C);
MediumSlateBlue
= TColor($EE687B);
MediumSpringGreen = TColor($9AFA00);
MediumTurquoise
= TColor($CCD148);
MediumVioletRed = TColor($8515C7);
MidnightBlue
= TColor($701919);
MintCream = TColor($FAFF5);
MistyRose = TColor
($E1E4FF);
Moccasin = TColor($B5E4FF);
NavajoWhite = TColor($ADDEFF
);
Navy = TColor($800000);
OldLace = TColor($E6F5FD);
Olive
= TColor($008080);
OliveDrab = TColor($238E6B);
Orange = TColor
($00A5FF);
OrangeRed = TColor($0045FF);
Orchid = TColor($D670DA
);
PaleGoldenRod = TColor($AAE8EE);
PaleGreen = TColor($98FB98
);
PaleTurquoise = TColor($EEEEAF);
PaleVioletRed = TColor($9370DB
);
PapayaWhip = TColor($D5EFFF);
PeachPuff = TColor($B9DAFF);
Peru = TColor($3F85CD);
Pink = TColor($CBC0FF);
Plum = TColor
($DDA0DD);
PowderBlue = TColor($E6E0B0);
Purple = TColor($800080
);
RebeccaPurple = TColor($993366);
Red = TColor($0000FF);
RosyBrown
```

```

    = TColor($8F8FBC);
    RoyalBlue = TColor($E16941);
    SaddleBrown
    = TColor($13458B);
    Salmon = TColor($7280FA);
    SandyBrown = TColor
    ($60A4F4);
    SeaGreen = TColor($578B2E);
    SeaShell = TColor($EEF5FF
    );
    Sienna = TColor($2D52A0);
    Silver = TColor($C0C0C0);
    SkyBlue
    = TColor($EBCE87);
    SlateBlue = TColor($CD5A6A);
    SlateGray = TColor
    ($908070);
    SlateGrey = TColor($908070);
    Snow = TColor($FAFAFF
    );
    SpringGreen = TColor($7FFF00);
    SteelBlue = TColor($B48246)
    ;
    Tan = TColor($8CB4D2);
    Teal = TColor($808000);
    Thistle = TColor
    ($D8BFD8);
    Tomato = TColor($4763FF);
    Turquoise = TColor($D0E040
    );
    Violet = TColor($EE82EE);
    Wheat = TColor($B3DEF5);
    White
    = TColor($FFFFFF);
    WhiteSmoke = TColor($F5F5F5);
    Yellow = TColor
    ($00FFFF);
    YellowGreen = TColor($32CD9A);
    MoneyGreen = TColor
    ($C0DCC0);
    Cream = TColor($F0FBFF);
    MedGray = TColor($A4A0A0)
    ;
    LtGray = TColor($C0C0C0);
    DkGray = TColor($808080);
case Integer
  of
0: (
public
  R : Byte;
  G : Byte;
  B : Byte;
  A : Byte;
)

```

```

;
1: (
public
  Color : TColor;
);
end

```

76.3.1 Method overview

Page	Method	Description
1614	<code>assign(TColorRec):TColor</code>	
1614	<code>assign(TColor):TColorRec</code>	

76.3.2 TColorRec.assign(TColor):TColorRec

Declaration: `TColorRec.class operator :=(AColor: TColor) : TColorRec`

Visibility: public

76.3.3 TColorRec.assign(TColorRec):TColor

Declaration: `TColorRec.class operator :=(AColor: TColorRec) : TColor`

Visibility: public

Chapter 77

Reference for unit 'sysutils'

77.1 Used units

Table 77.1: Used units by unit 'sysutils'

Name	Page
errors	722
Linux	957
sysconst	??
System	1339
Unix	2089
unixtype	2127

77.2 Overview

This documentation describes the `sysutils` unit. The `sysutils` unit was started by Gertjan Schouten, and completed by Michael Van Canneyt. It aims to be compatible to the Delphi `sysutils` unit, but in contrast with the latter, it is designed to work on multiple platforms. It is implemented on all supported platforms.

77.3 Type Helpers for basic types

The `sysutils` unit contains type helpers for basic language types: boolean, ordinals (shortint, smallint, byte, word, integer, cardinal, int64, wqord, nativeint, nativeuint), strings, floating-point and GUID values. They can be used as-is, or they can be descended from to form your own type helpers.

See also: `TGuidHelper` ([1850](#)), `TStringHelper` ([1895](#)), `TByteHelper` ([1824](#)), `TShortIntHelper` ([1879](#)), `TSmallIntHelper` ([1891](#)), `TWordHelper` ([1929](#)), `TCardinalHelper` ([1828](#)), `TIntegerHelper` ([1856](#)), `TInt64Helper` ([1852](#)), `TQWordHelper` ([1875](#)), `TNativeIntHelper` ([1867](#)), `TBooleanHelper` ([1820](#)), `TByteBoolHelper` ([1822](#)), `TWordBoolHelper` ([1927](#)), `TLongBoolHelper` ([1861](#)), `TSingleHelper` ([1885](#)), `TDoubleHelper` ([1832](#)), `TExtendedHelper` ([1844](#))

77.4 Localization support

Localization support depends on various constants and structures being initialized correctly. On Windows and OS/2 this is done automatically: a widestring manager is installed by default which helps taking care of the current locale when performing various operations on strings. The various internationalization settings (date/time format, currency, language etc) are also initialized correctly on these platforms.

On Unixes, the widestring support is in a separate unit: `cwstring`, which loads the various needed functions from the C library. It should be added manually to the `uses` clause of your program. No internationalization (or localisation) settings are applied by this unit, these must be initialized separately by including the `locale` unit in the `uses` clause of your program.

77.5 Unicode and codepage awareness

The many functions that deal with filenames in the `sysutils` routines have been changed from `AnsiString` to `RawByteString` so they do not perform implicit codepage conversions to the ANSI code page. At the same time, overloaded versions that accept a Unicode string have been created.

For routines that access actual OS functions using single-byte string APIs, the strings are converted to ensure that the OS routine receives a string with the correct encoding when using single-byte strings. This encoding is normally the `DefaultFileSystemCodePage` (1418) encoding.

On systems with a Unicode I/O API (2-byte strings), the native API is used, meaning that Unicode strings will be passed on as-is, but single-byte strings will be converted (implicitly) to Unicode.

The following is a minimal list of functions that have been changed and duplicated:

Table 77.2:

Name	Description
<code>FileCreate</code> (1694)	Create a new file and return a handle to it.
<code>FileOpen</code> (1700)	Open an existing file and return a file handle
<code>FileExists</code> (1696)	Check whether a particular file exists in the file system.
<code>DirectoryExists</code> (1681)	Check whether a directory exists in the file system.
<code>FileSetDate</code> (1703)	Set the date of a file.
<code>FileGetAttr</code> (1697)	Return attributes of a file.
<code>FileSetAttr</code> (1703)	Set the attributes of a file.
<code>DeleteFile</code> (1680)	Delete a file from the file system.
<code>RenameFile</code> (1743)	Rename a file.
<code>FileSearch</code> (1701)	Search for a file in a path.
<code>ExeSearch</code> (1687)	Search for an executable
<code>FindFirst</code> (1705)	Start a file search and return a findhandle
<code>FindNext</code> (1707)	Find the next entry in a findhandle.
<code>FindClose</code> (1705)	Close a find handle
<code>FileIsReadOnly</code> (1699)	Check whether a file is read-only.
<code>GetCurrentDir</code> (1725)	Return the current working directory of the application.
<code>SetCurrentDir</code> (1746)	Set the current directory of the application.

The following functions do not interact with the OS, but may nevertheless change the codepage of the strings involved in their operation:

Table 77.3:

Name	Description
ChangeFileExt (1667)	Change the extension of a filename.
ExtractFilePath (1692)	Extract the path from a filename.
ExtractFileDrive (1691)	Extract the drive part from a filename.
ExtractFileName (1691)	Extract the filename part from a full path filename.
ExtractFileExt (1691)	Return the extension from a filename.
ExtractFileDir (1690)	Extract the drive and directory part of a filename.
ExtractShortPathName (1693)	Returns a 8.3 path name
ExpandFileName (1688)	Expand a relative filename to an absolute filename.
ExpandFileNameCase (1688)	Expand a filename entered as case insensitive to the full path as stored on the disk.
ExtractRelativepath (1692)	Extract a relative path from a filename, given a base directory.
ExpandUNCFileName (1689)	Expand a relative filename to an absolute UNC filename.
IncludeTrailingPathDelimiter (1734)	Add trailing directory separator to a pathname, if needed.
IncludeTrailingBackslash (1733)	Add trailing directory separator to a pathname, if needed.
ExcludeTrailingBackslash (1686)	Strip trailing directory separator from a pathname, if needed.
ExcludeTrailingPathDelimiter (1686)	Strip trailing directory separator from a pathname, if needed.
IncludeLeadingPathDelimiter (1733)	Prepend a path delimiter if there is not already one.
ExcludeLeadingPathDelimiter (1686)	Strip the leading path delimiter of a path
IsPathDelimiter (1738)	Is the character at the given position a pathdelimiter ?
DoDirSeparators (1682)	Convert known directory separators to the current directory separator.
SetDirSeparators (1747)	Set the directory separators to the known directory separators.
GetDirs (1726)	Return a list of directory names from a path.
ConcatPaths (1671)	Concatenate an array of paths to form a single path
GetEnvironmentVariable (1727)	Return the value of an environment variable.

77.6 Miscellaneous conversion routines

Functions for various conversions.

Table 77.4:

Name	Description
BCDToInt (1664)	Convert BCD number to integer
CompareMem (1668)	Compare two memory regions
FloatToStrF (1709)	Convert float to formatted string
FloatToStr (1708)	Convert float to string
FloatToText (1711)	Convert float to string
FormatFloat (1722)	Format a floating point value
GetDirs (1726)	Split string in list of directories
IntToHex (1735)	return hexadecimal representation of integer
IntToStr (1736)	return decimal representation of integer
StrToIntDef (1770)	Convert string to integer with default value
StrToInt (1769)	Convert string to integer
StrToFloat (1768)	Convert string to float
TextToFloat (1776)	Convert null-terminated string to float

77.7 Date/time routines

Functions for date and time handling.

Table 77.5:

Name	Description
<code>DateTimeToFileDate</code> (1674)	Convert <code>DateTime</code> type to file date
<code>DateTimeToStr</code> (1674)	Construct string representation of <code>DateTime</code>
<code>DateTimeToString</code> (1675)	Construct string representation of <code>DateTime</code>
<code>DateTimeToSystemTime</code> (1676)	Convert <code>DateTime</code> to system time
<code>DateTimeToTimeStamp</code> (1677)	Convert <code>DateTime</code> to timestamp
<code>DateToStr</code> (1677)	Construct string representation of date
<code>Date</code> (1673)	Get current date
<code>DayOfWeek</code> (1678)	Get day of week
<code>DecodeDate</code> (1679)	Decode <code>DateTime</code> to year month and day
<code>DecodeTime</code> (1679)	Decode <code>DateTime</code> to hours, minutes and seconds
<code>EncodeDate</code> (1683)	Encode year, day and month to <code>DateTime</code>
<code>EncodeTime</code> (1684)	Encode hours, minutes and seconds to <code>DateTime</code>
<code>FormatDateTime</code> (1721)	Return string representation of <code>DateTime</code>
<code>IncMonth</code> (1734)	Add 1 to month
<code>IsLeapYear</code> (1737)	Determine if year is leap year
<code>MSecsToTimeStamp</code> (1741)	Convert nr of milliseconds to timestamp
<code>Now</code> (1742)	Get current date and time
<code>StrToDateTime</code> (1766)	Convert string to <code>DateTime</code>
<code>StrToDate</code> (1764)	Convert string to date
<code>StrToTime</code> (1771)	Convert string to time
<code>SystemTimeToDateTime</code> (1775)	Convert system time to datetime
<code>TimeStampToDateTime</code> (1777)	Convert time stamp to <code>DateTime</code>
<code>TimeStampToMSecs</code> (1778)	Convert <code>TimeStamp</code> to number of milliseconds
<code>TimeToStr</code> (1778)	return string representation of <code>Time</code>
<code>Time</code> (1777)	Get current time

77.8 File Name handling routines

Functions for file manipulation.

Table 77.6:

Name	Description
AnsiCompareFileName (1649)	Compare 2 filenames
AnsiLowerCaseFileName (1654)	Create lowercase filename
AnsiUpperCaseFileName (1662)	Create uppercase filename
AddDisk (1648)	Add disk to list of disk drives
ChangeFileExt (1667)	Change extension of file name
CreateDir (1671)	Create a directory
DeleteFile (1680)	Delete a file
DiskFree (1681)	Free space on disk
DiskSize (1682)	Total size of disk
ExpandFileName (1688)	Create full file name
ExpandFileNameCase (1688)	Create full file name case insensitively
ExpandUNCFileName (1689)	Create full UNC file name
ExtractFileDir (1690)	Extract drive and directory part of filename
ExtractFileDrive (1691)	Extract drive part of filename
ExtractFileExt (1691)	Extract extension part of filename
ExtractFileName (1691)	Extract name part of filename
ExtractFilePath (1692)	Extract path part of filename
ExtractRelativePath (1692)	Construct relative path between two files
FileAge (1693)	Return file age
FileDateToDateTime (1696)	Convert file date to system date
FileExists (1696)	Determine whether a file exists on disk
FileGetAttr (1697)	Get attributes of file
FileGetDate (1698)	Get date of last file modification
FileSearch (1701)	Search for file in path
FileSetAttr (1703)	Get file attributes
FileSetDate (1703)	Get file dates
FindFirst (1705)	Start finding a file
FindNext (1707)	Find next file
GetCurrentDir (1725)	Return current working directory
RemoveDir (1743)	Remove a directory from disk
RenameFile (1743)	Rename a file on disk
SameFileName (1745)	Check whether 2 filenames are the same
SetCurrentDir (1746)	Set current working directory
SetDirSeparators (1747)	Set directory separator characters
FindClose (1705)	Stop searching a file
DoDirSeparators (1682)	Replace directory separator characters

77.9 File input/output routines

Functions for reading/writing to file.

Table 77.7:

Name	Description
FileCreate (1694)	Create a file and return handle
FileOpen (1700)	Open file end return handle
FileRead (1701)	Read from file
FileSeek (1702)	Set file position
FileTruncate (1704)	Truncate file length
FileWrite (1704)	Write to file
FileClose (1694)	Close file handle

77.10 PChar related functions

Most PChar functions are the same as their counterparts in the **STRINGS** unit. The following functions are the same :

1. StrCat (1750) : Concatenates two PChar strings.
2. StrComp (1751) : Compares two PChar strings.
3. StrCopy (1751) : Copies a PChar string.
4. StrECopy (1752) : Copies a PChar string and returns a pointer to the terminating null byte.
5. StrEnd (1753) : Returns a pointer to the terminating null byte.
6. StrLComp (1754) : Case insensitive compare of 2 PChar strings.
7. StrLCat (1755) : Appends at most L characters from one PChar to another PChar.
8. StrLComp (1756) : Case sensitive compare of at most L characters of 2 PChar strings.
9. StrLCopy (1757) : Copies at most L characters from one PChar to another.
10. StrLen (1757) : Returns the length (exclusive terminating null byte) of a PChar string.
11. StrLComp (1759) : Case insensitive compare of at most L characters of 2 PChar strings.
12. StrLower (1759) : Converts a PChar to all lowercase letters.
13. StrMove (1760) : Moves one PChar to another.
14. StrNew (1760) : Makes a copy of a PChar on the heap, and returns a pointer to this copy.
15. StrPos (1762) : Returns the position of one PChar string in another?
16. StrRScan (1762) : returns a pointer to the last occurrence of on PChar string in another one.
17. StrScan (1763) : returns a pointer to the first occurrence of on PChar string in another one.
18. StrUpper (1774) : Converts a PChar to all uppercase letters.

The subsequent functions are different from their counterparts in **STRINGS**, although the same examples can be used.

77.11 Date and time formatting characters

Various date and time formatting routines accept a format string to format the date and or time. The following characters can be used to control the date and time formatting:

c Formats date using `shortdateformat` and formats time using `longtimeformat` if the time is not zero.

f Same as **c**, but adds the time even if it is zero.

d day of month

dd day of month (leading zero)

ddd day of week (abbreviation)

dddd day of week (full)

dddddd `shortdateformat`

ddddddd `longdateformat`

m month or minutes if preceded by **h** or **hh** specifiers.

mm month or minutes if preceded by **h** or **hh** specifiers, with leading zero.

mmm month (abbreviation)

mmmm month (full)

y year (2 digits)

yy year (two digits)

yyyy year (with century)

h hour

hh hour (leading zero)

n minute

nn minute (leading zero)

s second

ss second (leading zero)

t `shorttimeformat`

tt `longtimeformat`

am/pm use 12 hour clock and display am and pm accordingly

a/p use 12 hour clock and display a and p accordingly

/ insert date separator

: insert time separator

"xx" literal text

'xx' literal text

z milliseconds

zzz milliseconds(leading zero)

[h] hours including the hours of the full days (i.e. can be > 24).

[hh] hours with leading zero, including the hours of the full days (i.e. can be > 24)

[n] minutes including the minutes of the full hours and days

[nn] minutes with leading zero, including the minutes of the full hours and days

[s] seconds including the seconds of the full minutes, hours and days.

[ss] seconds with leading zero, including the seconds of the full minutes, hours and days.

The forms in square brackets are only allowed if the `fdoInterval` (1637) option is included in the `Options` argument of `FormatDateTime`.

The date and time separators are taken from the `DefaultFormatSettings` (1644) record, unless a `TFormatSettings` (1637) record is passed to the `FormatDateTime` (1721) function.

Note that to include any of the above characters literally in the result string, they must be enclosed in double quotes.

See also: `DefaultFormatSettings` (1644), `TFormatSettings` (1637), `FormatDateTime` (1721), `TFormatDateTimeOption` (1637)

77.12 Formatting strings

Functions for formatting strings.

Table 77.8:

Name	Description
<code>AdjustLineBreaks</code> (1649)	Convert line breaks to line breaks for system
<code>FormatBuf</code> (1720)	Format a buffer
<code>Format</code> (1714)	Format arguments in string
<code>FmtStr</code> (1713)	Format buffer
<code>QuotedStr</code> (1742)	Quote a string
<code>StrFmt</code> (1753)	Format arguments in a string
<code>StrLFmt</code> (1758)	Format maximum L characters in a string
<code>TrimLeft</code> (1779)	Remove whitespace at the left of a string
<code>TrimRight</code> (1780)	Remove whitespace at the right of a string
<code>Trim</code> (1779)	Remove whitespace at both ends of a string

77.13 String functions

Functions for handling strings.

Table 77.9:

Name	Description
AnsiCompareStr (1650)	Compare two strings
AnsiCompareText (1651)	Compare two strings, case insensitive
AnsiExtractQuotedStr (1652)	Removes quotes from string
AnsiLastChar (1653)	Get last character of string
AnsiLowerCase (1653)	Convert string to all-lowercase
AnsiQuotedStr (1654)	Quotes a string
AnsiStrComp (1655)	Compare strings case-sensitive
AnsiStrIComp (1656)	Compare strings case-insensitive
AnsiStrLComp (1658)	Compare L characters of strings case sensitive
AnsiStrLIComp (1658)	Compare L characters of strings case insensitive
AnsiStrLastChar (1657)	Get last character of string
AnsiStrLower (1659)	Convert string to all-lowercase
AnsiStrUpper (1661)	Convert string to all-uppercase
AnsiUpperCase (1661)	Convert string to all-uppercase
AppendStr (1662)	Append 2 strings
AssignStr (1663)	Assign value of strings on heap
CompareStr (1669)	Compare two strings case sensitive
CompareText (1670)	Compare two strings case insensitive
DisposeStr (1682)	Remove string from heap
IsValidIdent (1738)	Is string a valid pascal identifier
LastDelimiter (1739)	Last occurrence of character in a string
LeftStr (1739)	Get first N characters of a string
LoadStr (1740)	Load string from resources
LowerCase (1740)	Convert string to all-lowercase
NewStr (1741)	Allocate new string on heap
RightStr (1745)	Get last N characters of a string
StrAlloc (1749)	Allocate memory for string
StrBufSize (1749)	Reserve memory for a string
StrDispose (1752)	Remove string from heap
StrPas (1761)	Convert PChar to pascal string
StrPCopy (1761)	Copy pascal string
StrPLCopy (1762)	Copy N bytes of pascal string
UpperCase (1790)	Convert string to all-uppercase

77.14 Constants, types and variables

77.14.1 Constants

`ConfigExtension : string = '.cfg'`

`ConfigExtension` is the default extension used by the `GetAppConfigFile (1725)` call. It can be set to any valid extension for the current OS.

`CPUEndian = TEndian.Little`

`CPUEndian` describes whether the current CPU is little or big endian.

`DateDelta = 693594`

Days between 1/1/0001 and 12/31/1899

`DriveDelim = DriveSeparator`

`DriveDelim` refers to the system unit's `DriveSeparator` constant, it is for Delphi compatibility only.

`EmptyStr : string = ''`

Empty String Constant

`EmptyWideStr : WideString = ''`

Empty wide string.

`faAnyFile = $000001FF`

Use this attribute in the `FindFirst` (1705) call to find all matching files.

`faArchive = $00000020`

Attribute of a file, meaning the file has the archive bit set. Used in `TSearchRec` (1640) and `FindFirst` (1705)

`faCompressed = $00000800platform`

`faTemporary` can be returned by `FindFirst` (1705) or `FindNext` (1707) to indicate that a returned file is compressed (on file systems that support this).

`faDirectory = $00000010`

Attribute of a file, meaning the file is a directory. Used in `TSearchRec` (1640) and `FindFirst` (1705)

`faEncrypted = $00004000platform`

`faEncrypted` can be returned by `FindFirst` (1705) or `FindNext` (1707) to indicate that a returned file is encrypted (on file systems that support this).

`faHidden = $00000002platform`

Attribute of a file, meaning the file is read-only. Used in `TSearchRec` (1640) and `FindFirst` (1705)

`faNormal = $00000080`

`faNormal` can be used in `FindFirst` (1705) to indicate that normal files must be included in the result.

`faReadOnly = $00000001`

Attribute of a file, meaning the file is read-only. Used in `TSearchRec` (1640) and `FindFirst` (1705)

`faSymLink = $00000400platform`

`faSymLink` means the file (as returned e.g. by `FindFirst (1705)`/`FindNext (1707)`), is a symlink. It's ignored under Windows.

`faSysFile = $00000004platform`

Attribute of a file, meaning the file is a system file. Used in `TSearchRec (1640)` and `FindFirst (1705)`

`faTemporary = $00000100platform`

`faTemporary` can be returned by `FindFirst (1705)` or `FindNext (1707)` to indicate that a returned file is a temporary file.

`faVirtual = $00010000platform`

`faVirtual` can be returned by `FindFirst (1705)` or `FindNext (1707)` to indicate that a returned file is virtual (on file systems that support this).

`faVolumeId = $00000008deprecated; platform`

Attribute of a file, meaning the entry contains the volume ID. Used in `TSearchRec (1640)` and `FindFirst (1705)`

`feInvalidHandle = THandle(- 1)`

`feInvalidHandle` is the return value of `FileOpen (1700)` in case of an error.

`fmOpenRead = $0000`

`fmOpenRead` is used in the `FileOpen (1700)` call to open a file in read-only mode.

`fmOpenReadWrite = $0002`

`fmOpenReadWrite` is used in the `FileOpen (1700)` call to open a file in read-write mode.

`fmOpenWrite = $0001`

`fmOpenWrite` is used in the `FileOpen (1700)` call to open a file in write-only mode.

`fmShareCompat = $0000`

`fmOpenShareCompat` is used in the `FileOpen (1700)` call OR-ed together with one of `fmOpenReadWrite (1625)`, `fmOpenRead (1625)` or `fmOpenWrite (1625)`, to open a file in a sharing modus that is equivalent to sharing implemented in MS-DOS.

`fmShareDenyNone = $0040`

`fmShareDenyNone` is used in the `FileOpen (1700)` call OR-ed together with one of `fmOpenReadWrite (1625)`, `fmOpenRead (1625)` or `fmOpenWrite (1625)`, to open a file so other processes can read/write the file as well.

`fmShareDenyRead = $0030`

`fmOpenShareRead` is used in the `FileOpen` (1700) call OR-ed together with one of `fmOpenReadWrite` (1625), `fmOpenRead` (1625) or `fmOpenWrite` (1625), to open a file so other processes cannot read from it.

This constant only works on Windows, because other operating systems do not support this constants.

`fmShareDenyWrite = $0020`

`fmOpenShareDenyWrite` is used in the `FileOpen` (1700) call OR-ed together with one of `fmOpenReadWrite` (1625), `fmOpenRead` (1625) or `fmOpenWrite` (1625), to open a file so other processes cannot write to it, they can only read.

`fmShareExclusive = $0010`

`fmOpenShareExclusive` is used in the `FileOpen` (1700) call OR-ed together with one of `fmOpenReadWrite` (1625), `fmOpenRead` (1625) or `fmOpenWrite` (1625), to open a file exclusively.

`fsFromBeginning = 0`

`fsFromBeginning` is used to indicate in the `FileSeek` (1702) call that a seek operation should be started at the start of the file.

`fsFromCurrent = 1`

`fsFromBeginning` is used to indicate in the `FileSeek` (1702) call that a seek operation should be started at the current position in the file.

`fsFromEnd = 2`

`fsFromBeginning` is used to indicate in the `FileSeek` (1702) call that a seek operation should be started at the last position in the file.

`GUID_NULL : TGuid = '{00000000-0000-0000-0000-000000000000}'`

NULL GUID constant

`HexDisplayPrefix : string = '$'`

`HexDisplayPrefix` is used by the formatting routines to indicate that the number which follows the prefix is in Hexadecimal notation.

`HoursPerDay = 24`

Number of hours in a day.

`JulianEpoch = TDateTime(- 2415018.5)`

Starting point of the Julian calendar

`LeadBytes : Set of Char = []`

LeadBytes contains the set of bytes that serve as lead byte in a MBCS string.

MaxCurrency : Currency = 922337203685477.5807

Maximum currency value

MaxDateTime : TDateTime = 2958465.999999999

Maximum TDateTime value.

MAX_PATH = MaxPathLen

MAX_PATH is the maximum number of characters that a filename (including path) can contain on the current operating system.

MinCurrency : Currency = - 922337203685477.5808

Minimum Currency value

MinDateTime : TDateTime = - 693593.999999999

Minimum TDateTime value.

MinsPerDay = HoursPerDay * MinsPerHour

Number of minutes per day.

MinsPerHour = 60

Number of minutes per hour.

MonthDays : Array[Boolean] of TDayTable = ((31, 28, 31, 30, 31, 30
 , 31, 31, 30, 31, 30, 31), (31, 29, 31, 30, 31, 30, 31, 31, 30, 31
 , 30, 31))

Array with number of days in the months for leap and non-leap years.

MSecsPerDay = SecsPerDay * MSecsPerSec

Number of milliseconds per day

MSecsPerSec = 1000

Number of milliseconds per second

NullStr : PString = @ EmptyStr

Pointer to an empty string

PathDelim = DirectorySeparator

`PathDelim` refers to the system unit's `DirectorySeparator` constant, it is for Delphi compatibility only.

`PathSep = PathSeparator`

`PathSep` refers to the system unit's `PathSeparator` constant, it is for Delphi compatibility only.

`pfBCB4Produced = $08000000`

Not used in Free Pascal.

`pfDelphi4Produced = $0C000000`

Not used in Free Pascal.

`pfDesignOnly = $00000002`

Package is a design-time only package

`pfExeModule = $00000000`

Package is an executable

`pfIgnoreDupUnits = $00000008`

Ignore duplicate units in package

`pfLibraryModule = $80000000`

Package is a library

`pfModuleTypeMask = $C0000000`

Mask for module type flags

`pfNeverBuild = $00000001`

Never-build flag was specified when compiling package

`pfPackageModule = $40000000`

Package is a real package (not exe)

`pfProducerMask = $0C000000`

Mask for producer flags

`pfProducerUndefined = $04000000`

Not used in Free Pascal.

`pfRunOnly = $00000004`

Package is a run-time only package

`pfV3Produced = $00000000`

Not used in Free Pascal.

`RTL_SIGBUS = 4`

Bus error signal number (Unix only)

`RTL_SIGDEFAULT = - 1`

Default signal handler (Unix only)

`RTL_SIGFPE = 1`

Floating Point Error signal number (Unix only)

`RTL_SIGILL = 3`

Illegal instruction signal number (Unix only)

`RTL_SIGINT = 0`

INTERRUPT signal number (Unix only)

`RTL_SIGLAST = RTL_SIGQUIT`

Last signal number (Unix only)

`RTL_SIGQUIT = 5`

QUIT signal number (Unix only)

`RTL_SIGSEGV = 2`

Segmentation fault signal number (Unix only)

`SecsPerDay = MinsPerDay * SecsPerMin`

Number of seconds per day

`SecsPerHour = SecsPerMin * MinsPerHour`

`SecsPerHour` is a constant indicating the number of seconds in an hour (3600).

`SecsPerMin = 60`

Number of seconds per minute

```
SwitchChars = ['-']
```

The characters in this set will be used by the `FindCmdLineSwitch` (1705) function to determine whether a command-line argument is a switch (an option) or a value. If the first character of an argument is in `SwitchChars`, it will be considered an option or switch.

```
SysConfigDir : string = ''
```

`SysConfigDir` is the default system configuration directory. It is set at application startup by the `sysutils` initialization routines.

This directory may be returned by the `GetAppConfigDir` (1724) call on some systems.

```
ufImplicitUnit = $10
```

Unit was implicitly imported into package (did not appear in package contains list)

```
ufMainUnit = $01
```

Unit is the main unit of the package

```
ufOrgWeakUnit = $08
```

Unit is the original weak packaged unit

```
ufPackageUnit = $02
```

Unit is a packaged unit (appeared in package contains list)

```
ufWeakPackageUnit = ufPackageUnit or ufWeakUnit
```

Weak (original or not) packaged unit

```
ufWeakUnit = $04
```

Unit is a weak packaged unit

```
UnixDateDelta = Trunc(UnixEpoch)
```

Number of days between 1.1.1900 and 1.1.1970

```
UnixEpoch = JulianEpoch + TDateTime(2440587.5)
```

Starting point of the unix calendar (1/1/1970)

77.14.2 Types

```
EHeapException = EHeapMemoryError
```

`EHeapMemoryError` is raised when an error occurs in the heap management routines.

```
ExceptClass = class of Exception
```

ExceptClass is a [Exception \(1808\)](#) class reference.

```
Int128Rec = packed record
case Integer of
0: (
public
  Lo : QWord
  ;
  Hi : QWord;
);
1: (
public
  DWords : Array[0..3] of DWord;
)
  ;
2: (
public
  Words : Array[0..7] of Word;
);
3: (
public
  Bytes
    : Array[0..15] of Byte;
);
end
```

Int128Rec is a record defining a 128-bit integer. It is made up of 2 QWords or 4 DWords or 8 words or 16 bytes.

```
Int64Rec = packed record
case Integer of
0: (
public
  Lo : Cardinal
  ;
  Hi : Cardinal;
);
1: (
public
  Words : Array[0..3] of Word;
);
2: (
public
  Bytes : Array[0..7] of Byte;
);
end
```

Int64Rec can be used to extract the parts of a Int64: the high and low cardinal, or a zero-based array of 4 words, or a zero based array of 8 bytes. Note that the meaning of the High and Low parts are different on various CPUs.

```
LongRec = packed record
```



```

case Integer of
0: (
public
  Lo : Word;
  Hi : Word;
);
1: (
public
  Bytes : Array[0..3] of Byte;
);
end

```

LongRec can be used to extract the parts of an long Integer: the high and low word, or the 4 separate bytes as a zero-based array of bytes. Note that the meaning (or ordering) of High and Low parts are different on various CPUs, and may differ from what is shown in the declaration: the ordering depends on the endianness of the CPU.

```

OWordRec = packed record
case Integer of
0: (
public
  Lo : QWord
  ;
  Hi : QWord;
);
1: (
public
  DWords : Array[0..3] of DWord;
)
  ;
2: (
public
  Words : Array[0..7] of Word;
);
3: (
public
  Bytes
    : Array[0..15] of Byte;
);
end

```

OWordRec is a record defining a 128-bit integer. It is made up of 2 QWords or 4 DWords or 8 words or 16 bytes.

```
PByteArray = ^TByteArray
```

Generic pointer to TByteArray ([1633](#)). Use to access memory regions as a byte array.

```
PDayTable = ^TDayTable
```

Pointer to TDayTable type.

PString = ObjPas.PString

Pointer to a anistring

PSysCharSet = ^TSysCharSet

Pointer to TSysCharSet ([1641](#)) type.

PWordarray = ^TWordArray

Generic pointer to TWordArray ([1642](#)). Use to access memory regions as a word array.

TArray<T> = Array of T

TArray is a generic array. It can be used to define dynamic arrays in generic functions or classes.

This definition is provided for Delphi compatibility only, it is not needed in Free Pascal, where 2 array types are equal if their element types are equal.

TBeepHandler = procedure

TBeepHandler is the prototype used by the OnBeep ([1645](#)) handler. This in turn is called by the Beep ([1664](#)) call to actually implement the beep functionality. The call takes no arguments.

TByteArray = Array[0..32767] of Byte

TByteArray is a generic array definition, mostly for use as a base type of the PByteArray ([1632](#)) type.

TByteBitIndex = 0..7

TByteBitIndex is the range of allowed bit indexes for a 8-bit unsigned integer type, it is used in the 8-bit helper TByteHelper ([1824](#)).

TBytes = Array of Byte

TBytes defines a dynamic array of bytes. This can be used to typecast e.g. strings to manipulate them byte for byte.

TCardinalBitIndex = 0..31

TIntegerBitIndex is the range of allowed bit indexes for a 32-bit unsigned integer type, it is used in the 32-bit helper TCardinalHelper ([1828](#)).

TCharArray = Array of Char

TCharArray is a dynamic array of characters.

TCompareOption = system.TCompareOption

TCompareOption is an alias for System.TCompareOption ([1388](#)).

`TCompareOptions = system.TCompareOptions`

`TCompareOptions` is an alias for `System.TCompareOptions` ([1389](#)).

`TCreateGUIDFunc = function(out GUID: TGuid) : Integer`

`TCreateGUIDFunc` is the prototype for a GUID creation handler. On return, the `GUID` argument should contain a new (unique) GUID. The return value of the function should be zero for success, nonzero for failure.

`TDayTable = Array[1..12] of Word`

Array of day names.

`TEndian = ObjPas.TEndian`

`TEndian` indicates whether the platform is little endian (LSB first), or big endian (MSB first).

`TEventType = (etCustom, etInfo, etWarning, etError, etDebug)`

Table 77.10: Enumeration values for type `TEventType`

Value	Explanation
<code>etCustom</code>	Custom log event, with application-specific meaning
<code>etDebug</code>	Debug message.
<code>etError</code>	Error condition message
<code>etInfo</code>	General information event message
<code>etWarning</code>	Warning message

`TEventType` is a type to be used by logging mechanisms (in particular, the `TCustomApplication` and `TEventLog` classes. It can be used to filter events, and write only certain types of event to the event log.

`TEventTypes = Set of TEventType`

`TEventTypes` is a set type of `TEventType`, defined for convenience. It is used in the custom application classes for logging purposes.

`TExecuteFlags= Set of (ExecInheritsHandles)`

Table 77.11: Enumeration values for type

Value	Explanation
<code>ExecInheritsHandles</code>	The new process inherits all (file) handles owned by the current process

`TExecuteFlags` is a set of flags to influence the behaviour of the `ExecuteProcess` ([1687](#)) call.

```
TFileName = string
```

TFileName is used in the TSearchRec (1640) definition.

```
TFilenameCaseMatch = (mkNone, mkExactMatch, mkSingleMatch, mkAmbiguous
)
```

Table 77.12: Enumeration values for type TFilenameCaseMatch

Value	Explanation
mkAmbiguous	More than one file will match the filename in a case-insensitive way
mkExactMatch	The filename can be used to refer to a file on the system (findFirst will find it).
mkNone	No file was found
mkSingleMatch	Exactly one match was found, but case didn't match.

TFilenameCaseMatch describes how ExpandFileNameCase (1688) found the file.

```
TFilenameCaseMatch = (mkNone, mkExactMatch, mkSingleMatch, mkAmbiguous
)
```

Table 77.13: Enumeration values for type TFilenameCaseMatch

Value	Explanation
mkAmbiguous	More than one file will match the filename in a case-insensitive way
mkExactMatch	The filename can be used to refer to a file on the system (findFirst will find it).
mkNone	No file was found
mkSingleMatch	Exactly one match was found, but case didn't match.

TFilenameCaseMatch describes how ExpandFileNameCase (1688) found the file.

```
TFileRec = FileRec
```

Alias for FileRec (1615) for Delphi compatibility.

```
TFileSearchOption = (sfoImplicitCurrentDir, sfoStripQuotes)
```

Table 77.14: Enumeration values for type TFileSearchOption

Value	Explanation
sfoImplicitCurrentDir	Always search the current directory first, even if it is not specified.
sfoStripQuotes	Strip quotes from the components in the search path.

TFileSearchOption enumerates the options that can be used in the FileSearch call to control the behaviour of the search mechanism

TFileSearchOptions = Set of TFileSearchOption

TFileSearchOptions is a set of TFileSearchOption (1635) values, used in the FileSearch (1701) call when searching for files.

TFloatFormat = (ffGeneral, ffExponent, ffFixed, ffNumber, ffCurrency)

Table 77.15: Enumeration values for type TFloatFormat

Value	Explanation
ffCurrency	Monetary format.
ffExponent	Scientific format.
ffFixed	Fixed point format.
ffGeneral	General number format.
ffNumber	Fixed point format with thousand separator

TFloatFormat is used to determine how a float value should be formatted in the FloatToText (1711) function.

```
TFloatRec = record
public
    Exponent : Integer;
    Negative : Boolean
;
    Digits : Array[0..18] of Char;
end
```

TFloatRec is used to describe a floating point value by the FloatToDecimal (1708) function.

TFloatValue = (fvExtended, fvCurrency, fvSingle, fvReal, fvDouble, fvComp)

Table 77.16: Enumeration values for type TFloatValue

Value	Explanation
fvComp	Comp value
fvCurrency	Currency value
fvDouble	Double value
fvExtended	Extended value
fvReal	Real value
fvSingle	Single value

TFloatValue determines which kind of value should be returned in the (untyped) buffer used by the TextToFloat (1776) function.

TFormatDateTimeOption = (fdoInterval)

Table 77.17: Enumeration values for type TFormatDateTimeOption

Value	Explanation
fdoInterval	Format the time as an interval, 24+hours are presented as such

TFormatDateTimeOption enumerates possible options to the FormatDateTime (1721) routine.

TFormatDateTimeOptions = Set of TFormatDateTimeOption

TFormatDateTimeOptions is a set of TFormatDateTimeOptions (1637), and is used in the last argument of FormatDateTime (1721)

```
TFormatSettings = record
public
  CurrencyFormat : Byte;
  NegCurrFormat
  : Byte;
  ThousandSeparator : Char;
  DecimalSeparator : Char;
  CurrencyDecimals : Byte;
  DateSeparator : Char;
  TimeSeparator
  : Char;
  ListSeparator : Char;
  CurrencyString : string;
  ShortDateFormat
  : string;
  LongDateFormat : string;
  TimeAMString : string;
  TimePMString
  : string;
  ShortTimeFormat : string;
  LongTimeFormat : string;
  ShortMonthNames : TMonthNameArray;
  LongMonthNames : TMonthNameArray
  ;
  ShortDayNames : TWeekNameArray;
  LongDayNames : TWeekNameArray
  ;
  TwoDigitYearCenturyWindow : Word;
end
```

TFormatSettings is a record that contains a copy of all variables which determine formatting in the various string formatting routines. It is used to pass local copies of these values to the various formatting routines in a thread-safe way.

TGetAppNameEvent = function : string

This callback type is used by the OnGetApplicationName (1646) to return an alternative application name.

TGetTempDirEvent = function(Global: Boolean) : string

Function prototype for OnGetTempDir (1646) handler.

```
TGetTempFileEvent = function(const Dir: string; const Prefix: string
)
                                : string
```

Function prototype for OnGetTempFile (1646) handler.

```
TGetVendorNameEvent = function : string
```

TGetVendorNameEvent is the function prototype for the OnGetVendorName (1646) callback, used by the VendorName (1790) function.

```
THandle = System.THandle
```

THandle refers to the definition of THandle in the system unit, and is provided for backward compatibility only.

```
TInt64BitIndex = 0..63
```

TInt64BitIndex is the range of allowed bit indexes for a 64-bit integer type, it is used in the 64-bit helper TInt64Helper (1852).

```
TIntegerBitIndex = 0..31
```

TIntegerBitIndex is the range of allowed bit indexes for a 32-bit signed integer type, it is used in the 32-bit helper TIntegerHelper (1856).

```
TIntegerSet = Set of
```

TIntegerSet is a generic integer subrange set definition whose size fits in a single integer.

```
TLocaleOptions = (loInvariantLocale, loUserLocale)
```

Table 77.18: Enumeration values for type TLocaleOptions

Value	Explanation
loInvariantLocale	Use system locale
loUserLocale	Use user locale

TLocaleOptions is used to indicate what locale should be used for some string operations such as UpperCase (1790), LowerCase (1740), CompareText (1670), SameText (1746). The following values are possible:

loInvariantLocale Use system locale

loUserLocale Use user locale

For consistent behaviour independent of the user or service applications use loInvariantLocale.

`TLongIntBitIndex = TIntegerBitIndex`

`TLongIntBitIndex` is the range of allowed bit indexes for a 32-bit signed integer type, it is used in the 32-bit helper `TLongintHelper` (1615).

`TMbcsByteType = (mbSingleByte, mbLeadByte, mbTrailByte)`

Table 77.19: Enumeration values for type `TMbcsByteType`

Value	Explanation
<code>mbLeadByte</code>	Uses lead-byte
<code>mbSingleByte</code>	Single bytes
<code>mbTrailByte</code>	Uses trailing byte

Type of multi-byte character set.

`TMonthNameArray = Array[1..12] of string`

`TMonthNameArray` is used in the month long and short name arrays.

`TNativeIntBitIndex = TInt64BitIndex`

`TNativeUIntBitIndex = TQwordBitIndex`

`TProcedure = procedure`

`TProcedure` is a general definition of a procedural callback.

`TQwordBitIndex = 0..63`

`TQwordBitIndex` is the range of allowed bit indexes for a 64-bit unsigned integer type, it is used in the 64-bit helper `TQWordHelper` (1875).

`TReplaceFlags= Set of (rfReplaceAll, rfIgnoreCase)`

Table 77.20: Enumeration values for type

Value	Explanation
<code>rfIgnoreCase</code>	Search case insensitive.
<code>rfReplaceAll</code>	Replace all occurrences of the search string with the replacement string.

`TReplaceFlags` determines the behaviour of the `StringReplace` (1755) function.

`TSearchRec = TRawbyteSearchRec`

TSearchRec is a search handle description record. It is initialized by a call to FindFirst (1705) and can be used to do subsequent calls to FindNext (1707). It contains the result of these function calls. It must be used to close the search sequence with a call to FindClose (1705).

Remark Not all fields of this record should be used. Some of the fields are for internal use only. (PathOnly for example, is only provided for Kylix compatibility)

TShortIntBitIndex = 0..7

TShortIntBitIndex is the range of allowed bit indexes for a 8-bit signed integer type, it is used in the 8-bit helper TShortIntHelper (1879).

TSignalState = (ssNotHooked, ssHooked, ssOverridden)

Table 77.21: Enumeration values for type TSignalState

Value	Explanation
ssHooked	A signal handler is set by the RTL code for the signal.
ssNotHooked	No signal handler is set for the signal.
ssOverridden	A signal handler was set for the signal by third-party code.

TSignalState indicates the state of a signal handler in a unix system for a particular signal.

TSmallIntBitIndex = 0..15

TSmallIntBitIndex is the range of allowed bit indexes for a 16-bit signed integer type, it is used in the 16-bit helper TSmallIntHelper (1891).

TStringArray = Array of string

TStringArray is a dynamic array of strings.

TStringBuilder = TAnsiStringBuilder

TStringSplitOptions = (None, ExcludeEmpty, ExcludeLastEmpty)

Table 77.22: Enumeration values for type TStringSplitOptions

Value	Explanation
ExcludeEmpty	Do not include empty strings in the result.
ExcludeLastEmpty	Only exclude the last element if it is empty
None	No options specified. The default

TStringSplitOptions describes the possible options for TStringHelper.Split (1912).

TSymLinkRec = TRawbyteSymLinkRec

TSymLinkRec contains information about the target of a symlink. Its actual type depends on the OS file API: it is either TRawbyteSymLinkRec (1796) or TUnicodeSymLinkRec (1798). Both types are used in the FileGetSymLinkTarget (1699) call.

TargetName #ShortDescr:

Size #ShortDescr:

Attr #ShortDescr:

Mode #ShortDescr:

TimeStamp #ShortDescr:

TSysCharSet = Set of AnsiChar

Generic set of characters type.

```
TSysLocale = record
public
  DefaultLCID : Integer;
  PriLangID :
    Integer;
  SubLangID : Integer;
case Byte of
1: (
public
  FarEast
    : Boolean;
  MiddleEast : Boolean;
);
2: (
public
  MBCS : Boolean
    ;
  RightToLeft : Boolean;
);
end
```

TSysLocale describes the current locale. If Fareast or MBCS is True, then the current locale uses a Multi-Byte Character Set. If MiddleEast or RightToLeft is True then words and sentences are read from right to left.

```
TSystemTime = record
public
  Year : Word;
  Month : Word;
  Day
    : Word;
  DayOfWeek : Word;
  Hour : Word;
  Minute : Word;
  Second
    : Word;
  MilliSecond : Word;
end
```

The System time structure contains the date/time in a human-understandable format.

```
TTerminateProc = function : Boolean
```

`TTerminateProc` is the procedural type which should be used when adding exit procedures.

```
TTextRec = TextRec
```

Alias for `TextRec` ([1615](#)) for Delphi compatibility.

```
TTimeStamp = record
public
  Time : LongInt;
  Date : LongInt;
end
```

`TTimeStamp` contains a timestamp, with the date and time parts specified as separate `TDateTime` values.

```
TUnicodeCharArray = Array of UnicodeChar
```

`TUnicodeCharArray` is a definition of an array of `UnicodeChar` elements.

```
TUseBoolStrs = (False, True)
```

Table 77.23: Enumeration values for type `TUseBoolStrs`

Value	Explanation
False	Numerical values should be used (0 and 1)
True	String representations should be used.

`TUseBoolStrs` is an enumerated type which indicates whether bool strs must be used when converting boolean to strings.

Because the identifiers `True` and `False` are already used for the system boolean type, You must use the scoped identifiers to get the `TUseBoolStrs` versions of these 2 identifiers. Failure to do so will result in an error.

```
TWeekNameArray = Array[1..7] of string
```

`TWeekNameArray` is used in the day long and short name arrays.

```
TWordArray = Array[0..16383] of Word
```

`TWordArray` is a generic array definition, mostly for use as a base type of the `PWordArray` ([1633](#)) type.

```
TWordBitIndex = 0..15
```

`TIntegerBitIndex` is the range of allowed bit indexes for a 16-bit unsigned integer type, it is used in the 16-bit helper `TWordHelper` (1929).

```
WordRec = packed record
public
  Lo : Byte;
  Hi : Byte;
end
```

`LongRec` can be used to extract the parts of a word: the high and low byte. Note that the meaning of the High and Low parts are different on various CPUs.

77.14.3 Variables

`CurrencyDecimals` : `Bytedeprecated`

`CurrencyDecimals` is the number of decimals to be used when formatting a currency. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.CurrencyFormat` (1644) instead.

`CurrencyFormat` : `Bytedeprecated`

`CurrencyFormat` is the default format string for positive currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.CurrencyFormat` (1644) instead.

`CurrencyString` : `stringdeprecated`

`CurrencyString` is the currency symbol for the current locale. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.CurrencyString` (1644) instead.

`DateSeparator` : `Chardeprecated`

`DateSeparator` is the character used by various date/time conversion routines as the character that separates the day from the month and the month from the year in a date notation. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.DateSeparator` (1644) instead.

`DecimalSeparator` : `Chardeprecated`

`DecimalSeparator` is used to display the decimal symbol in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.DecimalSeparator` (1644) instead.

```
DefaultFormatSettings : TFormatSettings = (CurrencyFormat: 1; NegCurrFormat
: 5; ThousandSeparator: ','; DecimalSeparator: '.'; CurrencyDecimals
: 2; DateSeparator: '-'; TimeSeparator: ':'; ListSeparator: ','; CurrencyString
: '$'; ShortDateFormat: 'd/m/y'; LongDateFormat: 'dd" "mmm" "yyyy'
; TimeAMString: 'AM'; TimePMString: 'PM'; ShortTimeFormat: 'hh:nn'
; LongTimeFormat: 'hh:nn:ss'; ShortMonthNames: ('Jan', 'Feb', 'Mar'
, 'Apr', 'May', 'Jun', 'Jul', 'Aug', 'Sep', 'Oct', 'Nov', 'Dec');
LongMonthNames: ('January', 'February', 'March', 'April', 'May',
'June', 'July', 'August', 'September', 'October', 'November', 'December'
); ShortDayNames: ('Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat'
); LongDayNames: ('Sunday', 'Monday', 'Tuesday', 'Wednesday', 'Thursday'
, 'Friday', 'Saturday'); TwoDigitYearCenturyWindow: 50)
```

`DefaultFormatSettings` contains the default settings for all type of formatting constants. If no thread-specific values are specified when a formatting function is called, this record is used as a default.

All other formatting constants refer to the fields of this variable using absolute addressing.

`FalseBoolStrs` : Array of string

`FalseBoolStrs` contains the strings that will result in a `False` return value by `StrToBool` (1763).

`FormatSettings` : `TFormatSettings`

`FormatSettings` is provided for Delphi compatibility, and refers to the `DefaultFormatSettings` (1644) variable.

`ListSeparator` : `Char` deprecated

`ListSeparator` is the character used in lists of values. It is locale dependent.

`LongDateFormat` : `string` deprecated

`LongDateFormat` contains a template to format a date in a long format. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.LongDateFormat` (1644) instead.

`LongDayNames` : `TWeekNameArray` deprecated

`LongDayNames` is an array with the full names of days. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

The array is indexed by values as returned by the `DayOfWeek` function.

This constant is deprecated. You should use `DefaultFormatSettings.LongDayNames` (1644) instead.

`LongMonthNames` : `TMonthNameArray` deprecated

`LongMonthNames` is an array with the full names of months. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.LongMonthNames` (1644) instead.

`LongTimeFormat` : `stringdeprecated`

`LongTimeFormat` contains a template to format a time in full notation. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.LongTimeFormat` (1644) instead.

`NegCurrFormat` : `Bytedeprecated`

`CurrencyFormat` is the default format string for negative currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default:

- 0** Left parenthesis, currency symbol, amount, right parenthesis. Ex: (\$1.2)
- 1** Negative sign, currency symbol, amount. Ex: -\$1.2
- 2** Monetary symbol, negative sign, amount. Ex: \$-1.2
- 3** Monetary symbol, amount, negative sign. Ex: \$1.2-
- 4** Left parenthesis, amount, currency symbol, right parenthesis. Ex: (1.2\$)
- 5** Negative sign, amount, currency symbol. Ex: -1.2\$
- 5** 6Amount, negative sign, currency symbol. Ex: 1.2-\$
- 5** 7Amount, currency symbol, negative sign. Ex: 1.2\$-
- 5** 8Negative sign, amount, space, currency symbol (as #5, adding a space before the currency symbol). Ex: -1.2 \$
- 9** Negative sign, currency symbol, space, amount (as #1, adding a space after the currency symbol). Ex: -\$ 1.2
- 10** Amount, space, currency symbol, negative sign (as #7, adding a space before the currency symbol). Ex: 1.2 \$-
- 11** Monetary symbol, space, amount, negative sign (as #3, adding a space after the currency symbol). Ex: \$ 1.2-
- 12** Monetary symbol, space, negative sign, amount (as #2, adding a space after the currency symbol). Ex: \$ -1.2
- 13** Amount, negative sign, space, currency symbol (as #6, adding a space before the currency symbol). Ex: 1.2- \$
- 14** Left parenthesis, currency symbol, space, amount, right parenthesis (as #0, adding a space after the currency symbol). Ex: (\$ 1.2)
- 15** Left parenthesis, amount, space, currency symbol, right parenthesis (as ##4, adding a space before the currency symbol). Ex: (1.2 \$)

`OnBeep` : `TBeepHandler = Nil`

`OnBeep` is called whenever `Beep` is called. `Beep` contains no implementation to actually produce a beep, since there is no way to implement beep in a meaningful way for all possible implementations.

`OnCreateGUID : TCreateGUIDFunc = Nil`

`OnCreateGUID` can be set to point to a custom routine that creates GUID values. If set, the `CreateGUID` (1672) function will use it to obtain a GUID value. If it is not set, a default implementation using random values will be used to create the unique value. The function should return a valid GUID in the `GUID` parameter, and should return zero in case of success.

`OnGetApplicationName : TGetAppNameEvent`

By default, the configuration file routines `GetAppConfigDir` (1724) and `GetAppConfigFile` (1725) use a default application name to construct a directory or filename. This callback can be used to provide an alternative application name.

Since the result of this callback will be used to construct a filename, care should be taken that the returned name does not contain directory separator characters or characters that cannot appear in a filename.

`OnGetTempDir : TGetTempDirEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempDir` (1730) function. Note that the returned name should have a trailing directory delimiter character.

`OnGetTempFile : TGetTempFileEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempFileName` (1730) function. Note that the values for `Prefix` and `Dir` should be observed.

`OnGetVendorName : TGetVendorNameEvent`

`OnGetVendorName` must be set in order for `VendorName` (1790) to return a value. It will then be used in `GetAppConfigDir` (1724) and `GetAppConfigFile` (1725) to determine the configuration directory. Set it to a callback that returns the actual vendor name for the application.

`OnShowException : procedure(Msg: ShortString)`

`OnShowException` is the callback that `ShowException` (1747) uses to display a message in a GUI application. For GUI applications, this variable should always be set. Note that no memory may be available when this callback is called, so the callback should already have all resources it needs, when the callback is set.

`ShortDateFormat : stringdeprecated`

`ShortDateFormat` contains a template to format a date in a short format. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ShortDateFormat` (1644) instead.

`ShortDayNames : TWeekNameArraydeprecated`

`ShortDayNames` is an array with the abbreviated names of days. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

The array is indexed by values as returned by the `DayOfWeek` function.

This constant is deprecated. You should use `DefaultFormatSettings.ShortDayNames` (1644) instead.

`ShortMonthNames` : `TMonthNameArray`~~deprecated~~

`ShortMonthNames` is an array with the abbreviated names of months. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ShortMonthNames` (1644) instead.

`ShortTimeFormat` : `string`~~deprecated~~

`ShortTimeFormat` contains a template to format a time in a short notation. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ShortTimeFormat` (1644) instead.

`SysLocale` : `TSysLocale`

`SysLocale` is initialized by the initialization code of the `SysUtils` unit. For an explanation of the fields, see `TSysLocale` (1641)

`ThousandSeparator` : `Char`~~deprecated~~

`ThousandSeparator` is used to separate groups of thousands in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ThousandSeparator` (1644) instead.

`TimeAMString` : `string`~~deprecated~~

`TimeAMString` is used to display the AM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.TimeAMString` (1644) instead.

`TimePMString` : `string`~~deprecated~~

`TimePMString` is used to display the PM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.TimePMString` (1644) instead.

`TimeSeparator` : `Char`~~deprecated~~

`TimeSeparator` is used by the time formatting routines to separate the hours from the minutes and the minutes from the seconds. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`TrueBoolStrs` : `Array of string`

`TrueBoolStrs` contains the strings that will result in a `True` return value by `StrToBool` ([1763](#)).

`TwoDigitYearCenturyWindow` : `Word`

Window to determine what century 2 digit years are in.

77.15 Procedures and functions

77.15.1 AbandonSignalHandler

Synopsis: Abandon the signal handler

Declaration: `procedure AbandonSignalHandler(RtlSigNum: Integer)`

Visibility: default

Description: `AbandonSignalHandler` tells the system routines that they should not re-install the signal handler for signal `RtlSigNum` under any circumstances. Normally, signal handlers are re-set when they are called. If `AbandonSignalHandler` has been called for a signal that is handled by the system code, the signal will not be re-set again.

77.15.2 Abort

Synopsis: Abort program execution.

Declaration: `procedure Abort`

Visibility: default

Description: `Abort` raises an `EAbort` ([1798](#)) exception.

See also: `EAbort` ([1798](#))

77.15.3 AddDisk

Synopsis: Add a disk to the list of known disks (Unix only)

Declaration: `function AddDisk(const path: string) : Byte`

Visibility: default

Description: On Unix-like platforms both the `DiskFree` ([1681](#)) and `DiskSize` ([1682](#)) functions need a file on the specified drive, since is required for the `statfs` system call.

These filenames are set in `drivestr[0..26]`, and the first 4 have been preset to :

Disk 0 ' . ' default drive - hence current directory is used.

Disk 1 ' /fd0/ . ' floppy drive 1.

Disk 2 ' /fd1/ . ' floppy drive 2.

Disk 3 ' / ' C: equivalent of DOS is the root partition.

Drives 4..26 can be set by your own applications with the `AddDisk` call.

The `AddDisk` call adds `Path` to the names of drive files, and returns the number of the disk that corresponds to this drive. If you add more than 21 drives, the count is wrapped to 4.

Errors: None.

See also: `DiskFree` ([1681](#)), `DiskSize` ([1682](#))

77.15.4 AddTerminateProc

Synopsis: Add a procedure to the exit chain.

Declaration: `procedure AddTerminateProc(TermProc: TTerminateProc)`

Visibility: default

Description: `AddTerminateProc` adds `TermProc` to the list of exit procedures. When the program exits, the list of exit procedures is run over, and all procedures are called one by one, in the reverse order that they were added to the exit chain.

Errors: If no memory is available on the heap, an exception may be raised.

See also: `TTerminateProc` ([1642](#)), `CallTerminateProcs` ([1666](#))

77.15.5 AdjustLineBreaks

Synopsis: Convert possible line-endings to the currently valid line ending.

Declaration: `function AdjustLineBreaks(const S: string) : string`
`function AdjustLineBreaks(const S: string; Style: TTextLineBreakStyle)`
`: string`

Visibility: default

Description: `AdjustLineBreaks` will change all occurrences of `#13` and `#10` characters with the correct line-ending characters for the current platform. This is `#13#10` on Windows and Dos. On Unix-like platforms, this is `#10` and for Mac OS X it is `#13`.

Errors: None.

See also: `AnsiCompareStr` ([1650](#)), `AnsiCompareText` ([1651](#))

Listing: `./examples/sysutex/ex48.pp`

Program `Example48;`

{ This program demonstrates the AdjustLineBreaks function }

Uses `sysutils;`

Const

`S = 'This is a string'#13'with embedded'#10'linefeed and'+`
`#13'CR characters';`

Begin

`WriteLn (AdjustLineBreaks(S));`

End.

77.15.6 AnsiCompareFileName

Synopsis: Compare 2 filenames.

Declaration: `function AnsiCompareFileName(const S1: string; const S2: string)`
`: SizeInt`

Visibility: default

Description: `AnsiCompareFileName` compares 2 filenames `S1` and `S2`, and returns

< 0 if `S1`<`S2`.
 = 0 if `S1`=`S2`.
 > 0 if `S1`>`S2`.

The function actually checks `FileNameCaseSensitive` and returns the result of `AnsiCompareStr` (1650) or `AnsiCompareText` (1651) depending on whether `FileNameCaseSensitive` is `True` or `False`

Errors: None.

See also: `AnsiCompareStr` (1650), `AnsiCompareText` (1651), `AnsiLowerCaseFileName` (1654)

77.15.7 AnsiCompareStr

Synopsis: Compare 2 ansistrings, case sensitive, ignoring accents characters.

Declaration: `function AnsiCompareStr(const S1: string; const S2: string) : Integer`

Visibility: default

Description: `AnsiCompareStr` compares two strings and returns the following result:

< 0 if `S1`<`S2`.
 0 if `S1`=`S2`.
 > 0 if `S1`>`S2`.

The comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to `AnsiCompareText` (1651), the comparison is case sensitive.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AdjustLineBreaks` (1649), `AnsiCompareText` (1651)

Listing: `./examples/sysutex/ex49.pp`

Program Example49;

{ This program demonstrates the AnsiCompareStr function }
{ \$H+ }

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

begin

 R:=**AnsiCompareStr**(S1,S2);
 Write ('',S1,' is ');
 If R<0 **then**
 write ('less than ')
 else If R=0 **then**
 Write ('equal to ')

```

    else
        Write ( 'larger than ');
    WriteLn ( '', S2, '' );
end;

Begin
    Testit( 'One string ', 'One smaller string ');
    Testit( 'One string ', 'one string ');
    Testit( 'One string ', 'One string ');
    Testit( 'One string ', 'One tall string ');
End.

```

77.15.8 AnsiCompareText

Synopsis: Compare 2 ansistrings, case insensitive, ignoring accents characters.

Declaration: `function AnsiCompareText(const S1: string; const S2: string) : Integer`

Visibility: default

Description: `AnsiCompareText` compares two strings and returns the following result:

```

<0if S1<S2.
0if S1=S2.
>0if S1>S2.

```

the comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to `AnsiCompareStr` ([1650](#)), the comparison is case insensitive.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AdjustLineBreaks` ([1649](#)), `AnsiCompareText` ([1651](#))

Listing: `./examples/sysutex/ex50.pp`

Program Example49;

```

{ This program demonstrates the AnsiCompareText function }
{$H+}

```

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

```

begin
    R:=AnsiCompareText(S1,S2);
    Write ( '', S1, ' is ');
    If R<0 then
        write ( 'less than ')
    else If R=0 then
        Write ( 'equal to ')
    else

```

```

    Write ( 'larger than ');
    Writeln ( '""', S2, '""');
end;

Begin
    Testit( 'One string ', 'One smaller string ');
    Testit( 'One string ', 'one string ');
    Testit( 'One string ', 'One string ');
    Testit( 'One string ', 'One tall string ');
End.

```

77.15.9 AnsiDequotedStr

Synopsis: Extract string without quotes

Declaration: `function AnsiDequotedStr(const S: string; AQuote: Char) : string`

Visibility: default

Description: `AnsiDequotedStr` is, similar to `AnsiExtractQuotedStr` (1652), a method to extract a string that was quoted using `AnsiQuotedStr` (1654). The string `S` must start and end with the quote character `AQuote` (they will be removed from the result) and all double occurrences of the quote character `AQuote` will be reduced to a single quote character.

Errors: If the string does not start and end with the quote character or has length less than 2, the original string is returned.

See also: `AnsiExtractQuotedStr` (1652), `AnsiQuotedStr` (1654)

77.15.10 AnsiExtractQuotedStr

Synopsis: Removes the first quoted string from a string.

Declaration: `function AnsiExtractQuotedStr(var Src: PChar; Quote: Char) : string`

Visibility: default

Description: `AnsiExtractQuotedStr` returns the first quoted string in `Src`, and deletes the result from `Src`. The resulting string has with `Quote` characters removed from the beginning and end of the string (if they are present), and double `Quote` characters replaced by a single `Quote` characters. As such, it reverses the action of `AnsiQuotedStr` (1654).

Errors: None.

See also: `AnsiQuotedStr` (1654)

Listing: `./examples/sysutex/ex51.pp`

```

Program Example51;
{ This program demonstrates the AnsiQuotedStr function }
Uses sysutils;

Var
    S : AnsiString;
    P : PChar;

Begin

```

```

S:= 'He said "Hello" and walked on';
P:= Pchar(S);
S:= AnsiQuotedStr(P, '"');
Writeln (S);
P:= Pchar(S);
Writeln (AnsiExtractQuotedStr(P, '"'));
End.

```

77.15.11 AnsiLastChar

Synopsis: Return a pointer to the last character of a string.

Declaration: `function AnsiLastChar(const S: string) : PChar`

Visibility: default

Description: This function returns a pointer to the last character of S.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets. If none is installed, this function is the same as `@S[Length[S]]`.

Errors: None.

See also: `AnsiStrLastChar` ([1657](#))

Listing: `./examples/sysutex/ex52.pp`

Program Example52;

{ This program demonstrates the AnsiLastChar function }

Uses sysutils;

Var S : AnsiString;
L : Longint;

Begin

```

S:= 'This is an ansistring.';
Writeln ('Last character of S is : ',AnsiLastChar(S));
L:= Longint(AnsiLastChar(S))-Longint(@S[1])+1;
Writeln ('Length of S is : ',L);

```

End.

77.15.12 AnsiLowerCase

Synopsis: Return a lowercase version of a string.

Declaration: `function AnsiLowerCase(const s: string) : string`

Visibility: default

Description: `AnsiLowerCase` converts the string S to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: [AnsiUpperCase \(1661\)](#), [AnsiStrLower \(1659\)](#), [AnsiStrUpper \(1661\)](#)

Listing: ./examples/sysutex/ex53.pp

Program Example53;

{ This program demonstrates the AnsiLowerCase function }

Uses sysutils;

Procedure Testit (S : **String**);

begin
 WriteLn (S, ' → ', AnsiLowerCase(S))
end;

Begin
 Testit('AN UPPERCASE STRING');
 Testit('Some mixed STring');
 Testit('a lowercase string');
End.

77.15.13 AnsiLowerCaseFileName

Synopsis: Convert filename to lowercase.

Declaration: function AnsiLowerCaseFileName(const s: string) : string

Visibility: default

Description: AnsiLowerCaseFileName simply returns the result of

`AnsiLowerCase(S);`

See also: [AnsiLowerCase \(1653\)](#), [AnsiCompareFileName \(1649\)](#), [AnsiUpperCaseFileName \(1662\)](#)

77.15.14 AnsiPos

Synopsis: Return Position of one ansistring in another.

Declaration: function AnsiPos(const substr: string; const s: string) : SizeInt

Visibility: default

Description: AnsiPos does the same as the standard Pos function.

See also: [AnsiStrPos \(1660\)](#), [AnsiStrScan \(1660\)](#), [AnsiStrRScan \(1660\)](#)

77.15.15 AnsiQuotedStr

Synopsis: Return a quoted version of a string.

Declaration: function AnsiQuotedStr(const S: string; Quote: Char) : string

Visibility: default

Description: `AnsiQuotedString` quotes the string `S` and returns the result. This means that it puts the `Quote` character at both the beginning and end of the string and replaces any occurrence of `Quote` in `S` with 2 `Quote` characters. The action of `AnsiQuotedString` can be reversed by `AnsiExtractQuotedStr` (1652).

For an example, see `AnsiExtractQuotedStr` (1652)

Errors: None.

See also: `AnsiExtractQuotedStr` (1652)

77.15.16 `AnsiSameStr`

Synopsis: Checks whether 2 strings are the same (case sensitive)

Declaration: `function AnsiSameStr(const s1: string; const s2: string) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareStr` (1650) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareStr` (1650), `SameText` (1746), `AnsiSameText` (1655)

77.15.17 `AnsiSameText`

Synopsis: Checks whether 2 strings are the same (case insensitive)

Declaration: `function AnsiSameText(const s1: string; const s2: string) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareText` (1651) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

See also: `AnsiCompareText` (1651), `SameText` (1746), `AnsiSameStr` (1655)

77.15.18 `AnsiStrComp`

Synopsis: Compare two null-terminated strings. Case sensitive.

Declaration: `function AnsiStrComp(S1: PChar; S2: PChar) : Integer`

Visibility: default

Description: `AnsiStrComp` compares 2 `PChar` strings, and returns the following result:

<0 if `S1 < S2`.

0 if `S1 = S2`.

>0 if `S1 > S2`.

The comparison of the two strings is case-sensitive.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareText` ([1651](#)), `AnsiCompareStr` ([1650](#))

Listing: ./examples/sysutex/ex54.pp

Program Example54;

{ This program demonstrates the AnsiStrComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar);

Var R : Longint;

begin

 R:=AnsiStrComp(S1,S2);

Write ('"',S1,'" is ');

If R<0 **then**

write ('less than ')

else If R=0 **then**

Write ('equal to ')

else

Write ('larger than ');

WriteLn ('"',S2,'"');

end;

Begin

 Testit('One string','One smaller string');

 Testit('One string','one string');

 Testit('One string','One string');

 Testit('One string','One tall string');

End.

77.15.19 AnsiStrIComp

Synopsis: Compare two null-terminated strings. Case insensitive.

Declaration: `function AnsiStrIComp(S1: PChar; S2: PChar) : Integer`

Visibility: default

Description: `AnsiStrIComp` compares 2 `PChar` strings, and returns the following result:

<0if S1<S2.

0if S1=S2.

>0if S1>S2.

The comparison of the two strings is case-insensitive.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: [AnsiCompareText \(1651\)](#), [AnsiCompareStr \(1650\)](#)

Listing: ./examples/sysutex/ex55.pp

Program Example55;

{ This program demonstrates the AnsiStrlComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar);

Var R : Longint;

begin

 R:= AnsiStrlComp (S1,S2);

Write ('',S1, ' is ');

If R<0 **then**

write ('less than ')

else If R=0 **then**

Write ('equal to ')

else

Write ('larger than ');

WriteLn ('',S2, ' ');

end;

Begin

 Testit('One string ', 'One smaller string ');

 Testit('One string ', 'one string ');

 Testit('One string ', 'One string ');

 Testit('One string ', 'One tall string ');

End.

77.15.20 AnsiStrLastChar

Synopsis: Return a pointer to the last character of a string.

Declaration: function AnsiStrLastChar(Str: PChar) : PChar

Visibility: default

Description: Return a pointer to the last character of the null-terminated string.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets. If none is installed, this function is the same as @S[Length[S]].

Errors: None.

See also: [AnsiCompareText \(1651\)](#), [AnsiCompareStr \(1650\)](#)

Listing: ./examples/sysutex/ex56.pp

Program Example56;

{ This program demonstrates the AnsiStrLComp function }

```

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar; L : longint);

Var R : Longint;

begin
  R:=AnsiStrLComp(S1,S2,L);
  Write ( 'First ',L, ' characters of "',S1,'" are ');
  If R<0 then
    write ( 'less than ' )
  else If R=0 then
    Write ( 'equal to ' )
  else
    Write ( 'larger than ' );
  WriteLn ( 'those of "',S2,'" ');
end;

Begin
  Testit( 'One string ', 'One smaller string ',255);
  Testit( 'One string ', 'One String ',4);
  Testit( 'One string ', '1 string ',0);
  Testit( 'One string ', 'One string. ',9);
End.

```

77.15.21 AnsiStrLComp

Synopsis: Compare a limited number of characters of 2 strings

Declaration: `function AnsiStrLComp(S1: PChar; S2: PChar; MaxLen: SizeUInt) : Integer`

Visibility: default

Description: `AnsiStrLComp` functions the same as `AnsiStrComp` ([1655](#)), but compares at most `MaxLen` characters. If the first `MaxLen` characters in both strings are the same, then zero is returned.

Note that this function processes embedded null characters, treating them as a normal character.

Errors: None.

See also: `AnsiStrComp` ([1655](#)), `AnsiStrIComp` ([1656](#)), `AnsiStrLComp` ([1658](#))

77.15.22 AnsiStrLIComp

Synopsis: Compares a given number of characters of a string, case insensitive.

Declaration: `function AnsiStrLIComp(S1: PChar; S2: PChar; MaxLen: SizeUInt) : Integer`

Visibility: default

Description: `AnsiStrLIComp` compares the first `Maxlen` characters of 2 `PChar` strings, `S1` and `S2`, and returns the following result:

```

<0if S1<S2.
0if S1=S2.
>0if S1>S2.

```

The comparison of the two strings is case-insensitive.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: [AnsiCompareText \(1651\)](#), [AnsiCompareStr \(1650\)](#)

Listing: ./examples/sysutex/ex57.pp

Program Example57;

{ This program demonstrates the AnsiStrLIComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar; L : longint);

Var R : Longint;

begin

R:=AnsiStrLIComp(S1,S2,L);

Write ('First ',L,' characters of "',S1,'" are ');

If R<0 **then**

write ('less than ');

else If R=0 **then**

Write ('equal to ');

else

Write ('larger than ');

WriteLn ('those of "',S2,'"');

end;

Begin

Testit('One string','One smaller string',255);

Testit('ONE STRING','one String',4);

Testit('One string','1 STRING',0);

Testit('One STRING','one string.',9);

End.

77.15.23 AnsiStrLower

Synopsis: Convert a null-terminated string to all-lowercase characters.

Declaration: function AnsiStrLower(Str: PChar) : PChar

Visibility: default

Description: `AnsiStrLower` converts the PChar `Str` to lowercase characters and returns the resulting pchar.

Note that `Str` itself is modified, not a copy, as in the case of `AnsiLowerCase` ([1653](#)). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: [AnsiStrUpper \(1661\)](#), [AnsiLowerCase \(1653\)](#)

Listing: ./examples/sysutex/ex59.pp

Program Example59;

{ This program demonstrates the AnsiStrLower function }

Uses sysutils , strings ;

Procedure Testit (S : PChar);

begin

WriteLn (S, ' → ', AnsiStrLower(**StrNew**(S)))

end;

Begin

 Testit('AN UPPERCASE STRING');

 Testit('Some mixed STring');

 Testit('a lowercase string');

End.

77.15.24 AnsiStrPos

Synopsis: Return position of one null-terminated substring in another

Declaration: function AnsiStrPos(str: PChar; substr: PChar) : PChar

Visibility: default

Description: AnsiStrPos returns a pointer to the first occurrence of SubStr in Str. If SubStr does not occur in Str then Nil is returned.

Errors: An access violation may occur if either Str or SubStr point to invalid memory.

See also: AnsiPos ([1654](#)), AnsiStrScan ([1660](#)), AnsiStrRScan ([1660](#))

77.15.25 AnsiStrRScan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: function AnsiStrRScan(Str: PChar; Chr: Char) : PChar

Visibility: default

Description: AnsiStrPos returns a pointer to the *last* occurrence of the character Chr in Str. If Chr does not occur in Str then Nil is returned.

Errors: An access violation may occur if Str points to invalid memory.

See also: AnsiPos ([1654](#)), AnsiStrScan ([1660](#)), AnsiStrPos ([1660](#))

77.15.26 AnsiStrScan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: function AnsiStrScan(Str: PChar; Chr: Char) : PChar

Visibility: default

Description: `AnsiStrPos` returns a pointer to the *first* occurrence of the character `Chr` in `Str`. If `Chr` does not occur in `Str` then `Nil` is returned.

Errors: An access violation may occur if `Str` points to invalid memory.

See also: `AnsiPos` ([1654](#)), `AnsiStrScan` ([1660](#)), `AnsiStrPos` ([1660](#))

77.15.27 AnsiStrUpper

Synopsis: Convert a null-terminated string to all-uppercase characters.

Declaration: `function AnsiStrUpper(Str: PChar) : PChar`

Visibility: default

Description: `AnsiStrUpper` converts the `PCharStr` to uppercase characters and returns the resulting string. Note that `Str` itself is modified, not a copy, as in the case of `AnsiUpperCase` ([1661](#)). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiUpperCase` ([1661](#)), `AnsiStrLower` ([1659](#)), `AnsiLowerCase` ([1653](#))

Listing: `./examples/sysutex/ex60.pp`

Program Example60;

{ This program demonstrates the AnsiStrUpper function }

Uses sysutils , strings ;

Procedure Testit (S : Pchar);

begin

WriteLn (S, ' → ', AnsiStrUpper(**StrNew**(S)))

end ;

Begin

 Testit('AN UPPERCASE STRING');

 Testit('Some mixed STring');

 Testit('a lowercase string');

End.

77.15.28 AnsiUpperCase

Synopsis: Return an uppercase version of a string, taking into account special characters.

Declaration: `function AnsiUpperCase(const s: string) : string`

Visibility: default

Description: `AnsiUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiStrUpper` ([1661](#)), `AnsiStrLower` ([1659](#)), `AnsiLowerCase` ([1653](#))

Listing: `./examples/sysutex/ex61.pp`

Program `Example60`;

{ This program demonstrates the AnsiUpperCase function }

Uses `sysutils`;

Procedure `Testit (S : String)`;

begin

`WriteLn (S, ' -> ', AnsiUpperCase(S))`
end;

Begin

`Testit('AN UPPERCASE STRING');`
`Testit('Some mixed STring');`
`Testit('a lowercase string');`

End.

77.15.29 AnsiUpperCaseFileName

Synopsis: Convert filename to uppercase.

Declaration: `function AnsiUpperCaseFileName(const s: string) : string`

Visibility: `default`

Description: `AnsiUpperCaseFileName` simply returns the result of

`AnsiUpperCase(S);`

See also: `AnsiUpperCase` ([1661](#)), `AnsiCompareFileName` ([1649](#)), `AnsiLowerCaseFileName` ([1654](#))

77.15.30 AppendStr

Synopsis: Append one ansistring to another.

Declaration: `procedure AppendStr(var Dest: string; const S: string)`

Visibility: `default`

Description: `AppendStr` appends `S` to `Dest`.

This function is provided for Delphi compatibility only, since it is completely equivalent to `Dest := Dest + S`.

Errors: None.

See also: [AssignStr \(1663\)](#), [NewStr \(1741\)](#), [DisposeStr \(1682\)](#)

Listing: ./examples/sysutex/ex62.pp

```

Program Example62;

{ This program demonstrates the AppendStr function }

Uses sysutils;

Var S : AnsiString;

Begin
  S:= 'This is an ';
  AppendStr(S, 'AnsiString ');
  WriteLn ('S = "', S, '"');
End.

```

77.15.31 ApplicationName

Synopsis: Return a default application name

Declaration: `function ApplicationName : string`

Visibility: default

Description: `ApplicationName` returns the name of the current application. Standard this is equal to the filename part minus extension of `ParamStr(0)`, but it can be customized by setting the `OnGetApplicationName (1646)` callback.

Note that the returned value is only the name portion. It does not contain any path or file extension.

Errors: None.

See also: [GetAppConfigDir \(1724\)](#), [OnGetApplicationName \(1646\)](#), [GetAppConfigFile \(1725\)](#), [ConfigExtension \(1623\)](#)

77.15.32 AssignStr

Synopsis: Assigns an ansistring to a null-terminated string.

Declaration: `procedure AssignStr(var P: PString; const S: string)`

Visibility: default

Description: `AssignStr` allocates `S` to `P`. The old value of `P` is disposed of.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

Errors: None.

See also: [NewStr \(1741\)](#), [AppendStr \(1662\)](#), [DisposeStr \(1682\)](#)

Listing: ./examples/sysutex/ex63.pp

Program Example63;

```
{ This program demonstrates the AssignStr function }
{$H+}
```

Uses sysutils;

Var P : PString;

Begin

```
P:=NewStr('A first AnsiString');
Writeln ('Before: P = "',P^,'"');
AssignStr(P,'A Second ansistring');
Writeln ('After : P = "',P^,'"');
DisposeStr(P);
```

End.

77.15.33 BCDToInt

Synopsis: Convert a BCD coded integer to a normal integer.

Declaration: `function BCDToInt(Value: Integer) : Integer`

Visibility: default

Description: BCDToInt converts a BCD coded integer to a normal integer.

Errors: None.

See also: StrToInt ([1769](#)), IntToStr ([1736](#))

Listing: ./examples/sysutex/ex64.pp

Program Example64;

```
{ This program demonstrates the BCDToInt function }
```

Uses sysutils;

Procedure Testit (L : longint);

begin

```
Writeln (L, ' -> ',BCDToInt(L));
```

end;

Begin

```
Testit(10);
Testit(100);
Testit(23);
```

End.

77.15.34 Beep

Synopsis: Sound the system bell.

Declaration: `procedure Beep`

Visibility: default

Description: Beep sounds the system bell, if one is available. The actual beep is produced by the OnBeep ([1645](#)) callback. The Sysutils unit itself contains no implementation of this call.

77.15.35 BoolToStr

Synopsis: Convert a boolean value to a string.

Declaration:

```
function BoolToStr(B: Boolean; UseBoolStrs: Boolean) : string
function BoolToStr(B: Boolean; const TrueS: string;
const FalseS: string) : string
```

Visibility: default

Description: BoolToStr converts the boolean B to one of the strings ' TRUE' or ' FALSE'

Errors: None.

See also: StrToBool ([1763](#))

77.15.36 ByteLength

Synopsis: Length (in bytes) of a unicodestring

Declaration:

```
function ByteLength(const S: UnicodeString) : Integer
```

Visibility: default

Description: ByteLength returns the length of a unicodestring in bytes. This equals the character length of the string (Length ([1615](#))) multiplied by the number of bytes per character (2).

See also: Length ([1615](#))

77.15.37 BytesOf

Synopsis: Return the bytes of a string in a TBytes array

Declaration:

```
function BytesOf(const Val: RawByteString) : TBytes
function BytesOf(const Val: AnsiChar) : TBytes
function BytesOf(const Val: UnicodeString) : TBytes; Overload
function BytesOf(const Val: WideChar) : TBytes; Overload
```

Visibility: default

Description: BytesOf returns a copy of the string's content as an array of bytes. For an empty string, zero bytes are returned (i.e. length(BytesOf(S))=0).

See also: TBytes ([1633](#))

77.15.38 ByteToCharIndex

Synopsis: Convert a character index in Bytes to an Index in characters

Declaration:

```
function ByteToCharIndex(const S: string; Index: SizeInt) : SizeInt
```

Visibility: default

Description: `ByteToCharIndex` returns the index (in characters) of the `Index`-th byte in `S`.

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1667](#)), `ByteToCharLen` ([1666](#))

77.15.39 ByteToCharLen

Synopsis: Convert a length in bytes to a length in characters.

Declaration: `function ByteToCharLen(const S: string; MaxLen: SizeInt) : SizeInt`

Visibility: default

Description: `ByteToCharLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1667](#)), `ByteToCharIndex` ([1665](#))

77.15.40 ByteType

Synopsis: Return the type of byte in an ansistring for a multi-byte character set

Declaration: `function ByteType(const S: string; Index: SizeUInt) : TMbcsByteType`

Visibility: default

Description: `ByteType` returns the type of byte in the ansistring `S` at (1-based) position `Index`.

Errors: No checking on the index is performed.

See also: `TMbcsByteType` ([1639](#)), `StrByteType` ([1750](#))

77.15.41 CallTerminateProcs

Synopsis: Call the exit chain procedures.

Declaration: `function CallTerminateProcs : Boolean`

Visibility: default

Description: `CallTerminateProcs` is run on program exit. It executes all terminate procedures that were added to the exit chain with `AddTerminateProc` ([1649](#)), and does this in reverse order.

Errors: If one of the exit procedure raises an exception, it is *not* caught, and the remaining exit procedures will not be executed.

See also: `TTerminateProc` ([1642](#)), `AddTerminateProc` ([1649](#))

77.15.42 ChangeFileExt

Synopsis: Change the extension of a filename.

Declaration:

```
function ChangeFileExt(const FileName: UnicodeString;
                      const Extension: UnicodeString) : UnicodeString
function ChangeFileExt(const FileName: RawByteString;
                      const Extension: RawByteString) : RawByteString
```

Visibility: default

Description: `ChangeFileExt` changes the file extension in `FileName` to `Extension`. The extension `Extension` includes the starting `.` (dot). The previous extension of `FileName` are all characters after the last `.`, the `.` character included.

If `FileName` doesn't have an extension, `Extension` is just appended.

Errors: None.

See also: `ExtractFileExt` ([1691](#)), `ExtractFileName` ([1691](#)), `ExtractFilePath` ([1692](#)), `ExpandFileName` ([1688](#))

77.15.43 CharInSet

Synopsis: Check whether a char is in a set of characters

Declaration:

```
function CharInSet(Ch: AnsiChar; const CSet: TSysCharSet) : Boolean
function CharInSet(Ch: WideChar; const CSet: TSysCharSet) : Boolean
```

Visibility: default

Description: `CharInSet` returns `True` if `Ch` matches one of the characters in `CSet`, it returns `False` otherwise. It is equivalent to

`Ch in CSet`

Later versions of this function may take `WideChar` into account.

77.15.44 CharToByteLen

Synopsis: Convert a length in characters to a length in bytes.

Declaration:

```
function CharToByteLen(const S: string; MaxLen: SizeInt) : SizeInt
```

Visibility: default

Description: `CharToByteLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

Errors: This function does not take into account MBCS yet.

See also: `ByteToCharLen` ([1666](#)), `ByteToCharIndex` ([1665](#))

77.15.45 CheckOSError

Synopsis: Check for OS error and raise exception

Declaration:

```
procedure CheckOSError(LastError: Integer)
```

Visibility: default

Description: `CheckOSError` checks if `LastError` is non-zero and calls `RaiseLastOSError` ([1743](#)) if this is the case.

See also: `RaiseLastOSError` ([1743](#))

77.15.46 CodePageNameToCodePage

Synopsis: Return a numeric identifier for the codepage.

Declaration: `function CodePageNameToCodePage(const cpname: AnsiString)
: TSystemCodePage`

Visibility: default

Description: `CodePageNameToCodePage` returns the code page number for the specified codepage `cpname`.

Errors: If the code page is not found in the list of code pages, \$FFFF is returned.

See also: `CodePageToCodePageName` ([1668](#))

77.15.47 CodePageToCodePageName

Synopsis: Convert a numeric codepage identifier to a codepage name

Declaration: `function CodePageToCodePageName(cp: TSystemCodePage) : AnsiString`

Visibility: default

Description: `CodePageToCodePageName` returns the name of the codepage `cp`.

Errors: If no matching codepage is found in the list of codepages, an empty string is returned.

See also: `CodePageNameToCodePage` ([1668](#))

77.15.48 CompareMem

Synopsis: Compare two memory areas.

Declaration: `function CompareMem(P1: Pointer; P2: Pointer; &Length: PtrUInt)
: Boolean`

Visibility: default

Description: `CompareMem` compares, byte by byte, 2 memory areas pointed to by `P1` and `P2`, for a length of `L` bytes.

The function returns `True` if all `L` bytes are the same, and `False` otherwise.

77.15.49 CompareMemRange

Synopsis: Compare 2 memory locations

Declaration: `function CompareMemRange(P1: Pointer; P2: Pointer; &Length: PtrUInt)
: Integer`

Visibility: default

Description: `CompareMemRange` compares the 2 memory locations pointed to by `P1` and `P2` byte per byte. It stops comparing after `Length` bytes have been compared, or when it has encountered 2 different bytes. The result is then

>0 if a byte in range `P1` was found that is bigger than the corresponding byte in range `P2`.

0 if all bytes in range `P1` are the same as the corresponding bytes in range `P2`.

<0 if a byte in range `P1` was found that is less than the corresponding byte in range `P2`.

77.15.51 CompareText

Synopsis: Compare 2 ansistrings case insensitive.

```
Declaration: function CompareText(const S1: string; const S2: string) : Integer
                ; Overload
function CompareText(const S1: string; const S2: string;
                LocaleOptions: TLocaleOptions) : Integer; Overload
```

Visibility: default

Description: CompareText compares two strings, S1 and S2, and returns the following result:

<0if $S1 < S2$.

0if $s_1=s_2$.

>0if $S1 > S2$.

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: [AnsiCompareText \(1651\)](#), [AnsiCompareStr \(1650\)](#), [CompareStr \(1669\)](#)

Listing: ./examples/sysutex/ex66.pp

Program Example66;

```
{ This program demonstrates the CompareText function }
{$H+}
```

Uses sysutils;

```
Procedure TestIt (S1,S2 : String);
```

```
Var R : Longint;
```

```
begin
  R:= CompareText(S1,S2);
  Write ( ' ',S1, ' is ' );
  If R<0 then
    write ( 'less than ' )
  else If R=0 then
    Write ( 'equal to ' )
  else
    Write ( 'larger than ' );
  WriteIn ( ' ',S2, ' ' );
end;
```

```
Begin
  Testit('One string','One smaller string');
  Testit('One string','one string');
  Testit('One string','One string');
  Testit('One string','One tall string');
End.
```

77.15.52 ComposeDateTime

Synopsis: Add a date and time

Declaration: `function ComposeDateTime(Date: TDateTime; Time: TDateTime) : TDateTime`

Visibility: default

Description: `ComposeDateTime` correctly adds `Date` and `Time`, also for dates before 1899-12-31. For dates after this date, it is just the mathematical addition.

Errors: None.

See also: `#rtl.dateutils.EncodeDateTime` (607)

77.15.53 ConcatPaths

Synopsis: Concatenate an array of paths to form a single path

Declaration: `function ConcatPaths(const Paths: Array of UnicodeString)`
 : `UnicodeString`
`function ConcatPaths(const Paths: Array of RawByteString)`
 : `RawByteString`

Visibility: default

Description: `ConcatPaths` will concatenate the different path components in `Paths` to a single path. It will insert directory separators between the various components of the path as needed. No directory separators will be added to the beginning or the end of the path, and none will be taken away.

See also: `IncludeTrailingPathDelimiter` (1734), `IncludeLeadingPathDelimiter` (1733), `ExcludeTrailingPathDelimiter` (1686), `IncludeTrailingPathDelimiter` (1734)

Listing: `./examples/sysutex/ex96.pp`

```

program ex96;

  { This program demonstrates the Concatpaths function }

uses sysutils;

begin
  // will write /this/path/more/levels/
  Writeln(ConcatPaths(['this/', 'path', 'more/levels/']));
  // will write this/path/more/levels/
  Writeln(ConcatPaths(['this/', 'path', 'more/levels/']));
  // will write this/path/more/levels
  Writeln(ConcatPaths(['this/', 'path', 'more/levels']));
end.

```

77.15.54 CreateDir

Synopsis: Create a new directory

Declaration: `function CreateDir(const NewDir: RawByteString) : Boolean`
 `function CreateDir(const NewDir: UnicodeString) : Boolean`

Visibility: default

Description: `CreateDir` creates a new directory with name `NewDir`. If the directory doesn't contain an absolute path, then the directory is created below the current working directory.

The function returns `True` if the directory was successfully created, `False` otherwise.

Errors: In case of an error, the function returns `False`.

See also: `RemoveDir` ([1743](#))

Listing: `./examples/sysutex/ex26.pp`

Program `Example26`;

```
{ This program demonstrates the CreateDir and RemoveDir functions }
{ Run this program twice in the same directory }
```

Uses `sysutils`;

Begin

```
If Not DirectoryExists ('NewDir') then
  If Not CreateDir ('NewDir') Then
    WriteLn ('Failed to create directory !')
  else
    WriteLn ('Created "NewDir" directory')
Else
  If Not RemoveDir ('NewDir') Then
    WriteLn ('Failed to remove directory !')
  else
    WriteLn ('Removed "NewDir" directory');
```

End.

77.15.55 CreateGUID

Synopsis: Create a new GUID

Declaration: `function CreateGUID(out GUID: TGuid) : Integer`

Visibility: `default`

Description: `CreateGUID` can be called to create a new GUID (Globally Unique Identifier) value. The function returns the new GUID value in `GUID` and returns zero in case the GUID was created successfully. If no GUID was created, a nonzero error code is returned.

The default mechanism for creating a new GUID is system dependent. If operating system support is available, it is used. If none is available, a default implementation using random numbers is used.

The `OnCreateGUID` callback can be set to hook a custom mechanism behind the `CreateGUID` function. This can be used to let the GUID be created by an external GUID creation library.

Errors: On error, a nonzero return value is returned.

See also: `GUIDCase` ([1732](#)), `IsEqualGUID` ([1737](#)), `StringToGUID` ([1755](#)), `TryStringToGUID` ([1782](#)), `GUIDToString` ([1732](#))

77.15.56 CurrentYear

Synopsis: Return the current year

Declaration: `function CurrentYear : Word`

Visibility: default

Description: `CurrentYear` returns the current year as a 4-digit number.

Errors: None.

See also: [Date \(1673\)](#), [Time \(1777\)](#), [Now \(1742\)](#)

77.15.57 CurrToStr

Synopsis: Convert a currency value to a string.

Declaration:

```
function CurrToStr(Value: Currency) : string
function CurrToStr(Value: Currency;
                    const FormatSettings: TFormatSettings) : string
```

Visibility: default

Description: `CurrToStr` will convert a currency value to a string with a maximum of 15 digits, and precision 2. Calling `CurrToStr` is equivalent to calling `FloatToStrF` ([1709](#)):

```
FloatToStrF(Value, ffNumber, 15, 2);
```

Note that on unix systems, the localization support must be enabled explicitly, see [Localization \(1616\)](#).

Errors: None.

See also: [FloatToStrF \(1709\)](#), [StrToCurr \(1764\)](#)

77.15.58 CurrToStrF

Synopsis: Format a currency to a string

Declaration:

```
function CurrToStrF(Value: Currency; Format: TFloatFormat;
                    Digits: Integer) : string
function CurrToStrF(Value: Currency; Format: TFloatFormat;
                    Digits: Integer;
                    const FormatSettings: TFormatSettings) : string
```

Visibility: default

Description: `CurrToStrF` formats the currency `Value` according to the value in `Format`, using the number of digits specified in `Digits`, and a precision of 19. This function simply calls `FloatToStrF` ([1709](#)).

Note that on unix systems, the localization support must be enabled explicitly, see [Localization \(1616\)](#).

See also: [FloatToStrF \(1709\)](#), [Localization \(1616\)](#)

77.15.59 Date

Synopsis: Return the current date.

Declaration:

```
function Date : TDateTime
```

Visibility: default

Description: `Date` returns the current date in `TDateTime` format.

Errors: None.

See also: `Time` ([1777](#)), `Now` ([1742](#))

Listing: `./examples/sysutex/ex1.pp`

Program `Example1`;

{ This program demonstrates the Date function }

uses `sysutils`;

Var `YY,MM,DD` : `Word`;

Begin

WriteIn (`'Date : ',Date`);

DeCodeDate (`Date,YY,MM,DD`);

WriteIn (`format ('Date is (DD/MM/YY): %d/%d/%d ',[dd,mm,yy])`);

End.

77.15.60 DateTimeToFileDate

Synopsis: Convert a `TDateTime` value to a file age (integer)

Declaration: `function DateTimeToFileDate(DateTime: TDateTime) : LongInt`

Visibility: `default`

Description: `DateTimeToFileDate` function converts a date/time indication in `TDateTime` format to a file-date function, such as returned for instance by the `FileAge` ([1693](#)) function.

Errors: None.

See also: `Time` ([1777](#)), `Date` ([1673](#)), `FileDateToDateTime` ([1696](#)), `DateTimeToSystemTime` ([1676](#)), `DateTimeToTimeStamp` ([1677](#))

Listing: `./examples/sysutex/ex2.pp`

Program `Example2`;

{ This program demonstrates the DateTimeToFileDate function }

Uses `sysutils`;

Begin

WriteIn (`'FileTime of now would be: ',DateTimeToFileDate (Now)`);

End.

77.15.61 DateTimeToStr

Synopsis: Converts a `TDateTime` value to a string using a predefined format.

Declaration: `function DateTimeToStr(DateTime: TDateTime; ForceTimeIfZero: Boolean) : string`
`function DateTimeToStr(DateTime: TDateTime;`
`const FormatSettings: TFormatSettings;`
`ForceTimeIfZero: Boolean) : string`

Visibility: default

Description: `DateTimeToStr` returns a string representation of `DateTime` using the formatting specified in `ShortDateFormat` and `LongTimeFormat`. It corresponds to a call to `FormatDateTime('c', DateTime)` (see `formatchars` (1621)).

Note that if the time part is 0 (i.e. midnight), no time is appended.

Note that on unix systems, the localization support must be enabled explicitly, see `Localization` (1616).

Errors: None.

See also: `FormatDateTime` (1721), `DefaultFormatSettings` (1644), `Localization` (1616)

Listing: `./examples/sysutex/ex3.pp`

Program `Example3`;

{ This program demonstrates the DateTimeToStr function }

Uses `sysutils`;

Begin

`WriteLn ('Today is : ', DateTimeToStr(Now));`

`WriteLn ('Today is : ', FormatDateTime('c', Now));`

End.

77.15.62 DateTimeToString

Synopsis: Converts a `TDateTime` value to a string with a given format.

Declaration: `procedure DateTimeToString(out Result: string; const FormatStr: string;`
`const DateTime: TDateTime;`
`Options: TFormatDateTimeOptions)`
`procedure DateTimeToString(out Result: string; const FormatStr: string;`
`const DateTime: TDateTime;`
`const FormatSettings: TFormatSettings;`
`Options: TFormatDateTimeOptions)`

Visibility: default

Description: `DateTimeToString` returns in `Result` a string representation of `DateTime` using the formatting specified in `FormatStr`.

for a list of characters that can be used in the `FormatStr` formatting string, see `formatchars` (1621).

Note that for 'c', if the time part is 0 (i.e. midnight), no time is appended.

Note that on unix systems, the localization support must be enabled explicitly, see `Localization` (1616).

Errors: In case a wrong formatting character is found, an `EConvertError` (1800) is raised.

See also: [FormatDateTime \(1721\)](#), [formatchars \(1621\)](#), [EConvertError \(1800\)](#), [Localization \(1616\)](#)

Listing: ./examples/sysutex/ex4.pp

```

Program Example4;

{ This program demonstrates the DateTimeToString function }

Uses sysutils;

Procedure today (Fmt : string);

Var S : AnsiString;

begin
    DateTimeToString (S,Fmt,Date);
    WriteLn (S);
end;

Procedure Now (Fmt : string);

Var S : AnsiString;

begin
    DateTimeToString (S,Fmt,Time);
    WriteLn (S);
end;

Begin
    Today ('Today is "dddd dd mmmm y');
    Today ('Today is "d mmm yy');
    Today ('Today is "d/mmm/yy');
    Now ('The time is 'am/pmh:n:s');
    Now ('The time is 'hh:nn:ssam/pm');
    Now ('The time is 'tt');
End.
```

77.15.63 DateTimeToSystemTime

Synopsis: Converts a TDateTime value to a systemtime structure.

Declaration: `procedure DateTimeToSystemTime(DateTime: TDateTime;
out SystemTime: TSystemTime)`

Visibility: default

Description: DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a system time SystemTime.

Errors: None.

See also: [DateTimeToFileDate \(1674\)](#), [SystemTimeToDateTime \(1775\)](#), [DateTimeToTimeStamp \(1677\)](#)

Listing: ./examples/sysutex/ex5.pp

Program Example5;

{ This program demonstrates the DateTimeToSystemTime function }

Uses sysutils;

Var ST : TSystemTime;

Begin

DateTimeToSystemTime(**Now**,ST);

With St **do**

begin

Writeln ('Today is ',year,'/',month,'/',Day);

Writeln ('The time is ',Hour,':',minute,':',Second,'.',MilliSecond);

end;

End.

77.15.64 DateTimeToTimeStamp

Synopsis: Converts a TDateTime value to a TimeStamp structure.

Declaration: function DateTimeToTimeStamp(DateTime: TDateTime) : TTimeStamp

Visibility: default

Description: DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a TTimeStamp format.

Errors: None.

See also: DateTimeToFileDate ([1674](#)), SystemTimeToDateTime ([1775](#)), DateTimeToSystemTime ([1676](#))

Listing: ./examples/sysutex/ex6.pp

Program Example6;

{ This program demonstrates the DateTimeToTimeStamp function }

Uses sysutils;

Var TS : TTimeStamp;

Begin

TS:=DateTimeToTimeStamp (**Now**);

With TS **do**

begin

Writeln ('Now is ',time,' millisecond past midnight');

Writeln ('Today is ',Date,' days past 1/1/0001');

end;

End.

77.15.65 DateToStr

Synopsis: Converts a TDateTime value to a date string with a predefined format.

Declaration: `function DateToStr(Date: TDateTime) : string`
`function DateToStr(Date: TDateTime;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `DateToStr` converts `Date` to a string representation. It uses `ShortDateFormat` as it's formatting string. It is hence completely equivalent to a `FormatDateTime('dddd', Date)`.

Note that on unix systems, the localization support must be enabled explicitly, see [Localization \(1616\)](#).

Errors: None.

See also: [TimeToStr \(1778\)](#), [DateTimeToStr \(1674\)](#), [FormatDateTime \(1721\)](#), [StrToDate \(1764\)](#), [Localization \(1616\)](#)

Listing: `./examples/sysutex/ex7.pp`

Program `Example7;`

`{ This program demonstrates the DateToStr function }`

Uses `sysutils;`

Begin

`WriteLn (Format ('Today is: %s ', [DateToStr (Date)]));`

End.

77.15.66 DayOfWeek

Synopsis: Returns the day of the week.

Declaration: `function DayOfWeek(DateTime: TDateTime) : Integer`

Visibility: default

Description: `DayOfWeek` returns the day of the week from `DateTime`. Sunday is counted as day 1, Saturday is counted as day 7. The result of `DayOfWeek` can serve as an index to the `LongDayNames` constant array, to retrieve the name of the day.

Errors: None.

See also: [Date \(1673\)](#), [DateToStr \(1677\)](#)

Listing: `./examples/sysutex/ex8.pp`

Program `Example8;`

`{ This program demonstrates the DayOfWeek function }`

Uses `sysutils;`

Begin

`WriteLn ('Today 's day is ', LongDayNames[DayOfWeek (Date)]);`

End.

77.15.67 DecodeDate

Synopsis: Decode a TDateTime to a year,month,day triplet

Declaration: `procedure DecodeDate(Date: TDateTime; out Year: Word; out Month: Word;
out Day: Word)`

Visibility: default

Description: `DecodeDate` decodes the Year, Month and Day stored in `Date`, and returns them in the Year, Month and Day variables.

Errors: None.

See also: `EncodeDate` ([1683](#)), `DecodeTime` ([1679](#))

Listing: `./examples/sysutex/ex9.pp`

Program `Example9`;

{ This program demonstrates the DecodeDate function }

Uses `sysutils`;

Var `YY,MM,DD` : `Word`;

Begin

`DecodeDate` (`Date`, `YY`, `MM`, `DD`);

`WriteLn` (`Format` ('Today is %d/%d/%d' , [`dd`, `mm`, `yy`]));

End.

77.15.68 DecodeDateFully

Synopsis: Decode a date with additional date of the week.

Declaration: `function DecodeDateFully(const DateTime: TDateTime; out Year: Word;
out Month: Word; out Day: Word; out DOW: Word)
: Boolean`

Visibility: default

Description: `DecodeDateFully`, like `DecodeDate` ([1679](#)), decodes `DateTime` in its parts and returns these in Year, Month, Day but in addition returns the day of the week in DOW.

Errors: None.

See also: `EncodeDate` ([1683](#)), `TryEncodeDate` ([1781](#)), `DecodeDate` ([1679](#))

77.15.69 DecodeTime

Synopsis: Decode a TDateTime to a hour,minute,second,millisecond quartet

Declaration: `procedure DecodeTime(Time: TDateTime; out Hour: Word; out Minute: Word;
out Second: Word; out MilliSecond: Word)`

Visibility: default

Description: `DecodeTime` decodes the hours, minutes, second and milliseconds stored in `Time`, and returns them in the Hour, Minute and Second and MilliSecond variables.

Errors: None.

See also: [EncodeTime \(1684\)](#), [DecodeDate \(1679\)](#)

Listing: ./examples/sysutex/ex10.pp

Program Example10;

{ This program demonstrates the DecodeTime function }

Uses sysutils;

Var HH,MM,SS,MS: Word;

Begin

DecodeTime(Time,HH,MM,SS,MS);

WriteLn (format('The time is %d:%d:%d.%d',[hh,mm,ss,ms]));

End.

77.15.70 DeleteFile

Synopsis: Delete a file from the file system.

Declaration: function DeleteFile(const FileName: UnicodeString) : Boolean
function DeleteFile(const FileName: RawByteString) : Boolean

Visibility: default

Description: DeleteFile deletes file FileName from disk. The function returns True if the file was successfully removed, False otherwise.

Errors: On error, False is returned.

See also: [FileCreate \(1694\)](#), [FileExists \(1696\)](#)

Listing: ./examples/sysutex/ex31.pp

Program Example31;

{ This program demonstrates the DeleteFile function }

Uses sysutils;

Var

 Line : **String**;

 F,I : Longint;

Begin

 F:= FileCreate('test.txt');

 Line:='Some string line.'#10;

For I:=1 **to** 10 **do**

 FileWrite (F,Line[I],**Length**(Line));

FileClose(F);

DeleteFile('test.txt');

End.

77.15.71 DirectoryExists

Synopsis: Check whether a directory exists in the file system.

Declaration: `function DirectoryExists(const Directory: UnicodeString;
FollowLink: Boolean) : Boolean`
`function DirectoryExists(const Directory: RawByteString;
FollowLink: Boolean) : Boolean`

Visibility: default

Description: `DirectoryExists` checks whether `Directory` exists in the file system and is actually a directory. If this is the case, the function returns `True`, otherwise `False` is returned.

See also: `FileExists` ([1696](#))

77.15.72 DiskFree

Synopsis: Return the amount of free disk space

Declaration: `function DiskFree(drive: Byte) : Int64`

Visibility: default

Description: `DiskFree` returns the free space (in bytes) on disk `Drive`. `Drive` is the number of the disk drive:

0for the current drive.

1for the first floppy drive.

2for the second floppy drive.

3for the first hard-disk partition.

4-26for all other drives and partitions.

Remark Under Linux, and Unix in general, the concept of disk is different than the dos one, since the file system is seen as one big directory tree. For this reason, the `DiskFree` and `DiskSize` ([1682](#)) functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` ([1648](#)).

Errors: On error, `-1` is returned.

See also: `DiskSize` ([1682](#)), `AddDisk` ([1648](#))

Listing: `./examples/sysutex/ex27.pp`

Program `Example27;`

{ This program demonstrates the DiskFree function }

Uses `sysutils;`

Begin

`Write ('Size of current disk : ',DiskSize(0));`

`WriteLn (' (= ',DiskSize(0) div 1024,'k)');`

`Write ('Free space of current disk : ',Diskfree(0));`

`WriteLn (' (= ',Diskfree(0) div 1024,'k)');`

End.

77.15.73 DiskSize

Synopsis: Return the total amount of disk space.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the size (in bytes) of disk `Drive`. `Drive` is the number of the disk drive:

0 for the current drive.

1 for the first floppy drive.

2 for the second floppy drive.

3 for the first hard-disk partition.

4-26 for all other drives and partitions.

Remark Under Linux, and Unix in general, the concept of disk is different than the dos one, since the file system is seen as one big directory tree. For this reason, the `DiskFree` (1681) and `DiskSize` functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` (1648)

For an example, see `DiskFree` (1681).

Errors: On error, -1 is returned.

See also: `DiskFree` (1681), `AddDisk` (1648)

77.15.74 DisposeStr

Synopsis: Dispose an anstring from the heap.

Declaration: `procedure DisposeStr(S: PString); Overload`
`procedure DisposeStr(S: PShortString); Overload`

Visibility: default

Description: `DisposeStr` removes the dynamically allocated string `S` from the heap, and releases the occupied memory.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

For an example, see `DisposeStr` (1682).

Errors: None.

See also: `NewStr` (1741), `AppendStr` (1662), `AssignStr` (1663)

77.15.75 DoDirSeparators

Synopsis: Convert known directory separators to the current directory separator.

Declaration: `procedure DoDirSeparators(var FileName: UnicodeString)`
`procedure DoDirSeparators(var FileName: RawByteString)`

Visibility: default

Description: This function replaces all known directory separators in `FileName` to the directory separator character for the current system. The list of known separators is specified in the `AllowDirectorySeparators` (1345) constant.

Errors: None.

See also: ExtractFileName ([1691](#)), ExtractFilePath ([1692](#))

Listing: ./examples/sysutex/ex32.pp

Program Example32;

{ This program demonstrates the DoDirSeparators function }
{ \$H+ }

Uses sysutils;

Procedure Testit (F : **String**);

begin

WriteIn ('Before : ',F);

 DoDirSeparators (F);

WriteIn ('After : ',F);

end;

Begin

 Testit (GetCurrentDir);

 Testit ('c:\pp\bin\win32');

 Testit ('/usr/lib/fpc');

 Testit ('\usr\lib\fpc');

End.

77.15.76 EncodeDate

Synopsis: Encode a Year,Month,Day to a TDateTime value.

Declaration: function EncodeDate(Year: Word; Month: Word; Day: Word) : TDateTime

Visibility: default

Description: EncodeDate encodes the Year, Month and Day variables to a date in TDateTime format. It does the opposite of the DecodeDate ([1679](#)) procedure.

The parameters must lie withing valid ranges (boundaries included):

Year must be between 1 and 9999.

Month must be within the range 1-12.

Day must be between 1 and 31.

Errors: In case one of the parameters is out of it's valid range, an EConvertError ([1800](#)) exception is raised.

See also: EncodeTime ([1684](#)), DecodeDate ([1679](#))

Listing: ./examples/sysutex/ex11.pp

Program Example11;

{ This program demonstrates the EncodeDate function }

Uses sysutils;

Var YY,MM,DD : Word;

Begin

```

DecodeDate ( Date, YY,MM,DD);
WriteLn ( 'Today is : ',FormatDateTime ( 'dd mmm yyyy ',EnCodeDate(YY,Mm,Dd)));
End.

```

77.15.77 EncodeTime

Synopsis: Encode a Hour,Min,Sec,millisecond to a TDateTime value.

Declaration: `function EncodeTime(Hour: Word; Minute: Word; Second: Word; MilliSecond: Word) : TDateTime`

Visibility: default

Description: EncodeTime encodes the Hour, Minute, Second, MilliSecond variables to a TDateTime format result. It does the opposite of the DecodeTime (1679) procedure.

The parameters must have a valid range (boundaries included):

Hour must be between 0 and 23.

Minute,second must both be between 0 and 59.

Millisecond must be between 0 and 999.

Errors: In case one of the parameters is out of it's valid range, an EConvertError (1800) exception is raised.

See also: EncodeDate (1683), DecodeTime (1679)

Listing: ./examples/sysutex/ex12.pp

Program Example12;

{ This program demonstrates the EncodeTime function }

Uses sysutils;

Var Hh,MM,SS,MS : Word;

Begin

```

DeCodeTime ( Time, Hh,MM,SS,MS);
WriteLn ( 'Present Time is : ',FormatDateTime( 'hh:mm:ss ',EnCodeTime (HH,MM,SS,MS)));
End.

```

77.15.78 ExceptAddr

Synopsis: Current exception address.

Declaration: `function ExceptAddr : CodePointer`

Visibility: default

Description: ExceptAddr returns the address from the currently treated exception object when an exception is raised, and the stack is unwound.

See also: ExceptObject (1685), ExceptionErrorMessage (1685), ShowException (1747)

77.15.79 ExceptFrameCount

Synopsis: Number of frames included in an exception backtrace

Declaration: `function ExceptFrameCount : LongInt`

Visibility: default

Description: `ExceptFrameCount` returns the number of frames that are included in an exception stack frame backtrace. The function returns 0 if there is currently no exception being handled. (i.e. it only makes sense to call this function in an `finally..end` or `except..end` block.

Errors: None.

See also: `ExceptFrames` (1685), `ExceptAddr` (1684), `ExceptObject` (1685), `#rtl.system.ExceptProc` (1348)

77.15.80 ExceptFrames

Synopsis: Return the current exception stack frames

Declaration: `function ExceptFrames : PCodePointer`

Visibility: default

Description: `ExceptFrames` returns the current list frames on the exception stack. If there is no exception in progress, `Nil` is returned.

See also: `ExceptFrameCount` (1685), `ExceptAddr` (1684), `ExceptObject` (1685), `#rtl.system.ExceptProc` (1348)

77.15.81 ExceptionErrorMessage

Synopsis: Return a message describing the exception.

Declaration: `function ExceptionErrorMessage(ExceptObject: TObject;
 ExceptAddr: Pointer; Buffer: PChar;
 Size: Integer) : Integer`

Visibility: default

Description: `ExceptionErrorMessage` creates a string that describes the exception object `ExceptObject` at address `ExceptAddr`. It can be used to display exception messages. The string will be stored in the memory pointed to by `Buffer`, and will at most have `Size` characters.

The routine checks whether `ExceptObject` is a `Exception` (1808) object or not, and adapts the output accordingly.

See also: `ExceptObject` (1685), `ExceptAddr` (1684), `ShowException` (1747)

77.15.82 ExceptObject

Synopsis: Current Exception object.

Declaration: `function ExceptObject : TObject`

Visibility: default

Description: `ExceptObject` returns the currently treated exception object when an exception is raised, and the stack is unwound.

Errors: If there is no exception, the function returns `Nil`

See also: `ExceptAddr` (1684), `ExceptionErrorMessage` (1685), `ShowException` (1747)

77.15.83 ExcludeLeadingPathDelimiter

Synopsis: Strip the leading path delimiter of a path

```
Declaration: function ExcludeLeadingPathDelimiter(const Path: UnicodeString)
              : UnicodeString
function ExcludeLeadingPathDelimiter(const Path: RawByteString)
              : RawByteString
```

Visibility: default

Description: `ExcludeLeadingPathDelimiter` will remove any path delimiter on the first position of `Path` if there is one. if there is none (or the path is empty), it is left untouched.

See also: [IncludeTrailingPathDelimiter \(1734\)](#), [IncludeLeadingPathDelimiter \(1733\)](#), [ExcludeTrailingPathDelimiter \(1686\)](#), [ConcatPaths \(1671\)](#)

Listing: ./examples/sysutex/ex95.pp

Program Example95;

```
{ This program demonstrates the IncludeLeadingPathDelimiter function }
```

Uses sysutils;

Begin

```
// Will print "/this/path"
WriteLn(IncludeLeadingPathDelimiter('this/path'));
// The same result
WriteLn(IncludeLeadingPathDelimiter('/this/path'));
End.
```

77.15.84 ExcludeTrailingBackslash

Synopsis: Strip trailing directory separator from a pathname, if needed.

```
Declaration: function ExcludeTrailingBackslash(const Path: UnicodeString)
              : UnicodeString
function ExcludeTrailingBackslash(const Path: RawByteString)
              : RawByteString
```

Visibility: default

Description: `ExcludeTrailingBackslash` is provided for backwards compatibility with Delphi. Use `ExcludeTrailingPathDelimiter` (1686) instead.

See also: [IncludeTrailingPathDelimiter \(1734\)](#), [ExcludeTrailingPathDelimiter \(1686\)](#), [PathDelim \(1628\)](#), [IsPathDelimiter \(1738\)](#)

77.15.85 ExcludeTrailingPathDelimiter

Synopsis: Strip trailing directory separator from a pathname, if needed.

```
Declaration: function ExcludeTrailingPathDelimiter(const Path: UnicodeString)
                                     : UnicodeString
function ExcludeTrailingPathDelimiter(const Path: RawByteString)
                                     : RawByteString
```

Visibility: default

Description: `ExcludeTrailingPathDelimiter` removes the trailing path delimiter character (`PathDelim` (1628)) from `Path` if it is present, and returns the result.

See also: `ExcludeTrailingBackslash` (1686), `IncludeTrailingPathDelimiter` (1734), `PathDelim` (1628), `IsPathDelimiter` (1738)

77.15.86 ExecuteProcess

Synopsis: Execute another process (program).

Declaration:

```
function ExecuteProcess(const Path: RawByteString;
                        const ComLine: RawByteString;
                        Flags: TExecuteFlags) : Integer
function ExecuteProcess(const Path: RawByteString;
                        const ComLine: Array of RawByteString;
                        Flags: TExecuteFlags) : Integer
function ExecuteProcess(const Path: UnicodeString;
                        const ComLine: UnicodeString;
                        Flags: TExecuteFlags) : Integer
function ExecuteProcess(const Path: UnicodeString;
                        const ComLine: Array of UnicodeString;
                        Flags: TExecuteFlags) : Integer
```

Visibility: default

Description: `ExecuteProcess` will execute the program in `Path`, passing it the arguments in `ComLine`. `ExecuteProcess` will then wait for the program to finish, and will return the exit code of the executed program. In case `ComLine` is a single string, it will be split out in an array of strings, taking into account common whitespace and quote rules.

The program specified in `Path` is not searched in the searchpath specified in the `PATH` environment variable, so the full path to the executable must be specified in `Path`, although some operating systems may perform this search anyway (notably, windows)

`Flags` can be used to control the passing of file handles: if `ExecInheritsHandles` is included, the file handles of the current process will be passed on to the newly executed process.

Errors: In case the program could not be executed or an other error occurs, an `EOSError` (1805) exception will be raised.

See also: `TExecuteFlags` (1634), `EOSError` (1805)

77.15.87 ExeSearch

Synopsis: Search for an executable

Declaration:

```
function ExeSearch(const Name: UnicodeString;
                  const DirList: UnicodeString) : UnicodeString
function ExeSearch(const Name: RawByteString;
                  const DirList: RawByteString) : RawByteString
```

Visibility: default

Description: `ExeSearch` searches for an executable `Name` in the list of directories `DirList` (a list of directories, separator by `PathSeparator` (1362)). If the current OS also searches implicitly in the current working directory, the current directory is searched in the first place.

If the executable is found, then the full path of the executable is returned. If it is not found, an empty string is returned.

No check is performed whether the found file is actually executable.

See also: `FileSearch` (1701)

77.15.88 ExpandFileName

Synopsis: Expand a relative filename to an absolute filename.

Declaration: `function ExpandFileName(const FileName: UnicodeString) : UnicodeString`
`function ExpandFileName(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExpandFileName` expands the filename to an absolute filename. It changes all directory separator characters to the one appropriate for the system first.

If an empty filename is passed, it is expanded to the current directory.

If `BasePath` is not passed, the current directory is used as base path.

Errors: None.

See also: `ExpandFileNameCase` (1688), `ExtractFileName` (1691), `ExtractFilePath` (1692), `ExtractFileDir` (1690), `ExtractFileDrive` (1691), `ExtractFileExt` (1691), `ExtractRelativePath` (1692)

Listing: `./examples/sysutex/ex33.pp`

Program `Example33`;

{ This program demonstrates the ExpandFileName function }

Uses `sysutils`;

Procedure `Testit (F : String)`;

begin

`WriteLn (F, ' expands to : ', ExpandFileName(F));`
end;

Begin

`Testit ('ex33.pp');`
 `Testit (ParamStr(0));`
 `Testit ('/pp/bin/win32/ppc386');`
 `Testit ('\\pp\\bin\\win32\\ppc386');`
 `Testit ('.');`

End.

77.15.89 ExpandFileNameCase

Synopsis: Expand a filename entered as case insensitive to the full path as stored on the disk.

Declaration:

```
function ExpandFileNameCase(const FileName: UnicodeString;
                           out MatchFound: TFilenameCaseMatch)
    : UnicodeString
function ExpandFileNameCase(const FileName: RawByteString;
                           out MatchFound: TFilenameCaseMatch)
    : RawByteString
```

Visibility: default

Description: On case insensitive platforms, `ExpandFileNameCase` behaves similarly to `ExpandFileName` (1688) except for the fact that it returns the final part of the path with the same case of letters as found on the disk (if it exists - otherwise the case equals the one provided on input). On case sensitive platforms it also checks whether one or more full paths exist on disk which would correspond to the provided input if treated case insensitively and returns the first such match found and information whether the match is unique or not.

Note that the behaviour is basically undefined if the input includes wildcards characters. Normally, wildcards in the last part of path provided on input are resolved to the first corresponding item found on the disk, but it is better not to rely on that and use other more suitable functions if working with wildcards like `FindFirst` (1705)/`FindNext` (1707).

Errors: None.

See also: `ExpandFileName` (1688), `ExtractFileName` (1691), `ExtractFilePath` (1692), `ExtractFileDir` (1690), `ExtractFileDrive` (1691), `ExtractFileExt` (1691), `ExtractRelativePath` (1692)

Listing: ./examples/sysutex/ex33.pp

Program Example33;

{ This program demonstrates the ExpandFileName function }

Uses sysutils;

Procedure Testit (F : **String**);

begin

WriteLn (F, ' expands to : ', **ExpandFileName**(F));

end;

Begin

 Testit('ex33.pp');

 Testit(**ParamStr**(0));

 Testit('/pp/bin/win32/ppc386');

 Testit('\pp\bin\win32\ppc386');

 Testit('.');

End.

77.15.90 ExpandUNCFileName

Synopsis: Expand a relative filename to an absolute UNC filename.

Declaration:

```
function ExpandUNCFileName(const FileName: UnicodeString)
    : UnicodeString
function ExpandUNCFileName(const FileName: RawByteString)
    : RawByteString
```

Visibility: default

Description: ExpandUNCFileName runs ExpandFileName (1688) on FileName and then attempts to replace the drive letter by the name of a shared disk.

Errors: If an unexpected error occurs while determining the name of the shared disk, an empty string is returned.

See also: ExpandFileName (1688), ExtractFileName (1691), ExtractFilePath (1692), ExtractFileDir (1690), ExtractFileDrive (1691), ExtractFileExt (1691), ExtractRelativePath (1692)

77.15.91 ExtractFileDir

Synopsis: Extract the drive and directory part of a filename.

Declaration: function ExtractFileDir(const FileName: UnicodeString) : UnicodeString
function ExtractFileDir(const FileName: RawByteString) : RawByteString

Visibility: default

Description: ExtractFileDir returns only the directory part of FileName, including a drive letter. The directory name has NO ending directory separator, in difference with ExtractFilePath (1692).

Errors: None.

See also: ExtractFileName (1691), ExtractFilePath (1692), ExtractFileDir (1690), ExtractFileDrive (1691), ExtractFileExt (1691), ExtractRelativePath (1692)

Listing: ./examples/sysutex/ex34.pp

Program Example34;

{ This program demonstrates the ExtractFileName function }
{ \$H+ }

Uses sysutils;

Procedure Testit(F : String);

begin

Writeln ('FileName : ', F);
 Writeln ('Has Name : ', ExtractFileName(F));
 Writeln ('Has Path : ', ExtractFilePath(F));
 Writeln ('Has Extension : ', ExtractFileExt(F));
 Writeln ('Has Directory : ', ExtractFileDir(F));
 Writeln ('Has Drive : ', ExtractFileDrive(F));

end;

Begin

 Testit (Paramstr(0));
 Testit ('/usr/local/bin/mysqld');
 Testit ('c:\pp\bin\win32\ppc386.exe');
 Testit ('/pp/bin/win32/ppc386.exe');

End.

77.15.92 ExtractFileDrive

Synopsis: Extract the drive part from a filename.

Declaration: `function ExtractFileDrive(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileDrive(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFileDrive` extracts the drive letter from a filename. Note that some operating systems do not support drive letters.

For an example, see `ExtractFileDir` (1690).

See also: `ExtractFileName` (1691), `ExtractFilePath` (1692), `ExtractFileDir` (1690), `ExtractFileDrive` (1691), `ExtractFileExt` (1691), `ExtractRelativePath` (1692)

77.15.93 ExtractFileExt

Synopsis: Return the extension from a filename.

Declaration: `function ExtractFileExt(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileExt(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFileExt` returns the extension (including the . (dot) character) of `FileName`.

For an example, see `ExtractFileDir` (1690).

Errors: None.

See also: `ChangeFileExt` (1667), `ExtractFileName` (1691), `ExtractFilePath` (1692), `ExtractFileDir` (1690), `ExtractFileDrive` (1691), `ExtractFileExt` (1691), `ExtractRelativePath` (1692)

77.15.94 ExtractFileName

Synopsis: Extract the filename part from a full path filename.

Declaration: `function ExtractFileName(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileName(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFileName` returns the filename part from `FileName`. The filename consists of all characters after the last directory separator character ('/' or '\') or drive letter.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` (1692) and `ExtractFileName`.

For an example, see `ExtractFileDir` (1690).

Errors: None.

See also: `ExtractFileName` (1691), `ExtractFilePath` (1692), `ExtractFileDir` (1690), `ExtractFileDrive` (1691), `ExtractFileExt` (1691), `ExtractRelativePath` (1692)

77.15.95 ExtractFilePath

Synopsis: Extract the path from a filename.

Declaration: `function ExtractFilePath(const FileName: UnicodeString) : UnicodeString`
`function ExtractFilePath(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFilePath` returns the path part (including drive letter) from `FileName`. The path consists of all characters before the last directory separator character ('/' or '\'), including the directory separator itself. In case there is only a drive letter, that will be returned.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` and `ExtractFileName` (1691).

For an example, see `ExtractFileDir` (1690).

Errors: None.

See also: `ExtractFileName` (1691), `ExtractFilePath` (1692), `ExtractFileDir` (1690), `ExtractFileDrive` (1691), `ExtractFileExt` (1691), `ExtractRelativePath` (1692)

77.15.96 ExtractRelativePath

Synopsis: Extract a relative path from a filename, given a base directory.

Declaration: `function ExtractRelativePath(const BaseName: UnicodeString;`
`const DestName: UnicodeString)`
`: UnicodeString`
`function ExtractRelativePath(const BaseName: RawByteString;`
`const DestName: RawByteString)`
`: RawByteString`

Visibility: default

Description: `ExtractRelativePath` constructs a relative path to go from `BaseName` to `DestName`. If `DestName` is on another drive (Not on Unix-like platforms) then the whole `Destname` is returned.

Note that directories must end on a path delimiter for this function to work correctly. If not, the last part is stripped and treated as a file name.

Errors: None.

See also: `ExtractFileName` (1691), `ExtractFilePath` (1692), `ExtractFileDir` (1690), `ExtractFileDrive` (1691), `ExtractFileExt` (1691)

Listing: ./examples/sysutex/ex35.pp

Program Example35;

{ This program demonstrates the ExtractRelativePath function }

Uses sysutils;

Procedure Testit (FromDir, ToDir : **String**);

begin

Write ('From "', FromDir, '" to "', ToDir, '" via " ');

WriteLn (ExtractRelativePath(FromDir, ToDir), '" ');

end;

Begin

```

Testit ('/pp/src/compiler/', '/pp/bin/win32/ppc386/');
Testit ('/pp/bin/win32/ppc386/', '/pp/src/compiler/');
Testit ('/pp/bin/win32/', '/pp/src/compiler/ppcx386/');
Testit ('/pp/bin/win32/', '/pp/src/compiler/ppcx386/');
Testit ('/pp/bin/win32', '/pp/src/compiler/ppcx386');
Testit ('e:/pp/bin/win32/ppc386/', 'd:/pp/src/compiler/');
Testit ('e:\pp\bin\win32\ppc386/', 'd:\pp\src\compiler/');
Testit ('C:\FPC\3.0.2\ ', 'C:\FPC\3.0.2\ ');
Testit ('C:\FPC\3.0.2\ ', 'C:\FPC\3.0.4 rc1\ ');
Testit ('Q:\ ', 'Q:\FPC\3.0.4 rc1\ ');

```

End.**77.15.97 ExtractShortPathName**

Synopsis: Returns a 8.3 path name

Declaration:

```

function ExtractShortPathName(const FileName: UnicodeString)
    : UnicodeString
function ExtractShortPathName(const FileName: RawByteString)
    : RawByteString

```

Visibility: default

Description: `ExtractShortPathName` returns a 8.3 compliant filename that represents the same file as `FileName`. On platforms other than windows, this is `FileName` itself.

See also: `ExtractFilePath` ([1692](#)), `ExtractFileName` ([1691](#))

77.15.98 FileAge

Synopsis: Return the timestamp of a file.

Declaration:

```

function FileAge(const FileName: UnicodeString) : LongInt
function FileAge(const FileName: UnicodeString;
    out FileDateTime: TDateTime; FollowLink: Boolean)
    : Boolean
function FileAge(const FileName: RawByteString;
    out FileDateTime: TDateTime; FollowLink: Boolean)
    : Boolean
function FileAge(const FileName: RawByteString) : LongInt

```

Visibility: default

Description: `FileAge` returns the last modification time of file `FileName`. The `FileDate` format can be transformed to `TDateTime` format with the `FileDateToDateTime` ([1696](#)) function.

Fileage cannot be used on directories, it will return -1 if `FileName` indicates a directory.

Errors: In case of errors, -1 is returned.

See also: `FileDateToDateTime` ([1696](#)), `FileExists` ([1696](#)), `FileGetAttr` ([1697](#))

Listing: `./examples/sysutex/ex36.pp`

```

Program Example36;

{ This program demonstrates the FileAge function }

Uses sysutils;

Var S : TDateTime;
     fa : Longint;

Begin
    fa:=FileAge( 'ex36.pp' );
    If Fa<>-1 then
        begin
            S:=FileDateToDateTime(fa);
            Writeln ( 'I 'm from ',DateTimeToStr(S))
        end;
End.

```

77.15.99 FileClose

Synopsis: Close a file handle.

Declaration: `procedure FileClose(Handle: THandle)`

Visibility: default

Description: `FileClose` closes the file handle `Handle`. After this call, attempting to read or write from the handle will result in an error.

For an example, see [FileCreate \(1694\)](#)

Errors: None.

See also: FileCreate (1694), FileWrite (1704), FileOpen (1700), FileRead (1701), FileTruncate (1704), FileSeek (1702)

77.15.100 FileCreate

Synopsis: Create a new file and return a handle to it.

```
Declaration: function FileCreate(const FileName: UnicodeString) : THandle
            function FileCreate(const FileName: UnicodeString; Rights: Integer)
                        : THandle
            function FileCreate(const FileName: UnicodeString; ShareMode: Integer;
                        Rights: Integer) : THandle
            function FileCreate(const FileName: RawByteString) : THandle
            function FileCreate(const FileName: RawByteString; Rights: Integer)
                        : THandle
            function FileCreate(const FileName: RawByteString; ShareMode: Integer;
                        Rights: Integer) : THandle
```

Visibility: default

Description: FileCreate creates a new file with name FileName on the disk and returns a file handle which can be used to read or write from the file with the FileRead (1701) and FileWrite (1704) functions.

If a file with name `FileName` already existed on the disk, it is overwritten.

The `ShareMode` parameter determines how file sharing is handled for the new file. It can have one or more of the following values, OR-ed together:

Table 77.24:

Name	Description
<code>fmShareCompat</code>	Open file in DOS share-compatibility mode
<code>fmShareDenyNone</code>	Do not lock file.
<code>fmShareDenyRead</code>	Lock file so other processes cannot read.
<code>fmShareDenyWrite</code>	Lock file so other processes can only read.
<code>fmShareExclusive</code>	Lock file for exclusive use

The optional `Rights` parameter only has an effect under UNIX, where it can be used to set the mode (read, write, execute, sticky bit, setgid and setuid flags) of the created file to the specified custom value. On other platforms, the `Rights` parameter is ignored.

Errors: If an error occurs (e.g. disk full or non-existent path), the function returns `THandle(-1)`.

See also: `FileClose` (1694), `FileWrite` (1704), `FileOpen` (1700), `FileRead` (1701), `FileTruncate` (1704), `FileSeek` (1702)

Listing: `./examples/sysutex/ex37.pp`

Program `Example37`;

{ This program demonstrates the FileCreate/FileSeek/FileReed/FileTruncate functions }

Uses `sysutils`;

Var `I,J,F : Longint`;

Begin

```

F:=FileCreate ('test.dat');
If F=-1 then
  Halt(1);
For I:=0 to 100 do
  FileWrite(F,I,SizeOf(i));
FileClose(f);
F:=FileOpen ('test.dat',fmOpenRead);
For I:=0 to 100 do
  begin
    FileRead (F,J,SizeOf(J));
    If J<>I then
      Writeln ('Mismatch at file position ',I)
    end;
FileSeek(F,0,fsFromBeginning);
Randomize;
Repeat
  FileSeek(F,Random(100)*4,fsFromBeginning);
  FileRead (F,J,SizeOf(J));
  Writeln ('Random read : ',j);
Until J>80;
FileClose(F);
F:=FileOpen('test.dat',fmOpenWrite);
I:=50*SizeOf(Longint);
If FileTruncate(F,I) then

```

```

    WriteLn('Successfully truncated file to ',l,' bytes. ');
    FileClose(F);
End.

```

77.15.101 FileDateToDateTime

Synopsis: Convert a `FileDate` value to a `TDateTime` value.

Declaration: `function FileDateToDateTime(Filedate: LongInt) : TDateTime`

Visibility: default

Description: `FileDateToDateTime` converts the date/time encoded in `filedate` to a `TDateTime` encoded form. It can be used to convert date/time values returned by the `FileAge` (1693) or `FindFirst` (1705)/`FindNext` (1707) functions to `TDateTime` form.

Errors: None.

See also: `DateTimeToFileDate` (1674)

Listing: `./examples/sysutex/ex13.pp`

Program `Example13`;

{ This program demonstrates the FileDateToDateTime function }

Uses `sysutils`;

Var

`ThisAge : Longint`;

Begin

`Write ('ex13.pp created on :');`

`ThisAge:=FileAge('ex13.pp');`

`WriteLn (DateTimeToStr(FileDateToDateTime(ThisAge)));`

End.

77.15.102 FileExists

Synopsis: Check whether a particular file exists in the file system.

Declaration: `function FileExists(const FileName: UnicodeString; FollowLink: Boolean) : Boolean`

`function FileExists(const FileName: RawByteString; FollowLink: Boolean) : Boolean`

Visibility: default

Description: `FileExists` returns `True` if a file with name `FileName` exists on the disk, `False` otherwise. On windows, this function will return `False` if a directory is passed as `FileName`.

On Unixes, passing a directory name used to result in `True`. (The rationale is that on UNIX, a directory is a file as well). As of version 3.2.0, this behaviour has been changed for a Delphi-compatible approach.

Note that this function accepts a single filename as an argument, without wildcards. To check for the existence of multiple files, see the `FindFirst` (1705) function.

Errors: None.

See also: [FindFirst \(1705\)](#), [FileAge \(1693\)](#), [FileGetAttr \(1697\)](#), [FileSetAttr \(1703\)](#)

Listing: ./examples/sysutex/ex38.pp

Program Example38 ;

{ This program demonstrates the FileExists function }

Uses sysutils ;

Begin

If FileExists (ParamStr(0)) **Then**

 WriteLn ('All is well, I seem to exist.');

End.

77.15.103 FileFlush

Synopsis: Synchronize file contents to disk

Declaration: function FileFlush(Handle: THandle) : Boolean

Visibility: default

Description: FileFlush can be used to force the operating system to write any cached changes to file Handle to disk. It returns True if the operation completed successfully. Note that not all operating systems support this operation.

Errors: On error, check the GetLastError ([1729](#)) function result for more information about the error.

See also: [FileClose \(1694\)](#), [FileWrite \(1704\)](#), [FileOpen \(1700\)](#)

77.15.104 FileGetAttr

Synopsis: Return attributes of a file.

Declaration: function FileGetAttr(const FileName: UnicodeString) : LongInt
function FileGetAttr(const FileName: RawByteString) : LongInt

Visibility: default

Description: FileGetAttr returns the attribute settings of file FileName. The attribute is a OR-ed combination of the following constants:

faReadOnlyThe file is read-only.

faHiddenThe file is hidden. (On UNIX, this means that the filename starts with a dot)

faSysFileThe file is a system file (On UNIX, this means that the file is a character, block or FIFO file).

faVolumeIdVolume Label. Only for DOS/Windows on a plain FAT (not VFAT or Fat32) file system.

faDirectoryFile is a directory.

faArchivefile should be archived. Not possible on Unix

Errors: In case of error, -1 is returned.

See also: FileSetAttr ([1703](#)), FileAge ([1693](#)), FileGetDate ([1698](#))

Listing: ./examples/sysutex/ex40.pp

Program Example40;

{ This program demonstrates the FileGetAttr function }

Uses sysutils;

Procedure Testit (**Name** : **String**);

Var F : Longint;

Begin

 F:= FileGetAttr (**Name**);

If F<>-1 **then**

begin

 Writeln ('Testing : ',**Name**);

If (F and faReadOnly)<>0 **then**

 Writeln ('File is ReadOnly');

If (F and faHidden)<>0 **then**

 Writeln ('File is hidden');

If (F and faSysFile)<>0 **then**

 Writeln ('File is a system file');

If (F and faVolumeID)<>0 **then**

 Writeln ('File is a disk label');

If (F and faArchive)<>0 **then**

 Writeln ('File is artchive file');

If (F and faDirectory)<>0 **then**

 Writeln ('File is a directory');

end

else

 Writeln ('Error reading attributes of ',**Name**);

end;

begin

 testit ('ex40.pp');

 testit (**ParamStr**(0));

 testit ('.');

 testit ('/');

End.

77.15.105 FileGetDate

Synopsis: Return the file time of an opened file.

Declaration: function FileGetDate(Handle: THandle) : LongInt

Visibility: default

Description: FileGetdate returns the filetype of the opened file with file handle Handle. It is the same as FileAge ([1693](#)), with this difference that FileAge only needs the file name, while FilegetDate needs an open file handle.

Errors: On error, -1 is returned.

See also: FileAge ([1693](#))

Listing: ./examples/sysutex/ex39.pp

Program Example39;

{ This program demonstrates the FileGetDate function }

Uses sysutils;

Var F,D : Longint;

Begin

F:= FileCreate('test.dat');

D:= **FileGetDate**(F);

WriteLn ('File created on ', **DateTimeToStr**(**FileDateToDateTime**(D)));

FileClose(F);

DeleteFile('test.dat');

End.

77.15.106 FileGetSymLinkTarget

Synopsis: Get the target filename and size of a symlink

Declaration: function FileGetSymLinkTarget(const FileName: UnicodeString;
 out SymLinkRec: TUnicodeSymLinkRec)
 : Boolean
 function FileGetSymLinkTarget(const FileName: UnicodeString;
 out TargetName: UnicodeString) : Boolean
 function FileGetSymLinkTarget(const FileName: RawByteString;
 out SymLinkRec: TRawbyteSymLinkRec)
 : Boolean
 function FileGetSymLinkTarget(const FileName: RawByteString;
 out TargetName: RawByteString) : Boolean

Visibility: default

Description: FileGetSymLinkTarget returns the target filename, size and attributes of a symbolic link in SymLinkRec. On unix-like systems, the filemode is also returned. The filename can be a relative filename, it will not be expanded.

See also: TUnicodeSymLinkRec ([1798](#)), TRawbyteSymLinkRec ([1796](#))

77.15.107 FileIsReadOnly

Synopsis: Check whether a file is read-only.

Declaration: function FileIsReadOnly(const FileName: UnicodeString) : Boolean
 function FileIsReadOnly(const FileName: RawByteString) : Boolean

Visibility: default

Description: FileIsReadOnly checks whether FileName exists in the file system and is a read-only file. If this is the case, the function returns True, otherwise False is returned.

See also: FileExists ([1696](#))

77.15.108 FileOpen

Synopsis: Open an existing file and return a file handle

```

Declaration: function FileOpen(const FileName: UnicodeString; Mode: Integer)
              : THandle
              function FileOpen(const FileName: RawByteString; Mode: Integer)
              : THandle

```

Visibility: default

Description: `FileOpen` opens a file with name `FileName` with mode `Mode`. `Mode` can be one of the following constants:

fmOpenReadOpen file in read-only mode

fmOpenWriteOpen file in write-only mode

fmOpenReadWriteOpen file in read/write mode.

Under Windows and Unix, the above mode can be or-ed with one of the following sharing/locking flags:

fmShareCompatOpen file in DOS share-compatibility mode

fmShareExclusiveLock file for exclusive use

fmShareDenyWriteLock file so other processes can only read.

fmShareDenyReadLock file so other processes cannot read.

fmShareDenyNoneDo not lock file.

If the file has been successfully opened, it can be read from or written to (depending on the `Mode` parameter) with the `FileRead` (1701) and `FileWrite` functions.

Remark Remark that you cannot open a file if it doesn't exist yet, i.e. it will not be created for you. If you want to create a new file, or overwrite an old one, use the `FileCreate` (1694) function.

There are some limitations to the sharing modes.

- 1.Sharing modes are only available on Unix and Windows platforms.
- 2.Unix only support sharing modes as of 2.4.0.
- 3.`fmShareDenyRead` only works under Windows at this time, and will always result in an error on Unix platforms because its file locking APIs do not support this concept.
- 4.File locking is advisory on Unix platforms. This means that the locks are only checked when a file is opened using a file locking mode. In other cases, existing locks are simply ignored. In particular, this means that `fmShareDenyNone` has no effect under Unix, because this can only be implemented as "use no locking" on those platforms. As a result, opening a file using this mode will always succeed under Unix as far as the locking is concerned, even if the file has already been opened using `fmShareExclusive`.
- 5.Under Solaris, closing a single file handle associated with a file will result in all locks on that file (even via other handles) being destroyed due to the behaviour of the underlying API (fcntl). Because of the same reason, on Solaris you cannot use `fmShareDenyWrite` in combination with `fmOpenWrite`, nor `fmShareExclusive` in combination with `fmOpenRead` although both work with `fmOpenReadWrite`.

For an example, see `FileCreate` (1694)

Errors: On Error, `THandle(-1)` is returned.

See also: `fmOpenRead` (1625), `fmOpenWrite` (1625), `fmOpenReadWrite` (1625), `fmShareDenyWrite` (1626), `fmShareExclusive` (1626), `fmShareDenyRead` (1626), `fmShareDenyNone` (1625), `fmShareCompat` (1625), `FileClose` (1694), `FileWrite` (1704), `FileCreate` (1694), `FileRead` (1701), `FileTruncate` (1704), `FileSeek` (1702)

77.15.109 FileRead

Synopsis: Read data from a file handle in a buffer.

Declaration: `function FileRead(Handle: THandle; out Buffer; Count: LongInt) : LongInt`

Visibility: default

Description: `FileRead` reads `Count` bytes from file-handle `Handle` and stores them into `Buffer`. `Buffer` must be at least `Count` bytes long. No checking on this is performed, so be careful not to overwrite any memory. `Handle` must be the result of a `FileOpen` (1700) call.

The function returns the number of bytes actually read, or -1 on error.

For an example, see `FileCreate` (1694)

Errors: On error, -1 is returned.

See also: `FileClose` (1694), `FileWrite` (1704), `FileCreate` (1694), `FileOpen` (1700), `FileTruncate` (1704), `FileSeek` (1702)

77.15.110 FileSearch

Synopsis: Search for a file in a path.

```
Declaration: function FileSearch(const Name: UnicodeString;
                                const DirList: UnicodeString;
                                Options: TFileSearchOptions) : UnicodeString
function FileSearch(const Name: UnicodeString;
                    const DirList: UnicodeString;
                    ImplicitCurrentDir: Boolean) : UnicodeString
function FileSearch(const Name: RawByteString;
                    const DirList: RawByteString;
                    Options: TFileSearchOptions) : RawByteString
function FileSearch(const Name: RawByteString;
                    const DirList: RawByteString;
                    ImplicitCurrentDir: Boolean) : RawByteString
```

Visibility: default

Description: `FileSearch` looks for the file `Name` in `DirList`, where `dirlist` is a list of directories, separated by semicolons or colons. It returns the full filename of the first match found. The optional `Options` parameter may be specified to influence the behaviour of the search algorithm. It is a set of the following options:

sfoImplicitCurrentDir Always search the current directory first, even if it is not specified.

sfoStripQuotes Strip quotes from the components in the search path.

A deprecated form of the function allowed to specify using the boolean `ImplicitCurrentDir` parameter whether the current directory was searched implicitly or not. By default, the current directory is searched.

Errors: On error, an empty string is returned.

See also: `ExpandFileName` (1688), `FindFirst` (1705)

Listing: `./examples/sysutex/ex41.pp`

Program Example41;

{ Program to demonstrate the FileSearch function. }

Uses Sysutils;

Const

```
{ $ifdef unix }
  FN = 'find';
  P = './bin:/usr/bin';
{ $else }
  FN = 'find.exe';
  P = 'c:\dos;c:\windows;c:\windows\system;c:\windows\system32';
{ $endif }
```

begin

```
  WriteLn ('find is in : ', FileSearch (FN,P));
end.
```

77.15.111 FileSeek

Synopsis: Set the current file position on a file handle.

Declaration:

```
function FileSeek(Handle: THandle; FOffset: LongInt; Origin: LongInt)
    : LongInt
function FileSeek(Handle: THandle; FOffset: Int64; Origin: LongInt)
    : Int64
```

Visibility: default

Description: FileSeek sets the file pointer on position Offset, starting from Origin. Origin can be one of the following values:

fsFromBeginning Offset is relative to the first byte of the file. This position is zero-based. i.e. the first byte is at offset 0.

fsFromCurrent Offset is relative to the current position.

fsFromEnd Offset is relative to the end of the file. This means that Offset can only be zero or negative in this case.

If successful, the function returns the new file position, relative to the beginning of the file.

Remark The above mentioned constants do not exist in Delphi.

Errors: On error, -1 is returned.

See also: FileClose ([1694](#)), FileWrite ([1704](#)), FileCreate ([1694](#)), FileOpen ([1700](#)), FileRead ([1701](#)), FileTruncate ([1704](#))

Listing: ./examples/sysutex/ex37.pp

Program Example37;

{ This program demonstrates the FileCreate/FileSeek/FileReed/FileTruncate functions }

Uses sysutils;

```

Var I,J,F : Longint;

Begin
  F:=FileCreate ('test.dat');
  If F=-1 then
    Halt(1);
  For I:=0 to 100 do
    FileWrite(F,I,SizeOf(i));
  FileClose(f);
  F:=FileOpen ('test.dat',fmOpenRead);
  For I:=0 to 100 do
    begin
      FileRead (F,J,SizeOf(J));
      If J<>I then
        WriteLn ('Mismatch at file position ',I)
      end;
      FileSeek(F,0,fsFromBeginning);
      Randomize;
      Repeat
        FileSeek(F,Random(100)*4,fsFromBeginning);
        FileRead (F,J,SizeOf(J));
        WriteLn ('Random read : ',j);
      Until J>80;
      FileClose(F);
      F:=FileOpen( 'test.dat',fmOpenWrite);
      I:=50*SizeOf(Longint);
      If FileTruncate(F,I) then
        WriteLn('Successfully truncated file to ',I,' bytes. ');
      FileClose(F);
End.

```

77.15.112 FileSetAttr

Synopsis: Set the attributes of a file.

Declaration: function FileSetAttr(const Filename: UnicodeString; Attr: LongInt)
 : LongInt
 function FileSetAttr(const Filename: RawByteString; Attr: LongInt)
 : LongInt

Visibility: default

Description: FileSetAttr sets the attributes of FileName to Attr. If the function was successful, 0 is returned, -1 otherwise. Attr can be set to an OR-ed combination of the predefined faXXX constants. This function is not implemented on Unixes.

Errors: On error, -1 is returned (always on Unixes).

See also: FileGetAttr ([1697](#)), FileGetDate ([1698](#)), FileSetDate ([1703](#))

77.15.113 FileSetDate

Synopsis: Set the date of a file.

Declaration: function FileSetDate(const FileName: UnicodeString; Age: LongInt)
 : LongInt


```
function FileSetDate(const FileName: RawByteString; Age: LongInt)
    : LongInt
function FileSetDate(Handle: THandle; Age: LongInt) : LongInt
```

Visibility: default

Description: `FileSetDate` sets the file date of the open file with handle `Handle` or to `Age`, where `Age` is a DOS date-and-time stamp value.

Alternatively, the filename may be specified with the `FileName` argument. This variant of the call is mandatory on Unixes, since there is no OS support for setting a file timestamp based on a handle. (the handle may not be a real file at all).

The function returns zero if successful.

Errors: On Unix, the handle variant always returns -1, since this is impossible to implement. On Windows and DOS, a negative error code is returned.

77.15.114 FileTruncate

Synopsis: Truncate an open file to a given size.

Declaration: `function FileTruncate(Handle: THandle; Size: Int64) : Boolean`

Visibility: default

Description: `FileTruncate` truncates the file with handle `Handle` to `Size` bytes. The file must have been opened for writing prior to this call. The function returns `True` is successful, `False` otherwise.

For an example, see `FileCreate` (1694).

Errors: On error, the function returns `False`.

See also: `FileClose` (1694), `FileWrite` (1704), `FileCreate` (1694), `FileOpen` (1700), `FileRead` (1701), `FileSeek` (1702)

77.15.115 FileWrite

Synopsis: Write data from a buffer to a given file handle.

Declaration: `function FileWrite(Handle: THandle; const Buffer; Count: LongInt)
 : LongInt`

Visibility: default

Description: `FileWrite` writes `Count` bytes from `Buffer` to the file with handle `Handle`. Prior to this call, the file must have been opened for writing. `Buffer` must be at least `Count` bytes large, or a memory access error may occur.

The function returns the number of bytes written, or -1 in case of an error.

For an example, see `FileCreate` (1694).

Errors: In case of error, -1 is returned.

See also: `FileClose` (1694), `FileCreate` (1694), `FileOpen` (1700), `FileRead` (1701), `FileTruncate` (1704), `FileSeek` (1702)

77.15.116 FindClose

Synopsis: Close a find handle

Declaration: `procedure FindClose(var F: TUnicodeSearchRec)`
`procedure FindClose(var F: TRawbyteSearchRec)`

Visibility: default

Description: `FindClose` ends a series of `FindFirst` (1705)/`FindNext` (1707) calls, and frees any memory used by these calls. It is *absolutely* necessary to do this call, or huge memory losses may occur.

For an example, see `FindFirst` (1705).

Errors: None.

See also: `FindFirst` (1705), `FindNext` (1707)

77.15.117 FindCmdLineSwitch

Synopsis: Check whether a certain switch is present on the command-line.

Declaration: `function FindCmdLineSwitch(const Switch: string;`
`const Chars: TSysCharSet; IgnoreCase: Boolean)`
`: Boolean`
`function FindCmdLineSwitch(const Switch: string; IgnoreCase: Boolean)`
`: Boolean`
`function FindCmdLineSwitch(const Switch: string) : Boolean`

Visibility: default

Description: `FindCmdLineSwitch` will check all command-line arguments for the presence of the option `Switch`. It will return `True` if it was found, `False` otherwise. Characters that appear in `Chars` (default is `SwitchChars` (1630)) are assumed to indicate an option (switch). If the parameter `IgnoreCase` is `True`, case will be ignored when looking for the switch. Default is to search case sensitive.

Errors: None.

See also: `SwitchChars` (1630)

77.15.118 FindFirst

Synopsis: Start a file search and return a findhandle

Declaration: `function FindFirst(const Path: UnicodeString; Attr: LongInt;`
`out Rslt: TUnicodeSearchRec) : LongInt`
`function FindFirst(const Path: RawByteString; Attr: LongInt;`
`out Rslt: TRawbyteSearchRec) : LongInt`

Visibility: default

Description: `FindFirst` looks for files that match the name (possibly with wildcards) in `Path` and extra attributes `Attr`. It then fills up the `Rslt` record with data gathered about the file. It returns 0 if a file matching the specified criteria is found, a nonzero value (-1 on Unix-like platforms) otherwise.

`Attr` is an or-ed combination of the following constants:

faAnyFile Find any file (this is a combination of the other flags).

faReadOnly The file is read-only.

faHiddenThe file is hidden. (On UNIX, this means that the filename starts with a dot)

faSysFileThe file is a system file (On unix, this means that the file is a character, block or FIFO file).

faVolumeIdDrive volume Label. Not possible under unix, and on Windows-like systems, this works only for plan FAT (not Fat32 or VFAT) file systems.

faDirectoryFile is a directory.

faArchivefile needs to be archived. Not possible on Unix

It is a common misconception that `Attr` specifies a set of attributes which must be matched in order for a file to be included in the list. This is not so: The value of `Attr` specifies *additional* attributes, this means that the returned files are either normal files or have an attribute which is present in `Attr`.

Specifically: specifying `faDirectory` as a value for `Attr` does not mean that only directories will be returned. Normal files *and* directories will be returned.

The `Rslt` record can be fed to subsequent calls to `FindNext`, in order to find other files matching the specifications.

Remark A successful `FindFirst` call must *always* be followed by a `FindClose` (1705) call with the same `Rslt` record. Failure to do so will result in memory leaks. If the `findfirst` call failed (i.e. returned a nonzero handle) there is no need to call `FindClose`.

Errors: On error the function returns -1 on Unix-like platforms, a nonzero error code on Windows.

See also: `FindClose` (1705), `FindNext` (1707)

Listing: ./examples/sysutex/ex43.pp

Program Example43;

{ This program demonstrates the FindFirst function }

Uses SysUtils;

Var Info : TSearchRec;
Count : Longint;

Begin

Count:=0;

If FindFirst ('*',faAnyFile,Info)=0 **then**

begin

Repeat

Inc(Count);

With Info **do**

begin

If (Attr **and** faDirectory) = faDirectory **then**

Write('Dir : ');

WriteLn (Name:40,Size:15);

end;

Until FindNext(info)<>0;

FindClose(Info);

end;

WriteLn ('Finished search. Found ',Count,' matches');

End.

77.15.119 FindNext

Synopsis: Find the next entry in a findhandle.

Declaration: `function FindNext (var Rslt: TUnicodeSearchRec) : LongInt`
`function FindNext (var Rslt: TRawbyteSearchRec) : LongInt`

Visibility: default

Description: `FindNext` finds a next occurrence of a search sequence initiated by `FindFirst`. If another record matching the criteria in `Rslt` is found, 0 is returned, a nonzero constant is returned otherwise.

Remark The last `FindNext` call must *always* be followed by a `FindClose` call with the same `Rslt` record. Failure to do so will result in memory loss.

For an example, see `FindFirst` (1705)

Errors: On error (no more file is found), a nonzero constant is returned.

See also: `FindFirst` (1705), `FindClose` (1705)

77.15.120 FloattoCurr

Synopsis: Convert a float to a Currency value.

Declaration: `function FloattoCurr (const Value: Extended) : Currency`

Visibility: default

Description: `FloatToCurr` converts the `Value` floating point value to a `Currency` value. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` (1627) and `MaxCurrency` (1627)). If not, an `EConvertError` (1800) exception is raised.

Errors: If `Value` is out of range, an `EConvertError` (1800) exception is raised.

See also: `EConvertError` (1800), `TryFloatToCurr` (1781), `MinCurrency` (1627), `MaxCurrency` (1627)

77.15.121 FloatToDateTime

Synopsis: Convert a float to a TDateTime value.

Declaration: `function FloatToDateTime (const Value: Extended) : TDateTime`

Visibility: default

Description: `FloatToDateTime` converts the `Value` floating point value to a `TDateTime` value. It checks whether `Value` is in the valid range of dates (determined by `MinDateTime` (1627) and `MaxDateTime` (1627)). If not, an `EConvertError` (1800) exception is raised.

Errors: If `Value` is out of range, an `EConvertError` (1800) exception is raised.

See also: `EConvertError` (1800), `MinDateTime` (1627), `MaxDateTime` (1627)

77.15.122 FloatToDecimal

Synopsis: Convert a float value to a TFloatRec value.

Declaration:

```
procedure FloatToDecimal(out Result: TFloatRec; const Value;
                        ValueType: TFloatValue; Precision: Integer;
                        Decimals: Integer)
procedure FloatToDecimal(out Result: TFloatRec; Value: Extended;
                        Precision: Integer; Decimals: Integer)
```

Visibility: default

Description: FloatToDecimal converts the float Value to a float description in the ResultTFloatRec (1636) format. It will store Precision digits in the Digits field, of which at most Decimal decimals.

Errors: None.

See also: TFloatRec (1636)

77.15.123 FloatToStr

Synopsis: Convert a float value to a string using a fixed format.

Declaration:

```
function FloatToStr(Value: Extended) : string
function FloatToStr(Value: Extended;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Double) : string
function FloatToStr(Value: Double;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Single) : string
function FloatToStr(Value: Single;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Currency) : string
function FloatToStr(Value: Currency;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Comp) : string
function FloatToStr(Value: Comp; const FormatSettings: TFormatSettings)
    : string
function FloatToStr(Value: Int64) : string
function FloatToStr(Value: Int64; const FormatSettings: TFormatSettings)
    : string
```

Visibility: default

Description: FloatToStr converts the floating point variable Value to a string representation. It will choose the shortest possible notation of the two following formats:

Fixed format will represent the string in fixed notation,

Decimal format will represent the string in scientific notation.

More information on these formats can be found in FloatToStrF (1709). FloatToStr is completely equivalent to the following call:

```
FloatToStrF(Value, ffGeneral, 15, 0);
```

Note that on unix systems, the localization support must be enabled explicitly, see Localization (1616).

Errors: None.

See also: FloatToStrF (1709), FormatFloat (1722), StrToFloat (1768)

Listing: ./examples/sysutex/ex67.pp

Program Example67;

{ This program demonstrates the FloatToStr function }

Uses sysutils;

Procedure Testit (Value : Extended);

begin

Writeln (Value, ' -> ', **FloatToStr** (Value));

Writeln (-Value, ' -> ', **FloatToStr** (-Value));

end;

Begin

 Testit (0.0);

 Testit (1.1);

 Testit (1.1e-3);

 Testit (1.1e-20);

 Testit (1.1e-200);

 Testit (1.1e+3);

 Testit (1.1e+20);

 Testit (1.1e+200);

End.

77.15.124 FloatToStrF

Synopsis: Convert a float value to a string using a given format.

Declaration: function FloatToStrF(Value: Extended; format: TFloatFormat;
 Precision: Integer; Digits: Integer) : string
 function FloatToStrF(Value: Extended; format: TFloatFormat;
 Precision: Integer; Digits: Integer;
 const FormatSettings: TFormatSettings) : string
 function FloatToStrF(Value: Double; format: TFloatFormat;
 Precision: Integer; Digits: Integer) : string
 function FloatToStrF(Value: Double; format: TFloatFormat;
 Precision: Integer; Digits: Integer;
 const FormatSettings: TFormatSettings) : string
 function FloatToStrF(Value: Single; format: TFloatFormat;
 Precision: Integer; Digits: Integer) : string
 function FloatToStrF(Value: Single; format: TFloatFormat;
 Precision: Integer; Digits: Integer;
 const FormatSettings: TFormatSettings) : string
 function FloatToStrF(Value: Comp; format: TFloatFormat;
 Precision: Integer; Digits: Integer) : string
 function FloatToStrF(Value: Comp; format: TFloatFormat;
 Precision: Integer; Digits: Integer;

```

        const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Currency; format: TFloatFormat;
        Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Currency; format: TFloatFormat;
        Precision: Integer; Digits: Integer;
        const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Int64; format: TFloatFormat;
        Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Int64; format: TFloatFormat;
        Precision: Integer; Digits: Integer;
        const FormatSettings: TFormatSettings) : string

```

Visibility: default

Description: `FloatToStrF` converts the floating point number value to a string representation, according to the settings of the parameters `Format`, `Precision` and `Digits`.

The meaning of the `Precision` and `Digits` parameter depends on the `Format` parameter. The format is controlled mainly by the `Format` parameter. It can have one of the following values:

ffcurrencyMoney format. Value is converted to a string using the global variables `CurrencyString`, `CurrencyFormat` and `NegCurrFormat`. The `Digits` parameter specifies the number of digits following the decimal point and should be in the range -1 to 18. If `Digits` equals -1, `CurrencyDecimals` is assumed. The `Precision` parameter is ignored.

ffExponentScientific format. Value is converted to a string using scientific notation: 1 digit before the decimal point, possibly preceded by a minus sign if `Value` is negative. The number of digits after the decimal point is controlled by `Precision` and must lie in the range 0 to 15.

ffFixedFixed point format. Value is converted to a string using fixed point notation. The result is composed of all digits of the integer part of `Value`, preceded by a minus sign if `Value` is negative. Following the integer part is `DecimalSeparator` and then the fractional part of `Value`, rounded off to `Digits` numbers. If the number is too large then the result will be in scientific notation.

ffGeneralGeneral number format. The argument is converted to a string using `ffExponent` or `ffFixed` format, depending on which one gives the shortest string. There will be no trailing zeroes. If `Value` is less than 0.00001 or if the number of decimals left of the decimal point is larger than `Precision` then scientific notation is used, and `Digits` is the minimum number of digits in the exponent. Otherwise `Digits` is ignored.

ffnumberIs the same as `ffFixed`, except that thousand separators are inserted in the resulting string.

Errors: None.

See also: `FloatToStr` ([1708](#)), `FloatToText` ([1711](#))

Listing: `./examples/sysutex/ex68.pp`

Program `Example68`;

{ This program demonstrates the FloatToStrF function }

Uses `sysutils`;

Const `Fmt : Array [TFloatFormat] of string[10] =`
 `('general', 'exponent', 'fixed', 'number', 'Currency');`

Procedure `Testit (Value : Extended);`

```

Var I,J : longint;
      FF : TFloatFormat;

begin
  For I:=5 to 15 do
    For J:=1 to 4 do
      For FF:=ffgeneral to ffcurrency do
        begin
          Write (Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ');
          Writeln (FloatToStrf(Value, FF, I, J));
          Write (-Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ');
          Writeln (FloatToStrf(-Value, FF, I, J));
        end;
      end;
    end;
  end;

Begin
  Testit (1.1);
  Testit (1.1E1);
  Testit (1.1E-1);
  Testit (1.1E5);
  Testit (1.1E-5);
  Testit (1.1E10);
  Testit (1.1E-10);
  Testit (1.1E15);
  Testit (1.1E-15);
  Testit (1.1E100);
  Testit (1.1E-100);
End.

```

77.15.125 FloatToText

Synopsis: Return a string representation of a float, with a given format.

Declaration:

```

function FloatToText(Buffer: PChar; Value: Extended;
                    format: TFloatFormat; Precision: Integer;
                    Digits: Integer) : LongInt
function FloatToText(Buffer: PChar; Value: Extended;
                    format: TFloatFormat; Precision: Integer;
                    Digits: Integer;
                    const FormatSettings: TFormatSettings) : LongInt

```

Visibility: default

Description: FloatToText converts the floating point variable Value to a string representation and stores it in Buffer. The conversion is governed by format, Precision and Digits. more information on these parameters can be found in FloatToStrF ([1709](#)). Buffer should point to enough space to hold the result. No checking on this is performed.

The result is the number of characters that was copied in Buffer.

Errors: None.

See also: FloatToStr ([1708](#)), FloatToStrF ([1709](#))

Listing: ./examples/sysutex/ex69.pp

```

Program Example68;

{ This program demonstrates the FloatToStrF function }

Uses sysutils;

Const Fmt : Array [TFloatFormat] of string[10] =
    ('general', 'exponent', 'fixed', 'number', 'Currency');

Procedure Testit (Value : Extended);

Var I, J : longint;
    FF : TFloatFormat;
    S : ShortString;

begin
    For I:=5 to 15 do
        For J:=1 to 4 do
            For FF:=ffgeneral to ffcurrency do
                begin
                    Write (Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ');
                    SetLength(S, FloatToText (@S[1], Value, FF, I, J));
                    Writeln (S);
                    Write (-Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ');
                    SetLength(S, FloatToText (@S[1], -Value, FF, I, J));
                    Writeln (S);
                end;
            end;
        end;
    end;

Begin
    Testit (1.1);
    Testit (1.1E1);
    Testit (1.1E-1);
    Testit (1.1E5);
    Testit (1.1E-5);
    Testit (1.1E10);
    Testit (1.1E-10);
    Testit (1.1E15);
    Testit (1.1E-15);
    Testit (1.1E100);
    Testit (1.1E-100);
End.

```

77.15.126 FloatToTextFmt

Synopsis: Convert a float value to a string using a given mask.

Declaration: function FloatToTextFmt (Buffer: PChar; Value: Extended; format: PChar;
 FormatSettings: TFormatSettings) : Integer
 function FloatToTextFmt (Buffer: PChar; Value: Extended; format: PChar)
 : Integer

Visibility: default

Description: FloatToTextFmt returns a textual representation of Value in the memory location pointed to by Buffer. it uses the formatting specification in Format to do this. The return value is the number of characters that were written in the buffer.

For a list of valid formatting characters, see [FormatFloat \(1722\)](#)

Errors: No length checking is performed on the buffer. The buffer should point to enough memory to hold the complete string. If this is not the case, an access violation may occur.

See also: [FormatFloat \(1722\)](#)

77.15.127 FmtStr

Synopsis: Format a string with given arguments.

Declaration:

```
procedure FmtStr(var Res: string; const Fmt: string;
                 const args: Array of const)
procedure FmtStr(var Res: string; const Fmt: string;
                 const args: Array of const;
                 const FormatSettings: TFormatSettings)
```

Visibility: default

Description: `FmtStr` calls [Format \(1714\)](#) with `Fmt` and `Args` as arguments, and stores the result in `Res`. For more information on how the resulting string is composed, see [Format \(1714\)](#).

Errors: In case of error, a [EConvertError \(1800\)](#) exception is raised.

See also: [Format \(1714\)](#), [FormatBuf \(1720\)](#), [EConvertError \(1800\)](#)

Listing: `./examples/sysutex/ex70.pp`

Program `Example70`;

{ This program demonstrates the FmtStr function }

Uses `sysutils`;

Var `S` : `AnsiString`;

Begin

`S := ''`;

`FmtStr` (`S`, 'For some nice examples of fomatting see %s.', ['Format']);

`Writeln` (`S`);

End.

77.15.128 ForceDirectories

Synopsis: Create a chain of directories

Declaration:

```
function ForceDirectories(const Dir: RawByteString) : Boolean
function ForceDirectories(const Dir: UnicodeString) : Boolean
```

Visibility: default

Description: `ForceDirectories` tries to create any missing directories in `Dir` till the whole path in `Dir` exists. It returns `True` if `Dir` already existed or was created successfully. If it failed to create any of the parts, `False` is returned.

77.15.129 Format

Synopsis: Format a string with given arguments.

Declaration: `function Format(const Fmt: string; const Args: Array of const) : string`
`function Format(const Fmt: string; const Args: Array of const;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: Format replaces all placeholders in `Fmt` with the arguments passed in `Args` and returns the resulting string. A placeholder looks as follows:

```
'%' [[Index] ':' ] ['-'] [Width] ['.' Precision] ArgType
```

elements between single quotes must be typed as shown without the quotes, and elements between square brackets [] are optional. The meaning of the different elements are shown below:

'%' starts the placeholder. If you want to insert a literal % character, then you must insert two of them : %%.

Index ':' takes the `Index`-th element in the argument array as the element to insert. If `index` is omitted, then the zeroth argument is taken.

'-' tells Format to left-align the inserted text. The default behaviour is to right-align inserted text. This can only take effect if the `Width` element is also specified.

Width the inserted string must have at least `Width` characters. If not, the inserted string will be padded with spaces. By default, the string is left-padded, resulting in a right-aligned string. This behaviour can be changed by the usage of the '-' character.

'.' **Precision** Indicates the precision to be used when converting the argument. The exact meaning of this parameter depends on `ArgType`.

The `Index`, `Width` and `Precision` parameters can be replaced by *, in which case their value will be read from the next element in the `Args` array. This value must be an integer, or an `EConvertError (1800)` exception will be raised.

The argument type is determined from `ArgType`. It can have one of the following values (case insensitive):

D Decimal format. The next argument in the `Args` array should be an integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

E Scientific format. The next argument in the `Args` array should be a Floating point value. The argument is converted to a decimal string using scientific notation, using `FloatToStrF (1709)`, where the optional precision is used to specify the total number of decimals. (default a value of 15 is used). The exponent is formatted using maximally 3 digits.

In short, the `E` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffexponent, Precision, 3)
```

F Fixed point format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string, using fixed notation (see `FloatToStrF (1709)`). `Precision` indicates the number of digits following the decimal point.

In short, the `F` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffFixed, ffixed, 9999, Precision)
```

GGeneral number format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string using fixed point notation or scientific notation, depending on which gives the shortest result. `Precision` is used to determine the number of digits after the decimal point.

In short, the `G` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffGeneral, Precision, 3)
```

MCurrency format. the next argument in the `Args` array must be a floating point value. The argument is converted to a decimal string using currency notation. This means that fixed-point notation is used, but that the currency symbol is appended. If precision is specified, then then it overrides the `CurrencyDecimals` global variable used in the `FloatToStrF` (1709)

In short, the `M` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffCurrency, 9999, Precision)
```

NNumber format. This is the same as fixed point format, except that thousand separators are inserted in the resulting string.

PPointer format. The next argument in the `Args` array must be a pointer (typed or untyped). The pointer value is converted to a string of length 8, representing the hexadecimal value of the pointer.

SString format. The next argument in the `Args` array must be a string. The argument is simply copied to the result string. If `Precision` is specified, then only `Precision` characters are copied to the result string.

UUnsigned decimal format. The next argument in the `Args` array should be an unsigned integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

Xhexadecimal format. The next argument in the `Args` array must be an integer. The argument is converted to a hexadecimal string with just enough characters to contain the value of the integer. If `Precision` is specified then the resulting hexadecimal representation will have at least `Precision` characters in it (with a maximum value of 32).

Errors: In case of error, an `EConvertError` exception is raised. Possible errors are:

- 1.Errors in the format specifiers.
- 2.The next argument is not of the type needed by a specifier.
- 3.The number of arguments is not sufficient for all format specifiers.

See also: `FormatBuf` (1720), `EConvertError` (1800)

Listing: `./examples/sysutex/ex71.pp`

Program `example71`;

```
{ $mode objfpc }
```

```
{ This program demonstrates the Format function }
```

Uses `sysutils`;

```
Var P : Pointer;  
      fmt, S : string;
```

```
{ Expected output:  
  [%d] => [10]
```

```

        [%%] => [%]
        [%10d] => [          10]
        [%10.4d] => [0010]
        [%10.4d] => [          0010]
        [%0:d] => [10]
        [%0:10d] => [          10]
        [%0:10.4d] => [          0010]
        [%0:-10d] => [10          ]
        [%0:-10.4d] => [0010          ]
        [%-*.d] => [00010]
    }
Procedure TestInteger;
begin
    Try
        Fmt:='[%d]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%%]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%10d]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        ffmt:='[%10.4d]';S:=Format (ffmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:d]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:10d]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:10.4d]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:-10d]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:-10.4d]';S:=Format (fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%-*.d]';S:=Format (fmt,[4,5,10]);writeln (Fmt:12,' => ',s);
    except
        On E : Exception do
            begin
                Writeln ('Exception caught : ',E.Message);
            end;
    end;
    writeln ('Press enter');
    readln;
end;

{ Expected output:
    [%x] => [A]
    [%10x] => [          A]
    [%10.4x] => [          000A]
    [%0:x] => [A]
    [%0:10x] => [          A]
    [%0:10.4x] => [          000A]
    [%0:-10x] => [A          ]
    [%0:-10.4x] => [000A          ]
    [%-*.x] => [0000A]
}
Procedure TestHexaDecimal;
begin
    try
        Fmt:='[%x]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%10x]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%10.4x]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:x]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:10x]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:10.4x]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:-10x]';S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%0:-10.4x]';S:=Format (fmt,[10]);writeln (Fmt:12,' => ',s);
        Fmt:='[%-*.x]';S:=Format (fmt,[4,5,10]);writeln (Fmt:12,' => ',s);
    
```

```

except
  On E : Exception do
    begin
      WriteLn ('Exception caught : ',E.Message);
    end;
end;
writeln ('Press enter');
readln;
end;

{ Expected output:
  [0x%p] => [0x0012D687]
  [0x%10p] => [0x 0012D687]
  [0x%10.4p] => [0x 0012D687]
  [0x%0:p] => [0x0012D687]
  [0x%0:10p] => [0x 0012D687]
  [0x%0:10.4p] => [0x 0012D687]
  [0x%0:-10p] => [0x0012D687 ]
  [0x%0:-10.4p] => [0x0012D687 ]
  [%-*.p] => [0012D687]
}

Procedure TestPointer;
begin
  P:= Pointer(1234567);
  try
    Fmt:= '[0x%p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[0x%10p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[0x%10.4p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[0x%0:p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[0x%0:10p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[0x%0:10.4p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[0x%0:-10p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[0x%0:-10.4p]'; S:=Format (fmt,[P]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%-*.p]'; S:=Format (fmt,[4,5,P]); writeln (Fmt:12, ' => ',s);
  except
    On E : Exception do
      begin
        WriteLn ('Exception caught : ',E.Message);
      end;
    end;
    writeln ('Press enter');
    readln;
  end;

{ Expected output:
  [%s]=> [This is a string]
  [%0:s]=> [This is a string]
  [%0:18s]=> [ This is a string]
  [%0:-18s]=> [This is a string ]
  [%0:18.12s]=> [ This is a st
  [%-*.s]=> [This is a st ]
}

Procedure TestString;
begin
  try
    Fmt:= '[%s]'; S:=Format(fmt,['This is a string']); Writeln(fmt:12, '=> ',s);
    fmt:= '[%0:s]'; s:=Format(fmt,['This is a string']); Writeln(fmt:12, '=> ',s);
    fmt:= '[%0:18s]'; s:=Format(fmt,['This is a string']); Writeln(fmt:12, '=> ',s);
  
```

```

    fmt:='[%0:-18s]';s:=Format(fmt,['This is a string']);Writeln(fmt:12,'=> ',s);
    fmt:='[%0:18.12s]';s:=Format(fmt,['This is a string']);Writeln(fmt:12,'=> ',s);
    fmt:='[%-*.s]';s:=Format(fmt,[18,12,'This is a string']);Writeln(fmt:12,'=> ',s);
except
  On E : Exception do
    begin
      Writeln ('Exception caught : ',E.Message);
    end;
end;
writeln ('Press enter');
readln;
end;

{ Expected output:
  [%e] => [1.2340000000000000E+000]
  [%10e] => [1.2340000000000000E+000]
  [%10.4e] => [1.234E+000]
  [%0:e] => [1.2340000000000000E+000]
  [%0:10e] => [1.2340000000000000E+000]
  [%0:10.4e] => [1.234E+000]
  [%0:-10e] => [1.2340000000000000E+000]
  [%0:-10.4e] => [1.234E+000]
  [%-*.e] => [1.2340E+000]
}
Procedure TestExponential;
begin
  Try
    Fmt:='[%e]';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
    Fmt:='[%10e]';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
    Fmt:='[%10.4e]';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
    Fmt:='[%0:e]';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
    Fmt:='[%0:10e]';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
    Fmt:='[%0:10.4e]';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
    Fmt:='[%0:-10e]';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
    Fmt:='[%0:-10.4e]';S:=Format (fmt,[1.234]);writeln (Fmt:12,' => ',s);
    Fmt:='[%-*.e]';S:=Format (fmt,[4,5,1.234]);writeln (Fmt:12,' => ',s);
  except
    On E : Exception do
      begin
        Writeln ('Exception caught : ',E.Message);
      end;
    end;
  writeln ('Press enter');
  readln;
end;

{ Expected output:
  [%e] => [-1.2340000000000000E+000]
  [%10e] => [-1.2340000000000000E+000]
  [%10.4e] => [-1.234E+000]
  [%0:e] => [-1.2340000000000000E+000]
  [%0:10e] => [-1.2340000000000000E+000]
  [%0:10.4e] => [-1.234E+000]
  [%0:-10e] => [-1.2340000000000000E+000]
  [%0:-10.4e] => [-1.234E+000]
  [%-*.e] => [-1.2340E+000]
}
Procedure TestNegativeExponential;

```

```

begin
  Try
    Fmt:= '%e' ;S:=Format (Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10e' ;S:=Format (Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10.4e' ;S:=Format (Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:e' ;S:=Format (Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:10e' ;S:=Format (Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:10.4e' ;S:=Format (Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:-10e' ;S:=Format (Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:-10.4e' ;S:=Format (Fmt,[ -1.234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%-*.e' ;S:=Format (Fmt,[4,5, -1.234]);writeln (Fmt:12, ' => ',s);
  except
    On E : Exception do
      begin
        Writeln ('Exception caught : ',E.Message);
      end;
    end;
  writeln ('Press enter');
  readln;
end;

{ Expected output:
  [%e] => [1.2340000000000000E-002]
  [%10e] => [1.2340000000000000E-002]
  [%10.4e] => [1.234E-002]
  [%0:e] => [1.2340000000000000E-002]
  [%0:10e] => [1.2340000000000000E-002]
  [%0:10.4e] => [1.234E-002]
  [%0:-10e] => [1.2300000000000000E-002]
  [%0:-10.4e] => [1.234E-002]
  [%-*.e] => [1.2340E-002]
}

Procedure TestSmallExponential;
begin
  Try
    Fmt:= '%e' ;S:=Format (Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10e' ;S:=Format (Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%10.4e' ;S:=Format (Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:e' ;S:=Format (Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:10e' ;S:=Format (Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:10.4e' ;S:=Format (Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:-10e' ;S:=Format (Fmt,[0.0123]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%0:-10.4e' ;S:=Format (Fmt,[0.01234]);writeln (Fmt:12, ' => ',s);
    Fmt:= '%-*.e' ;S:=Format (Fmt,[4,5,0.01234]);writeln (Fmt:12, ' => ',s);
  except
    On E : Exception do
      begin
        Writeln ('Exception caught : ',E.Message);
      end;
    end;
  writeln ('Press enter');
  readln;
end;

{ Expected output:
  [%e] => [-1.2340000000000000E-002]
  [%10e] => [-1.2340000000000000E-002]
  [%10.4e] => [-1.234E-002]

```



```

    [%0:e] => [-1.2340000000000000E-002]
    [%0:10e] => [-1.2340000000000000E-002]
    [%0:10.4e] => [-1.234E-002]
    [%0:-10e] => [-1.2340000000000000E-002]
    [%0:-10.4e] => [-1.234E-002]
    [%-*.e] => [-1.2340E-002]
}
Procedure TestSmallNegExponential;
begin
    Try
        Fmt:= '%e' ;S:=Format (Fmt,[-0.01234]);writeln (Fmt:12, ' => ',s);
        Fmt:= '%10e' ;S:=Format (Fmt,[-0.01234]);writeln (Fmt:12, ' => ',s);
        Fmt:= '%10.4e' ;S:=Format (Fmt,[-0.01234]);writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:e' ;S:=Format (Fmt,[-0.01234]);writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:10e' ;S:=Format (Fmt,[-0.01234]);writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:10.4e' ;S:=Format (Fmt,[-0.01234]);writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:-10e' ;S:=Format (Fmt,[-0.01234]);writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:-10.4e' ;S:=Format (fmt,[-0.01234]);writeln (Fmt:12, ' => ',s);
        Fmt:= '%-*.e' ;S:=Format (fmt,[4,5,-0.01234]);writeln (Fmt:12, ' => ',s);
    except
        On E : Exception do
            begin
                Writeln ('Exception caught : ',E.Message);
            end;
        end;
        writeln ('Press enter');
        readln;
    end;

begin
    TestInteger;
    TestHexadecimal;
    TestPointer;
    teststring;
    TestExponential;
    TestNegativeExponential;
    TestSmallExponential;
    TestSmallNegExponential;
end.

```

77.15.130 FormatBuf

Synopsis: Format a string with given arguments and store the result in a buffer.

Declaration:

```

function FormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
    fmtLen: Cardinal; const Args: Array of const)
    : Cardinal
function FormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
    fmtLen: Cardinal; const Args: Array of const;
    const FormatSettings: TFormatSettings) : Cardinal

```

Visibility: default

Description: FormatBuf calls Format (1714) and stores the result in Buf.

See also: Format (1714)

Listing: ./examples/sysutex/ex72.pp

Program Example72;

{ This program demonstrates the FormatBuf function }

Uses sysutils;

Var

S : ShortString;

Const

Fmt : ShortString = 'For some nice examples of fomatting see %s.';

Begin

S:= '';

SetLength(S, **FormatBuf** (S[1], 255, Fmt[1], **Length**(Fmt), ['Format']));

WriteLn (S);

End.

77.15.131 FormatCurr

Synopsis: Format a currency

Declaration: function FormatCurr(const Format: string; Value: Currency) : string
 function FormatCurr(const Format: string; Value: Currency;
 const FormatSettings: TFormatSettings) : string

Visibility: default

Description: FormatCurr formats the currency Value according to the formatting rule in the Format parameter, and returns the resulting string.

For an explanation of the formatting characters usable in the Format parameter, see FormatFloat (1722).

See also: FormatFloat (1722), FloatToText (1711)

77.15.132 FormatDateTime

Synopsis: Return a string representation of a TDateTime value with a given format.

Declaration: function FormatDateTime(const FormatStr: string; DateTime: TDateTime;
 Options: TFormatDateTimeOptions) : string
 function FormatDateTime(const FormatStr: string; DateTime: TDateTime;
 const FormatSettings: TFormatSettings;
 Options: TFormatDateTimeOptions) : string

Visibility: default

Description: FormatDateTime formats the date and time encoded in DateTime according to the formatting given in FormatStr. The complete list of formatting characters can be found in formatchars (1621).

When the format string is empty, 'c' is used instead.

Note that on unix systems, the localization support must be enabled explicitly, see Localization (1616).

Errors: On error (such as an invalid character in the formatting string), and `EConvertError` (1800) exception is raised.

See also: `DateTimeToStr` (1674), `DateToStr` (1677), `TimeToStr` (1778), `StrToDateTime` (1766), `EConvertError` (1800), `Localization` (1616)

Listing: `./examples/sysutex/ex14.pp`

Program `Example14`;

{ This program demonstrates the FormatDateTime function }

Uses `sysutils`;

Var `ThisMoment` : `TDateTime`;

Begin

`ThisMoment:=Now`;

`WriteLn` ('Now : ', `FormatDateTime` ('hh:nn ', `ThisMoment`));

`WriteLn` ('Now : ', `FormatDateTime` ('DD MM YYYY', `ThisMoment`));

`WriteLn` ('Now : ', `FormatDateTime` ('c', `ThisMoment`));

End.

77.15.133 FormatFloat

Synopsis: Format a float according to a certain mask.

Declaration: `function FormatFloat(const Format: string; Value: Extended) : string`
`function FormatFloat(const Format: string; Value: Extended;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `FormatFloat` formats the floating-point value given by `Value` using the format specifications in `Format`. The format specifier can give format specifications for positive, negative or zero values (separated by a semicolon).

If the format specifier is empty or the value needs more than 18 digits to be correctly represented, the result is formatted with a call to `FloatToStrF` (1709) with the `ffGeneral` format option.

The following format specifiers are supported:

0 is a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the 0. If not, the 0 is left as-is.

is also a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the #. If not, it is removed. by a space.

. determines the location of the decimal point. Only the first '.' character is taken into account. If the value contains digits after the decimal point, then it is replaced by the value of the `DecimalSeparator` character.

, determines the use of the thousand separator character in the output string. If the format string contains one or more ',' characters, then thousand separators will be used. The `ThousandSeparator` character is used.

E+ determines the use of scientific notation. If 'E+' or 'E-' (or their lowercase counterparts) are present then scientific notation is used. The number of digits in the output string is determined by the number of 0 characters after the 'E+'

;This character separates sections for positive, negative, and zero numbers in the format string.

Errors: If an error occurs, an exception is raised.

See also: FloatToStr ([1708](#))

Listing: ./examples/sysutex/ex89.pp

Program Example89;

{ This program demonstrates the FormatFloat function }

Uses sysutils;

Const

```
NrFormat=9;
FormatStrings : Array[1..NrFormat] of string = (
    '',
    '0',
    '0.00',
    '###',
    '###0.00',
    '###0.00;(#,###0.00)',
    '###0.00;;Zero',
    '0.000E+00',
    '###E-0');
NrValue = 5;
FormatValues : Array[1..NrValue] of Double =
    (1234,-1234,0.5,0,-0.5);

Width  = 12;
FWidth = 20;
```

Var

```
I,J : Integer;
S : String;
```

begin

```
Write( 'Format':FWidth);
For I:=1 to NrValue do
    Write(FormatValues[I]:Width:2);
Writeln;
For I:=1 to NrFormat do
    begin
        Write(FormatStrings[I]:FWidth);
        For J:=1 to NrValue do
            begin
                S:=FormatFloat(FormatStrings[I],FormatValues[J]);
                Write(S:Width);
            end;
        Writeln;
    end;
```

End.

77.15.134 FreeAndNil

Synopsis: Free object if needed, and set object reference to `Nil`

Declaration: `procedure FreeAndNil (var obj)`

Visibility: default

Description: `FreeAndNil` will free the object in `Obj` and will set the reference in `Obj` to `Nil`. The reference is set to `Nil` first, so if an exception occurs in the destructor of the object, the reference will be `Nil` anyway.

Errors: Exceptions that occur during the destruction of `Obj` are not caught.

77.15.135 FreeMemAndNil

Synopsis: Free the heap memory pointed to by a pointer and set pointer to nil.

Declaration: `procedure FreeMemAndNil (var p)`

Visibility: default

Description: `FreeMemAndNil` will free the memory pointed to by `P` and will set `P` to `Nil`. Note that this function is not type safe; the programmer is responsible for ensuring that this function is called with a correct pointer parameter. Failure to do so may result in run-time errors.

See also: `FreeAndNil` ([1723](#))

77.15.136 GetAppConfigDir

Synopsis: Return the appropriate directory for the application's configuration files.

Declaration: `function GetAppConfigDir (Global: Boolean) : string`

Visibility: default

Description: `GetAppConfigDir` returns the name of a directory in which the application should store its configuration files on the current OS. If the parameter `Global` is `True` then the directory returned is a global directory, i.e. valid for all users on the system. If the parameter `Global` is false, then the directory is specific for the user who is executing the program. On systems that do not support multi-user environments, these two directories may be the same.

The directory which is returned is the name of the directory where the application is supposed to store files. This does not mean that the directory exists, or that the user can write in this directory (especially if `Global=True`). It just returns the name of the appropriate location. Also note that the returned name always contains an ending path delimiter.

On systems where the operating system provides a call to determine this location, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` ([1663](#)) call, but can be configured by means of the `OnGetApplicationName` ([1646](#)) callback.

If `VendorName` ([1790](#)) is not-empty, then `VendorName` will also be inserted before the application-specific directory.

Errors: None.

See also: `GetAppConfigFile` ([1725](#)), `ApplicationName` ([1663](#)), `OnGetApplicationName` ([1646](#)), `CreateDir` ([1671](#)), `SysConfigDir` ([1630](#)), `VendorName` ([1790](#))

77.15.137 GetAppConfigFile

Synopsis: Return an appropriate name for an application configuration file.

Declaration: `function GetAppConfigFile(Global: Boolean) : string`
`function GetAppConfigFile(Global: Boolean; SubDir: Boolean) : string`

Visibility: default

Description: `GetAppConfigFile` returns the name of a file in which the application can store its configuration parameters. The exact name and location of the file depends on the customs of the operating system.

The `Global` parameter determines whether it is a global configuration file (value `True`) or a personal configuration file (value `False`).

The parameter `SubDir`, in case it is set to `True`, will insert the name of a directory before the filename. This can be used in case the application needs to store other data than configuration data in an application-specific directory. Default behaviour is to set this to `False`.

Note that on Windows, even when `SubDir` is `False`, a subdirectory is created for the application configuration files, as per the windows specifications. Specifying `true` will create a subdirectory of the application settings subdirectory.

The default file extension of the returned file is: `.cfg`

No assumptions should be made about the existence or writeability of this file, or the directory where the file should reside. It is best to call `ForceDirectories` (1713) prior to opening a file with the resulting filename.

On systems where the operating system provides a call to determine the location of configuration files, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` (1663) call, but can be configured by means of the `OnGetApplicationName` (1646) callback.

If `VendorName` (1790) is not-empty, then `VendorName` will be inserted in the path for the config file directory.

Errors: None.

See also: `GetAppConfigDir` (1724), `OnGetApplicationName` (1646), `ApplicationName` (1663), `CreateDir` (1671), `ConfigExtension` (1623), `SysConfigDir` (1630), `VendorName` (1790)

77.15.138 GetCurrentDir

Synopsis: Return the current working directory of the application.

Declaration: `function GetCurrentDir : AnsiString`

Visibility: default

Description: `GetCurrentDir` returns the current working directory.

Errors: None.

See also: `SetCurrentDir` (1746), `DiskFree` (1681), `DiskSize` (1682)

Listing: `./examples/sysutex/ex28.pp`

Program Example28;

{ This program demonstrates the GetCurrentDir function }

Uses sysutils;

Begin

WriteLn ('Current Directory is : ',GetCurrentDir);

End.

77.15.139 GetDirs

Synopsis: Return a list of directory names from a path.

Declaration: function GetDirs(var DirName: UnicodeString;
 var Dirs: Array of PUnicodeChar) : LongInt
 function GetDirs(var DirName: RawByteString;
 var Dirs: Array of PAnsiChar) : LongInt

Visibility: default

Description: GetDirs splits DirName in a null-byte separated list of directory names, Dirs is an array of PChars, pointing to these directory names. The function returns the number of directories found, or -1 if none were found. DirName must contain only OSDirSeparator as Directory separator chars.

Errors: None.

See also: ExtractRelativePath ([1692](#))

Listing: ./examples/sysutex/ex45.pp

Program Example45;

{ This program demonstrates the GetDirs function }
{ \$H+ }

Uses sysutils;

Var Dirs : **Array**[0..127] **of** pchar;
 I,Count : longint;
 Dir,NewDir : **String**;

Begin

 Dir:=GetCurrentDir;

WriteLn ('Dir : ',Dir);

 NewDir:=' ';

 count:=GetDirs (Dir , Dirs);

For I:=0 **to** Count-1 **do**

begin

 NewDir:=NewDir+ ' / '+**StrPas** (Dirs [I]);

WriteLn (NewDir);

end;

End.

77.15.140 GetDriveIDFromLetter

Synopsis: Return the drive ID based on a drive letter

Declaration: `function GetDriveIDFromLetter(const ADrive: RawByteString) : Byte`
`function GetDriveIDFromLetter(const ADrive: UnicodeString) : Byte`

Visibility: default

Description: `GetDriveIDFromLetter` returns the drive ID based on a drive letter. The drive ID can then be used in the `DiskSize` (1682) and `DiskFree` (1681) calls.

See also: `DiskSize` (1682), `DiskFree` (1681)

77.15.141 GetEnvironmentString

Synopsis: Return an environment variable by index.

Declaration: `function GetEnvironmentString(Index: Integer) : AnsiString`

Visibility: default

Description: `GetEnvironmentString` returns the Index-th environment variable. The index is 1 based, and is bounded from above by the result of `GetEnvironmentVariableCount` (1727).

For an example, `GetEnvironmentVariableCount` (1727).

Remark Note that on Windows, environment strings can start with an equal sign (=). This is a trick used to pass the current working directory to a newly created process. In this case, extracting the variable name as the characters before the first equal sign will result in an empty name.

Errors: If there is no environment, an empty string is returned.

See also: `GetEnvironmentVariable` (1727), `GetEnvironmentVariableCount` (1727)

77.15.142 GetEnvironmentVariable

Synopsis: Return the value of an environment variable.

Declaration: `function GetEnvironmentVariable(const EnvVar: AnsiString) : AnsiString`
`function GetEnvironmentVariable(const EnvVar: UnicodeString)`
`: UnicodeString`

Visibility: default

Description: `GetEnvironmentVariable` returns the value of the `EnvVar` environment variable. If the specified variable does not exist or `EnvVar` is empty, an empty string is returned.

See also: `GetEnvironmentString` (1727), `GetEnvironmentVariableCount` (1727)

77.15.143 GetEnvironmentVariableCount

Synopsis: Return the number of variables in the environment.

Declaration: `function GetEnvironmentVariableCount : Integer`

Visibility: default

Description: `GetEnvironmentVariableCount` returns the number of variables in the environment. The number is 1 based, but the result may be zero if there are no environment variables.

Errors: If there is no environment, -1 may be returned.

See also: `GetEnvironmentString` ([1727](#)), `GetEnvironmentVariable` ([1727](#))

Listing: `./examples/sysutex/ex92.pp`

```
{ $h+ }
program example92;

{ This program demonstrates the
  GetEnvironmentVariableCount function }

uses sysutils;

Var
  I : Integer;

begin
  For I:=1 to GetEnvironmentVariableCount do
    Writeln(i:3, ' : ', GetEnvironmentString(i));
  end.
```

77.15.144 `GetFileAsString`

Synopsis: Return the contents of a file as a string

Declaration:

```
function GetFileAsString(const aFileName: RawByteString) : RawByteString
function GetFileAsString(const aFileName: RawByteString;
                          aEncoding: TEncoding) : RawByteString
function GetFileAsString(const aFileName: UnicodeString) : UnicodeString
function GetFileAsString(const aFileName: UnicodeString;
                          aEncoding: TEncoding) : UnicodeString
```

Visibility: default

Description: `GetFileAsString` returns the contents of `aFileName` or `aHandle` as a string. You can specify the string encoding in the `aEncoding` argument. If no encoding is specified `TEncoding.SystemEncoding` ([1843](#)) is used. The whole file is read in the case of `aHandle`: The file position is first set to offset zero.

Errors: If an invalid file handle or a file handle that does not support the seek operation, a `EInOutError` ([1802](#)) exception is raised.

See also: `GetFileContents` ([1728](#)), `TEncoding.SystemEncoding` ([1843](#)), `TEncoding.GetAnsiString` ([1838](#))

77.15.145 `GetFileContents`

Synopsis: Return the contents of a file as an array of bytes

Declaration:

```
function GetFileContents(const aFileName: RawByteString) : TBytes
function GetFileContents(const aFileName: UnicodeString) : TBytes
function GetFileContents(const aHandle: THandle) : TBytes
```

Visibility: default

Description: `GetFileContents` returns the contents of `aFileName` or `aHandle` as an array of bytes. The whole file is read in the case of `aHandle`: The file position is first set to offset zero.

Errors: If an invalid file handle or a file handle that does not support the seek operation, a `EInOutError` (1802) exception is raised.

See also: `GetFileAsString` (1728)

77.15.146 `GetFileHandle`

Synopsis: Extract OS handle from an untyped file or text file.

Declaration: `function GetFileHandle(var f: File) : THandle`
`function GetFileHandle(var f: Text) : THandle`

Visibility: default

Description: `GetFileHandle` returns the operating system handle for the file descriptor `F`. It can be used in various file operations which are not directly supported by the pascal language.

77.15.147 `GetLastError`

Synopsis: Return the last code from the OS.

Declaration: `function GetLastError : Integer`

Visibility: default

Description: `GetLastError` returns the error code from the last operating system call. It does not reset this code. In general, it should be called when an operating system call reported an error condition. In that case, `GetLastError` gives extended information about the error.

No assumptions should be made about the resetting of the error code by subsequent OS calls. This may be platform dependent.

See also: `RaiseLastError` (1743)

77.15.148 `GetLocalTime`

Synopsis: Get the local time.

Declaration: `procedure GetLocalTime(var SystemTime: TSystemTime)`

Visibility: default

Description: `GetLocalTime` returns the system time in a `TSystemTime` (1642) format.

Errors: None.

See also: `Now` (1742), `Date` (1673), `Time` (1777), `TSystemTime` (1642)

77.15.149 `GetLocalTimeOffset`

Synopsis: Return local timezone offset

Declaration: `function GetLocalTimeOffset : Integer`

Visibility: default

Description: `GetLocalTimeOffset` returns the local timezone offset in minutes. This is the difference between UTC time and local time:

$$\text{UTC} = \text{LocalTime} + \text{GetLocalTimeOffset}$$

The `TDatetime-overloads` return the offset at the specified `DateTime`. In case the `TDatetime-aware` function is not supported on the current platform, `False` is returned or it falls back to the offset to current time (depending on the overload used).

Note that on Linux/Unix, the information returned from the `TDateTime-unaware` function may be inaccurate around the DST time changes (for optimization). In that case, the `unix.ReReadLocalTime` (2119) unit must be used to re-initialize the timezone information.

The TDateTime-aware overloads are supported currently only on Windows Vista and newer.

See also: [unix.ReReadLocalTime \(2119\)](#), [Date \(1673\)](#), [Time \(1777\)](#), [Now \(1742\)](#)

77.15.150 GetModuleName

Synopsis: Return the name of the current module

Declaration: `function GetModuleName(Module: HMODULE) : string`

Visibility: default

Description: `GetModuleName` returns the name of the current module. On windows, this is the name of the executable when executed in an executable, or the name of the library when executed in a library.

On all other platforms, the result is always empty, since they provide no such functionality.

77.15.151 GetTempDir

Synopsis: Return name of system's temporary directory

```
Declaration: function GetTempDir(Global: Boolean) : string
            function GetTempDir : string
```

Visibility: default

Description: `GetTempDir` returns the temporary directory of the system. If `Global` is `True` (the default value) it returns the system temporary directory, if it is `False` then a directory private to the user is returned. The returned name will end with a directory delimiter character.

These directories may be the same. No guarantee is made that this directory exists or is writeable by the user.

The OnGetTempDir (1646) handler may be set to provide custom handling of this routine: One could implement callbacks which take into consideration frameworks like KDE or GNOME, and return a different value from the default system implementation.

Errors: On error, an empty string is returned.

See also: [OnGetTempDir \(1646\)](#), [GetTempFileName \(1730\)](#)

77.15.152 GetTempFileName

Synopsis: Return the name of a temporary file.

```
Declaration: function GetTempFileName(const Dir: string; const Prefix: string)
                                     : string
function GetTempFileName : string
function GetTempFileName(Dir: PChar; Prefix: PChar; uUnique: DWord;
                        TempFileName: PChar) : DWord
```

Visibility: default

Description: `GetTempFileName` returns the name of a temporary file in directory `Dir`. The name of the file starts with `Prefix`.

If `Dir` is empty, the value returned by `GetTempDir` is used, and if `Prefix` is empty, 'TMP' is used.

The `OnGetTempFile` (1646) handler may be set to provide custom handling of this routine: One could implement callbacks which take into consideration frameworks like KDE or GNOME, and return a different value from the default system implementation.

Errors: On error, an empty string is returned.

See also: `GetTempDir` (1730), `OnGetTempFile` (1646)

77.15.153 GetTickCount

Synopsis: Get tick count (32-bit, deprecated)

Declaration: `function GetTickCount : LongWord`

Visibility: default

Description: `GetTickCount` returns an increasing clock tick count in milliseconds. It is useful for time measurements, but no assumptions should be made as to the interval between the ticks. This function is provided for Delphi compatibility, use `GetTickCount64` (1731) instead.

See also: `GetTickCount64` (1731), `Now` (1742), `Time` (1777), `Sleep` (1747)

77.15.154 GetTickCount64

Synopsis: Get tick count (64-bit)

Declaration: `function GetTickCount64 : QWord`

Visibility: default

Description: `GetTickCount64` returns an increasing clock tick count in milliseconds. It is useful for time measurements, but no assumptions should be made as to the interval between the ticks.

See also: `Now` (1742), `Time` (1777), `Sleep` (1747)

77.15.155 GetUserDir

Synopsis: Returns the current user's home directory.

Declaration: `function GetUserDir : string`

Visibility: default

Description: `GetUserDir` returns the home directory of the current user. On Unix-like systems (that includes Mac OS X), this is the value of the HOME environment variable. On Windows, this is the PROFILE special folder. On all other platforms, the application installation directory is returned.

If non-empty, it contains a trailing path delimiter.

See also: `GetAppConfigDir` (1724)

77.15.156 GuidCase

Synopsis: Return the index of a GUID in an array of GUID values

Declaration: `function GuidCase(const GUID: TGuid; const List: Array of TGuid)
: Integer`

Visibility: default

Description: `GuidCase` returns the index of GUID in the array `List`, where 0 denotes the first element in the list. If GUID is not present in the list, -1 is returned.

See also: `IsEqualGUID` ([1737](#))

77.15.157 GUIDToString

Synopsis: Convert a TGUID to a string representation.

Declaration: `function GUIDToString(const GUID: TGuid) : string`

Visibility: default

Description: `GUIDToString` converts the GUID identifier in `GUID` to a string representation in the form

`{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}`

Where each X is a hexadecimal digit.

Errors: None.

See also: `Supports` ([1774](#)), `#rtl.system.TGUID` ([1395](#)), `StringToGUID` ([1755](#)), `IsEqualGuid` ([1737](#))

77.15.158 HashName

Synopsis: Calculate a hash from a null-terminated string

Declaration: `function HashName(Name: PAnsiChar) : LongWord`

Visibility: default

Description: `HashName` calculates a hash value from a null terminated string. The hash value is calculated in such a way that it returns the same value for strings that only differ in case.

77.15.159 HookSignal

Synopsis: Hook a specified signal

Declaration: `procedure HookSignal(RtlSigNum: Integer)`

Visibility: default

Description: `HookSignal` installs the RTL default signal handler for signal `RtlSigNum`. It does not check whether the signal is already handled, and should therefor only be called if `InquireSignal` returns `ssNotHooked`.

77.15.160 IncAMonth

Synopsis: Increase a date with a certain amount of months

Declaration: `procedure IncAMonth(var Year: Word; var Month: Word; var Day: Word;
NumberOfMonths: Integer)`

Visibility: default

Description: `IncAMonth` increases the date as specified by `Year`, `Month`, `Day` with `NumberOfMonths`. It takes care of the number of days in a month when calculating the result.

This function does the same as `IncMonth` (1734), but operates on an already decoded date.

See also: `IncMonth` (1734)

77.15.161 IncludeLeadingPathDelimiter

Synopsis: Prepend a path delimiter if there is not already one.

Declaration: `function IncludeLeadingPathDelimiter(const Path: UnicodeString)
: UnicodeString
function IncludeLeadingPathDelimiter(const Path: RawByteString)
: RawByteString`

Visibility: default

Description: `IncludeLeadingPathDelimiter` will insert a path delimiter (`#rtl.system.DirectorySeparator` (1347)) in the first position of `Path`, if there is not already a directory separator at that position. It will return the resulting string. If the path is empty, a `DirectorySeparator` character is returned.

See also: `IncludeTrailingPathDelimiter` (1734), `ExcludeLeadingPathDelimiter` (1686), `ExcludeTrailingPathDelimiter` (1686), `ConcatPaths` (1671)

Listing: `./examples/sysutex/ex94.pp`

Program `Example94`;

{ This program demonstrates the IncludeLeadingPathDelimiter function }

Uses `sysutils`;

Begin

End.

77.15.162 IncludeTrailingBackslash

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration: `function IncludeTrailingBackslash(const Path: UnicodeString)
: UnicodeString
function IncludeTrailingBackslash(const Path: RawByteString)
: RawByteString`

Visibility: default

Description: `IncludeTrailingBackslash` is provided for backwards compatibility with Delphi. Use `IncludeTrailingPathDelimiter` (1734) instead.

See also: `IncludeTrailingPathDelimiter` (1734), `ExcludeTrailingPathDelimiter` (1686), `PathDelim` (1628), `IsPathDelimiter` (1738)

77.15.163 IncludeTrailingPathDelimiter

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration:

```
function IncludeTrailingPathDelimiter(const Path: UnicodeString)
    : UnicodeString
function IncludeTrailingPathDelimiter(const Path: RawByteString)
    : RawByteString
```

Visibility: default

Description: `IncludeTrailingPathDelimiter` adds a trailing path delimiter character (`PathDelim` (1628)) to `Path` if none is present yet, and returns the result.

If `Path` is empty, a path delimiter is returned, for Delphi compatibility.

See also: `IncludeTrailingBackslash` (1733), `ExcludeTrailingPathDelimiter` (1686), `PathDelim` (1628), `IsPathDelimiter` (1738)

77.15.164 IncMonth

Synopsis: Increases the month in a `TDateTime` value with a given amount.

Declaration:

```
function IncMonth(const DateTime: TDateTime; NumberOfMonths: Integer)
    : TDateTime
```

Visibility: default

Description: `IncMonth` increases the month number in `DateTime` with `NumberOfMonths`. It wraps the result as to get a month between 1 and 12, and updates the year accordingly. `NumberOfMonths` can be negative, and can be larger than 12 (in absolute value).

Errors: None.

See also: `Date` (1673), `Time` (1777), `Now` (1742)

Listing: ./examples/sysutex/ex15.pp

Program Example15;

{ This program demonstrates the IncMonth function }

Uses sysutils;

Var ThisDay : TDateTime;

Begin

```
  ThisDay := Date;
  WriteLn ( 'ThisDay : ', DateToStr ( ThisDay ) );
  WriteLn ( '6 months ago : ', DateToStr ( IncMonth ( ThisDay , - 6 ) ) );
  WriteLn ( '6 months from now : ', DateToStr ( IncMonth ( ThisDay , 6 ) ) );
  WriteLn ( '12 months ago : ', DateToStr ( IncMonth ( ThisDay , - 12 ) ) );
```

```

Writeln ( '12 months from now : ' , DateToStr(IncMonth(ThisDay,12)));
Writeln ( '18 months ago : ' , DateToStr(IncMonth(ThisDay,-18)));
Writeln ( '18 months from now : ' , DateToStr(IncMonth(ThisDay,18)));
End.

```

77.15.165 InquireSignal

Synopsis: Check whether a signal handler is set (unix only)

Declaration: `function InquireSignal(RtlSigNum: Integer) : TSignalState`

Visibility: default

Description: `RtlSigNum` will check whether the signal `RtlSigNum` is being handled, and by whom. It returns a `TSignalState` result to report the state of the signal, which can be one of the following values:

ssNotHooked No signal handler is set for the signal.

ssHooked A signal handler is set by the RTL code for the signal.

ssOverridden A signal handler was set for the signal by third-party code.

This routine works by resetting the signal handlers, so it is risky to call.

77.15.166 IntToHex

Synopsis: Convert an integer value to a hexadecimal string.

Declaration: `function IntToHex(Value: LongInt; Digits: Integer) : string`
`function IntToHex(Value: Int64; Digits: Integer) : string`
`function IntToHex(Value: QWord; Digits: Integer) : string`
`function IntToHex(Value: Int8) : string`
`function IntToHex(Value: UInt8) : string`
`function IntToHex(Value: Int16) : string`
`function IntToHex(Value: UInt16) : string`
`function IntToHex(Value: Int32) : string`
`function IntToHex(Value: UInt32) : string`
`function IntToHex(Value: Int64) : string`
`function IntToHex(Value: UInt64) : string`

Visibility: default

Description: `IntToHex` converts `Value` to a hexadecimal string representation. The result will contain at least `Digits` characters. If `Digits` is less than the needed number of characters, the string will NOT be truncated. If `Digits` is larger than the needed number of characters, the result is padded with zeroes.

Errors: None.

See also: `IntToStr` ([1736](#))

Listing: `./examples/sysutex/ex73.pp`

Program `Example73;`

```
{ This program demonstrates the IntToHex function }
```

```

Uses sysutils;

Var I : longint;

Begin
  For I:=0 to 31 do
    begin
      WriteLn (IntToHex(1 shl I,8));
      WriteLn (IntToHex(15 shl I,8))
    end;
End.

```

77.15.167 IntToStr

Synopsis: Convert an integer value to a decimal string.

Declaration: `function IntToStr(Value: LongInt) : string`
`function IntToStr(Value: Int64) : string`
`function IntToStr(Value: QWord) : string`

Visibility: default

Description: `IntToStr` converts `Value` to its string representation. The resulting string has only as much characters as needed to represent the value. If the value is negative a minus sign is prepended to the string.

Errors: None.

See also: `IntToHex` ([1735](#)), `StrToInt` ([1769](#)), `UIntToStr` ([1786](#))

Listing: `./examples/sysutex/ex74.pp`

Program Example74;

{ This program demonstrates the IntToStr function }

Uses sysutils;

Var I : longint;

```

Begin
  For I:=0 to 31 do
    begin
      WriteLn (IntToStr(1 shl I));
      WriteLn (IntToStr(15 shl I));
    end;
End.

```

77.15.168 IsDelimiter

Synopsis: Check whether a given string is a delimiter character.

Declaration: `function IsDelimiter(const Delimiters: string; const S: string;`
`Index: SizeInt) : Boolean`

Visibility: default

Description: `IsDelimiter` checks whether the `Index`-th character in the string `S` is a delimiter character as passed in `Delimiters`. If `Index` is out of range, `False` is returned.

Errors: None.

See also: `LastDelimiter` ([1739](#))

77.15.169 IsEqualGUID

Synopsis: Check whether two `TGUID` variables are equal.

Declaration: `function IsEqualGUID(const guid1: TGUID; const guid2: TGUID) : Boolean`

Visibility: default

Description: `IsEqualGUID` checks whether `guid1` and `guid2` are equal, and returns `True` if this is the case, or `False` otherwise.

See also: `Supports` ([1774](#)), `#rtl.system.TGUID` ([1395](#)), `StringToGUID` ([1755](#)), `GuidToString` ([1732](#))

77.15.170 IsLeadChar

Synopsis: Is the character code the lead character of a multi-byte character

Declaration: `function IsLeadChar(C: AnsiChar) : Boolean; Overload`
`function IsLeadChar(B: Byte) : Boolean; Overload`
`function IsLeadChar(Ch: WideChar) : Boolean; Overload`

Visibility: default

Description: `IsLeadChar` returns `True` if the character `C` (or byte `B`) is the lead character (or byte) of a multi-byte character. In case of `Ch` a UTF-32 lead character.

Errors: None.

77.15.171 IsLeapYear

Synopsis: Determine whether a year is a leap year.

Declaration: `function IsLeapYear(Year: Word) : Boolean`

Visibility: default

Description: `IsLeapYear` returns `True` if `Year` is a leap year, `False` otherwise.

Errors: None.

See also: `IncMonth` ([1734](#)), `Date` ([1673](#))

Listing: `./examples/sysutex/ex16.pp`

Program `Example16;`

`{ This program demonstrates the IsLeapYear function }`

Uses `sysutils;`

Var `YY,MM,dd : Word;`

```

Procedure TestYear (Y : Word);

begin
    WriteLn (Y, ' is leap year : ', IsLeapYear(Y));
end;

Begin
    DeCodeDate (Date , YY, mm, dd);
    TestYear(yy);
    TestYear(2000);
    TestYear(1900);
    TestYear(1600);
    TestYear(1992);
    TestYear(1995);
End.

```

77.15.172 IsPathDelimiter

Synopsis: Is the character at the given position a pathdelimiter ?

Declaration: `function IsPathDelimiter(const Path: UnicodeString; Index: Integer) : Boolean`
`function IsPathDelimiter(const Path: RawByteString; Index: Integer) : Boolean`

Visibility: default

Description: `IsPathDelimiter` returns `True` if the character at position `Index` equals `PathDelim` (1628), i.e. if it is a path delimiter character for the current platform.

Errors: `IncludeTrailingPathDelimiter` (1734) `ExcludeTrailingPathDelimiter` (1686) `PathDelim` (1628)

77.15.173 IsValidIdent

Synopsis: Check whether a string is a valid identifier name.

Declaration: `function IsValidIdent(const Ident: string; AllowDots: Boolean; StrictDots: Boolean) : Boolean`

Visibility: default

Description: `IsValidIdent` returns `True` if `Ident` can be used as a component name. It returns `False` otherwise. `Ident` must consist of a letter or underscore, followed by a combination of letters, numbers or underscores to be a valid identifier.

Errors: None.

Listing: `./examples/sysutex/ex75.pp`

Program Example75;

{ This program demonstrates the IsValidIdent function }

Uses sysutils;

Procedure Testit (S : **String**);

```

begin
  Write ( '"', S, '"' is ');
  If not IsValidIdent(S) then
    Write('NOT ');
    WriteLn ('a valid identifier');
end;

Begin
  Testit ('_MyObj');
  Testit ('My__Obj1');
  Testit ('My_1_Obj');
  Testit ('1MyObject');
  Testit ('My@Object');
  Testit ('M123');
End.

```

77.15.174 LastDelimiter

Synopsis: Return the last occurrence of a set of delimiters in a string.

Declaration: `function LastDelimiter(const Delimiters: string; const S: string)
: SizeInt`

Visibility: default

Description: `LastDelimiter` returns the *last* occurrence of any character in the set `Delimiters` in the string `S`.

Listing: ./examples/sysutex/ex88.pp

Program example88;

{ This program demonstrates the LastDelimiter function }

uses SysUtils;

begin

 WriteLn (LastDelimiter ('\\.: ', 'c:\\filename.ext'));

end.

77.15.175 LeftStr

Synopsis: Return a number of characters starting at the left of a string.

Declaration: `function LeftStr(const S: string; Count: Integer) : string`

Visibility: default

Description: `LeftStr` returns the `Count` leftmost characters of `S`. It is equivalent to a call to `Copy (S, 1, Count)`.

Errors: None.

See also: `RightStr` ([1745](#)), `TrimLeft` ([1779](#)), `TrimRight` ([1780](#)), `Trim` ([1779](#))

Listing: ./examples/sysutex/ex76.pp

```

Program Example76;

{ This program demonstrates the LeftStr function }

Uses sysutils;

Begin
  Writeln ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ',20));
  Writeln ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ',15));
  Writeln ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ',1));
  Writeln ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ',200));
End.

```

77.15.176 LoadStr

Synopsis: Load a string from the resource tables.

Declaration: `function LoadStr(Ident: Integer) : string`

Visibility: default

Description: This function is not yet implemented. resources are not yet supported.

77.15.177 LowerCase

Synopsis: Return a lowercase version of a string.

```
Declaration: function LowerCase(const s: string) : string; Overload
function LowerCase(const s: string; LocaleOptions: TLocaleOptions)
: string; Overload
function LowerCase(const V: variant) : string; Overload
function LowerCase(const s: UnicodeString) : UnicodeString; Overload
```

Visibility: default

Description: LowerCase returns the lowercase equivalent of S. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the lowercase function of the system unit, and is provided for compatibility only.

Lowercase does not change the number of characters (or bytes) in an ansistring or shortstring.

Errors: None.

See also: [AnsiLowerCase \(1653\)](#), [UpperCase \(1790\)](#), [AnsiUpperCase \(1661\)](#)

Listing: ./examples/sysutex/ex77.pp

```
Program Example77;  
  
{ This program demonstrates the LowerCase function }  
  
Uses sysutils;  
  
Begin  
    WriteLn (LowerCase('THIS WILL COME out all LoWeRcAsE !'));  
End.
```

77.15.178 MSecsToTimeStamp

Synopsis: Convert a number of milliseconds to a TDateTime value.

Declaration: `function MSecsToTimeStamp(MSecs: Comp) : TTimeStamp`

Visibility: default

Description: `MSecsToTimeStamp` converts the given number of milliseconds to a `TTimeStamp` date/time notation.

Use `TTimeStamp` variables if you need to keep very precise track of time.

Errors: None.

See also: `TimeStampToMSecs` ([1778](#)), `DateTimeToTimeStamp` ([1677](#))

Listing: `./examples/sysutex/ex17.pp`

Program `Example17;`

{ This program demonstrates the MSecsToTimeStamp function }

Uses `sysutils;`

Var `MS : Comp;`
 `TS : TTimeStamp;`
 `DT : TDateTime;`

Begin

`TS:=DateTimeToTimeStamp(Now);`
 `WriteLn ('Now in days since 1/1/0001 : ',TS.Date);`
 `WriteLn ('Now in millisecs since midnight : ',TS.Time);`
 `MS:=TimeStampToMSecs(TS);`
 `WriteLn ('Now in millisecs since 1/1/0001 : ',MS);`
 `MS:=MS-1000*3600*2;`
 `TS:=MSecsToTimeStamp(MS);`
 `DT:=TimeStampToDateTime(TS);`
 `WriteLn ('Now minus 1 day : ',DateTimeToStr(DT));`

End.

77.15.179 NewStr

Synopsis: Allocate a new ansistring on the heap.

Declaration: `function NewStr(const S: string) : PString; Overload`

Visibility: default

Description: `NewStr` assigns a new dynamic string on the heap, copies `S` into it, and returns a pointer to the newly assigned string.

This function is obsolete, and shouldn't be used any more. The `AnsiString` mechanism also allocates ansistrings on the heap, and should be preferred over this mechanism.

For an example, see `AssignStr` ([1663](#)).

Errors: If not enough memory is present, an `EOutOfMemory` exception will be raised.

See also: `AssignStr` ([1663](#)), `DisposeStr` ([1682](#))

77.15.180 Now

Synopsis: Returns the current date and time.

Declaration: `function Now : TDateTime`

Visibility: default

Description: `Now` returns the current date and time. It is equivalent to `Date+Time`.

Errors: None.

See also: `Date` ([1673](#)), `Time` ([1777](#))

Listing: `./examples/sysutex/ex18.pp`

Program `Example18;`

{ This program demonstrates the Now function }

Uses `sysutils;`

Begin

`WriteLn ('Now : ', DateTimeToStr (Now));`

End.

77.15.181 OutOfMemoryError

Synopsis: Raise an `EOutOfMemory` exception

Declaration: `procedure OutOfMemoryError`

Visibility: default

Description: `OutOfMemoryError` raises an `EOutOfMemory` ([1805](#)) exception, with an exception object that has been allocated on the heap at program startup. The program should never create an `EOutOfMemory` ([1805](#)) exception, but always call this routine.

See also: `EOutOfMemory` ([1805](#))

77.15.182 QuotedStr

Synopsis: Return a quotes version of a string.

Declaration: `function QuotedStr(const S: string) : string`

Visibility: default

Description: `QuotedStr` returns the string `S`, quoted with single quotes. This means that `S` is enclosed in single quotes, and every single quote in `S` is doubled. It is equivalent to a call to `AnsiQuotedStr(s, '"')`.

Errors: None.

See also: `AnsiQuotedStr` ([1654](#)), `AnsiExtractQuotedStr` ([1652](#))

Listing: `./examples/sysutex/ex78.pp`

```

Program Example78;

{ This program demonstrates the QuotedStr function }

Uses sysutils;

Var S : AnsiString;

Begin
  S:= 'He said ''Hello'' and walked on';
  WriteLn (S);
  WriteLn (' becomes');
  WriteLn (QuotedStr(S));
End.

```

77.15.183 RaiseLastError

Synopsis: Raise an exception with the last Operating System error code.

Declaration: `procedure RaiseLastError; Overload`
`procedure RaiseLastError(LastError: Integer); Overload`

Visibility: default

Description: `RaiseLastError` raises an `EOSError` ([1805](#)) exception with the error code returned by `GetLastError`. If the Error code is nonzero, then the corresponding error message will be returned. If the error code is zero, a standard message will be returned.

Errors: This procedure may not be implemented on all platforms. If it is not, then a normal Exception ([1808](#)) will be raised.

See also: `EOSError` ([1805](#)), `GetLastError` ([1729](#)), Exception ([1808](#))

77.15.184 RemoveDir

Synopsis: Remove a directory from the file system.

Declaration: `function RemoveDir(const Dir: RawByteString) : Boolean`
`function RemoveDir(const Dir: UnicodeString) : Boolean`

Visibility: default

Description: `RemoveDir` removes directory `Dir` from the disk. If the directory is not absolute, it is appended to the current working directory.

For an example, see `CreateDir` ([1671](#)).

Errors: In case of error (e.g. the directory isn't empty) the function returns `False`. If successful, `True` is returned.

77.15.185 RenameFile

Synopsis: Rename a file.

Declaration: `function RenameFile(const OldName: UnicodeString;
 const NewName: UnicodeString) : Boolean
 function RenameFile(const OldName: RawByteString;
 const NewName: RawByteString) : Boolean`

Visibility: default

Description: `RenameFile` renames a file from `OldName` to `NewName`. The function returns `True` if successful, `False` otherwise. For safety, the new name must be a full path specification, including the directory, otherwise it will be assumed to be a filename relative to the current working directory. *Remark:* The implementation of `RenameFile` relies on the underlying OS's support for renaming/-moving a file. Whether or not a file can be renamed across disks or partitions depends entirely on the OS. On unix-like OS-es, the rename function will fail when used across partitions. On Windows, it will work.

Errors: On Error, `False` is returned.

See also: `DeleteFile` ([1680](#))

Listing: `./examples/sysutex/ex44.pp`

Program `Example44`;

{ This program demonstrates the RenameFile function }

Uses `sysutils`;

Var `F : Longint`;
 `S : String`;

Begin

`S := 'Some short file.'`;
 `F := FileCreate ('test.dap');`
 `FileWrite(F, S[1], Length(S));`
 `FileClose(F);`
 If `RenameFile ('test.dap', 'test.dat')` **then**
 `Writeln ('Successfully renamed files.');`

End.

77.15.186 ReplaceDate

Synopsis: Replace the date part of a date/time stamp

Declaration: `procedure ReplaceDate(var DateTime: TDateTime; const NewDate: TDateTime)`

Visibility: default

Description: `ReplaceDate` replaces the date part of `DateTime` with `NewDate`. The time part is left unchanged.

See also: `ReplaceTime` ([1744](#))

77.15.187 ReplaceTime

Synopsis: Replace the time part

Declaration: `procedure ReplaceTime(var dateTime: TDateTime; NewTime: TDateTime)`

Visibility: default

Description: `ReplaceTime` replaces the time part in `dateTime` with `NewTime`. The date part remains untouched.

77.15.188 RightStr

Synopsis: Return a number of characters from a string, starting at the end.

Declaration: `function RightStr(const S: string; Count: Integer) : string`

Visibility: default

Description: `RightStr` returns the `Count` rightmost characters of `S`. It is equivalent to a call to `Copy (S, Length (S) + 1 - Count, Count)`.

If `Count` is larger than the actual length of `S` only the real length will be used.

Errors: None.

See also: `LeftStr` ([1739](#)), `Trim` ([1779](#)), `TrimLeft` ([1779](#)), `TrimRight` ([1780](#))

Listing: `./examples/sysutex/ex79.pp`

Program `Example79;`

{ This program demonstrates the RightStr function }

Uses `sysutils;`

Begin

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz', 20)`);

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz', 15)`);

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz', 1)`);

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz', 200)`);

End.

77.15.189 SafeLoadLibrary

Synopsis: Load a library safely

Declaration: `function SafeLoadLibrary(const FileName: AnsiString; ErrorMode: DWord)
: HMODULE`

Visibility: default

Description: `SafeLoadLibrary` saves and restores some registers before and after issuing a call to `LoadLibrary`.

Errors: None.

77.15.190 SameFileName

Synopsis: Are two filenames referring to the same file ?

Declaration: `function SameFileName(const S1: string; const S2: string) : Boolean`

Visibility: default

Description: `SameFileName` returns `True` if calling `AnsiCompareFileName` ([1649](#)) with arguments `S1` and `S2` returns 0, and returns `False` otherwise.

Errors: None.

See also: `AnsiCompareFileName` ([1649](#))

77.15.191 SameStr

Synopsis: Check whether 2 strings are the same, case insensitive

```
Declaration: function SameStr(const s1: string; const s2: string) : Boolean
                ; Overload
                function SameStr(const s1: string; const s2: string;
                                LocaleOptions: TLocaleOptions) : Boolean; Overload
```

Visibility: default

Description: SameStr checks whether S1 and S2 are the same. This is equivalent to checking that CompareStr (1669) returns 0.

Errors: None.

See also: [CompareStr \(1669\)](#)

77.15.192 SameText

Synopsis: Checks whether 2 strings are the same (case insensitive)

```
Declaration: function SameText(const s1: string; const s2: string) : Boolean
                ; Overload
    function SameText(const s1: string; const s2: string;
        LocaleOptions: TLocaleOptions) : Boolean; Overload
```

Visibility: default

Description: SameText calls CompareText (1670) with S1 and S2 as parameters and returns True if the result of that call is zero, or False otherwise.

Errors: None.

See also: [CompareText \(1670\)](#), [AnsiSameText \(1655\)](#), [AnsiSameStr \(1655\)](#)

77.15.193 SetCurrentDir

Synopsis: Set the current directory of the application.

```
Declaration: function SetCurrentDir(const NewDir: RawByteString) : Boolean
              function SetCurrentDir(const NewDir: UnicodeString) : Boolean
```

Visibility: default

Description: `SetCurrentDir` sets the current working directory of your program to `NewDir`. It returns `True` if the function was successful, `False` otherwise.

Errors: In case of error, `False` is returned.

See also: [GetCurrentDir \(1725\)](#)

77.15.194 SetDirSeparators

Synopsis: Set the directory separators to the known directory separators.

Declaration: `function SetDirSeparators(const FileName: UnicodeString) : UnicodeString`
`function SetDirSeparators(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `SetDirSeparators` returns `FileName` with all possible `DirSeparators` replaced by `OSDirSeparator`.

Errors: None.

See also: `ExpandFileName` (1688), `ExtractFilePath` (1692), `ExtractFileDir` (1690)

Listing: `./examples/sysutex/ex47.pp`

Program `Example47;`

`{ This program demonstrates the SetDirSeparators function }`

Uses `sysutils;`

Begin

`WriteLn (SetDirSeparators ('/pp/bin/win32/ppc386'));`

End.

77.15.195 ShowException

Synopsis: Show the current exception to the user.

Declaration: `procedure ShowException(ExceptObject: TObject; ExceptAddr: Pointer)`

Visibility: default

Description: `ShowException` shows a message stating that a `ExceptObject` was raised at address `ExceptAddr`.

It uses `ExceptionErrorMessage` (1685) to create the message, and is aware of the fact whether the application is a console application or a GUI application. For a console application, the message is written to standard error output. For a GUI application, `OnShowException` (1646) is executed.

Errors: If, for a GUI application, `OnShowException` (1646) is not set, no message will be displayed to the user.

The exception message can be at most 255 characters long: It is possible that no memory can be allocated on the heap, so ansistrings are not available, so a shortstring is used to display the message.

See also: `ExceptObject` (1685), `ExceptAddr` (1684), `ExceptionErrorMessage` (1685)

77.15.196 Sleep

Synopsis: Suspend execution of a program for a certain time.

Declaration: `procedure Sleep(milliseconds: Cardinal)`

Visibility: default

Description: `Sleep` suspends the execution of the program for the specified number of milliseconds (`milliseconds`).

After the specified period has expired, program execution resumes.

Remark The indicated time is not exact, i.e. it is a minimum time. No guarantees are made as to the exact duration of the suspension.

77.15.197 SScanf

Synopsis: Scan a string for substrings and return the content of these substrings as typed values

Declaration: `function SScanf(const s: string; const fmt: string;
const Pointers: Array of Pointer) : Integer`

Visibility: default

Description: `SScanF` does in essence the opposite of `Format` (1714): it scans the string `S` for the elements specified in `Fmt`, and returns the value of the found elements in the memory locations pointed to by the addresses in `Pointers`. The `Fmt` can contain placeholders of the form `%X` where `X` can be one of the following characters:

dPlaceholder for a decimal number.

fPlaceholder for a floating point number (an extended)

sPlaceholder for a string of arbitrary length.

cPlaceholder for a single character

The `Pointers` array contains a list of pointers, each pointer should point to a memory location of a type that corresponds to the type of placeholder in that position:

dA pointer to an integer.

fA pointer to an extended.

sA pointer to an ansistring.

cA pointer to a single character.

On return, these locations will be filled with the actual values found in `S` for the placeholders in `fmt`. The return value of the function is the number of found values.

Errors: No error checking is performed on the type of the memory location.

See also: `Format` (1714)

Listing: `./examples/sysutex/ex98.pp`

```
Program Example98;
{$mode objfpc}
{$h+}
{ This program demonstrates the function }

Uses sysutils;

var
  count, i: Integer;
  f: Extended;
  s: String;

begin
  count:=SScanf('234 32.4 hello ', '%d %f %s', [@i, @f, @s]);
  writeln(count, ' ', i, ' ', f, ' ', s);
End.
```

77.15.198 StrAlloc

Synopsis: Allocate a null-terminated string on the heap.

Declaration: `function StrAlloc(Size: Cardinal) : PChar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Additionally, `StrAlloc` allocates 4 extra bytes to store the size of the allocated memory. Therefore this function is NOT compatible with the `StrAlloc` (1288) function of the `Strings` unit.

For an example, see `StrBufSize` (1749).

Errors: None.

See also: `StrBufSize` (1749), `StrDispose` (1752), `StrAlloc` (1288)

77.15.199 StrBufSize

Synopsis: Return the size of a null-terminated string allocated on the heap.

Declaration: `function StrBufSize(Str: PChar) : Cardinal`
`function StrBufSize(str: PWideChar) : Cardinal`

Visibility: default

Description: `StrBufSize` returns the memory allocated for `Str`. This function ONLY gives the correct result if `Str` was allocated using `StrAlloc` (1749).

Errors: If no more memory is available, a runtime error occurs.

See also: `StrAlloc` (1749), `StrDispose` (1752)

Listing: `./examples/sysutex/ex46.pp`

Program `Example46`;

{ This program demonstrates the StrBufSize function }
{ \$H+ }

Uses `sysutils`;

Const `S = 'Some nice string'`;

Var `P : Pchar`;

Begin

`P := StrAlloc(Length(S)+1);`
`StrPCopy(P, S);`
`Write (P, ' has length ', Length(S));`
`WriteLn (' and buffer size ', StrBufSize(P));`
`StrDispose(P);`

End.

77.15.200 StrByteType

Synopsis: Return the type of byte in a null-terminated string for a multi-byte character set

Declaration: `function StrByteType(Str: PChar; Index: SizeUInt) : TmbcsByteType`

Visibility: default

Description: `StrByteType` returns the type of byte in the null-terminated string `Str` at (0-based) position `Index`.

Errors: No checking on the index is performed.

See also: `TmbcsByteType` ([1639](#)), `ByteType` ([1666](#))

77.15.201 strcat

Synopsis: Concatenate 2 null-terminated strings.

Declaration: `function strcat(dest: PChar; source: PChar) : PChar`
`function strcat(dest: PWideChar; source: PWideChar) : PWideChar`

Visibility: default

Description: Attaches `Source` to `Dest` and returns `Dest`.

Errors: No length checking is performed.

See also: `StrLCat` ([1755](#))

Listing: `./examples/stringex/ex11.pp`

Program `Example11;`

Uses `strings;`

{ Program to demonstrate the StrCat function. }

Const `P1 : PChar = 'This is a PChar String.';`

Var `P2 : PChar;`

begin

`P2:= StrAlloc (StrLen(P1)*2+1);`

`StrMove (P2,P1,StrLen(P1)+1); { P2=P1 }`

`StrCat (P2,P1); { Append P2 once more }`

`Writeln ('P2 : ',P2);`

`StrDispose(P2);`

end.

77.15.202 StrCharLength

Synopsis: Return the length of a null-terminated string in characters.

Declaration: `function StrCharLength(const Str: PChar) : SizeInt`

Visibility: default

Description: `StrCharLength` returns the length of the null-terminated string `Str` (a widestring) in characters (not in bytes). It uses the widestring manager to do this.

77.15.203 strcmp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: `function strcmp(str1: PChar; str2: PChar) : SizeInt`
`function strcmp(str1: PWideChar; str2: PWideChar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

For an example, see StrLComp ([1756](#)).

Errors: None.

See also: StrLComp ([1756](#)), StrIComp ([1754](#)), StrLComp ([1759](#))

77.15.204 StrCopy

Synopsis: Copy a null-terminated string

Declaration: `function strcpy(dest: PChar; source: PChar) : PChar; Overload`
`function StrCopy(Dest: PWideChar; Source: PWideChar) : PWideChar`
`; Overload`

Visibility: default

Description: Copy the null terminated string in Source to Dest, and returns a pointer to Dest. Dest needs enough room to contain Source, i.e. StrLen(Source)+1 bytes.

Errors: No length checking is performed.

See also: StrPCopy ([1761](#)), StrLCopy ([1757](#)), StrECopy ([1752](#))

Listing: ./examples/stringex/ex4.pp

Program Example4;

Uses strings;

{ Program to demonstrate the StrCopy function. }

Const P : PChar = 'This is a PCHAR string.';

var PP : PChar;

begin

PP:= StrAlloc (StrLen(P)+1);

STrCopy (PP,P);

If StrComp (PP,P)<>0 **then**

 Writeln ('Oh-oh problems... ')

else

 Writeln ('All is well : PP=',PP);

 StrDispose(PP);

end.

77.15.205 StrDispose

Synopsis: Dispose of a null-terminated string on the heap.

Declaration: `procedure StrDispose(Str: PChar)`
`procedure StrDispose(str: PWideChar)`

Visibility: default

Description: `StrDispose` frees any memory allocated for `Str`. This function will only function correctly if `Str` has been allocated on the heap, for example using `StrAlloc` (1749) or `StrNew` (1760) from the `SysUtils` unit.

For an example, see `StrBufSize` (1749).

Errors: If an invalid pointer is passed, or a pointer not allocated with `StrAlloc`, an error may occur.

See also: `StrBufSize` (1749), `StrAlloc` (1749), `StrNew` (1760)

77.15.206 strecopy

Synopsis: Copy a null-terminated string, return a pointer to the end.

Declaration: `function strecopy(dest: PChar; source: PChar) : PChar`
`function strecopy(dest: PWideChar; source: PWideChar) : PWideChar`

Visibility: default

Description: Copies the Null-terminated string in `Source` to `Dest`, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

Errors: No length checking is performed.

See also: `StrLCopy` (1757), `StrCopy` (1751)

Listing: `./examples/stringex/ex6.pp`

Program Example6;

Uses strings;

{ Program to demonstrate the StrECopy function. }

Const P : PChar = 'This is a PCHAR string.';

Var PP : PChar;

begin

PP:= StrAlloc (StrLen(P)+1);

If Longint(StrECopy(PP,P)) - Longint(PP) <> StrLen(P) **then**

Writeln ('Something is wrong here !')

else

Writeln ('PP= ',PP);

StrDispose(PP);

end.

77.15.207 strend

Synopsis: Return a pointer to the end of a null-terminated string

Declaration: `function strend(p: PChar) : PChar`
`function strend(p: PWideChar) : PWideChar`

Visibility: default

Description: Returns a pointer to the end of P. (i.e. to the terminating null-character.

Errors: None.

See also: `StrLen` ([1757](#))

Listing: `./examples/stringex/ex7.pp`

Program `Example6;`

Uses `strings;`

{ Program to demonstrate the StrEnd function. }

Const `P : PChar = 'This is a PCHAR string.';`

begin

If `Longint(StrEnd(P)) - Longint(P) <> StrLen(P)` **then**

Writeln `('Something is wrong here !')`

else

Writeln `('All is well..');`

end.

77.15.208 StrFmt

Synopsis: Format a string with given arguments, store the result in a buffer.

Declaration: `function StrFmt(Buffer: PChar; Fmt: PChar; const args: Array of const)`
`: PChar`
`function StrFmt(Buffer: PChar; Fmt: PChar; const Args: Array of const;`
`const FormatSettings: TFormatSettings) : PChar`

Visibility: default

Description: `StrFmt` will format `fmt` with `Args`, as the `Format` ([1714](#)) function does, and it will store the result in `Buffer`. The function returns `Buffer`. `Buffer` should point to enough space to contain the whole result.

Errors: for a list of errors, see `Format` ([1714](#)).

See also: `StrLFmt` ([1758](#)), `FmtStr` ([1713](#)), `Format` ([1714](#)), `FormatBuf` ([1720](#))

Listing: `./examples/sysutex/ex80.pp`

Program `Example80;`

{ This program demonstrates the StrFmt function }

Uses `sysutils;`

```
Var S : AnsiString;
```

```
Begin
```

```
  SetLength(S,80);
```

```
  WriteLn (StrFmt (@S[1], 'For some nice examples of fomatting see %s.', ['Format']));
```

```
End.
```

77.15.209 stricmp

Synopsis: Compare 2 null-terminated strings, case insensitive.

Declaration: `function stricmp(str1: PChar; str2: PChar) : SizeInt`
`function stricmp(str1: PWideChar; str2: PWideChar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings S1 and S2, ignoring case. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrLComp ([1756](#)), StrComp ([1751](#)), StrLComp ([1759](#))

Listing: ./examples/stringex/ex8.pp

```
Program Example8;
```

```
Uses strings;
```

```
{ Program to demonstrate the StrLComp function. }
```

```
Const P1 : PChar = 'This is the first string.';  
       P2 : PChar = 'This is the second string.';
```

```
Var L : Longint;
```

```
begin
```

```
  Write ('P1 and P2 are ');
```

```
  If StrComp (P1,P2)<>0 then write ('NOT ');
```

```
  write ('equal. The first ');
```

```
  L:=1;
```

```
  While StrLComp(P1,P2,L)=0 do inc (L);
```

```
  dec(L);
```

```
  WriteLn (L, ' characters are the same.');
```

```
end.
```

77.15.210 StringOf

Synopsis: Create a Unicode string from an array of bytes

Declaration: `function StringOf(const Bytes: TBytes) : UnicodeString`

Visibility: default

Description: `StringOf` converts an array of bytes (`Bytes`) to a Unicode string. It interprets the bytes as a single-byte string, using the default codepage.

To create a string where the bytes are interpreted as wide chars, use `WideStringOf` ([1794](#)) instead.

Errors: None.

See also: `WideBytesOf` ([1791](#)), `WideStringOf` ([1794](#))

77.15.211 `StringReplace`

Synopsis: Replace occurrences of one substring with another in a string.

Declaration:

```
function StringReplace(const S: string; const OldPattern: string;
                      const NewPattern: string; Flags: TReplaceFlags;
                      out aCount: Integer) : string
function StringReplace(const S: string; const OldPattern: string;
                      const NewPattern: string; Flags: TReplaceFlags)
                      : string
```

Visibility: default

Description: `StringReplace` searches the string `S` for occurrences of the string `OldPattern` and, if it is found, replaces it with `NewPattern`. It returns the resulting string. The behaviour of `StringReplace` can be tuned with `Flags`, which is of type `TReplaceFlags` ([1639](#)). Standard behaviour is to replace only the first occurrence of `OldPattern`, and to search case sensitively.

Errors: None.

See also: `TReplaceFlags` ([1639](#)), `WideStringReplace` ([1794](#))

77.15.212 `StringToGUID`

Synopsis: Convert a string to a native `TGUID` type.

Declaration: `function StringToGUID(const S: string) : TGUID`

Visibility: default

Description: `StringToGUID` converts the string `S` to a valid GUID. The string `S` should be of the form

```
{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}
```

Where each `X` is a hexadecimal digit. The dashes and braces are required.

Errors: In case `S` contains an invalid GUID representation, a `EConvertError` ([1800](#)) exception is raised.

See also: `Supports` ([1774](#)), `#rtl.system.TGUID` ([1395](#)), `GUIDToString` ([1732](#)), `IsEqualGuid` ([1737](#))

77.15.213 `strlcat`

Synopsis: Concatenate 2 null-terminated strings, with length boundary.

Declaration:

```
function strlcat(dest: PChar; source: PChar; l: SizeInt) : PChar
function strlcat(dest: PWideChar; source: PWideChar; l: SizeInt)
                : PWideChar
```

Visibility: default

Description: Adds MaxLen characters from Source to Dest, and adds a terminating null-character. Returns Dest.

Errors: None.

See also: StrCat ([1750](#))

Listing: ./examples/stringex/ex12.pp

```

Program Example12;

Uses strings;

{ Program to demonstrate the StrLCat function. }

Const P1 : PChar = '1234567890';

Var P2 : PChar;

begin
  P2:= StrAlloc (StrLen(P1)*2+1);
  P2^:=#0; { Zero length }
  StrCat (P2,P1);
  StrLCat (P2,P1,5);
  Writeln ('P2 = ',P2);
  StrDispose(P2)
end.

```

77.15.214 strlcomp

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: `function strlcomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`
`function strlcomp(str1: PWideChar; str2: PWideChar; l: SizeInt)`
`: SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrComp ([1751](#)), StrIComp ([1754](#)), StrLComp ([1759](#))

Listing: ./examples/stringex/ex8.pp

```

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

```

Visibility: default

Description: Returns the length of the null-terminated string *P*. If *P* equals *Nil* then zero (0) is returned.

Errors: None.

See also: *StrNew* ([1760](#))

Listing: ./examples/stringex/ex1.pp

Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }

Const P : PChar = 'This is a constant pchar string';

begin

WriteLn ('P : ',p);

WriteLn ('length(P) : ',**StrLen**(P));

end.

77.15.217 StrLFmt

Synopsis: Format a string with given arguments, but with limited length.

Declaration: function *StrLFmt*(Buffer: PChar; Maxlen: Cardinal; Fmt: PChar;
 const args: Array of const) : PChar
function *StrLFmt*(Buffer: PChar; Maxlen: Cardinal; Fmt: PChar;
 const args: Array of const;
 const FormatSettings: TFormatSettings) : PChar

Visibility: default

Description: *StrLFmt* will format *fmt* with *Args*, as the *Format* ([1714](#)) function does, and it will store maximally *Maxlen* characters of the result in *Buffer*. The function returns *Buffer*. *Buffer* should point to enough space to contain *MaxLen* characters.

Errors: for a list of errors, see *Format* ([1714](#)).

See also: *StrFmt* ([1753](#)), *FmtStr* ([1713](#)), *Format* ([1714](#)), *FormatBuf* ([1720](#))

Listing: ./examples/sysutex/ex81.pp

Program Example80;

{ This program demonstrates the StrFmt function }

Uses sysutils;

Var S : AnsiString;

Begin

 SetLength(S,80);

WriteLn (**StrLFmt** (@S[1],80,'For some nice examples of fomattting see %s.',['Format']));

End.

77.15.218 strlicomp

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`
`function strlicomp(str1: PWideChar; str2: PWideChar; l: SizeInt)`
`: SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2, ignoring case. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

For an example, see StrIComp ([1754](#))

Errors: None.

See also: StrLComp ([1756](#)), StrComp ([1751](#)), StrIComp ([1754](#))

77.15.219 strlower

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: PChar) : PChar`
`function strlower(p: PWideChar) : PWideChar`

Visibility: default

Description: Converts P to an all-lowercase string. Returns P.

Errors: None.

See also: StrUpper ([1774](#))

Listing: ./examples/stringex/ex14.pp

Program Example14;

Uses strings;

{ Program to demonstrate the StrLower and StrUpper functions. }

Const

P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';
P2 : PChar = 'this is a lowercase string';

begin

P1:=StrNew(P1);
P2:=strNew(P2);
Writeln ('Uppercase : ',StrUpper(P2));
StrLower(P1);
Writeln ('Lowercase : ',P1);
StrDispose(P1);
StrDispose(P2);
end.

77.15.220 StrMove

Synopsis: Move a null-terminated string to new location.

```
Declaration: function strmove(dest: PChar; source: PChar; l: SizeInt) : PChar
              ; Overload
              function StrMove(dest: PWideChar; source: PWideChar; l: SizeInt)
              : PWideChar; Overload
```

Visibility: default

Description: Copies `MaxLen` characters from `Source` to `Dest`. No terminating null-character is copied. Returns `Dest`.

Errors: None.

See also: [StrLCopy \(1757\)](#), [StrCopy \(1751\)](#)

Listing: ./examples/stringex/ex10.pp

Program Example10;

Uses strings;

```
{ Program to demonstrate the StrMove function. }
```

```
Const P1 : PCHAR = 'This is a pchar string.';
```

```
Var P2 : Pchar;
```

```
begin
  P2:= StrAlloc (StrLen(P1)+1);
  StrMove (P2,P1,StrLen(P1)+1); { P2:=P1 }
  Writeln ('P2 = ',P2);
  StrDispose(P2);
end.
```

77.15.221 strnew

Synopsis: Allocate room for new null-terminated string.

```
Declaration: function strnew(p: PChar) : PChar; Overload
              function strnew(p: PWideChar) : PWideChar; Overload
```

Visibility: default

Description: Copies P to the Heap, and returns a pointer to the copy.

Errors: Returns `Nil` if no memory was available for the copy.

See also: StrCopy (1751), StrDispose (1752)

Listing: ./examples/stringex/ex16.pp

Program Example16:

Uses strings;

```

{ Program to demonstrate the StrNew function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin
  P2:=StrNew (P1);
  If P1=P2 then
    writeln ('This can''t be happening...')
  else
    writeln ('P2 : ',P2);
  StrDispose(P2);
end.

```

77.15.222 StrNextChar

Synopsis: Returns a pointer to the location of the next empty character in a null-terminated string

Declaration: `function StrNextChar(const Str: PChar) : PChar`

Visibility: default

Description: `StrNextChar` returns a pointer to the null-character that terminates the string `Str`

Errors: if `Str` is not properly terminated, an access violation may occur.

77.15.223 StrPas

Synopsis: Convert a null-terminated string to an ansistring.

Declaration: `function StrPas(Str: PChar) : string; Overload`
`function StrPas(Str: PWideChar) : UnicodeString; Overload`

Visibility: default

Description: Converts a null terminated string in `Str` to an `Ansistring`, and returns this string. This string is NOT truncated at 255 characters as is the system unit's version.

Errors: None.

See also: `StrPCopy` ([1761](#)), `StrPLCopy` ([1762](#))

77.15.224 StrPCopy

Synopsis: Copy an ansistring to a null-terminated string.

Declaration: `function StrPCopy(Dest: PChar; const Source: string) : PChar; Overload`
`function StrPCopy(Dest: PWideChar; const Source: UnicodeString)`
`: PWideChar; Overload`

Visibility: default

Description: `StrPCopy` Converts the `Ansistring` in `Source` to a Null-terminated string, and copies it to `Dest`.
`Dest` needs enough room to contain the string `Source`, i.e. `Length(Source)+1` bytes.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `Source`.

See also: `StrPLCopy` ([1762](#)), `StrPas` ([1761](#))

77.15.225 StrPLCopy

Synopsis: Copy a limited number of characters from an ansistring to a null-terminated string.

Declaration: `function StrPLCopy(Dest: PChar; const Source: string; MaxLen: SizeUInt)
: PChar; Overload
function StrPLCopy(Dest: PWideChar; const Source: UnicodeString;
MaxLen: SizeUInt) : PWideChar; Overload`

Visibility: default

Description: StrPLCopy Converts maximally MaxLen characters of the Ansistring in Source to a Null-terminated string, and copies it to Dest. Dest needs enough room to contain the characters.

Errors: No checking is performed to see whether Dest points to enough memory to contain L characters of Source.

See also: StrPCopy ([1761](#))

77.15.226 strpos

Synopsis: Find position of one null-terminated substring in another.

Declaration: `function strpos(str1: PChar; str2: PChar) : PChar
function strpos(str1: PWideChar; str2: PWideChar) : PWideChar`

Visibility: default

Description: Returns a pointer to the first occurrence of S2 in S1. If S2 does not occur in S1, returns Nil.

Errors: None.

See also: StrScan ([1763](#)), StrRScan ([1762](#))

Listing: ./examples/stringex/ex15.pp

Program Example15;

Uses strings;

{ Program to demonstrate the StrPos function. }

Const P : PChar = 'This is a PChar string.';
S : Pchar = 'is';

begin

WriteLn ('Position of ''is'' in P : ',sizeint(**StrPos**(P,S))–sizeint(P));
end.

77.15.227 strscan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar
function strscan(p: PWideChar; c: WideChar) : PWideChar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character *C* in the null-terminated string *P*. If *C* does not occur, returns *Nil*.

For an example, see [StrScan \(1763\)](#).

Errors: None.

See also: [StrScan \(1763\)](#), [StrPos \(1762\)](#)

77.15.228 StrScan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar; Overload`
`function StrScan(P: PWideChar; C: WideChar) : PWideChar; Overload`

Visibility: default

Description: Returns a pointer to the first occurrence of the character *C* in the null-terminated string *P*. If *C* does not occur, returns *Nil*.

Errors: None.

See also: [StrRScan \(1762\)](#), [StrPos \(1762\)](#)

Listing: `./examples/stringex/ex13.pp`

Program Example13;

Uses strings;

{ Program to demonstrate the StrScan and StrRScan functions. }

Const *P* : PChar = 'This is a PCHAR string.';
S : Char = 's' ;

begin

WriteLn ('P, starting from first 's' : ', **StrScan**(*P*,*s*));

WriteLn ('P, starting from last 's' : ', **StrRScan**(*P*,*s*));

end.

77.15.229 StrToBool

Synopsis: Convert a string to a boolean value

Declaration: `function StrToBool(const S: string) : Boolean`
`function StrToBool(const S: string;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `StrToBool` will convert the string *S* to a boolean value. The string *S* can contain one of 'True', 'False' (case is ignored) or a numerical value. If it contains a numerical value, 0 is converted to False, all other values result in True. If the string *S* contains no valid boolean, then an `EConvertError (1800)` exception is raised.

Errors: On error, an `EConvertError (1800)` exception is raised.

See also: [BoolToStr \(1665\)](#)

77.15.230 StrToBoolDef

Synopsis: Convert string to boolean value, returning default in case of error

Declaration: `function StrToBoolDef(const S: string; Default: Boolean) : Boolean`
`function StrToBoolDef(const S: string; Default: Boolean;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `StrToBoolDef` tries to convert the string `S` to a boolean value, and returns the boolean value in case of success. In case `S` does not contain a valid boolean string, `Default` is returned.

See also: `StrToBool` ([1763](#)), `TryStrToBool` ([1782](#))

77.15.231 StrToCurr

Synopsis: Convert a string to a currency value

Declaration: `function StrToCurr(const S: string) : Currency`
`function StrToCurr(const S: string;`
`const FormatSettings: TFormatSettings) : Currency`

Visibility: default

Description: `StrToCurr` converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, an `EConvertError` ([1800](#)) exception is raised.

Errors: On error, an `EConvertError` ([1800](#)) exception is raised.

See also: `CurrToStr` ([1673](#)), `StrToCurrDef` ([1764](#))

77.15.232 StrToCurrDef

Synopsis: Convert a string to a currency value, using a default value

Declaration: `function StrToCurrDef(const S: string; Default: Currency) : Currency`
`function StrToCurrDef(const S: string; Default: Currency;`
`const FormatSettings: TFormatSettings) : Currency`

Visibility: default

Description: `StrToCurrDef` converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, the fallback `Default` value is returned.

Errors: On error, the `Default` value is returned.

See also: `CurrToStr` ([1673](#)), `StrToCurr` ([1764](#))

77.15.233 StrToDate

Synopsis: Convert a date string to a `TDateTime` value.

Declaration:

```
function StrToDate(const S: ShortString) : TDateTime
function StrToDate(const S: AnsiString) : TDateTime
function StrToDate(const S: ShortString; separator: Char) : TDateTime
function StrToDate(const S: AnsiString; separator: Char) : TDateTime
function StrToDate(const S: string; FormatSettings: TFormatSettings)
    : TDateTime
function StrToDate(const S: ShortString; const useformat: string;
    separator: Char) : TDateTime
function StrToDate(const S: AnsiString; const useformat: string;
    separator: Char) : TDateTime
function StrToDate(const S: PChar; Len: Integer;
    const useformat: string; separator: Char) : TDateTime
```

Visibility: default

Description: StrToDate converts the string S to a TDateTime date value. The Date must consist of 1 to three digits, separated by the DateSeparator character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the ShortDateFormat variable.

Errors: On error (e.g. an invalid date or invalid character), an EConvertError (1800) exception is raised.

See also: StrToTime (1771), DateToStr (1677), TimeToStr (1778), EConvertError (1800)

Listing: ./examples/sysutex/ex19.pp

Program Example19;

{ This program demonstrates the StrToDate function }

Uses sysutils;

Procedure TestStr (S : String);

begin

 WriteLn (S, ' : ', DateToStr(StrToDate(S)));
end;

Begin

 WriteLn ('ShortDateFormat ', ShortDateFormat);
 TestStr(DateTimeToStr(Date));
 TestStr('05'+DateSeparator+'05'+DateSeparator+'1999');
 TestStr('5'+DateSeparator+'5');
 TestStr('5');

End.

77.15.234 StrToDateDef

Synopsis: Convert string to date, returning a default value

Declaration:

```
function StrToDateDef(const S: ShortString; const Defvalue: TDateTime)
    : TDateTime
function StrToDateDef(const S: ShortString; const Defvalue: TDateTime;
    separator: Char) : TDateTime
```

```
function StrToDateDef(const S: AnsiString; const Defvalue: TDateTime)
    : TDateTime
function StrToDateDef(const S: AnsiString; const Defvalue: TDateTime;
    separator: Char) : TDateTime
```

Visibility: default

Description: `StrToDateDef` tries to convert the string `S` to a valid `TDateTime` date value, and returns `DefValue` if `S` does not contain a valid date indication.

Errors: None.

See also: `StrToDate` (1764), `TryStrToDate` (1783), `StrToTimeDef` (1772)

77.15.235 StrToDateTime

Synopsis: Convert a date/time string to a `TDateTime` value.

```
Declaration: function StrToDateTime(const S: AnsiString) : TDateTime
function StrToDateTime(const s: ShortString;
    const FormatSettings: TFormatSettings) : TDateTime
function StrToDateTime(const s: AnsiString;
    const FormatSettings: TFormatSettings) : TDateTime
```

Visibility: default

Description: `StrToDateTime` converts the string `S` to a `TDateTime` date and time value. The date and time parts must be separated by a space.

For the date part, the same restrictions apply as for the `StrToDate` (1764) function: The Date must consist of 1 to three numbers, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the 3 numbers (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` (1800) exception is raised.

See also: `StrToDate` (1764), `StrToTime` (1771), `DateTimeToStr` (1674), `EConvertError` (1800)

Listing: ./examples/sysutex/ex20.pp

Program Example20;

{ This program demonstrates the StrToDateTime function }

Uses sysutils;

Procedure TestStr (S : **String**);

begin

WriteLn (S, ' : ', **DateTimeToStr**(**StrToDateTime**(S)));

end;

Begin

WriteLn ('ShortDateFormat ', ShortDateFormat);

 TestStr(**DateTimeToStr**(**Now**));

```

TestStr( '05-05-1999 15:50 ' );
TestStr( '5-5 13:30 ' );
TestStr( '5 1:30PM' );
End.

```

77.15.236 StrToDateTimeDef

Synopsis: Convert string to date/time, returning a default value

Declaration:

```

function StrToDateTimeDef(const S: ShortString;
                          const Defvalue: TDateTime) : TDateTime
function StrToDateTimeDef(const S: AnsiString;
                          const Defvalue: TDateTime) : TDateTime
function StrToDateTimeDef(const S: AnsiString;
                          const Defvalue: TDateTime;
                          const FormatSettings: TFormatSettings)
                          : TDateTime

```

Visibility: default

Description: `StrToDateTimeDef` tries to convert the string `S` to a valid `TDateTime` date and time value, and returns `DefValue` if `S` does not contain a valid date-time indication.

Errors: None.

See also: `StrToTimeDef` ([1772](#)), `StrToDateDef` ([1765](#)), `TryStrToDateTime` ([1783](#)), `StrToDateTime` ([1766](#))

77.15.237 StrToDWord

Synopsis: Convert string to DWord (cardinal)

Declaration: `function StrToDWord(const s: string) : DWord`

Visibility: default

Description: `StrToDWord` will convert the string `S` to a `DWord` value, and returns the value.

Errors: In case the string `S` is not a valid number, or is a value outside the `DWord` range, an `EConvertError` exception will be raised.

See also: `TryStrToDWord` ([1784](#)), `StrToDWordDef` ([1767](#))

77.15.238 StrToDWordDef

Synopsis: Convert string to DWord (cardinal), using default

Declaration: `function StrToDWordDef(const S: string; Default: DWord) : DWord`

Visibility: default

Description: `StrToDWordDef` will try to convert the string `S` to a `DWord` value. If the conversion was successful, it returns the value.

If the conversion failed, the fallback value in `Default` is returned.

See also: `TryStrToDWord` ([1784](#)), `StrToDWord` ([1767](#))

77.15.239 StrToFloat

Synopsis: Convert a string to a floating-point value.

Declaration: `function StrToFloat(const S: string) : Extended`
`function StrToFloat(const S: string;`
`const FormatSettings: TFormatSettings) : Extended`

Visibility: default

Description: `StrToFloat` converts the string `S` to a floating point value. `S` should contain a valid string representation of a floating point value (either in decimal or scientific notation). The `thousandseparator` character may however not be used.

Up to and including version 2.2.2 of the compiler, if the string contains a decimal value, then the decimal separator character can either be a '.' or the value of the `DecimalSeparator` variable.

As of version 2.3.1, the string may contain only the `DecimalSeparator` character. The dot ('.') can no longer be used instead of the `DecimalSeparator`.

Errors: If the string `S` doesn't contain a valid floating point string, then an exception will be raised.

See also: `TextToFloat` (1776), `FloatToStr` (1708), `FormatFloat` (1722), `StrToInt` (1769)

Listing: `./examples/sysutex/ex90.pp`

Program `Example90`;

```
{ This program demonstrates the StrToFloat function }
{$mode objfpc}
{$h+ }
```

Uses `SysUtils`;

Const

```
NrValues = 5;
TestStr : Array[1..NrValues] of string =
    ('1,1 ', '-0,2 ', '1,2E-4 ', '0 ', '1E4 ');
```

Procedure `Testit`;

Var

```
I : Integer;
E : Extended;
```

begin

```
  Writeln('Using DecimalSeparator : ', DecimalSeparator);
  For I:=1 to NrValues do
    begin
      Writeln('Converting : ', TestStr[I]);
      Try
        E:=StrToFloat(TestStr[I]);
        Writeln('Converted value : ', E);
      except
        On E : Exception do
          Writeln('Exception when converting : ', E.Message);
      end;
    end;
  end;
```

end;

Begin

```

DecimalSeparator:= ',';
Testit;
DecimalSeparator:= '.';
Testit;
End.
```

77.15.240 StrToFloatDef

Synopsis: Convert a string to a float, with a default value.

Declaration: `function StrToFloatDef(const S: string; const Default: Extended) : Extended`
`function StrToFloatDef(const S: string; const Default: Extended; const FormatSettings: TFormatSettings) : Extended`

Visibility: default

Description: `StrToFloatDef` tries to convert the string `S` to a floating point value, and returns this value. If the conversion fails for some reason, the value `Default` is returned instead.

Errors: None. On error, the `Default` value is returned.

77.15.241 StrToInt

Synopsis: Convert a string to an integer value.

Declaration: `function StrToInt(const s: string) : LongInt`

Visibility: default

Description: `StrToInt` will convert the string `S` to a 32-bit signed integer. If the string contains invalid characters or has an invalid format, then an `EConvertError` (1800) is raised.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (-). Spaces are not allowed.

The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference. For enumerated values, the string must be the name of the enumerated value. The name is searched case insensitively.

For hexadecimal values, the prefix '0x' or 'x' (case insensitive) may be used as well.

Errors: In case of error, an `EConvertError` is raised.

See also: `IntToStr` (1736), `StrToUInt` (1773), `StrToInt64` (1770), `StrToIntDef` (1770), `EConvertError` (1800)

Listing: ./examples/sysutex/ex82.pp

Program Example82;

```
{ $mode objfpc }
```

```
{ This program demonstrates the StrToInt function }
```

```
Uses sysutils;
```

```
Begin
```

```
  Writeln ( StrToInt( '1234' ));
```

```
  Writeln ( StrToInt( '-1234' ));
```

```

Writeln (StrToInt('0'));
Try
  Writeln (StrToInt('12345678901234567890'));
except
  On E : EConvertError do
    Writeln ('Invalid number encountered');
end;
End.

```

77.15.242 StrToInt64

Synopsis: Convert a string to an Int64 value.

Declaration: `function StrToInt64(const s: string) : Int64`

Visibility: default

Description: `StrToInt64` converts the string `S` to a `Int64` value, and returns this value. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the `$` character) are supported.

Errors: On error, a `EConvertError` (1800) exception is raised.

See also: `TryStrToInt64` (1785), `StrToInt64Def` (1770), `StrToInt` (1769), `TryStrToInt` (1784), `StrToIntDef` (1770)

77.15.243 StrToInt64Def

Synopsis: Convert a string to an Int64 value, with a default value

Declaration: `function StrToInt64Def(const S: string; Default: Int64) : Int64`

Visibility: default

Description: `StrToInt64Def` tries to convert the string `S` to a `Int64` value, and returns this value. If the conversion fails for some reason, the value `Default` is returned instead.

Errors: None. On error, the `Default` value is returned.

See also: `StrToInt64` (1770), `TryStrToInt64` (1785), `StrToInt` (1769), `TryStrToInt` (1784), `StrToIntDef` (1770)

77.15.244 StrToIntDef

Synopsis: Convert a string to an integer value, with a default value.

Declaration: `function StrToIntDef(const S: string; Default: LongInt) : LongInt`

Visibility: default

Description: `StrToIntDef` will convert a string to an integer. If the string contains invalid characters or has an invalid format, then `Default` is returned.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (`-`). Spaces are not allowed.

Errors: None.

See also: `IntToStr` (1736), `StrToInt` (1769)

Listing: ./examples/sysutex/ex83.pp

Program Example82;

```
{ $mode objfpc }

{ This program demonstrates the StrToInt function }

Uses sysutils;

Begin
  WriteLn ( StrToIntDef( '1234', 0 ));
  WriteLn ( StrToIntDef( '-1234', 0 ));
  WriteLn ( StrToIntDef( '0', 0 ));
  Try
    WriteLn ( StrToIntDef( '12345678901234567890', 0 ));
  except
    On E : EConvertError do
      WriteLn ( 'Invalid number encountered' );
  end;
End.
```

77.15.245 StrToQWord

Synopsis: Convert a string to a QWord.

Declaration: function StrToQWord(const s: string) : QWord

Visibility: default

Description: TryStrToQWord converts the string S to a valid QWord (unsigned 64-bit) value, and returns the result.

Errors: If the string S does not contain a valid QWord value, a EConvertError (1800) exception is raised.

See also: TryStrToQWord (1785), StrToQWordDef (1771), StrToInt64 (1770), StrToInt (1769)

77.15.246 StrToQWordDef

Synopsis: Try to convert a string to a QWord, returning a default value in case of failure.

Declaration: function StrToQWordDef(const S: string; Default: QWord) : QWord

Visibility: default

Description: StrToQWordDef tries to convert the string S to a valid QWord (unsigned 64-bit) value, and returns the result. If the conversion fails, the function returns the value passed in Def.

See also: StrToQWord (1771), TryStrToQWord (1785), StrToInt64Def (1770), StrToIntDef (1770)

77.15.247 StrToTime

Synopsis: Convert a time string to a TDateTime value.

Declaration: function StrToTime(const S: Shortstring) : TDateTime
 function StrToTime(const S: Ansistring) : TDateTime
 function StrToTime(const S: ShortString; separator: Char) : TDateTime

```

function StrToTime(const S: AnsiString; separator: Char) : TDateTime
function StrToTime(const S: string; FormatSettings: TFormatSettings)
    : TDateTime
function StrToTime(const S: PChar; Len: Integer; separator: Char)
    : TDateTime

```

Visibility: default

Description: `StrToTime` converts the string `S` to a `TDateTime` time value. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` (1800) exception is raised.

See also: `StrToDate` (1764), `StrToDateTime` (1766), `TimeToStr` (1778), `EConvertError` (1800)

Listing: `./examples/sysutex/ex21.pp`

Program Example21;

{ This program demonstrates the StrToTime function }

Uses sysutils;

Procedure TestStr (S : **String**);

begin

WriteLn (S, ' : ', **TimeToStr**(**StrToTime**(S)));

end;

Begin

teststr (**TimeToStr**(**Time**));
 teststr ('12:00');
 teststr ('15:30');
 teststr ('3:30PM');

End.

77.15.248 StrToTimeDef

Synopsis: Convert string to time, returning a default value

Declaration:

```

function StrToTimeDef(const S: ShortString; const Defvalue: TDateTime)
    : TDateTime
function StrToTimeDef(const S: ShortString; const Defvalue: TDateTime;
    separator: Char) : TDateTime
function StrToTimeDef(const S: AnsiString; const Defvalue: TDateTime)
    : TDateTime
function StrToTimeDef(const S: AnsiString; const Defvalue: TDateTime;
    separator: Char) : TDateTime

```

Visibility: default

Description: `StrToTimeDef` tries to convert the string `S` to a valid `TDateTime` time value, and returns `DefValue` if `S` does not contain a valid time indication.

Errors: None.

See also: `StrToTime` (1771), `TryStrToTime` (1785), `StrToDateDef` (1765)

77.15.249 StrToInt

Synopsis: Convert a string to unsigned integer value

Declaration: `function StrToInt(const s: string) : Cardinal`

Visibility: default

Description: `StrToInt` will convert the string `S` to an unsigned 32-bit integer. If the string contains invalid characters or has an invalid format, then an `EConvertError` (1800) is raised.

To be successfully converted, a string can contain a combination of `numerical` characters. Spaces are not allowed.

The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference.

For hexadecimal values, the prefix `'0x'` or `'x'` (case insensitive) may be used as well.

Errors: In case of error, an `EConvertError` is raised.

See also: `UIntToStr` (1786), `StrToInt` (1769), `StrToInt64` (1770), `StrToUInt64` (1773), `StrToIntDef` (1770), `EConvertError` (1800)

77.15.250 StrToUInt64

Synopsis: Convert a string to unsigned integer value

Declaration: `function StrToUInt64(const s: string) : UInt64`

Visibility: default

Description: `StrToUInt64` will convert the string `S` to an unsigned 64-bit integer. If the string contains invalid characters or has an invalid format, then an `EConvertError` (1800) is raised.

To be successfully converted, a string can contain a combination of `numerical` characters, possibly preceded by a minus sign (`-`). Spaces are not allowed.

The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference.

For hexadecimal values, the prefix `'0x'` or `'x'` (case insensitive) may be used as well.

Errors: In case of error, an `EConvertError` is raised.

See also: `UIntToStr` (1786), `StrToInt` (1769), `StrToInt64` (1770), `StrToUInt64` (1773), `StrToIntDef` (1770), `EConvertError` (1800)

77.15.251 StrToUInt64Def

Synopsis: Convert a string to an unsigned 64-bit integer value, with a default value.

Declaration: `function StrToUInt64Def(const S: string; Default: UInt64) : UInt64`

Visibility: default

Description: `StrToIntDef` will convert a string to an unsigned 64-bit integer. If the string contains invalid characters or has an invalid format, then `Default` is returned.

To be successfully converted, a string can contain a combination of `numerical` characters. Spaces are not allowed.

Errors: None.

See also: `IntToStr` (1736), `StrToUInt64` (1773), `TryStrToUInt64` (1786), `StrToInt64` (1770)

77.15.252 StrToUIntDef

Synopsis: Convert a string to an unsigned integer value, with a default value.

Declaration: `function StrToUIntDef(const S: string; Default: Cardinal) : Cardinal`

Visibility: default

Description: `StrToUIntDef` will convert a string to an integer. If the string contains invalid characters or has an invalid format, then `Default` is returned.

To be successfully converted, a string can contain a combination of numerical characters. Spaces are not allowed.

Errors: None.

See also: `IntToStr` (1736), `StrToUInt` (1773), `TryStrToUInt` (1786), `StrToInt` (1769)

77.15.253 strupper

Synopsis: Convert null-terminated string to all-uppercase

Declaration: `function strupper(p: PChar) : PChar`
`function strupper(p: PWideChar) : PWideChar`

Visibility: default

Description: Converts `P` to an all-uppercase string. Returns `P`.

For an example, see `StrLower` (1759)

Errors: None.

See also: `StrLower` (1759)

77.15.254 Supports

Synopsis: Check whether a class or given interface supports an interface

Declaration: `function Supports(const Instance: IInterface; const AClass: TClass;
out Obj) : Boolean; Overload`
`function Supports(const Instance: IInterface; const IID: TGuid;
out Intf) : Boolean; Overload`
`function Supports(const Instance: TObject; const IID: TGuid; out Intf)
: Boolean; Overload`
`function Supports(const Instance: TObject; const IID: Shortstring;
out Intf) : Boolean; Overload`
`function Supports(const Instance: IInterface; const AClass: TClass)
: Boolean; Overload`
`function Supports(const Instance: IInterface; const IID: TGuid)
: Boolean; Overload`
`function Supports(const Instance: TObject; const IID: TGuid) : Boolean
; Overload`
`function Supports(const Instance: TObject; const IID: Shortstring)
: Boolean; Overload`
`function Supports(const AClass: TClass; const IID: TGuid) : Boolean
; Overload`
`function Supports(const AClass: TClass; const IID: Shortstring)
: Boolean; Overload`

Visibility: default

Description: Supports checks whether Instance supports the interface identified by IID. It returns True if it is supported, False. Optionally, a pointer to the interface is returned to Intf.

Errors: None.

See also: StringToGUID ([1755](#))

77.15.255 SysErrorMessage

Synopsis: Format a system error message.

Declaration: `function SysErrorMessage(ErrorCode: Integer) : string`

Visibility: default

Description: SysErrorMessage returns a string that describes the operating system error code ErrorCode.

Errors: This routine may not be implemented on all platforms.

See also: EOSError ([1805](#))

77.15.256 SystemTimeToDateTime

Synopsis: Convert a system time to a TDateTime value.

Declaration: `function SystemTimeToDateTime(const SystemTime: TSystemTime) : TDateTime`

Visibility: default

Description: SystemTimeToDateTime converts a TSystemTime record to a TDateTime style date/time indication.

Errors: None.

See also: DateTimeToSystemTime ([1676](#))

Listing: ./examples/sysutex/ex22.pp

Program Example22;

{ This program demonstrates the SystemTimeToDateTime function }

Uses sysutils;

Var ST : TSystemTime;

Begin

 DateTimeToSystemTime(**Now**, ST);

With St **do**

begin

Writeln ('Today is ', year, '/', month, '/', Day);

Writeln ('The time is ', Hour, ':', minute, ':', Second, '.', MilliSecond);

end;

Writeln ('Converted : ', **DateTimeToStr**(SystemTimeToDateTime(ST)));

End.

77.15.257 TextToFloat

Synopsis: Convert a buffer to a float value.

Declaration:

```
function TextToFloat(Buffer: PChar; out Value: Extended) : Boolean
function TextToFloat(Buffer: PChar; out Value: Extended;
                    const FormatSettings: TFormatSettings) : Boolean
function TextToFloat(Buffer: PChar; out Value; ValueType: TFloatValue)
                    : Boolean
function TextToFloat(Buffer: PChar; out Value; ValueType: TFloatValue;
                    const FormatSettings: TFormatSettings) : Boolean
```

Visibility: default

Description: `TextToFloat` converts the string in `Buffer` to a floating point value. `Buffer` should contain a valid string representation of a floating point value (either in decimal or scientific notation).

If the buffer contains a decimal value, then the decimal separator character must be the value of the `DecimalSeparator` variable.

Remark Note that this behaviour has changed, earlier implementations also allowed the use of '.' in addition to the decimal separator character.

The function returns `True` if the conversion was successful.

Errors: If there is an invalid character in the buffer, then the function returns `False`

See also: `StrToFloat` ([1768](#)), `FloatToStr` ([1708](#)), `FormatFloat` ([1722](#))

Listing: ./examples/sysutex/ex91.pp

Program Example91;

```
{ This program demonstrates the TextToFloat function }
{$mode objfpc}
{$h+ }
```

Uses SysUtils;

Const

```
NrValues = 5;
TestStr : Array[1..NrValues] of pchar =
    ('1', '1', '-0,2', '1,2E-4', '0', '1E4');
```

Procedure Testit;

Var

```
I : Integer;
E : Extended;
```

begin

```
Writeln('Using DecimalSeparator : ', DecimalSeparator);
```

```
For I:=1 to NrValues do
```

```
begin
```

```
Writeln('Converting : ', TestStr[I]);
```

```
If TextToFloat(TestStr[I], E) then
```

```
Writeln('Converted value : ', E)
```

```
else
```

```
Writeln('Unable to convert value.');
```

```
end;
```

```
end;
```

```

Begin
  DecimalSeparator:= ',';
  Testit;
  DecimalSeparator:= '.';
  Testit;
End.

```

77.15.258 Time

Synopsis: Returns the current time.

Declaration: `function Time : TDateTime`

Visibility: default

Description: `Time` returns the current time in `TDateTime` format. The date part of the `TDateTimeValue` is set to zero.

Errors: None.

See also: `Now` ([1742](#)), `Date` ([1673](#))

Listing: `./examples/sysutex/ex23.pp`

Program `Example23;`

{ This program demonstrates the Time function }

Uses `sysutils;`

```

Begin
  WriteLn ('The time is : ',TimeToStr(Time));
End.

```

77.15.259 TimeStampToDateTime

Synopsis: Convert a `TimeStamp` value to a `TDateTime` value.

Declaration: `function TimeStampToDateTime(const TimeStamp: TTimeStamp) : TDateTime`

Visibility: default

Description: `TimeStampToDateTime` converts `TimeStamp` to a `TDateTime` format variable. It is the inverse operation of `DateTimeToTimeStamp` ([1677](#)).

Errors: None.

See also: `DateTimeToTimeStamp` ([1677](#)), `TimeStampToMSecs` ([1778](#))

Listing: `./examples/sysutex/ex24.pp`

Program `Example24;`

{ This program demonstrates the TimeStampToDateTime function }

Uses `sysutils;`

```

Var TS : TTimeStamp;
      DT : TDateTime;

Begin
  TS:=DateTimeToTimeStamp (Now);
  With TS do
    begin
      WriteLn ('Now is ',time,' millisecond past midnight');
      WriteLn ('Today is ' ,Date,' days past 1/1/0001');
    end;
  DT:=TimeStampToDateTime(TS);
  WriteLn ('Together this is : ',DateTimeToStr(DT));
End.

```

77.15.260 TimeStampToMSecs

Synopsis: Converts a timestamp to a number of milliseconds.

Declaration: `function TimeStampToMSecs(const TimeStamp: TTimeStamp) : Comp`

Visibility: default

Description: `TimeStampToMSecs` converts `TimeStamp` to the number of milliseconds since 1/1/0001.

Use `TTimeStamp` variables if you need to keep very precise track of time.

For an example, see `MSecsToTimeStamp` ([1741](#)).

Errors: None.

See also: `MSecsToTimeStamp` ([1741](#)), `TimeStampToDateTime` ([1777](#))

77.15.261 TimeToStr

Synopsis: Convert a `TDateTime` time to a string using a predefined format.

Declaration: `function TimeToStr(Time: TDateTime) : string`
`function TimeToStr(Time: TDateTime;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `TimeToStr` converts the time in `Time` to a string. It uses the `LongTimeFormat` variable to see what formatting needs to be applied. It is therefor entirely equivalent to a `FormatDateTime('tt', Time)` call.

Note that on unix systems, the localization support must be enabled explicitly, see `Localization` ([1616](#)).

Errors: None.

Listing: `./examples/sysutex/ex25.pp`

Program `Example25;`

{ This program demonstrates the TimeToStr function }

Uses `sysutils;`

```

Begin
  WriteLn ('The current time is : ', TimeToStr(Time));
End.

```

77.15.262 Trim

Synopsis: Trim whitespace from the ends of a string.

Declaration: `function Trim(const S: string) : string`
`function Trim(const S: WideString) : WideString`
`function Trim(const S: UnicodeString) : UnicodeString`

Visibility: default

Description: `Trim` strips blank characters (spaces and control characters) at the beginning and end of `S` and returns the resulting string. All characters with ordinal values less than or equal to 32 (a space) are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `TrimLeft` ([1779](#)), `TrimRight` ([1780](#))

Listing: `./examples/sysutex/ex84.pp`

Program `Example84`;

{ This program demonstrates the Trim function }

Uses `sysutils`;
`{ $H+ }`

Procedure `Testit (S : String)`;

begin
`WriteLn (' ', Trim(S), ' ');`
end;

Begin
`Testit (' ha ha what gets lost ? ');`
`Testit (#10#13'haha ');`
`Testit (' ');`
End.

77.15.263 TrimLeft

Synopsis: Trim whitespace from the beginning of a string.

Declaration: `function TrimLeft(const S: string) : string`
`function TrimLeft(const S: WideString) : WideString`
`function TrimLeft(const S: UnicodeString) : UnicodeString`

Visibility: default

Description: `Trim` strips blank characters (spaces and control characters) at the beginning of `S` and returns the resulting string. All characters with ordinal values less than or equal to 32 (a space) are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `Trim` ([1779](#)), `TrimRight` ([1780](#))

Listing: `./examples/sysutex/ex85.pp`

Program `Example85`;

{ This program demonstrates the TrimLeft function }

Uses `sysutils`;
`{ $H+ }`

Procedure `Testit (S : String);`

begin
 `WriteLn ('"', TrimLeft(S), '"');`
end;

Begin
 `Testit (' ha ha what gets lost ? ');`
 `Testit (#10#13'haha ');`
 `Testit (' ');`

End.

77.15.264 TrimRight

Synopsis: Trim whitespace from the end of a string.

Declaration: `function TrimRight(const S: string) : string`
 `function TrimRight(const S: WideString) : WideString`
 `function TrimRight(const S: UnicodeString) : UnicodeString`

Visibility: default

Description: `Trim` strips blank characters (spaces and control characters) at the end of `S` and returns the resulting string. All characters with ordinal values less than or equal to 32 (a space) are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `Trim` ([1779](#)), `TrimLeft` ([1779](#))

Listing: `./examples/sysutex/ex86.pp`

Program `Example86`;

{ This program demonstrates the TrimRight function }

Uses `sysutils`;
`{ $H+ }`

Procedure `Testit (S : String);`

```

begin
  WriteLn ( ' ', TrimRight(S), ' ');
end;

Begin
  Testit ( '  ha ha what gets lost ? ');
  Testit (#10#13'haha ');
  Testit ( '          ');
End.

```

77.15.265 TryEncodeDate

Synopsis: Try to encode a date, and indicate success.

Declaration: `function TryEncodeDate(Year: Word; Month: Word; Day: Word;
out Date: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDate` will check the validity of the Year, Month and Day arguments, and if they are all valid, then they will be encoded as a `TDateTime` value and returned in `Date`. The function will return `True` in this case. If an invalid argument is passed, then `False` will be returned.

Errors: None. If an error occurs during the encoding, `False` is returned.

See also: `EncodeDate` ([1683](#)), `DecodeDateFully` ([1679](#)), `DecodeDate` ([1679](#)), `TryEncodeTime` ([1781](#))

77.15.266 TryEncodeTime

Synopsis: Try to encode a time, and indicate success.

Declaration: `function TryEncodeTime(Hour: Word; Min: Word; Sec: Word; MSec: Word;
out Time: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeTime` will check the validity of the Hour, Min, Sec and MSec arguments, and will encode them in a `TDateTime` value which is returned in `Time`. If the arguments are valid, then `True` is returned, otherwise `False` is returned.

Errors: None. If an error occurs during the encoding, `False` is returned.

See also: `EncodeTime` ([1684](#)), `DecodeTime` ([1679](#)), `TryEncodeDate` ([1781](#))

77.15.267 TryFloatToCurr

Synopsis: Try to convert a float value to a currency value and report on success.

Declaration: `function TryFloatToCurr(const Value: Extended; var AResult: Currency)
: Boolean`

Visibility: default

Description: `TryFloatToCurr` tries convert the `Value` floating point value to a `Currency` value. If successful, the function returns `True` and the resulting currency value is returned in `AResult`. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` ([1627](#)) and `MaxCurrency` ([1627](#))). If not, `False` is returned.

Errors: If `Value` is out of range, `False` is returned.

See also: `FloatToCurr` ([1707](#)), `MinCurrency` ([1627](#)), `MaxCurrency` ([1627](#))

77.15.268 TryStringToGUID

Synopsis: Try to transform a string to a GUID

Declaration: `function TryStringToGUID(const S: string; out Guid: TGuid) : Boolean`

Visibility: default

Description: `TryStringToGUID` tries to convert the string `S` to a `TGUID` value, returned in `GUID`. It returns `True` if the conversion succeeds, and `False` if the string `S` does not contain a valid GUID notation. The string `S` must be 38 characters long, must start with `{` and end on `}`, and contain a valid GUID string (hex number grouped using 8-4-4-4-12 digits).

Errors: In case `S` does not contain a valid GUID number, `False` is returned.

See also: `StringToGUID` ([1755](#))

77.15.269 TryStrToBool

Synopsis: Try to convert a string to a boolean value

Declaration: `function TryStrToBool(const S: string; out Value: Boolean) : Boolean`
`function TryStrToBool(const S: string; out Value: Boolean;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToBool` tries to convert the string `S` to a boolean value, and returns this value in `Value`. In this case, the function returns `True`. If `S` does not contain a valid boolean string, the function returns `False`, and the contents of `Value` is undetermined.

Valid boolean string constants are in the `FalseBoolStrs` ([1644](#)) (for `False` values) and `TrueBoolStrs` ([1648](#)) (for `True` values) variables.

See also: `StrToBool` ([1763](#)), `StrToBoolDef` ([1764](#))

77.15.270 TryStrToCurr

Synopsis: Try to convert a string to a currency

Declaration: `function TryStrToCurr(const S: string; out Value: Currency) : Boolean`
`function TryStrToCurr(const S: string; out Value: Currency;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToCurr` converts the string `S` to a currency value and returns the value in `Value`. The function returns `True` if it was successful, `False` if not. This is contrary to `StrToCurr` ([1764](#)), which raises an exception when the conversion fails.

The function takes into account locale information.

See also: `StrToCurr` ([1764](#)), `TextToFloat` ([1776](#))

77.15.271 TryStrToDate

Synopsis: Try to convert a string with a date indication to a TDateTime value

Declaration: `function TryStrToDate(const S: ShortString; out Value: TDateTime) : Boolean`
`function TryStrToDate(const S: AnsiString; out Value: TDateTime) : Boolean`
`function TryStrToDate(const S: ShortString; out Value: TDateTime; separator: Char) : Boolean`
`function TryStrToDate(const S: AnsiString; out Value: TDateTime; separator: Char) : Boolean`
`function TryStrToDate(const S: ShortString; out Value: TDateTime; const useformat: string; separator: Char) : Boolean`
`function TryStrToDate(const S: AnsiString; out Value: TDateTime; const useformat: string; separator: Char) : Boolean`
`function TryStrToDate(const S: string; out Value: TDateTime; const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToDate` tries to convert the string `S` to a `TDateTime` date value, and stores the date in `Value`. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

The function returns `True` if the string contained a valid date indication, `False` otherwise.

See also: `StrToDate` (1764), `StrToTime` (1771), `TryStrToTime` (1785), `TryStrToDateTime` (1783), `DateToStr` (1677), `TimeToStr` (1778)

77.15.272 TryStrToDateTime

Synopsis: Try to convert a string with date/time indication to a TDateTime value

Declaration: `function TryStrToDateTime(const S: ShortString; out Value: TDateTime) : Boolean`
`function TryStrToDateTime(const S: AnsiString; out Value: TDateTime) : Boolean`
`function TryStrToDateTime(const S: string; out Value: TDateTime; const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToDateTime` tries to convert the string `S` to a `TDateTime` date and time value, and stores the result in `Value`. The date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month (This is *not* supported in Delphi). The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns `True` if the string contained a valid date and time indication, `False` otherwise.

See also: `TryStrToDate` (1783), `TryStrToTime` (1785), `StrToDateTime` (1766), `StrToTime` (1771), `DateToStr` (1677), `TimeToStr` (1778)

77.15.273 TryStrToDWord

Synopsis: Try to convert a string to DWord (cardinal)

Declaration: `function TryStrToDWord(const s: string; out D: DWord) : Boolean`

Visibility: default

Description: `TryStrToDWord` will try to convert the string `S` to a `DWord` value. It returns `True` if the conversion was successful, and in that case returns the value in `D`.

If the conversion failed or the value was outside of the valid range for `DWord` values, `False` is returned.

See also: `StrToDWord` ([1767](#)), `StrToDWordDef` ([1767](#))

77.15.274 TryStrToFloat

Synopsis: Try to convert a string to a float.

Declaration: `function TryStrToFloat(const S: string; out Value: Single) : Boolean`
`function TryStrToFloat(const S: string; out Value: Single;`
`const FormatSettings: TFormatSettings) : Boolean`
`function TryStrToFloat(const S: string; out Value: Double) : Boolean`
`function TryStrToFloat(const S: string; out Value: Double;`
`const FormatSettings: TFormatSettings) : Boolean`
`function TryStrToFloat(const S: string; out Value: Extended) : Boolean`
`function TryStrToFloat(const S: string; out Value: Extended;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToFloat` tries to convert the string `S` to a floating point value, and stores the result in `Value`. It returns `True` if the operation was successful, and `False` if it failed. This operation takes into account the system settings for floating point representations.

Errors: On error, `False` is returned.

See also: `StrToFloat` ([1768](#))

77.15.275 TryStrToInt

Synopsis: Try to convert a string to an integer, and report on success.

Declaration: `function TryStrToInt(const s: string; out i: LongInt) : Boolean`

Visibility: default

Description: `TryStrToInt` tries to convert the string `S` to an integer, and returns `True` if this was successful. In that case the converted integer is returned in `I`. If the conversion failed, (an invalid string, or the value is out of range) then `False` is returned.

Errors: None. On error, `False` is returned.

See also: `StrToInt` ([1769](#)), `TryStrToUInt` ([1786](#)), `TryStrToInt64` ([1785](#)), `StrToIntDef` ([1770](#)), `StrToInt64` ([1770](#)), `StrToInt64Def` ([1770](#))

77.15.276 TryStrToInt64

Synopsis: Try to convert a string to an int64 value, and report on success.

Declaration: `function TryStrToInt64(const s: string; out i: Int64) : Boolean`

Visibility: default

Description: `TryStrToInt64` tries to convert the string `S` to a `Int64` value, and returns this value in `I` if successful. If the conversion was successful, the function result is `True`, or `False` otherwise. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the `$` character) are supported.

Errors: None. On error, `False` is returned.

See also: `StrToInt64` (1770), `StrToInt64Def` (1770), `StrToInt` (1769), `TryStrToInt` (1784), `StrToIntDef` (1770)

77.15.277 TryStrToQWord

Synopsis: Try to convert a string to a QWord value, and report on success

Declaration: `function TryStrToQWord(const s: string; out Q: QWord) : Boolean`

Visibility: default

Description: `TryStrToQWord` tries to convert the string `S` to a valid `QWord` (unsigned 64-bit) value, and stores the result in `I`. If the conversion fails, the function returns `False`, else it returns `True`.

See also: `StrToQWord` (1771), `StrToQWordDef` (1771), `TryStrToInt64` (1785), `TryStrToInt` (1784)

77.15.278 TryStrToTime

Synopsis: Try to convert a string with a time indication to a `TDateTime` value

```
Declaration: function TryStrToTime(const S: ShortString; out Value: TDateTime)
              : Boolean
function TryStrToTime(const S: AnsiString; out Value: TDateTime)
              : Boolean
function TryStrToTime(const S: ShortString; out Value: TDateTime;
                      separator: Char) : Boolean
function TryStrToTime(const S: AnsiString; out Value: TDateTime;
                      separator: Char) : Boolean
function TryStrToTime(const S: string; out Value: TDateTime;
                      const FormatSettings: TFormatSettings) : Boolean
```

Visibility: default

Description: `TryStrToTime` tries to convert the string `S` to a `TDateTime` time value, and stores the result in `Value`. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns `True` if the string contained a valid time indication, `False` otherwise.

See also: `TryStrToDate` (1783), `TryStrToDateTime` (1783), `StrToDate` (1764), `StrToTime` (1771), `DateToStr` (1677), `TimeToStr` (1778)

77.15.279 TryStrToUInt

Synopsis: Try to convert a string to an unsigned integer, and report on success.

Declaration: `function TryStrToUInt(const s: string; out C: Cardinal) : Boolean`

Visibility: default

Description: `TryStrToUInt` tries to convert the string `S` to an unsigned 32-bit integer (a `Cardinal`), and returns `True` if this was successful. In that case the converted unsigned integer is returned in `C`. If the conversion failed, (an invalid string, or the value is out of range) then `False` is returned.

Errors: None. On error, `False` is returned.

See also: `StrToInt` ([1769](#)), `TryStrToInt` ([1784](#)), `TryStrToInt64` ([1785](#)), `StrToIntDef` ([1770](#)), `StrToInt64` ([1770](#)), `StrToInt64Def` ([1770](#))

77.15.280 TryStrToUInt64

Synopsis: Try to convert a string to an unsigned 64-bit integer, and report on success.

Declaration: `function TryStrToUInt64(const s: string; out u: UInt64) : Boolean`

Visibility: default

Description: `TryStrToUInt64` tries to convert the string `S` to an unsigned 64-bit integer (a `Cardinal`), and returns `True` if this was successful. In that case the converted unsigned integer is returned in `U`. If the conversion failed, (an invalid string, or the value is out of range) then `False` is returned.

Errors: None. On error, `False` is returned.

See also: `StrToInt` ([1769](#)), `TryStrToInt` ([1784](#)), `TryStrToInt64` ([1785](#)), `StrToIntDef` ([1770](#)), `StrToInt64` ([1770](#)), `StrToInt64Def` ([1770](#))

77.15.281 UIntToStr

Synopsis: Unsigned integer to String

Declaration: `function UIntToStr(Value: QWord) : string`
`function UIntToStr(Value: Cardinal) : string`

Visibility: default

Description: `UIntToStr` is the unsigned counterpart to `IntToStr` ([1736](#)): it converts the unsigned integer `Value` to its string representation. The resulting string has only as much characters as needed to represent the value.

Errors: None

See also: `IntToStr` ([1736](#))

77.15.282 UnhookSignal

Synopsis: UnHook a specified signal

Declaration: `procedure UnhookSignal(RtlSigNum: Integer; OnlyIfHooked: Boolean)`

Visibility: default

Description: `UnhookSignal` de-installs the RTL default signal handler for signal `RtlSigNum`. If `OnlyIfHooked` is `True` then `UnhookSignal` will first check if the signal was hooked by the RTL routines, and has not been overridden since.

77.15.283 UnicodeCompareStr

Synopsis: Compare 2 Unicode strings

Declaration: `function UnicodeCompareStr(const s1: UnicodeString;
const s2: UnicodeString) : PtrInt`

Visibility: default

Description: `UnicodeCompareStr` compares 2 Unicode strings `S1` and `S2` in a case sensitive manner. The result of the function is

< 0 If `S1`<`S2`

0 If `S1`=`S2`

> 0 If `S1`>`S2`

This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1787](#)), `CompareStr` ([1669](#)), `CompareText` ([1670](#)), `UnicodeSameStr` ([1789](#))

77.15.284 UnicodeCompareText

Synopsis: Compare 2 strings case insensitively

Declaration: `function UnicodeCompareText(const s1: UnicodeString;
const s2: UnicodeString) : PtrInt`

Visibility: default

Description: `UnicodeCompareText` compares 2 Unicode strings `S1` and `S2`, ignoring case. The result of the function is

< 0 If `S1`<`S2`

0 If `S1`=`S2`

> 0 If `S1`>`S2`

This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1787](#)), `CompareStr` ([1669](#)), `CompareText` ([1670](#)), `UnicodeSameStr` ([1789](#))

77.15.285 UnicodeFmtStr

Synopsis: Format a string with given arguments, procedural version.

Declaration: `procedure UnicodeFmtStr(var Res: UnicodeString;
const Fmt: UnicodeString;
const args: Array of const)
procedure UnicodeFmtStr(var Res: UnicodeString;
const Fmt: UnicodeString;
const args: Array of const;
const FormatSettings: TFormatSettings)`

Visibility: default

Description: `UnicodeFmtStr` calls `UnicodeFormat` (1788) with `Fmt` and `Args` as arguments, and stores the result in `Res`. For more information on how the resulting string is composed, see `UnicodeFormat` (1788).

Errors: In case of error, an `EConvertError` (1800) exception is raised.

See also: `UnicodeFormat` (1788), `UnicodeFormatBuf` (1788)

77.15.286 UnicodeFormat

Synopsis: Format Unicode string

Declaration:

```
function UnicodeFormat(const Fmt: UnicodeString;
                      const Args: Array of const) : UnicodeString
function UnicodeFormat(const Fmt: UnicodeString;
                      const Args: Array of const;
                      const FormatSettings: TFormatSettings)
                      : UnicodeString
```

Visibility: default

Description: `UnicodeFormat` is the Unicode equivalent of `Format` (1714). It follows the same rules and uses the same formatting strings.

Errors: In case of error, an `EConvertError` (1800) exception is raised.

See also: `Format` (1714), `UnicodeFormatBuf` (1788)

77.15.287 UnicodeFormatBuf

Synopsis: Format a Unicode string with given arguments and store the result in a unicodebuffer.

Declaration:

```
function UnicodeFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                          fmtLen: Cardinal; const Args: Array of const)
                          : Cardinal
function UnicodeFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                          fmtLen: Cardinal; const Args: Array of const;
                          const FormatSettings: TFormatSettings)
                          : Cardinal
```

Visibility: default

Description: `UnicodeFormatBuf` is the Unicode equivalent of `FormatBuf` (1720). It follows the same rules and uses the same formatting st

Errors: In case of error, an `EConvertError` (1800) exception is raised.

See also: `FormatBuf` (1720), `UnicodeFormat` (1788)

77.15.288 UnicodeLowerCase

Synopsis: Return lowercase version of a string

Declaration:

```
function UnicodeLowerCase(const s: UnicodeString) : UnicodeString
```

Visibility: default

Description: `UnicodeLowerCase` returns an all-lowercase version of the unicodestring `S`. It relies on the Unicode manager to do so.

See also: `UnicodeUpperCase` ([1790](#)), `UpperCase` ([1790](#)), `LowerCase` ([1740](#))

77.15.289 UnicodeSameStr

Synopsis: Check whether 2 strings are equal

Declaration: `function UnicodeSameStr(const s1: UnicodeString;
const s2: UnicodeString) : Boolean`

Visibility: default

Description: `UnicodeSameStr` checks whether the Unicode strings `S1` and `S2` are equal, case sensitively. The function returns `True` if the strings are equal, `False` if they are not. This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1787](#)), `CompareStr` ([1669](#)), `CompareText` ([1670](#)), `UnicodeSameText` ([1789](#)), `SameStr` ([1746](#))

77.15.290 UnicodeSameText

Synopsis: Check whether 2 strings are the same, ignoring case

Declaration: `function UnicodeSameText(const s1: UnicodeString;
const s2: UnicodeString) : Boolean`

Visibility: default

Description: `UnicodeSameText` checks whether the Unicode strings `S1` and `S2` are equal, ignoring case. The function returns `True` if the strings are equal, `False` if they are not. This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1787](#)), `CompareStr` ([1669](#)), `CompareText` ([1670](#)), `UnicodeSameStr` ([1789](#)), `SameText` ([1746](#))

77.15.291 UnicodeStringReplace

Synopsis: Replace one occurrence of a string with another

Declaration: `function UnicodeStringReplace(const S: UnicodeString;
const OldPattern: UnicodeString;
const NewPattern: UnicodeString;
Flags: TReplaceFlags) : UnicodeString
function UnicodeStringReplace(const S: UnicodeString;
const OldPattern: UnicodeString;
const NewPattern: UnicodeString;
Flags: TReplaceFlags; out aCount: Integer)
: UnicodeString`

Visibility: default

Description: `UnicodeStringReplace` is the Unicode version of `StringReplace` ([1755](#)); it follows the same rules and has the same behaviour, but operates on Unicode strings instead of ansistrings.

See also: `StringReplace` ([1755](#))

77.15.292 UnicodeUpperCase

Synopsis: Return uppercase version of a string

Declaration: `function UnicodeUpperCase(const s: UnicodeString) : UnicodeString`

Visibility: default

Description: `UnicodeUpperCase` returns an all-uppercase version of the unicodestring S. It relies on the Unicode manager to do so.

See also: `UnicodeLowerCase` (1788), `LowerCase` (1740), `UpperCase` (1790)

77.15.293 UpperCase

Synopsis: Return an uppercase version of a string.

Declaration: `function UpperCase(const s: string) : string; Overload`
`function UpperCase(const s: string; LocaleOptions: TLocaleOptions)`
`: string; Overload`
`function UpperCase(const s: UnicodeString) : UnicodeString; Overload`

Visibility: default

Description: `UpperCase` returns the uppercase equivalent of S. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the `UpCase` function of the system unit, and is provided for compatibility only.

Errors: None.

See also: `AnsiLowerCase` (1653), `LowerCase` (1740), `AnsiUpperCase` (1661)

Listing: `./examples/sysutex/ex87.pp`

Program `Example87;`

{ This program demonstrates the UpperCase function }

Uses `sysutils;`

Begin

`WriteLn (UpperCase('this will come OUT ALL uPpErCaSe !'));`
End.

77.15.294 VendorName

Synopsis: Return Application vendor Name

Declaration: `function VendorName : string`

Visibility: default

Description: `VendorName` returns the application vendor name. In order to set the application vendor name, the `OnGetVendorName` (1646) event must be set, and an appropriate return value must be returned. The Vendor name is used in `GetAppConfigDir` (1724) and `GetAppConfigFile` (1725) to determine the configuration directory.

Errors: If `OnGetVendorName` (1646) is not set, an empty string is returned.

See also: `OnGetVendorName` (1646), `GetAppConfigDir` (1724), `GetAppConfigFile` (1725)

77.15.295 WideBytesOf

Synopsis: Returns the contents of a widestring as an array of bytes

Declaration: `function WideBytesOf(const Value: UnicodeString) : TBytes`

Visibility: default

Description: `WideBytesOf` returns the contents of the widestring `Value` as an array of bytes. The array will have as length twice the length of the wide string, as each wide character contains 2 bytes.

See also: `StringOf` ([1754](#))

77.15.296 WideCompareStr

Synopsis: Compare two widestrings (case sensitive)

Declaration: `function WideCompareStr(const s1: WideString; const s2: WideString)
: PtrInt`

Visibility: default

Description: `WideCompareStr` compares two widestrings and returns the following result:

`< 0` if `S1<S2`.
`0` if `S1=S2`.
`> 0` if `S1>S2`.

The comparison takes into account wide characters, i.e. it takes care of strange accented characters. Contrary to `WideCompareText` ([1791](#)), the comparison is case sensitive.

Errors: None.

See also: `WideCompareText` ([1791](#)), `WideSameStr` ([1793](#)), `WideSameText` ([1793](#))

77.15.297 WideCompareText

Synopsis: Compare two widestrings (ignoring case).

Declaration: `function WideCompareText(const s1: WideString; const s2: WideString)
: PtrInt`

Visibility: default

Description: `WideCompareStr` compares two widestrings and returns the following result:

`< 0` if `S1<S2`.
`0` if `S1=S2`.
`> 0` if `S1>S2`.

The comparison takes into account wide characters, i.e. it takes care of strange accented characters. Contrary to `WideCompareStr` ([1791](#)), the comparison is case insensitive.

Errors: None.

See also: `WideCompareStr` ([1791](#)), `WideSameStr` ([1793](#)), `WideSameText` ([1793](#))

77.15.298 WideFmtStr

Synopsis: Widestring format

Declaration:

```
procedure WideFmtStr(var Res: WideString; const Fmt: WideString;
                    const args: Array of const)
procedure WideFmtStr(var Res: WideString; const Fmt: WideString;
                    const args: Array of const;
                    const FormatSettings: TFormatSettings)
```

Visibility: default

Description: `WideFmtStr` formats `Args` according to the format string in `Fmt` and returns the resulting string in `Res`.

See also: `WideFormat` ([1792](#)), `WideFormatBuf` ([1792](#)), `Format` ([1714](#))

77.15.299 WideFormat

Synopsis: Format a wide string.

Declaration:

```
function WideFormat(const Fmt: WideString; const Args: Array of const)
                : WideString
function WideFormat(const Fmt: WideString; const Args: Array of const;
                const FormatSettings: TFormatSettings) : WideString
```

Visibility: default

Description: `WideFormat` does the same as `Format` ([1714](#)) but accepts as a formatting string a `WideString`. The resulting string is also a `WideString`.

For more information about the used formatting characters, see the `Format` ([1714](#)) string.

See also: `Format` ([1714](#))

77.15.300 WideFormatBuf

Synopsis: Format widestring in a buffer.

Declaration:

```
function WideFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                    fmtLen: Cardinal; const Args: Array of const)
                : Cardinal
function WideFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                    fmtLen: Cardinal; const Args: Array of const;
                    const FormatSettings: TFormatSettings) : Cardinal
```

Visibility: default

Description: `WideFormatBuf` calls simply `WideFormat` ([1792](#)) with `Fmt` (with length `FmtLen` bytes) and stores maximum `BufLen` bytes in the buffer `buf`. It returns the number of copied bytes.

See also: `WideFmtStr` ([1792](#)), `WideFormat` ([1792](#)), `Format` ([1714](#)), `FormatBuf` ([1720](#))

77.15.301 WideLowerCase

Synopsis: Change a widestring to all-lowercase.

Declaration: `function WideLowerCase(const s: WideString) : WideString`

Visibility: default

Description: `WideLowerCase` converts the string `S` to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark On Unix-like platforms, a widestring manager must be installed for this function to work correctly.

Errors: None.

See also: `WideUpperCase` ([1794](#))

77.15.302 WideSameStr

Synopsis: Check whether two widestrings are the same (case sensitive)

Declaration: `function WideSameStr(const s1: WideString; const s2: WideString)
: Boolean`

Visibility: default

Description: `WideSameStr` returns `True` if `WideCompareStr` ([1791](#)) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameText` ([1793](#)), `WideCompareStr` ([1791](#)), `WideCompareText` ([1791](#)), `AnsiSameStr` ([1655](#))

77.15.303 WideSameText

Synopsis: Check whether two widestrings are the same (ignoring case)

Declaration: `function WideSameText(const s1: WideString; const s2: WideString)
: Boolean`

Visibility: default

Description: `WideSameText` returns `True` if `WideCompareText` ([1791](#)) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameStr` ([1793](#)), `WideCompareStr` ([1791](#)), `WideCompareText` ([1791](#)), `AnsiSameText` ([1655](#))

77.15.304 WideStrAlloc

Synopsis: Allocate a null-terminated widestring on the heap.

Declaration: `function WideStrAlloc(size: Cardinal) : PWideChar`

Visibility: default

Description: `WideStrAlloc` reserves memory on the heap for a widestring with length `Len`, (terminating `#0#0` included), and returns a pointer to it.

Additionally, `WideStrAlloc` allocates 4 extra bytes to store the size of the allocated memory.

Errors: None.

See also: `StrBufSize` ([1749](#)), `StrDispose` ([1752](#)), `StrAlloc` ([1288](#))

77.15.305 WideStringOf

Synopsis: Create Unicode string from array of bytes

Declaration: `function WideStringOf(const Value: TBytes) : UnicodeString`

Visibility: default

Description: `WideStringOf` converts an array of bytes (`Bytes`) to a Unicode string. It considers each pair of bytes in the array as a single wide char. The array should have an even length. If the length is uneven, the last byte will be ignored.

This function performs the opposite operation of `BytesOf` ([1665](#)).

To create a string where the bytes are interpreted as ansichars, use `StringOf` ([1754](#)) instead.

See also: `StringOf` ([1754](#)), `WideBytesOf` ([1791](#)), `BytesOf` ([1665](#))

77.15.306 WideStringReplace

Synopsis: Replace occurrences of one substring with another in a widestring.

```
Declaration: function WideStringReplace(const S: WideString;
                                     const OldPattern: WideString;
                                     const NewPattern: WideString;
                                     Flags: TReplaceFlags) : WideString
function WideStringReplace(const S: WideString;
                           const OldPattern: WideString;
                           const NewPattern: WideString;
                           Flags: TReplaceFlags; out aCount: Integer)
                           : WideString
```

Visibility: default

Description: `WideStringReplace` searches the string `S` for occurrences of the string `OldPattern` and, if it is found, replaces it with `NewPattern`. It returns the resulting string. The behaviour of `StringReplace` can be tuned with `Flags`, which is of type `TReplaceFlags` ([1639](#)). Standard behaviour is to replace only the first occurrence of `OldPattern`, and to search case sensitively.

Errors: None.

See also: `TReplaceFlags` ([1639](#)), `StringReplace` ([1755](#))

77.15.307 WideUpperCase

Synopsis: Change a widestring to all-uppercase.

Declaration: `function WideUpperCase(const s: WideString) : WideString`

Visibility: default

Description: `WideUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark On Unix-like platforms, a widestring manager must be installed for this function to work correctly.

Errors: None.

See also: `WideLowerCase` ([1793](#))

77.15.308 WrapText

Synopsis: Word-wrap a text.

Declaration: `function WrapText(const Line: string; const BreakStr: string;
const BreakChars: TSysCharSet; MaxCol: Integer)
: string
function WrapText(const Line: string; MaxCol: Integer) : string`

Visibility: default

Description: `WrapText` does a wordwrap at column `MaxCol` of the string in `Line`. It breaks the string only at characters which are in `BreakChars` (default whitespace and hyphen) and inserts then the string `BreakStr` (default the lineending character for the current OS).

Portions of text that are between single or double quotes will be considered single words and the text will not be broken between the quotes.

See also: `StringReplace` ([1755](#))

77.16 TRawbyteSearchRec

```
TRawbyteSearchRec = record
public
    Time : LongInt;
    Size : Int64
;
    Attr : LongInt;
    Name : RawByteString;
    ExcludeAttr : LongInt
;
    FindHandle : Pointer;
    Mode : TMode;
private
    function GetTimeStamp
    : TDateTime;
public
    property TimeStamp : TDateTime;
end
```

`TRawbyteSearchRec` is a search handle description record using single-byte strings. It is initialized by a call to `FindFirst` ([1705](#)) and can be used to do subsequent calls to `FindNext` ([1707](#)). It contains the result of these function calls. It must be used to close the search sequence with a call to `FindClose` ([1705](#)).

Remark Not all fields of this record should be used. Some of the fields are for internal use only. (`PathOnly` for example, is only provided for Kylix compatibility)

Remark Note that for files with Unicode filenames this is a converted value from the Unicode filename. Depending on the codepage, this may or may not be a correct rendering of the correct Unicode filename.

77.16.1 Property overview

Page	Properties	Access	Description
1796	TimeStamp	r	

77.16.2 TRawbyteSearchRec.TimeStamp

Synopsis:

Declaration: `Property TimeStamp : TDateTime`

Visibility: `public`

Access: `Read`

Description: `TimeStamp` is the file timestamp (`Date`) in `TDateTime` format, as opposed to file system timestamp.

See also: `TRawbyteSearchRec.Date` ([1795](#))

77.17 TRawbyteSymLinkRec

```
TRawbyteSymLinkRec = record
public
    TargetName : RawByteString;
    Size : Int64;
    Attr : LongInt;
    Mode : TMode;
private
    function
        GetTimeStamp : TDateTime;
public
    property TimeStamp : TDateTime
    ;
end
```

`TSymLinkRec` contains information about the target of a symlink. It is used in `FileGetSymLinkTarget` ([1699](#)) to return information. The following fields are present:

TargetName Target file filename in single-byte string

Size Target file size

Attr Target file attributes

Mode `#ShortDescr:TRawbyteSymLinkRec.Mode`

TimeStamp Target file timestamp

77.17.1 Property overview

Page	Properties	Access	Description
1796	<code>TimeStamp</code>	<code>r</code>	Target file timestamp

77.17.2 TRawbyteSymLinkRec.TimeStamp

Synopsis: Target file timestamp

Declaration: `Property TimeStamp : TDateTime`

Visibility: `public`

Access: `Read`

77.18 TUnicodeSearchRec

```
TUnicodeSearchRec = record
public
    Time : LongInt;
    Size : Int64
    ;
    Attr : LongInt;
    Name : UnicodeString;
    ExcludeAttr : LongInt
    ;
    FindHandle : Pointer;
    Mode : TMode;
private
    function GetTimeStamp
        : TDateTime;
public
    property TimeStamp : TDateTime;
end
```

TRawbyteSearchRec is a search handle description record using multi-byte strings. It is initialized by a call to FindFirst (1705) and can be used to do subsequent calls to FindNext (1707). It contains the result of these function calls. It must be used to close the search sequence with a call to FindClose (1705).

Remark Not all fields of this record should be used. Some of the fields are for internal use only. (PathOnly for example, is only provided for Kylix compatibility)

77.18.1 Property overview

Page	Properties	Access	Description
1797	TimeStamp	r	Time stamp as datetime

77.18.2 TUnicodeSearchRec.TimeStamp

Synopsis: Time stamp as datetime

Declaration: Property TimeStamp : TDateTime

Visibility: public

Access: Read

Description: TimeStamp is the file timestamp (Date) in TDateTime format, as opposed to file system timestamp.

See also: TRawbyteSearchRec.Date ([1795](#))

77.19 TUnicodeSymLinkRec

```
TUnicodeSymLinkRec = record
public
    TargetName : UnicodeString;
```

```

    Attr : LongInt;
    Size : Int64;
    Mode : TMode;
private
    function
        GetTimeStamp : TDateTime;
public
    property TimeStamp : TDateTime
        ;
end

```

TUnicodeSymLinkRec contains information about the target of a symlink. It is used in FileGetSymLinkTarget (1699) to return information. The following fields are present:

TargetName Target file filename in single-byte string

Size Target file size

Attr Target file attributes

Mode #ShortDescr:TRawbyteSymLinkRec.Mode

TimeStamp Target file timestamp

77.19.1 Property overview

Page	Properties	Access	Description
1798	TimeStamp	r	Target file timestamp

77.19.2 TUnicodeSymLinkRec.TimeStamp

Synopsis: Target file timestamp

Declaration: Property TimeStamp : TDateTime

Visibility: public

Access: Read

77.20 EAbort

77.20.1 Description

Abort is raised by the Abort (1648) procedure. It is not displayed in GUI applications, and serves only to immediately abort the current procedure, and return control to the main program loop.

See also: Abort ([1648](#))

77.21 EAbstractError

77.21.1 Description

EAbstractError is raised when an abstract error occurs, i.e. when an unimplemented abstract method is called.

77.22 EAccessViolation

77.22.1 Description

`EAccessViolation` is raised when the OS reports an Access Violation, i.e. when invalid memory is accessed.

See also: `EObjectCheck` ([1804](#))

77.23 EArgumentException

77.23.1 Description

`EArgumentException` is raised by many character conversion/handling routines to indicate an erroneous argument was passed to the function (usually indicating an invalid codepoint in a Unicode string).

See also: `EArgumentOutOfRangeException` ([1799](#))

77.24 EArgumentNilException

77.24.1 Description

`EArgumentNilException` is an exception raised when an argument is `Nil` when it should not be `Nil`.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1808](#))

77.25 EArgumentOutOfRangeException

77.25.1 Description

`EArgumentOutOfRangeException` is raised by many character conversion/handling routines to indicate an erroneous argument was passed to the function (indicating an invalid character index in a Unicode string).

See also: `EArgumentException` ([1799](#))

77.26 EAssertionFailed

77.26.1 Description

`EAssertionFailed` is raised when an application that is compiled with assertions, encounters an invalid assertion.

77.27 EBusError

77.27.1 Description

`EBusError` is raised in case of a bus error.

77.28 EControlC

77.28.1 Description

`EControlC` is raised when the user has pressed CTRL-C in a console application.

77.29 EConvertError

77.29.1 Description

`EConvertError` is raised by the various conversion routines in the `SysUtils` unit. The message will contain more specific error information.

77.30 EDirectoryNotFoundException

77.30.1 Description

`EDirectoryNotFoundException` is an exception raised when a directory is referenced that does not exist.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1808](#)), `EFileNotFoundException` ([1801](#)), `EPathNotFoundException` ([1805](#)), `EPathTooLongException` ([1806](#))

77.31 EDivByZero

77.31.1 Description

`EDivByZero` is used when the operating system or CPU signals a division by zero error.

77.32 EEncodingError

77.32.1 Description

`EEncodingError` is the exception classed used by the `TEncoding` class to indicate errors.

See also: `TEncoding` ([1838](#))

77.33 EExternal

77.33.1 Description

`EExternal` is the base exception for all external exceptions, as reported by the CPU or operating system, as opposed to internal exceptions, which are raised by the program itself. The `SysUtils` unit converts all operating system errors to descendents of `EExternal`.

See also: `EIntError` ([1802](#)), `EExternal` ([1801](#)), `EMathError` ([1803](#)), `EExternalException` ([1801](#)), `EAccessViolation` ([1799](#)), `EPrivilege` ([1806](#)), `EStackOverflow` ([1807](#)), `EControlC` ([1800](#))

77.34 EExternalException

77.34.1 Description

`EExternalException` is raised when an external routine raises an exception.

See also: `EExternal` ([1801](#))

77.35 EFileNotFoundException

77.35.1 Description

`EFileNotFoundException` is an exception raised when a file is referenced that does not exist. This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1808](#)), `EPathNotFoundException` ([1805](#)), `EDirectoryNotFoundException` ([1800](#)), `EPathTooLongException` ([1806](#))

77.36 EFormatError

77.36.1 Description

`EFormatError` is raised in case of an error in one of the various `Format` ([1714](#)) functions.

See also: `Format` ([1714](#))

77.37 EHeapMemoryError

77.37.1 Description

`EHeapMemoryError` is raised when an error occurs in heap (dynamically allocated) memory.

See also: `EHeapException` ([1630](#)), `EOutOfMemory` ([1805](#)), `EInvalidPointer` ([1803](#))

77.37.2 Method overview

Page	Method	Description
1802	<code>FreeInstance</code>	Free the exception instance

77.37.3 EHeapMemoryError.FreeInstance

Synopsis: Free the exception instance

Declaration: `procedure FreeInstance; Override`

Visibility: `public`

Description: `FreeInstance` checks whether the exception instance may be freed prior to calling the inherited `FreeInstance`. The exception is only freed in case of normal program shutdown, if a heap error occurred, the exception instance is not freed.

77.38 EInOutError

77.38.1 Description

`EInOutError` is raised when a IO routine of Free Pascal returns an error. The error is converted to an `EInOutError` only if the input/output checking feature of FPC is turned on. The error code of the input/output operation is returned in `ErrorCode` (??).

See also: `EInOutError.ErrorCode` (??)

77.39 EIntError

77.39.1 Description

`EIntError` is used when the operating system or CPU signals an integer operation error, e.g., an overflow.

77.40 EIntfCastError

77.40.1 Description

`EIntfCastError` is raised when an invalid interface cast is encountered.

See also: `EInvalidCast` ([1802](#))

77.41 EIntOverflow

77.41.1 Description

`EIntOverflow` is used when the operating system or CPU signals a integer overflow error.

See also: `EIntError` ([1802](#)), `EDivByZero` ([1800](#)), `ERangeError` ([1806](#))

77.42 EInvalidCast

77.42.1 Description

`EInvalidCast` is raised when an invalid typecast error (using the `as` operator) is encountered.

See also: `EIntfCastError` ([1802](#))

77.43 EInvalidContainer

77.43.1 Description

EInvalidContainer is not yet used by Free Pascal, and is provided for Delphi compatibility only.

77.44 EInvalidInsert

77.44.1 Description

EInvalidInsert is not yet used by Free Pascal, and is provided for Delphi compatibility only.

77.45 EInvalidOp

77.45.1 Description

EInvalidOp is raised when an invalid operation is encountered.

77.46 EInvalidOpException

77.46.1 Description

EInvalidOpException is raised when an invalid operation is attempted.

See also: Exception ([1808](#))

77.47 EInvalidPointer

77.47.1 Description

EInvalidPointer is raised when an invalid heap pointer is used.

See also: EHeapException ([1630](#)), EHeapMemoryError ([1801](#)), EOutOfMemory ([1805](#))

77.48 EMathError

77.48.1 Description

EMathError is used when the operating system or CPU signals a floating point overflow error.

See also: EIntError ([1802](#)), EIntOverflow ([1802](#)), EDivByZero ([1800](#)), ERangeError ([1806](#))

77.49 ENoConstructException

77.49.1 Description

ENoConstructException is the exception raised when an instance of type TCharacter is being created. The TCharacter class only contains static methods, no instances of this class should

be instantiated.

77.50 ENoDynLibsSupport

77.50.1 Description

`ENoDynLibsSupport` is raised when no dynamic library support is detected and a dynamic library loading operation is attempted.

See also: `EThreadError` ([1807](#)), `Exception` ([1808](#))

77.51 ENoThreadSupport

77.51.1 Description

`ENoThreadSupport` is raised when some thread routines are invoked, and thread support was not enabled when the program was compiled.

77.52 ENotImplemented

77.52.1 Description

`ENotImplemented` can be used to raise an exception when a particular call had been defined, but was not implemented.

77.53 ENotSupportedException

77.53.1 Description

`ENotSupportedException` is an exception raised when a function or procedure is not supported for a certain platform.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1808](#))

77.54 ENoWideStringSupport

77.54.1 Description

`ENoWideStringSupport` is the exception raised when a run-time 233 occurs, i.e. when widestring routines are called and the application does not contain widestring support.

77.55 EObjectCheck

77.55.1 Description

`EObjectCheck` is raised when the `-CR` (check object references) command-line option or `{ $OBJECTCHECKS ON }` directive is in effect and a `Nil` reference to an object or class was encountered.

See also: [EAccessViolation \(1799\)](#)

77.56 EOSError

77.56.1 Description

`EOSError` is raised when some Operating System call fails. The `ErrorCode` (??) property contains the operating system error code.

See also: `EOSError.ErrorCode` (??)

77.57 EOutOfMemory

77.57.1 Description

`EOutOfMemory` occurs when memory can no longer be allocated on the heap. An instance of `EOutOfMemory` is allocated on the heap at program startup, so it is available when needed.

See also: [EHeapException \(1630\)](#), [EHeapMemoryError \(1801\)](#), [EInvalidPointer \(1803\)](#)

77.58 EOverflow

77.58.1 Description

`EOverflow` occurs when a float operation overflows. (i.e. result is too big to represent).

See also: [EIntError \(1802\)](#), [EIntOverflow \(1802\)](#), [EDivByZero \(1800\)](#), [ERangeError \(1806\)](#), [EUnderFlow \(1807\)](#)

77.59 EPackageError

77.59.1 Description

`EPackageError` is not yet used by Free Pascal, and is provided for Delphi compatibility only.

77.60 EPathNotFoundException

77.60.1 Description

`EPathNotFoundException` is an exception raised when a path is referenced that does not exist. This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: [Exception \(1808\)](#), [EFileNotFoundException \(1801\)](#), [EDirectoryNotFoundException \(1800\)](#), [EPathTooLongException \(1806\)](#)

77.61 EPathTooLongException

77.61.1 Description

`EPathTooLongException` is an exception raised when a pathname argument is longer than the allowed pathname length for files.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1808](#)), `EFileNotFoundException` ([1801](#)), `EDirectoryNotFoundException` ([1800](#)), `EPathNotFoundException` ([1805](#))

77.62 EPrivilege

77.62.1 Description

`EPrivilege` is raised when the OS reports that an invalid instruction was executed.

77.63 EProgrammerNotFound

77.63.1 Description

`EProgrammerNotFound` is a Delphi-compatibility exception. It is not used in FPC. Some replies on [stackoverflow](#) suggest it is an internal joke of the Delpi team.

77.64 EPropReadOnly

77.64.1 Description

`EPropReadOnly` is raised when an attempt is made to write to a read-only property.

77.65 EPropWriteOnly

77.65.1 Description

`EPropWriteOnly` is raised when an attempt is made to read from a write-only property.

See also: `EPropReadOnly` ([1806](#))

77.66 ERangeError

77.66.1 Description

`ERangeError` is raised by the Free Pascal runtime library if range checking is on, and a range check error occurs.

See also: `EIntError` ([1802](#)), `EDivByZero` ([1800](#)), `EIntOverflow` ([1802](#))

77.67 ESafecallException

77.67.1 Description

ESafecallException is not yet used by Free Pascal, and is provided for Delphi compatibility only.

77.68 ESigQuit

77.68.1 Description

ESigQuit is used when a QUIT signal is received and a run-time error 233 is converted to an exception.

See also: Exception ([1808](#))

77.69 EStackOverflow

77.69.1 Description

EStackOverflow occurs when the stack has grown too big (e.g. by infinite recursion).

77.70 EThreadError

77.71 EUnderflow

77.71.1 Description

EOverflow occurs when a float operation underflows (i.e. result is too small to represent).

See also: EIntError ([1802](#)), EIntOverflow ([1802](#)), EDivByZero ([1800](#)), ERangeError ([1806](#)), EOverflow ([1805](#))

77.72 EVariantError

77.72.1 Description

EVariantError is raised by the internal variant routines.

77.72.2 Method overview

Page	Method	Description
1807	CreateCode	Create an instance of EVariantError with a particular error code.

77.72.3 EVariantError.CreateCode

Synopsis: Create an instance of EVariantError with a particular error code.

Declaration: constructor CreateCode (Code: LongInt)

Visibility: default

Description: `CreateCode` calls the inherited constructor, and sets the `ErrCode` (??) property to `Code`.

See also: `ErrCode` (??)

77.73 Exception

77.73.1 Description

`Exception` is the base class for all exception handling routines in the RTL and FCL. While it is possible to raise an exception with any class descending from `TObject`, it is recommended to use `Exception` as the basis of exception class objects: the `Exception` class introduces properties to associate a message and a help context with the exception being raised. What is more, the `SysUtils` unit sets the necessary hooks to catch and display unhandled exceptions: in such cases, the message displayed to the end user, will be the message stored in the exception class.

See also: `ExceptObject` (1685), `ExceptAddr` (1684), `ExceptionErrorMessage` (1685), `ShowException` (1747), `Abort` (1648)

77.73.2 Method overview

Page	Method	Description
1808	<code>Create</code>	Constructs a new exception object with a given message.
1809	<code>CreateFmt</code>	Constructs a new exception object and formats a new message.
1810	<code>CreateFmtHelp</code>	Constructs a new exception object and sets the help context and formats the message
1809	<code>CreateHelp</code>	Constructs a new exception object and sets the help context.
1809	<code>CreateRes</code>	Constructs a new exception object and gets the message from a resource.
1809	<code>CreateResFmt</code>	Constructs a new exception object and formats the message from a resource.
1810	<code>CreateResFmtHelp</code>	Constructs a new exception object and sets the help context and formats the message from a resource
1810	<code>CreateResHelp</code>	Constructs a new exception object and sets the help context and gets the message from a resource
1810	<code>ToString</code>	Nicely formatted version of the exception message

77.73.3 Property overview

Page	Properties	Access	Description
1811	<code>HelpContext</code>	rw	Help context associated with the exception.
1811	<code>Message</code>	rw	Message associated with the exception.

77.73.4 Exception.Create

Synopsis: Constructs a new exception object with a given message.

Declaration: `constructor Create(const msg: string)`

Visibility: public

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.CreateFmt` (1809), `Exception.Message` (1811)

77.73.5 Exception.CreateFmt

Synopsis: Constructs a new exception object and formats a new message.

Declaration: `constructor CreateFmt(const msg: string; const args: Array of const)`

Visibility: public

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` (1808), `Exception.Message` (1811), `Format` (1714)

77.73.6 Exception.CreateRes

Synopsis: Constructs a new exception object and gets the message from a resource.

Declaration: `constructor CreateRes(ResString: PString)`

Visibility: public

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` (1808), `Exception.CreateFmt` (1809), `Exception.CreateResFmt` (1809), `Exception.Message` (1811)

77.73.7 Exception.CreateResFmt

Synopsis: Constructs a new exception object and formats the message from a resource.

Declaration: `constructor CreateResFmt(ResString: PString; const Args: Array of const)`

Visibility: public

Description: `CreateResFmt` does the same as `CreateFmt` (1809), but fetches the message from the resource string `ResString`.

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` (1808), `Exception.CreateFmt` (1809), `Exception.CreateRes` (1809), `Exception.Message` (1811)

77.73.8 Exception.CreateHelp

Synopsis: Constructs a new exception object and sets the help context.

Declaration: `constructor CreateHelp(const Msg: string; AHelpContext: LongInt)`

Visibility: public

Description: `CreateHelp` does the same as the `Create` (1808) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1811) property.

See also: `Exception.Create` (1808)

77.73.9 Exception.CreateFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message

Declaration: constructor `CreateFmtHelp(const Msg: string;
const Args: Array of const;
AHelpContext: LongInt)`

Visibility: public

Description: `CreateFmtHelp` does the same as the `CreateFmt` (1809) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1811) property.

See also: `Exception.CreateFmt` (1809)

77.73.10 Exception.CreateResHelp

Synopsis: Constructs a new exception object and sets the help context and gets the message from a resource

Declaration: constructor `CreateResHelp(ResString: PString; AHelpContext: LongInt)`

Visibility: public

Description: `CreateResHelp` does the same as the `CreateRes` (1809) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1811) property.

See also: `Exception.CreateRes` (1809)

77.73.11 Exception.CreateResFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message from a resource

Declaration: constructor `CreateResFmtHelp(ResString: PString;
const Args: Array of const;
AHelpContext: LongInt)`

Visibility: public

Description: `CreateResFmtHelp` does the same as the `CreateResFmt` (1809) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1811) property.

See also: `Exception.CreateResFmt` (1809)

77.73.12 Exception.ToString

Synopsis: Nicely formatted version of the exception message

Declaration: function `ToString` : string; Override

Visibility: public

Description: `ToString` overrides the `ToString` method to return a concatenation of classname and `Exception.Message` (1811).

See also: `Exception.Message` (1811)

77.73.13 Exception.HelpContext

Synopsis: Help context associated with the exception.

Declaration: `Property HelpContext : LongInt`

Visibility: public

Access: Read,Write

Description: `HelpContext` is the help context associated with the exception, and can be used to provide context-sensitive help when the exception error message is displayed. It should be set in the exception constructor.

See also: `Exception.CreateHelp` ([1809](#)), `Exception.Message` ([1811](#))

77.73.14 Exception.Message

Synopsis: Message associated with the exception.

Declaration: `Property Message : string`

Visibility: public

Access: Read,Write

Description: `Message` provides additional information about the exception. It is shown to the user in e.g. the `ShowException` ([1747](#)) routine, and should be set in the constructor when the exception is raised.

See also: `Exception.Create` ([1808](#)), `Exception.HelpContext` ([1811](#))

77.74 EZeroDivide

77.74.1 Description

`EZeroDivide` occurs when a float division by zero occurs.

See also: `EIntError` ([1802](#)), `EIntOverflow` ([1802](#)), `EDivByZero` ([1800](#)), `ERangeError` ([1806](#))

77.75 IReadWriteSync

77.75.1 Description

`IReadWriteSync` is an interface for synchronizing read/write operations. Writers are always guaranteed to have exclusive access: readers may or may not have simultaneous access, depending on the implementation.

77.75.2 Method overview

Page	Method	Description
1812	<code>BeginRead</code>	Start a read operation.
1812	<code>BeginWrite</code>	Start a write operation.
1812	<code>EndRead</code>	End a read operation
1812	<code>EndWrite</code>	End a write operation.

77.75.3 IReadWriteSync.BeginRead

Synopsis: Start a read operation.

Declaration: `procedure BeginRead`

Visibility: `default`

Description: `BeginRead` indicates that a read operation is about to be started. If a write operation is in progress, then the call will block until the write operation finished. Depending on the implementation the call may also block if another read operation is in progress.

After `BeginRead`, any write operation started with `BeginWrite` (1812) will block until `EndRead` (1812) is called.

See also: `IReadWriteSync.EndRead` (1812), `IReadWriteSync.BeginWrite` (1812), `IReadWriteSync.EndWrite` (1812)

77.75.4 IReadWriteSync.EndRead

Synopsis: End a read operation

Declaration: `procedure EndRead`

Visibility: `default`

Description: `EndRead` signals the end of a read operation. If there was any blocked write operation, that will be unblocked by a call to `EndRead`.

See also: `IReadWriteSync.BeginRead` (1812), `IReadWriteSync.BeginWrite` (1812), `IReadWriteSync.EndWrite` (1812)

77.75.5 IReadWriteSync.BeginWrite

Synopsis: Start a write operation.

Declaration: `function BeginWrite : Boolean`

Visibility: `default`

Description: `BeginWrite` signals the begin of a write operation. This call will block if any other read or write operation is currently in progress. It will resume only after all other read or write operations have finished.

See also: `IReadWriteSync.EndRead` (1812), `IReadWriteSync.EndWrite` (1812), `IReadWriteSync.BeginRead` (1812)

77.75.6 IReadWriteSync.EndWrite

Synopsis: End a write operation.

Declaration: `procedure EndWrite`

Visibility: `default`

Description: `EndWrite` signals the end of a write operation. After the call to `EndWrite` any other read or write operations can start.

See also: `IReadWriteSync.EndRead` (1812), `IReadWriteSync.EndWrite` (1812), `IReadWriteSync.BeginRead` (1812)

77.76 TAnsiStringBuilder

77.76.1 Description

`TAnsiStringBuilder` is a class to construct an ansistring out of other strings or characters. It's methods can be used instead of constructing the string manually using the normal `+` or `concat` operators. If used properly (e.g. by setting a sufficiently large `Capacity` (1819)), will result in faster operation. It offers various methods to append to the string.

To create a unicode string, use the `TUnicodeStringBuilder` (1918) class instead.

See also: `TUnicodeStringBuilder` (1918)

77.76.2 Method overview

Page	Method	Description
1814	<code>Append</code>	Append data in string form to the buffer
1815	<code>AppendFormat</code>	Append the result of a <code>Format</code>
1815	<code>AppendLine</code>	Append a string followed by a newline
1815	<code>Clear</code>	Clear the string being built
1815	<code>CopyTo</code>	Copy string bytes to an array
1813	<code>Create</code>	Create a new <code>TAnsiStringBuilder</code> instance.
1816	<code>EnsureCapacity</code>	Set the capacity if needed
1816	<code>Equals</code>	Check if 2 stringbuilders have the same content string
1816	<code>Insert</code>	Insert data in string form into the buffer at a given position
1817	<code>Remove</code>	Remove data from the string
1817	<code>Replace</code>	Replace a range of characters.
1818	<code>ToString</code>	Return the string buffer as an <code>AnsiString</code>

77.76.3 Property overview

Page	Properties	Access	Description
1819	<code>Capacity</code>	rw	Current capacity of the string buffer
1818	<code>Chars</code>	rw	Indexed access to the characters in the string
1819	<code>Length</code>	rw	Current length of the string buffer
1819	<code>MaxCapacity</code>	r	Maximum capacity of the string buffer

77.76.4 TAnsiStringBuilder.Create

Synopsis: Create a new `TAnsiStringBuilder` instance.

Declaration: constructor `Create`

```

constructor Create(aCapacity: Integer)
constructor Create(const AValue: AnsiString)
constructor Create(aCapacity: Integer; aMaxCapacity: Integer)
constructor Create(const AValue: AnsiString; aCapacity: Integer)
constructor Create(const AValue: AnsiString; StartIndex: Integer;
                  aLength: Integer; aCapacity: Integer)
```

Visibility: public

Description: `Create` creates an empty `TAnsiStringBuilder` instance. It can optionally set the initial capacity to `aCapacity` and the maximum capacity to `aMaxCapacity` and can also initialize the

string buffer with characters from aValue: aLength characters starting at StartIndex (1-based) will be copied to the string buffer. If aLength and StartIndex are omitted, then all characters are copied.

See also: Capacity (1819), MaxCapacity (1819)

77.76.5 TAnsiStringBuilder.Append

Synopsis: Append data in string form to the buffer

Declaration:

```
function Append(const AValue: Boolean) : TAnsiStringBuilder
function Append(const AValue: Byte) : TAnsiStringBuilder
function Append(const AValue: AnsiChar) : TAnsiStringBuilder
function Append(const AValue: Currency) : TAnsiStringBuilder
function Append(const AValue: Double) : TAnsiStringBuilder
function Append(const AValue: SmallInt) : TAnsiStringBuilder
function Append(const AValue: LongInt) : TAnsiStringBuilder
function Append(const AValue: Int64) : TAnsiStringBuilder
function Append(const AValue: TObject) : TAnsiStringBuilder
function Append(const AValue: ShortInt) : TAnsiStringBuilder
function Append(const AValue: Single) : TAnsiStringBuilder
function Append(const AValue: UInt64) : TAnsiStringBuilder
function Append(const AValue: Array of AnsiChar) : TAnsiStringBuilder
function Append(const AValue: Word) : TAnsiStringBuilder
function Append(const AValue: Cardinal) : TAnsiStringBuilder
function Append(const AValue: PAnsiChar) : TAnsiStringBuilder
function Append(const AValue: RawByteString) : TAnsiStringBuilder
function Append(const AValue: AnsiChar; RepeatCount: Integer)
    : TAnsiStringBuilder
function Append(const AValue: Array of AnsiChar; StartIndex: Integer;
    SBCharCount: Integer) : TAnsiStringBuilder
function Append(const AValue: AnsiString; StartIndex: Integer;
    Count: Integer) : TAnsiStringBuilder
function Append(const Fmt: AnsiString; const Args: Array of const)
    : TAnsiStringBuilder
```

Visibility: public

Description: Append in its various overloaded forms will append the aValue argument to the buffer, after converting it to a string value if necessary:

- For integer values the various IntToStr (1736) functions will be used.
- For TObject (1615) the TObject.ToString (1615) is used.
- The repeatCount argument will repeat the character as many times as instructed using StringOfChar (1615).
- If the StartIndex and SBCharCount are specified, then SBCharCount characters are copied starting from position StartIndex.

An overloaded version exists with the same arguments as AppendFormat (1815).

See also: StringOfChar (1615), AppendFormat (1815), AppendLine (1815), Insert (1816), Remove (1817)

77.76.6 TAnsiStringBuilder.AppendFormat

Synopsis: Append the result of a `Format`

Declaration: `function AppendFormat(const Fmt: AnsiString; const Args: Array of const)
: TAnsiStringBuilder`

Visibility: public

Description: `AppendFormat` calls `Format` (1714) with `fmt` and `Args` and calls `append` (1814) with the resulting string.

Errors: the call to `Format` may result in an exception if the format parameters do not match the passed arguments.

See also: `Append` (1814), `Insert` (1816), `Remove` (1817), `Format` (1714)

77.76.7 TAnsiStringBuilder.AppendLine

Synopsis: Append a string followed by a newline

Declaration: `function AppendLine : TAnsiStringBuilder
function AppendLine(const AValue: RawByteString) : TAnsiStringBuilder`

Visibility: public

Description: `AppendLine` will append `aValue` (if it is specified) and appends the OS linebreak character (`sLineBreak` (1364)).

See also: `TAnsiStringBuilder.AppendFormat` (1815), `TAnsiStringBuilder.Append` (1814), `#rtl.system.sLineBreak` (1364), `Remove` (1817), `Insert` (1816)

77.76.8 TAnsiStringBuilder.Clear

Synopsis: Clear the string being built

Declaration: `procedure Clear`

Visibility: public

Description: `Clear` sets the length of the string to 0 and sets the `Capacity` (1819) to the default capacity (64 bytes).

See also: `Capacity` (1819), `Remove` (1817)

77.76.9 TAnsiStringBuilder.CopyTo

Synopsis: Copy string bytes to an array

Declaration: `procedure CopyTo(SourceIndex: Integer;
var Destination: Array of AnsiChar;
DestinationIndex: Integer; Count: Integer)`

Visibility: public

Description: `CopyTo` copies `aCount` characters from the string, starting at position `SourceIndex` (0-based) in the string to build, to the character array `Destination` at position `DestinationIndex`.

Errors: If the range of characters to copy falls outside the allowed range of characters in either source (available characters) or destination (available room for characters), then an `ERangeError` (1806) exception is raised.

See also: `ERangeError` (1806)

77.76.10 `TAnsiStringBuilder.EnsureCapacity`

Synopsis: Set the capacity if needed

Declaration: `function EnsureCapacity(aCapacity: Integer) : Integer`

Visibility: public

Description: `EnsureCapacity` checks that `aCapacity` is in the allowed range (less than `MaxCapacity` (1819)) and if the current capacity is less than `aCapacity`, increases the capacity to `aCapacity`.

Errors: If `aCapacity` is larger than `MaxCapacity` (1819) or negative, an `ERangeError` (1806) exception is raised.

See also: `MaxCapacity` (1819)

77.76.11 `TAnsiStringBuilder.Equals`

Synopsis: Check if 2 stringbuilders have the same content string

Declaration: `function Equals(StringBuilder: TAnsiStringBuilder) : Boolean`
`; Reintroduce`

Visibility: public

Description: `Equals` checks that the self instance has the same content as the `StringBuilder` instance. It checks the length and content (as bytes) of the strings.

See also: `TAnsiStringBuilder.Clear` (1815)

77.76.12 `TAnsiStringBuilder.Insert`

Synopsis: Insert data in string form into the buffer at a given position

Declaration: `function Insert(Index: Integer; const AValue: Boolean)`
`: TAnsiStringBuilder`
`function Insert(Index: Integer; const AValue: Byte) : TAnsiStringBuilder`
`function Insert(Index: Integer; const AValue: AnsiChar)`
`: TAnsiStringBuilder`
`function Insert(Index: Integer; const AValue: Currency)`
`: TAnsiStringBuilder`
`function Insert(Index: Integer; const AValue: Double)`
`: TAnsiStringBuilder`
`function Insert(Index: Integer; const AValue: SmallInt)`
`: TAnsiStringBuilder`
`function Insert(Index: Integer; const AValue: LongInt)`
`: TAnsiStringBuilder`
`function Insert(Index: Integer; const AValue: Array of AnsiChar)`
`: TAnsiStringBuilder`
`function Insert(Index: Integer; const AValue: Int64)`

Declaration:

```
function Replace(const OldChar: AnsiChar; const NewChar: AnsiChar)
    : TAnsiStringBuilder
function Replace(const OldChar: AnsiChar; const NewChar: AnsiChar;
    StartIndex: Integer; Count: Integer)
    : TAnsiStringBuilder
function Replace(const OldValue: RawByteString;
    const NewValue: RawByteString) : TAnsiStringBuilder
function Replace(const OldValue: RawByteString;
    const NewValue: RawByteString; StartIndex: Integer;
    Count: Integer) : TAnsiStringBuilder
```

Visibility: public

Description: Replace replaces occurrences of OldValue with the characters in NewValue. The search operation starts at position StartIndex (0-based, default 0) till position StartIndex+aCount is reached.

Errors: If StartIndex or StartIndex+aCount is out of range, an ERangeError (1806) exception is raised.

See also: AppendFormat (1815), AppendLine (1815), Append (1814), Insert (1816), Clear (1815), Remove (1817)

77.76.15 TAnsiStringBuilder.ToString

Synopsis: Return the string buffer as an AnsiString

Declaration:

```
function ToString : AnsiString; Override
function ToString(aStartIndex: Integer; aLength: Integer) : AnsiString
    ; Reintroduce
```

Visibility: public

Description: ToString returns the current content of the buffer as an AnsiString.

See also: Clear (1815), CopyTo (1815)

77.76.16 TAnsiStringBuilder.Chars

Synopsis: Indexed access to the characters in the string

Declaration: Property Chars[index: Integer]: AnsiChar; default

Visibility: public

Access: Read,Write

Description: Chars allows indexed access to the characters in the string using a zero-based Index. The characters can be read or written. The allowed range for Index is 0 to Length (1819)-1.

See also: Length (1819)

77.76.17 TAnsiStringBuilder.Length

Synopsis: Current length of the string buffer

Declaration: `Property &Length : Integer`

Visibility: public

Access: Read,Write

Description: `Length` can be used to get or set the current length (in characters) of the string buffer. When setting the length, the new length is checked whether it lies within the maximum capacity (`MaxCapacity` (1819)) for the string buffer: if not, an `ERangeError` (1806) exception is raised. The capacity of the buffer will be adjusted so the buffer has enough capacity to accomodate the new length.

See also: `MaxCapacity` (1819), `Capacity` (1819), `ERangeError` (1806)

77.76.18 TAnsiStringBuilder.Capacity

Synopsis: Current capacity of the string buffer

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` can be used to get or set the capacity of the string buffer (in characters). When setting the capacity, the new length is checked whether it lies within the maximum capacity (`MaxCapacity` (1819)) for the string buffer: if not, an `ERangeError` (1806) exception is raised.

See also: `MaxCapacity` (1819), `Length` (1819), `ERangeError` (1806)

77.76.19 TAnsiStringBuilder.MaxCapacity

Synopsis: Maximum capacity of the string buffer

Declaration: `Property MaxCapacity : Integer`

Visibility: public

Access: Read

Description: `MaxCapacity` returns the maximum capacity of the string buffer (in characters). It is set when the stringbuilder is created, in the constructor of the builder. The `Capacity` (1819) (and consequently, the `Length` (1819)) will never be allowed to exceed `MaxCapacity`.

See also: `Capacity` (1819), `Length` (1819), `ERangeError` (1806)

77.77 TBigEndianUnicodeEncoding**77.77.1 Description**

`TBigEndianUnicodeEncoding` is the encoding class used to represent the UTF-16 big-endian encoding.

See also: `TBigEndianUnicodeEncoding` (1819), `TUTF7Encoding` (1925), `TMBCSEncoding` (1862), `TBigEndianUnicodeEncoding` (1819)

77.77.2 Method overview

Page	Method	Description
1820	Clone	Clone a TBigEndianUnicodeEncoding instance
1820	GetPreamble	Return BOM marker bytes

77.77.3 TBigEndianUnicodeEncoding.Clone

Synopsis: Clone a TBigEndianUnicodeEncoding instance

Declaration: `function Clone : TEncoding; Override`

Visibility: `public`

Description: `Clone` overrides `TEncoding.Clone` ([1838](#)) to provide a clone of the `TBigEndianUnicodeEncoding` instance.

See also: `TEncoding.Clone` ([1838](#))

77.77.4 TBigEndianUnicodeEncoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: `public`

Description: `GetPreamble` overrides `TEncoding.GetPreamble` ([1841](#)) to return the 2 UTF-16 BOM Marker bytes (\$FF,\$FE).

See also: `TEncoding.GetPreamble` ([1841](#))

77.78 TBooleanHelper**77.78.1 Description**

`TBooleanHelper` is a helper type for the `Boolean` type. It contains mostly conversion routines to and from other types.

See also: `TStringHelper` ([1895](#)), `TShortIntHelper` ([1879](#)), `TSmallIntHelper` ([1891](#)), `TWordHelper` ([1929](#)), `TCardinalHelper` ([1828](#)), `TIntegerHelper` ([1856](#)), `TInt64Helper` ([1852](#)), `TQWordHelper` ([1875](#)), `TNativeIntHelper` ([1867](#)), `TByteHelper` ([1824](#)), `TByteBoolHelper` ([1822](#)), `TWordBoolHelper` ([1927](#)), `TLongBoolHelper` ([1861](#))

77.78.2 Method overview

Page	Method	Description
1821	Parse	Convert string value to boolean value.
1821	Size	Return the size (in bytes) of the
1822	ToInteger	Convert to an integer value
1821	ToString	Convert a boolean value to string.
1821	TryToParse	Try to convert a string to a boolean value

77.78.3 TBooleanHelper.Parse

Synopsis: Convert string value to boolean value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: public

Description: `Parse` attempts to convert the string `S` to a boolean value. It uses the `StrToBool` (1763) function to perform the conversion.

Errors: If `S` does not contain a valid string representation, then an `EConvertError` (1800) exception is raised.

See also: `TBooleanHelper.TryParse` (1821), `TBooleanHelper.ToString` (1821), `TBooleanHelper.ToInteger` (1822)

77.78.4 TBooleanHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` returns the size (in bytes) of the boolean value. This is equivalent to `SizeOf(Boolean)`.

See also: `SizeOf` (1547)

77.78.5 TBooleanHelper.ToString

Synopsis: Convert a boolean value to string.

Declaration: `class function ToString(const AValue: Boolean;
 UseBoolStrs: TUseBoolStrs) : string; Overload
 ; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: public

Description: `ToString` will, in the class method version, convert the `AValue` boolean to a string representation. In the function method version the boolean value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the boolean strings `BoolStrs` (1615). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` (1665) function.

See also: `BoolStrs` (1615), `BoolToStr` (1665)

77.78.6 TBooleanHelper.TryParse

Synopsis: Try to convert a string to a boolean value

Declaration: `class function TryParse(const S: string; out AValue: Boolean)
 : Boolean; Static`

Visibility: public

Description: `TryParse` will attempt to convert the string `S` to a boolean value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TBooleanHelper.Parse` (1821), `TBooleanHelper.ToString` (1821)

77.78.7 TBooleanHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the boolean value, typecasted to `Integer`.

See also: `TBooleanHelper.ToString` ([1821](#))

77.79 TByteBoolHelper

77.79.1 Description

`TByteBoolHelper` is a helper type for the `ByteBool` type. It contains mostly conversion routines to and from other types.

See also: `TStringHelper` ([1895](#)), `TShortIntHelper` ([1879](#)), `TSmallIntHelper` ([1891](#)), `TWordHelper` ([1929](#)), `TCardinalHelper` ([1828](#)), `TIntegerHelper` ([1856](#)), `TInt64Helper` ([1852](#)), `TQWordHelper` ([1875](#)), `TNativeIntHelper` ([1867](#)), `TByteHelper` ([1824](#)), `TByteBoolHelper` ([1822](#)), `TWordBoolHelper` ([1927](#)), `TLongBoolHelper` ([1861](#))

77.79.2 Method overview

Page	Method	Description
1822	<code>Parse</code>	Convert string value to <code>ByteBool</code> value.
1822	<code>Size</code>	Return the size (in bytes) of the
1823	<code>ToInteger</code>	Convert to an integer value
1823	<code>ToString</code>	Convert a <code>ByteBool</code> value to string.
1823	<code>TryToParse</code>	Try to convert a string to a <code>ByteBool</code> value

77.79.3 TByteBoolHelper.Parse

Synopsis: Convert string value to `ByteBool` value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: public

Description: `Parse` attempts to convert the string `S` to a `ByteBool` value. It uses the `StrToBool` ([1763](#)) function to perform the conversion.

Errors: If `S` does not contain a valid string representation, then an `EConvertError` ([1800](#)) exception is raised.

See also: `TByteBoolHelper.TryToParse` ([1823](#)), `TByteBoolHelper.ToString` ([1823](#)), `TByteBoolHelper.ToInteger` ([1823](#))

77.79.4 TByteBoolHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` returns the size (in bytes) of the `ByteBool` value. This is equivalent to `SizeOf (ByteBool)`.

See also: `SizeOf` ([1547](#))

77.79.5 TByteBoolHelper.ToString

Synopsis: Convert a `ByteBool` value to string.

Declaration:

```
class function ToString(const AValue: Boolean;
                        UseBoolStrs: TUseBoolStrs) : string; Overload
; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload
```

Visibility: public

Description: `ToString` will, in the class method version, convert the `AValue` `ByteBool` to a string representation. In the function method version the `ByteBool` value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the `ByteBool` strings `BoolStrs` ([1615](#)). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` ([1665](#)) function.

See also: `BoolStrs` ([1615](#)), `BoolToStr` ([1665](#))

77.79.6 TByteBoolHelper.TryParse

Synopsis: Try to convert a string to a `ByteBool` value

Declaration:

```
class function TryParse(const S: string; out AValue: Boolean)
                        : Boolean; Static
```

Visibility: public

Description: `TryParse` will attempt to convert the string `S` to a `ByteBool` value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TByteBoolHelper.Parse` ([1822](#)), `TByteBoolHelper.ToString` ([1823](#))

77.79.7 TByteBoolHelper.ToInteger

Synopsis: Convert to an integer value

Declaration:

```
function ToInteger : Integer
```

Visibility: public

Description: `ToInteger` will return the `ByteBool` value, typecasted to `Integer`.

See also: `TByteBoolHelper.ToString` ([1823](#))

77.80 TByteHelper

77.80.1 Description

TByteHelper contains some auxiliary routines for a byte-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: TStringHelper ([1895](#)), TShortIntHelper ([1879](#)), TSmallIntHelper ([1891](#)), TWordHelper ([1929](#)), TCardinalHelper ([1828](#)), TIntegerHelper ([1856](#)), TInt64Helper ([1852](#)), TQWordHelper ([1875](#)), TNativeIntHelper ([1867](#)), TNativeUIntHelper ([1871](#))

77.80.2 Method overview

Page	Method	Description
1827	ClearBit	Set bit to 0
1824	Parse	Convert from a string
1827	SetBit	Set bit to 1
1824	Size	Size, in bytes, of the byte value
1827	TestBit	Check bit
1826	ToBinString	Convert to a binary string representation
1825	ToBoolean	Convert to a boolean value
1825	ToDouble	Convert to a double-sized floating point value
1826	ToExtended	Convert to an extended-sized floating point value
1827	ToggleBit	Invert bit
1826	ToHexString	Convert to a hexadecimal string representation
1826	ToSingle	Convert to a single-sized floating point value
1825	ToString	Convert the value to string
1825	TryParse	Try to convert a string to a byte, report success or failure

77.80.3 TByteHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Byte; Static`

Visibility: public

Description: Parse will attempt to convert the string AString to a byte value. It uses the StrToInt ([1769](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid byte value, an EConvertError ([1800](#)) exception is raised.

See also: TByteHelper.ToString ([1825](#)), TByteHelper.TryParse ([1825](#)), StrToInt ([1769](#))

77.80.4 TByteHelper.Size

Synopsis: Size, in bytes, of the byte value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in bytes) of the byte value. This is equivalent to SizeOf(Byte).

Errors: None.

See also: SizeOf ([1547](#))

77.80.5 TByteHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Byte) : string; Overload; Static
function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the byte value itself is used. The `IntToStr` (1736) function is used to do the conversion.

See also: `TByteHelper.Parse` (1824), `IntToStr` (1736)

77.80.6 TByteHelper.TryParse

Synopsis: Try to convert a string to a byte, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Byte)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a byte, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the byte is returned in `AValue`.

It uses the `val` (1615) function to perform the conversion, so no localization is taken into account.

See also: `TByteHelper.Parse` (1824), `Val` (1570)

77.80.7 TByteHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the byte value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TByteHelper.ToSingle` (1826), `TByteHelper.ToDouble` (1825), `TByteHelper.ToExtended` (1826), `TByteHelper.ToString` (1825), `TByteHelper.ToHexString` (1826)

77.80.8 TByteHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the byte value to a double-sized floating point value.

See also: `TByteHelper.ToBoolean` (1825), `TByteHelper.ToExtended` (1826), `TByteHelper.ToSingle` (1826), `TByteHelper.ToString` (1825), `TByteHelper.ToHexString` (1826)

77.80.9 TByteHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the byte value to an extended-sized floating point value

See also: `TByteHelper.ToBoolean` (1825), `TByteHelper.ToSingle` (1826), `TByteHelper.ToDouble` (1825), `TByteHelper.ToString` (1825), `TByteHelper.ToHexString` (1826)

77.80.10 TByteHelper.ToBinString

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: public

Description: `ToBinString` converts the byte value to a binary string representation, showing all 8 bits.

See also: `TByteHelper.ToHexString` (1826), `TByteHelper.ToString` (1825)

77.80.11 TByteHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the byte value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TByteHelper.ToBoolean` (1825), `TByteHelper.ToSingle` (1826), `TByteHelper.ToDouble` (1825), `TByteHelper.ToString` (1825), `TByteHelper.ToExtended` (1826)

77.80.12 TByteHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the byte value to a single-sized floating point value.

See also: `TByteHelper.ToBoolean` (1825), `TByteHelper.ToDouble` (1825), `TByteHelper.ToExtended` (1826), `TByteHelper.ToString` (1825), `TByteHelper.ToHexString` (1826)

77.80.13 TByteHelper.SetBit

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TByteBitIndex) : Byte`

Visibility: public

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TByteHelper.ClearBit` (1827), `TByteHelper.ToggleBit` (1827), `TByteHelper.TestBit` (1827), `TByteHelper.HighestSetBitPos` (1824), `TByteHelper.LowestSetBitPos` (1824), `TByteHelper.SetBitsCount` (1824), `TByteHelper.Bits` (1824)

77.80.14 TByteHelper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TByteBitIndex) : Byte`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TByteHelper.SetBit` (1827), `TByteHelper.ToggleBit` (1827), `TByteHelper.TestBit` (1827), `TByteHelper.HighestSetBitPos` (1824), `TByteHelper.LowestSetBitPos` (1824), `TByteHelper.SetBitsCount` (1824), `TByteHelper.Bits` (1824)

77.80.15 TByteHelper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TByteBitIndex) : Byte`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TByteHelper.SetBit` (1827), `TByteHelper.ClearBit` (1827), `TByteHelper.TestBit` (1827), `TByteHelper.HighestSetBitPos` (1824), `TByteHelper.LowestSetBitPos` (1824), `TByteHelper.SetBitsCount` (1824), `TByteHelper.Bits` (1824)

77.80.16 TByteHelper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TByteBitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TByteHelper.SetBit` (1827), `TByteHelper.ClearBit` (1827), `TByteHelper.ToggleBit` (1827), `TByteHelper.HighestSetBitPos` (1824), `TByteHelper.LowestSetBitPos` (1824), `TByteHelper.SetBitsCount` (1824), `TByteHelper.Bits` (1824)

77.81 TCardinalHelper

77.81.1 Description

TCardinalHelper contains some auxiliary routines for a Cardinal-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: TStringHelper ([1895](#)), TShortIntHelper ([1879](#)), TSmallIntHelper ([1891](#)), TWordHelper ([1929](#)), TByteHelper ([1824](#)), TIntegerHelper ([1856](#)), TInt64Helper ([1852](#)), TQWordHelper ([1875](#)), TNativeIntHelper ([1867](#)), TNativeUIntHelper ([1871](#))

77.81.2 Method overview

Page	Method	Description
1831	ClearBit	Set bit to 0
1828	Parse	Convert from a string
1831	SetBit	Set bit to 1
1828	Size	Size, in bytes, of the Cardinal value
1831	TestBit	Check bit
1830	ToBinString	Convert to a binary string representation
1829	ToBoolean	Convert to a boolean value
1829	ToDouble	Convert to a double-sized floating point value
1830	ToExtended	Convert to an extended-sized floating point value
1831	ToggleBit	Invert bit
1830	ToHexString	Convert to a hexadecimal string representation
1830	ToSingle	Convert to a single-sized floating point value
1829	ToString	Convert the value to string
1829	TryParse	Try to convert a string to a Cardinal, report success or failure

77.81.3 TCardinalHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Cardinal; Static`

Visibility: public

Description: Parse will attempt to convert the string AString to a Cardinal value. It uses the StrToInt ([1769](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid Cardinal value, an EConvertError ([1800](#)) exception is raised.

See also: TCardinalHelper.ToString ([1829](#)), TCardinalHelper.TryParse ([1829](#)), StrToInt ([1769](#))

77.81.4 TCardinalHelper.Size

Synopsis: Size, in bytes, of the Cardinal value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in Cardinals) of the Cardinal value. This is equivalent to SizeOf (Cardinal).

Errors: None.

See also: SizeOf ([1547](#))

77.81.5 TCardinalHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Cardinal) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `Cardinal` value itself is used. The `IntToStr` ([1736](#)) function is used to do the conversion.

See also: `TCardinalHelper.Parse` ([1828](#)), `IntToStr` ([1736](#))

77.81.6 TCardinalHelper.TryParse

Synopsis: Try to convert a string to a Cardinal, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Cardinal)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Cardinal`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `Cardinal` is returned in `AValue`.

It uses the `val` ([1615](#)) function to perform the conversion, so no localization is taken into account.

See also: `TCardinalHelper.Parse` ([1828](#)), `Val` ([1570](#))

77.81.7 TCardinalHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `Cardinal` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TCardinalHelper.ToSingle` ([1830](#)), `TCardinalHelper.ToDouble` ([1829](#)), `TCardinalHelper.ToExtended` ([1830](#)), `TCardinalHelper.ToString` ([1829](#)), `TCardinalHelper.ToHexString` ([1830](#))

77.81.8 TCardinalHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Cardinal` value to a double-sized floating point value.

See also: `TCardinalHelper.ToBoolean` ([1829](#)), `TCardinalHelper.ToExtended` ([1830](#)), `TCardinalHelper.ToSingle` ([1830](#)), `TCardinalHelper.ToString` ([1829](#)), `TCardinalHelper.ToHexString` ([1830](#))

77.81.9 TCardinalHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the Cardinal value to an extended-sized floating point value.

See also: `TCardinalHelper.ToBoolean` (1829), `TCardinalHelper.ToSingle` (1830), `TCardinalHelper.ToDouble` (1829), `TCardinalHelper.ToString` (1829), `TCardinalHelper.ToHexString` (1830)

77.81.10 TCardinalHelper.ToBinString

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: public

Description: `ToBinString` converts the Cardinal value to a binary string representation, showing all 32 bits.

See also: `TCardinalHelper.ToHexString` (1830), `TCardinalHelper.ToString` (1829)

77.81.11 TCardinalHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the Cardinal value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TCardinalHelper.ToBoolean` (1829), `TCardinalHelper.ToSingle` (1830), `TCardinalHelper.ToDouble` (1829), `TCardinalHelper.ToString` (1829), `TCardinalHelper.ToExtended` (1830)

77.81.12 TCardinalHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the Cardinal value to a single-sized floating point value.

See also: `TCardinalHelper.ToBoolean` (1829), `TCardinalHelper.ToDouble` (1829), `TCardinalHelper.ToExtended` (1830), `TCardinalHelper.ToString` (1829), `TCardinalHelper.ToHexString` (1830)

77.81.13 TCardinalHelper.SetBit

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TCardinalBitIndex) : Cardinal`

Visibility: public

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TCardinalHelper.ClearBit` ([1831](#)), `TCardinalHelper.ToggleBit` ([1831](#)), `TCardinalHelper.TestBit` ([1831](#)), `TCardinalHelper.HighestSetBitPos` ([1828](#)), `TCardinalHelper.LowestSetBitPos` ([1828](#)), `TCardinalHelper.SetBitsCount` ([1828](#)), `TCardinalHelper.Bits` ([1828](#))

77.81.14 TCardinalHelper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TCardinalBitIndex) : Cardinal`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TCardinalHelper.SetBit` ([1831](#)), `TCardinalHelper.ToggleBit` ([1831](#)), `TCardinalHelper.TestBit` ([1831](#)), `TCardinalHelper.HighestSetBitPos` ([1828](#)), `TCardinalHelper.LowestSetBitPos` ([1828](#)), `TCardinalHelper.SetBitsCount` ([1828](#)), `TCardinalHelper.Bits` ([1828](#))

77.81.15 TCardinalHelper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TCardinalBitIndex) : Cardinal`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TCardinalHelper.SetBit` ([1831](#)), `TCardinalHelper.ToggleBit` ([1831](#)), `TCardinalHelper.TestBit` ([1831](#)), `TCardinalHelper.HighestSetBitPos` ([1828](#)), `TCardinalHelper.LowestSetBitPos` ([1828](#)), `TCardinalHelper.SetBitsCount` ([1828](#)), `TCardinalHelper.Bits` ([1828](#))

77.81.16 TCardinalHelper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TCardinalBitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TCardinalHelper.SetBit` ([1831](#)), `TCardinalHelper.ToggleBit` ([1831](#)), `TCardinalHelper.TestBit` ([1831](#)), `TCardinalHelper.HighestSetBitPos` ([1828](#)), `TCardinalHelper.LowestSetBitPos` ([1828](#)), `TCardinalHelper.SetBitsCount` ([1828](#)), `TCardinalHelper.Bits` ([1828](#))

77.82 TDoubleHelper

77.82.1 Description

`TDoubleHelper` is the helper type for the Double-sized floating point type. It contains some conversion methods, as well as access to the low-level structure of the floating-point representation of a Double.

: TDoubleHelper ([1832](#)), TExtendedHelper ([1844](#))

77.82.2 Method overview

Page	Method	Description
1835	BuildUp	Build a Double-sized floating point from its composing parts
1835	Exponent	Exponent of the floating-point value
1836	Fraction	Fraction of the floating-point value
1832	IsInfinity	Check whether a value is positive or negative infinity.
1833	IsNan	Check whether a value equals NaN.
1833	IsNegativeInfinity	Check whether a value is negative infinity.
1833	IsPositiveInfinity	Check whether a value is positive infinity.
1836	Mantissa	Mantissa of the floating-point
1833	Parse	Convert a string to a floating point value
1834	Size	Size (in bytes) of a Double-sized floating point value.
1836	SpecialType	Return the type of the Double-sized floating point value
1834	ToString	Convert a Double-sized floating point value to a string
1835	TryParse	Try to convert a string to a Double-sized floating point value.

77.82.3 Property overview

Page	Properties	Access	Description
1836	Bytes	rw	Indexed access to the individual bytes of the floating point value
1837	Exp	rw	The bit pattern of the exponent as stored in memory.
1837	Frac	rw	Bitpattern that makes up the fractional part.
1837	Sign	rw	Sign of the floating point value
1837	Words	rw	Indexed access to the words that make up the floating point value

77.82.4 TDoubleHelper.IsInfinity

- Check whether a value is positive or negative infinity.

```

class function IsInfinity(const AValue: Double) : Boolean; Overload
                                ; Static
function IsInfinity : Boolean; Overload

```

: public

IsInfinity checks whether a Double-sized floating point value represents a positive or negative infinity. If so, it returns **True**. When the class function version is used, the value can be specified using **AValue**. In the method version, the used value is (**Self**).

: TDoubleHelper.IsNan (1833), TDoubleHelper.IsPositiveInfinity (1833), TDoubleHelper.IsNegativeInfinity (1833)

77.82.5 TDoubleHelper.IsNan

Synopsis: Check whether a value equals NaN.

Declaration: `class function IsNan(const AValue: Double) : Boolean; Overload; Static
function IsNan : Boolean; Overload`

Visibility: public

Description: `IsNan` checks whether a Double-sized floating point value is NaN (Not a Number). If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsInfinity` (1832), `TDoubleHelper.IsPositiveInfinity` (1833), `TDoubleHelper.IsNegativeInfinity` (1833)

77.82.6 TDoubleHelper.IsNegativeInfinity

Synopsis: Check whether a value is negative infinity.

Declaration: `class function IsNegativeInfinity(const AValue: Double) : Boolean
; Overload; Static
function IsNegativeInfinity : Boolean; Overload`

Visibility: public

Description: `IsNegativeInfinity` checks whether a Double-sized floating point value represents a negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsNan` (1833), `TDoubleHelper.IsPositiveInfinity` (1833), `TDoubleHelper.IsInfinity` (1832)

77.82.7 TDoubleHelper.IsPositiveInfinity

Synopsis: Check whether a value is positive infinity.

Declaration: `class function IsPositiveInfinity(const AValue: Double) : Boolean
; Overload; Static
function IsPositiveInfinity : Boolean; Overload`

Visibility: public

Description: `IsPositiveInfinity` checks whether a Double-sized floating point value represents a positive infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsNan` (1833), `TDoubleHelper.IsNegativeInfinity` (1833), `TDoubleHelper.IsInfinity` (1832)

77.82.8 TDoubleHelper.Parse

Synopsis: Convert a string to a floating point value

Declaration: `class function Parse(const AString: string) : Double; Overload; Static
class function Parse(const AString: string;
const AFormatSettings: TFormatSettings) : Double
; Overload; Static`

Visibility: public

Description: Parse will try to convert AString to a Double-sized floating point value. It will take into account internationalization settings. (it uses FloatToStr).

Errors: If the string AString is not a valid floating-point value, a EConvertError (1800) exception is raised.

See also: FloatToStr (1708), TDoubleHelper.ToString (1834), TDoubleHelper.TryParse (1835)

77.82.9 TDoubleHelper.Size

Synopsis: Size (in bytes) of a Double-sized floating point value.

Declaration: class function Size : Integer; Static

Visibility: public

Description: Size is the size (in bytes) of a Double-sized floating point value. It is equivalent to calling SizeOf(Double).

See also: SizeOf (1547)

77.82.10 TDoubleHelper.ToString

Synopsis: Convert a Double-sized floating point value to a string

```
Declaration: class function ToString(const AValue: Double) : string; Overload
              ; Static
class function ToString(const AValue: Double;
                        const AFormat: TFloatFormat;
                        const APrecision: Integer;
                        const ADigits: Integer) : string; Overload
              ; Static
class function ToString(const AValue: Double;
                        const AFormat: TFloatFormat;
                        const APrecision: Integer;
                        const ADigits: Integer;
                        const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
class function ToString(const AValue: Double;
                        const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
function ToString(const AFormat: TFloatFormat;
                  const APrecision: Integer; const ADigits: Integer)
              : string; Overload
function ToString(const AFormat: TFloatFormat;
                  const APrecision: Integer; const ADigits: Integer;
                  const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString(const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString : string; Overload
```

Visibility: public

Description: `ToString` will convert `AValue` (or `Self` in the plain method version) to a string. Optionally `FormatSettings` can be specified, to be able to specify the decimal separator character to use.

Additionally, a precision `APrecision` and number of digits `ADigits` can be specified, in conjunction with a `AFormat` parameter to specify the form in which the floating-point value must be represented. (see `TFloatFormat` (1636) for an explanation of the various values). In this case, `FloatToStrF` (1709) is used to format the value. In the absence of these parameters, `FloatToStr` (1708) is called.

See also: `FloatToStr` (1708), `FloatToStrF` (1709), `TFloatFormat` (1636)

77.82.11 `TDoubleHelper.TryParse`

Synopsis: Try to convert a string to a Double-sized floating point value.

Declaration:

```
class function TryParse(const AString: string; out AValue: Double)
                        : Boolean; Overload; Static
class function TryParse(const AString: string; out AValue: Double;
                        const AFormatSettings: TFormatSettings) : Boolean
                        ; Overload; Static
```

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a Double-sized floating point value and reports `True` if the conversion was successful. In that case the parsed value is returned in `AValue`.

If the conversion failed, `False` is returned.

See also: `TDoubleHelper.Parse` (1833), `TDoubleHelper.ToString` (1834)

77.82.12 `TDoubleHelper.BuildUp`

Synopsis: Build a Double-sized floating point from its composing parts

Declaration:

```
procedure BuildUp(const ASignFlag: Boolean; const AMantissa: QWord;
                  const AExponent: Integer)
```

Visibility: public

Description: `BuildUp` will compose a Double-sized floating point value from the sign `ASignFlag`, mantissa `AMantissa` and exponent `AExponent`. It simply sets the `Sign` (1837), `Exp` (1837) and `Frac` (1837) properties in 1 call.

See also: `TDoubleHelper.Sign` (1837), `TDoubleHelper.Exp` (1837), `TDoubleHelper.Frac` (1837)

77.82.13 `TDoubleHelper.Exponent`

Synopsis: Exponent of the floating-point value

Declaration:

```
function Exponent : Integer
```

Visibility: public

Description: `Exponent` is the value X in the representation of the floating-point value in $m \times 2^X$, i.e. the exponent.

See also: `TDoubleHelper.Sign` (1837), `TDoubleHelper.Exp` (1837), `TDoubleHelper.Frac` (1837), `TDoubleHelper.Fraction` (1836), `TDoubleHelper.Mantissa` (1836)

77.82.14 TDoubleHelper.Fraction

Synopsis: Fraction of the floating-point value

Declaration: `function Fraction : Extended`

Visibility: public

Description: `Fraction` is the decimal part of the floating-point value.

See also: `TDoubleHelper.Sign` ([1837](#)), `TDoubleHelper.Exp` ([1837](#)), `TDoubleHelper.Exponent` ([1835](#)), `TDoubleHelper.Frac` ([1837](#)), `TDoubleHelper.Mantissa` ([1836](#))

77.82.15 TDoubleHelper.Mantissa

Synopsis: Mantissa of the floating-point

Declaration: `function Mantissa : QWord`

Visibility: public

Description: `Mantissa` is the value of the significand without the hidden bit. This means it the plain bit pattern as it is stored in memory.

See also: `TDoubleHelper.Sign` ([1837](#)), `TDoubleHelper.Exp` ([1837](#)), `TDoubleHelper.Exponent` ([1835](#)), `TDoubleHelper.Frac` ([1837](#)), `TDoubleHelper.Fraction` ([1836](#))

77.82.16 TDoubleHelper.SpecialType

Synopsis: Return the type of the Double-sized floating point value

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` checks whether the Double-sized floating point value equals one of several special values, and returns an enumerated value describing which value this is. See `TFloatSpecial` ([1615](#)) for an explanation of the possible values.

See also: `TFloatSpecial` ([1615](#))

77.82.17 TDoubleHelper.Bytes

Synopsis: Indexed access to the individual bytes of the floating point value

Declaration: `Property Bytes[AIndex: Cardinal]: Byte`

Visibility: public

Access: Read, Write

Description: `Bytes` can be used to get or set the various bytes that make up the Double-sized floating point value. The index runs from 0 to `Size-1`.

See also: `TDoubleHelper.Words` ([1837](#)), `TDoubleHelper.Size` ([1834](#))

77.82.18 TDoubleHelper.Words

Synopsis: Indexed access to the words that make up the floating point value

Declaration: `Property Words[AIndex: Cardinal]: Word`

Visibility: public

Access: Read,Write

Description: `Words` can be used to get or set the various bytes that make up the Double-sized floating point value. The index runs from 0 to $(\text{Size}-1) \div 2$.

See also: `TDoubleHelper.Bytes` ([1836](#)), `TDoubleHelper.Size` ([1834](#))

77.82.19 TDoubleHelper.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

Description: `Sign` returns `True` if the sign bit of the value is set (i.e. it is a negative value) or `False` if it is not set (i.e. it is a positive value).

See also: `TDoubleHelper.Bytes` ([1836](#)), `TDoubleHelper.Exp` ([1837](#)), `TDoubleHelper.Frac` ([1837](#)), `TDoubleHelper.Mantissa` ([1836](#)), `TDoubleHelper.Fraction` ([1836](#)), `TDoubleHelper.Exponent` ([1835](#))

77.82.20 TDoubleHelper.Exp

Synopsis: The bit pattern of the exponent as stored in memory.

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` is the internal representation of the `Exponent` ([1835](#)).

See also: `TDoubleHelper.Bytes` ([1836](#)), `TDoubleHelper.Sign` ([1837](#)), `TDoubleHelper.Frac` ([1837](#)), `TDoubleHelper.Mantissa` ([1836](#)), `TDoubleHelper.Fraction` ([1836](#)), `TDoubleHelper.Exponent` ([1835](#))

77.82.21 TDoubleHelper.Frac

Synopsis: Bitpattern that makes up the fractional part.

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: `Frac` is the bit pattern representing the fractional part (significand) including the preceding 1 (the hidden bit).

See also: `TDoubleHelper.Bytes` ([1836](#)), `TDoubleHelper.Sign` ([1837](#)), `TDoubleHelper.Exp` ([1837](#)), `TDoubleHelper.Mantissa` ([1836](#)), `TDoubleHelper.Fraction` ([1836](#)), `TDoubleHelper.Exponent` ([1835](#))

77.83 TEncoding

77.83.1 Description

`TEncoding` is a mostly abstract class that contains various methods to deal with different encodings in single- and double-byte strings. In practice, one instance of a descendent of this class for each needed encoding can be instantiated and used. The class contains several class methods and properties to create such instances, and has several often-used instances available as class properties, in particular the default encoding.

When using encodings (and in particular `TEncoding.Default` (1843) or `TEncoding.ANSI` (1842)), if the `DefaultSystemCodePage` (1419) changes, you should call `TEncoding.FreeEncodings` (1838) to regenerate the encodings.

See also: `TEncoding.ANSI` (1842), `TEncoding.ASCII` (1842), `TEncoding.Default` (1843), `TEncoding.BigEndianUnicode` (1843), `TEncoding.Unicode` (1843), `TEncoding.UTF7` (1844), `TEncoding.UTF8` (1844)

77.83.2 Method overview

Page	Method	Description
1838	<code>Clone</code>	Clone a <code>TEncoding</code> instance
1839	<code>Convert</code>	Convert an array of bytes from one encoding to another
1839	<code>GetBufferEncoding</code>	Attempt to guess the encoding of a buffer
1840	<code>GetEncoding</code>	Get an encoding instance for a given codepage.
1840	<code>GetMaxByteCount</code>	Returns the maximum number of bytes needed to represent a string
1840	<code>GetMaxCharCount</code>	Return the maximum number of characters that can be represented in a number of bytes
1841	<code>GetPreamble</code>	Return the BOM Marker used by the encoding
1841	<code>GetString</code>	Return a string based on an array of bytes
1839	<code>IsStandardEncoding</code>	Check if the encoding is one of the standard encodings

77.83.3 Property overview

Page	Properties	Access	Description
1842	<code>ANSI</code>	r	Ansi encoding instance
1842	<code>ASCII</code>	r	ASCII encoding instance
1843	<code>BigEndianUnicode</code>	r	Big-endian Unicode (UTF16BE) encoding instance
1841	<code>CodePage</code>	r	Codepage for this encoding
1843	<code>Default</code>	r	Default codepage
1842	<code>EncodingName</code>	r	Name of this encoding
1842	<code>IsSingleByte</code>	r	Is the encoding a single-byte encoding or not ?
1843	<code>SystemEncoding</code>	r	System encoding
1843	<code>Unicode</code>	r	UTF16 encoding instance
1844	<code>UTF7</code>	r	UTF7 encoding instance
1844	<code>UTF8</code>	r	UTF8 encoding instance

77.83.4 TEncoding.Clone

Synopsis: Clone a `TEncoding` instance

Declaration: `function Clone : TEncoding; Virtual`

Visibility: public

Description: `Clone` creates a copy of a `TEncoding` instance. This method returns `Nil` in `TEncoding` and must be implemented in descendent classes.

See also: `TEncoding.Create` ([1838](#))

77.83.5 TEncoding.Convert

Synopsis: Convert an array of bytes from one encoding to another

Declaration:

```
class function Convert(Source: TEncoding; Destination: TEncoding;
    const Bytes: TBytes) : TBytes; Overload
class function Convert(Source: TEncoding; Destination: TEncoding;
    const Bytes: TBytes; StartIndex: Integer;
    Count: Integer) : TBytes; Overload
```

Visibility: public

Description: `Convert` will convert the bytes in `Bytes` from encoding `Source` to encoding `Destination` and returns the converted bytes as an array. If `StartIndex` and `Count` are specified, the conversion starts at (zero-based) index `StartIndex`, and only `Count` bytes will be converted.

See also: `TEncoding.GetBytes` ([1838](#)), `TEncoding.GetChars` ([1838](#))

77.83.6 TEncoding.IsStandardEncoding

Synopsis: Check if the encoding is one of the standard encodings

Declaration:

```
class function IsStandardEncoding(AEncoding: TEncoding) : Boolean
    ; Static
```

Visibility: public

Description: `IsStandardEncoding` will return `True` is one of the standard encoding instances `TEncoding.ANSI` ([1842](#)), `TEncoding.ASCII` ([1842](#)), `TEncoding.Default` ([1843](#)), `TEncoding.BigEndianUnicode` ([1843](#)), `TEncoding.Unicode` ([1843](#)), `TEncoding.UTF7` ([1844](#)) or `TEncoding.UTF8` ([1844](#)). Otherwise it returns `False`.

See also: `TEncoding.ANSI` ([1842](#)), `TEncoding.ASCII` ([1842](#)), `TEncoding.Default` ([1843](#)), `TEncoding.BigEndianUnicode` ([1843](#)), `TEncoding.Unicode` ([1843](#)), `TEncoding.UTF7` ([1844](#)), `TEncoding.UTF8` ([1844](#))

77.83.7 TEncoding.GetBufferEncoding

Synopsis: Attempt to guess the encoding of a buffer

Declaration:

```
class function GetBufferEncoding(const Buffer: TBytes;
    var AEncoding: TEncoding) : Integer
    ; Overload; Static
class function GetBufferEncoding(const Buffer: TBytes;
    var AEncoding: TEncoding;
    ADefaultEncoding: TEncoding) : Integer
    ; Overload; Static
```

Visibility: public

Description: `GetBufferEncoding` checks the BOM marker of an array of bytes `Buffer`, and returns the found encoding in `AEncoding`. Only the `TEncoding.BigEndianUnicode` (1843) `TEncoding.Unicode` (1843) and `TEncoding.UTF8` (1844) encodings will be tried.

If `AEncoding` is non-`Nil` on entry, it will be used to check the BOM marker with. No other encoding will be tried in that case.

If `ADefaultEncoding` is specified, it will be returned in case no match was found.

The function returns the number of bytes in the BOM Marker.

See also: `TEncoding.BigEndianUnicode` (1843), `TEncoding.Unicode` (1843), `TEncoding.UTF8` (1844), `TEncoding.GetPreamble` (1841)

77.83.8 TEncoding.GetEncoding

Synopsis: Get an encoding instance for a given codepage.

Declaration:

```
class function GetEncoding(CodePage: Integer) : TEncoding; Overload
; Static
class function GetEncoding(const EncodingName: UnicodeString)
: TEncoding; Overload; Static
```

Visibility: public

Description: `GetEncoding` will return an instance of `TEncoding` for the given codepage `CodePage`. The codepage can also be specified by name `EncodingName`. The returned instance is an appropriate descendent of `TEncoding` and needs to be freed by the caller.

See also: `TUnicodeEncoding` (1916), `TBigEndianUnicodeEncoding` (1819), `TUTF8Encoding` (1926), `TUTF7Encoding` (1925), `TMBCSEncoding` (1862)

77.83.9 TEncoding.GetMaxByteCount

Synopsis: Returns the maximum number of bytes needed to represent a string

Declaration:

```
function GetMaxByteCount(CharCount: Integer) : Integer; Virtual
; Abstract
```

Visibility: public

Description: `GetMaxByteCount` returns the maximum number of bytes needed to represent a string of `CharCount` characters in the given encoding.

This is an abstract method, implemented by descendents of `TEncoding`.

See also: `TEncoding.GetMaxCharCount` (1840)

77.83.10 TEncoding.GetMaxCharCount

Synopsis: Return the maximum number of characters that can be represented in a number of bytes

Declaration:

```
function GetMaxCharCount(ByteCount: Integer) : Integer; Virtual
; Abstract
```

Visibility: public

Description: `GetMaxCharCount` returns the theoretical maximum number of characters that can be represented in a buffer of length `ByteCount` in the given encoding. Note that the actual number of characters that can be represented may well be much less and depends on the encoding and the actual characters.

This is an abstract method, implemented by descendents of `TEncoding`.

See also: `TEncoding.GetMaxByteCount` ([1840](#))

77.83.11 `TEncoding.GetPreamble`

Synopsis: Return the BOM Marker used by the encoding

Declaration: `function GetPreamble : TBytes; Virtual; Abstract`

Visibility: `public`

Description: `GetPreamble` returns the BOM marker bytes used by the encoding. This is only meaningful for the UTF8 and Unicode encodings, for all other encodings there is no BOM Marker.

See also: `TUnicodeEncoding` ([1916](#)), `TBigEndianUnicodeEncoding` ([1819](#)), `TUTF8Encoding` ([1926](#))

77.83.12 `TEncoding.GetString`

Synopsis: Return a string based on an array of bytes

Declaration: `function GetString(const Bytes: TBytes) : UnicodeString; Overload`
`function GetString(const Bytes: TBytes; ByteIndex: Integer;`
`ByteCount: Integer) : UnicodeString; Overload`

Visibility: `public`

Description: `GetString` will return a Unicode string, created from the bytes in the `Bytes` array. The bytes array will be interpreted according to the encoding which the `TEncoding` represents.

If `ByteIndex` and `ByteCount` are specified, only the `ByteCount` bytes starting at position `ByteIndex` will be converted.

Errors: In case of invalid bytes, an `EEncodingError` exception may be raised.

77.83.13 `TEncoding.CodePage`

Synopsis: Codepage for this encoding

Declaration: `Property CodePage : Cardinal`

Visibility: `public`

Access: `Read`

Description: `CodePage` is the numerical codepage for this encoding. It is a number as used in the Windows codepage registry.

See also: `TEncoding.EncodingName` ([1842](#))

77.83.14 TEncoding.EncodingName

Synopsis: Name of this encoding

Declaration: `Property EncodingName : UnicodeString`

Visibility: public

Access: Read

Description: `EncodingName` is the name for this encoding. It's based on the windows name for the encoding and is calculated from the codepage.

See also: `TEncoding.CodePage` ([1841](#))

77.83.15 TEncoding.IsSingleByte

Synopsis: Is the encoding a single-byte encoding or not ?

Declaration: `Property IsSingleByte : Boolean`

Visibility: public

Access: Read

Description: `IsSingleByte` determines whether an encoding is single-byte or not. It is `false` for all standard encodings.

77.83.16 TEncoding.ANSI

Synopsis: Ansi encoding instance

Declaration: `Property ANSI : TEncoding`

Visibility: public

Access: Read

Description: `ANSI` is the ANSI codepage encoding instance, it is the default single-byte string codepage on windows (as returned by `DefaultSystemCodePage` ([1615](#))). This instance is created and maintained by the system, it should not be freed.

See also: `(??)`, `TEncoding.ASCII` ([1842](#)), `TEncoding.Default` ([1843](#)), `TEncoding.BigEndianUnicode` ([1843](#)), `TEncoding.Unicode` ([1843](#)), `TEncoding.UTF7` ([1844](#)), `TEncoding.UTF8` ([1844](#))

77.83.17 TEncoding.ASCII

Synopsis: ASCII encoding instance

Declaration: `Property ASCII : TEncoding`

Visibility: public

Access: Read

Description: `ASCII` is the ASCII codepage (`CP_ASCII`) encoding instance. This instance is created and maintained by the system, it should not be freed.

See also: `TEncoding.ANSI` ([1842](#)), `TEncoding.ASCII` ([1842](#)), `TEncoding.Default` ([1843](#)), `TEncoding.BigEndianUnicode` ([1843](#)), `TEncoding.Unicode` ([1843](#)), `TEncoding.UTF7` ([1844](#)), `TEncoding.UTF8` ([1844](#))

77.83.18 TEncoding.BigEndianUnicode

Synopsis: Big-endian Unicode (UTF16BE) encoding instance

Declaration: `Property BigEndianUnicode : TEncoding`

Visibility: public

Access: Read

Description: `BigEndianUnicode` is the Big-endian Unicode encoding instance (CP_UTF16BE) This instance is created and maintained by the system, it should not be freed.

See also: [\(??\)](#), [TEncoding.ANSI \(1842\)](#), [TEncoding.ASCII \(1842\)](#), [TEncoding.Default \(1843\)](#), [TEncoding.Unicode \(1843\)](#), [TEncoding.UTF7 \(1844\)](#), [TEncoding.UTF8 \(1844\)](#)

77.83.19 TEncoding.Default

Synopsis: Default codepage

Declaration: `Property Default : TEncoding`

Visibility: public

Access: Read

Description: `Default` is the default encoding instance (it equals the ANSI codepage). This instance is created and maintained by the system, it should not be freed.

if the `DefaultSystemCodePage` ([1419](#)) changes, you should call `TEncoding.FreeEncodings` ([1838](#)) to regenerate the default encoding using the new code page.

See also: [\(??\)](#), [TEncoding.ANSI \(1842\)](#), [TEncoding.ASCII \(1842\)](#), [TEncoding.BigEndianUnicode \(1843\)](#), [TEncoding.Unicode \(1843\)](#), [TEncoding.UTF7 \(1844\)](#), [TEncoding.UTF8 \(1844\)](#)

77.83.20 TEncoding.SystemEncoding

Synopsis: System encoding

Declaration: `Property SystemEncoding : TEncoding`

Visibility: public

Access: Read

Description: `SystemEncoding` is the encoding as referenced by the `DefaultSystemCodePage`.

See also: `DefaultSystemCodePage` ([1419](#))

77.83.21 TEncoding.Unicode

Synopsis: UTF16 encoding instance

Declaration: `Property Unicode : TEncoding`

Visibility: public

Access: Read

Description: `Unicode` is the Big-endian Unicode encoding instance (`CP_UTF16`) This instance is created and maintained by the system, it should not be freed.

See also: [\(??\)](#), [TEncoding.ANSI \(1842\)](#), [TEncoding.ASCII \(1842\)](#), [TEncoding.Default \(1843\)](#), [TEncoding.BigEndianUnicode \(1843\)](#), [TEncoding.Unicode \(1843\)](#), [TEncoding.UTF7 \(1844\)](#), [TEncoding.UTF8 \(1844\)](#)

77.83.22 TEncoding.UTF7

Synopsis: UTF7 encoding instance

Declaration: `Property UTF7 : TEncoding`

Visibility: public

Access: Read

Description: `UTF7` is the UTF7 encoding instance (`CP_UTF7`) This instance is created and maintained by the system, it should not be freed.

See also: [\(??\)](#), [TEncoding.ANSI \(1842\)](#), [TEncoding.ASCII \(1842\)](#), [TEncoding.Default \(1843\)](#), [TEncoding.BigEndianUnicode \(1843\)](#), [TEncoding.Unicode \(1843\)](#), [TEncoding.UTF8 \(1844\)](#)

77.83.23 TEncoding.UTF8

Synopsis: UTF8 encoding instance

Declaration: `Property UTF8 : TEncoding`

Visibility: public

Access: Read

Description: `UTF8` is the UTF7 encoding instance (`CP_UTF7`) This instance is created and maintained by the system, it should not be freed.

See also: [\(??\)](#), [TEncoding.ANSI \(1842\)](#), [TEncoding.ASCII \(1842\)](#), [TEncoding.Default \(1843\)](#), [TEncoding.BigEndianUnicode \(1843\)](#), [TEncoding.Unicode \(1843\)](#), [TEncoding.UTF7 \(1844\)](#)

77.84 TExtendedHelper

77.84.1 Description

`TExtendedHelper` is the helper type for the Extended-sized floating point type. It contains some conversion methods, as well as access to the low-level structure of the floating-point representation of a `Extended`.

See also: [TDoubleHelper \(1832\)](#), [TExtendedHelper \(1844\)](#)

77.84.2 Method overview

Page	Method	Description
1848	BuildUp	Build a Extended-sized floating point from its composing parts
1848	Exponent	Exponent of the floating-point value
1848	Fraction	Fraction of the floating-point value
1847	IsInfinity	Check whether a value is positive or negative infinity.
1847	IsNan	Check whether a value equals NaN.
1847	IsNegativeInfinity	Check whether a value is negative infinity.
1847	IsPositiveInfinity	Check whether a value is positive infinity.
1849	Mantissa	Mantissa of the floating-point
1846	Parse	Convert a string to a floating point value
1848	Size	Size (in bytes) of a Extended-sized floating point value.
1849	SpecialType	Return the type of the Extended-sized floating point value
1845	ToString	Convert a Extended-sized floating point value to a string
1846	TryParse	Try to convert a string to a Extended-sized floating point value.

77.84.3 Property overview

Page	Properties	Access	Description
1849	Bytes	rw	Indexed access to the individual bytes of the floating point value
1850	Exp	rw	The bit pattern of the exponent as stored in memory.
1850	Frac	rw	Bitpattern that makes up the fractional part.
1850	Sign	rw	Sign of the floating point value
1849	Words	rw	Indexed access to the words that make up the floating point value

77.84.4 TExtendedHelper.ToString

Synopsis: Convert a Extended-sized floating point value to a string

```

Declaration: class function ToString(const AValue: Extended) : string; Overload
              ; Static
class function ToString(const AValue: Extended;
                        const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
class function ToString(const AValue: Extended;
                        const AFormat: TFloatFormat;
                        const APrecision: Integer;
                        const ADigits: Integer) : string; Overload
              ; Static
class function ToString(const AValue: Extended;
                        const AFormat: TFloatFormat;
                        const APrecision: Integer;
                        const ADigits: Integer;
                        const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
function ToString(const AFormat: TFloatFormat;
                  const APrecision: Integer; const ADigits: Integer)
                  : string; Overload
function ToString(const AFormat: TFloatFormat;
                  const APrecision: Integer; const ADigits: Integer;
                  const AFormatSettings: TFormatSettings) : string
                  ; Overload
function ToString(const AFormatSettings: TFormatSettings) : string

```

```

        ; Overload
function ToString : string; Overload

```

Visibility: public

Description: `ToString` will convert `AValue` (or `Self` in the plain method version) to a string. Optionally `FormatSettings` can be specified, to be able to specify the decimal separator character to use.

Additionally, a precision `APrecision` and number of digits `ADigits` can be specified, in conjunction with a `AFormat` parameter to specify the form in which the floating-point value must be represented. (see `TFloatFormat` (1636) for an explanation of the various values). In this case, `FloatToStrF` (1709) is used to format the value. In the absence of these parameters, `FloatToStr` (1708) is called.

See also: `FloatToStr` (1708), `FloatToStrF` (1709), `TFloatFormat` (1636)

77.84.5 TExtendedHelper.Parse

Synopsis: Convert a string to a floating point value

```

Declaration: class function Parse(const AString: string) : Extended; Overload
               ; Static
               class function Parse(const AString: string;
               const AFormatSettings: TFormatSettings) : Extended
               ; Overload; Static

```

Visibility: public

Description: `Parse` will try to convert `AString` to a `Extended`-sized floating point value. It will take into account internationalization settings. (it uses `FloatToStr`).

Errors: If the string `AString` is not a valid floating-point value, a `EConvertError` (1800) exception is raised.

See also: `FloatToStr` (1708), `TExtendedHelper.ToString` (1845), `TExtendedHelper.TryParse` (1846)

77.84.6 TExtendedHelper.TryParse

Synopsis: Try to convert a string to a `Extended`-sized floating point value.

```

Declaration: class function TryParse(const AString: string; out AValue: Extended)
               : Boolean; Overload; Static
               class function TryParse(const AString: string; out AValue: Extended;
               const AFormatSettings: TFormatSettings) : Boolean
               ; Overload; Static

```

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Extended`-sized floating point value and reports `True` if the conversion was successful. In that case the parsed value is returned in `AValue`.

If the conversion failed, `False` is returned.

See also: `TExtendedHelper.Parse` (1846), `TExtendedHelper.ToString` (1845)

77.84.7 TExtendedHelper.IsNan

Synopsis: Check whether a value equals NaN.

```
Declaration: class function IsNan(const AValue: Extended) : Boolean; Overload
                ; Static
                function IsNan : Boolean; Overload
```

Visibility: public

Description: `IsNaN` checks whether a Extended-sized floating point value is NaN (Not a Number). If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: TExtendedHelper.IsInfinity (1847), TExtendedHelper.IsPositiveInfinity (1847), TExtendedHelper.IsNegativeInfinity (1847)

77.84.8 TExtendedHelper.IsInfinity

Synopsis: Check whether a value is positive or negative infinity.

```
Declaration: class function IsInfinity(const AValue: Extended) : Boolean; Overload
                ; Static
                function IsInfinity : Boolean; Overload
```

Visibility: public

Description: `IsInfinity` checks whether a Extended-sized floating point value represents a positive or negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: TExtendedHelper.IsNan ([1847](#)), TExtendedHelper.IsPositiveInfinity ([1847](#)), TExtendedHelper.IsNegativeInfinity ([1847](#))

77.84.9 TExtendedHelper.IsNegativeInfinity

Synopsis: Check whether a value is negative infinity.

```
Declaration: class function IsNegativeInfinity(const AValue: Extended) : Boolean
                                                    ; Overload; Static
function IsNegativeInfinity : Boolean; Overload
```

Visibility: public

Description: `IsNegativeInfinity` checks whether a Extended-sized floating point value represents a negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: TExtendedHelper.IsNaN (1847), TExtendedHelper.IsPositiveInfinity (1847), TExtendedHelper.IsInfinity (1847)

77.84.10 TExtendedHelper.IsPositiveInfinity

Synopsis: Check whether a value is positive infinity.

```
Declaration: class function IsPositiveInfinity(const AValue: Extended) : Boolean
                                         ; Overload; Static
      function IsPositiveInfinity : Boolean; Overload
```


Visibility: public

Description: `IsPositiveInfinity` checks whether a Extended-sized floating point value represents a positive infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TExtendedHelper.IsNan` (1847), `TExtendedHelper.IsNegativeInfinity` (1847), `TExtendedHelper.IsInfinity` (1847)

77.84.11 TExtendedHelper.Size

Synopsis: Size (in bytes) of a Extended-sized floating point value.

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` is the size (in bytes) of a Extended-sized floating point value. It is equivalent to calling `SizeOf(Extended)`.

See also: `SizeOf` (1547)

77.84.12 TExtendedHelper.BuildUp

Synopsis: Build a Extended-sized floating point from its composing parts

Declaration: `procedure BuildUp(const ASignFlag: Boolean; const AMantissa: QWord; const AExponent: Integer)`

Visibility: public

Description: `BuildUp` will compose a Extended-sized floating point value from the sign `ASignFlag`, mantissa `AMantissa` and exponent `AExponent`. It simply sets the `Sign` (1850), `Exp` (1850) and `Frac` (1850) properties in 1 call.

See also: `TExtendedHelper.Sign` (1850), `TExtendedHelper.Exp` (1850), `TExtendedHelper.Frac` (1850)

77.84.13 TExtendedHelper.Exponent

Synopsis: Exponent of the floating-point value

Declaration: `function Exponent : Integer`

Visibility: public

Description: `Exponent` is the value X in the representation of the floating-point value in $m \cdot 2^X$, i.e. the exponent.

See also: `TExtendedHelper.Sign` (1850), `TExtendedHelper.Exp` (1850), `TExtendedHelper.Frac` (1850), `TExtendedHelper.Fraction` (1848), `TExtendedHelper.Mantissa` (1849)

77.84.14 TExtendedHelper.Fraction

Synopsis: Fraction of the floating-point value

Declaration: `function Fraction : Extended`

Visibility: public

Description: `Fraction` is the decimal part of the floating-point value.

See also: `TExtendedHelper.Sign` ([1850](#)), `TExtendedHelper.Exp` ([1850](#)), `TExtendedHelper.Exponent` ([1848](#)), `TExtendedHelper.Frac` ([1850](#)), `TExtendedHelper.Mantissa` ([1849](#))

77.84.15 TExtendedHelper.Mantissa

Synopsis: Mantissa of the floating-point

Declaration: `function Mantissa : QWord`

Visibility: `public`

Description: `Mantissa` is the value of the significand without the hidden bit. This means it the plain bit pattern as it is stored in memory.

See also: `TExtendedHelper.Sign` ([1850](#)), `TExtendedHelper.Exp` ([1850](#)), `TExtendedHelper.Exponent` ([1848](#)), `TExtendedHelper.Frac` ([1850](#)), `TExtendedHelper.Fraction` ([1848](#))

77.84.16 TExtendedHelper.SpecialType

Synopsis: Return the type of the Extended-sized floating point value

Declaration: `function SpecialType : TFloatSpecial`

Visibility: `public`

Description: `SpecialType` checks whether the Extended-sized floating point value equals one of several special values, and returns an enumerated value describing which value this is. See `TFloatSpecial` ([1615](#)) for an explanation of the possible values.

See also: `TFloatSpecial` ([1615](#))

77.84.17 TExtendedHelper.Bytes

Synopsis: Indexed access to the individual bytes of the floating point value

Declaration: `Property Bytes[AIndex: Cardinal]: Byte`

Visibility: `public`

Access: `Read,Write`

Description: `Bytes` can be used to get or set the various bytes that make up the Extended-sized floating point value. The index runs from 0 to `Size-1`.

See also: `TExtendedHelper.Words` ([1849](#)), `TExtendedHelper.Size` ([1848](#))

77.84.18 TExtendedHelper.Words

Synopsis: Indexed access to the words that make up the floating point value

Declaration: `Property Words[AIndex: Cardinal]: Word`

Visibility: `public`

Access: `Read,Write`

Description: `Words` can be used to get or set the various bytes that make up the Extended-sized floating point value. The index runs from 0 to $(\text{Size}-1) \div 2$.

See also: `TExtendedHelper.Bytes` ([1849](#)), `TExtendedHelper.Size` ([1848](#))

77.84.19 TExtendedHelper.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Sign` returns `True` if the sign bit of the value is set (i.e. it is a negative value) or `False` if it is not set (i.e. it is a positive value).

See also: `TExtendedHelper.Bytes` ([1849](#)), `TExtendedHelper.Exp` ([1850](#)), `TExtendedHelper.Frac` ([1850](#)), `TExtendedHelper.Mantissa` ([1849](#)), `TExtendedHelper.Fraction` ([1848](#)), `TExtendedHelper.Exponent` ([1848](#))

77.84.20 TExtendedHelper.Exp

Synopsis: The bit pattern of the exponent as stored in memory.

Declaration: `Property Exp : QWord`

Visibility: `public`

Access: `Read,Write`

Description: `Exp` is the internal representation of the Exponent ([1848](#)).

See also: `TExtendedHelper.Bytes` ([1849](#)), `TExtendedHelper.Sign` ([1850](#)), `TExtendedHelper.Frac` ([1850](#)), `TExtendedHelper.Mantissa` ([1849](#)), `TExtendedHelper.Fraction` ([1848](#)), `TExtendedHelper.Exponent` ([1848](#))

77.84.21 TExtendedHelper.Frac

Synopsis: Bitpattern that makes up the fractional part.

Declaration: `Property Frac : QWord`

Visibility: `public`

Access: `Read,Write`

Description: `Frac` is the bit pattern representing the fractional part (significand) including the preceding 1 (the hidden bit).

See also: `TExtendedHelper.Bytes` ([1849](#)), `TExtendedHelper.Sign` ([1850](#)), `TExtendedHelper.Exp` ([1850](#)), `TExtendedHelper.Mantissa` ([1849](#)), `TExtendedHelper.Fraction` ([1848](#)), `TExtendedHelper.Exponent` ([1848](#))

77.85 TGuidHelper

77.85.1 Description

`TGuidHelper` provides various methods for a `TGUID` ([1615](#)) type.

See also: `TGUID` ([1615](#))

77.85.2 Method overview

Page	Method	Description
1851	Create	Initialize a TGUID instance from data.
1851	NewGuid	Create a new GUID
1852	ToByteArray	Convert to array of bytes
1852	ToString	Convert to string

77.85.3 TGuidHelper.Create

Synopsis: Initialize a TGUID instance from data.

Declaration: `class function Create(const Data; BigEndian: Boolean) : TGuid; Overload; Static`
`class function Create(const Data: Array of Byte; AStartIndex: Cardinal; BigEndian: Boolean) : TGuid; Overload; Static`
`class function Create(const Data; DataEndian: TEndian) : TGuid; Overload; Static`
`class function Create(const B: TBytes; DataEndian: TEndian) : TGuid; Overload; Static`
`class function Create(const B: TBytes; AStartIndex: Cardinal; DataEndian: TEndian) : TGuid; Overload; Static`
`class function Create(const S: string) : TGuid; Overload; Static`
`class function Create(A: Integer; B: SmallInt; C: SmallInt; const D: TBytes) : TGuid; Overload; Static`
`class function Create(A: Integer; B: SmallInt; C: SmallInt; D: Byte; E: Byte; F: Byte; G: Byte; H: Byte; I: Byte; J: Byte; K: Byte) : TGuid; Overload; Static`
`class function Create(A: Cardinal; B: Word; C: Word; D: Byte; E: Byte; F: Byte; G: Byte; H: Byte; I: Byte; J: Byte; K: Byte) : TGuid; Overload; Static`

Visibility: default

Description: Create will initialize a TGUID ([1615](#)) from byte data. The byte-data can come in different forms

Data can be a plain buffer. The GUID Data will be read from the buffer (SizeOf(TGUID) bytes), according to the BigEndian argument.

Data can be an array of bytes. SizeOf(TGUID) bytes will be read from the array, starting at index StartIndex (default 0). The GUID Data will be read according to the BigEndian argument.

Scan can be a string containing a string representation of the GUID, which is converted using StringToGUID ([1755](#)).

A,B,C,D (optionally E,F,G,H,I,J,K) where the arguments are simply the various components of the GUID.

See also: TGUID ([1615](#)), StringToGUID ([1755](#))

77.85.4 TGuidHelper.NewGuid

Synopsis: Create a new GUID

Declaration: `class function NewGuid : TGuid; Static`

Visibility: default

Description: NewGUID creates and returns a new (??) using CreateGUID (1672)

See also: CreateGUID (1672)

77.85.5 TGuidHelper.ToByteArray

Synopsis: Convert to array of bytes

Declaration: `function ToByteArray(DataEndian: TEndian) : TBytes`

Visibility: default

Description: ToByteArray converts the TGUID to an array of bytes (of length `SizeOf(TGUID)`). The bytes will be ordered according to DataEndian.

See also: TGUIDHelper.ToString (1852), TGUIDHelper.Create (1851)

77.85.6 TGuidHelper.ToString

Synopsis: Convert to string

Declaration: `function ToString(SkipBrackets: Boolean) : string`

Visibility: default

Description: ToString will convert the TGUID to a string representation, using GUIDToString (1732)

See also: GUIDToString (1732)

77.86 TInt64Helper

77.86.1 Description

TInt64Helper contains some auxiliary routines for a Int64-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: TStringHelper (1895), TShortIntHelper (1879), TSmallIntHelper (1891), TWordHelper (1929), TCardinalHelper (1828), TIntegerHelper (1856), TByteHelper (1824), TQWordHelper (1875), TNativeIntHelper (1867), TNativeUIntHelper (1871)

77.86.2 Method overview

Page	Method	Description
1856	ClearBit	Set bit to 0
1853	Parse	Convert from a string
1855	SetBit	Set bit to 1
1853	Size	Size, in bytes, of the Int64 value
1856	TestBit	Check bit
1855	ToBinString	Convert to a binary string representation
1854	ToBoolean	Convert to a boolean value
1854	ToDouble	Convert to a double-sized floating point value
1854	ToExtended	Convert to an extended-sized floating point value
1856	ToggleBit	Invert bit
1855	ToHexString	Convert to a hexadecimal string representation
1855	ToSingle	Convert to a single-sized floating point value
1853	ToString	Convert the value to string
1854	TryParse	Try to convert a string to a Int64, report success or failure

77.86.3 TInt64Helper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Int64; Static`

Visibility: public

Description: Parse will attempt to convert the string `AString` to a `Int64` value. It uses the `StrToInt64` ([1770](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid Int64 value, an `EConvertError` ([1800](#)) exception is raised.

See also: [TInt64Helper.ToString \(1853\)](#), [TInt64Helper.TryParse \(1854\)](#), [StrToInt64 \(1770\)](#)

77.86.4 TInt64Helper.Size

Synopsis: Size, in bytes, of the Int64 value

```
Declaration: class function Size : Integer; Static
```

Visibility: public

Description: `Size` returns the size (in `Int64`s) of the `Int64` value. This is equivalent to `SizeOf(Int64)`.

Errors: None.

See also: [SizeOf \(1547\)](#)

77.86.5 TInt64Helper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: Int64) : string; Overload
                ; Static
                function ToString : string; Overload
```

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `Int64` value itself is used. The `IntToStr` (1736) function is used to do the conversion.

See also: `TInt64Helper.Parse` (1853), `IntToStr` (1736)

77.86.6 `TInt64Helper.TryParse`

Synopsis: Try to convert a string to a `Int64`, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Int64)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Int64`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `Int64` is returned in `AValue`.

It uses the `val` (1615) function to perform the conversion, so no localization is taken into account.

See also: `TInt64Helper.Parse` (1853), `Val` (1570)

77.86.7 `TInt64Helper.ToBoolean`

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `Int64` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TInt64Helper.ToSingle` (1855), `TInt64Helper.ToDouble` (1854), `TInt64Helper.ToExtended` (1854), `TInt64Helper.ToString` (1853), `TInt64Helper.ToHexString` (1855)

77.86.8 `TInt64Helper.ToDouble`

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Int64` value to a double-sized floating point value.

See also: `TInt64Helper.ToBoolean` (1854), `TInt64Helper.ToExtended` (1854), `TInt64Helper.ToSingle` (1855), `TInt64Helper.ToString` (1853), `TInt64Helper.ToHexString` (1855)

77.86.9 `TInt64Helper.ToExtended`

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `Int64` value to an extended-sized floating point value.

See also: `TInt64Helper.ToBoolean` (1854), `TInt64Helper.ToSingle` (1855), `TInt64Helper.ToDouble` (1854), `TInt64Helper.ToString` (1853), `TInt64Helper.ToHexString` (1855)

77.86.10 `TInt64Helper.ToBinString`

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: `public`

Description: `ToBinString` converts the `Int64` value to a binary string representation, showing all 64 bits.

See also: `TInt64Helper.ToHexString` (1855), `TInt64Helper.ToString` (1853)

77.86.11 `TInt64Helper.ToHexString`

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: `public`

Description: `ToHexString` converts the `Int64` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TInt64Helper.ToBoolean` (1854), `TInt64Helper.ToSingle` (1855), `TInt64Helper.ToDouble` (1854), `TInt64Helper.ToString` (1853), `TInt64Helper.ToExtended` (1854)

77.86.12 `TInt64Helper.ToSingle`

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: `public`

Description: `ToSingle` converts the `Int64` value to a single-sized floating point value.

See also: `TInt64Helper.ToBoolean` (1854), `TInt64Helper.ToDouble` (1854), `TInt64Helper.ToExtended` (1854), `TInt64Helper.ToString` (1853), `TInt64Helper.ToHexString` (1855)

77.86.13 `TInt64Helper.SetBit`

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TInt64BitIndex) : Int64`

Visibility: `public`

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TInt64Helper.ClearBit` (1856), `TInt64Helper.ToggleBit` (1856), `TInt64Helper.TestBit` (1856), `TInt64Helper.HighestSetBitPos` (1852), `TInt64Helper.LowestSetBitPos` (1852), `TInt64Helper.SetBitsCount` (1852), `TInt64Helper.Bits` (1852)

77.86.14 TInt64Helper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TInt64BitIndex) : Int64`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TInt64Helper.SetBit` ([1855](#)), `TInt64Helper.ToggleBit` ([1856](#)), `TInt64Helper.TestBit` ([1856](#)), `TInt64Helper.HighestSetBitPos` ([1852](#)), `TInt64Helper.LowestSetBitPos` ([1852](#)), `TInt64Helper.SetBitsCount` ([1852](#)), `TInt64Helper.Bits` ([1852](#))

77.86.15 TInt64Helper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TInt64BitIndex) : Int64`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TInt64Helper.SetBit` ([1855](#)), `TInt64Helper.ToggleBit` ([1856](#)), `TInt64Helper.TestBit` ([1856](#)), `TInt64Helper.HighestSetBitPos` ([1852](#)), `TInt64Helper.LowestSetBitPos` ([1852](#)), `TInt64Helper.SetBitsCount` ([1852](#)), `TInt64Helper.Bits` ([1852](#))

77.86.16 TInt64Helper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TInt64BitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TInt64Helper.SetBit` ([1855](#)), `TInt64Helper.ToggleBit` ([1856](#)), `TInt64Helper.TestBit` ([1856](#)), `TInt64Helper.HighestSetBitPos` ([1852](#)), `TInt64Helper.LowestSetBitPos` ([1852](#)), `TInt64Helper.SetBitsCount` ([1852](#)), `TInt64Helper.Bits` ([1852](#))

77.87 TIntegerHelper**77.87.1 Description**

`TIntegerHelper` contains some auxiliary routines for a Integer-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1895](#)), `TShortIntHelper` ([1879](#)), `TSmallIntHelper` ([1891](#)), `TWordHelper` ([1929](#)), `TCardinalHelper` ([1828](#)), `TByteHelper` ([1824](#)), `TInt64Helper` ([1852](#)), `TQWordHelper` ([1875](#)), `TNativeIntHelper` ([1867](#)), `TNativeUIntHelper` ([1871](#))

77.87.2 Method overview

Page	Method	Description
1860	ClearBit	Set bit to 0
1857	Parse	Convert from a string
1860	SetBit	Set bit to 1
1857	Size	Size, in bytes, of the Integer value
1860	TestBit	Check bit
1859	ToBinString	Convert to a binary string representation
1858	ToBoolean	Convert to a boolean value
1858	ToDouble	Convert to a double-sized floating point value
1859	ToExtended	Convert to an extended-sized floating point value
1860	ToggleBit	Invert bit
1859	ToHexString	Convert to a hexadecimal string representation
1859	ToSingle	Convert to a single-sized floating point value
1857	ToString	Convert the value to string
1858	TryParse	Try to convert a string to a Integer, report success or failure

77.87.3 TIntegerHelper.Size

Synopsis: Size, in bytes, of the Integer value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in Integers) of the Integer value. This is equivalent to `SizeOf(Integer)`.

Errors: None.

See also: `SizeOf` ([1547](#))

77.87.4 TIntegerHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Integer) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the Integer value itself is used. The `IntToStr` ([1736](#)) function is used to do the conversion.

See also: `TIntegerHelper.Parse` ([1857](#)), `IntToStr` ([1736](#))

77.87.5 TIntegerHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Integer; Static`

Visibility: public

Description: `Parse` will attempt to convert the string `AString` to a `Integer` value. It uses the `StrToInt` (1769) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `Integer` value, an `EConvertError` (1800) exception is raised.

See also: `TIntegerHelper.ToString` (1857), `TIntegerHelper.TryParse` (1858), `StrToInt` (1769)

77.87.6 TIntegerHelper.TryParse

Synopsis: Try to convert a string to a `Integer`, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Integer) : Boolean; Static`

Visibility: `public`

Description: `TryParse` attempts to convert the string `AString` to a `Integer`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `Integer` is returned in `AValue`.

It uses the `val` (1615) function to perform the conversion, so no localization is taken into account.

See also: `TIntegerHelper.Parse` (1857), `Val` (1570)

77.87.7 TIntegerHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: `public`

Description: `ToBoolean` converts the `Integer` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TIntegerHelper.ToSingle` (1859), `TIntegerHelper.ToDouble` (1858), `TIntegerHelper.ToExtended` (1859), `TIntegerHelper.ToString` (1857), `TIntegerHelper.ToHexString` (1859)

77.87.8 TIntegerHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: `public`

Description: `ToDouble` converts the `Integer` value to a double-sized floating point value.

See also: `TIntegerHelper.ToBoolean` (1858), `TIntegerHelper.ToExtended` (1859), `TIntegerHelper.ToSingle` (1859), `TIntegerHelper.ToString` (1857), `TIntegerHelper.ToHexString` (1859)

77.87.9 TIntegerHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `Integer` value to an extended-sized floating point value.

See also: `TIntegerHelper.ToBoolean` (1858), `TIntegerHelper.ToSingle` (1859), `TIntegerHelper.ToDouble` (1858), `TIntegerHelper.ToString` (1857), `TIntegerHelper.HexString` (1859)

77.87.10 TIntegerHelper.ToBinString

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: public

Description: `ToBinString` converts the `Integer` value to a binary string representation, showing all 32 bits.

See also: `TIntegerHelper.HexString` (1859), `TIntegerHelper.ToString` (1857)

77.87.11 TIntegerHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `Integer` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TIntegerHelper.ToBoolean` (1858), `TIntegerHelper.ToSingle` (1859), `TIntegerHelper.ToDouble` (1858), `TIntegerHelper.ToString` (1857), `TIntegerHelper.ToExtended` (1859)

77.87.12 TIntegerHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `Integer` value to a single-sized floating point value.

See also: `TIntegerHelper.ToBoolean` (1858), `TIntegerHelper.ToDouble` (1858), `TIntegerHelper.ToExtended` (1859), `TIntegerHelper.ToString` (1857), `TIntegerHelper.HexString` (1859)

77.87.13 TIntegerHelper.SetBit

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TIntegerBitIndex) : Integer`

Visibility: public

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TIntegerHelper.ClearBit` (1860), `TIntegerHelper.ToggleBit` (1860), `TIntegerHelper.TestBit` (1860), `TIntegerHelper.HighestSetBitPos` (1856), `TIntegerHelper.LowestSetBitPos` (1856), `TIntegerHelper.SetBitsCount` (1856), `TIntegerHelper.Bits` (1856)

77.87.14 TIntegerHelper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TIntegerBitIndex) : Integer`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TIntegerHelper.SetBit` (1860), `TIntegerHelper.ToggleBit` (1860), `TIntegerHelper.TestBit` (1860), `TIntegerHelper.HighestSetBitPos` (1856), `TIntegerHelper.LowestSetBitPos` (1856), `TIntegerHelper.SetBitsCount` (1856), `TIntegerHelper.Bits` (1856)

77.87.15 TIntegerHelper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TIntegerBitIndex) : Integer`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TIntegerHelper.SetBit` (1860), `TIntegerHelper.ToggleBit` (1860), `TIntegerHelper.TestBit` (1860), `TIntegerHelper.HighestSetBitPos` (1856), `TIntegerHelper.LowestSetBitPos` (1856), `TIntegerHelper.SetBitsCount` (1856), `TIntegerHelper.Bits` (1856)

77.87.16 TIntegerHelper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TIntegerBitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TIntegerHelper.SetBit` (1860), `TIntegerHelper.ToggleBit` (1860), `TIntegerHelper.TestBit` (1860), `TIntegerHelper.HighestSetBitPos` (1856), `TIntegerHelper.LowestSetBitPos` (1856), `TIntegerHelper.SetBitsCount` (1856), `TIntegerHelper.Bits` (1856)

77.88 TLongBoolHelper

77.88.1 Description

TLongBoolHelper is a helper type for the LongBool type. It contains mostly conversion routines to and from other types.

See also: TStringHelper ([1895](#)), TShortIntHelper ([1879](#)), TSmallIntHelper ([1891](#)), TWordHelper ([1929](#)), TCardinalHelper ([1828](#)), TIntegerHelper ([1856](#)), TInt64Helper ([1852](#)), TQWordHelper ([1875](#)), TNativeIntHelper ([1867](#)), TByteHelper ([1824](#)), TByteBoolHelper ([1822](#)), TWordBoolHelper ([1927](#)), TLongBoolHelper ([1861](#))

77.88.2 Method overview

Page	Method	Description
1861	Parse	Convert string value to LongBool value.
1861	Size	Return the size (in bytes) of the
1862	ToInteger	Convert to an integer value
1861	ToString	Convert a LongBool value to string.
1862	TryToParse	Try to convert a string to a LongBool value

77.88.3 TLongBoolHelper.Parse

Synopsis: Convert string value to LongBool value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: public

Description: Parse attempts to convert the string S to a LongBool value. It uses the StrToBool ([1763](#)) function to perform the conversion.

Errors: If S does not contain a valid string representation, then an EConvertError ([1800](#)) exception is raised.

See also: TLongBoolHelper.TryToParse ([1862](#)), TLongBoolHelper.ToString ([1861](#)), TLongBoolHelper.ToInteger ([1862](#))

77.88.4 TLongBoolHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in bytes) of the LongBool value. This is equivalent to SizeOf(LongBool).

See also: SizeOf ([1547](#))

77.88.5 TLongBoolHelper.ToString

Synopsis: Convert a LongBool value to string.

Declaration: `class function ToString(const AValue: Boolean;
 UseBoolStrs: TUseBoolStrs) : string; Overload
 ; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: public

Description: `ToString` will, in the class method version, convert the `AValue LongBool` to a string representation. In the function method version the `LongBool` value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the `LongBool` strings `BoolStrs` (1615). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` (1665) function.

See also: `BoolStrs` (1615), `BoolToStr` (1665)

77.88.6 TLongBoolHelper.TryParse

Synopsis: Try to convert a string to a `LongBool` value

Declaration: `class function TryParse(const S: string; out AValue: Boolean)
: Boolean; Static`

Visibility: public

Description: `TryParse` will attempt to convert the string `S` to a `LongBool` value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TLongBoolHelper.Parse` (1861), `TLongBoolHelper.ToString` (1861)

77.88.7 TLongBoolHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the `LongBool` value, typecasted to `Integer`.

See also: `TLongBoolHelper.ToString` (1861)

77.89 TMBCSEncoding

77.89.1 Description

`TMBCSEncoding` is the encoding class used for most of the encodings, except the actual Unicode encodings. The codepage is specified during creation, and is by default the system codepage.

The name is somewhat misleading, since the MBCS is also used for single-byte encodings.

See also: `TUnicodeEncoding` (1916), `TUTF8Encoding` (1926), `TUTF7Encoding` (1925), `TBigendianUnicodeEncoding` (1819)

77.89.2 Method overview

Page	Method	Description
1863	Clone	Clone a TMBCSEncoding instance
1863	Create	Create a new instance of a multi-byte character set encoding
1863	GetMaxByteCount	Return max number of bytes needed to represent a string
1864	GetMaxCharCount	Return max number of characters that can be represented by an array of bytes
1864	GetPreamble	Return BOM marker bytes

77.89.3 TMBCSEncoding.Create

Synopsis: Create a new instance of a multi-byte character set encoding

Declaration: `constructor Create; Virtual; Overload`
`constructor Create(ACodePage: Integer); Virtual; Overload`
`constructor Create(ACodePage: Integer; MBToWCharFlags: Integer;`
`WCharToMBFlags: Integer); Virtual; Overload`

Visibility: public

Description: `Create` instantiates a new instance of the multi-byte character set encoding. The `ACodePage` parameter is optional, and defaults to `DefaultSystemCodePage` ([1615](#)).

The `MBToWCharFlags` and `WCharToMBFlags` parameters are stored but are otherwise unused in the Free Pascal implementation of `TMBCSEncoding`

77.89.4 TMBCSEncoding.Clone

Synopsis: Clone a `TMBCSEncoding` instance

Declaration: `function Clone : TEncoding; Override`

Visibility: public

Description: `Clone` overrides `TEncoding.Clone` ([1838](#)) to provide a clone of the `TMBCSEncoding` instance.

See also: `TEncoding.Clone` ([1838](#))

77.89.5 TMBCSEncoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: `function GetMaxByteCount(CharCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxByteCount` overrides `TEncoding.GetMaxByteCount` ([1840](#)) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxByteCount` ([1840](#))

77.89.6 TMBCSEncoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: `function GetMaxCharCount (ByteCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxCharCount` overrides `TEncoding.GetMaxCharCount` ([1840](#)) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxCharCount` ([1840](#))

77.89.7 TMBCSEncoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: public

Description: `GetPreamble` overrides `TEncoding.GetPreamble` ([1841](#)) to return the BOM Marker bytes (none, for this implementation).

See also: `TEncoding.GetPreamble` ([1841](#))

77.90 TMREWException

77.90.1 Description

`TMREWException` is the exception used by the `TMultiReadExclusiveWriteSynchronizer` ([1864](#)) class, for example in case of a deadlock.

See also: `TMultiReadExclusiveWriteSynchronizer` ([1864](#))

77.91 TMultiReadExclusiveWriteSynchronizer

77.91.1 Description

`TMultiReadExclusiveWriteSynchronizer` is a default implementation of the `IReadWriteSync` ([1811](#)) interface. It uses a single mutex to protect access to the read/write resource, resulting in a single thread having access to the resource.

See also: `IReadWriteSync` ([1811](#))

77.91.2 Interfaces overview

Page	Interfaces	Description
1811	<code>IReadWriteSync</code>	Read/Write synchronizer

77.91.3 Method overview

Page	Method	Description
1866	Beginread	Request read access to the resource
1865	Beginwrite	Request write access to the resource.
1865	Create	Create a new instance of the <code>TMultiReadExclusiveWriteSynchronizer</code> class
1865	Destroy	Destroys the <code>TMultiReadExclusiveWriteSynchronizer</code> instance
1866	Endread	Release read access to the resource
1866	Endwrite	Release write access to the resource

77.91.4 Property overview

Page	Properties	Access	Description
1866	RevisionLevel	r	
1867	WriterThreadID	r	

77.91.5 TMultiReadExclusiveWriteSynchronizer.Create

Synopsis: Create a new instance of the `TMultiReadExclusiveWriteSynchronizer` class

Declaration: `constructor Create; Virtual`

Visibility: `public`

Description: `Create` creates a new instance of `TMultiReadExclusiveWriteSynchronizer`. It initializes a `TRTLCriticalSection`.

Errors: None.

See also: `TRTLCriticalSection` ([1400](#))

77.91.6 TMultiReadExclusiveWriteSynchronizer.Destroy

Synopsis: Destroys the `TMultiReadExclusiveWriteSynchronizer` instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Create` destroys the instance of `TMultiReadExclusiveWriteSynchronizer`. It frees the `TRTLCriticalSection` it initialized, and calls the inherited destructor.

Errors: None.

See also: `TRTLCriticalSection` ([1400](#))

77.91.7 TMultiReadExclusiveWriteSynchronizer.Beginwrite

Synopsis: Request write access to the resource.

Declaration: `function Beginwrite : Boolean`

Visibility: `public`

Description: `Beginwrite` is the implementation of `IReadWriteSync.BeginWrite`. It simply enters the critical section, and returns `True`.

Errors: None.

See also: `IReadWriteSync.BeginWrite` ([1812](#)), `EndWrite` ([1866](#))

77.91.8 TMultiReadExclusiveWriteSynchronizer.Endwrite

Synopsis: Release write access to the resource

Declaration: `procedure Endwrite`

Visibility: `public`

Description: `Beginwrite` is the implementation of `IReadWriteSync.EndWrite`. It simply leaves the critical section.

Errors: None.

See also: `IReadWriteSync.EndWrite` ([1812](#)), `BeginWrite` ([1865](#))

77.91.9 TMultiReadExclusiveWriteSynchronizer.Beginread

Synopsis: Request read access to the resource

Declaration: `procedure Beginread`

Visibility: `public`

Description: `BeginRead` is the implementation of `IReadWriteSync.BeginRead`. It simply attempts to enter the critical section.

Errors: None.

See also: `IReadWriteSync.BeginRead` ([1812](#)), `EndRead` ([1866](#))

77.91.10 TMultiReadExclusiveWriteSynchronizer.Endread

Synopsis: Release read access to the resource

Declaration: `procedure Endread`

Visibility: `public`

Description: `EndRead` is the implementation of `IReadWriteSync.EndRead`. It simply leaves the critical section.

Errors: None.

See also: `IReadWriteSync.EndRead` ([1812](#)), `BeginRead` ([1866](#))

77.91.11 TMultiReadExclusiveWriteSynchronizer.RevisionLevel

Declaration: `Property RevisionLevel : Cardinal`

Visibility: `public`

Access: `Read`

77.91.12 TMultiReadExclusiveWriteSynchronizer.WriterThreadID

Declaration: `Property WriterThreadID : TThreadID`

Visibility: `public`

Access: `Read`

77.92 TNativeIntHelper**77.92.1 Description**

`TNativeIntHelper` contains some auxiliary routines for a `NativeInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1895), `TShortIntHelper` (1879), `TSmallIntHelper` (1891), `TWordHelper` (1929), `TCardinalHelper` (1828), `TIntegerHelper` (1856), `TInt64Helper` (1852), `TQWordHelper` (1875), `TNativeIntHelper` (1867), `TByteHelper` (1824)

77.92.2 Method overview

Page	Method	Description
1870	<code>ClearBit</code>	Set bit to 0
1867	<code>Parse</code>	Convert from a string
1870	<code>SetBit</code>	Set bit to 1
1868	<code>Size</code>	Size, in bytes, of the <code>NativeInt</code> value
1871	<code>TestBit</code>	Check bit
1869	<code>ToBinString</code>	Convert to a binary string representation
1868	<code>ToBoolean</code>	Convert to a boolean value
1869	<code>ToDouble</code>	Convert to a double-sized floating point value
1869	<code>ToExtended</code>	Convert to an extended-sized floating point value
1870	<code>ToggleBit</code>	Invert bit
1869	<code>ToHexString</code>	Convert to a hexadecimal string representation
1870	<code>ToSingle</code>	Convert to a single-sized floating point value
1868	<code>ToString</code>	Convert the value to string
1868	<code>TryParse</code>	Try to convert a string to a <code>NativeInt</code> , report success or failure

77.92.3 TNativeIntHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : NativeInt; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a `NativeInt` value. It uses the `StrToInt` (1769) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `NativeInt` value, an `EConvertError` (1800) exception is raised.

See also: `TNativeIntHelper.ToString` (1868), `TNativeIntHelper.TryParse` (1868), `StrToInt` (1769)

77.92.4 TNativeIntHelper.Size

Synopsis: Size, in bytes, of the NativeInt value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in NativeInts) of the NativeInt value. This is equivalent to `SizeOf (NativeInt)`.

Errors: None.

See also: `SizeOf` ([1547](#))

77.92.5 TNativeIntHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: NativeInt) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the NativeInt value itself is used. The `IntToStr` ([1736](#)) function is used to do the conversion.

See also: `TNativeIntHelper.Parse` ([1867](#)), `IntToStr` ([1736](#))

77.92.6 TNativeIntHelper.TryParse

Synopsis: Try to convert a string to a NativeInt, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: NativeInt)
: Boolean; Static`

Visibility: public

Description: TryParse attempts to convert the string AString to a NativeInt, and reports the success of the attempt. If the attempt is successful, then True is returned, and the actual value of the NativeInt is returned in AValue.

It uses the `val` ([1615](#)) function to perform the conversion, so no localization is taken into account.

See also: `TNativeIntHelper.Parse` ([1867](#)), `Val` ([1570](#))

77.92.7 TNativeIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: ToBoolean converts the NativeInt value to a boolean: it returns True if the value is nonzero, False if it is zero.

See also: `TNativeIntHelper.ToSingle` ([1870](#)), `TNativeIntHelper.ToDouble` ([1869](#)), `TNativeIntHelper.ToExtended` ([1869](#)), `TNativeIntHelper.ToString` ([1868](#)), `TNativeIntHelper.HexString` ([1869](#))

77.92.8 TNativeIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `NativeInt` value to a double-sized floating point value.

See also: `TNativeIntHelper.ToBoolean` (1868), `TNativeIntHelper.ToExtended` (1869), `TNativeIntHelper.ToSingle` (1870), `TNativeIntHelper.ToString` (1868), `TNativeIntHelper.ToHexString` (1869)

77.92.9 TNativeIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `NativeInt` value to an extended-sized floating point value.

See also: `TNativeIntHelper.ToBoolean` (1868), `TNativeIntHelper.ToSingle` (1870), `TNativeIntHelper.ToDouble` (1869), `TNativeIntHelper.ToString` (1868), `TNativeIntHelper.ToHexString` (1869)

77.92.10 TNativeIntHelper.ToBinString

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: public

Description: `ToBinString` converts the `NativeInt` value to a binary string representation, showing all bits.

See also: `TNativeIntHelper.ToHexString` (1869), `TNativeIntHelper.ToString` (1868)

77.92.11 TNativeIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `NativeInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TNativeIntHelper.ToBoolean` (1868), `TNativeIntHelper.ToSingle` (1870), `TNativeIntHelper.ToDouble` (1869), `TNativeIntHelper.ToString` (1868), `TNativeIntHelper.ToExtended` (1869)

77.92.12 TNativeIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `NativeInt` value to a single-sized floating point value.

See also: `TNativeIntHelper.ToBoolean` ([1868](#)), `TNativeIntHelper.ToDouble` ([1869](#)), `TNativeIntHelper.ToExtended` ([1869](#)), `TNativeIntHelper.ToString` ([1868](#)), `TNativeIntHelper.ToHexString` ([1869](#))

77.92.13 TNativeIntHelper.SetBit

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TNativeIntBitIndex) : NativeInt`

Visibility: public

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TNativeIntHelper.ClearBit` ([1870](#)), `TNativeIntHelper.ToggleBit` ([1870](#)), `TNativeIntHelper.TestBit` ([1871](#)), `TNativeIntHelper.HighestSetBitPos` ([1867](#)), `TNativeIntHelper.LowestSetBitPos` ([1867](#)), `TNativeIntHelper.SetBitsCount` ([1867](#)), `TNativeIntHelper.Bits` ([1867](#))

77.92.14 TNativeIntHelper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TNativeIntBitIndex) : NativeInt`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TNativeIntHelper.SetBit` ([1870](#)), `TNativeIntHelper.ToggleBit` ([1870](#)), `TNativeIntHelper.TestBit` ([1871](#)), `TNativeIntHelper.HighestSetBitPos` ([1867](#)), `TNativeIntHelper.LowestSetBitPos` ([1867](#)), `TNativeIntHelper.SetBitsCount` ([1867](#)), `TNativeIntHelper.Bits` ([1867](#))

77.92.15 TNativeIntHelper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TNativeIntBitIndex) : NativeInt`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TNativeIntHelper.SetBit` ([1870](#)), `TNativeIntHelper.ToggleBit` ([1870](#)), `TNativeIntHelper.TestBit` ([1871](#)), `TNativeIntHelper.HighestSetBitPos` ([1867](#)), `TNativeIntHelper.LowestSetBitPos` ([1867](#)), `TNativeIntHelper.SetBitsCount` ([1867](#)), `TNativeIntHelper.Bits` ([1867](#))

77.92.16 TNativeIntHelper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TNativeIntBitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TNativeIntHelper.SetBit` (1870), `TNativeIntHelper.ToggleBit` (1870), `TNativeIntHelper.TestBit` (1871), `TNativeIntHelper.HighestSetBitPos` (1867), `TNativeIntHelper.LowestSetBitPos` (1867), `TNativeIntHelper.SetBitsCount` (1867), `TNativeIntHelper.Bits` (1867)

77.93 TNativeUIntHelper

77.93.1 Description

`NativeUInt` contains some auxiliary routines for a `NativeUInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1895), `TShortIntHelper` (1879), `TSmallIntHelper` (1891), `TWordHelper` (1929), `TCardinalHelper` (1828), `TIntegerHelper` (1856), `TInt64Helper` (1852), `TQWordHelper` (1875), `TNativeIntHelper` (1867), `TByteHelper` (1824)

77.93.2 Method overview

Page	Method	Description
1874	<code>ClearBit</code>	Set bit to 0
1871	<code>Parse</code>	Convert from a string
1874	<code>SetBit</code>	Set bit to 1
1872	<code>Size</code>	Size, in bytes, of the <code>NativeUInt</code> value
1875	<code>TestBit</code>	Check bit
1873	<code>ToBinString</code>	Convert to a binary string representation
1873	<code>ToBoolean</code>	Convert to a boolean value
1873	<code>ToDouble</code>	Convert to a double-sized floating point value
1873	<code>ToExtended</code>	Convert to an extended-sized floating point value
1874	<code>ToggleBit</code>	Invert bit
1873	<code>ToHexString</code>	Convert to a hexadecimal string representation
1874	<code>ToSingle</code>	Convert to a single-sized floating point value
1872	<code>ToString</code>	Convert the value to string
1872	<code>TryParse</code>	Try to convert a string to a <code>NativeUInt</code> , report success or failure

77.93.3 TNativeUIntHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : NativeUInt; Static`

Visibility: public

Description: `Parse` will attempt to convert the string `AString` to a `NativeUInt` value. It uses the `StrToInt` (1769) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid NativeUInt value, an EConvertError (1800) exception is raised.

See also: TNativeUIntHelper.ToString (1872), TNativeUIntHelper.TryParse (1872), StrToInt (1769)

77.93.4 TNativeUIntHelper.Size

Synopsis: Size, in bytes, of the NativeUInt value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in NativeUInts) of the NativeUInt value. This is equivalent to `SizeOf(NativeUInt)`.

Errors: None.

See also: SizeOf (1547)

77.93.5 TNativeUIntHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: NativeUInt) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the NativeUInt value itself is used. The IntToStr (1736) function is used to do the conversion.

See also: TNativeUIntHelper.Parse (1871), IntToStr (1736)

77.93.6 TNativeUIntHelper.TryParse

Synopsis: Try to convert a string to a NativeUInt, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: NativeUInt)
: Boolean; Static`

Visibility: public

Description: TryParse attempts to convert the string AString to a NativeUInt, and reports the success of the attempt. If the attempt is successful, then True is returned, and the actual value of the NativeUInt is returned in AValue.

It uses the val (1615) function to perform the conversion, so no localization is taken into account.

See also: TNativeUIntHelper.Parse (1871), Val (1570)

77.93.7 TNativeUIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `NativeUInt` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TNativeUIntHelper.ToSingle` ([1874](#)), `TNativeUIntHelper.ToDouble` ([1873](#)), `TNativeUIntHelper.ToExtended` ([1873](#)), `TNativeUIntHelper.ToString` ([1872](#)), `TNativeUIntHelper.ToHexString` ([1873](#))

77.93.8 TNativeUIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `NativeUInt` value to a double-sized floating point value.

See also: `TNativeUIntHelper.ToBoolean` ([1873](#)), `TNativeUIntHelper.ToExtended` ([1873](#)), `TNativeUIntHelper.ToSingle` ([1874](#)), `TNativeUIntHelper.ToString` ([1872](#)), `TNativeUIntHelper.ToHexString` ([1873](#))

77.93.9 TNativeUIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `NativeUInt` value to an extended-sized floating point value.

See also: `TNativeUIntHelper.ToBoolean` ([1873](#)), `TNativeUIntHelper.ToSingle` ([1874](#)), `TNativeUIntHelper.ToDouble` ([1873](#)), `TNativeUIntHelper.ToString` ([1872](#)), `TNativeUIntHelper.ToHexString` ([1873](#))

77.93.10 TNativeUIntHelper.ToBinString

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: public

Description: `ToBinString` converts the `NativeUInt` value to a binary string representation, showing all bits.

77.93.11 TNativeUIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `NativeUInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TNativeUIntHelper.ToBoolean` (1873), `TNativeUIntHelper.ToSingle` (1874), `TNativeUIntHelper.ToDouble` (1873), `TNativeUIntHelper.ToString` (1872), `TNativeUIntHelper.ToExtended` (1873)

77.93.12 TNativeUIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `NativeUInt` value to a single-sized floating point value.

See also: `TNativeUIntHelper.ToBoolean` (1873), `TNativeUIntHelper.ToDouble` (1873), `TNativeUIntHelper.ToExtended` (1873), `TNativeUIntHelper.ToString` (1872), `TNativeUIntHelper.HexString` (1873)

77.93.13 TNativeUIntHelper.SetBit

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TNativeUIntBitIndex) : NativeUInt`

Visibility: public

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TNativeUIntHelper.ClearBit` (1874), `TNativeUIntHelper.ToggleBit` (1874), `TNativeUIntHelper.TestBit` (1875), `TNativeUIntHelper.HighestSetBitPos` (1871), `TNativeUIntHelper.LowestSetBitPos` (1871), `TNativeUIntHelper.SetBitsCount` (1871), `TNativeUIntHelper.Bits` (1871)

77.93.14 TNativeUIntHelper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TNativeUIntBitIndex) : NativeUInt`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TNativeUIntHelper.SetBit` (1874), `TNativeUIntHelper.ToggleBit` (1874), `TNativeUIntHelper.TestBit` (1875), `TNativeUIntHelper.HighestSetBitPos` (1871), `TNativeUIntHelper.LowestSetBitPos` (1871), `TNativeUIntHelper.SetBitsCount` (1871), `TNativeUIntHelper.Bits` (1871)

77.93.15 TNativeUIntHelper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TNativeUIntBitIndex) : NativeUInt`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TNativeUIntHelper.SetBit` ([1874](#)), `TNativeUIntHelper.ToggleBit` ([1874](#)), `TNativeUIntHelper.TestBit` ([1875](#)), `TNativeUIntHelper.HighestSetBitPos` ([1871](#)), `TNativeUIntHelper.LowestSetBitPos` ([1871](#)), `TNativeUIntHelper.SetBitsCount` ([1871](#)), `TNativeUIntHelper.Bits` ([1871](#))

77.93.16 TNativeUIntHelper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TNativeUIntBitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TNativeUIntHelper.SetBit` ([1874](#)), `TNativeUIntHelper.ToggleBit` ([1874](#)), `TNativeUIntHelper.TestBit` ([1875](#)), `TNativeUIntHelper.HighestSetBitPos` ([1871](#)), `TNativeUIntHelper.LowestSetBitPos` ([1871](#)), `TNativeUIntHelper.SetBitsCount` ([1871](#)), `TNativeUIntHelper.Bits` ([1871](#))

77.94 TQWordHelper

77.94.1 Description

`TQWordHelper` contains some auxiliary routines for a `QWord`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1895](#)), `TShortIntHelper` ([1879](#)), `TSmallIntHelper` ([1891](#)), `TWordHelper` ([1929](#)), `TCardinalHelper` ([1828](#)), `TIntegerHelper` ([1856](#)), `TInt64Helper` ([1852](#)), `TByteHelper` ([1824](#)), `TNativeIntHelper` ([1867](#)), `TNativeUIntHelper` ([1871](#))

77.94.2 Method overview

Page	Method	Description
1878	<code>ClearBit</code>	Set bit to 0
1875	<code>Parse</code>	Convert from a string
1878	<code>SetBit</code>	Set bit to 1
1876	<code>Size</code>	Size, in bytes, of the <code>QWord</code> value
1879	<code>TestBit</code>	Check bit
1877	<code>ToBinString</code>	Convert to a binary string representation
1877	<code>ToBoolean</code>	Convert to a boolean value
1877	<code>ToDouble</code>	Convert to a double-sized floating point value
1877	<code>ToExtended</code>	Convert to an extended-sized floating point value
1879	<code>ToggleBit</code>	Invert bit
1878	<code>ToHexString</code>	Convert to a hexadecimal string representation
1878	<code>ToSingle</code>	Convert to a single-sized floating point value
1876	<code>ToString</code>	Convert the value to string
1876	<code>TryParse</code>	Try to convert a string to a <code>QWord</code> , report success or failure

77.94.3 TQWordHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : QWord; Static`

Visibility: public

Description: Parse will attempt to convert the string `AString` to a `QWord` value. It uses the `StrToQWord` (1771) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid QWord value, an `EConvertError (1800)` exception is raised.

See also: [TQWordHelper.ToString \(1876\)](#), [TQWordHelper.TryParse \(1876\)](#), [StrToQWord \(1771\)](#)

77.94.4 TQWordHelper.Size

Synopsis: Size, in bytes, of the QWord value

```
Declaration: class function Size : Integer; Static
```

Visibility: public

Description: `Size` returns the size (in QWords) of the QWord value. This is equivalent to `SizeOf (QWord)`.

Errors: None.

See also: [SizeOf \(1547\)](#)

77.94.5 TQWordHelper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: QWord) : string; Overload
                ; Static
                function ToString : string; Overload
```

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the QWord value itself is used. The IntToStr (1736) function is used to do the conversion.

See also: [TQWordHelper.Parse \(1875\)](#), [IntToStr \(1736\)](#)

77.94.6 TQWordHelper.TryParse

Synopsis: Try to convert a string to a QWord, report success or failure

```
Declaration: class function TryParse(const AString: string; out AValue: QWord)
                                     : Boolean; Static
```

Visibility: public

Description: TryParse attempts to convert the string AString to a QWord, and reports the success of the attempt. If the attempt is successful, then True is returned, and the actual value of the QWord is returned in AValue.

It uses the `val (1615)` function to perform the conversion, so no localization is taken into account.

See also: [TQWordHelper.Parse \(1875\)](#), [Val \(1570\)](#)

77.94.7 TQWordHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `QWord` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TQWordHelper.ToSingle` ([1878](#)), `TQWordHelper.ToDouble` ([1877](#)), `TQWordHelper.ToExtended` ([1877](#)), `TQWordHelper.ToString` ([1876](#)), `TQWordHelper.ToHexString` ([1878](#))

77.94.8 TQWordHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `QWord` value to a double-sized floating point value.

See also: `TQWordHelper.ToBoolean` ([1877](#)), `TQWordHelper.ToExtended` ([1877](#)), `TQWordHelper.ToSingle` ([1878](#)), `TQWordHelper.ToString` ([1876](#)), `TQWordHelper.ToHexString` ([1878](#))

77.94.9 TQWordHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `QWord` value to an extended-sized floating point value.

See also: `TQWordHelper.ToBoolean` ([1877](#)), `TQWordHelper.ToSingle` ([1878](#)), `TQWordHelper.ToDouble` ([1877](#)), `TQWordHelper.ToString` ([1876](#)), `TQWordHelper.ToHexString` ([1878](#))

77.94.10 TQWordHelper.ToBinString

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: public

Description: `ToBinString` converts the `QWord` value to a binary string representation, showing all 64 bits.

See also: `TQWordHelper.ToHexString` ([1878](#)), `TQWordHelper.ToString` ([1876](#))

77.94.11 TQWordHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `QWord` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TQWordHelper.ToBoolean` ([1877](#)), `TQWordHelper.ToSingle` ([1878](#)), `TQWordHelper.ToDouble` ([1877](#)), `TQWordHelper.ToString` ([1876](#)), `TQWordHelper.ToExtended` ([1877](#))

77.94.12 TQWordHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `QWord` value to a single-sized floating point value.

See also: `TQWordHelper.ToBoolean` ([1877](#)), `TQWordHelper.ToDouble` ([1877](#)), `TQWordHelper.ToExtended` ([1877](#)), `TQWordHelper.ToString` ([1876](#)), `TQWordHelper.ToHexString` ([1878](#))

77.94.13 TQWordHelper.SetBit

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TQwordBitIndex) : QWord`

Visibility: public

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TQWordHelper.ClearBit` ([1878](#)), `TQWordHelper.ToggleBit` ([1879](#)), `TQWordHelper.TestBit` ([1879](#)), `TQWordHelper.HighestSetBitPos` ([1875](#)), `TQWordHelper.LowestSetBitPos` ([1875](#)), `TQWordHelper.SetBitsCount` ([1875](#)), `TQWordHelper.Bits` ([1875](#))

77.94.14 TQWordHelper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TQwordBitIndex) : QWord`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TQWordHelper.SetBit` ([1878](#)), `TQWordHelper.ToggleBit` ([1879](#)), `TQWordHelper.TestBit` ([1879](#)), `TQWordHelper.HighestSetBitPos` ([1875](#)), `TQWordHelper.LowestSetBitPos` ([1875](#)), `TQWordHelper.SetBitsCount` ([1875](#)), `TQWordHelper.Bits` ([1875](#))

77.94.15 TQWordHelper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TQwordBitIndex) : QWord`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TQWordHelper.SetBit` (1878), `TQWordHelper.ToggleBit` (1879), `TQWordHelper.TestBit` (1879), `TQWordHelper.HighestSetBitPos` (1875), `TQWordHelper.LowestSetBitPos` (1875), `TQWordHelper.SetBitsCount` (1875), `TQWordHelper.Bits` (1875)

77.94.16 TQWordHelper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TQwordBitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TQWordHelper.SetBit` (1878), `TQWordHelper.ToggleBit` (1879), `TQWordHelper.TestBit` (1879), `TQWordHelper.HighestSetBitPos` (1875), `TQWordHelper.LowestSetBitPos` (1875), `TQWordHelper.SetBitsCount` (1875), `TQWordHelper.Bits` (1875)

77.95 TShortIntHelper

77.95.1 Description

`TShortIntHelper` contains some auxiliary routines for a `ShortInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1895), `TByteHelper` (1824), `TSmallIntHelper` (1891), `TWordHelper` (1929), `TCardinalHelper` (1828), `TIntegerHelper` (1856), `TInt64Helper` (1852), `TQWordHelper` (1875), `TNativeIntHelper` (1867), `TNativeUIntHelper` (1871)

77.95.2 Method overview

Page	Method	Description
1883	ClearBit	Set bit to 0
1880	Parse	Convert from a string
1882	SetBit	Set bit to 1
1880	Size	Size, in bytes, of the ShortInt value
1883	TestBit	Check bit
1882	ToBinString	Convert to a binary string representation
1881	ToBoolean	Convert to a boolean value
1881	ToDouble	Convert to a double-sized floating point value
1881	ToExtended	Convert to an extended-sized floating point value
1883	ToggleBit	Invert bit
1882	ToHexString	Convert to a hexadecimal string representation
1882	ToSingle	Convert to an single-sized floating point value
1880	ToString	Convert the value to string
1881	TryParse	Try to convert a string to a ShortInt, report success or failure

77.95.3 TShortIntHelper.Parse

Synopsis: Convert from a string

```
Declaration: class function Parse(const AString: string) : ShortInt; Static
```

Visibility: public

Description: Parse will attempt to convert the string `AsString` to a `ShortInt` value. It uses the `StrToInt` (1769) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid ShortInt value, an EConvertError (1800) exception is raised.

See also: [TShortIntHelper.ToString \(1880\)](#), [TShortIntHelper.TryParse \(1881\)](#), [StrToInt \(1769\)](#)

77.95.4 TShortIntHelper.Size

Synopsis: Size, in bytes, of the ShortInt value

Declaration: class function Size : Integer; Static

Visibility: public

Description: `Size` returns the size (in `ShortInts`) of the `ShortInt` value. This is equivalent to `SizeOf(Byte)`.

Errors: None.

See also: [SizeOf \(1547\)](#)

77.95.5 TShortIntHelper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: ShortInt) : string; Overload
              ; Static
              function ToString : string; Overload
```

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `ShortInt` value itself is used. The `IntToStr` (1736) function is used to do the conversion.

See also: `TShortIntHelper.Parse` (1880), `IntToStr` (1736)

77.95.6 TShortIntHelper.TryParse

Synopsis: Try to convert a string to a `ShortInt`, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: ShortInt) : Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `ShortInt`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `ShortInt` is returned in `AValue`.

It uses the `val` (1615) function to perform the conversion, so no localization is taken into account.

See also: `TShortIntHelper.Parse` (1880), `Val` (1570)

77.95.7 TShortIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `ShortInt` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TShortIntHelper.ToSingle` (1882), `TShortIntHelper.ToDouble` (1881), `TShortIntHelper.ToExtended` (1881), `TShortIntHelper.ToString` (1880), `TShortIntHelper.ToHexString` (1882)

77.95.8 TShortIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `ShortInt` value to a double-sized floating point value.

See also: `TShortIntHelper.ToBoolean` (1881), `TShortIntHelper.ToExtended` (1881), `TShortIntHelper.ToSingle` (1882), `TShortIntHelper.ToString` (1880), `TShortIntHelper.ToHexString` (1882)

77.95.9 TShortIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `ShortInt` value to an extended-sized floating point value.

See also: `TShortIntHelper.ToBoolean` (1881), `TShortIntHelper.ToSingle` (1882), `TShortIntHelper.ToDouble` (1881), `TShortIntHelper.ToString` (1880), `TShortIntHelper.ToHexString` (1882)

77.95.10 TShortIntHelper.ToBinString

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: public

Description: `ToBinString` converts the `shortint` value to a binary string representation, showing all 8 bits.

See also: `TShortIntHelper.ToHexString` (1882), `TShortIntHelper.ToString` (1880)

77.95.11 TShortIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `ShortInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TShortIntHelper.ToBoolean` (1881), `TShortIntHelper.ToSingle` (1882), `TShortIntHelper.ToDouble` (1881), `TShortIntHelper.ToString` (1880), `TShortIntHelper.ToExtended` (1881)

77.95.12 TShortIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `ShortInt` value to a single-sized floating point value.

See also: `TShortIntHelper.ToBoolean` (1881), `TShortIntHelper.ToDouble` (1881), `TShortIntHelper.ToExtended` (1881), `TShortIntHelper.ToString` (1880), `TShortIntHelper.ToHexString` (1882)

77.95.13 TShortIntHelper.SetBit

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TShortIntBitIndex) : ShortInt`

Visibility: public

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TShortIntHelper.ClearBit` (1883), `TShortIntHelper.ToggleBit` (1883), `TShortIntHelper.TestBit` (1883), `TShortIntHelper.HighestSetBitPos` (1879), `TShortIntHelper.LowestSetBitPos` (1879), `TShortIntHelper.SetBitsCount` (1879), `TShortIntHelper.Bits` (1879)

77.95.14 TShortIntHelper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TShortIntBitIndex) : ShortInt`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TShortIntHelper.SetBit` ([1882](#)), `TShortIntHelper.ToggleBit` ([1883](#)), `TShortIntHelper.TestBit` ([1883](#)), `TShortIntHelper.HighestSetBitPos` ([1879](#)), `TShortIntHelper.LowestSetBitPos` ([1879](#)), `TShortIntHelper.SetBitsCount` ([1879](#)), `TShortIntHelper.Bits` ([1879](#))

77.95.15 TShortIntHelper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TShortIntBitIndex) : ShortInt`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TShortIntHelper.SetBit` ([1882](#)), `TShortIntHelper.ClearBit` ([1883](#)), `TShortIntHelper.TestBit` ([1883](#)), `TShortIntHelper.HighestSetBitPos` ([1879](#)), `TShortIntHelper.LowestSetBitPos` ([1879](#)), `TShortIntHelper.SetBitsCount` ([1879](#)), `TShortIntHelper.Bits` ([1879](#))

77.95.16 TShortIntHelper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TShortIntBitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TShortIntHelper.SetBit` ([1882](#)), `TShortIntHelper.ClearBit` ([1883](#)), `TShortIntHelper.ToggleBit` ([1883](#)), `TShortIntHelper.HighestSetBitPos` ([1879](#)), `TShortIntHelper.LowestSetBitPos` ([1879](#)), `TShortIntHelper.SetBitsCount` ([1879](#)), `TShortIntHelper.Bits` ([1879](#))

77.96 TSimpleRWSync

77.96.1 Description

`TSimpleRWSync` implements a simple read/write locking mechanism. It controls access to an object: only a single thread is allowed access to an object for either read or write operations.

Access is controlled through a single critical section.

See also: `TMultiReadExclusiveWriteSynchronizer` ([1864](#))

77.96.2 Interfaces overview

Page	Interfaces	Description
1811	<code>IReadWriteSync</code>	Read/Write synchronizer

77.96.3 Method overview

Page	Method	Description
1885	<code>Beginread</code>	Acquire a read lock
1884	<code>Beginwrite</code>	Acquire a write lock
1884	<code>Create</code>	Create a new instance of <code>TSimpleRWSync</code>
1884	<code>Destroy</code>	Removes the <code>TSimpleRWSync</code> instance from memory
1885	<code>Endread</code>	Release the read lock
1885	<code>Endwrite</code>	Release the write lock

77.96.4 TSimpleRWSync.Create

Synopsis: Create a new instance of `TSimpleRWSync`

Declaration: `constructor Create; Virtual`

Visibility: `public`

Description: `Create` allocates a new instance of `TSimpleRWSync` and initializes the critical section for use in the various methods.

See also: `TSimpleRWSync.Destroy` ([1884](#))

77.96.5 TSimpleRWSync.Destroy

Synopsis: Removes the `TSimpleRWSync` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` releases the critical section and removes the `TSimpleRWSync` instance from memory.

See also: `TSimpleRWSync.Create` ([1884](#))

77.96.6 TSimpleRWSync.Beginwrite

Synopsis: Acquire a write lock

Declaration: `function Beginwrite : Boolean`

Visibility: `public`

Description: `Beginwrite` waits till all other threads have released their read or write locks on the object, and then acquires a write lock on the object.

See also: `TSimpleRWSync.BeginRead` ([1885](#)), `TSimpleRWSync.EndWrite` ([1885](#))

77.96.7 TSimpleRWSync.Endwrite

Synopsis: Release the write lock

Declaration: `procedure Endwrite`

Visibility: `public`

Description: `EndWrite` releases the current threads lock on the object, allowing other threads to acquire a read or write lock on the object.

See also: `TSimpleRWSync.BeginWrite` ([1884](#)), `TSimpleRWSync.EndRead` ([1885](#))

77.96.8 TSimpleRWSync.Beginread

Synopsis: Acquire a read lock

Declaration: `procedure Beginread`

Visibility: `public`

Description: `BeginRead` waits till all other threads have released their read or write locks on the object, and then acquires a read lock on the object.

See also: `TSimpleRWSync.BeginWrite` ([1884](#)), `TSimpleRWSync.EndRead` ([1885](#))

77.96.9 TSimpleRWSync.Endread

Synopsis: Release the read lock

Declaration: `procedure Endread`

Visibility: `public`

Description: `EndRead` releases the current threads read lock on the object, allowing other threads to acquire a read or write lock on the object.

See also: `TSimpleRWSync.BeginRead` ([1885](#)), `TSimpleRWSync.EndWrite` ([1885](#))

77.97 TSingleHelper

77.97.1 Description

`TSingleHelper` is the helper type for the single-sized floating point type. It contains some conversion methods, as well as access to the low-level structure of the floating-point representation of a single.

See also: `TDoubleHelper` ([1832](#)), `TExtendedHelper` ([1844](#))

77.97.2 Method overview

Page	Method	Description
1889	BuildUp	Build a single-sized floating point from its composing parts
1889	Exponent	Exponent of the floating-point value
1889	Fraction	Fraction of the floating-point value
1886	IsInfinity	Check whether a value is positive or negative infinity.
1886	IsNan	Check whether a value equals NaN.
1887	IsNegativeInfinity	Check whether a value is negative infinity.
1887	IsPositiveInfinity	Check whether a value is positive infinity.
1890	Mantissa	Mantissa of the floating-point
1887	Parse	Convert a string to a floating point value
1888	Size	Size (in bytes) of a single-sized floating point value.
1890	SpecialType	Return the type of the single-sized floating point value
1888	ToString	Convert a single-sized floating point value to a string
1889	TryParse	Try to convert a string to a single-sized floating point value.

77.97.3 Property overview

Page	Properties	Access	Description
1890	Bytes	rw	Indexed access to the individual bytes of the floating point value
1891	Exp	rw	The bit pattern of the exponent as stored in memory.
1891	Frac	rw	Bitpattern that makes up the fractional part.
1891	Sign	rw	Sign of the floating point value
1890	Words	rw	Indexed access to the words that make up the floating point value

77.97.4 TSingleHelper.IsNan

Synopsis: Check whether a value equals NaN.

Declaration: `class function IsNan(const AValue: Single) : Boolean; Overload; Static
function IsNan : Boolean; Overload`

Visibility: public

Description: `IsNan` checks whether a single-sized floating point value is NaN (Not a Number). If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TSingleHelper.IsInfinity` ([1886](#)), `TSingleHelper.IsPositiveInfinity` ([1887](#)), `TSingleHelper.IsNegativeInfinity` ([1887](#))

77.97.5 TSingleHelper.IsInfinity

Synopsis: Check whether a value is positive or negative infinity.

Declaration: `class function IsInfinity(const AValue: Single) : Boolean; Overload
; Static
function IsInfinity : Boolean; Overload`

Visibility: public

Description: `IsInfinity` checks whether a single-sized floating point value represents a positive or negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TSingleHelper.IsNan` ([1886](#)), `TSingleHelper.IsPositiveInfinity` ([1887](#)), `TSingleHelper.IsNegativeInfinity` ([1887](#))

77.97.6 `TSingleHelper.IsNegativeInfinity`

Synopsis: Check whether a value is negative infinity.

Declaration:

```
class function IsNegativeInfinity(const AValue: Single) : Boolean
                                ; Overload; Static
function IsNegativeInfinity : Boolean; Overload
```

Visibility: public

Description: `IsNegativeInfinity` checks whether a single-sized floating point value represents a negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TSingleHelper.IsNan` ([1886](#)), `TSingleHelper.IsPositiveInfinity` ([1887](#)), `TSingleHelper.IsInfinity` ([1886](#))

77.97.7 `TSingleHelper.IsPositiveInfinity`

Synopsis: Check whether a value is positive infinity.

Declaration:

```
class function IsPositiveInfinity(const AValue: Single) : Boolean
                                ; Overload; Static
function IsPositiveInfinity : Boolean; Overload
```

Visibility: public

Description: `IsPositiveInfinity` checks whether a single-sized floating point value represents a positive infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TSingleHelper.IsNan` ([1886](#)), `TSingleHelper.IsNegativeInfinity` ([1887](#)), `TSingleHelper.IsInfinity` ([1886](#))

77.97.8 `TSingleHelper.Parse`

Synopsis: Convert a string to a floating point value

Declaration:

```
class function Parse(const AString: string) : Single; Overload; Static
class function Parse(const AString: string;
                    const AFormatSettings: TFormatSettings) : Single
                    ; Overload; Static
```

Visibility: public

Description: `Parse` will try to convert `AString` to a single-sized floating point value. It will take into account internationalization settings. (it uses `FloatToStr`).

Errors: If the string `AString` is not a valid floating-point value, a `EConvertError` ([1800](#)) exception is raised.

See also: `FloatToStr` ([1708](#)), `TSingleHelper.ToString` ([1888](#)), `TSingleHelper.TryParse` ([1889](#))

77.97.9 TSingleHelper.Size

Synopsis: Size (in bytes) of a single-sized floating point value.

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size is the size (in bytes) of a single-sized floating point value. It is equivalent to calling `SizeOf (Single)`.

See also: `SizeOf` ([1547](#))

77.97.10 TSingleHelper.ToString

Synopsis: Convert a single-sized floating point value to a string

```
Declaration: class function ToString(const AValue: Single) : string; Overload
              ; Static
class function ToString(const AValue: Single;
                        const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
class function ToString(const AValue: Single;
                        const AFormat: TFloatFormat;
                        const APrecision: Integer;
                        const ADigits: Integer) : string; Overload
              ; Static
class function ToString(const AValue: Single;
                        const AFormat: TFloatFormat;
                        const APrecision: Integer;
                        const ADigits: Integer;
                        const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
function ToString(const AFormat: TFloatFormat;
                  const APrecision: Integer; const ADigits: Integer)
              : string; Overload
function ToString(const AFormat: TFloatFormat;
                  const APrecision: Integer; const ADigits: Integer;
                  const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString(const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString : string; Overload
```

Visibility: public

Description: ToString will convert AValue (or Self in the plain method version) to a string. Optionally FormatSettings can be specified, to be able to specify the decimal separator character to use.

Additionally, a precision APrecision and number of digits ADigits can be specified, in conjunction with a AFormat parameter to specify the form in which the floating-point value must be represented. (see TFloatFormat ([1636](#)) for an explanation of the various values). In this case, FloatToStrF ([1709](#)) is used to format the value. In the absence of these parameters, FloatToStr ([1708](#)) is called.

See also: `FloatToStr` ([1708](#)), `FloatToStrF` ([1709](#)), `TFloatFormat` ([1636](#))

77.97.11 TSingleHelper.TryParse

Synopsis: Try to convert a string to a single-sized floating point value.

Declaration: `class function TryParse(const AString: string; out AValue: Single) : Boolean; Overload; Static`
`class function TryParse(const AString: string; out AValue: Single; const AFormatSettings: TFormatSettings) : Boolean; Overload; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a single-sized floating point value and reports `True` if the conversion was successful. In that case the parsed value is returned in `AValue`.

If the conversion failed, `False` is returned.

See also: `TSingleHelper.Parse` ([1887](#)), `TSingleHelper.ToString` ([1888](#))

77.97.12 TSingleHelper.BuildUp

Synopsis: Build a single-sized floating point from its composing parts

Declaration: `procedure BuildUp(const ASignFlag: Boolean; const AMantissa: QWord; const AExponent: Integer)`

Visibility: public

Description: `BuildUp` will compose a single-sized floating point value from the sign `ASignFlag`, mantissa `AMantissa` and exponent `AExponent`. It simply sets the `Sign` ([1891](#)), `Exp` ([1891](#)) and `Frac` ([1891](#)) properties in 1 call.

See also: `TSingleHelper.Sign` ([1891](#)), `TSingleHelper.Exp` ([1891](#)), `TSingleHelper.Frac` ([1891](#))

77.97.13 TSingleHelper.Exponent

Synopsis: Exponent of the floating-point value

Declaration: `function Exponent : Integer`

Visibility: public

Description: `Exponent` is the value X in the representation of the floating-point value in $m \cdot 2^{\hat{X}}$, i.e. the exponent.

See also: `TSingleHelper.Sign` ([1891](#)), `TSingleHelper.Exp` ([1891](#)), `TSingleHelper.Frac` ([1891](#)), `TSingleHelper.Fraction` ([1889](#)), `TSingleHelper.Mantissa` ([1890](#))

77.97.14 TSingleHelper.Fraction

Synopsis: Fraction of the floating-point value

Declaration: `function Fraction : Extended`

Visibility: public

Description: `Fraction` is the decimal part of the floating-point value.

See also: `TSingleHelper.Sign` ([1891](#)), `TSingleHelper.Exp` ([1891](#)), `TSingleHelper.Exponent` ([1889](#)), `TSingleHelper.Frac` ([1891](#)), `TSingleHelper.Mantissa` ([1890](#))

77.97.15 TSingleHelper.Mantissa

Synopsis: Mantissa of the floating-point

Declaration: `function Mantissa : QWord`

Visibility: public

Description: `Mantissa` is the value of the significant without the hidden bit. This means it the plain bit pattern as it is stored in memory.

See also: `TSingleHelper.Sign` ([1891](#)), `TSingleHelper.Exp` ([1891](#)), `TSingleHelper.Exponent` ([1889](#)), `TSingleHelper.Frac` ([1891](#)), `TSingleHelper.Fraction` ([1889](#))

77.97.16 TSingleHelper.SpecialType

Synopsis: Return the type of the single-sized floating point value

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` checks whether the single-sized floating point value equals one of several special values, and returns an enumerated value describing which value this is. See `TFloatSpecial` ([1615](#)) for an explanation of the possible values.

See also: `TFloatSpecial` ([1615](#))

77.97.17 TSingleHelper.Bytes

Synopsis: Indexed access to the individual bytes of the floating point value

Declaration: `Property Bytes[AIndex: Cardinal]: Byte`

Visibility: public

Access: Read,Write

Description: `Bytes` can be used to get or set the various bytes that make up the single-sized floating point value. The index runs from 0 to `Size-1`.

See also: `TSingleHelper.Words` ([1890](#)), `TSingleHelper.Size` ([1888](#))

77.97.18 TSingleHelper.Words

Synopsis: Indexed access to the words that make up the floating point value

Declaration: `Property Words[AIndex: Cardinal]: Word`

Visibility: public

Access: Read,Write

Description: `Words` can be used to get or set the various bytes that make up the single-sized floating point value. The index runs from 0 to $(\text{Size}-1) \div 2$.

See also: `TSingleHelper.Bytes` ([1890](#)), `TSingleHelper.Size` ([1888](#))

77.97.19 TSingleHelper.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

Description: `Sign` returns `True` if the sign bit of the value is set (i.e. it is a negative value) or `False` if it is not set (i.e. it is a positive value).

See also: `TSingleHelper.Bytes` (1890), `TSingleHelper.Exp` (1891), `TSingleHelper.Frac` (1891), `TSingleHelper.Mantissa` (1890), `TSingleHelper.Fraction` (1889), `TSingleHelper.Exponent` (1889)

77.97.20 TSingleHelper.Exp

Synopsis: The bit pattern of the exponent as stored in memory.

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` is the internal representation of the Exponent (1889).

See also: `TSingleHelper.Bytes` (1890), `TSingleHelper.Sign` (1891), `TSingleHelper.Frac` (1891), `TSingleHelper.Mantissa` (1890), `TSingleHelper.Fraction` (1889), `TSingleHelper.Exponent` (1889)

77.97.21 TSingleHelper.Frac

Synopsis: Bitpattern that makes up the fractional part.

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: `Frac` is the bit pattern representing the fractional part (significand) including the preceding 1 (the hidden bit).

See also: `TSingleHelper.Bytes` (1890), `TSingleHelper.Sign` (1891), `TSingleHelper.Exp` (1891), `TSingleHelper.Mantissa` (1890), `TSingleHelper.Fraction` (1889), `TSingleHelper.Exponent` (1889)

77.98 TSmallIntHelper**77.98.1 Description**

`TSmallIntHelper` contains some auxiliary routines for a `SmallInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1895), `TShortIntHelper` (1879), `TByteHelper` (1824), `TWordHelper` (1929), `TCardinalHelper` (1828), `TIntegerHelper` (1856), `TInt64Helper` (1852), `TQWordHelper` (1875), `TNativeIntHelper` (1867), `TNativeUIntHelper` (1871)

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `SmallInt` value itself is used. The `IntToStr` (1736) function is used to do the conversion.

See also: `TSmallIntHelper.Parse` (1892), `IntToStr` (1736)

77.98.6 TSmallIntHelper.TryParse

Synopsis: Try to convert a string to a `SmallInt`, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: SmallInt) : Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `SmallInt`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `SmallInt` is returned in `AValue`.

It uses the `val` (1615) function to perform the conversion, so no localization is taken into account.

See also: `TSmallIntHelper.Parse` (1892), `Val` (1570)

77.98.7 TSmallIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `SmallInt` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TSmallIntHelper.ToSingle` (1894), `TSmallIntHelper.ToDouble` (1894), `TSmallIntHelper.ToExtended` (1894), `TSmallIntHelper.ToString` (1892), `TSmallIntHelper.ToHexString` (1893)

77.98.8 TSmallIntHelper.ToBinString

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: public

Description: `ToBinString` converts the `smallint` value to a binary string representation, showing all 16 bits.

See also: `TSmallIntHelper.ToHexString` (1893), `TSmallIntHelper.ToString` (1892)

77.98.9 TSmallIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString : string; Overload`
`function ToHexString(const AMinDigits: Integer) : string; Overload`

Visibility: public

Description: `ToHexString` converts the `SmallInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TSmallIntHelper.ToBoolean` (1893), `TSmallIntHelper.ToSingle` (1894), `TSmallIntHelper.ToDouble` (1894), `TSmallIntHelper.ToString` (1892), `TSmallIntHelper.ToExtended` (1894)

77.98.10 TSmallIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: `public`

Description: `ToSingle` converts the `SmallInt` value to a single-sized floating point value.

See also: `TSmallIntHelper.ToBoolean` (1893), `TSmallIntHelper.ToDouble` (1894), `TSmallIntHelper.ToExtended` (1894), `TSmallIntHelper.ToString` (1892), `TSmallIntHelper.ToHexString` (1893)

77.98.11 TSmallIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: `public`

Description: `ToDouble` converts the `SmallInt` value to a double-sized floating point value

See also: `TSmallIntHelper.ToBoolean` (1893), `TSmallIntHelper.ToExtended` (1894), `TSmallIntHelper.ToSingle` (1894), `TSmallIntHelper.ToString` (1892), `TSmallIntHelper.ToHexString` (1893)

77.98.12 TSmallIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: `public`

Description: `ToDouble` converts the `SmallInt` value to an extended-sized floating point value.

See also: `TSmallIntHelper.ToBoolean` (1893), `TSmallIntHelper.ToSingle` (1894), `TSmallIntHelper.ToDouble` (1894), `TSmallIntHelper.ToString` (1892), `TSmallIntHelper.ToHexString` (1893)

77.98.13 TSmallIntHelper.SetBit

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TSmallIntBitIndex) : SmallInt`

Visibility: `public`

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TSmallIntHelper.ClearBit` (1895), `TSmallIntHelper.ToggleBit` (1895), `TSmallIntHelper.TestBit` (1895), `TSmallIntHelper.HighestSetBitPos` (1891), `TSmallIntHelper.LowestSetBitPos` (1891), `TSmallIntHelper.SetBitsCount` (1891), `TSmallIntHelper.Bits` (1891)

77.98.14 TSmallIntHelper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TSmallIntBitIndex) : SmallInt`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TSmallIntHelper.SetBit` (1894), `TSmallIntHelper.ToggleBit` (1895), `TSmallIntHelper.TestBit` (1895), `TSmallIntHelper.HighestSetBitPos` (1891), `TSmallIntHelper.LowestSetBitPos` (1891), `TSmallIntHelper.SetBitsCount` (1891), `TSmallIntHelper.Bits` (1891)

77.98.15 TSmallIntHelper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TSmallIntBitIndex) : SmallInt`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TSmallIntHelper.SetBit` (1894), `TSmallIntHelper.ToggleBit` (1895), `TSmallIntHelper.TestBit` (1895), `TSmallIntHelper.HighestSetBitPos` (1891), `TSmallIntHelper.LowestSetBitPos` (1891), `TSmallIntHelper.SetBitsCount` (1891), `TSmallIntHelper.Bits` (1891)

77.98.16 TSmallIntHelper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TSmallIntBitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TSmallIntHelper.SetBit` (1894), `TSmallIntHelper.ToggleBit` (1895), `TSmallIntHelper.TestBit` (1895), `TSmallIntHelper.HighestSetBitPos` (1891), `TSmallIntHelper.LowestSetBitPos` (1891), `TSmallIntHelper.SetBitsCount` (1891), `TSmallIntHelper.Bits` (1891)

77.99 TStringHelper

77.99.1 Description

`TStringHelper` adds various helper routines to the string type. These are mostly conversion routines, and some formatting routines.

For similarity to C-like languages, all the indexes in these helper routines are zero based.

See also: `TGUIDHelper` (1850)

77.99.2 Method overview

Page	Method	Description
1898	Compare	Compare 2 strings
1899	CompareOrdinal	Compare 2 strings byte for byte
1899	CompareText	Compare 2 strings case insensitively.
1905	CompareTo	Compare string to another
1905	Contains	Check if the string contains another
1899	Copy	Return a unique copy of a string
1905	CopyTo	Copy part of the string to an array of characters
1905	CountChar	Count the occurrences of a character
1900	Create	Create a new string
1906	DeQuotedString	Return a dequoted version of the string
1900	EndsText	Check if one string is the ending of another.
1906	EndsWith	Check if the string is ended by another.
1900	Equals	Check if 2 strings are equal
1901	Format	Format a string using provided arguments.
1906	GetHashCode	Get a hash code for the string
1906	IndexOf	Find the position (index) of a string or character
1907	IndexOfAny	Find the position (index) of any string or character in a list.
1908	IndexOfAnyUnquoted	Find the position (index) of any string or character in a list.
1907	IndexOfUnQuoted	Index of string, skipping quoted parts.
1908	Insert	Insert a string at a given position
1909	IsDelimiter	Check whether a character at a given position is a delimiter
1909	IsEmpty	Check whether the string is empty.
1901	IsNullOrEmpty	Check if a string is empty
1901	IsNullOrWhiteSpace	Check if a string is empty or contains only whitespace characters.
1901	Join	Join a series of strings, separated using a given separator
1909	LastDelimiter	Return the last position of one of a series of delimiters
1909	LastIndexOf	Find the last position (index) of a string or character
1910	LastIndexOfAny	Find the last position (index) of any string or character in a list.
1902	LowerCase	Return the lowercase version of a string.
1910	PadLeft	Pad the string on the left with an indicated character
1911	PadRight	Pad the string on the right with an indicated character
1902	Parse	Return a string representation of the argument
1911	QuotedString	Return a quoted version of the string
1911	Remove	Remove a number of characters from the string
1912	Replace	Replace occurrences of one string with another.
1912	Split	Split a string in a number of parts
1913	StartsWith	Check if one string starts with another
1913	Substring	Return a part of the string
1902	ToBoolean	Convert string to boolean
1914	ToCharArray	Return the string as an array of characters.
1903	ToDouble	Convert string to double-sized floating point value
1903	ToExtended	Convert string to extended-sized floating point value
1903	ToInt64	Convert string to 64-bit signed integer
1904	ToInteger	Convert string to 32-bit signed integer
1914	ToLower	Convert to lowercase
1914	ToLowerInvariant	Convert to lowercase
1904	ToSingle	Convert string to single-sized floating point value
1914	ToUpper	Convert to uppercase.
1915	ToUpperInvariant	Convert to uppercase
1915	Trim	Strips a set of trim characters from the beginning and end of the string.
1916	TrimEnd	Alias for TrimRight
1915	TrimLeft	Strips a set of trim characters from the beginning of the string.
1915	TrimRight	Strips a set of trim characters from the end of the string.
1916	TrimStart	Alias for TrimLeft
1904	UpperCase	Return uppercase version of a string

77.99.3 Property overview

Page	Properties	Access	Description
1916	Chars	r	Zero-based Indexed access to the characters in the string.
1916	Length	r	Return the length of the string

77.99.4 TStringHelper.Compare

Synopsis: Compare 2 strings

```

Declaration: class function Compare(const A: string; const B: string) : Integer
                ; Overload; Static
class function Compare(const A: string; const B: string;
                IgnoreCase: Boolean) : Integer; Overload; Static
class function Compare(const A: string; const B: string;
                Options: TCompareOptions) : Integer; Overload
                ; Static
class function Compare(const A: string; IndexA: SizeInt;
                const B: string; IndexB: SizeInt; ALen: SizeInt)
                : Integer; Overload; Static
class function Compare(const A: string; IndexA: SizeInt;
                const B: string; IndexB: SizeInt; ALen: SizeInt;
                IgnoreCase: Boolean) : Integer; Overload; Static
class function Compare(const A: string; IndexA: SizeInt;
                const B: string; IndexB: SizeInt; ALen: SizeInt;
                Options: TCompareOptions) : Integer; Overload
                ; Static

```

Visibility: public

Description: Compare compares strings A and B. It returns the following result:

- 0 if the strings are equal
- a negative number if $A < B$
- a positive number if $A > B$

The comparison can be influenced by using the appropriate overloaded version of the function.

- If the `IndexA` and `IndexB` parameters are present, the comparison starts at character index `IndexA` and `IndexB`. The indexes are zero-based.
- If the `ALen` parameter is present, then only the first `ALen` characters are compared. If not enough characters are present in either `A` or `B`, the comparison will include only as much characters as are present.
- If `IgnoreCase` is present and used, it determines whether the comparison is done case-sensitively. This form is deprecated, it is recommended to use the `AOptions` parameter and to include `coIgnoreCase`.
- The `AOptions` argument can be used to specify additional options. See `TCompareOption` (1388) for a list of possible values in this set.

Errors: None.

See also: [TStringHelper.CompareOrdinal \(1899\)](#), [TCompareOption \(1388\)](#), [TStringHelper.CompareTo \(1905\)](#)

77.99.5 TStringHelper.CompareOrdinal

Synopsis: Compare 2 strings byte for byte

Declaration: `class function CompareOrdinal(const A: string; const B: string) : Integer; Overload; Static`
`class function CompareOrdinal(const A: string; IndexA: SizeInt; const B: string; IndexB: SizeInt; ALen: SizeInt) : Integer; Overload; Static`

Visibility: public

Description: `CompareOrdinal` compares 2 strings A and B bitwise. It is faster than a regular compare, but offers less options.

- 0 if the strings are equal
- a negative number if $A < B$
- a positive number if $A > B$

Optionally, a zero-based starting index for the compare can be given for each of the strings: `IndexA` and `IndexB`. In this case a maximum amount of characters (`ALen`) to be compared must also be specified.

Errors: None.

See also: `TStringHelper.Compare` ([1898](#)), `TStringHelper.CompareTo` ([1905](#))

77.99.6 TStringHelper.CompareText

Synopsis: Compare 2 strings case insensitively.

Declaration: `class function CompareText(const A: string; const B: string) : Integer; Static`

Visibility: public

Description: `CompareText` simply calls `SysUtils` ([1670](#)) with the 2 passed arguments.

Errors: None.

See also: `SysUtils` ([1670](#)), `TStringHelper.CompareTo` ([1905](#))

77.99.7 TStringHelper.Copy

Synopsis: Return a unique copy of a string

Declaration: `class function Copy(const Str: string) : string; Static`

Visibility: public

Description: `Copy` will copy the string on which it operates, and makes sure the result has reference count 1.

See also: `UniqueString` ([1615](#))

77.99.11 TStringHelper.Format

Synopsis: Format a string using provided arguments.

Declaration: `class function Format(const AFormat: string; const args: Array of const) : string; Overload; Static`
`function Format(const args: Array of const) : string; Overload`

Visibility: public

Description: `Format` just calls `Sysutils.Format` (1714), passing on `AFormat` and `Args`. If `AFormat` is omitted, the string itself is used as the formatting string.

See also: `Sysutils.Format` (1714)

77.99.12 TStringHelper.IsNullOrEmpty

Synopsis: Check if a string is empty

Declaration: `class function IsNullOrEmpty(const AValue: string) : Boolean; Static`

Visibility: public

Description: `IsNullOrEmpty` returns `True` if string `A` has length 0.

See also: `System.Length` (1615), `TStringHelper.IsNullOrEmptyWhiteSpace` (1901)

77.99.13 TStringHelper.IsNullOrEmptyWhiteSpace

Synopsis: Check if a string is empty or contains only whitespace characters.

Declaration: `class function IsNullOrEmptyWhiteSpace(const AValue: string) : Boolean`
`; Static`

Visibility: public

Description: `IsNullOrEmpty` returns `True` if string `A` has length 0 or contains only whitespace characters (characters with ASCII code 32 or less).

See also: `TStringHelper.IsNullOrEmpty` (1901), `Trim` (1779)

77.99.14 TStringHelper.Join

Synopsis: Join a series of strings, separated using a given separator

Declaration: `class function Join(const Separator: string;`
`const Values: Array of const) : string; Overload`
`; Static`
`class function Join(const Separator: string;`
`const Values: Array of string) : string; Overload`
`; Static`
`class function Join(const Separator: string;`
`const Values: Array of string; StartIndex: SizeInt;`
`ACount: SizeInt) : string; Overload; Static`

Visibility: public

In case an array of strings is passed on, a start index `StartIndex` and element count `ACount` can be passed on as well.

See also: [TStringHelper.Split \(1912\)](#)

Synopsis: Return the lowercase version of a string.

Visibility: public

See also: [sysutils.LowerCase \(1740\)](#)

Synopsis: Return a string representation of the argument

Visibility: public

Integer the result is formatted using `IntToStr` (1736).

Synopsis: Convert string to boolean

Visibility: public

Description: `ToBoolean` returns the contents of the string `S` as a boolean (if possible). It uses `StrToBool` (1763) to convert the value to a boolean.

Errors: If the string contains a value that cannot be translated to a boolean, an `EConvertError` (1800) exception may be raised.

See also: `StrToBool` (1763), `EConvertError` (1800), `TStringHelper.ToDouble` (1903), `TStringHelper.ToExtended` (1903), `TStringHelper.ToInt64` (1903), `TStringHelper.ToInteger` (1904), `TStringHelper.ToSingle` (1904)

77.99.18 TStringHelper.ToDouble

Synopsis: Convert string to double-sized floating point value

Declaration: `class function ToDouble(const S: string) : Double; Overload; Static
function ToDouble : Double; Overload`

Visibility: public

Description: `ToDouble` returns the contents of the string `S` as a Double-sized floating point value (if possible). It uses `StrToFloat` (1768) to convert the value to a floating point value.

Errors: If the string contains a value that cannot be translated to a floating point value, an `EConvertError` (1800) exception may be raised.

See also: `StrToFloat` (1768), `EConvertError` (1800), `TStringHelper.ToBoolean` (1902), `TStringHelper.ToExtended` (1903), `TStringHelper.ToInt64` (1903), `TStringHelper.ToInteger` (1904), `TStringHelper.ToSingle` (1904)

77.99.19 TStringHelper.ToExtended

Synopsis: Convert string to extended-sized floating point value

Declaration: `class function ToExtended(const S: string) : Extended; Overload
; Static
function ToExtended : Extended; Overload`

Visibility: public

Description: `ToExtended` returns the contents of the string `S` as a Extended-sized floating point value (if possible). It uses `StrToFloat` (1768) to convert the value to a floating point value.

Errors: If the string contains a value that cannot be translated to a floating point value, an `EConvertError` (1800) exception may be raised.

See also: `StrToFloat` (1768), `EConvertError` (1800), `TStringHelper.ToBoolean` (1902), `TStringHelper.ToDouble` (1903), `TStringHelper.ToInt64` (1903), `TStringHelper.ToInteger` (1904), `TStringHelper.ToSingle` (1904)

77.99.20 TStringHelper.ToInt64

Synopsis: Convert string to 64-bit signed integer

Declaration: `class function ToInt64(const S: string) : Int64; Overload; Static
function ToInt64 : Int64; Overload`

Visibility: public

Description: `ToInt64` returns the contents of the string `S` as a 64-bit signed integer value (if possible). It uses `StrToInt64` (1770) to convert the value to an 64-bit sized integer value.

Errors: If the string contains a value that cannot be translated to an integer value, an `EConvertError` (1800) exception may be raised.

See also: `StrToInt64` (1770), `EConvertError` (1800), `TStringHelper.ToBoolean` (1902), `TStringHelper.ToDouble` (1903), `TStringHelper.ToExtended` (1903), `TStringHelper.ToInteger` (1904), `TStringHelper.ToSingle` (1904)

77.99.21 `TStringHelper.ToInteger`

Synopsis: Convert string to 32-bit signed integer

Declaration: `class function ToInteger(const S: string) : Integer; Overload; Static
function ToInteger : Integer; Overload`

Visibility: public

Description: `ToInteger` returns the contents of the string `S` as a 32-bit signed integer value (if possible). It uses `StrToInt64` (1770) to convert the value to an 64-bit sized integer value.

Errors: If the string contains a value that cannot be translated to an integer value, an `EConvertError` (1800) exception may be raised.

See also: `StrToInt64` (1770), `EConvertError` (1800), `TStringHelper.ToBoolean` (1902), `TStringHelper.ToDouble` (1903), `TStringHelper.ToExtended` (1903), `TStringHelper.ToInt64` (1903), `TStringHelper.ToSingle` (1904)

77.99.22 `TStringHelper.ToSingle`

Synopsis: Convert string to single-sized floating point value

Declaration: `class function ToSingle(const S: string) : Single; Overload; Static
function ToSingle : Single; Overload`

Visibility: public

Description: `ToSingle` returns the contents of the string `S` as a single-sized floating point value (if possible). It uses `StrToFloat` (1768) to convert the value to a floating point value.

Errors: If the string contains a value that cannot be translated to a floating point value, an `EConvertError` (1800) exception may be raised.

See also: `StrToFloat` (1768), `EConvertError` (1800), `TStringHelper.ToBoolean` (1902), `TStringHelper.ToDouble` (1903), `TStringHelper.ToInt64` (1903), `TStringHelper.ToInteger` (1904), `TStringHelper.ToExtended` (1903)

77.99.23 `TStringHelper.UpperCase`

Synopsis: Return uppercase version of a string

Declaration: `class function UpperCase(const S: string) : string; Overload; Static`

Visibility: public

Description: `UpperCase` returns an uppercase version of the string `S`.

See also: `#rtl.sysutils.UpperCase` (1790)

77.99.24 TStringHelper.CompareTo

Synopsis: Compare string to another

Declaration: `function CompareTo(const B: string) : Integer`

Visibility: public

Description: `CompareTo` will compare the string value to the string B. It returns the following result:

- 0 if the strings are equal
- a negative number if `Self < B`
- a positive number if `Self > B`

The `StrComp` ([1751](#)) function is used for this.

See also: `TStringHelper.Compare` ([1898](#)), `TStringHelper.CompareOrdinal` ([1899](#)), `StrComp` ([1751](#))

77.99.25 TStringHelper.Contains

Synopsis: Check is the string contains another

Declaration: `function Contains(const AValue: string) : Boolean`

Visibility: public

Description: `Contains` returns `True` if the string value contains `AValue`, i.e. it returns `Pos(Self, AValue) > 0`.

See also: `Pos` ([1518](#))

77.99.26 TStringHelper.CopyTo

Synopsis: Copy part of the string to an array of characters

Declaration: `procedure CopyTo(SourceIndex: SizeInt; var destination: Array of Char;
DestinationIndex: SizeInt; ACount: SizeInt)`

Visibility: public

Description: `CopyTo` copies at most `ACount` characters from the source string (`Self`) to the array `Destination`, starting at (zero based) index `SourceIndex`. The characters are copied to the array starting at position `DestinationIndex` (zero based).

See also: `Copy` ([1449](#))

77.99.27 TStringHelper.CountChar

Synopsis: Count the occurrences of a character

Declaration: `function CountChar(const C: Char) : SizeInt`

Visibility: public

Description: `CountChar` returns the number of occurrences of `C` in the string (`Self`).

See also: `TStringHelper.IndexOf` ([1906](#)), `TStringHelper.IndexOfAny` ([1907](#))

77.99.28 TStringHelper.DeQuotedString

Synopsis: Return a dequoted version of the string

Declaration: `function DeQuotedString : string; Overload`
`function DeQuotedString(const AQuoteChar: Char) : string; Overload`

Visibility: public

Description: `DeQuotedString` will return a dequoted version of the string (`Self`), where the quote character is `AQuoteChar` (default: a single quote `'`). The string must start and end with the quote character, or it is returned as-is. Any double occurrences of the quote character `AQuoteChar` will be returned as a single quote.

See also: `AnsiQuotedString` ([1615](#)), `AnsiExtractQuotedString` ([1615](#))

77.99.29 TStringHelper.EndsWith

Synopsis: Check if the string is ended by another.

Declaration: `function EndsWith(const AValue: string) : Boolean; Overload`
`function EndsWith(const AValue: string; IgnoreCase: Boolean) : Boolean`
`; Overload`

Visibility: public

Description: `EndsWith` returns `True` if the string (`Self`) ends on `AValue`, i.e. whether the last characters in `Self` are the ones found in `AValue`. The comparison is done case insensitively depending on the `IgnoreCase` argument (which is false by default).

See also: `CompareText` ([1670](#)), `TStringHelper.EndsWithText` ([1900](#))

77.99.30 TStringHelper.GetHashCode

Synopsis: Get a hash code for the string

Declaration: `function GetHashCode : Integer`

Visibility: public

Description: `GetHashCode` returns a hash value for the string (`Self`).

77.99.31 TStringHelper.IndexOf

Synopsis: Find the position (index) of a string or character

Declaration: `function IndexOf(AValue: Char) : SizeInt; Overload`
`function IndexOf(const AValue: string) : SizeInt; Overload`
`function IndexOf(AValue: Char; StartIndex: SizeInt) : SizeInt; Overload`
`function IndexOf(const AValue: string; StartIndex: SizeInt) : SizeInt`
`; Overload`
`function IndexOf(AValue: Char; StartIndex: SizeInt; ACount: SizeInt)`
`: SizeInt; Overload`
`function IndexOf(const AValue: string; StartIndex: SizeInt;`
`ACount: SizeInt) : SizeInt; Overload`

Visibility: public

Description: `IndexOf` returns the zero-based index of `AValue` in the string (`Self`). The value to search for can be a character or string (`AValue`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero based) index `StartIndex`. When specified, the search will start at the given character. Not specifying this option is equivalent to specifying zero.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying the amount of remaining characters.

See also: `Pos` ([1518](#)), `TStringHelper.IndexOfUnQuoted` ([1907](#)), `TStringHelper.IndexOfAny` ([1907](#)), `TStringHelper.IndexOfAnyUnquoted` ([1908](#)), `TStringHelper.LastIndexOf` ([1909](#)), `TStringHelper.LastIndexOfAny` ([1910](#))

77.99.32 TStringHelper.IndexOfUnQuoted

Synopsis: Index of string, skipping quoted parts.

Declaration:

```
function IndexOfUnQuoted(const AValue: string; StartQuote: Char;
                        EndQuote: Char; StartIndex: SizeInt) : SizeInt
; Overload
```

Visibility: public

Description: `IndexOfUnQuoted` will return the zero-based index of `AValue` in the string (`Self`), but disregards any quoted parts in the string. A quoted part is determined by a starting `StartQuote` and end-quote character `EndQuote`. The search starts at (zero-based) position `StartIndex`, which is by default 0.

See also: `Pos` ([1518](#)), `TStringHelper.IndexOf` ([1906](#)), `TStringHelper.IndexOfAny` ([1907](#)), `TStringHelper.IndexOfAnyUnquoted` ([1908](#)), `TStringHelper.LastIndexOf` ([1909](#)), `TStringHelper.LastIndexOfAny` ([1910](#))

77.99.33 TStringHelper.IndexOfAny

Synopsis: Find the position (index) of any string or character in a list.

Declaration:

```
function IndexOfAny(const AnyOf: Array of Char) : SizeInt; Overload
function IndexOfAny(const AnyOf: Array of Char; StartIndex: SizeInt)
: SizeInt; Overload
function IndexOfAny(const AnyOf: Array of Char; StartIndex: SizeInt;
                    ACount: SizeInt) : SizeInt; Overload
function IndexOfAny(const AnyOf: Array of string) : SizeInt; Overload
function IndexOfAny(const AnyOf: Array of string; StartIndex: SizeInt)
: SizeInt; Overload
function IndexOfAny(const AnyOf: Array of string; StartIndex: SizeInt;
                    ACount: SizeInt) : SizeInt; Overload
function IndexOfAny(const AnyOf: Array of string; StartIndex: SizeInt;
                    ACount: SizeInt; out AMatch: SizeInt) : SizeInt
; Overload
```

Visibility: public

Description: `IndexOfAny` returns the zero-based index of the first matching element in an array of characters or strings (`AnyOf`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero-based) index `StartIndex`. When specified, the search will start at the given character. Not specifying this option is equivalent to specifying zero.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying the amount of remaining characters.

If `AMatch` is specified, on successful return it will contain the index of the element in the array that contains the found match.

See also: `Pos` (1518), `TStringHelper.IndexOf` (1906), `TStringHelper.IndexOfUnquoted` (1907), `TStringHelper.IndexOfAnyUnquoted` (1908), `TStringHelper.LastIndexOf` (1909), `TStringHelper.LastIndexOfAny` (1910)

77.99.34 TStringHelper.IndexOfAnyUnquoted

Synopsis: Find the position (index) of any string or character in a list.

Declaration:

```
function IndexOfAnyUnquoted(const AnyOf: Array of Char;
                           StartQuote: Char; EndQuote: Char) : SizeInt
                           ; Overload
function IndexOfAnyUnquoted(const AnyOf: Array of Char;
                           StartQuote: Char; EndQuote: Char;
                           StartIndex: SizeInt) : SizeInt; Overload
function IndexOfAnyUnquoted(const AnyOf: Array of Char;
                           StartQuote: Char; EndQuote: Char;
                           StartIndex: SizeInt; ACount: SizeInt)
                           : SizeInt; Overload
function IndexOfAnyUnquoted(const AnyOf: Array of string;
                           StartQuote: Char; EndQuote: Char;
                           StartIndex: SizeInt; out Matched: SizeInt)
                           : SizeInt; Overload
```

Visibility: public

Description: `IndexOfAnyUnquoted` returns the zero-based index of the first matching element in an array of characters or strings (`AnyOf`), but disregards any quoted parts in the string. A quoted part is determined by a starting `StartQuote` and end-quote character `EndQuote`.

if no match is found, -1 is returned.

The search can be refined by specifying a (zero-based) index `StartIndex`. When specified, the search will start at the given character. Not specifying this option is equivalent to specifying zero.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying the amount of remaining characters.

If `AMatch` is specified, on successful return it will contain the index of the element in the array that contains the found match.

See also: `Pos` (1518), `TStringHelper.IndexOf` (1906), `TStringHelper.IndexOfUnquoted` (1907), `TStringHelper.IndexOfAny` (1907), `TStringHelper.LastIndexOf` (1909), `TStringHelper.LastIndexOfAny` (1910)

77.99.35 TStringHelper.Insert

Synopsis: Insert a string at a given position

Declaration:

```
function Insert(StartIndex: SizeInt; const AValue: string) : string
```

Visibility: public

Description: Insert inserts the string AValue in a string (Self) at the (zero-based) position StartIndex. It returns the resulting string (Self). If StartIndex is less than zero, it is set to zero. If StartIndex is higher than the length, AValue is appended to the string.

See also: Insert ([1496](#))

77.99.36 TStringHelper.IsDelimiter

Synopsis: Check whether a character at a given position is a delimiter

Declaration: function IsDelimiter(const Delimiters: string; Index: SizeInt) : Boolean

Visibility: public

Description: IsDelimiter returns True if the character at (zero-based) position Index is one of the delimiter characters in Delimiters. If Index is out of range, False is returned.

See also: IsDelimiter ([1736](#))

77.99.37 TStringHelper.IsEmpty

Synopsis: Check whether the string is empty.

Declaration: function IsEmpty : Boolean

Visibility: public

Description: IsEmpty returns True if the string has length zero.

See also: TStringHelper.IsNullOrEmpty ([1901](#)), TStringHelper.Length ([1916](#)), Length ([1503](#))

77.99.38 TStringHelper.LastDelimiter

Synopsis: Return the last position of one of a series of delimiters

Declaration: function LastDelimiter(const Delims: string) : SizeInt

Visibility: public

Description: LastDelimiter searches the string backwards for an occurrence of one of the characters in Delims, and returns the corresponding (zero-based) index in the string. If no occurrence is found, -1 is returned.

See also: TStringHelper.isDelimiter ([1909](#)), TStringHelper.IndexOf ([1906](#)), TStringHelper.IndexOfAny ([1907](#)), TStringHelper.LastIndexOf ([1909](#)), TStringHelper.LastIndexOfAny ([1910](#))

77.99.39 TStringHelper.LastIndexOf

Synopsis: Find the last position (index) of a string or character

Declaration: function LastIndexOf(AValue: Char) : SizeInt; Overload
function LastIndexOf(const AValue: string) : SizeInt; Overload
function LastIndexOf(AValue: Char; AStartIndex: SizeInt) : SizeInt
; Overload
function LastIndexOf(const AValue: string; AStartIndex: SizeInt)

```

        : SizeInt; Overload
function LastIndexOf(AValue: Char; AStartIndex: SizeInt;
        ACount: SizeInt) : SizeInt; Overload
function LastIndexOf(const AValue: string; AStartIndex: SizeInt;
        ACount: SizeInt) : SizeInt; Overload

```

Visibility: public

Description: `LastIndexOf` returns the zero-based index of the last occurrence of `AValue` in the string (`Self`). The value to search for can be a character or string (`AValue`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero based) index `StartIndex`. When specified, the search will start at the given character and proceeds towards the beginning of the string. Not specifying this option is equivalent to specifying `length-1`.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying `StartIndex+1`.

See also: `Pos` ([1518](#)), `TStringHelper.IndexOfUnquoted` ([1907](#)), `TStringHelper.IndexOfAny` ([1907](#)), `TStringHelper.IndexOfAnyUnquoted` ([1908](#)), `TStringHelper.IndexOf` ([1906](#)), `TStringHelper.LastIndexOfAny` ([1910](#))

77.99.40 TStringHelper.LastIndexOfAny

Synopsis: Find the last position (index) of any string or character in a list.

```

Declaration: function LastIndexOfAny(const AnyOf: Array of Char) : SizeInt; Overload
function LastIndexOfAny(const AnyOf: Array of Char;
        AStartIndex: SizeInt) : SizeInt; Overload
function LastIndexOfAny(const AnyOf: Array of Char;
        AStartIndex: SizeInt; ACount: SizeInt) : SizeInt
; Overload

```

Visibility: public

Description: `LastIndexOfAny` returns the zero-based index of the first matching element in an array of characters or strings (`AnyOf`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero-based) index `StartIndex`. When specified, the search will start at the given character and proceeds to the start of the string. Not specifying this option is equivalent to specifying `Length-1`.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying `StartIndex+1`.

See also: `Pos` ([1518](#)), `TStringHelper.IndexOf` ([1906](#)), `TStringHelper.IndexOfUnquoted` ([1907](#)), `TStringHelper.IndexOfAnyUnquoted` ([1908](#)), `TStringHelper.LastIndexOf` ([1909](#)), `TStringHelper.IndexOfAny` ([1907](#))

77.99.41 TStringHelper.PadLeft

Synopsis: Pad the string on the left with an indicated character

```

Declaration: function PadLeft(ATotalWidth: SizeInt) : string; Overload
function PadLeft(ATotalWidth: SizeInt; PaddingChar: Char) : string
; Overload

```

Visibility: public

Description: `PadLeft` pads the string (`Self`) on the left (i.e. at the beginning) till it reaches length `ATotalWidth` with character `PaddingChar`. If `PaddingChar` is omitted, a space is used.

See also: `TStringHelper.PadRight` ([1911](#))

77.99.42 `TStringHelper.PadRight`

Synopsis: Pad the string on the right with an indicated character

Declaration:

```
function PadRight(ATotalWidth: SizeInt) : string; Overload
function PadRight(ATotalWidth: SizeInt; PaddingChar: Char) : string
; Overload
```

Visibility: public

Description: `PadLeft` pads the string (`Self`) on the right (i.e. at the end) till it reaches length `ATotalWidth` with character `PaddingChar`. If `PaddingChar` is omitted, a space is used.

See also: `TStringHelper.PadLeft` ([1910](#))

77.99.43 `TStringHelper.QuotedString`

Synopsis: Return a quoted version of the string

Declaration:

```
function QuotedString : string; Overload
function QuotedString(const AQuoteChar: Char) : string; Overload
```

Visibility: public

Description: `QuotedString` returns a quoted version of the string (`Self`). The quote character is specified in `AQuoteChar`, which by default is the double quote (`"`). Any existing quote characters occurrences will be doubled.

See also: `QuotedStr` ([1742](#)), `AnsiQuotedStr` ([1654](#))

77.99.44 `TStringHelper.Remove`

Synopsis: Remove a number of characters from the string

Declaration:

```
function Remove(StartIndex: SizeInt) : string; Overload
function Remove(StartIndex: SizeInt; ACount: SizeInt) : string
; Overload
```

Visibility: public

Description: `Remove` removes `ACount` characters from the string, starting at (zero-based) index `StartIndex`. If `ACount` is omitted, all remaining characters are removed.

See also: `Delete` ([1453](#)), `TStringHelper.Replace` ([1912](#)), `TStringHelper.Insert` ([1908](#))

77.99.45 TStringHelper.Replace

Synopsis: Replace occurrences of one string with another.

Declaration: function Replace(OldChar: Char; NewChar: Char) : string; Overload
 function Replace(OldChar: Char; NewChar: Char;
 ReplaceFlags: TReplaceFlags) : string; Overload
 function Replace(const OldValue: string; const NewValue: string)
 : string; Overload
 function Replace(const OldValue: string; const NewValue: string;
 ReplaceFlags: TReplaceFlags) : string; Overload

Visibility: public

Description: Replace will replace occurrences of OldChar with NewChar or OldValue with NewValue.

If rfReplaceAll is in the ReplaceFlags, then all occurrences will be replaced, otherwise only the first occurrence is replaced.

If rfCaseInsensitive is in the ReplaceFlags, then the search for OldChar or OldValue is performed ignoring case.

See also: StringReplace ([1755](#)), TReplaceFlags ([1639](#))

77.99.46 TStringHelper.Split

Synopsis: Split a string in a number of parts

Declaration: function Split(const Separators: Array of Char) : TStringArray
 ; Overload
 function Split(const Separators: Array of Char; ACount: SizeInt)
 : TStringArray; Overload
 function Split(const Separators: Array of Char;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of Char; ACount: SizeInt;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of string) : TStringArray
 ; Overload
 function Split(const Separators: Array of string; ACount: SizeInt)
 : TStringArray; Overload
 function Split(const Separators: Array of string;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of string; ACount: SizeInt;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuote: Char)
 : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char) : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char; Options: TStringSplitOptions)
 : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char; ACount: SizeInt) : TStringArray
 ; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char; ACount: SizeInt;
 Options: TStringSplitOptions) : TStringArray; Overload

```

function Split(const Separators: Array of string; AQuote: Char)
    : TStringArray; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char) : TStringArray; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char; Options: TStringSplitOptions)
    : TStringArray; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char; ACount: SizeInt) : TStringArray
    ; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char; ACount: SizeInt;
    Options: TStringSplitOptions) : TStringArray; Overload

```

Visibility: public

Description: Split will split the string (Self) using Separators as separator characters.

If ACount is supplied, then at most ACount strings will be included in the result. The default behaviour is to supply all strings.

if Options contains ExcludeEmpty then no empty strings will be included in the result. Empty strings may be included if multiple successive separator characters are found in the source string, but not for the last character: If the last characters is a separator string, the 'empty string' behind it is not added to the result.

If AQuoteStart and AQuoteEnd are supplied, then no splitting will be performed between AQuoteStart and AQuoteEnd characters.

See also: TStringHelper.Join ([1901](#)), TStringHelper.IndexOfAny ([1907](#)), TStringHelper.IndexOfAnyUnquoted ([1908](#))

77.99.47 TStringHelper.StartsWith

Synopsis: Check if one string starts with another

```

Declaration: function StartsWith(const AValue: string) : Boolean; Overload
function StartsWith(const AValue: string; IgnoreCase: Boolean) : Boolean
    ; Overload

```

Visibility: public

Description: StartsWith will return True if the first characters of the string (Self) equal the string AValue.

If IgnoreCase is True, then the comparison is done case insensitive. The default is to compare strings case sensitively.

See also: TStringHelper.EndsWith ([1906](#))

77.99.48 TStringHelper.Substring

Synopsis: Return a part of the string

```

Declaration: function Substring(AStartIndex: SizeInt) : string; Overload
function Substring(AStartIndex: SizeInt; ALen: SizeInt) : string
    ; Overload

```

Visibility: public

Description: `SubString` returns the portion of the string starting at (zero-based) index `AStartIndex` with length `ALen`. If `ALen` is omitted, then all remaining characters are returned.

See also: `TStringHelper.Insert` (1908), `Copy` (1449), `TStringHelper.ToCharArray` (1914)

77.99.49 `TStringHelper.ToCharArray`

Synopsis: Return the string as an array of characters.

Declaration: `function ToCharArray : TCharArray; Overload`
`function ToCharArray(AStartIndex: SizeInt; ALen: SizeInt) : TCharArray`
`; Overload`

Visibility: public

Description: `ToCharArray` returns part of the string (`Self`) as an array of characters. The characters are copied starting at (zero-based) index `AStartIndex` and at most `ALen` characters are copied. If `AStartIndex` and `ALen` are omitted, all the characters are returned.

Errors: If `AStartIndex` is less than zero, an `EAccessViolation` (1799) exception may be raised.

See also: `TStringHelper.Substring` (1913), `TStringHelper.Insert` (1908), `Copy` (1449)

77.99.50 `TStringHelper.ToLower`

Synopsis: Convert to lowercase

Declaration: `function ToLower : string; Overload`

Visibility: public

Description: `ToLower` returns a lowercase version of the string.

See also: `TStringHelper.LowerCase` (1902), `TStringHelper.ToUpper` (1914), `TStringHelper.ToUpperInvariant` (1915)

77.99.51 `TStringHelper.ToLowerInvariant`

Synopsis: Convert to lowercase

Declaration: `function ToLowerInvariant : string`

Visibility: public

Description: `ToLowerInvariant` is equal to `TStringHelper.ToLower` (1914)

See also: `TStringHelper.ToLower` (1914), `TStringHelper.ToUpper` (1914), `TStringHelper.ToUpperInvariant` (1915)

77.99.52 `TStringHelper.ToUpper`

Synopsis: Convert to uppercase.

Declaration: `function ToUpper : string; Overload`

Visibility: public

Description: `>ToUpper` returns an uppercase version of the string.

See also: `TStringHelper.ToLower` (1914), `TStringHelper.ToLowerInvariant` (1914), `TStringHelper.ToUpperInvariant` (1915)

77.99.53 TStringHelper.ToUpperInvariant

Synopsis: Convert to uppercase

Declaration: `function ToUpperInvariant : string`

Visibility: public

Description: `ToUpperInvariant` is equal to `TStringHelper.ToUpper` (1914)

See also: `TStringHelper.ToLower` (1914), `TStringHelper.ToLowerInvariant` (1914), `TStringHelper.ToUpper` (1914)

77.99.54 TStringHelper.Trim

Synopsis: Strips a set of trim characters from the beginning and end of the string.

Declaration: `function Trim : string; Overload`
`function Trim(const ATrimChars: Array of Char) : string; Overload`

Visibility: public

Description: `Trim` returns the string (`Self`), removing all characters occurring in `ATrimChars` from the start and end of the string. If `ATrimChars` is not specified, all characters with ASCII code 32 or lower are assumed.

See also: `Trim` (1779), `TStringHelper.TrimLeft` (1915), `TStringHelper.TrimRight` (1915)

77.99.55 TStringHelper.TrimLeft

Synopsis: Strips a set of trim characters from the beginning of the string.

Declaration: `function TrimLeft : string; Overload`
`function TrimLeft(const ATrimChars: Array of Char) : string; Overload`

Visibility: public

Description: `Trim` returns the string (`Self`), removing all characters occurring in `ATrimChars` from the start of the string. If `ATrimChars` is not specified, all characters with ASCII code 32 or lower are assumed.

See also: `TrimLeft` (1779), `TStringHelper.Trim` (1915), `TStringHelper.TrimRight` (1915)

77.99.56 TStringHelper.TrimRight

Synopsis: Strips a set of trim characters from the end of the string.

Declaration: `function TrimRight : string; Overload`
`function TrimRight(const ATrimChars: Array of Char) : string; Overload`

Visibility: public

Description: `Trim` returns the string (`Self`), removing all characters occurring in `ATrimChars` from the end of the string. If `ATrimChars` is not specified, all characters with ASCII code 32 or lower are assumed.

See also: `Trim` (1779), `TStringHelper.Trim` (1915), `TStringHelper.TrimLeft` (1915)

77.99.57 TStringHelper.TrimEnd

Synopsis: Alias for TrimRight

Declaration: `function TrimEnd(const ATrimChars: Array of Char) : string`

Visibility: public

Description: TrimEnd is an alias for TStringHelper.TrimRight ([1915](#))

See also: TStringHelper.TrimRight ([1915](#)), TStringHelper.TrimStart ([1916](#))

77.99.58 TStringHelper.TrimStart

Synopsis: Alias for TrimLeft

Declaration: `function TrimStart(const ATrimChars: Array of Char) : string`

Visibility: public

Description: TrimStart is an alias for TStringHelper.TrimLeft ([1915](#))

See also: TStringHelper.TrimEnd ([1916](#)), TStringHelper.TrimLeft ([1915](#))

77.99.59 TStringHelper.Chars

Synopsis: Zero-based Indexed access to the characters in the string.

Declaration: `Property Chars[AIndex: SizeInt]: Char`

Visibility: public

Access: Read

Description: Chars provides zero-based indexed access to the characters in the string. The first character is at index 0, the last at Length-1.

See also: TStringHelper.Length ([1916](#))

77.99.60 TStringHelper.Length

Synopsis: Return the length of the string

Declaration: `Property &Length : SizeInt`

Visibility: public

Access: Read

Description: Length returns the length (in bytes for single-byte strings) of the string.

See also: Length ([1503](#))

77.100 TUnicodeEncoding

77.100.1 Description

TUnicodeEncoding is the encoding class used to represent the UTF-16 encoding.

See also: TUnicodeEncoding ([1916](#)), TUTF7Encoding ([1925](#)), TMBCSEncoding ([1862](#)), TBigendianUnicodeEncoding ([1819](#))

77.100.2 Method overview

Page	Method	Description
1917	Clone	Clone a TUnicodeEncoding instance
1917	Create	Create a new instance of the TUnicodeEncoding class
1917	GetMaxByteCount	Return max number of bytes needed to represent a string
1917	GetMaxCharCount	Return max number of characters that can be represented by an array of bytes
1918	GetPreamble	Return BOM marker bytes

77.100.3 TUnicodeEncoding.Create

Synopsis: Create a new instance of the TUnicodeEncoding class

Declaration: constructor Create; Virtual

Visibility: public

Description: Create creates a new instance of the TUnicodeEncoding class and sets the codepage to CP_UTF16.

See also: TEncoding.CodePage ([1841](#)), TEncoding ([1838](#))

77.100.4 TUnicodeEncoding.Clone

Synopsis: Clone a TUnicodeEncoding instance

Declaration: function Clone : TEncoding; Override

Visibility: public

Description: Clone overrides TEncoding.Clone ([1838](#)) to provide a clone of the TUnicodeEncoding instance.

See also: TEncoding.Clone ([1838](#))

77.100.5 TUnicodeEncoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: function GetMaxByteCount(CharCount: Integer) : Integer; Override

Visibility: public

Description: GetMaxByteCount overrides TEncoding.GetMaxByteCount ([1840](#)) to return the maximum number of bytes needed to represent a string.

See also: TEncoding.GetMaxByteCount ([1840](#))

77.100.6 TUnicodeEncoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: function GetMaxCharCount(ByteCount: Integer) : Integer; Override

Visibility: public

Description: GetMaxCharCount overrides TEncoding.GetMaxCharCount ([1840](#)) to return the maximum number of bytes needed to represent a string.

See also: TEncoding.GetMaxCharCount ([1840](#))

77.100.7 TUnicodeEncoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: `public`

Description: `GetPreamble` overrides `TEncoding.GetPreamble` (1841) to return the 2 UTF-16 BOM Marker bytes (\$FF,\$FE).

See also: `TEncoding.GetPreamble` (1841)

77.101 TUnicodeStringBuilder

77.101.1 Description

`TUnicodeStringBuilder` is a class to construct an anstring out of other strings or characters. It's methods can be used instead of constructing the string manually using the normal `+` or `concat` operators. If used properly (e.g. by setting a sufficiently large `Capacity` (1924)), will result in faster operation. It offers various methods to append to the string.

To create a unicode string, use the `TUnicodeStringBuilder` (1918) class instead.

See also: `TUnicodeStringBuilder` (1918)

77.101.2 Method overview

Page	Method	Description
1919	<code>Append</code>	Append data in string form to the buffer
1920	<code>AppendFormat</code>	Append the result of a <code>Format</code>
1920	<code>AppendLine</code>	Append a string followed by a newline
1920	<code>Clear</code>	Clear the string being built
1921	<code>CopyTo</code>	Copy string bytes to an array
1918	<code>Create</code>	Create a new <code>TUnicodeStringBuilder</code> instance.
1921	<code>EnsureCapacity</code>	Set the capacity if needed
1921	<code>Equals</code>	Check if 2 stringbuilders have the same content string
1921	<code>Insert</code>	Insert data in string form into the buffer at a given position
1922	<code>Remove</code>	Remove data from the string
1923	<code>Replace</code>	Replace a range of characters.
1923	<code>ToString</code>	Return the string buffer as an <code>UnicodeString</code>

77.101.3 Property overview

Page	Properties	Access	Description
1924	<code>Capacity</code>	<code>rw</code>	Current capacity of the string buffer
1923	<code>Chars</code>	<code>rw</code>	Indexed access to the characters in the string
1924	<code>Length</code>	<code>rw</code>	Currentl length of the string buffer
1924	<code>MaxCapacity</code>	<code>r</code>	Maximum capacity of the string buffer

77.101.4 TUnicodeStringBuilder.Create

Synopsis: Create a new `TUnicodeStringBuilder` instance.

Declaration: constructor Create

```

constructor Create(aCapacity: Integer)
constructor Create(const AValue: UnicodeString)
constructor Create(aCapacity: Integer; aMaxCapacity: Integer)
constructor Create(const AValue: UnicodeString; aCapacity: Integer)
constructor Create(const AValue: UnicodeString; StartIndex: Integer;
                  aLength: Integer; aCapacity: Integer)

```

Visibility: public

Description: Create creates an empty TUnicodeStringBuilder instance. It can optionally set the initial capacity to aCapacity and the maximum capacity to aMaxCapacity and can also initialize the string buffer with characters from aValue: aLength characters starting at StartIndex (1-based) will be copied to the string buffer. If aLength and StartIndex are omitted, then all characters are copied.

See also: Capacity ([1924](#)), MaxCapacity ([1924](#))

77.101.5 TUnicodeStringBuilder.Append

Synopsis: Append data in string form to the buffer

Declaration: function Append(const AValue: Boolean) : TUnicodeStringBuilder
function Append(const AValue: Byte) : TUnicodeStringBuilder
function Append(const AValue: WideChar) : TUnicodeStringBuilder
function Append(const AValue: Currency) : TUnicodeStringBuilder
function Append(const AValue: Double) : TUnicodeStringBuilder
function Append(const AValue: SmallInt) : TUnicodeStringBuilder
function Append(const AValue: LongInt) : TUnicodeStringBuilder
function Append(const AValue: Int64) : TUnicodeStringBuilder
function Append(const AValue: TObject) : TUnicodeStringBuilder
function Append(const AValue: ShortInt) : TUnicodeStringBuilder
function Append(const AValue: Single) : TUnicodeStringBuilder
function Append(const AValue: UInt64) : TUnicodeStringBuilder
function Append(const AValue: Array of WideChar) : TUnicodeStringBuilder
function Append(const AValue: Word) : TUnicodeStringBuilder
function Append(const AValue: Cardinal) : TUnicodeStringBuilder
function Append(const AValue: PWideChar) : TUnicodeStringBuilder
function Append(const AValue: UnicodeString) : TUnicodeStringBuilder
function Append(const AValue: RawByteString) : TUnicodeStringBuilder
function Append(const AValue: WideChar; RepeatCount: Integer)
: TUnicodeStringBuilder
function Append(const AValue: Array of WideChar; StartIndex: Integer;
SBCharCount: Integer) : TUnicodeStringBuilder
function Append(const AValue: UnicodeString; StartIndex: Integer;
Count: Integer) : TUnicodeStringBuilder
function Append(const Fmt: UnicodeString; const Args: Array of const)
: TUnicodeStringBuilder

Visibility: public

Description: Append in its various overloaded forms will append the aValue argument to the buffer, after converting it to a string value if necessary:

- For integer values the various IntToStr ([1736](#)) functions will be used.

- For TObject (1615) the TObject.ToString (1615) is used.
- The repeatCount argument will repeat the character as many times as instructed using StringOfChar (1615).
- If the StartIndex and SBCharCount are specified, then SBCharCount characters are copied starting from position StartIndex.

An overloaded version exists with the same arguments as AppendFormat (1920).

See also: StringOfChar (1615), AppendFormat (1920), AppendLine (1920), Insert (1921), Remove (1922)

77.101.6 TUnicodeStringBuilder.AppendFormat

Synopsis: Append the result of a Format

Declaration: `function AppendFormat(const Fmt: UnicodeString;
const Args: Array of const) : TUnicodeStringBuilder`

Visibility: public

Description: AppendFormat calls Format (1714) with fmt and Args and calls append (1919) with the resulting string.

Errors: the call to Format may result in an exception if the format parameters do not match the passed arguments.

See also: Append (1919), Insert (1921), Remove (1922), Format (1714)

77.101.7 TUnicodeStringBuilder.AppendLine

Synopsis: Append a string followed by a newline

Declaration: `function AppendLine : TUnicodeStringBuilder
function AppendLine(const AValue: RawByteString) : TUnicodeStringBuilder`

Visibility: public

Description: AppendLine will append aValue (if it is specified) and appends the OS linebreak character (sLineBreak (1364)).

See also: TUnicodeStringBuilder.AppendFormat (1920), TUnicodeStringBuilder.Append (1919), #rtl.system.sLineBreak (1364), Remove (1922), Insert (1921)

77.101.8 TUnicodeStringBuilder.Clear

Synopsis: Clear the string being built

Declaration: `procedure Clear`

Visibility: public

Description: Clear sets the length of the string to 0 and sets the Capacity (1924) to the default capacity (64 bytes).

See also: Capacity (1924), Remove (1922)

77.101.9 TUnicodeStringBuilder.CopyTo

Synopsis: Copy string bytes to an array

Declaration: `procedure CopyTo(SourceIndex: Integer;
var Destination: Array of WideChar;
DestinationIndex: Integer; Count: Integer)`

Visibility: public

Description: `CopyTo` copies `aCount` characters from the string, starting at position `SourceIndex` (0-based) in the string to build, to the character array `Destination` at position `DestinationIndex`.

Errors: If the range of characters to copy falls outside the allowed range of characters in either source (available characters) or destination (available room for characters), then an `ERangeError` (1806) exception is raised.

See also: `ERangeError` (1806)

77.101.10 TUnicodeStringBuilder.EnsureCapacity

Synopsis: Set the capacity if needed

Declaration: `function EnsureCapacity(aCapacity: Integer) : Integer`

Visibility: public

Description: `EnsureCapacity` checks that `aCapacity` is in the allowed range (less than `MaxCapacity` (1924)) and if the current capacity is less than `aCapacity`, increases the capacity to `aCapacity`.

Errors: If `aCapacity` is larger than `MaxCapacity` (1924) or negative, an `ERangeError` (1806) exception is raised.

See also: `MaxCapacity` (1924)

77.101.11 TUnicodeStringBuilder.Equals

Synopsis: Check if 2 stringbuilders have the same content string

Declaration: `function Equals(StringBuilder: TUnicodeStringBuilder) : Boolean
; Reintroduce`

Visibility: public

Description: `Equals` checks that the self instance has the same content as the `StringBuilder` instance. It checks the length and content (as bytes) of the strings.

See also: `TUnicodeStringBuilder.Clear` (1920)

77.101.12 TUnicodeStringBuilder.Insert

Synopsis: Insert data in string form into the buffer at a given position

Declaration: `function Insert(Index: Integer; const AValue: Boolean)
: TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: Byte)
: TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: WideChar)`

```

        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: Currency)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: Double)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: SmallInt)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: LongInt)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: Array of WideChar)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: Int64)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: TObject)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: ShortInt)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: Single)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: UnicodeString)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: Word)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: Cardinal)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: UInt64)
        : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: UnicodeString;
        const aRepeatCount: Integer) : TUnicodeStringBuilder
function Insert(Index: Integer; const AValue: Array of WideChar;
        startIndex: Integer; SBCharCount: Integer)
        : TUnicodeStringBuilder

```

Visibility: public

Description: Insert in its various overloaded forms will insert the aValue argument into the buffer at position Index (0-based), after converting it to a string value if necessary:

- For integer values the various IntToStr ([1736](#)) functions will be used.
- For TObject ([1615](#)) the TObject.ToString ([1615](#)) is used.
- The repeatCount argument will insert the character as many times as instructed.
- If the StartIndex and SBCharCount are specified, then SBCharCount characters are copied starting from position StartIndex.

See also: AppendFormat ([1920](#)), AppendLine ([1920](#)), Append ([1919](#)), Remove ([1922](#)), Replace ([1923](#))

77.101.13 TUnicodeStringBuilder.Remove

Synopsis: Remove data from the string

```

Declaration: function Remove(StartIndex: Integer; RemLength: Integer)
        : TUnicodeStringBuilder

```

Visibility: public

Description: Remove will remove `RemLength` characters from the string buffer, starting at position `StartIndex` (0-based).

Errors: If the range of characters to remove falls outside the allowed range of characters, then an `ERangeError` (1806) exception is raised.

See also: `AppendFormat` (1920), `AppendLine` (1920), `Append` (1919), `Insert` (1921), `Clear` (1920)

77.101.14 TUnicodeStringBuilder.Replace

Synopsis: Replace a range of characters.

Declaration:

```
function Replace(const OldChar: WideChar; const NewChar: WideChar)
    : TUnicodeStringBuilder
function Replace(const OldChar: WideChar; const NewChar: WideChar;
    StartIndex: Integer; Count: Integer)
    : TUnicodeStringBuilder
function Replace(const OldValue: UnicodeString;
    const NewValue: UnicodeString) : TUnicodeStringBuilder
function Replace(const OldValue: UnicodeString;
    const NewValue: UnicodeString; StartIndex: Integer;
    Count: Integer) : TUnicodeStringBuilder
```

Visibility: public

Description: Replace replaces occurrences of `OldValue` with the characters in `NewValue`. The search operation starts at position `StartIndex` (0-based, default 0) till position `StartIndex+aCount` is reached.

Errors: If `StartIndex` or `StartIndex+aCount` is out of range, an `ERangeError` (1806) exception is raised.

See also: `AppendFormat` (1920), `AppendLine` (1920), `Append` (1919), `Insert` (1921), `Clear` (1920), `Remove` (1922)

77.101.15 TUnicodeStringBuilder.ToString

Synopsis: Return the string buffer as an `UnicodeString`

Declaration:

```
function ToString : UnicodeString
function ToString(aStartIndex: Integer; aLength: Integer)
    : UnicodeString; Reintroduce
```

Visibility: public

Description: `ToString` returns the current content of the buffer as an `UnicodeString`.

See also: `Clear` (1920), `CopyTo` (1921)

77.101.16 TUnicodeStringBuilder.Chars

Synopsis: Indexed access to the characters in the string

Declaration: `Property Chars[index: Integer]: WideChar; default`

Visibility: public

Access: Read,Write

Description: `Chars` allows indexed access to the characters in the string using a zero-based `Index`. The characters can be read or written. The allowed range for `Index` is 0 to `Length` (1924)-1.

See also: `Length` (1924)

77.101.17 `TUnicodeStringBuilder.Length`

Synopsis: Current length of the string buffer

Declaration: `Property &Length : Integer`

Visibility: public

Access: Read,Write

Description: `Length` can be used to get or set the current length (in characters) of the string buffer. When setting the length, the new length is checked whether it lies within the maximum capacity (`MaxCapacity` (1924)) for the string buffer: if not, an `ERangeError` (1806) exception is raised. The capacity of the buffer will be adjusted so the buffer has enough capacity to accomodate the new length.

See also: `MaxCapacity` (1924), `Capacity` (1924), `ERangeError` (1806)

77.101.18 `TUnicodeStringBuilder.Capacity`

Synopsis: Current capacity of the string buffer

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` can be used to get or set the capacity of the string buffer (in characters). When setting the capacity, the new length is checked whether it lies within the maximum capacity (`MaxCapacity` (1924)) for the string buffer: if not, an `ERangeError` (1806) exception is raised.

See also: `MaxCapacity` (1924), `Length` (1924), `ERangeError` (1806)

77.101.19 `TUnicodeStringBuilder.MaxCapacity`

Synopsis: Maximum capacity of the string buffer

Declaration: `Property MaxCapacity : Integer`

Visibility: public

Access: Read

Description: `MaxCapacity` returns the maximum capacity of the string buffer (in characters). It is set when the stringbuilder is created, in the constructor of the builder. The `Capacity` (1924) (and consequently, the `Length` (1924)) will never be allowed to exceed `MaxCapacity`.

See also: `Capacity` (1924), `Length` (1924), `ERangeError` (1806)

77.102 TUTF7Encoding

77.102.1 Description

TUTF7Encoding is the encoding class used to represent the UTF7 encoding. This encoding is not so often used, and the class is provided mostly for completeness.

See also: TUnicodeEncoding ([1916](#)), TUTF8Encoding ([1926](#)), TMBCSEncoding ([1862](#)), TBigendianUnicodeEncoding ([1819](#))

77.102.2 Method overview

Page	Method	Description
1925	Clone	Clone a TUTF7Encoding instance
1925	Create	Create a new instance of the TUTF7Encoding class
1925	GetMaxByteCount	Return max number of bytes needed to represent a string
1926	GetMaxCharCount	Return max number of characters that can be represented by an array of bytes

77.102.3 TUTF7Encoding.Create

Synopsis: Create a new instance of the TUTF7Encoding class

Declaration: `constructor Create; Override`

Visibility: `public`

Description: Create creates a new instance of the TUTF7Encoding class and sets the codepage to CP_UTF7.

See also: TEncoding.CodePage ([1841](#)), TEncoding ([1838](#))

77.102.4 TUTF7Encoding.Clone

Synopsis: Clone a TUTF7Encoding instance

Declaration: `function Clone : TEncoding; Override`

Visibility: `public`

Description: Clone overrides TEncoding.Clone ([1838](#)) to provide a clone of the TUTF7Encoding instance.

See also: TEncoding.Clone ([1838](#))

77.102.5 TUTF7Encoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: `function GetMaxByteCount (CharCount: Integer) : Integer; Override`

Visibility: `public`

Description: GetMaxByteCount overrides TEncoding.GetMaxByteCount ([1840](#)) to return the maximum number of bytes needed to represent a string.

See also: TEncoding.GetMaxByteCount ([1840](#))

77.102.6 TUTF7Encoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: `function GetMaxCharCount (ByteCount: Integer) : Integer; Override`

Visibility: `public`

Description: `GetMaxCharCount` overrides `TEncoding.GetMaxCharCount` ([1840](#)) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxCharCount` ([1840](#))

77.103 TUTF8Encoding

77.103.1 Description

`TUTF8Encoding` is the encoding class used to represent the UTF-8 encoding.

See also: `TUnicodeEncoding` ([1916](#)), `TUTF7Encoding` ([1925](#)), `TMBCSEncoding` ([1862](#)), `TBigendianUnicodeEncoding` ([1819](#))

77.103.2 Method overview

Page	Method	Description
1926	<code>Clone</code>	Clone a <code>TUTF8Encoding</code> instance
1926	<code>Create</code>	Create a new instance of the <code>TUTF8Encoding</code> class
1927	<code>GetMaxByteCount</code>	Return max number of bytes needed to represent a string
1927	<code>GetMaxCharCount</code>	Return max number of characters that can be represented by an array of bytes
1927	<code>GetPreamble</code>	Return BOM marker bytes

77.103.3 TUTF8Encoding.Create

Synopsis: Create a new instance of the `TUTF8Encoding` class

Declaration: `constructor Create; Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TUTF8Encoding` class and sets the codepage to `CP_UTF8`.

See also: `TEncoding.CodePage` ([1841](#)), `TEncoding` ([1838](#))

77.103.4 TUTF8Encoding.Clone

Synopsis: Clone a `TUTF8Encoding` instance

Declaration: `function Clone : TEncoding; Override`

Visibility: `public`

Description: `Clone` overrides `TEncoding.Clone` ([1838](#)) to provide a clone of the `TUTF8Encoding` instance.

See also: `TEncoding.Clone` ([1838](#))

77.103.5 TUTF8Encoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: `function GetMaxByteCount (CharCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxByteCount` overrides `TEncoding.GetMaxByteCount` (1840) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxByteCount` (1840)

77.103.6 TUTF8Encoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: `function GetMaxCharCount (ByteCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxCharCount` overrides `TEncoding.GetMaxCharCount` (1840) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxCharCount` (1840)

77.103.7 TUTF8Encoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: public

Description: `GetPreamble` overrides `TEncoding.GetPreamble` (1841) to return the 3 UTF8 BOM Marker bytes (\$EF,\$BB,\$BF).

See also: `TEncoding.GetPreamble` (1841)

77.104 TWordBoolHelper

77.104.1 Description

`TWordBoolHelper` is a helper type for the `WordBool` type. It contains mostly conversion routines to and from other types.

See also: `TStringHelper` (1895), `TShortIntHelper` (1879), `TSmallIntHelper` (1891), `TWordHelper` (1929), `TCardinalHelper` (1828), `TIntegerHelper` (1856), `TInt64Helper` (1852), `TQWordHelper` (1875), `TNativeIntHelper` (1867), `TByteHelper` (1824), `TByteBoolHelper` (1822), `TWordBoolHelper` (1927), `TLongBoolHelper` (1861)

77.104.2 Method overview

Page	Method	Description
1928	<code>Parse</code>	Convert string value to <code>WordBool</code> value.
1928	<code>Size</code>	Return the size (in bytes) of the
1929	<code>ToInteger</code>	Convert to an integer value
1928	<code>ToString</code>	Convert a <code>WordBool</code> value to string.
1929	<code>TryToParse</code>	Try to convert a string to a <code>WordBool</code> value

77.104.3 TWordBoolHelper.Parse

Synopsis: Convert string value to `WordBool` value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: `public`

Description: `Parse` attempts to convert the string `S` to a `WordBool` value. It uses the `StrToBool` ([1763](#)) function to perform the conversion.

Errors: If `S` does not contain a valid string representation, then an `EConvertError` ([1800](#)) exception is raised.

See also: `TWordBoolHelper.TryToParse` ([1929](#)), `TWordBoolHelper.ToString` ([1928](#)), `TWordBoolHelper.ToInteger` ([1929](#))

77.104.4 TWordBoolHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in bytes) of the `WordBool` value. This is equivalent to `SizeOf(WordBool)`.

See also: `SizeOf` ([1547](#))

77.104.5 TWordBoolHelper.ToString

Synopsis: Convert a `WordBool` value to string.

Declaration: `class function ToString(const AValue: Boolean;
 UseBoolStrs: TUseBoolStrs) : string; Overload
 ; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: `public`

Description: `ToString` will, in the class method version, convert the `AValue` `WordBool` to a string representation. In the function method version the `WordBool` value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the `WordBool` strings `BoolStrs` ([1615](#)). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` ([1665](#)) function.

See also: `BoolStrs` ([1615](#)), `BoolToStr` ([1665](#))

77.104.6 TWordBoolHelper.TryParse

Synopsis: Try to convert a string to a WordBool value

Declaration: `class function TryToParse(const S: string; out AValue: Boolean)
: Boolean; Static`

Visibility: public

Description: `TryToParse` will attempt to convert the string `S` to a `WordBool` value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TWordBoolHelper.Parse` ([1928](#)), `TWordBoolHelper.ToString` ([1928](#))

77.104.7 TWordBoolHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the `WordBool` value, typecasted to `Integer`.

See also: `TWordBoolHelper.ToString` ([1928](#))

77.105 TWordHelper

77.105.1 Description

`TWordHelper` contains some auxiliary routines for a Word-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1895](#)), `TShortIntHelper` ([1879](#)), `TSmallIntHelper` ([1891](#)), `TByteHelper` ([1824](#)), `TCardinalHelper` ([1828](#)), `TIntegerHelper` ([1856](#)), `TInt64Helper` ([1852](#)), `TQWordHelper` ([1875](#)), `TNativeIntHelper` ([1867](#)), `TNativeUIntHelper` ([1871](#))

77.105.2 Method overview

Page	Method	Description
1932	<code>ClearBit</code>	Set bit to 0
1930	<code>Parse</code>	Convert from a string
1932	<code>SetBit</code>	Set bit to 1
1930	<code>Size</code>	Size, in bytes, of the Word value
1933	<code>TestBit</code>	Check bit
1931	<code>ToBinString</code>	Convert to a binary string representation
1931	<code>ToBoolean</code>	Convert to a boolean value
1931	<code>ToDouble</code>	Convert to a double-sized floating point value
1931	<code>ToExtended</code>	Convert to an extended-sized floating point value
1933	<code>ToggleBit</code>	Invert bit
1932	<code>ToHexString</code>	Convert to a hexadecimal string representation
1932	<code>ToSingle</code>	Convert to a single-sized floating point value
1930	<code>ToString</code>	Convert the value to string
1930	<code>TryParse</code>	Try to convert a string to a Word, report success or failure

77.105.3 TWordHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Word; Static`

Visibility: public

Description: `Parse` will attempt to convert the string `AString` to a `Word` value. It uses the `StrToInt` (1769) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `Word` value, an `EConvertError` (1800) exception is raised.

See also: `TWordHelper.ToString` (1930), `TWordHelper.TryParse` (1930), `StrToInt` (1769)

77.105.4 TWordHelper.Size

Synopsis: Size, in bytes, of the `Word` value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` returns the size (in Words) of the `Word` value. This is equivalent to `SizeOf(Word)`.

Errors: None.

See also: `SizeOf` (1547)

77.105.5 TWordHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Word) : string; Overload; Static`
`function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `Word` value itself is used. The `IntToStr` (1736) function is used to do the conversion.

See also: `TWordHelper.Parse` (1930), `IntToStr` (1736)

77.105.6 TWordHelper.TryParse

Synopsis: Try to convert a string to a `Word`, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Word)`
`: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Word`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `Word` is returned in `AValue`.

It uses the `val` (1615) function to perform the conversion, so no localization is taken into account.

See also: `TWordHelper.Parse` (1930), `Val` (1570)

77.105.7 TWordHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `Word` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TWordHelper.ToSingle` ([1932](#)), `TWordHelper.ToDouble` ([1931](#)), `TWordHelper.ToExtended` ([1931](#)), `TWordHelper.ToString` ([1930](#)), `TWordHelper.ToHexString` ([1932](#))

77.105.8 TWordHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Word` value to a double-sized floating point value.

See also: `TWordHelper.ToBoolean` ([1931](#)), `TWordHelper.ToExtended` ([1931](#)), `TWordHelper.ToSingle` ([1932](#)), `TWordHelper.ToString` ([1930](#)), `TWordHelper.ToHexString` ([1932](#))

77.105.9 TWordHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `Word` value to an extended-sized floating point value.

See also: `TWordHelper.ToBoolean` ([1931](#)), `TWordHelper.ToSingle` ([1932](#)), `TWordHelper.ToDouble` ([1931](#)), `TWordHelper.ToString` ([1930](#)), `TWordHelper.ToHexString` ([1932](#))

77.105.10 TWordHelper.ToBinString

Synopsis: Convert to a binary string representation

Declaration: `function ToBinString : string`

Visibility: public

Description: `ToBinString` converts the `word` value to a binary string representation, showing all 16 bits.

See also: `TWordHelper.ToHexString` ([1932](#)), `TWordHelper.ToString` ([1930](#))

77.105.11 TWordHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `Word` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TWordHelper.ToBoolean` ([1931](#)), `TWordHelper.ToSingle` ([1932](#)), `TWordHelper.ToDouble` ([1931](#)), `TWordHelper.ToString` ([1930](#)), `TWordHelper.ToExtended` ([1931](#))

77.105.12 TWordHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `Word` value to a single-sized floating point value.

See also: `TWordHelper.ToBoolean` ([1931](#)), `TWordHelper.ToDouble` ([1931](#)), `TWordHelper.ToExtended` ([1931](#)), `TWordHelper.ToString` ([1930](#)), `TWordHelper.ToHexString` ([1932](#))

77.105.13 TWordHelper.SetBit

Synopsis: Set bit to 1

Declaration: `function SetBit(const Index: TWordBitIndex) : Word`

Visibility: public

Description: `SetBit` puts value 1 to bit number determined by argument `Index`.

See also: `TWordHelper.ClearBit` ([1932](#)), `TWordHelper.ToggleBit` ([1933](#)), `TWordHelper.TestBit` ([1933](#)), `TWordHelper.HighestSetBitPos` ([1929](#)), `TWordHelper.LowestSetBitPos` ([1929](#)), `TWordHelper.SetBitsCount` ([1929](#)), `TWordHelper.Bits` ([1929](#))

77.105.14 TWordHelper.ClearBit

Synopsis: Set bit to 0

Declaration: `function ClearBit(const Index: TWordBitIndex) : Word`

Visibility: public

Description: `ClearBit` puts value 0 to bit number determined by argument `Index`.

See also: `TWordHelper.SetBit` ([1932](#)), `TWordHelper.ToggleBit` ([1933](#)), `TWordHelper.TestBit` ([1933](#)), `TWordHelper.HighestSetBitPos` ([1929](#)), `TWordHelper.LowestSetBitPos` ([1929](#)), `TWordHelper.SetBitsCount` ([1929](#)), `TWordHelper.Bits` ([1929](#))

77.105.15 TWordHelper.ToggleBit

Synopsis: Invert bit

Declaration: `function ToggleBit(const Index: TWordBitIndex) : Word`

Visibility: public

Description: `ToggleBit` reads bit value from bit number determined by argument `Index`, inverts it (if it was 0 it becomes 1, and vice versa), and stores it back.

See also: `TWordHelper.SetBit` ([1932](#)), `TWordHelper.ToggleBit` ([1933](#)), `TWordHelper.TestBit` ([1933](#)), `TWordHelper.HighestSetBitPos` ([1929](#)), `TWordHelper.LowestSetBitPos` ([1929](#)), `TWordHelper.SetBitsCount` ([1929](#)), `TWordHelper.Bits` ([1929](#))

77.105.16 TWordHelper.TestBit

Synopsis: Check bit

Declaration: `function TestBit(const Index: TWordBitIndex) : Boolean`

Visibility: public

Description: `TestBit` reads boolean value (true if bit is 1, and false if bit is 0) from bit number determined by argument `Index`.

See also: `TWordHelper.SetBit` ([1932](#)), `TWordHelper.ToggleBit` ([1933](#)), `TWordHelper.TestBit` ([1933](#)), `TWordHelper.HighestSetBitPos` ([1929](#)), `TWordHelper.LowestSetBitPos` ([1929](#)), `TWordHelper.SetBitsCount` ([1929](#)), `TWordHelper.Bits` ([1929](#))

Chapter 78

Reference for unit 'Types'

78.1 Used units

Table 78.1: Used units by unit 'Types'

Name	Page
System	1339

78.2 Overview

Starting with D6, types from Windows specific units that were needed in Kylix were extracted to this unit. So it mostly contains type of Windows origin that are needed in the VCL framework.

78.3 Constants, types and variables

78.3.1 Constants

`E_FAIL = HRESULT($80004005)`

Defined for Delphi compatibility, this should not be used.

`E_INVALIDARG = HRESULT($80070057)`

Defined for Delphi compatibility, this should not be used.

`GUID_NULL : TGuid = '{00000000-0000-0000-0000-000000000000}'`

`GUID_NULL` is the definition of the NULL (empty) GUID.

`LOCK_EXCLUSIVE = 2`

Defined for Delphi compatibility, this should not be used.

`LOCK_ONLYONCE = 4`

Defined for Delphi compatibility, this should not be used.

`LOCK_WRITE = 1`

Defined for Delphi compatibility, this should not be used.

`STATFLAG_DEFAULT = 0`

Defined for Delphi compatibility, this should not be used.

`STATFLAG_NONAME = 1`

Defined for Delphi compatibility, this should not be used.

`STATFLAG_NOOPEN = 2`

Defined for Delphi compatibility, this should not be used.

`STGTY_LOCKBYTES = 3`

Defined for Delphi compatibility, this should not be used.

`STGTY_PROPERTY = 4`

Defined for Delphi compatibility, this should not be used.

`STGTY_STORAGE = 1`

Defined for Delphi compatibility, this should not be used.

`STGTY_STREAM = 2`

Defined for Delphi compatibility, this should not be used.

`STG_E_ABNORMALAPIEXIT = HRESULT($800300FA)`

Defined for Delphi compatibility, this should not be used.

`STG_E_ACCESSDENIED = HRESULT($80030005)`

Defined for Delphi compatibility, this should not be used.

`STG_E_BADBASEADDRESS = HRESULT($80030110)`

Defined for Delphi compatibility, this should not be used.

`STG_E_CANTSAVE = HRESULT($80030103)`

Defined for Delphi compatibility, this should not be used.

`STG_E_DISKISWRITEPROTECTED = HRESULT($80030013)`

Defined for Delphi compatibility, this should not be used.

STG_E_DOCFILECORRUPT = HRESULT(\$80030109)

Defined for Delphi compatibility, this should not be used.

STG_E_EXTANTMARSHALLINGS = HRESULT(\$80030108)

Defined for Delphi compatibility, this should not be used.

STG_E_FILEALREADYEXISTS = HRESULT(\$80030050)

Defined for Delphi compatibility, this should not be used.

STG_E_FILENOTFOUND = HRESULT(\$80030002)

Defined for Delphi compatibility, this should not be used.

STG_E_INCOMPLETE = HRESULT(\$80030201)

Defined for Delphi compatibility, this should not be used.

STG_E_INSUFFICIENTMEMORY = HRESULT(\$80030008)

Defined for Delphi compatibility, this should not be used.

STG_E_INUSE = HRESULT(\$80030100)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDFLAG = HRESULT(\$800300FF)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDFUNCTION = HRESULT(\$80030001)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDHANDLE = HRESULT(\$80030006)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDHEADER = HRESULT(\$800300FB)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDNAME = HRESULT(\$800300FC)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDPARAMETER = HRESULT(\$80030057)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDPOINTER = HRESULT(\$80030009)

Defined for Delphi compatibility, this should not be used.

STG_E_LOCKVIOLATION = HRESULT(\$80030021)

Defined for Delphi compatibility, this should not be used.

STG_E_MEDIUMFULL = HRESULT(\$80030070)

Defined for Delphi compatibility, this should not be used.

STG_E_NOMOREFILES = HRESULT(\$80030012)

Defined for Delphi compatibility, this should not be used.

STG_E_NOTCURRENT = HRESULT(\$80030101)

Defined for Delphi compatibility, this should not be used.

STG_E_OLDDLL = HRESULT(\$80030105)

Defined for Delphi compatibility, this should not be used.

STG_E_OLDFORMAT = HRESULT(\$80030104)

Defined for Delphi compatibility, this should not be used.

STG_E_PATHNOTFOUND = HRESULT(\$80030003)

Defined for Delphi compatibility, this should not be used.

STG_E_PROPSSETMISMATCHED = HRESULT(\$800300F0)

Defined for Delphi compatibility, this should not be used.

STG_E_READFAULT = HRESULT(\$8003001E)

Defined for Delphi compatibility, this should not be used.

STG_E_REVERTED = HRESULT(\$80030102)

Defined for Delphi compatibility, this should not be used.

STG_E_SEEKERROR = HRESULT(\$80030019)

Defined for Delphi compatibility, this should not be used.

STG_E_SHAREREQUIRED = HRESULT(\$80030106)

Defined for Delphi compatibility, this should not be used.

STG_E_SHAREVIOLATION = HRESULT(\$80030020)

Defined for Delphi compatibility, this should not be used.

STG_E_TERMINATED = HRESULT(\$80030202)

Defined for Delphi compatibility, this should not be used.

STG_E_TOOMANYOPENFILES = HRESULT(\$80030004)

Defined for Delphi compatibility, this should not be used.

STG_E_UNIMPLEMENTEDFUNCTION = HRESULT(\$800300FE)

Defined for Delphi compatibility, this should not be used.

STG_E_UNKNOWN = HRESULT(\$800300FD)

Defined for Delphi compatibility, this should not be used.

STG_E_WRITEFAULT = HRESULT(\$8003001D)

Defined for Delphi compatibility, this should not be used.

STG_S_BLOCK = \$00030201

Defined for Delphi compatibility, this should not be used.

STG_S_CONVERTED = \$00030200

Defined for Delphi compatibility, this should not be used.

STG_S_MONITORING = \$00030203

Defined for Delphi compatibility, this should not be used.

STG_S_RETRYNOW = \$00030202

Defined for Delphi compatibility, this should not be used.

STREAM_SEEK_CUR = 1

Defined for Delphi compatibility, this should not be used.

STREAM_SEEK_END = 2

Defined for Delphi compatibility, this should not be used.

STREAM_SEEK_SET = 0

Defined for Delphi compatibility, this should not be used.

78.3.2 Types

`ArgList = Pointer`

`ArgList` is defined for Delphi/Kylix compatibility and should not be used.

`DWORD = LongWord`

Alias for cardinal type

`FILETIME = _FILETIME`

Alias for the `_FILETIME` type

`Largeint = Int64`

`Largeint` is an alias for the `Int64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LargeUint = QWord`

`LargeUint` is an alias for the `QWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LARGE_INT = Largeint`

`LARGE_INT` is an alias for the `Int64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LARGE_UINT = LargeUint`

`LARGE_UINT` is an alias for the `QWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PByte = System.PByte`

`PByte` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PCLSID = PGuid`

`PCLSID` is a pointer to a `TCLSID` type.

`PDisplay = Pointer`

`PDisplay` is defined for Delphi/Kylix compatibility and should not be used.

`PDouble = System.PDouble`

`PDouble` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PDWord = ^DWORD`

`PDWord` is equivalent to the `PCardinal` type.

`PEvent` = `Pointer`

`PEvent` is defined for Delphi/Kylix compatibility and should not be used.

`PFileTime` = `^TFileTime`

Pointer to `TFileTime` type

`PLargeInt` = `^Largeint`

`PLargeInt` is an alias for the `PInt64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PLargeUInt` = `^LargeUInt`

`PLargeUInt` is an alias for the `PQWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PLongint` = `System.PLongint`

`PLongint` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PoleStr` = `PWideChar`

`PoleStr` is a pointer to a (double) null-terminated array of `TChar` characters.

`PPoint` = `^TPoint`

`PPoint` is a typed pointer to the `TPoint` (1949) type.

`PPoleStr` = `^PoleStr`

`PPoleStr` is a typed pointer to a `PoleStr` variable.

`PRect` = `^TRect`

`PRect` is a typed pointer to the `TRect` (1957) type.

`PSize` = `^TSize`

`PSize` is a typed pointer to the `TSize` (1962) type.

`PSmallInt` = `System.PSmallInt`

`PSmallInt` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PSmallPoint` = `^TSmallPoint`

`PSmallPoint` is a typed pointer to the `TSmallPoint` (1944) record.

PStatStg = ^TStatStg

Pointer to TStatStg record.

PXrmOptionDescRec = ^TXrmOptionDescRec

PXrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

Region = Pointer

Region is defined for Delphi/Kylix compatibility and should not be used.

STATSTG = TStatStg

Alias for the TStatStg type.

TagPoint = TPoint deprecated

tagPOINT is a simple alias for TPoint (1949)

TagSize = TSize deprecated

tagSize is an alias for the TSize (1962) type.

```
tagSTATSTG = record
public
  pwcsName : POleStr;
  dwType : DWORD
  ;
  cbSize : LARGE_UINT;
  mtime : TFileTime;
  ctime : TFileTime
  ;
  atime : TFileTime;
  grfMode : DWORD;
  grfLocksSupported : DWORD
  ;
  clsid : TCLSID;
  grfStateBits : DWORD;
  reserved : DWORD;
end
```

tagSTATSTG is used in the IStream.Stat (1968) call. It describes a storage medium (typically a file).

TArray4IntegerType = Array[0..3] of LongInt

TBooleanDynArray = Array of Boolean

TBooleanDynArray is a standard definition of a dynamical array of booleans.

`TByteDynArray` = Array of Byte

`TByteDynArray` is a standard definition of a dynamical array of (8-bit, unsigned) bytes.

`TCardinalDynArray` = Array of Cardinal

`TCardinalDynArray` is a standard definition of a dynamical array of (32-bit, unsigned) cardinals.

`TCLSID` = `TGuid`

`TCLSID` is an alias for the `#rtl.system.TGUID` (1395) type.

`TCompDynArray` = Array of Comp

`TCurrencyArray` = Array of currency

`TDirection` = (FromBeginning, FromEnd)

Table 78.2: Enumeration values for type `TDirection`

Value	Explanation
FromBeginning	
FromEnd	

`TDoubleDynArray` = Array of Double

`TSoubleDynArray` is a standard definition of a dynamical array of doubles. (regular floating point type)

`TDuplicates` = (dupIgnore, dupAccept, dupError)

Table 78.3: Enumeration values for type `TDuplicates`

Value	Explanation
dupAccept	Accept duplicates, adding them to the list.
dupError	Raise an error when an attempt is made to add a duplicate.
dupIgnore	Ignore the new item, do not add it to the list.

`TDuplicates` can be used to indicate how a list structure acts on the addition of a duplicate item to the list.

dupIgnore Ignore the new item, do not add it to the list.

dupAccept Accept duplicates, adding them to the list.

dupError Raise an error when an attempt is made to add a duplicate.

`TEndian = Objpas.TEndian`

`TExtendedDynArray = Array of Extended`

`TFileTime = _FILETIME`

Alias for the `_FILETIME` type

`TInt64DynArray = Array of Int64`

`TInt64DynArray` is a standard definition of a dynamical array of (64-bit, signed) `int64s`.

`TIntegerDynArray = Array of Integer`

`TIntegerDynArray` is a standard definition of a dynamical array of (32-bit, signed) integers.

`TListCallback = procedure(data: pointer; arg: pointer) of object`

`TListCallback` is the prototype for a `Foreach` operation on a list. It will be called with as `Data` the pointer in the list, and `Arg` will contain the extra user data added to the `Foreach` call. It can be used in methods of objects; for a version that can be used as a global procedure, see `TListStaticCallback` (1943)

`TListStaticCallback = procedure(data: pointer; arg: pointer)`

`TListStaticCallback` is the prototype for a `Foreach` operation on a list. It will be called with as `Data` the pointer in the list, and `Arg` will contain the extra user data added to the `Foreach` call. It can be used in plain procedures; for a version that can be used as a method, see `TListCallback` (1943)

`TLongWordDynArray = Array of LongWord`

`TLongWordDynArray` is a standard definition of a dynamical array of (32-bit, unsigned) `LongWords`.

`TObjectDynArray = Array of TObject`

`TOLEChar = WideChar`

`TOLEChar` is an alias for the `WideChar` type, defined in the system unit.

`TPointerDynArray = Array of Pointer`

Dynamic array of untyped pointers

`TQWordDynArray = Array of QWord`

`TQWordDynArray` is a standard definition of a dynamical array of (64-bit, unsigned) `QWords`.

TShortIntDynArray = Array of ShortInt

TShortintDynArray is a standard definition of a dynamical array of (8-bit, signed) shortints.

TSingleDynArray = Array of Single

TSingleDynArray is a standard definition of a dynamical array of singles. (smallest floating point type)

TSmallIntDynArray = Array of SmallInt

TSmallintDynArray is a standard definition of a dynamical array of (16-bit, unsigned) integers.

```
TSmallPoint = packed record
public
  X : SmallInt;
  Y : SmallInt
;
end
```

TSmallPoint defines a point in a 2-dimensional plane, just like TPoint (1949), but the coordinates have a smaller range: The coordinates are smallints (16-bit, signed) and they run from -MaxSmallInt to maxSmallint.

TSplitRectType = (srLeft, srRight, srTop, srBottom)

Table 78.4: Enumeration values for type TSplitRectType

Value	Explanation
srBottom	
srLeft	
srRight	
srTop	

TStatStg = tagSTATSTG

TStatStg is a record type describing a storage medium. It is uses in the IStream.Stat (1968) function.

TStringDynArray = Array of AnsiString

TStringDynArray is a standard definition of a dynamical array of Ansistrings.

TValueRelationship = - 1..1

TWideStringDynArray = Array of WideString

TWideStringDynArray is a standard definition of a dynamical array of WideStrings.

```
TWordDynArray = Array of Word
```

TWordDynArray is a standard definition of a dynamical array of (16-bit, unsigned) words.

```
TXrmOptionDescRec = record
end
```

TXrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

```
Widget = Pointer
```

Widget is defined for Delphi/Kylix compatibility and should not be used.

```
WidgetClass = Pointer
```

WidgetClass is defined for Delphi/Kylix compatibility and should not be used.

```
XrmOptionDescRec = TXrmOptionDescRec
```

XrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

```
_FILETIME = packed record
public
    dwLowDateTime : DWORD;
    dwHighDateTime
    : DWORD;
end
```

_FILETIME describes a file time stamp. It is defined for Delphi/Kylix compatibility and should not be used except when implementing or accessing the IStream interface. The TDateTime type should be used instead.

78.4 Procedures and functions

78.4.1 Bounds

Synopsis: Create a rectangle, given a position and size

Declaration: `function Bounds(ALeft: Integer; ATop: Integer; AWidth: Integer; AHeight: Integer) : TRect`

Visibility: default

Description: Bounds returns a TRect structure with the indicated position (Left=ALeft and Top=ATop) and size (Right=ALeft+AWidth and Bottom=ATop+AHeight)

See also: Rect ([1948](#)), PtInRect ([1947](#)), IntersectRect ([1946](#)), UnionRect ([1948](#))

78.4.2 CenterPoint

Synopsis: Return the center point of a rectangle

Declaration: `function CenterPoint (const Rect: TRect) : TPoint`

Visibility: default

Description: `CenterPoint` returns the center point of the rectangle `Rect`.

See also: `PtinRect` (1947), `IntersectRect` (1946), `IsRectEmpty` (1947), `OffsetRect` (1947), `InflateRect` (1946), `Size` (1948), `IsRectEmpty` (1947)

78.4.3 EqualRect

Synopsis: Check if two rectangles are equal.

Declaration: `function EqualRect (const r1: TRect; const r2: TRect) : Boolean`

Visibility: default

Description: `EqualRect` returns `True` if the rectangles `R1` and `R2` are equal (i.e. have the position and size). If the rectangles differ, the function returns `False`

See also: `Rect` (1948), `Bounds` (1945), `PtinRect` (1947), `IntersectRect` (1946), `UnionRect` (1948), `IsRectEmpty` (1947), `OffsetRect` (1947), `InflateRect` (1946), `Size` (1948)

78.4.4 InflateRect

Synopsis: Increase the rectangle in size, keeping it centered

Declaration: `function InflateRect (var Rect: TRect; dx: Integer; dy: Integer)
: Boolean`

Visibility: default

Description: `InflateRect` inflates the rectangle horizontally with `dx` pixels on each side, and vertically with `dy` pixels, thus keeping its center point on the same location. It returns `true` if the operation was successfully, `False` if it was not (only possible if the address of `Rect` is `Nil`).

See also: `PtinRect` (1947), `IntersectRect` (1946), `IsRectEmpty` (1947), `OffsetRect` (1947), `CenterPoint` (1946), `Size` (1948), `IsRectEmpty` (1947)

78.4.5 IntersectRect

Synopsis: Return the intersection of 2 rectangles

Declaration: `function IntersectRect (var Rect: TRect; const R1: TRect;
const R2: TRect) : Boolean`

Visibility: default

Description: `IntersectRect` returns the intersection of the 2 rectangles `R1` and `R2` in `Rect`. It returns `True` if the 2 rectangles have an intersection, otherwise `False` is returned, and `Rect` is filled with zero.

See also: `PtinRect` (1947), `UnionRect` (1948), `IsRectEmpty` (1947), `OffsetRect` (1947), `InflateRect` (1946), `Size` (1948)

78.4.6 IsRectEmpty

Synopsis: Check whether a rectangle is empty

Declaration: `function IsRectEmpty(const Rect: TRect) : Boolean`

Visibility: default

Description: `IsRectEmpty` returns true if the rectangle is empty, i.e. has a zero or negative width or height.

See also: `PtinRect` (1947), `IntersectRect` (1946), `IsRectEmpty` (1947), `OffsetRect` (1947), `InflateRect` (1946), `Size` (1948)

78.4.7 OffsetRect

Synopsis: Offset the rectangle

Declaration: `function OffsetRect(var Rect: TRect; DX: Integer; DY: Integer) : Boolean`

Visibility: default

Description: `OffsetRect` offsets the rectangle `Rect` by a horizontal distance `DX` and a vertical distance `DY`. The operation returns `True` if the operation was successful, `false` if it was not (only possible if the address of `Rect` is `Nil`).

See also: `PtinRect` (1947), `IntersectRect` (1946), `IsRectEmpty` (1947), `OffsetRect` (1947), `InflateRect` (1946), `Size` (1948), `IsRectEmpty` (1947)

78.4.8 Point

Synopsis: Create a point

Declaration: `function Point(x: Integer; y: Integer) : TPoint`

Visibility: default

Description: `Point` returns a `TPoint` structure with the given position (`X`, `Y`).

See also: `Rect` (1948), `PtInRect` (1947)

78.4.9 PtInRect

Synopsis: Check whether a point is inside a rectangle.

Declaration: `function PtInRect(const Rect: TRect; const p: TPoint) : Boolean`

Visibility: default

Description: `PtInRect` returns `True` if `p` is located inside `Rect`, and `False` if it is located outside the rectangle.

Remark Note that the bottom, right edges are not considered part of the rectangle, therefore a point located on one of these edges will not be considered part of the rectangle, meaning that for a record (10,10,100,100) the point (90,100) will not be considered part of the record, but 90, 10 will be.

See also: `IntersectRect` (1946), `UnionRect` (1948), `IsRectEmpty` (1947), `OffsetRect` (1947), `InflateRect` (1946), `Size` (1948)

78.4.10 Rect

Synopsis: Create a rectangle record

Declaration: `function Rect (Left: Integer; Top: Integer; Right: Integer;
Bottom: Integer) : TRect`

Visibility: default

Description: `Rect` returns a rectangle structure with the 4 members `Left`, `Top`, `Right` and `Bottom` as passed in the arguments.

See also: `Bounds` (1945), `PtInRect` (1947), `IntersectRect` (1946), `UnionRect` (1948), `IsRectEmpty` (1947), `OffsetRect` (1947), `InflateRect` (1946), `Size` (1948)

78.4.11 Size

Synopsis: Return the size of the rectangle

Declaration: `function Size (AWidth: Integer; AHeight: Integer) : TSize`
`function Size (const ARect: TRect) : TSize`

Visibility: default

Description: `Size` returns a `TSize` record with the indicated `AWidth`, `AHeight`. In the case `ARect` is passed, the width and height are calculated (taking into account that the right, bottom are not considered part of the rectangle).

See also: `PtInRect` (1947), `IntersectRect` (1946), `IsRectEmpty` (1947), `OffsetRect` (1947), `InflateRect` (1946), `CenterPoint` (1946), `IsRectEmpty` (1947)

78.4.12 UnionRect

Synopsis: Return the union of 2 rectangles.

Declaration: `function UnionRect (var Rect: TRect; const R1: TRect; const R2: TRect)
: Boolean`

Visibility: default

Description: `UnionRect` returns the rectangle that encompasses both `R1` and `R2` in `Rect`. It returns `True` if the resulting rectangle is not empty, `False` if the result is an empty rectangle (in which case the result is filled with zeroes)

See also: `PtInRect` (1947), `IntersectRect` (1946), `IsRectEmpty` (1947), `OffsetRect` (1947), `InflateRect` (1946), `Size` (1948)

78.5 TPoint

```
TPoint = packed record
public
  X : LongInt;
  Y : LongInt;
class
  function Zero : TPoint; Static;
  function Add(const apt: TPoint
```

```

) : TPoint;
function Distance(const apt: TPoint) : ValReal;
function
IsZero : Boolean;
function Subtract(const apt: TPoint) : TPoint
;
SetLocation;
Offset;
class function PointInCircle(const apt
: TPoint; const acenter: TPoint;
const
aradius: Integer) : Boolean; Static;
TPoint.class operator =(const
apt1: TPoint; const apt2: TPoint)
: Boolean
;
TPoint.class operator <>(const apt1: TPoint; const apt2: TPoint
)
: Boolean;
TPoint.class operator +
(const apt1: TPoint; const apt2: TPoint) : TPoint;
TPoint.class
operator -(const apt1: TPoint; const apt2: TPoint) : TPoint;
TPoint
.class operator :=(const aspt: TSmallPoint) : TPoint;
TPoint.class
operator explicit(const apt: TPoint) : TSmallPoint;
end

```

TPoint is a generic definition of a point in a 2-dimensional discrete plane, where X indicates the horizontal position, and Y the vertical position (positions usually measured in pixels), and 0, 0 is the origin of the plane.

Usually, the origin is the upper-left corner of the screen, with Y increasing as one moves further down the screen - this is opposite to the mathematical view where Y increases as one moves upwards.

The coordinates are integers, (32-bit, signed) so the coordinate system runs from -MaxInt to MaxInt.

78.5.1 Method overview

Page	Method	Description
1950	Add	
1951	add(TPoint,TPoint):TPoint	
1951	assign(TSmallPoint):TPoint	
1950	Distance	
1951	equal(TPoint,TPoint):Boolean	
1951	explicit(TPoint):TSmallPoint	
1950	IsZero	
1951	notequal(TPoint,TPoint):Boolean	
1951	Offset	
1951	PointInCircle	
1950	SetLocation	
1950	Subtract	
1951	subtract(TPoint,TPoint):TPoint	
1950	Zero	

78.5.2 TPoint.Zero

Declaration: `class function Zero : TPoint; Static`

Visibility: `public`

78.5.3 TPoint.Add

Declaration: `function Add(const apt: TPoint) : TPoint`

Visibility: `public`

78.5.4 TPoint.Distance

Declaration: `function Distance(const apt: TPoint) : ValReal`

Visibility: `public`

78.5.5 TPoint.IsZero

Declaration: `function IsZero : Boolean`

Visibility: `public`

78.5.6 TPoint.Subtract

Declaration: `function Subtract(const apt: TPoint) : TPoint`

Visibility: `public`

78.5.7 TPoint.SetLocation

Declaration: `procedure SetLocation(const apt: TPoint)`
`procedure SetLocation(ax: LongInt; ay: LongInt)`

Visibility: `public`

78.5.8 TPoint.Offset

Declaration: `procedure Offset(const apt: TPoint)`
`procedure Offset(dx: LongInt; dy: LongInt)`

Visibility: public

78.5.9 TPoint.PointInCircle

Declaration: `class function PointInCircle(const apt: TPoint; const acenter: TPoint;`
`const aradius: Integer) : Boolean; Static`

Visibility: public

78.5.10 TPoint.equal(TPoint,TPoint):Boolean

Declaration: `TPoint.class operator =(const apt1: TPoint; const apt2: TPoint)`
`: Boolean`

Visibility: public

78.5.11 TPoint.notequal(TPoint,TPoint):Boolean

Declaration: `TPoint.class operator <>(const apt1: TPoint; const apt2: TPoint)`
`: Boolean`

Visibility: public

78.5.12 TPoint.add(TPoint,TPoint):TPoint

Declaration: `TPoint.class operator +(const apt1: TPoint; const apt2: TPoint) : TPoint`

Visibility: public

78.5.13 TPoint.subtract(TPoint,TPoint):TPoint

Declaration: `TPoint.class operator -(const apt1: TPoint; const apt2: TPoint) : TPoint`

Visibility: public

78.5.14 TPoint.assign(TSmallPoint):TPoint

Declaration: `TPoint.class operator :=(const aspt: TSmallPoint) : TPoint`

Visibility: public

78.5.15 TPoint.explicit(TPoint):TSmallPoint

Declaration: `TPoint.class operator explicit(const apt: TPoint) : TSmallPoint`

Visibility: public

78.6 TPointF

```

TPointF = packed record
public
  x : Single;
  y : Single;
  Add;
  function Distance(const apt: TPointF) : Single;
  function DotProduct
    (const apt: TPointF) : Single;
  function IsZero : Boolean;
  Subtract
  ;
  SetLocation;
  Offset;
  function Scale(afactor: Single) : TPointF
  ;
  function Ceiling : TPoint;
  function Truncate : TPoint;
  function
    Floor : TPoint;
  function Round : TPoint;
  function &Length : Single
  ;
  Create;
  TPointF.class operator =(const apt1: TPointF; const
    apt2: TPointF)
    : Boolean;
  TPointF.class
  operator <>(const apt1: TPointF; const apt2: TPointF)
    : Boolean;
  TPointF.class operator +(const apt1
    : TPointF; const apt2: TPointF)
    : TPointF
  ;
  TPointF.class operator -(const apt1: TPointF; const apt2: TPointF
    )
    : TPointF;
  TPointF.class operator
    -(const apt1: TPointF) : TPointF;
  TPointF.class operator *(const
    apt1: TPointF; const apt2: TPointF)
    :
    Single;
  TPointF.class operator *(const apt1: TPointF; afactor:
    single) : TPointF;
  TPointF.class operator *(afactor: single; const
    apt1: TPointF) : TPointF;
end

```

78.6.1 Method overview

Page	Method	Description
1953	Add	
1955	add(TPointF,TPointF):TPointF	
1954	Ceiling	
1955	Create	
1953	Distance	
1953	DotProduct	
1955	equal(TPointF,TPointF):Boolean	
1954	Floor	
1953	IsZero	
1955	Length	
1956	multiply(single,TPointF):TPointF	
1956	multiply(TPointF,single):TPointF	
1955	multiply(TPointF,TPointF):Single	
1955	negative(TPointF):TPointF	
1955	notequal(TPointF,TPointF):Boolean	
1954	Offset	
1954	Round	
1954	Scale	
1954	SetLocation	
1954	Subtract	
1955	subtract(TPointF,TPointF):TPointF	
1954	Truncate	

78.6.2 TPointF.Add

Declaration: `function Add(const apt: TPoint) : TPointF`
`function Add(const apt: TPointF) : TPointF`

Visibility: public

78.6.3 TPointF.Distance

Declaration: `function Distance(const apt: TPointF) : Single`

Visibility: public

78.6.4 TPointF.DotProduct

Declaration: `function DotProduct(const apt: TPointF) : Single`

Visibility: public

78.6.5 TPointF.IsZero

Declaration: `function IsZero : Boolean`

Visibility: public

78.6.6 TPointF.Subtract

Declaration: `function Subtract(const apt: TPointF) : TPointF`
`function Subtract(const apt: TPoint) : TPointF`

Visibility: public

78.6.7 TPointF.SetLocation

Declaration: `procedure SetLocation(const apt: TPointF)`
`procedure SetLocation(const apt: TPoint)`
`procedure SetLocation(ax: LongInt; ay: LongInt)`

Visibility: public

78.6.8 TPointF.Offset

Declaration: `procedure Offset(const apt: TPointF)`
`procedure Offset(const apt: TPoint)`
`procedure Offset(dx: LongInt; dy: LongInt)`

Visibility: public

78.6.9 TPointF.Scale

Declaration: `function Scale(afactor: Single) : TPointF`

Visibility: public

78.6.10 TPointF.Ceiling

Declaration: `function Ceiling : TPoint`

Visibility: public

78.6.11 TPointF.Truncate

Declaration: `function Truncate : TPoint`

Visibility: public

78.6.12 TPointF.Floor

Declaration: `function Floor : TPoint`

Visibility: public

78.6.13 TPointF.Round

Declaration: `function Round : TPoint`

Visibility: public

78.6.14 TPointF.Length

Declaration: `function &Length : Single`

Visibility: `public`

78.6.15 TPointF.Create

Declaration: `class function Create(const ax: Single; const ay: Single) : TPointF
; Overload; Static
class function Create(const apt: TPointF) : TPointF; Overload; Static`

Visibility: `public`

78.6.16 TPointF.equal(TPointF,TPointF):Boolean

Declaration: `TPointF.class operator =(const apt1: TPointF; const apt2: TPointF)
: Boolean`

Visibility: `public`

78.6.17 TPointF.notequal(TPointF,TPointF):Boolean

Declaration: `TPointF.class operator <>(const apt1: TPointF; const apt2: TPointF)
: Boolean`

Visibility: `public`

78.6.18 TPointF.add(TPointF,TPointF):TPointF

Declaration: `TPointF.class operator +(const apt1: TPointF; const apt2: TPointF)
: TPointF`

Visibility: `public`

78.6.19 TPointF.subtract(TPointF,TPointF):TPointF

Declaration: `TPointF.class operator -(const apt1: TPointF; const apt2: TPointF)
: TPointF`

Visibility: `public`

78.6.20 TPointF.negative(TPointF):TPointF

Declaration: `TPointF.class operator -(const apt1: TPointF) : TPointF`

Visibility: `public`

78.6.21 TPointF.multiply(TPointF,TPointF):Single

Declaration: `TPointF.class operator *(const apt1: TPointF; const apt2: TPointF)
: Single`

Visibility: `public`

78.6.22 TPointF.multiply(TPointF,single):TPointF

Declaration: TPointF.class operator *(const apt1: TPointF; afactor: single) : TPointF

Visibility: public

78.6.23 TPointF.multiply(single,TPointF):TPointF

Declaration: TPointF.class operator *(afactor: single; const apt1: TPointF) : TPointF

Visibility: public

78.7 TRect

```

TRect = packed record
private
    function getHeight : LongInt;
    function
        getLocation : TPoint;
    function getSize : TSize;
    function getWidth
        : LongInt;
    procedure setHeight (AValue: LongInt);
    procedure setSize
        (AValue: TSize);
    procedure setWidth (AValue: LongInt);
public
    Create
    ;
    TRect.class operator =(L: TRect; R: TRect) : Boolean;
    TRect
        .class operator <>(L: TRect; R: TRect) : Boolean;
    TRect.class operator
        +(L: TRect; R: TRect) : TRect;
    TRect.class operator *(L: TRect
        ; R: TRect) : TRect;
    class function Empty : TRect; Static;
    procedure
        NormalizeRect;
    function IsEmpty : Boolean;
    Contains;
    function
        IntersectsWith(R: TRect) : Boolean;
    Intersect;
    Union;
    Offset
    ;
    SetLocation;
    Inflate;
    function CenterPoint : TPoint;
    SplitRect
    ;
    property Height : LongInt;

```

```

    property Width : LongInt;
    property
    Size : TSize;
    property Location : TPoint;
case LongInt of
0: (
    public
    Left : LongInt;
    Top : LongInt;
    Right : LongInt;
    Bottom
    : LongInt;
);
1: (
public
    TopLeft : TPoint;
    BottomRight : TPoint
    ;
);
2: (
public
    Vector : TArray4IntegerType;
);
end

```

TRect defines a rectangle in a discrete plane. It is described by the horizontal (`left`, `right`) or vertical (`top`, `Bottom`) positions (in pixels) of the edges, or, alternatively, by the coordinates of the top left (`TopLeft`) and bottom right (`BottomRight`) corners.

78.7.1 Method overview

Page	Method	Description
1958	<code>add(TRect,TRect):TRect</code>	
1960	<code>CenterPoint</code>	
1959	<code>Contains</code>	
1958	<code>Create</code>	
1958	<code>Empty</code>	
1958	<code>equal(TRect,TRect):Boolean</code>	
1959	<code>Inflate</code>	
1959	<code>Intersect</code>	
1959	<code>IntersectsWith</code>	
1959	<code>IsEmpty</code>	
1958	<code>multiply(TRect,TRect):TRect</code>	
1958	<code>NormalizeRect</code>	
1958	<code>notequal(TRect,TRect):Boolean</code>	
1959	<code>Offset</code>	
1959	<code>SetLocation</code>	
1960	<code>SplitRect</code>	
1959	<code>Union</code>	

78.7.2 Property overview

Page	Properties	Access	Description
1960	Height	rw	
1960	Location	rw	
1960	Size	rw	
1960	Width	rw	

78.7.3 TRect.Create

Declaration: constructor Create(Origin: TPoint)
 constructor Create(Origin: TPoint; AWidth: LongInt; AHeight: LongInt)
 constructor Create(ALeft: LongInt; ATop: LongInt; ARight: LongInt;
 ABottom: LongInt)
 constructor Create(P1: TPoint; P2: TPoint; Normalize: Boolean)
 constructor Create(R: TRect; Normalize: Boolean)

Visibility: public

78.7.4 TRect.equal(TRect,TRect):Boolean

Declaration: TRect.class operator =(L: TRect; R: TRect) : Boolean

Visibility: public

78.7.5 TRect.notequal(TRect,TRect):Boolean

Declaration: TRect.class operator <>(L: TRect; R: TRect) : Boolean

Visibility: public

78.7.6 TRect.add(TRect,TRect):TRect

Declaration: TRect.class operator +(L: TRect; R: TRect) : TRect

Visibility: public

78.7.7 TRect.multiply(TRect,TRect):TRect

Declaration: TRect.class operator *(L: TRect; R: TRect) : TRect

Visibility: public

78.7.8 TRect.Empty

Declaration: class function Empty : TRect; Static

Visibility: public

78.7.9 TRect.NormalizeRect

Declaration: procedure NormalizeRect

Visibility: public

78.7.10 TRect.IsEmpty

Declaration: `function IsEmpty : Boolean`

Visibility: `public`

78.7.11 TRect.Contains

Declaration: `function Contains(Pt: TPoint) : Boolean`
`function Contains(R: TRect) : Boolean`

Visibility: `public`

78.7.12 TRect.IntersectsWith

Declaration: `function IntersectsWith(R: TRect) : Boolean`

Visibility: `public`

78.7.13 TRect.Intersect

Declaration: `class function Intersect(R1: TRect; R2: TRect) : TRect; Static`
`procedure Intersect(R: TRect)`

Visibility: `public`

78.7.14 TRect.Union

Declaration: `class function Union(R1: TRect; R2: TRect) : TRect; Static`
`procedure Union(R: TRect)`
`class function Union(const Points: Array of TPoint) : TRect; Static`

Visibility: `public`

78.7.15 TRect.Offset

Declaration: `procedure Offset(DX: LongInt; DY: LongInt)`
`procedure Offset(DP: TPoint)`

Visibility: `public`

78.7.16 TRect.SetLocation

Declaration: `procedure SetLocation(X: LongInt; Y: LongInt)`
`procedure SetLocation(P: TPoint)`

Visibility: `public`

78.7.17 TRect.Inflate

Declaration: `procedure Inflate(DX: LongInt; DY: LongInt)`
`procedure Inflate(DL: LongInt; DT: LongInt; DR: LongInt; DB: LongInt)`

Visibility: `public`

78.7.18 TRect.CenterPoint

Declaration: `function CenterPoint : TPoint`

Visibility: `public`

78.7.19 TRect.SplitRect

Declaration: `function SplitRect (SplitType: TSplitRectType; ASize: LongInt) : TRect`
`function SplitRect (SplitType: TSplitRectType; Percent: Double) : TRect`

Visibility: `public`

78.7.20 TRect.Height

Declaration: `Property Height : LongInt`

Visibility: `public`

Access: `Read,Write`

78.7.21 TRect.Width

Declaration: `Property Width : LongInt`

Visibility: `public`

Access: `Read,Write`

78.7.22 TRect.Size

Declaration: `Property Size : TSize`

Visibility: `public`

Access: `Read,Write`

78.7.23 TRect.Location

Declaration: `Property Location : TPoint`

Visibility: `public`

Access: `Read,Write`

78.8 TRectF

```
TRectF = packed record
private
  function GetHeight : Single;
  function
    GetWidth : Single;
  procedure SetHeight (AValue: Single);
  procedure
```

```

    SetWidth(AValue: Single);
public
    function Union(const r: TRectF
    ) : TRectF;
    procedure Offset(const dx: Single; const dy: Single
    );
    property Width : Single;
    property Height : Single;
case Integer
    of
0: (
public
    Left : Single;
    Top : Single;
    Right : Single
    ;
    Bottom : Single;
);
1: (
public
    TopLeft : TPointF;
    BottomRight
    : TPointF;
);
end

```

78.8.1 Method overview

Page	Method	Description
1961	Offset	
1961	Union	

78.8.2 Property overview

Page	Properties	Access	Description
1962	Height	rw	
1962	Width	rw	

78.8.3 TRectF.Union

Declaration: `function Union(const r: TRectF) : TRectF`

Visibility: public

78.8.4 TRectF.Offset

Declaration: `procedure Offset(const dx: Single; const dy: Single)`

Visibility: public

78.8.5 TRectF.Width

Declaration: Property Width : Single

Visibility: public

Access: Read,Write

78.8.6 TRectF.Height

Declaration: Property Height : Single

Visibility: public

Access: Read,Write

78.9 TSize

```
TSize = packed record
public
  cx : LongInt;
  cy : LongInt;
  function
    Add(const asz: TSize) : TSize;
    function Distance(const asz: TSize
    ) : Double;
    function IsZero : Boolean;
    function Subtract(const
    asz: TSize) : TSize;
    TSize.class operator =(const asz1: TSize;
    const asz2: TSize) : Boolean;
    TSize.class operator <>(const asz1
    : TSize; const asz2: TSize) : Boolean;
    TSize.class operator +(const
    asz1: TSize; const asz2: TSize) : TSize;
    TSize.class operator
    -(const asz1: TSize; const asz2: TSize) : TSize;
  property Width
    : LongInt;
  property Height : LongInt;
end
```

TSize is a type to describe the size of a rectangular area, where cx is the width, cy is the height (in pixels) of the rectangle.

78.9.1 Method overview

Page	Method	Description
1963	Add	
1964	add(TSize,TSize):TSize	
1963	Distance	
1963	equal(TSize,TSize):Boolean	
1963	IsZero	
1963	notequal(TSize,TSize):Boolean	
1963	Subtract	
1964	subtract(TSize,TSize):TSize	

78.9.2 Property overview

Page	Properties	Access	Description
1964	Height	rw	
1964	Width	rw	

78.9.3 TSize.Add

Declaration: `function Add(const asz: TSize) : TSize`

Visibility: public

78.9.4 TSize.Distance

Declaration: `function Distance(const asz: TSize) : Double`

Visibility: public

78.9.5 TSize.IsZero

Declaration: `function IsZero : Boolean`

Visibility: public

78.9.6 TSize.Subtract

Declaration: `function Subtract(const asz: TSize) : TSize`

Visibility: public

78.9.7 TSize.equal(TSize,TSize):Boolean

Declaration: `TSize.class operator =(const asz1: TSize; const asz2: TSize) : Boolean`

Visibility: public

78.9.8 TSize.notequal(TSize,TSize):Boolean

Declaration: `TSize.class operator <>(const asz1: TSize; const asz2: TSize) : Boolean`

Visibility: public

78.9.9 TSize.add(TSize,TSize):TSize

Declaration: `TSize.class operator +(const asz1: TSize; const asz2: TSize) : TSize`

Visibility: public

78.9.10 TSize.subtract(TSize,TSize):TSize

Declaration: `TSize.class operator -(const asz1: TSize; const asz2: TSize) : TSize`

Visibility: public

78.9.11 TSize.Width

Declaration: `Property Width : LongInt`

Visibility: public

Access: Read,Write

78.9.12 TSize.Height

Declaration: `Property Height : LongInt`

Visibility: public

Access: Read,Write

78.10 IClassFactory**78.10.1 Description**

`IClassFactory` is defined for Delphi/Kylix compatibility and should not be used.

78.10.2 Method overview

Page	Method	Description
1964	<code>CreateInstance</code>	Create a new instance of an interface.
1965	<code>LockServer</code>	Lock ActiveX server object.

78.10.3 IClassFactory.CreateInstance

Synopsis: Create a new instance of an interface.

Declaration: `function CreateInstance(const unkOuter: IUnknown; const riid: TGuid;
out vObject) : HRESULT`

Visibility: default

Description: `IClassFactory.CreateInstance` is defined for Delphi/Kylix compatibility and should not be used.

78.10.4 IClassFactory.LockServer

Synopsis: Lock ActiveX server object.

Declaration: `function LockServer(fLock: LongBool) : HRESULT`

Visibility: default

Description: `IClassFactory.LockServer` is defined for Delphi/Kylix compatibility and should not be used.

78.11 ISequentialStream

78.11.1 Description

`ISequentialStream` is the interface for streams which only support sequential reading of chunks of data. It is defined for Delphi/Kylix compatibility and should not be used.

See also: `IStream` ([1965](#))

78.11.2 Method overview

Page	Method	Description
1965	Read	Read data from the stream
1965	Write	Write data to the stream

78.11.3 ISequentialStream.Read

Synopsis: Read data from the stream

Declaration: `function Read(pv: Pointer; cb: DWORD; pcbRead: PDWord) : HRESULT`

Visibility: default

Description: `Read` reads `cbCount` bytes from the stream into the memory pointed to by `pv` and returns the number of bytes read in `pcbRead`. The result is zero for success or an error code.

See also: `ISequentialStream.Write` ([1965](#))

78.11.4 ISequentialStream.Write

Synopsis: Write data to the stream

Declaration: `function Write(pv: Pointer; cb: DWORD; pcbWritten: PDWord) : HRESULT`

Visibility: default

Description: `Write` writes `cbCount` bytes from the memory pointed to by `pv` to the stream and returns the number of bytes written in `pcbWritten`. The result is zero for success or an error code.

See also: `ISequentialStream.Read` ([1965](#))

78.12 IStream

78.12.1 Description

An abstract interface for an external (non pascal) stream, as defined in Microsoft COM interfaces

78.12.2 Method overview

Page	Method	Description
1968	Clone	Clone the stream instance
1967	Commit	Commit data to the stream
1966	CopyTo	Copy data from one stream to another
1967	LockRegion	Lock a region of bytes in the stream
1967	Revert	Revert changes
1966	Seek	Set the stream position
1966	SetSize	Set the stream size
1968	Stat	return information about the stream.
1967	UnlockRegion	Unlocks a previously locked region of bytes in the stream

78.12.3 IStream.Seek

Synopsis: Set the stream position

Declaration: `function Seek(dlibMove: Largeint; dwOrigin: DWORD;
out libNewPosition: LargeUint) : HRESULT`

Visibility: default

Description: `Seek` sets the stream position at `dlibMove` bytes from `dwOrigin` (one of the `SEEK_*` constants) and returns the new absolute position in `libNewPosition`. The function returns zero on success, or an error code.

Errors: On error, a nonzero exit code is returned.

78.12.4 IStream.SetSize

Synopsis: Set the stream size

Declaration: `function SetSize(libNewSize: LargeUint) : HRESULT`

Visibility: default

Description: `SetSize` sets the size of the stream to `libNewSize` bytes, if the stream allows it. On success, zero is returned.

Errors: On error, a nonzero exit code is returned.

78.12.5 IStream.CopyTo

Synopsis: Copy data from one stream to another

Declaration: `function CopyTo(stm: IStream; cb: LargeUint; out cbRead: LargeUint;
out cbWritten: LargeUint) : HRESULT`

Visibility: default

Description: `CopyTo` copies `cb` bytes from the stream to target stream `stm`. `cbRead` returns how many bytes were read from the stream, `cbwrite` returns how many bytes were actually written to the destination stream. The function returns zero on success.

Errors: On error, a nonzero exit code is returned.

78.12.6 IStream.Commit

Synopsis: Commit data to the stream

Declaration: `function Commit(grfCommitFlags: DWORD) : HRESULT`

Visibility: default

Description: `Commit` commits the data in the stream to the underlying medium. `Flags` is a set of options to control the commit operation (see MSDN for the possible flags).

Errors: On error, a nonzero exit code is returned.

78.12.7 IStream.Revert

Synopsis: Revert changes

Declaration: `function Revert : HRESULT`

Visibility: default

Description: `Revert` reverts all changes that were done to a transacted stream, i.e. all changes since the last commit. The function returns zero on success.

Errors: On error, a nonzero exit code is returned.

78.12.8 IStream.LockRegion

Synopsis: Lock a region of bytes in the stream

Declaration: `function LockRegion(libOffset: LargeUInt; cb: LargeUInt;
dwLockType: DWORD) : HRESULT`

Visibility: default

Description: `LockRegion` locks a region of the storage, starting at `libOffset`, for `cbCount` bytes. The applied lock is of type `dwLockType`. The function returns zero if the lock was successfully applied.

Errors: On error, a nonzero exit code is returned.

78.12.9 IStream.UnlockRegion

Synopsis: Unlocks a previously locked region of bytes in the stream

Declaration: `function UnlockRegion(libOffset: LargeUInt; cb: LargeUInt;
dwLockType: DWORD) : HRESULT`

Visibility: default

Description: `UnlockRegion` removes the lock on a region of the storage, starting at `libOffset`, for `cbCount` bytes. The lock must be of type `dwLockType`. The function returns zero if the lock was successfully removed.

Errors: On error, a nonzero exit code is returned.

78.12.10 IStream.Stat

Synopsis: return information about the stream.

Declaration: `function Stat(out statstg: TStatStg; grfStatFlag: DWORD) : HRESULT`

Visibility: default

Description: `Stat` returns information about the stream in `statstg`, taking into account the flags in `grfStatFlag` (one of the `STATFLAG_` constants). The function returns zero if the call was successful.

Errors: On error, a nonzero exit code is returned.

78.12.11 IStream.Clone

Synopsis: Clone the stream instance

Declaration: `function Clone(out stm: IStream) : HRESULT`

Visibility: default

Description: `Clone` returns an independent but initially equal copy of the stream in `stm`. The function returns zero if the call was successful.

Errors: On error, a nonzero exit code is returned.

78.13 TBitConverter

78.13.1 Method overview

Page	Method	Description
1968	<code>From</code>	
1969	<code>InTo</code>	
1968	<code>UnsafeFrom</code>	
1969	<code>UnsafeInTo</code>	

78.13.2 TBitConverter.UnsafeFrom

Declaration: `class procedure UnsafeFrom<T>(const ASrcValue: T;
var ADestination: Array of Byte;
AOffset: Integer); Static`

Visibility: default

78.13.3 TBitConverter.From

Declaration: `class procedure From<T>(const ASrcValue: T;
var ADestination: Array of Byte;
AOffset: Integer); Static`

Visibility: default

78.13.4 TBitConverter.UnsafeInTo

Declaration: `class function UnsafeInTo<T>(const ASource: Array of Byte;
AOffset: Integer) : T; Static`

Visibility: default

78.13.5 TBitConverter.InTo

Declaration: `class function InTo<T>(const ASource: Array of Byte; AOffset: Integer)
: T; Static`

Visibility: default

Chapter 79

Reference for unit 'TypeInfo'

79.1 Used units

Table 79.1: Used units by unit 'TypeInfo'

Name	Page
System	1339
sysutils	1615

79.2 Overview

The `TypeInfo` unit contains many routines which can be used for the querying of the Run-Time Type Information (RTTI) which is generated by the compiler for classes that are compiled under the `{ $M+ }` switch. This information can be used to retrieve or set property values for published properties for totally unknown classes. In particular, it can be used to stream classes. The `TPersistent` class in the `Classes` unit is compiled in the `{ $M+ }` state and serves as the base class for all classes that need to be streamed.

The unit should be compatible to the Delphi unit with the same name.

The examples in this chapter use a `rttiobj` auxiliary unit, which contains an object that has a published property for all supported types. It also contains some auxiliary routines and definitions. This unit is included in the documentation sources, in the directory `typinfex`.

79.3 Auxiliary functions

Other `typinfo` related functions.

Table 79.2:

Name	Description
<code>GetEnumName</code> (1986)	Get an enumerated type element name
<code>GetEnumValue</code> (1988)	Get ordinal number of an enumerated type, based on the name.
<code>GetEnumNameCount</code> (1987)	Get number of elements in an enumerated type.
<code>GetTypeData</code> (2001)	Skip type name and return a pointer to the type data
<code>SetToString</code> (2011)	Convert a set to its string representation
<code>StringToSet</code> (2013)	Convert a string representation of a set to a set

79.4 Getting or setting property values

Functions to set or set a property's value.

Table 79.3:

Name	Description
<code>GetEnumProp</code> (1987)	Return the value of an enumerated type property
<code>GetFloatProp</code> (1988)	Return the value of a float property
<code>GetInt64Prop</code> (1989)	Return the value of an Int64 property
<code>GetMethodProp</code> (1990)	Return the value of a procedural type property
<code>GetObjectProp</code> (1992)	Return the value of an object property
<code>GetOrdProp</code> (1994)	Return the value of an ordinal type property
<code>GetProperty</code> (1997)	Return the value of a property as a variant
<code>GetSetProp</code> (1998)	Return the value of a set property
<code>GetStrProp</code> (2000)	Return the value of a string property
<code>GetWideStrProp</code> (2002)	Return the value of a widestring property
<code>GetVariantProp</code> (2001)	Return the value of a variant property
<code>SetEnumProp</code> (2007)	Set the value of an enumerated type property
<code>SetFloatProp</code> (2007)	Set the value of a float property
<code>SetInt64Prop</code> (2007)	Set the value of an Int64 property
<code>SetMethodProp</code> (2008)	Set the value of a procedural type property
<code>SetObjectProp</code> (2009)	Set the value of an object property
<code>SetOrdProp</code> (2009)	Set the value of an ordinal type property
<code>SetPropertyValue</code> (2010)	Set the value of a property through a variant
<code>SetSetProp</code> (2011)	Set the value of a set property
<code>SetStrProp</code> (2011)	Set the value of a string property
<code>SetWideStrProp</code> (2013)	Set the value of a widestring property
<code>SetVariantProp</code> (2013)	Set the value of a variant property

79.5 Examining published property information

Functions for retrieving or examining property information

Table 79.4:

Name	Description
FindPropInfo (1984)	Getting property type information, With error checking.
GetPropInfo (1995)	Getting property type information, No error checking.
GetPropInfos (1995)	Find property information of a certain kind
GetObjectPropClass (1993)	Return the declared class of an object property
GetPropList (1996)	Get a list of all published properties
IsPublishedProp (2002)	Is a property published
IsStoredProp (2003)	Is a property stored
PropIsType (2004)	Is a property of a certain kind
PropType (2005)	Return the type of a property

79.6 Constants, types and variables

79.6.1 Constants

`BooleanIdents : Array[Boolean] of string = ('False', 'True')`

Names for boolean values

`DotSep : string = '.'`

Name separator character

`OnGetPropValue : TGetPropValue = Nil`

This callback is set by the variants unit to enable reading of properties as a variant. If set, it is called by the `GetPropValue` (1997) function.

`OnGetVariantprop : TGetVariantProp = Nil`

This callback is set by the variants unit to enable reading of variant properties. If set, it is called by the `GetVariantProp` (2001) function.

`OnSetPropValue : TSetPropValue = Nil`

This callback is set by the variants unit to enable writing of properties as a variant. If set, it is called by the `SetPropValue` (2010) function.

`OnSetVariantprop : TSetVariantProp = Nil`

This callback is set by the variants unit to enable writing of variant properties. If set, it is called by the `GetVariantProp` (2001) function.

`ptConst = 3`

Constant used in access method

`ptField = 0`

Property access directly from field

```
ptStatic = 1
```

Property access via static method

```
ptVirtual = 2
```

Property access via virtual method

```
tkAny = [Low(TTypeKind)..High(TTypeKind)]
```

Any property type

```
tkArray = System.tkArray
```

Array property.

```
tkAString = System.tkAString
```

Ansistring property.

```
tkBool = System.tkBool
```

Boolean property.

```
tkChar = System.tkChar
```

Char property.

```
tkClass = System.tkClass
```

Class property.

```
tkClassRef = System.tkClassRef
```

```
tkDynArray = System.tkDynArray
```

Dynamical array property.

```
tkEnumeration = System.tkEnumeration
```

Enumeration type property.

```
tkFile = System.tkFile
```

```
tkFloat = System.tkFloat
```

Float property.

`tkHelper = System.tkHelper`

`tkInt64 = System.tkInt64`

Int64 property.

`tkInteger = System.tkInteger`

Integer property.

`tkInterface = System.tkInterface`

Interface property.

`tkInterfaceRaw = System.tkInterfaceRaw`

Raw interface property.

`tkLString = System.tkLString`

Longstring property.

`tkMethod = System.tkMethod`

Method property.

`tkMethods = [tkMethod]`

Only method properties. (event handlers)

`tkObject = System.tkObject`

Object property.

`tkPointer = System.tkPointer`

`tkProcedure = tkProcVar`

Procedure kind

`tkProcVar = System.tkProcVar`

`tkProperties = tkAny - tkMethods - [tkUnknown]`

Real properties. (not methods)

`tkQWord = System.tkQWord`

QWord property.

```
tkRecord = System.tkRecord
```

Record property.

```
tkSet = System.tkSet
```

Set property.

```
tkSString = System.tkSString
```

Shortstring property.

```
tkString = tkSString
```

Alias for the `tsSString` enumeration value

```
tkUChar = System.tkUChar
```

```
tkUnknown = System.tkUnknown
```

Unknown property type.

```
tkUString = System.tkUString
```

```
tkVariant = System.tkVariant
```

Variant property.

```
tkWChar = System.tkWChar
```

Widechar property.

```
tkWString = System.tkWString
```

Widestring property.

79.6.2 Types

```
PClassData = ^TClassData
```

`PClassData` is a pointer to a `TClassData` (2015) record.

```
PInitManagedField = ^TInitManagedField
```

`PInitManagedField` is a pointer to a `TInitManagedField` (1978) record.

```
PInterfaceData = ^TInterfaceData
```

`PInterfaceData` is a pointer to a `TInterfaceData` (2016) record.

`PInterfaceRawData = ^TInterfaceRawData`

Pointer to a `TInterfaceRawData` record.

`PIntfMethodEntry = ^TIntfMethodEntry`

`PIntfMethodEntry` is a pointer to a `TIntfMethodEntry` (2019) record.

`PIntfMethodTable = ^TIntfMethodTable`

`PIntfMethodTable` is a pointer to a `TIntfMethodTable` (2021) record.

`PManagedField = ^TManagedField`

`PManagedField` is a pointer to `TManagedField` (2022). It is used to describe automatically managed fields in records when the type kind is `tkRecord`.

`PParameterLocation = ^TParameterLocation`

`PParameterLocation` defines a pointer to a `TParameterLocation` (2023) record.

`PParameterLocations = ^TParameterLocations`

`PParameterLocations` points to a `TParameterLocations` (2024) record.

`PProcedureParam = ^TProcedureParam`

`PProcedureParam` is a pointer to `TProcedureParam`. It is used in `TProcedureSignature` (2026).

`PPropData = ^TPropData`

`PPropData` is a pointer to a `TPropData` (2027) record.

`PPropInfo = ^TPropInfo`

Pointer to `TPropInfo` (2029) record

`PPropList = ^TPropList`

Pointer to `TPropList` (1980)

`PTypeInfo = ^PTypeInfo`

Pointer to `PTypeInfo` (1977) pointer

`PRecInitData = ^TRecInitData`

`PRecInitData` is a pointer to a `TRecInitData` (1981) record.

`PRecOpOffsetTable = ^TRecOpOffsetTable`

PRecOpOffsetTable is a Pointer to a TRecOpOffsetTable (1981) record.

PTypeData = ^TTypeData

Pointer to TTypeData (2045) record.

PTypeInfo = ^TTypeInfo

Pointer to TTypeInfo (1982) record

PVmtFieldClassTab = ^TVmtFieldClassTab

PVmtFieldClassTab points to a TVmtFieldClassTab (1983) record.

PVmtFieldEntry = ^TVmtFieldEntry

Pointer to #rtl.typinfo.TVmtFieldEntry (2048) type.

PVmtFieldTable = ^TVmtFieldTable

Pointer to #rtl.typinfo.TVmtFieldTable (2049) type.

PVmtMethodEntry = ^TVmtMethodEntry

PVmtMethodEntry is a Pointer to TVmtMethodEntry (1983) record.

PVmtMethodParam = ^TVmtMethodParam

PVmtMethodParam is a pointer to a TVmtMethodParam (2050) record.

PVmtMethodTable = ^TVmtMethodTable

PVmtMethodTable is a pointer to a TVmtMethodTable (2051) record.

ShortStringBase = string

ShortStringBase is the base definition of a short string.

```
TCallConv = (ccReg, ccCdecl, ccPascal, ccStdCall, ccSafeCall, ccCppdecl
,
            ccFar16, ccOldFPCCall, ccInternProc, ccSysCall, ccSoftFloat
,
            ccMWPascal)
```

Table 79.5: Enumeration values for type TCallConv

Value	Explanation
ccCdecl	Cdecl calling convention.
ccCppdecl	Cppdecl calling convention
ccFar16	Far16 calling convention (Delphi compatibility)
ccInternProc	InternProc calling convention (compiler internal)
ccMWPPascal	MWPPascal (MetroWerks Pascal) calling convention.
ccOldFPCCall	OldFPCCall calling convention (deprecated)
ccPascal	Pascal calling convention.
ccReg	Register calling convention
ccSafeCall	SafeCall calling convention.
ccSoftFloat	Softfloat calling convention.
ccStdCall	stdcall calling convention.
ccSysCall	SysCall calling convention.

TCallConv is a type describing the calling convention used by a method. It contains an element for all supported calling conventions.

```
TFloatType = (ftSingle, ftDouble, ftExtended, ftComp, ftCurr)
```

Table 79.6: Enumeration values for type TFloatType

Value	Explanation
ftComp	Comp-type float
ftCurr	Currency-type float
ftDouble	Double-sized float
ftExtended	Extended-size float
ftSingle	Single-sized float

The size of a float type.

```
TGetPropValue = function(Instance: TObject; PropInfo: PPropInfo;
    PreferStrings: Boolean) : Variant
```

The callback function must return the property with name `PropName` of instance `Instance`. If `PreferStrings` is true, it should favour converting the property to a string value. The function needs to return the variant with the property value.

```
TGetVariantProp = function(Instance: TObject; PropInfo: PPropInfo
    )
    : Variant
```

The callback function must return the variant property with name `PropName` of instance `Instance`.

```
TInitManagedField = TManagedField
```

TInitManagedField is an alias for TManagedField ([2022](#)).

```
TIntfFlag = (ifHasGuid, ifDispInterface, ifDispatch, ifHasStrGUID)
```

Table 79.7: Enumeration values for type TIntfFlag

Value	Explanation
ifDispatch	Interface is a dispatch interface
ifDispInterface	Interface is a dual dispatch interface
ifHasGuid	Interface has GUID identifier
ifHasStrGUID	Interface has a string GUID identifier

Type of interface.

```
TIntfFlags = Set of TIntfFlag
```

Set of TIntfFlag (1979).

```
TIntfFlagsBase = Set of TIntfFlag
```

Set of TIntfFlag (1979).

```
TMethodKind = (mkProcedure, mkFunction, mkConstructor, mkDestructor,
  mkClassProcedure, mkClassFunction, mkClassConstructor
  ,
  mkClassDestructor, mkOperatorOverload)
```

Table 79.8: Enumeration values for type TMethodKind

Value	Explanation
mkClassConstructor	Class constructor method.
mkClassDestructor	Class destructor method.
mkClassFunction	Class function
mkClassProcedure	Class procedure
mkConstructor	Class constructor
mkDestructor	Class Destructor
mkFunction	Function method
mkOperatorOverload	Operator overloader
mkProcedure	Procedure method.

Method type description

```
TOrdType = (otSByte, otUByte, otSWord, otUWord, otSLong, otULong, otSQWord
  ,
  otUQWord)
```

Table 79.9: Enumeration values for type TOrdType

Value	Explanation
otSByte	Signed byte
otSLong	Signed longint
otSQWord	Signed QWord
otSWord	Signed word
otUByte	Unsigned byte
otULong	Unsigned longint (Cardinal)
otUQWord	Unsigned QWord
otUWord	Unsigned word

If the property is and ordinal type, then TOrdType determines the size and sign of the ordinal type:

```
TParamFlag = (pfVar, pfConst, pfArray, pfAddress, pfReference, pfOut,
  pfConstRef, pfHidden, pfHigh, pfSelf, pfVmt, pfResult)
```

Table 79.10: Enumeration values for type TParamFlag

Value	Explanation
pfAddress	Parameter is passed by address
pfArray	Parameter is an array parameter
pfConst	Parameter is a const parameter (i.e. cannot be modified)
pfConstRef	Constref parameter type
pfHidden	hidden parameter type
pfHigh	High bound parameter type
pfOut	Parameter is a string parameter
pfReference	Parameter is passed by reference
pfResult	Result location parameter
pfSelf	Self parameter type
pfVar	Parameter is a var parameter (passed by reference)
pfVmt	VMT parameter type

TParamFlag describes a parameter.

```
TParamFlags = Set of TParamFlag
```

The kind of parameter for a method

```
TProcInfoProc = procedure(PropInfo: PPropInfo) of object
```

Property info callback method

```
TPropList = Array[0..65535] of PPropInfo
```

Array of property information pointers

```
TRecInitData = packed record
```

```

public
  Terminator : Pointer;
  Size
  : Integer;
  InitOffsetOp : PRecOpOffsetTable;
  ManagementOp : Pointer
  ;
  ManagedFieldCount : Integer;
end

```

TRecInitData describes the generated RTTI info with which you can initialize a record that contains managed fields.

```

TRecOpOffsetEntry = packed record
public
  ManagementOperator : CodePointer
  ;
  FieldOffset : SizeUInt;
end

```

TRecOpOffsetEntry describes management operator info for a record.

```

TRecOpOffsetTable = packed record
public
  Count : LongWord;
  Entries
  : Array[0..0] of TRecOpOffsetEntry;
end

```

TRecOpOffsetTable is a table of TRecOpOffsetEntry (1981) records with management operator info for the managed fields of a record.

```
TRegisterType = (Invalid, Int, FP, MMX, MultiMedia, Special, Address)
```

Table 79.11: Enumeration values for type TRegisterType

Value	Explanation
Address	Address register
FP	Floating-point register
Int	Integer register
Invalid	Invalid register
MMX	MMX register
MultiMedia	Multimedia register
Special	Special register

TRegisterType describes the type of the CPU register.

```

TSetPropValue = procedure (Instance: TObject; PropInfo: PPropInfo;
  const Value: Variant)

```

The callback function must set the property with name PropName of instance Instance to Value.

```
TSetVariantProp = procedure (Instance: TObject; PropInfo: PPropInfo
;
                                const Value: Variant)
```

The callback function must set the variant property with name `PropName` of instance to `Value`.

```
TSubRegister = (None, Lo, Hi, Word, DWord, QWord, FloatSingle, FloatDouble
,
                FloatQuad, MultiMediaSingle, MultiMediaDouble,
                MultiMediaWhole, MultiMediaX, MultiMediaY)
```

Table 79.12: Enumeration values for type `TSubRegister`

Value	Explanation
DWord	DWord size
FloatDouble	Double-sized float value
FloatQuad	Quadruple-sized float value
FloatSingle	Single-sized float value
Hi	High
Lo	Low
MultiMediaDouble	Multimedia register double-sized float
MultiMediaSingle	Multimedia register single-sized float
MultiMediaWhole	Multimedia register whole-sized
MultiMediaX	Multimedia register X position
MultiMediaY	Multimedia register Y position
None	None
QWord	QWord size
Word	Word size

`TSubRegister` describes CPU sub-register sizes or locations.

```
TTypeInfo = record
public
    Kind : TTypeKind;
    Name : ShortString
;
end
```

The `TypeInfo` function returns a pointer to a `TTypeInfo` record.

Note that the `Name` field is stored with as much bytes as needed to store the name, it is not padded to 255 characters. The type data immediately follows the `TTypeInfo` record as a `TTypeData` (2045) record.

```
TTypeKind = System.TTypeKind
```

`TTypeKind` was moved to the system unit, see `#rtl.system.TTypeKind` (1405)

```
TTypeKinds = Set of TTypeKind
```

Set of `TTypeKind` (1982) enumeration.

```

TVmtFieldClassTab = packed record
public
  Count : Word;
  ClassRef
    : Array[0..0] of PClass;
end

```

TVmtFieldClassTab describes the fields of class type. A pointer to this table is present in TVmtFieldTable (2049)

```

TVmtMethodEntry = packed record
public
  Name : PShortString;
  CodeAddress
    : CodePointer;
end

```

TVmtMethodEntry is a description of the VMT info generated for a method of a class. This is different from interface method RTTI info, which is described by TIntfMethodEntry (2019)

79.7 Procedures and functions

79.7.1 AddEnumElementAliases

Synopsis: Define aliases for enumerated elements

Declaration: `procedure AddEnumElementAliases(aTypeInfo: PTypeInfo;`
`const aNames: Array of string;`
`aStartValue: Integer)`

Visibility: default

Description: AddEnumElementAliases defines aliases for enumerated values of type aTypeInfo. The aliases are specified in aNames, and are applied as of the element with ordinal value aStartIndex. The aliases will be used in GetEnumValue (1988)

See also: RemoveEnumElementAliases (2006), GetEnumValue (1988), GetEnumeratedAliasValue (1986)

79.7.2 AlignPTypeInfo

Synopsis: Align TTypeInfo info

Declaration: `function AlignPTypeInfo(p: Pointer) : Pointer`

Visibility: default

Description: AlignPTypeInfo will align the pointer p on a correct boundary for TParamFlags (1980) data for the current platform and returns the resulting address.

See also: align (1970), AlignTypeData (1984), AlignPTypeInfo (1983)

79.7.3 AlignTParamFlags

Synopsis: Align TParamFlags info

Declaration: `function AlignTParamFlags(p: Pointer) : Pointer`

Visibility: default

Description: `AlignTParamFlags` will align the pointer `p` on a correct boundary for TParamFlags (1980) data for the current platform and returns the resulting address.

See also: `align` (1970), `AlignTypeData` (1984), `AlignPTypeInfo` (1983)

79.7.4 AlignTypeData

Synopsis: Align type data

Declaration: `function AlignTypeData(p: Pointer) : Pointer`

Visibility: default

Description: `AlignTypeData` will align the pointer `p` on a correct boundary for type data for the current platform and returns the resulting address.

See also: `align` (1970), `AlignTParamFlags` (1984), `AlignPTypeInfo` (1983)

79.7.5 DerefTypeInfoPtr

Synopsis: Dereference type info pointer

Declaration: `function DerefTypeInfoPtr(Info: PTypeInfo) : PTypeInfo`

Visibility: default

Description: `DerefTypeInfoPtr` can be used to dereference the `Info` type info pointer if need be: in FPC version 3.0, this pointer does not need dereferencing, but in FPC version 3.1, the pointer must be dereferenced. This is useful for code that must work in version 3.0 and later.

Errors: The function handles nil values well.

See also: `PTypeInfo` (1977)

79.7.6 FindPropInfo

Synopsis: Return property information by property name.

```
Declaration: function FindPropInfo(Instance: TObject; const PropName: string)
                : PPropInfo
function FindPropInfo(Instance: TObject; const PropName: string;
                AKinds: TTypeKinds) : PPropInfo
function FindPropInfo(AClass: TClass; const PropName: string)
                : PPropInfo
function FindPropInfo(AClass: TClass; const PropName: string;
                AKinds: TTypeKinds) : PPropInfo
```

Visibility: default

Description: `FindPropInfo` examines the published property information of a class and returns a pointer to the property information for property `PropName`. The class to be examined can be specified in one of two ways:

A`Class` class pointer.

Instance an instance of the class to be investigated.

If the property does not exist, a `EPropertyError` exception will be raised. The `GetPropInfo` (1995) function has the same function as the `FindPropInfo` function, but returns `Nil` if the property does not exist.

Errors: Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetPropInfo` (1995), `GetPropList` (1996), `GetPropInfos` (1995)

Listing: `./examples/typinfex/ex14.pp`

Program `example13`;

{ This program demonstrates the FindPropInfo function }

{ \$mode objfpc }

uses

`rttiobj, typinfo, sysutils;`

Var

`O : TMyTestObject;`

`PT : PTypeData;`

`PI : PPropInfo;`

`I, J : Longint;`

`PP : PPropList;`

`pri : PPropInfo;`

begin

`O := TMyTestObject.Create;`

`PI := FindPropInfo(O, 'BooleanField');`

`WriteLn('FindPropInfo(Instance, BooleanField) : ', PI^.Name);`

`PI := FindPropInfo(O.ClassType, 'ByteField');`

`WriteLn('FindPropInfo(Class, ByteField) : ', PI^.Name);`

`Write('FindPropInfo(Class, NonExistingProp) : ');`

Try

`PI := FindPropInfo(O, 'NonExistingProp');`

except

On `E: Exception` **do**

`WriteLn('Caught exception "', E.ClassName, '" with message : ', E.Message);`

end;

`O.Free;`

end.

79.7.7 GetDynArrayProp

Synopsis: Get the value of a dynamic array valued property

Declaration: `function GetDynArrayProp(Instance: TObject; const PropName: string)
: Pointer`

```
function GetDynArrayProp (Instance: TObject; PropInfo: PPropInfo)
    : Pointer
```

Visibility: default

Description: `GetDynArrayProp` returns the value of a dynamic array valued property of the object `Instance` as a pointer. The property to read can be specified using the name `PropName` or the property info `PropInfo`.

See also: `SetDynArrayProp` (2006)

79.7.8 GetEnumeratedAliasValue

Synopsis: Return ordinal value for an enumerated value

```
Declaration: function GetEnumeratedAliasValue (aTypeInfo: PTypeInfo;
    const aName: string) : Integer
```

Visibility: default

Description: `GetEnumeratedAliasValue` will return the ordinal value of the alias `aName` for type `aTypeInfo`.

See also: `AddEnumElementAliases` (1983), `RemoveEnumElementAliases` (2006), `GetEnumValue` (1988)

79.7.9 GetEnumName

Synopsis: Return name of enumeration constant.

```
Declaration: function GetEnumName (TypeInfo: PTypeInfo; Value: Integer) : string
```

Visibility: default

Description: `GetEnumName` scans the type information for the enumeration type described by `TypeInfo` and returns the name of the enumeration constant for the element with ordinal value equal to `Value`.

If `Value` is out of range, the first element of the enumeration type is returned. The result is returned in the case that was used in the declaration. (In earlier versions of FPC, the name was lowercased).

This can be used in combination with `GetOrdProp` to stream a property of an enumerated type.

Errors: No check is done to determine whether `TypeInfo` really points to the type information for an enumerated type.

See also: `GetOrdProp` (1994), `GetEnumValue` (1988)

Listing: ./examples/typinfex/ex9.pp

```
program example9;

{ This program demonstrates the GetEnumName, GetEnumValue functions }

{$mode objfpc}

uses rttiobj, typinfo;

Var
    O : TMyTestObject;
    TI : PTypeInfo;

begin
```

```

O:= TMyTestObject.Create;
TI:= GetPropInfo (O, 'MyEnumField')^. PropType;
WriteLn ( 'GetEnumName      : ', GetEnumName ( TI, Ord (O. MyEnumField) ));
WriteLn ( 'GetEnumValue ( mefirst ) : ', GetEnumName ( TI, GetEnumValue ( TI, ' mefirst ' )));
O.Free;
end.

```

79.7.10 GetEnumNameCount

Synopsis: Return number of names in an enumerated type

Declaration: `function GetEnumNameCount (enum1: PTypeInfo) : SizeInt`

Visibility: default

Description: `GetEnumNameCount` returns the number of values (names) in the enumerated type, described by `enum1`

Errors: No checking is done to see whether `Enum1` is really type information of an enumerated type.

See also: `GetEnumValue` (1988), `GetEnumName` (1986)

79.7.11 GetEnumProp

Synopsis: Return the value of an enumeration type property.

Declaration: `function GetEnumProp (Instance: TObject; const PropName: string) : string`
`function GetEnumProp (Instance: TObject; const PropInfo: PPropInfo)`
`: string`

Visibility: default

Description: `GetEnumProp` returns the value of an property of an enumerated type and returns the name of the enumerated value for the object `Instance`. The property whose value must be returned can be specified by its property info in `PropInfo` or by its name in `PropName`

Errors: No check is done to determine whether `PropInfo` really points to the property information for an enumerated type. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetEnumProp` (2007), `GetOrdProp` (1994), `GetStrProp` (2000), `GetInt64Prop` (1989), `GetMethodProp` (1990), `GetSetProp` (1998), `GetObjectProp` (1992), `GetEnumProp` (1987)

Listing: `./examples/typinfex/ex2.pp`

```

program example2;

{ This program demonstrates the GetEnumProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  TI : PTypeInfo;

```

```

begin
  O:= TMyTestObject.Create;
  PI:= GetPropInfo(O, 'MyEnumField');
  TI:= PI^.PropType;
  Writeln('Enum property      : ');
  Writeln('Value                : ', GetEnumName(TI, Ord(O.MyEnumField)));
  Writeln('Get (name)                 : ', GetEnumProp(O, 'MyEnumField'));
  Writeln('Get (propinfo)             : ', GetEnumProp(O, PI));
  SetEnumProp(O, 'MyEnumField', 'meFirst');
  Writeln('Set (name, meFirst)        : ', GetEnumName(TI, Ord(O.MyEnumField)));
  SetEnumProp(O, PI, 'meSecond');
  Writeln('Set (propinfo, meSecond)   : ', GetEnumName(TI, Ord(O.MyEnumField)));
  O.Free;
end.

```

79.7.12 GetEnumValue

Synopsis: Get ordinal value for enumerated type by name

Declaration: `function GetEnumValue(TypeInfo: PTypeInfo; const Name: string) : Integer`

Visibility: default

Description: `GetEnumValue` scans the type information for the enumeration type described by `TypeInfo` and returns the ordinal value for the element in the enumerated type that has identifier `Name`. The identifier is searched in a case-insensitive manner.

This can be used to set the value of enumerated properties from a stream.

For an example, see `GetEnumName` (1986).

Errors: If `Name` is not found in the list of enumerated values, then -1 is returned. No check is done whether `TypeInfo` points to the type information for an enumerated type.

See also: `GetEnumName` (1986), `SetOrdProp` (2009)

79.7.13 GetFloatProp

Synopsis: Return value of floating point property

Declaration: `function GetFloatProp(Instance: TObject; PropInfo: PPropInfo) : Extended`
`function GetFloatProp(Instance: TObject; const PropName: string)`
`: Extended`

Visibility: default

Description: `GetFloatProp` returns the value of the float property described by `PropInfo` or with name `Propname` for the object `Instance`. All float types are converted to extended.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid float property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetFloatProp` (2007), `GetOrdProp` (1994), `GetStrProp` (2000), `GetInt64Prop` (1989), `GetMethodProp` (1990), `GetSetProp` (1998), `GetObjectProp` (1992), `GetEnumProp` (1987)

Listing: `./examples/typinfex/ex4.pp`

```

program example4;

{ This program demonstrates the GetFloatProp function }

{$mode objfpc}

uses rttiobj , typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Real property : ');
  PI:=GetPropInfo(O, 'RealField');
  Writeln('Value           : ',O.RealField);
  Writeln('Get (name)        : ',GetFloatProp(O, 'RealField'));
  Writeln('Get (propinfo)       : ',GetFloatProp(O, PI));
  SetFloatProp(O, 'RealField',system.PI);
  Writeln('Set (name,pi)        : ',O.RealField);
  SetFloatProp(O, PI,exp(1));
  Writeln('Set (propinfo,e)     : ',O.RealField);
  Writeln('Extended property : ');
  PI:=GetPropInfo(O, 'ExtendedField');
  Writeln('Value           : ',O.ExtendedField);
  Writeln('Get (name)        : ',GetFloatProp(O, 'ExtendedField'));
  Writeln('Get (propinfo)     : ',GetFloatProp(O, PI));
  SetFloatProp(O, 'ExtendedField',system.PI);
  Writeln('Set (name,pi)      : ',O.ExtendedField);
  SetFloatProp(O, PI,exp(1));
  Writeln('Set (propinfo,e)   : ',O.ExtendedField);
  O.Free;
end.

```

79.7.14 GetInt64Prop

Synopsis: return value of an Int64 property

Declaration: `function GetInt64Prop(Instance: TObject; PropInfo: PPropInfo) : Int64`
`function GetInt64Prop(Instance: TObject; const PropName: string) : Int64`

Visibility: default

Remark Publishing of Int64 properties is not yet supported by Free Pascal. This function is provided for Delphi compatibility only at the moment.

`GetInt64Prop` returns the value of the property of type `Int64` that is described by `PropInfo` or with name `Propname` for the object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid `Int64` property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception

See also: [SetInt64Prop \(2007\)](#), [GetOrdProp \(1994\)](#), [GetStrProp \(2000\)](#), [GetFloatProp \(1988\)](#), [GetMethodProp \(1990\)](#), [GetSetProp \(1998\)](#), [GetObjectProp \(1992\)](#), [GetEnumProp \(1987\)](#)

Listing: ./examples/typinfex/ex15.pp

```

program example15;

{ This program demonstrates the GetInt64Prop function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Int64 property : ');
  PI:=GetPropInfo(O, 'Int64Field');
  Writeln('Value           : ',O.Int64Field);
  Writeln('Get (name)       : ',GetInt64Prop(O, 'Int64Field'));
  Writeln('Get (propinfo)    : ',GetInt64Prop(O, PI));
  SetInt64Prop(O, 'Int64Field',12345);
  Writeln('Set (name,12345)   : ',O.Int64Field);
  SetInt64Prop(O, PI,54321);
  Writeln('Set (propinfo,54321) : ',O.Int64Field);
  O.Free;
end.

```

79.7.15 GetInterfaceProp

Synopsis: Return interface-typed property

Declaration: `function GetInterfaceProp(Instance: TObject; const PropName: string) : IInterface`
`function GetInterfaceProp(Instance: TObject; PropInfo: PPropInfo) : IInterface`

Visibility: default

Description: `GetInterfaceProp` returns the interface which the property described by `PropInfo` or with name `Propname` points to for object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetInterfaceProp` (2008), `GetOrdProp` (1994), `GetStrProp` (2000), `GetFloatProp` (1988), `GetInt64Prop` (1989), `GetSetProp` (1998), `GetObjectProp` (1992), `GetEnumProp` (1987)

79.7.16 GetMethodProp

Synopsis: Return value of a method property

Declaration: `function GetMethodProp(Instance: TObject; PropInfo: PPropInfo) : TMethod`
`function GetMethodProp(Instance: TObject; const PropName: string) : TMethod`

Visibility: default

Description: `GetMethodProp` returns the method the property described by `PropInfo` or with name `Propname` for object `Instance`. The return type `TMethod` is defined in the `SysUtils` unit as:

```
TMethod = packed record
  Code, Data: Pointer;
end;
```

`Data` points to the instance of the class with the method `Code`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (2008), `GetOrdProp` (1994), `GetStrProp` (2000), `GetFloatProp` (1988), `GetInt64Prop` (1989), `GetSetProp` (1998), `GetObjectProp` (1992), `GetEnumProp` (1987)

Listing: `./examples/typinfex/ex6.pp`

```
program example6;

{ This program demonstrates the GetMethodProp function }

{$mode objfpc}

uses rttiobj, typinfo, sysutils;

Type
  TNotifyObject = Class(TObject)
    Procedure Notification1(Sender : TObject);
    Procedure Notification2(Sender : TObject);
  end;

Procedure TNotifyObject.Notification1(Sender : TObject);

begin
  Write('Received notification 1 of object with class: ');
  WriteLn(Sender.ClassName);
end;

Procedure TNotifyObject.Notification2(Sender : TObject);

begin
  Write('Received notification 2 of object with class: ');
  WriteLn(Sender.ClassName);
end;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  NO : TNotifyObject;
  M : TMethod;

Procedure PrintMethod (Const M : TMethod);

begin
  If (M.Data=Pointer(NO)) Then
```



```

    If (M.Code=Pointer(@TNotifyObject.Notification1)) then
        Writeln('Notification1')
    else If (M.Code=Pointer(@TNotifyObject.Notification2)) then
        Writeln('Notification2')
    else
        begin
            Write('Unknown method address (data:');
            Write(hexStr(Longint(M.data),8));
            Writeln(',code:',hexstr(Longint(M.Code),8),')');
        end;
end;

begin
    O:=TMyTestObject.Create;
    NO:=TNotifyObject.Create;
    O.NotifyEvent:=@NO.Notification1;
    PI:=GetPropertyInfo(O,'NotifyEvent');
    Writeln('Method property : ');
    Write('Notifying                               : ');
    O.Notify;
    Write('Get (name)                               : ');
    M:=GetMethodProp(O,'NotifyEvent');
    PrintMethod(M);
    Write('Notifying                               : ');
    O.Notify;
    Write('Get (propinfo)                             : ');
    M:=GetMethodProp(O,PI);
    PrintMethod(M);
    M:=TMethod(@NO.Notification2);
    SetMethodProp(O,'NotifyEvent',M);
    Write('Set (name,Notification2)                   : ');
    M:=GetMethodProp(O,PI);
    PrintMethod(M);
    Write('Notifying                               : ');
    O.Notify;
    Write('Set (propinfo,Notification1) : ');
    M:=TMethod(@NO.Notification1);
    SetMethodProp(O,PI,M);
    M:=GetMethodProp(O,PI);
    PrintMethod(M);
    Write('Notifying                               : ');
    O.Notify;
    O.Free;
end.

```

79.7.17 TObjectProp

Synopsis: Return value of an object-type property.

Declaration: function TObjectProp(Instance: TObject; const PropName: string)
: TObject

```

function TObjectProp(Instance: TObject; const PropName: string;
    MinClass: TClass) : TObject
function TObjectProp(Instance: TObject; PropInfo: PPropInfo) : TObject
function TObjectProp(Instance: TObject; PropInfo: PPropInfo;
    MinClass: TClass) : TObject

```

Visibility: default

Description: `GetObjectProp` returns the object which the property described by `PropInfo` with name `Propname` points to for object `Instance`.

If `MinClass` is specified, then if the object is not descendent of class `MinClass`, then `Nil` is returned.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (2008), `GetOrdProp` (1994), `GetStrProp` (2000), `GetFloatProp` (1988), `GetInt64Prop` (1989), `GetSetProp` (1998), `GetObjectProp` (1992), `GetEnumProp` (1987)

Listing: `./examples/typinfex/ex5.pp`

```

program example5;

{ This program demonstrates the GetObjectProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  NO1, NO2 : TNamedObject;

begin
  O := TMyTestObject.Create;
  NO1 := TNamedObject.Create;
  NO1.ObjectName := 'First named object';
  NO2 := TNamedObject.Create;
  NO2.ObjectName := 'Second named object';
  O.ObjField := NO1;
  Writeln('Object property : ');
  PI := GetPropInfo(O, 'ObjField');
  Write('Property class : ');
  Writeln(GetObjectPropClass(O, 'ObjField').ClassName);
  Write('Value : ');
  Writeln((O.ObjField as TNamedObject).ObjectName);
  Write('Get (name) : ');
  Writeln((GetObjectProp(O, 'ObjField') as TNamedObject).ObjectName);
  Write('Get (propinfo) : ');
  Writeln((GetObjectProp(O, PI, TObj) as TNamedObject).ObjectName);
  SetObjectProp(O, 'ObjField', NO2);
  Write('Set (name, NO2) : ');
  Writeln((O.ObjField as TNamedObject).ObjectName);
  SetObjectProp(O, PI, NO1);
  Write('Set (propinfo, NO1) : ');
  Writeln((O.ObjField as TNamedObject).ObjectName);
  O.Free;
end.

```

79.7.18 GetObjectPropClass

Synopsis: Return class of property.

Declaration: `function GetObjectPropClass(Instance: TObject; const PropName: string)
: TClass
function GetObjectPropClass(AClass: TClass; const PropName: string)
: TClass`

Visibility: default

Description: `GetObjectPropClass` returns the declared class of the property with name `PropName`. This may not be the actual class of the property value.

For an example, see `GetObjectProp` (1992).

Errors: No checking is done whether `Instance` is non-nil. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (2008), `GetOrdProp` (1994), `GetStrProp` (2000), `GetFloatProp` (1988), `GetInt64Prop` (1989)

79.7.19 GetOrdProp

Synopsis: Get the value of an ordinal property

Declaration: `function GetOrdProp(Instance: TObject; PropInfo: PPropInfo) : Int64
function GetOrdProp(Instance: TObject; const PropName: string) : Int64`

Visibility: default

Description: `GetOrdProp` returns the value of the ordinal property described by `PropInfo` or with name `PropName` for the object `Instance`. The value is returned as a longint, which should be typecast to the needed type.

Ordinal properties that can be retrieved include:

Integers and subranges of integersThe value of the integer will be returned.

Enumerated types and subranges of enumerated typesThe ordinal value of the enumerated type will be returned.

SetsIf the base type of the set has less than 31 possible values. If a bit is set in the return value, then the corresponding element of the base ordinal class of the set type must be included in the set.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetOrdProp` (2009), `GetStrProp` (2000), `GetFloatProp` (1988), `GetInt64Prop` (1989), `GetMethodProp` (1990), `GetSetProp` (1998), `GetObjectProp` (1992), `GetEnumProp` (1987)

Listing: ./examples/typinfex/ex1.pp

```
program example1;

{ This program demonstrates the GetOrdProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
```

```

PI : PPropInfo;

begin
  O:= TMyTestObject.Create;
  WriteLn ( 'Boolean property      : ' );
  WriteLn ( 'Value                  : ', O.BooleanField );
  WriteLn ( 'Ord ( Value )          : ', Ord ( O.BooleanField ) );
  WriteLn ( 'Get ( name )           : ', GetOrdProp ( O, 'BooleanField' ) );
  PI := GetPropInfo ( O, 'BooleanField' );
  WriteLn ( 'Get ( propinfo )       : ', GetOrdProp ( O, PI ) );
  SetOrdProp ( O, 'BooleanField', Ord ( False ) );
  WriteLn ( 'Set ( name, false )    : ', O.BooleanField );
  SetOrdProp ( O, PI, Ord ( True ) );
  WriteLn ( 'Set ( propinfo, true ) : ', O.BooleanField );
  O.Free;
end.

```

79.7.20 GetPropInfo

Synopsis: Return property type information, by property name.

Declaration: `function GetPropInfo (TypeInfo: PTypeInfo; const PropName: string) : PPropInfo`
`function GetPropInfo (TypeInfo: PTypeInfo; const PropName: string; AKinds: TTypeKinds) : PPropInfo`
`function GetPropInfo (Instance: TObject; const PropName: string) : PPropInfo`
`function GetPropInfo (Instance: TObject; const PropName: string; AKinds: TTypeKinds) : PPropInfo`
`function GetPropInfo (AClass: TClass; const PropName: string) : PPropInfo`
`function GetPropInfo (AClass: TClass; const PropName: string; AKinds: TTypeKinds) : PPropInfo`

Visibility: default

Description: `GetPropInfo` returns a pointer to the `TPropInfo` record for the `PropName` property of a class. The class to examine can be specified in one of three ways:

Instance An instance of the class.

AClass A class pointer to the class.

TypeInfo A pointer to the type information of the class.

In each of these three ways, if `AKinds` is specified, if the property has `TypeKind` which is not included in `AKinds`, `Nil` will be returned.

For an example, see most of the other functions.

Errors: If the property `PropName` does not exist, `Nil` is returned.

See also: `GetPropInfos` ([1995](#)), `GetPropList` ([1996](#))

79.7.21 GetPropInfos

Synopsis: Return a list of published properties.

Declaration: `procedure GetPropInfos (TypeInfo: PTypeInfo; PropList: PPropList)`

Visibility: default

Description: `GetPropInfos` stores pointers to the property information of all published properties of a class with class info `TypeInfo` in the list pointed to by `PropList`. The `PropList` pointer must point to a memory location that contains enough space to hold all properties of the class and its parent classes.

Errors: No checks are done to see whether `PropList` points to a memory area that is big enough to hold all pointers.

See also: `GetPropInfo` (1995), `GetPropList` (1996)

Listing: `./examples/typinfex/ex12.pp`

Program `example12`;

{ This program demonstrates the GetPropInfos function }

uses

`rttiobj, typinfo;`

Var

`O : TMyTestObject;`

`PT : PTypeData;`

`PI : PTypeInfo;`

`I, J : Longint;`

`PP : PPropList;`

`prl : PPropInfo;`

begin

`O := TMyTestObject.Create;`

`PI := O.ClassInfo;`

`PT := GetTypeData(PI);`

`WriteLn('Property Count : ', PT^.PropCount);`

`GetMem(PP, PT^.PropCount * SizeOf(Pointer));`

`GetPropInfos(PI, PP);`

For `I := 0 to PT^.PropCount - 1 do`

begin

With `PP^[I]^ do`

begin

`Write('Property ', i + 1 : 3, ': ', name : 30);`

`writeln(' Type: ', TypeName[typinfo.PropType(O, Name)]);`

end;

end;

`FreeMem(PP);`

`O.Free;`

end.

79.7.22 GetPropList

Synopsis: Return a list of a certain type of published properties.

Declaration: `function GetPropList(TypeInfo: PTypeInfo; TypeKinds: TTypeKinds;
PropList: PPropList; Sorted: Boolean) : LongInt`
`function GetPropList(TypeInfo: PTypeInfo; out PropList: PPropList)
: SizeInt`

```
function GetPropList(AClass: TClass; out PropList: PPropList) : Integer
function GetPropList(Instance: TObject; out PropList: PPropList)
    : Integer
```

Visibility: default

Description: GetPropList stores pointers to property information of the class with class info TypeInfo for properties of kind TypeKinds in the list pointed to by PropList. PropList must contain enough space to hold all properties.

The function returns the number of pointers that matched the criteria and were stored in PropList.

Errors: No checks are done to see whether PropList points to a memory area that is big enough to hold all pointers.

See also: GetPropInfos ([1995](#)), GetPropInfo ([1995](#))

Listing: ./examples/typinfex/ex13.pp

Program example13;

{ This program demonstrates the GetPropList function }

uses

rttiobj, typinfo;

Var

O : TMyTestObject;

PT : PTypeData;

PI : PTypeInfo;

I, J : Longint;

PP : PPropList;

pri : PPropInfo;

begin

O:=TMyTestObject.Create;

PI:=O.ClassInfo;

PT:=GetTypeData(PI);

WriteLn('Total property Count : ', PT^.PropCount);

GetMem(PP, PT^.PropCount*SizeOf(Pointer));

J:=GetPropList(PI, OrdinalTypes, PP);

WriteLn('Ordinal property Count : ', J);

For I:=0 to J-1 do

begin

With PP^[I]^ do

begin

Write('Property ', i+1:3, ': ', name:30);

writeln(' Type: ', TypeName[typinfo.PropType(O, Name)]);

end;

end;

FreeMem(PP);

O.Free;

end.

79.7.23 GetPropValue

Synopsis: Get property value as a string.

Declaration:

```
function GetPropValue(Instance: TObject; const PropName: string)
    : Variant
function GetPropValue(Instance: TObject; const PropName: string;
    PreferStrings: Boolean) : Variant
function GetPropValue(Instance: TObject; PropInfo: PPropInfo) : Variant
function GetPropValue(Instance: TObject; PropInfo: PPropInfo;
    PreferStrings: Boolean) : Variant
```

Visibility: default

Description: Due to missing Variant support, GetPropValue is not yet implemented. The declaration is provided for compatibility with Delphi.

79.7.24 GetRawByteStrProp

Synopsis: Return the value of a string property as a RawByteString

Declaration:

```
function GetRawByteStrProp(Instance: TObject; PropInfo: PPropInfo)
    : RawByteString
function GetRawByteStrProp(Instance: TObject; const PropName: string)
    : RawByteString
```

Visibility: default

Description: GetRawByteStrProp returns the value of a string property of the object Instance as a RawByteString. This means it has the codepage of the actual value, no codepage translation is done. The property to read can be specified using the name PropName or the property info PropInfo.

See also: GetStrProp ([2000](#))

79.7.25 GetRawInterfaceProp

Synopsis: Get a raw (CORBA) interface property.

Declaration:

```
function GetRawInterfaceProp(Instance: TObject; const PropName: string)
    : Pointer
function GetRawInterfaceProp(Instance: TObject; PropInfo: PPropInfo)
    : Pointer
```

Visibility: default

Description: GetRawInterfaceProp can be used to retrieve the value of a published CORBA interface property with name PropName from object Instance. Alternatively, the required property information can be specified by PropInfo instead of the property name. In difference with the GetInterfaceProp ([1990](#)) function, no reference counting is done.

Errors: If the property PropName does not exist, an EPropertyError exception is raised.

See also: GetInterfaceProp ([1990](#)), SetRawInterfaceProp ([2010](#))

79.7.26 GetSetProp

Synopsis: Return the value of a set property.

Declaration: `function GetSetProp(Instance: TObject; const PropName: string) : string`
`function GetSetProp(Instance: TObject; const PropName: string;`
`Brackets: Boolean) : string`
`function GetSetProp(Instance: TObject; const PropInfo: PPropInfo;`
`Brackets: Boolean) : string`

Visibility: default

Description: `GetSetProp` returns the contents of a set property as a string. The property to be returned can be specified by its name in `PropName` or by its property information in `PropInfo`.

The returned set is a string representation of the elements in the set as returned by `SetToString` (2011). The `Brackets` option can be used to enclose the string representation in square brackets.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetSetProp` (2011), `GetStrProp` (2000), `GetFloatProp` (1988), `GetInt64Prop` (1989), `GetMethodProp` (1990)

Listing: `./examples/typinfex/ex7.pp`

```
program example7;

{ This program demonstrates the GetSetProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

Function SetAsString (ASet : TMyEnums) : String;

Var
  i : TmyEnum;

begin
  result := '';
  For i := mefirst to methird do
    If i in ASet then
      begin
        If (Result <> '') then
          Result := Result + ', ';
        Result := Result + MyEnumNames[i];
      end;
  end;

Var
  S : TMyEnums;

begin
  O := TMyTestObject.Create;
  O.SetField := [ mefirst, meSecond, meThird ];
  WriteLn('Set property      : ');
  WriteLn('Value                : ', SetAsString(O.SetField));
```

```

WriteLn ( 'Ord (Value)                : ', Byte (O. SetField));
WriteLn ( 'Get (name)                  : ', GetSetProp (O, 'SetField'));
PI := GetPropInfo (O, 'SetField');
WriteLn ( 'Get (propinfo)              : ', GetSetProp (O, PI, false));
S := [meFirst, meThird];
SetOrdProp (O, 'SetField', Byte (S));
Write ( 'Set (name, [mefirst, methird]) : ');
WriteLn (SetAsString (O. SetField));
S := [meSecond];
SetOrdProp (O, PI, Byte (S));
Write ( 'Set (propinfo, [meSecond])     : ');
WriteLn (SetAsString (O. SetField));
O. Free;
end.

```

79.7.27 GetStrProp

Synopsis: Return the value of a string property.

Declaration: `function GetStrProp (Instance: TObject; PropInfo: PPropInfo) : Ansistring`
`function GetStrProp (Instance: TObject; const PropName: string) : string`

Visibility: default

Description: `GetStrProp` returns the value of the string property described by `PropInfo` or with name `PropName` for object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid string property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetStrProp` ([2011](#)), `SetWideStrProp` ([2013](#)), `GetOrdProp` ([1994](#)), `GetFloatProp` ([1988](#)), `GetInt64Prop` ([1989](#)), `GetMethodProp` ([1990](#))

Listing: `./examples/typinfex/ex3.pp`

```

program example3;

{ This program demonstrates the GetStrProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O := TMyTestObject.Create;
  PI := GetPropInfo (O, 'AnsiStringField');
  WriteLn ('String property : ');
  WriteLn ('Value                : ', O. AnsiStringField);
  WriteLn ('Get (name)            : ', GetStrProp (O, 'AnsiStringField'));
  WriteLn ('Get (propinfo)          : ', GetStrProp (O, PI));
  SetStrProp (O, 'AnsiStringField', 'First');
  WriteLn ('Set (name, ''First'')      : ', O. AnsiStringField);

```

```

program example11;

{ This program demonstrates the IsStoredProp function }

{$mode objfpc}

uses rttiobj ,typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Stored tests      : ');
  Write('IsStoredProp(O,StoredIntegerConstFalse)      : ');
  Writeln(IsStoredProp(O, 'StoredIntegerConstFalse'));
  Write('IsStoredProp(O,StoredIntegerConstTrue)      : ');
  Writeln(IsStoredProp(O, 'StoredIntegerConstTrue'));
  Write('IsStoredProp(O,StoredIntegerMethod)      : ');
  Writeln(IsStoredProp(O, 'StoredIntegerMethod'));
  Write('IsStoredProp(O,StoredIntegerVirtualMethod) : ');
  Writeln(IsStoredProp(O, 'StoredIntegerVirtualMethod'));
  O.Free;
end.

```

79.7.35 IsWriteableProp

Synopsis: Can the property be written

Declaration:

```

function IsWriteableProp(PropInfo: PPropInfo) : Boolean
function IsWriteableProp(Instance: TObject; const PropName: string)
    : Boolean
function IsWriteableProp(AClass: TClass; const PropName: string)
    : Boolean

```

Visibility: default

Description: IsWriteableProp returns True if the property described by information PropInfo can be written to, i.e. has a write specifier. It returns False if the property can only be read.

See also: IsReadableProp ([2003](#))

79.7.36 PropIsType

Synopsis: Check the type of a published property.

Declaration:

```

function PropIsType(Instance: TObject; const PropName: string;
    TypeKind: TTypeKind) : Boolean
function PropIsType(AClass: TClass; const PropName: string;
    TypeKind: TTypeKind) : Boolean

```

Visibility: default

Description: PropIsType returns True if the property with name PropName has type TypeKind. It returns False otherwise. The class to be examined can be specified in one of two ways:

AClassA class pointer.

InstanceAn instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` (2002), `IsStoredProp` (2003), `PropType` (2005)

Listing: `./examples/typinfex/ex16.pp`

```

program example16;

{ This program demonstrates the PropIsType function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;

begin
  O := TMyTestObject.Create;
  Writeln( 'Property tests      : ');
  Write( 'PropIsType(O, BooleanField, tkBool)      : ');
  Writeln( PropIsType(O, 'BooleanField', tkBool));
  Write( 'PropIsType(Class, BooleanField, tkBool) : ');
  Writeln( PropIsType(O.ClassType, 'BooleanField', tkBool));
  Write( 'PropIsType(O, ByteField, tkString)      : ');
  Writeln( PropIsType(O, 'ByteField', tkString));
  Write( 'PropIsType(Class, ByteField, tkString)  : ');
  Writeln( PropIsType(O.ClassType, 'ByteField', tkString));
  O.Free;
end.

```

79.7.37 PropType

Synopsis: Return the type of a property

Declaration: `function PropType(Instance: TObject; const PropName: string) : TTypeKind`
`function PropType(AClass: TClass; const PropName: string) : TTypeKind`

Visibility: default

Description: `PropType` returns the type of the property `PropName` for a class. The class to be examined can be specified in one of 2 ways:

AClassA class pointer.

InstanceAn instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` (2002), `IsStoredProp` (2003), `PropIsType` (2004)

Listing: `./examples/typinfex/ex17.pp`

```

program example17;

{ This program demonstrates the PropType function }

{$mode objfpc}

uses rttiobj , typinfo;

Var
  O : TMyTestObject;

begin
  O:= TMyTestObject.Create;
  Writeln( 'Property tests      : ');
  Write( 'PropType(O, BooleanField)      : ');
  Writeln(TypeNames[PropType(O, 'BooleanField')]);
  Write( 'PropType(Class, BooleanField) : ');
  Writeln(TypeNames[PropType(O.ClassType, 'BooleanField')]);
  Write( 'PropType(O, ByteField)          : ');
  Writeln(TypeNames[PropType(O, 'ByteField')]);
  Write( 'PropType(Class, ByteField)      : ');
  Writeln(TypeNames[PropType(O.ClassType, 'ByteField')]);
  O.Free;
end.

```

79.7.38 RemoveEnumElementAliases

Synopsis: Remove aliases for enumerated elements.

Declaration: `procedure RemoveEnumElementAliases(aTypeInfo: PTypeInfo)`

Visibility: default

Description: `RemoveEnumElementAliases` removes all aliases for enumerated type `aTypeInfo`. The aliases must have been defined using `AddEnumElementAliases` ([1983](#)).

Errors: `AddEnumElementAliases` ([1983](#)) `GetEnumValue` ([1988](#)) `GetEnumeratedAliasValue` ([1986](#))

79.7.39 SetDynArrayProp

Synopsis: SetSize the value of a dynamic array valued property

Declaration: `procedure SetDynArrayProp(Instance: TObject; const PropName: string;
const Value: Pointer)
procedure SetDynArrayProp(Instance: TObject; PropInfo: PPropInfo;
const Value: Pointer)`

Visibility: default

Description: `SetDynArrayProp` returns the value of a dynamic array valued property of the object `Instance` to the pointer `Value`. The property to read can be specified using the name `PropName` or the property info `PropInfo`.

See also: `GetDynArrayProp` ([1985](#))

79.7.40 SetEnumProp

Synopsis: Set value of an enumerated-type property

Declaration:

```
procedure SetEnumProp(Instance: TObject; const PropName: string;
                      const Value: string)
procedure SetEnumProp(Instance: TObject; const PropInfo: PPropInfo;
                      const Value: string)
```

Visibility: default

Description: `SetEnumProp` sets the property described by `PropInfo` or with name `PropName` to `Value`. `Value` must be a string with the name of the enumerate value, i.e. it can be used as an argument to `GetEnumValue` (1988).

For an example, see `GetEnumProp` (1987).

Errors: No checks are done to ensure `Instance` or `PropInfo` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetEnumProp` (1987), `SetStrProp` (2011), `SetFloatProp` (2007), `SetInt64Prop` (2007), `SetMethodProp` (2008)

79.7.41 SetFloatProp

Synopsis: Set value of a float property.

Declaration:

```
procedure SetFloatProp(Instance: TObject; const PropName: string;
                      Value: Extended)
procedure SetFloatProp(Instance: TObject; PropInfo: PPropInfo;
                      Value: Extended)
```

Visibility: default

Description: `SetFloatProp` assigns `Value` to the property described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see `GetFloatProp` (1988).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid float property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetFloatProp` (1988), `SetOrdProp` (2009), `SetStrProp` (2011), `SetInt64Prop` (2007), `SetMethodProp` (2008)

79.7.42 SetInt64Prop

Synopsis: Set value of a Int64 property

Declaration:

```
procedure SetInt64Prop(Instance: TObject; PropInfo: PPropInfo;
                      const Value: Int64)
procedure SetInt64Prop(Instance: TObject; const PropName: string;
                      const Value: Int64)
```

Visibility: default

Description: `SetInt64Prop` assigns `Value` to the property of type `Int64` that is described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see `GetInt64Prop` (1989).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid `Int64` property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [GetInt64Prop \(1989\)](#), [GetMethodProp \(1990\)](#), [SetOrdProp \(2009\)](#), [SetStrProp \(2011\)](#), [SetFloatProp \(2007\)](#)

79.7.43 SetInterfaceProp

Synopsis: Set interface-valued property

Declaration:

```
procedure SetInterfaceProp(Instance: TObject; const PropName: string;
                           const Value: IInterface)
procedure SetInterfaceProp(Instance: TObject; PropInfo: PPropInfo;
                           const Value: IInterface)
```

Visibility: default

Description: `SetInterfaceProp` assigns `Value` to the object property described by `PropInfo` or with name `Propname` for the object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid interface property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [GetInterfaceProp \(1990\)](#), [SetObjectProp \(2009\)](#), [SetOrdProp \(2009\)](#), [SetStrProp \(2011\)](#), [SetFloatProp \(2007\)](#), [SetInt64Prop \(2007\)](#), [SetMethodProp \(2008\)](#)

79.7.44 SetMethodProp

Synopsis: Set the value of a method property

Declaration:

```
procedure SetMethodProp(Instance: TObject; PropInfo: PPropInfo;
                        const Value: TMethod)
procedure SetMethodProp(Instance: TObject; const PropName: string;
                        const Value: TMethod)
```

Visibility: default

Description: `SetMethodProp` assigns `Value` to the method the property described by `PropInfo` or with name `Propname` for object `Instance`.

The type `TMethod` of the `Value` parameter is defined in the `SysUtils` unit as:

```
TMethod = packed record
    Code, Data: Pointer;
end;
```

`Data` should point to the instance of the class with the method `Code`.

For an example, see [GetMethodProp \(1990\)](#).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [GetMethodProp \(1990\)](#), [SetOrdProp \(2009\)](#), [SetStrProp \(2011\)](#), [SetFloatProp \(2007\)](#), [SetInt64Prop \(2007\)](#)

79.7.45 SetObjectProp

Synopsis: Set the value of an object-type property.

Declaration:

```
procedure SetObjectProp(Instance: TObject; const PropName: string;
                        Value: TObject)
procedure SetObjectProp(Instance: TObject; PropInfo: PPropInfo;
                        Value: TObject)
```

Visibility: default

Description: `SetObjectProp` assigns `Value` to the object property described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see `GetObjectProp` (1992).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid object property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetObjectProp` (1992), `SetOrdProp` (2009), `SetStrProp` (2011), `SetFloatProp` (2007), `SetInt64Prop` (2007), `SetMethodProp` (2008)

79.7.46 SetOrdProp

Synopsis: Set value of an ordinal property

Declaration:

```
procedure SetOrdProp(Instance: TObject; PropInfo: PPropInfo;
                    Value: Int64)
procedure SetOrdProp(Instance: TObject; const PropName: string;
                    Value: Int64)
```

Visibility: default

Description: `SetOrdProp` assigns `Value` to the ordinal property described by `PropInfo` or with name `Propname` for the object `Instance`.

Ordinal properties that can be set include:

Integers and subranges of integersThe actual value of the integer must be passed.

Enumerated types and subranges of enumerated typesThe ordinal value of the enumerated type must be passed.

Subrange typesof integers or enumerated types. Here the ordinal value must be passed.

SetsIf the base type of the set has less than 31 possible values. For each possible value; the corresponding bit of `Value` must be set.

For an example, see `GetOrdProp` (1994).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. No range checking is performed. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetOrdProp` (1994), `SetStrProp` (2011), `SetFloatProp` (2007), `SetInt64Prop` (2007), `SetMethodProp` (2008)

79.7.47 SetPropValue

Synopsis: Set property value as variant

Declaration: `procedure SetPropValue(Instance: TObject; const PropName: string;
const Value: Variant)
procedure SetPropValue(Instance: TObject; PropInfo: PPropInfo;
const Value: Variant)`

Visibility: default

Description: Due to missing Variant support, this function is not yet implemented; it is provided for Delphi compatibility only.

79.7.48 SetRawByteStrProp

Synopsis: Set the value of a string property using a RawByteString

Declaration: `procedure SetRawByteStrProp(Instance: TObject; const PropName: string;
const Value: RawByteString)
procedure SetRawByteStrProp(Instance: TObject; PropInfo: PPropInfo;
const Value: RawByteString)`

Visibility: default

Description: `GetRawByteStrProp` writes the value of a string property of the object `Instance` to `Value`, a `RawByteString`. This means no codepage translation is done. The property to write can be specified using the name `PropName` or the property info `PropInfo`.

See also: `SetStrProp` ([2011](#)), `GetRawByteStrProp` ([1998](#))

79.7.49 SetRawInterfaceProp

Synopsis: Set a raw (CORBA) interface property.

Declaration: `procedure SetRawInterfaceProp(Instance: TObject;
const PropName: string;
const Value: Pointer)
procedure SetRawInterfaceProp(Instance: TObject; PropInfo: PPropInfo;
const Value: Pointer)`

Visibility: default

Description: `SetRawInterfaceProp` can be used to set the value of a published CORBA interface with name `PropName` from object `Instance` to `Value`. Alternatively, the required property information can be specified by `PropInfo` instead of the property name. In difference with the `SetInterfaceProp` ([2008](#)) procedure, no reference counting is done.

Errors: If the property `PropName` does not exist, an `EPropertyError` exception is raised.

See also: `SetInterfaceProp` ([2008](#)), `GetRawInterfaceProp` ([1998](#))

79.7.50 SetSetProp

Synopsis: Set value of set-typed property.

Declaration:

```
procedure SetSetProp(Instance: TObject; const PropName: string;
                    const Value: string)
procedure SetSetProp(Instance: TObject; const PropInfo: PPropInfo;
                    const Value: string)
```

Visibility: default

Description: SetSetProp sets the property specified by PropInfo or PropName for object Instance to Value. Value is a string which contains a comma-separated list of values, each value being a string-representation of the enumerated value that should be included in the set. The value should be accepted by the StringToSet (2013) function.

The value can be formed using the SetToString (2011) function.

For an example, see GetSetProp (1998).

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid ordinal property of Instance. No range checking is performed. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetSetProp (1998), SetOrdProp (2009), SetStrProp (2011), SetFloatProp (2007), SetInt64Prop (2007), SetMethodProp (2008), SetToString (2011), StringToSet (2013)

79.7.51 SetStrProp

Synopsis: Set value of a string property

Declaration:

```
procedure SetStrProp(Instance: TObject; const PropName: string;
                    const Value: AnsiString)
procedure SetStrProp(Instance: TObject; PropInfo: PPropInfo;
                    const Value: Ansistring)
```

Visibility: default

Description: SetStrProp assigns Value to the string property described by PropInfo or with name Propname for object Instance.

For an example, see GetStrProp (2000)

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid string property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetStrProp (2000), SetWideStrProp (2013), SetOrdProp (2009), SetFloatProp (2007), SetInt64Prop (2007), SetMethodProp (2008)

79.7.52 SetToString

Synopsis: Convert set to a string description

Declaration:

```
function SetToString(TypeInfo: PTypeInfo; Value: LongInt;
                    Brackets: Boolean) : string
function SetToString(PropInfo: PPropInfo; Value: LongInt;
                    Brackets: Boolean) : string
function SetToString(PropInfo: PPropInfo; Value: LongInt) : string
```

```

function SetToString(TypeInfo: PTypeInfo; Value: Pointer;
                    Brackets: Boolean) : string
function SetToString(PropInfo: PPropInfo; Value: Pointer;
                    Brackets: Boolean) : string

```

Visibility: default

Description: `SetToString` takes an integer representation of a set (as received e.g. by `GetOrdProp`) and turns it into a string representing the elements in the set, based on the type information found in the `PropInfo` property information. By default, the string representation is not surrounded by square brackets. Setting the `Brackets` parameter to `True` will surround the string representation with brackets.

The function returns the string representation of the set.

Errors: No checking is done to see whether `PropInfo` points to valid property information.

See also: `GetEnumName` ([1986](#)), `GetEnumValue` ([1988](#)), `StringToSet` ([2013](#))

Listing: `./examples/typinfex/ex18.pp`

```

program example18;

{ This program demonstrates the SetToString function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  I : longint;

begin
  O := TMyTestObject.Create;
  PI := GetPropInfo(O, 'SetField');
  O.SetField := [meFirst, meSecond, meThird];
  I := GetOrdProp(O, PI);
  Writeln('Set property to string : ');
  Writeln('Value : ', SetToString(PI, I, False));
  O.SetField := [meFirst, meSecond];
  I := GetOrdProp(O, PI);
  Writeln('Value : ', SetToString(PI, I, True));
  I := StringToSet(PI, 'meFirst');
  SetOrdProp(O, PI, I);
  I := GetOrdProp(O, PI);
  Writeln('Value : ', SetToString(PI, I, False));
  I := StringToSet(PI, '[meSecond, meThird]');
  SetOrdProp(O, PI, I);
  I := GetOrdProp(O, PI);
  Writeln('Value : ', SetToString(PI, I, True));
  O.Free;
end.

```

79.7.53 SetUnicodeStrProp

Synopsis: Set UnicodeString-valued property

Declaration: `procedure SetUnicodeStrProp(Instance: TObject; const PropName: string;
const Value: UnicodeString)
procedure SetUnicodeStrProp(Instance: TObject; PropInfo: PPropInfo;
const Value: UnicodeString)`

Visibility: default

Description: `SetUnicodeStrProp` sets the `UnicodeString` property from `Instance` to `Value`, where the property is identified by the `PropInfo` pointer or the `PropertyName`.

Errors: If no property of the indicated name exists, or it is not of type `UnicodeString`, an exception will occur.

See also: `SetStrProp` (2011), `GetUnicodeStrProp` (2001)

79.7.54 SetVariantProp

Synopsis: Set value of a variant property

Declaration: `procedure SetVariantProp(Instance: TObject; const PropName: string;
const Value: Variant)
procedure SetVariantProp(Instance: TObject; PropInfo: PPropInfo;
const Value: Variant)`

Visibility: default

Description: Due to missing `Variant` support, this function is not yet implemented. Provided for Delphi compatibility only.

79.7.55 SetWideStrProp

Synopsis: Set a widestring property

Declaration: `procedure SetWideStrProp(Instance: TObject; const PropName: string;
const Value: WideString)
procedure SetWideStrProp(Instance: TObject; PropInfo: PPropInfo;
const Value: WideString)`

Visibility: default

Description: `SetWideStrProp` assigns `Value` to the widestring property described by `PropInfo` or with name `Propname` for object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid widestring property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetWideStrProp` (2002), `SetStrProp` (2011), `SetOrdProp` (2009), `SetFloatProp` (2007), `SetInt64Prop` (2007), `SetMethodProp` (2008)

79.7.56 StringToSet

Synopsis: Convert string description to a set.

Declaration: `function StringToSet(PropInfo: PPropInfo; const Value: string) : LongInt
function StringToSet(TypeInfo: PTypeInfo; const Value: string) : LongInt
procedure StringToSet(PropInfo: PPropInfo; const Value: string;
Result: Pointer)`

```
procedure StringToSet (TypeInfo: PTypeInfo; const Value: string;
                      Result: Pointer)
```

Visibility: default

Description: `StringToSet` converts the string representation of a set in `Value` to a integer representation of the set, using the property information found in `PropInfo`. This property information should point to the property information of a set property. The function returns the integer representation of the set. (i.e, the set value, typecast to an integer)

The string representation can be surrounded with square brackets, and must consist of the names of the elements of the base type of the set. The base type of the set should be an enumerated type. The elements should be separated by commas, and may be surrounded by spaces. each of the names will be fed to the `GetEnumValue` (1988) function.

For an example, see `SetToString` (2011).

Errors: No checking is done to see whether `PropInfo` points to valid property information. If a wrong name is given for an enumerated value, then an `EPropertyError` will be raised.

See also: `GetEnumName` (1986), `GetEnumValue` (1988), `SetToString` (2011)

79.8 TArrayTypeData

```
TArrayTypeData = packed record
private
    function GetElType : PTypeInfo
    ;
    function GetDims(aIndex: Byte) : PTypeInfo;
public
    property
        ElType : PTypeInfo;
        property Dims[Index: Byte]: PTypeInfo;
        Size
        : SizeInt;
        ElCount : SizeInt;
        ElTypeRef : PTypeInfo;
        DimCount
        : Byte;
        DimsRef : Array[0..255] of PTypeInfo;
end
```

`TArrayTypeData` is used to describe arrays in RTTI. It can be encountered when the type kind is `tkArray`, and is used for both static and dynamic arrays and single or multi-dimensional arrays. The type of the array elements is described in `elType`, and the ranges for each of the dimensions (specified in `DimCount` in `Dims`).

79.8.1 Property overview

Page	Properties	Access	Description
2015	Dims	r	Range information for each dimension in the array
2015	ElType	r	Type information for an element in the array

79.8.2 TArrayTypeData.ElType

Synopsis: Type information for an element in the array

Declaration: `Property ElType : PTypeInfo`

Visibility: public

Access: Read

79.8.3 TArrayTypeData.Dims

Synopsis: Range information for each dimension in the array

Declaration: `Property Dims[Index: Byte]: PTypeInfo`

Visibility: public

Access: Read

79.9 TClassData

```
TClassData = packed record
private
    function GetUnitName : ShortString
    ;
    function GetPropertyTable : PPropData;
public
    ClassType : TClass
    ;
    Parent : PTypeInfo;
    PropCount : SmallInt;
    property UnitName
    : ShortString;
    property PropertyTable : PPropData;
private
    UnitNameField
    : ShortString;
end
```

TClassData describes the memory layout of RTTI data generated for a class.

79.9.1 Property overview

Page	Properties	Access	Description
2016	PropertyTable	r	Property info for this class
2015	UnitName	r	Name of unit in which class is implemente

79.9.2 TClassData.UnitName

Synopsis: Name of unit in which class is implemente

Declaration: `Property UnitName : ShortString`

Visibility: public

Access: Read

Description: `UnitName` returns the name of the unit in which the class is implemented.

79.9.3 TClassData.PropertyTable

Synopsis: Property info for this class

Declaration: `Property PropertyTable : PPropData`

Visibility: public

Access: Read

Description: `PropertyTable` returns a pointer to a table with property RTTI.

79.10 TInterfaceData

```
TInterfaceData = packed record
private
    function GetUnitName : ShortString
    ;
    function GetPropertyTable : PPropData;
    function GetMethodTable
    : PIntfMethodTable;
public
    Parent : PTypeInfo;
    Flags : TIntfFlagsBase
    ;
    GUID : TGuid;
    property UnitName : ShortString;
    property PropertyTable
    : PPropData;
    property MethodTable : PIntfMethodTable;
private
    UnitNameField : ShortString;
end
```

`TInterfaceData` describes the memory layout of RTTI data generated for a COM interface. CORBA interfaces are described by `TInterfaceRawData` (2018).

79.10.1 Property overview

Page	Properties	Access	Description
2017	MethodTable	r	Method info for this interface
2017	PropertyTable	r	Property info for this interface
2017	UnitName	r	Unit name

79.10.2 TInterfaceData.UnitName

Synopsis: Unit name

Declaration: `Property UnitName : ShortString`

Visibility: public

Access: Read

Description: `UnitName` returns the unit name in which the interface is defined.

79.10.3 TInterfaceData.PropertyTable

Synopsis: Property info for this interface

Declaration: `Property PropertyTable : PPropData`

Visibility: public

Access: Read

Description: `PropertyTable` returns a pointer to a table with property RTTI.

See also: `TInterfaceData.MethodTable` ([2017](#))

79.10.4 TInterfaceData.MethodTable

Synopsis: Method info for this interface

Declaration: `Property MethodTable : PIntfMethodTable`

Visibility: public

Access: Read

Description: `MethodTable` returns a pointer to a table with method RTTI.

See also: `TInterfaceData.PropertyTable` ([2017](#))

79.11 TInterfaceRawData

```
TInterfaceRawData = packed record
private
    function GetUnitName
        : ShortString;
    function GetIIDStr : ShortString;
    function GetPropertyTable
        : PPropData;
    function GetMethodTable : PIntfMethodTable;
public
    Parent : PTypeInfo;
    Flags : TIntfFlagsBase;
    IID : TGuid;
    property UnitName : ShortString;
    property IIDStr : ShortString
    ;
```

```

property PropertyTable : PPropData;
property MethodTable : PIntfMethodTable
;
private
    UnitNameField : ShortString;
end

```

`TRawInterfaceData` describes the memory layout of RTTI data generated for a CORBA interface. COM interfaces are described by `TInterfaceData` ([2016](#)).

79.11.1 Property overview

Page	Properties	Access	Description
2018	<code>IIDStr</code>	r	GUID as string
2019	<code>MethodTable</code>	r	Method info for this interface
2018	<code>PropertyTable</code>	r	Property info for this interface
2018	<code>UnitName</code>	r	Name of unit in which interface is defined.

79.11.2 TInterfaceRawData.UnitName

Synopsis: Name of unit in which interface is defined.

Declaration: `Property UnitName : ShortString`

Visibility: public

Access: Read

Description: `UnitName` returns the unit name in which the interface is defined.

79.11.3 TInterfaceRawData.IIDStr

Synopsis: GUID as string

Declaration: `Property IIDStr : ShortString`

Visibility: public

Access: Read

Description: `IIDStr` returns a string representation of IID.

79.11.4 TInterfaceRawData.PropertyTable

Synopsis: Property info for this interface

Declaration: `Property PropertyTable : PPropData`

Visibility: public

Access: Read

Description: `PropertyTable` returns a pointer to a table with property RTTI.

See also: `TInterfaceRawData.MethodTable` ([2019](#))

79.11.5 TInterfaceRawData.MethodTable

Synopsis: Method info for this interface

Declaration: `Property MethodTable : PIntfMethodTable`

Visibility: `public`

Access: `Read`

Description: `MethodTable` returns a pointer to a table with method RTTI.

See also: `TInterfaceRawData.PropertyTable` ([2018](#))

79.12 TIntfMethodEntry

```

TIntfMethodEntry = packed record
private
    function GetParam(Index
        : Word) : PVmtMethodParam;
    function GetResultLocs : PParameterLocations
    ;
    function GetTail : Pointer;
    function GetNext : PIntfMethodEntry
    ;
    function GetName : ShortString;
public
    ResultType : PTypeInfo
    ;
    CC : TCallConv;
    Kind : TMethodKind;
    ParamCount : Word;
    StackSize
        : SizeInt;
    NamePtr : PShortString;
    property Name : ShortString
    ;
    property Param[Index: Word]: PVmtMethodParam;
    property ResultLocs
        : PParameterLocations;
    property Tail : Pointer;
    property Next
        : PIntfMethodEntry;
end

```

`TIntfMethodEntry` is a description of the RTTI generated for an `Interface` method. This is different from class or record method RTTI info, which is described by `TVmtMethodEntry` ([1983](#))

79.12.1 Property overview

Page	Properties	Access	Description
2020	Name	r	Name of the method
2021	Next	r	Pointer next <code>TIntfMethodEntry</code> entry in array.
2020	Param	r	Indexed access to parameter descriptions
2020	ResultLocs	r	Result location descriptions
2021	Tail	r	Pointer to location after <code>TIntfMethodEntry</code> data.

79.12.2 TIntfMethodEntry.Name

Synopsis: Name of the method

Declaration: `Property Name : ShortString`

Visibility: public

Access: Read

Description: `Name` dereferences the `NamePtr` field and returns the name of the method.

See also: `TIntfMethodEntry.Param` ([2020](#))

79.12.3 TIntfMethodEntry.Param

Synopsis: Indexed access to parameter descriptions

Declaration: `Property Param[Index: Word]: PVmtMethodParam`

Visibility: public

Access: Read

Description: `Param` offers indexed access to the parameter descriptions. It returns the location of the `Index`-th parameter of the method. `Index` must be in the range 0 to `ParamCount-1` (included).

See also: `TIntfMethodEntry.ResultLocs` ([2020](#))

79.12.4 TIntfMethodEntry.ResultLocs

Synopsis: Result location descriptions

Declaration: `Property ResultLocs : PParameterLocations`

Visibility: public

Access: Read

Description: `ResultLocs` points to a record with result location descriptors: this describes where the result(s) will be written.

See also: `TParameterLocations` ([2024](#))

79.12.5 TIntfMethodEntry.Tail

Synopsis: Pointer to location after TIntfMethodEntry data.

Declaration: `Property Tail : Pointer`

Visibility: `public`

Access: `Read`

Description: `Tail` returns a pointer to the memory location after the `TIntfMethodEntry` data, which can be again a `TIntfMethodEntry` record or other RTTI Data.

See also: `TIntfMethodEntry.Next` ([2021](#))

79.12.6 TIntfMethodEntry.Next

Synopsis: Pointer next TIntfMethodEntry entry in array.

Declaration: `Property Next : TIntfMethodEntry`

Visibility: `public`

Access: `Read`

Description: `Next` is the same as `TIntfMethodEntry.Tail` ([2021](#)), but is typed: it returns a pointer to the next `TIntfMethodEntry` record in the RTTI.

See also: `TIntfMethodEntry.Tail` ([2021](#))

79.13 TIntfMethodTable

```
TIntfMethodTable = packed record
private
  function GetMethod(Index
    : Word) : TIntfMethodEntry;
public
  Count : Word;
  RTTICount : Word
  ;
  property Method[Index: Word] : TIntfMethodEntry;
end
```

`TIntfMethodTable` is a record structure describing all the methods of an interface for which RTTI is generated. It is basically an array of pointers `TIntfMethodTable.Method` ([2022](#)).

79.13.1 Property overview

Page	Properties	Access	Description
2022	Method	r	indexed access to the methods of the interface

79.13.2 TIntfMethodTable.Method

Synopsis: indexed access to the methods of the interface

Declaration: `Property Method[Index: Word]: PIntfMethodEntry`

Visibility: public

Access: Read

Description: `Method` offers indexed access to the method descriptions. It returns the location of the `Index`-th method of the interface `Index` must be in the range 0 to `Count-1` (included).

See also: `PIntfMethodEntry` ([1976](#)), `TIntfMethodEntry` ([2019](#))

79.14 TManagedField

```
TManagedField = packed record
private
    function GetTypeRef : PTypeInfo
    ;
public
    property TypeRef : PTypeInfo;
    TypeRefRef : PTypeInfo
    ;
    FldOffset : SizeInt;
end
```

`TManagedField` describes 1 managed field in a record. It consists of type information (`TypeRef`) and an offset in the record's memory layout (`FldOffset`). Size can be determined from the type information.

79.14.1 Property overview

Page	Properties	Access	Description
2022	<code>TypeRef</code>	r	Type information for the field

79.14.2 TManagedField.TypeRef

Synopsis: Type information for the field

Declaration: `Property TypeRef : PTypeInfo`

Visibility: public

Access: Read

79.15 TParameterLocation

```
TParameterLocation = packed record
private
    LocType : Byte;
    function
```

```

    GetRegType : TRegisterType;
    function GetReference : Boolean;
    function GetShiftVal : Int8;
public
    RegSub : TSubRegister;
    RegNumber
    : Word;
    Offset : SizeInt;
    property Reference : Boolean;
    property
    RegType : TRegisterType;
    property ShiftVal : Int8;
end

```

`TParameterLocation` is used by RTTI to describe the location of a parameter (argument) when arguments are passed to a method call. It has the same memory layout as the actual RTTI data. It offers the following fields and properties:

RegSub Sub register indicator

RegNumber Register number

Offset Stack offset or index of register

Property Reference Is the offset a stack offset or register index

Property RegType Register type

Property ShiftVal Register shift

79.15.1 Property overview

Page	Properties	Access	Description
2023	Reference	r	Is the offset a stack offset or register index
2024	RegType	r	Register type
2024	ShiftVal	r	Register shift

79.15.2 TParameterLocation.Reference

Synopsis: Is the offset a stack offset or register index

Declaration: `Property Reference : Boolean`

Visibility: public

Access: Read

Description: `Reference` indicates whether the register is the index register (`True`), otherwise the register in which (part of) the parameter resides.

See also: `TParameterLocation.ShiftVal` ([2024](#))

79.15.3 TParameterLocation.RegType

Synopsis: Register type

Declaration: `Property RegType : TRegisterType`

Visibility: public

Access: Read

Description: `RegType` returns the type of the register location. It is calculated from a private field.

See also: `TRegisterType` ([1981](#))

79.15.4 TParameterLocation.ShiftVal

Synopsis: Register shift

Declaration: `Property ShiftVal : Int8`

Visibility: public

Access: Read

Description: `ShiftVal` is zero if `Reference` ([2023](#)) is false, or `Offset` otherwise.

See also: `Reference` ([2023](#))

79.16 TParameterLocations

```
TParameterLocations = packed record
private
  function GetLocation
    (aIndex: Byte) : PParameterLocation;
  function GetTail : Pointer
  ;
public
  Count : Byte;
  property Location[Index: Byte]: PParameterLocation
  ;
  property Tail : Pointer;
end
```

`TParameterLocations` is used by RTTI to describe the array of locations of method parameters (arguments) when arguments are passed to a method call. It describes the memory layout of the actual RTTI data. It offers the following fields and properties:

79.16.1 Property overview

Page	Properties	Access	Description
2025	Location	r	Indexed access to the various parameter location descriptors
2025	Tail	r	Memory location after parameter data.

79.16.2 TParameterLocations.Location

Synopsis: Indexed access to the various parameter location descriptors

Declaration: `Property Location[Index: Byte]: PParameterLocation`

Visibility: public

Access: Read

Description: `Location` offers indexed access to the various `TParameterLocation` (2023) records that make up a method's parameters description. Note that it returns a pointer to the actual record, not a copy of the record.

See also: `PParameterLocations` (1976), `TParameterLocation` (2023), `PParameterLocation` (1976)

79.16.3 TParameterLocations.Tail

Synopsis: Memory location after parameter data.

Declaration: `Property Tail : Pointer`

Visibility: public

Access: Read

Description: `Tail` points to the memory location after the `TParameterLocations` data (the last `TParameterLocation` (2023) record). It can be used to get the location of the next structure in the RTTI.

See also: `TParameterLocation` (2023)

79.17 TProcedureParam

```
TProcedureParam = packed record
private
  function GetParamType :
    PTypeInfo;
  function GetFlags : Byte;
public
  property ParamType
    : PTypeInfo;
  property Flags : Byte;
  ParamFlags : TParamFlags
  ;
  ParamTypeRef : PTypeInfo;
  Name : ShortString;
end
```

`TProcedureParam` describes a single parameter to a procedure (or function).

79.17.1 Property overview

Page	Properties	Access	Description
2026	Flags	r	Flags for this parameter (see <code>TParamFlags</code>)
2026	ParamType	r	Type information for this parameter

79.17.2 TProcedureParam.ParamType

Synopsis: Type information for this parameter

Declaration: `Property ParamType : PTypeInfo`

Visibility: `public`

Access: `Read`

79.17.3 TProcedureParam.Flags

Synopsis: Flags for this parameter (see `TParamFlags`)

Declaration: `Property Flags : Byte`

Visibility: `public`

Access: `Read`

79.18 TProcedureSignature

```
TProcedureSignature = packed record
private
    function GetResultType
        : PTypeInfo;
public
    property ResultType : PTypeInfo;
    Flags :
        Byte;
    CC : TCallConv;
    ResultTypeRef : PTypeInfo;
    ParamCount
        : Byte;
    function GetParam(ParamIndex: Integer) : PProcedureParam
        ;
end
```

`TProcedureSignature` describes a procedure/method call signature. It consists of some flags (`Flags`), a calling convention (`CC`), the result type (`ResultType`) if any, and a list of `ParamCount` parameters (of type `TProcedureParam` ([2025](#))).

79.18.1 Method overview

Page	Method	Description
2027	<code>GetParam</code>	Get parameter signature

79.18.2 Property overview

Page	Properties	Access	Description
2027	<code>ResultType</code>	<code>r</code>	Result type info (Nil if no result)

79.18.3 TProcedureSignature.GetParam

Synopsis: Get parameter signature

Declaration: `function GetParam(ParamIndex: Integer) : PProcedureParam`

Visibility: public

Description: `GetParam` can be used to retrieve a pointer to the description of a parameter. The index `ParamIndex` is zero-based.

Errors: In case of an invalid parameter index, `Nil` is returned.

See also: `TProcedureParam` ([2025](#))

79.18.4 TProcedureSignature.ResultType

Synopsis: Result type info (Nil if no result)

Declaration: `Property ResultType : PTypeInfo`

Visibility: public

Access: Read

79.19 TPropData

```
TPropData = packed record
private
    function GetProp(Index: Word)
        : PPropInfo;
    function GetTail : Pointer;
public
    PropCount : Word
    ;
    PropList : record
    public
        _alignmentdummy : PtrInt;
    end
    ;
    property Prop[Index: Word]: PPropInfo;
    property Tail : Pointer
    ;
end
```

The `TPropData` record is not used, but is provided for completeness and compatibility with Delphi.

79.19.1 Property overview

Page	Properties	Access	Description
2028	Prop	r	Indexed access to property type info
2028	Tail	r	Pointer to next RTTI structure.

79.19.2 TPropData.Prop

Synopsis: Indexed access to property type info

Declaration: `Property Prop[Index: Word]: PPropInfo`

Visibility: public

Access: Read

Description: `Prop` provides indexed access to the property type info of all properties of a class. Valid values for `Index` are in the range `0..WordCount-1`

See also: `PPropInfo` ([1976](#)), `TPropInfo` ([2029](#))

79.19.3 TPropData.Tail

Synopsis: Pointer to next RTTI structure.

Declaration: `Property Tail : Pointer`

Visibility: public

Access: Read

Description: `Tail` points to the memory area after the last property info. It can be used to get the next RTTI info.

79.20 TPropInfo

```

TPropInfo = packed record
private
    function GetPropType : PTypeInfo
    ;
    function GetTail : Pointer;
    function GetNext : PPropInfo;
public
    PropTypeRef : PTypeInfo;
    GetProc : CodePointer;
    SetProc :
    CodePointer;
    StoredProc : CodePointer;
    Index : Integer;
    Default
    : LongInt;
    NameIndex : SmallInt;
    PropProcs : Byte;
    Name : ShortString
    ;
    property PropType : PTypeInfo;
    property Tail : Pointer;
    property
    Next : PPropInfo;
end

```

The `TPropInfo` record describes one published property of a class. The property information of a class are stored as an array of `TPropInfo` records.

The `Name` field is stored not with 255 characters, but with just as many characters as required to store the name.

79.20.1 Property overview

Page	Properties	Access	Description
2029	Next	r	Typed pointer <code>TPropInfo</code> record after current <code>TPropInfo</code> data.
2029	PropType	r	Property type
2029	Tail	r	Pointer to memory location after <code>TPropInfo</code> data.

79.20.2 TPropInfo.PropertyType

Synopsis: Property type

Declaration: `Property PropType : PTypeInfo`

Visibility: public

Access: Read

79.20.3 TPropInfo.Tail

Synopsis: Pointer to memory location after `TPropInfo` data.

Declaration: `Property Tail : Pointer`

Visibility: public

Access: Read

Description: `Tail` points to the memory location right after the `TPropInfo` data. This can be another `TPropInfo` record, or a completely different kind of information.

See also: `TPropInfo.Next` ([2029](#))

79.20.4 TPropInfo.Next

Synopsis: Typed pointer `TPropInfo` record after current `TPropInfo` data.

Declaration: `Property Next : PPropInfo`

Visibility: public

Access: Read

Description: `Next` points to the same memory location as `TPropInfo.Tail` ([2029](#)), but is typed. It should not be used on the last element of a `TPropInfo` array.

See also: `TPropInfo.Tail` ([2029](#))

79.21 TTypeData

```

TTypeData = packed record
private
    function GetBaseType : PTypeInfo
    ;
    function GetCompType : PTypeInfo;
    function GetParentInfo : PTypeInfo
    ;
    function GetRecInitData : PRecInitData;
    function GetHelperParent
    : PTypeInfo;
    function GetExtendedInfo : PTypeInfo;
    function GetIntfParent
    : PTypeInfo;
    function GetRawIntfParent : PTypeInfo;
    function
    GetIIDStr : ShortString;
    function GetElType : PTypeInfo;
    function
    GetElType2 : PTypeInfo;
    function GetInstanceType : PTypeInfo;
    function GetRefType : PTypeInfo;
public
    property BaseType : PTypeInfo
    ;
    property CompType : PTypeInfo;
    property ParentInfo : PTypeInfo
    ;
    property RecInitData : PRecInitData;
    property HelperParent
    : PTypeInfo;
    property ExtendedInfo : PTypeInfo;
    property IntfParent
    : PTypeInfo;
    property RawIntfParent : PTypeInfo;
    property IIDStr
    : ShortString;
    property ElType2 : PTypeInfo;
    property ElType
    : PTypeInfo;
    property InstanceType : PTypeInfo;
    property RefType
    : PTypeInfo;
case TTypeKind of
tkUnknown: (
);, tkLString: (
);,
    tkWString: (
);, tkVariant: (
);, tkUString: (
);
tkAString: (

```

```

public
    CodePage : Word;
);
tkInt64: (
public
    OrdType : TOrdType;
case
    TTypeKind of
tkInteger: (
public
    MinValue : LongInt;
    MaxValue
        : LongInt;
case TTypeKind of
tkEnumeration: (
public
    BaseTypeRef
        : PPTypInfo;
    NameList : ShortString;
);
);, tkChar: (
public
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
public
    BaseTypeRef : PPTypInfo;
    NameList : ShortString;
);
);, tkEnumeration: (
public
    MinValue : LongInt;
    MaxValue :
        LongInt;
case TTypeKind of
tkEnumeration: (
public
    BaseTypeRef
        : PPTypInfo;
    NameList : ShortString;
);
);, tkBool: (
public
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
public
    BaseTypeRef : PPTypInfo;
    NameList : ShortString;
);
);

```



```

);, tkWChar: (
public
    MinValue : LongInt;
    MaxValue : LongInt
    ;
case TTypeKind of
tkEnumeration: (
public
    BaseTypeRef : PTypeInfo
    ;
    NameList : ShortString;
);
);
tkInt64: (
public
    MinInt64Value
        : Int64;
    MaxInt64Value : Int64;
);
tkQWord: (
public
    MinQWordValue
        : QWord;
    MaxQWordValue : QWord;
);
tkSet: (
public
    SetSize :
        SizeInt;
    CompTypeRef : PTypeInfo;
);
);, tkQWord: (
public
    OrdType
        : TOrdType;
case TTypeKind of
tkInteger: (
public
    MinValue : LongInt
    ;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
public
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
);
);, tkChar
    : (
public
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind
    of

```

```

tkEnumeration: (
public
  BaseTypeRef : PTypeInfo;
  NameList
    : ShortString;
);
);, tkEnumeration: (
public
  MinValue : LongInt
    ;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
public
  BaseTypeRef : PTypeInfo;
  NameList : ShortString;
);
);, tkBool
  : (
public
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind
  of
tkEnumeration: (
public
  BaseTypeRef : PTypeInfo;
  NameList
    : ShortString;
);
);, tkWChar: (
public
  MinValue : LongInt;
  MaxValue
    : LongInt;
case TTypeKind of
tkEnumeration: (
public
  BaseTypeRef
    : PTypeInfo;
  NameList : ShortString;
);
);
tkInt64: (
public
  MinInt64Value : Int64;
  MaxInt64Value : Int64;
);
tkQWord: (
public
  MinQWordValue : QWord;
  MaxQWordValue : QWord;
);
tkSet: (

```

```

public
  SetSize : SizeInt;
  CompTypeRef : PPTypeInfo;
);
);, tkInteger
  : (
public
  OrdType : TOrdType;
case TTypeKind of
tkInteger: (
public
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
public
  BaseTypeRef : PPTypeInfo;
  NameList : ShortString;
);
);, tkChar: (
public
  MinValue : LongInt;
  MaxValue : LongInt
  ;
case TTypeKind of
tkEnumeration: (
public
  BaseTypeRef : PPTypeInfo
  ;
  NameList : ShortString;
);
);, tkEnumeration: (
public
  MinValue
  : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
public
  BaseTypeRef : PPTypeInfo;
  NameList : ShortString;
);
);, tkBool: (
public
  MinValue : LongInt;
  MaxValue : LongInt
  ;
case TTypeKind of
tkEnumeration: (
public
  BaseTypeRef : PPTypeInfo
  ;

```

```

    NameList : ShortString;
);
);, tkWChar: (
public
    MinValue :
        LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration:
    (
public
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
);
);
tkInt64: (
public
    MinInt64Value : Int64;
    MaxInt64Value : Int64
    ;
);
tkQWord: (
public
    MinQWordValue : QWord;
    MaxQWordValue :
        QWord;
);
tkSet: (
public
    SetSize : SizeInt;
    CompTypeRef : PTypeInfo
    ;
);
);, tkChar: (
public
    OrdType : TOrdType;
case TTypeKind of
    tkInteger: (
public
        MinValue : LongInt;
        MaxValue : LongInt;
case
    TTypeKind of
tkEnumeration: (
public
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
);
);, tkChar: (
public
    MinValue : LongInt
    ;
    MaxValue : LongInt;
case TTypeKind of

```

```

tkEnumeration: (
public
  BaseTypeRef : PTypeInfo;
  NameList : ShortString;
);
);, tkEnumeration
  : (
public
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind
of
tkEnumeration: (
public
  BaseTypeRef : PTypeInfo;
  NameList
  : ShortString;
);
);, tkBool: (
public
  MinValue : LongInt;
  MaxValue
  : LongInt;
case TTypeKind of
tkEnumeration: (
public
  BaseTypeRef
  : PTypeInfo;
  NameList : ShortString;
);
);, tkWChar: (
public
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
public
  BaseTypeRef : PTypeInfo;
  NameList : ShortString;
  );
);
tkInt64: (
public
  MinInt64Value : Int64;
  MaxInt64Value
  : Int64;
);
tkQWord: (
public
  MinQWordValue : QWord;
  MaxQWordValue
  : QWord;
);

```

```

tkSet: (
public
    SetSize : SizeInt;
    CompTypeRef :
    PPTypeInfo;
);
);, tkEnumeration: (
public
    OrdType : TOrdType;
    case TTypeKind of
tkInteger: (
public
    MinValue : LongInt;
    MaxValue
    : LongInt;
case TTypeKind of
tkEnumeration: (
public
    BaseTypeRef
    : PPTypeInfo;
    NameList : ShortString;
);
);, tkChar: (
public
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
public
    BaseTypeRef : PPTypeInfo;
    NameList : ShortString;
    );
);, tkEnumeration: (
public
    MinValue : LongInt;
    MaxValue :
    LongInt;
case TTypeKind of
tkEnumeration: (
public
    BaseTypeRef
    : PPTypeInfo;
    NameList : ShortString;
);
);, tkBool: (
public
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
public
    BaseTypeRef : PPTypeInfo;

```

```

    NameList : ShortString;
  );
);, tkWChar: (
public
  MinValue : LongInt;
  MaxValue : LongInt
  ;
case TTypeKind of
tkEnumeration: (
public
  BaseTypeRef : PTypeInfo
  ;
  NameList : ShortString;
);
);
tkInt64: (
public
  MinInt64Value
    : Int64;
  MaxInt64Value : Int64;
);
tkQWord: (
public
  MinQWordValue
    : QWord;
  MaxQWordValue : QWord;
);
tkSet: (
public
  SetSize :
  SizeInt;
  CompTypeRef : PTypeInfo;
);
);, tkBool: (
public
  OrdType
    : TOrdType;
case TTypeKind of
tkInteger: (
public
  MinValue : LongInt
  ;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
public
  BaseTypeRef : PTypeInfo;
  NameList : ShortString;
);
);, tkChar
  : (
public
  MinValue : LongInt;
  MaxValue : LongInt;

```

```

case TTypeKind
  of
tkEnumeration: (
public
  BaseTypeRef : PTypeInfo;
  NameList
    : ShortString;
);
);, tkEnumeration: (
public
  MinValue : LongInt
    ;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
public
  BaseTypeRef : PTypeInfo;
  NameList : ShortString;
);
);, tkBool
  : (
public
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind
  of
tkEnumeration: (
public
  BaseTypeRef : PTypeInfo;
  NameList
    : ShortString;
);
);, tkWChar: (
public
  MinValue : LongInt;
  MaxValue
    : LongInt;
case TTypeKind of
tkEnumeration: (
public
  BaseTypeRef
    : PTypeInfo;
  NameList : ShortString;
);
);
tkInt64: (
public
  MinInt64Value : Int64;
  MaxInt64Value : Int64;
);
tkQWord: (
public
  MinQWordValue : QWord;
  MaxQWordValue : QWord;

```



```

);
tkSet: (
public
    SetSize : SizeInt;
    CompTypeRef : PPTypInfo;
);
);, tkWChar:
(
public
    OrdType : TOrdType;
case TTypeKind of
tkInteger: (
public
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
public
    BaseTypeRef : PPTypInfo;
    NameList : ShortString;
    );
);, tkChar: (
public
    MinValue : LongInt;
    MaxValue : LongInt
    ;
case TTypeKind of
tkEnumeration: (
public
    BaseTypeRef : PPTypInfo
    ;
    NameList : ShortString;
);
);, tkEnumeration: (
public
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
public
    BaseTypeRef : PPTypInfo;
    NameList : ShortString;
    );
);, tkBool: (
public
    MinValue : LongInt;
    MaxValue : LongInt
    ;
case TTypeKind of
tkEnumeration: (
public

```

```

    BaseTypeRef : PTypeInfo
    ;
    NameList : ShortString;
);
);, tkWChar: (
public
    MinValue :
    LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration:
    (
public
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
);
);
tkInt64: (
public
    MinInt64Value : Int64;
    MaxInt64Value : Int64
    ;
);
tkQWord: (
public
    MinQWordValue : QWord;
    MaxQWordValue :
    QWord;
);
tkSet: (
public
    SetSize : SizeInt;
    CompTypeRef : PTypeInfo
    ;
);
);, tkSet: (
public
    OrdType : TOrdType;
case TTypeKind of
tkInteger
    : (
public
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind
    of
tkEnumeration: (
public
    BaseTypeRef : PTypeInfo;
    NameList
    : ShortString;
);
);, tkChar: (
public

```

```

    MinValue : LongInt;
    MaxValue
      : LongInt;
case TTypeKind of
tkEnumeration: (
public
    BaseTypeRef
      : PTypeInfo;
    NameList : ShortString;
);
);, tkEnumeration: (
public
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
public
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
  );
);, tkBool: (
public
    MinValue : LongInt;
    MaxValue : LongInt
  ;
case TTypeKind of
tkEnumeration: (
public
    BaseTypeRef : PTypeInfo
  ;
    NameList : ShortString;
);
);, tkWChar: (
public
    MinValue :
      LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration:
  (
public
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
  );
  );
tkInt64: (
public
    MinInt64Value : Int64;
    MaxInt64Value : Int64
  ;
);
tkQWord: (
public

```

```

    MinQWordValue : QWord;
    MaxQWordValue :
    QWord;
);
tkSet: (
public
    SetSize : SizeInt;
    CompTypeRef : PPTypeInfo
    ;
);
);
tkFloat: (
public
    FloatType : TFloatType;
);
tkSSString:
(
public
    MaxLength : Byte;
);
tkClass: (
public
    ClassType : TClass
    ;
    ParentInfoRef : PPTypeInfo;
    PropCount : SmallInt;
    UnitName
    : ShortString;
);
tkRecord: (
public
    RecInitInfo : Pointer;
    RecSize
    : Integer;
case Boolean of
False: (
public
    ManagedFldCount : Integerdeprecated
    ;
);
True: (
public
    TotalFieldCount : Integer;
);
);
tkHelper:
(
public
    HelperParentRef : PPTypeInfo;
    ExtendedInfoRef : PPTypeInfo
    ;
    HelperProps : SmallInt;
    HelperUnit : ShortString;
);

```

```

tkMethod
  : (
public
  MethodKind : TMethodKind;
  ParamCount : Byte;
  ParamList
    : Array[0..1023] of Char;
);
tkProcVar: (
public
  ProcSig : TProcedureSignature
  ;
);
tkInterface: (
public
  IntfParentRef : PTypeInfo;
  IntfFlags
    : TIntfFlagsBase;
  GUID : TGuid;
  IntfUnit : ShortString;
);
tkInterfaceRaw
  : (
public
  RawIntfParentRef : PTypeInfo;
  RawIntfFlags : TIntfFlagsBase
  ;
  IID : TGuid;
  RawIntfUnit : ShortString;
);
tkArray: (
public
  ArrayData : TArrayTypeData;
);
tkDynArray: (
public
  elSize :
  PtrUInt;
  elType2Ref : PTypeInfo;
  varType : LongInt;
  elTypeRef
    : PTypeInfo;
  DynUnitName : ShortStringBase;
);
tkClassRef: (
public
  InstanceTypeRef : PTypeInfo;
);
tkPointer: (
public
  RefTypeRef
    : PTypeInfo;
);
end

```

If the `TypeInfo` kind is `tkClass`, then the property information follows the `UnitName` string, as an array of `TPropInfo` (2029) records.

79.21.1 Property overview

Page	Properties	Access	Description
2045	<code>BaseType</code>	r	Base type on which this type is based.
2045	<code>CompType</code>	r	Comp type
2047	<code>ElType</code>	r	Dynamical array Element type
2047	<code>ElType2</code>	r	Dynamical array Element type
2046	<code>ExtendedInfo</code>	r	Type information for the extended type (record or class).
2046	<code>HelperParent</code>	r	Type information for parent helper class
2047	<code>IIDStr</code>	r	IID string representation of interface
2047	<code>InstanceType</code>	r	Pointer to instance type data
2046	<code>IntfParent</code>	r	Parent interface type data.
2045	<code>ParentInfo</code>	r	Parent class type info
2047	<code>RawIntfParent</code>	r	Raw interface parent.
2046	<code>RecInitData</code>	r	Pointer to record initialization data
2047	<code>RefType</code>	r	Type info for referred type (Nil for untyped pointer)

79.21.2 TTypeData.BaseType

Synopsis: Base type on which this type is based.

Declaration: `Property BaseType : PTypeInfo`

Visibility: public

Access: Read

79.21.3 TTypeData.CompType

Synopsis: Comp type

Declaration: `Property CompType : PTypeInfo`

Visibility: public

Access: Read

79.21.4 TTypeData.ParentInfo

Synopsis: Parent class type info

Declaration: `Property ParentInfo : PTypeInfo`

Visibility: public

Access: Read

79.21.5 TTypeData.RecInitData

Synopsis: Pointer to record initialization data

Declaration: `Property RecInitData : PRecInitData`

Visibility: public

Access: Read

Description: `RecInitData` is a pointer to a `TRecInitData` (1981) record. It is only valid if the type data describes a record.

See also: `TRecInitData` (1981)

79.21.6 TTypeData.HelperParent

Synopsis: Type information for parent helper class

Declaration: `Property HelperParent : PTypeInfo`

Visibility: public

Access: Read

Description: `HelperParent` points to the type information of the parent helper class. It is `Nil` if there is no parent class.

See also: `TTypeData.ExtendedInfo` (2046)

79.21.7 TTypeData.ExtendedInfo

Synopsis: Type information for the extended type (record or class).

Declaration: `Property ExtendedInfo : PTypeInfo`

Visibility: public

Access: Read

Description: `ExtendedInfo` points to the type information of the type that is being extended.

See also: `TTypeData.HelperParent` (2046)

79.21.8 TTypeData.IntfParent

Synopsis: Parent interface type data.

Declaration: `Property IntfParent : PTypeInfo`

Visibility: public

Access: Read

79.21.9 TTypeData.RawIntfParent

Synopsis: Raw interface parent.

Declaration: `Property RawIntfParent : PTypeInfo`

Visibility: public

Access: Read

79.21.10 TTypeData.IIDStr

Synopsis: IID string representation of interface

Declaration: `Property IIDStr : ShortString`

Visibility: public

Access: Read

79.21.11 TTypeData.ElType2

Synopsis: Dynamical array Element type

Declaration: `Property ElType2 : PTypeInfo`

Visibility: public

Access: Read

79.21.12 TTypeData.ElType

Synopsis: Dynamical array Element type

Declaration: `Property ElType : PTypeInfo`

Visibility: public

Access: Read

79.21.13 TTypeData.InstanceType

Synopsis: Pointer to instance type data

Declaration: `Property InstanceType : PTypeInfo`

Visibility: public

Access: Read

79.21.14 TTypeData.RefType

Synopsis: Type info for referred type (Nil for untyped pointer)

Declaration: `Property RefType : PTypeInfo`

Visibility: public

Access: Read

79.22 TVmtFieldEntry

```

TVmtFieldEntry = packed record
private
    function GetNext : PVmtFieldEntry
    ;
    function GetTail : Pointer;
public
    FieldOffset : PtrUInt;
    TypeIndex : Word;
    Name : ShortString;
    property Tail : Pointer
    ;
    property Next : PVmtFieldEntry;
end

```

TVmtFieldEntry records are generated by the compiler for all fields of a record or class that have RTTI associated with them. They describe the field as known to the compiler.

79.22.1 Property overview

Page	Properties	Access	Description
2048	Next	r	Pointer to the next TVmtFieldEntry.
2048	Tail	r	Pointer to the next RTTI structure.

79.22.2 TVmtFieldEntry.Tail

Synopsis: Pointer to the next RTTI structure.

Declaration: `Property Tail : Pointer`

Visibility: `public`

Access: `Read`

Description: Tail points to the memory location after the TVmtFieldEntry record. This can be another TVmtFieldEntry record or an entirely different data structure.

See also: TVmtFieldEntry.Next ([2048](#))

79.22.3 TVmtFieldEntry.Next

Synopsis: Pointer to the next TVmtFieldEntry.

Declaration: `Property Next : PVmtFieldEntry`

Visibility: `public`

Access: `Read`

Description: Next is the same as TVmtFieldEntry.Tail ([2048](#)), but is typed. Note that on the last TVmtFieldEntry in the array, the next element is not a TVmtFieldEntry.

See also: TVmtFieldEntry.Tail ([2048](#))

79.23 TVmtFieldTable

```

TVmtFieldTable = packed record
private
    function GetField(aIndex
        : Word) : PVmtFieldEntry;
public
    Count : Word;
    ClassTab : PVmtFieldClassTab
    ;
    Fields : Array[0..0] of TVmtFieldEntry;
    property Field[aIndex
        : Word]: PVmtFieldEntry;
end

```

TVmtFieldTable describes the fields for which RTTI was generated. A TVmtFieldTable entry is generated by the compiler in the RTTI information, it is not something one creates manually. Basically it contains a list of TVmtFieldEntry (2048) values.

79.23.1 Property overview

Page	Properties	Access	Description
2049	Field	r	Indexed access to the fields in the table.

79.23.2 TVmtFieldTable.Field

Synopsis: Indexed access to the fields in the table.

Declaration: Property Field[aIndex: Word]: PVmtFieldEntry

Visibility: public

Access: Read

Description: Field returns the location of the aIndexthe field in the table.

See also: TVmtFieldEntry ([2048](#))

79.24 TVmtMethodParam

```

TVmtMethodParam = packed record
private
    function GetTail : Pointer
    ;
    function GetNext : PVmtMethodParam;
    function GetName : ShortString
    ;
public
    ParamType : PTypeInfo;
    Flags : TParamFlags;
    NamePtr
        : PShortString;
    ParaLocs : PParameterLocations;

```

```

    property Name
      : ShortString;
    property Tail : Pointer;
    property Next : PVmtMethodParam
  ;
end

```

TVmtMethodParam describes the type and location of a parameter of a method.

79.24.1 Property overview

Page	Properties	Access	Description
2050	Name	r	Parameter name
2050	Next	r	Pointer to the next TVmtMethodParam record.
2050	Tail	r	Pointer to location after TVmtMethodParam data.

79.24.2 TVmtMethodParam.Name

Synopsis: Parameter name

Declaration: `Property Name : ShortString`

Visibility: public

Access: Read

Description: Name is an ease-of-access property for the NamePtr field, it simply returns the name as a string.

79.24.3 TVmtMethodParam.Tail

Synopsis: Pointer to location after TVmtMethodParam data.

Declaration: `Property Tail : Pointer`

Visibility: public

Access: Read

Description: Tail points to the memory location just after the TVmtMethodParam structure. It can be used to get access to the next RTTI data, which can be again a TVmtMethodParam structure or another structure.

See also: TVmtMethodParam.Next ([2050](#))

79.24.4 TVmtMethodParam.Next

Synopsis: Pointer to the next TVmtMethodParam record.

Declaration: `Property Next : PVmtMethodParam`

Visibility: public

Access: Read

Description: Next is the same as TVmtMethodParam.Tail ([2050](#)), but is typed: it returns a pointer to the next TVmtMethodParam record in the RTTI.

See also: TVmtMethodParam.Tail ([2050](#))

79.25 TVmtMethodTable

```
TVmtMethodTable = packed record
private
    function GetEntry(Index
        : LongWord) : PVmtMethodEntry;
public
    Count : LongWord;
    property
        Entry[Index: LongWord]: PVmtMethodEntry;
private
    Entries : Array
        [0..0] of TVmtMethodEntry;
end
```

TVmtMethodTable is a record structure describing all the VMT methods of a class. It is basically an array of pointers TVmtMethodTable.Entry ([2051](#)).

79.25.1 Property overview

Page	Properties	Access	Description
2051	Entry	r	Indexed access to VMT method information

79.25.2 TVmtMethodTable.Entry

Synopsis: Indexed access to VMT method information

Declaration: `Property Entry[Index: LongWord]: PVmtMethodEntry`

Visibility: public

Access: Read

Description: Method offers indexed access to the method descriptions. It returns the location of the Index-th method of the VMT table Index must be in the range 0 to Count-1 (included).

See also: PVmtMethodEntry ([1977](#)), TVmtMethodEntry ([1983](#))

79.26 EPropertyConvertError

79.26.1 Description

EPropertyConvertError is not used in the Free Pascal implementation of the typinfo unit, but is declared for Delphi compatibility.

79.27 EPropertyError

79.27.1 Description

Exception raised in case of an error in one of the functions.

Chapter 80

Reference for unit 'unicodedata'

80.1 Used units

Table 80.1: Used units by unit 'unicodedata'

Name	Page
System	1339

80.2 Overview

The `fpwiderstring` ([2052](#)) unit relies on having relevant Unicode collation data linked in the binary. The Unicode data is managed using the routines in the `unicodedata` unit. The FPC project distributes some Unicode collation data in `.bco` files which can be loaded using the `LoadCollation` ([2063](#)) routines. The `LoadCollation` is the main routine of this unit.

All collation data requires at least the Default Unicode Collation Element Table to be registered (called `DUCET`). The `DUCET` encoding is provided by the `unicodeducet` unit, part of the `rtl-Unicode` package.

There are two ways to register collations :

1. **at compile time**: by including the desired collation unit, for example for Russian and Japanese languages to be available you will have to include `collation_ru` and `collation_ja` from package "rtl-unicode".
2. **at runtime** using the above mentioned `LoadCollation` function.

The two ways can co-exist: some collations may be compile time included (for example for most used collations) and others can be loaded at runtime in the same application.

The binary collation files are endian sensitive:

- there are files for little endian systems named `collation__le.bco` (such as `collation_ru_le.bco` and `collation_ja_le.bco`)
- there are files for big endian systems named `collation__be.bco` (such as `collation_ru_be.bco` and `collation_ja_be.bco`).

Note that the compile time units collation units (collation_**lang**.pas) include already the unicode-ducet.pas (DUCET) unit so it is not necessary to include it manually, contrary to the binary files. So an application that only uses the binary collation files should at least include the `unicodeducet` unit or manually load the binary collation `collation_ducet_le.bco` or `collation_ducet_be.bco`, depending on the endianness of the platform. The `LoadCollation` (2063) call using a directory and the language `ducet` automatically select the correct file.

80.3 Constants, types and variables

80.3.1 Resource strings

```
SCollationNotFound = 'Collation not found : "%s".'
```

Error message when a collation is not found.

80.3.2 Constants

```
DEFAULT_UCA_COMPARISON_STRENGTH = 3
```

```
DirectorySeparator = '/'
```

```
ENDIAN_SUFFIX : Array[TEndianKind] of UnicodeString = ('le', 'be'
)
```

`ENDIAN_SUFFIX` contains the suffixes used in `LoadCollation` (2063) when constructing a collation filename for a language.

```
ERROR_INVALID_CODEPOINT_SEQUENCE = 1
```

Error exit code for `UnicodeToLower/UnicodeToUpper`

```
HIGH_SURROGATE_BEGIN = Word($D800)
```

First value for high surrogate values.

```
HIGH_SURROGATE_COUNT = HIGH_SURROGATE_END - HIGH_SURROGATE_BEGIN
+ 1
```

Number of high surrogate values.

```
HIGH_SURROGATE_END = Word($DBFF)
```

Last value for high surrogate values.

```
LOW_SURROGATE_BEGIN = Word($DC00)
```

First value for low surrogate values.

```
LOW_SURROGATE_END = Word($DFFF)
```

Last value for low surrogate values.

`MAX_LEGAL_UTF32 = $10FFFF`

Maximum value of a legally encoded UTF32 value (currently unused)

`MAX_WORD = High (Word)`

`MAX_WORD` is the maximum value of a `WORD` typed value.

`reCodesetConversion = reRangeError`

`ROOT_COLLATION_NAME = 'DUCET'`

Name of the root collation (used if no collation name is given)

`UCS4_HALF_BASE = LongWord($10000)`

Offset for UCS4 character encoding

`UCS4_HALF_MASK = Word($3FF)`

Unused currently

`UGC_ClosePunctuation = 14`

Unicode token category: Close punctuation

`UGC_CombiningMark = 6`

Unicode token category: Uppercase letter

`UGC_ConnectPunctuation = 11`

Unicode token category: Connect punctuation

`UGC_Control = 25`

Unicode token category: control token

`UGC_CurrencySymbol = 19`

Unicode token category: Currency symbol

`UGC_DashPunctuation = 12`

Unicode token category: Dash punctuation

`UGC_DecimalNumber = 8`

Unicode token category: Uppercase letter

UGC_EnclosingMark = 7

Unicode token category: Uppercase letter

UGC_FinalPunctuation = 16

Unicode token category: Final punctuation

UGC_Format = 26

Unicode token category: Formatting token

UGC_InitialPunctuation = 15

Unicode token category: Initial punctuation

UGC_LetterNumber = 9

Unicode token category: Letter-number

UGC_LineSeparator = 23

Unicode token category: Line separator

UGC_LowercaseLetter = 1

Unicode general category: Lowercase letter

UGC_MathSymbol = 18

Unicode token category: Math symbol

UGC_ModifierLetter = 3

Unicode general category: modifier letter

UGC_ModifierSymbol = 20

Unicode token category: modifier symbol

UGC_NonSpacingMark = 5

Unicode general category: Non-spacing mark

UGC_OpenPunctuation = 13

Unicode token category: Open punctuation

UGC_OtherLetter = 4

Unicode general category: Other letter

UGC_OtherNumber = 10

Unicode token category: Other number

UGC_OtherPunctuation = 17

Unicode token category: Other punctuation

UGC_OtherSymbol = 21

Unicode token category: Other symbol

UGC_ParagraphSeparator = 24

Unicode token category: Paragraph separator

UGC_PrivateUse = 28

Unicode token category: For private use

UGC_SpaceSeparator = 22

Unicode token category: Space separator

UGC_Surrogate = 27

Unicode token category: Surrogate token

UGC_TitlecaseLetter = 2

Unicode general category: Titlecase letter

UGC_Unassigned = 29

Unicode token category: As yet unassigned

UGC_UppercaseLetter = 0

Unicode general category: Uppercase letter

```
UnicodeCategoryNames : Array[0..29] of string = ('Lu', 'Ll', 'Lt'
, 'Lm', 'Lo', 'Mn', 'Mc', 'Me', 'Nd', 'Nl', 'No', 'Pc', 'Pd', 'Ps'
, 'Pe', 'Pi', 'Pf', 'Po', 'Sm', 'Sc', 'Sk', 'So', 'Zs', 'Zl', 'Zp'
, 'Cc', 'Cf', 'Cs', 'Co', 'Cn')
```

ZERO_UINT24 : UInt24 = (byte2: 0; byte1: 0; byte0: 0)

TUInt24Rec value with all bytes zero.

80.3.3 Types

`PCollationTableItem = ^TCollationTableItem`

`PUCA_DataBook = ^TUCA_DataBook`

Pointer to TUCA_DataBook type.

`PUCA_PropItemContextRec = ^TUCA_PropItemContextRec`

Pointer to TUCA_PropItemContextRec

`PUCA_PropItemContextTreeNodeRec =
^TUCA_PropItemContextTreeNodeRec`

Pointer to TUCA_PropItemContextTreeNodeRec

`PUCA_PropItemContextTreeRec = ^TUCA_PropItemContextTreeRec`

Pointer to TUCA_PropItemContextTreeRec

`PUCA_PropItemRec = ^TUCA_PropItemRec`

Pointer to TUCA_PropItemRec

`PUCA_PropWeights = ^TUCA_PropWeights`

Pointer to TUCA_PropWeights

`PUC_Prop = ^TUC_Prop`

Pointer to TUC_Prop record

`PUInt24 = ^UInt24`

Pointer to TUInt24Rec

`TCategoryMask = Set of`

`TCollationField = (BackWard, VariableLowLimit, VariableHighLimit,
Alternate, Normalization, Strength)`

Table 80.2: Enumeration values for type TCollationField

Value	Explanation
Alternate	
BackWard	Backwards encoded
Normalization	
Strength	
VariableHighLimit	Has upper bound on variable weights
VariableLowLimit	Has lower bound on variable weights

TCollationField describes some properties of the collation data items.

TCollationFields = Set of TCollationField

Set of TCollationField

TCollationName = Array[0..(128-1)] of Byte

Collation name string type (fixed length)

```
TCollationTableItem = record
public
  Collation : PUCA_DataBook;
  Aliases : TUnicodeStringArray;
end
```

TCollationTableItemArray = Array of TCollationTableItem

TCollationVersion = TCollationName

TEndianKind = (Little, Big)

Table 80.3: Enumeration values for type TEndianKind

Value	Explanation
Big	Big-endian platform
Little	Little-endian platform

TEndianKind is an auxiliary enumerated type to enumerate the endianness of platforms.

TSetOfByte = Set of Byte

TUCASortKey = Array of TUCASortKeyItem

Array of TUCASortKeyItem

TUCASortKeyItem = Word

Alias for WORD

```
TUCA_PropWeights = packed record
public
  Weights : Array[0..2] of
    Word;
end
```

TUC_PropWeights describes the weights of collation characteristics of a unicode character. It is an internal structure which should not be used directly, the actual structure is subject to change.

```
TUCA_VariableKind = (ucaShifted, ucaNonIgnorable, ucaBlanked,
    ucaShiftedTrimmed, ucaIgnoreSP)
```

Table 80.4: Enumeration values for type TUCA_VariableKind

Value	Explanation
ucaBlanked	Variable collation elements and any subsequent ignorable collation elements are reset so that all weigh
ucaIgnoreSP	Not implemented (variant of Shifted that reduces the set of variable collation elements to include only
ucaNonIgnorable	Variable collation elements are not reset to be quaternary collation elements
ucaShifted	Variable collation elements are reset to zero at levels one through three
ucaShiftedTrimmed	This option is the same as Shifted, except that all trailing FFFFs are trimmed from the sort key.

Options for weighting data

```
TUnicodeStringArray = Array of UnicodeString
```

```
UInt24 = TUInt24Rec
```

Alias for TUInt24Rec

80.4 Procedures and functions

80.4.1 AddAliasCollation

```
Declaration: function AddAliasCollation(ACollation: PUCA_DataBook;
    AALias: UnicodeString) : Boolean
```

Visibility: default

80.4.2 BytesToName

```
Declaration: function BytesToName(const ABytes: Array of Byte) : UnicodeString
```

Visibility: default

80.4.3 BytesToString

```
Declaration: function BytesToString(const ABytes: Array of Byte;
    const AValidChars: TSetOfByte) : UnicodeString
```

Visibility: default

80.4.4 CanonicalOrder

Synopsis: Put unicode string in canonical order.

```
Declaration: procedure CanonicalOrder(var AString: UnicodeString); Overload
    procedure CanonicalOrder(AString: PUnicodeChar; const ALength: SizeInt)
        ; Overload
```

Visibility: default

Description: CanonicalOrder transforms a unicode string AString (or the alternate form using a null-terminated AStr with length ALength) so it is in canonical order (as defined by the unicode specification). A string needs to be in canonical order to be able to compare strings. This function is called as part of NormalizeNFD (2064).

See also: NormalizeNFD (2064)

80.4.5 CompareSortKey

Synopsis: Compare two sort keys.

Declaration:

```
function CompareSortKey(const A: TUCASortKey; const B: TUCASortKey)
    : Integer; Overload
function CompareSortKey(const A: TUCASortKey; const B: Array of Word)
    : Integer; Overload
```

Visibility: default

Description: CompareSortKey compares 2 sort keys A and B. It returns

- a negative number if A comes alphabetically ordered before B.
- Zero if A is alphabetically identical to B.
- A positive number if A is alphabetically ordered after B.

Sort keys can be constructed from unicode strings using ComputeSortKey (2060).

See also: ComputeSortKey (2060)

80.4.6 ComputeSortKey

Synopsis: Compute the sort key for a string

Declaration:

```
function ComputeSortKey(const AString: UnicodeString;
    const ACollation: PUCA_DataBook) : TUCASortKey
    ; Overload
function ComputeSortKey(const AStr: PUnicodeChar;
    const ALength: SizeInt;
    const ACollation: PUCA_DataBook) : TUCASortKey
    ; Overload
```

Visibility: default

Description: ComputeSortKey computes the sort key for a unicode string AString (or the alternate form using a null-terminated AStr with length ALength) using the Unicode Collation Algorithm data in ACollation. This key can then be used in CompareSortKey (2060) to compare unicode strings.

See also: CompareSortKey (2060)

80.4.7 FilterString

Declaration: `function FilterString(const AStr: PUnicodeChar; const ALength: SizeInt;
const AExcludedMask: TCategoryMask) : UnicodeString
; Overload
function FilterString(const AStr: UnicodeString;
const AExcludedMask: TCategoryMask) : UnicodeString
; Overload`

Visibility: default

80.4.8 FindCollation

Synopsis: Find a collation by name

Declaration: `function FindCollation(AName: UnicodeString) : PUCA_DataBook; Overload
function FindCollation(const AIndex: Integer) : PUCA_DataBook; Overload`

Visibility: default

Description: `FindCollection` searches a collation with name `AName` or index `AIndex` in the list of known collations and returns a pointer to the collation data. If the requested collation is not known, i.e. the name is not found, or the index is out of range, then `Nil` is returned. The valid index range is 0 to `GetCollationCount-1`.

See also: `GetCollationCount` ([2062](#))

80.4.9 FreeCollation

Synopsis: Free collation data.

Declaration: `procedure FreeCollation(AItem: PUCA_DataBook)`

Visibility: default

Description: `FreeCollation` removes all structures in the collation data from memory. It will not do anything when the header field `Dynamic` is `false`. (collations loaded and registered using `LoadCollation` ([2063](#)) are always dynamic and must be freed).

See also: `LoadCollation` ([2063](#))

80.4.10 FromUCS4

Synopsis: Convert UCS4 to UnicodeChar

Declaration: `procedure FromUCS4(const AValue: UCS4Char; out AHighS: UnicodeChar;
out ALowS: UnicodeChar)`

Visibility: default

Description: `FromUCS4` converts the UCS4 encoded unicode character `AValue` to a set of unicode (surrogate pair) characters encoded in UTF16: `AHighS`, `ALowS`.

See also: `ToUCS4` ([2065](#)), `UnicodeIsHighSurrogate` ([2065](#)), `UnicodeIsLowSurrogate` ([2065](#)), `UnicodeIsSurrogatePair` ([2066](#))

Declaration:

```
function IncrementalCompareString(const AStrA: PUnicodeChar;
                                const ALengthA: SizeInt;
                                const AStrB: PUnicodeChar;
                                const ALengthB: SizeInt;
                                const ACollation: PUCA_DataBook)
                                : Integer; Overload
function IncrementalCompareString(const AStrA: UnicodeString;
                                const AStrB: UnicodeString;
                                const ACollation: PUCA_DataBook)
                                : Integer; Overload
```

Visibility: default

Description: `IncrementalCompareString` creates 2 compare keys from the strings `AStrA` and `AStrB` using collation data in `ACollation`. The keys are computed only to the point where the two strings differ. This means the keys cannot be reused for other comparisons if the strings differ. The two strings can be specified as a unicode string or as a pointer to a null-terminated character array with a length (`ALengthA` and `ALengthB`). It returns then the result of `CompareSortKey` (2060).

Errors: None.

See also: `ComputeSortKey` (2060), `CompareSortKey` (2060)

80.4.15 LoadCollation

Synopsis: Load a binary collation data file from file

Declaration:

```
function LoadCollation(const AData: Pointer;
                      const ADataLength: Integer;
                      var AAliases: TUnicodeStringArray) : PUCA_DataBook
                      ; Overload
function LoadCollation(const AData: Pointer; const ADataLength: Integer)
                      : PUCA_DataBook; Overload
function LoadCollation(const AFileName: UnicodeString;
                      var AAliases: TUnicodeStringArray) : PUCA_DataBook
                      ; Overload
function LoadCollation(const AFileName: UnicodeString) : PUCA_DataBook
                      ; Overload
function LoadCollation(const ADirectory: UnicodeString;
                      const ALanguage: UnicodeString;
                      var AAliases: TUnicodeStringArray) : PUCA_DataBook
                      ; Overload
function LoadCollation(const ADirectory: UnicodeString;
                      const ALanguage: UnicodeString) : PUCA_DataBook
                      ; Overload
```

Visibility: default

Description: `LoadCollation` loads collation data from file `AFileName`, or from a memory block `AData` with length `ADataLength`. If successful, it returns a pointer which can be used to register the collation using `RegisterCollation` (2064). if there is a problem with the data, `Nil` is returned.

The filename can also be specified as a `Directory` and language name `ALanguage`. The latter is prepended with `collation_` and appended with the native endianness of the current platform, and has extension `.bco`

Errors: If the file containing data does not exist or has a size which is less than the encoded header size, Nil is returned.

See also: RegisterCollation ([2064](#))

80.4.16 NormalizeNFD

Synopsis: Perform unicode normalization D on a string

Declaration:

```
function NormalizeNFD(const AString: UnicodeString) : UnicodeString
    ; Overload
function NormalizeNFD(const AStr: PUnicodeChar; ALength: SizeInt)
    : UnicodeString; Overload
```

Visibility: default

Description: NormalizeNFD normalizes the string AString (or the alternate form using a null-terminated AStr with length ALength) to Unicode Normalization Form D. The resulting string can be used to determine equivalence of unicode strings.

See also: CanonicalOrder ([2059](#))

80.4.17 PrepareCollation

Synopsis: Prepare a collation for use in the list

Declaration:

```
procedure PrepareCollation(ACollation: PUCA_DataBook;
    const ABaseName: UnicodeString;
    const AChangedFields: TCollationFields)
```

Visibility: default

Description: PrepareCollation will link collation definition ACollation to the base collection with name ABaseName (if empty, it defaults to the root collation). It will also initialize some fields in the definition, copying them from the base collation, but excludes the fields enumerated in AChangedFields. It should normally not be needed to call this function, it is called as part of LoadCollation ([2063](#)).

See also: LoadCollation ([2063](#))

80.4.18 RegisterCollation

Synopsis: Register a new collation

Declaration:

```
function RegisterCollation(const ACollation: PUCA_DataBook) : Boolean
    ; Overload
function RegisterCollation(const ACollation: PUCA_DataBook;
    const AAliasList: Array of UnicodeString)
    : Boolean; Overload
function RegisterCollation(ADirectory: UnicodeString;
    ALanguage: UnicodeString) : Boolean; Overload
```

Visibility: default

Description: `RegisterCollation` registers a new collation `ACollation` in the list of known collations. The collation data can be specified directly (`ACollation`) or a name of a language (`ALanguage`) in a directory (`ADirectory`). The latter option will load the binary encoded collation from file using `LoadCollation` (2063).

If the collation is loaded correctly, `True` is returned, otherwise `False` is returned (for instance when a collation with the same name is already loaded).

See also: `UnRegisterCollation` (2067), `UnRegisterCollations` (2067), `LoadCollation` (2063)

80.4.19 ToUCS4

Synopsis: Encode unicode UTF16 surrogate pair to UCS4 character

Declaration: `function ToUCS4(const AHighS: UnicodeChar; const ALowS: UnicodeChar) : UCS4Char`

Visibility: default

Description: `ToUCS4` converts set of unicode (surrogate pair) characters encoded in UTF16: `AHighS`, `ALowS` to a UCS4 encoded unicode character.

See also: `FromUCS4` (2061), `UnicodeIsHighSurrogate` (2065), `UnicodeIsLowSurrogate` (2065), `UnicodeIsSurrogatePair` (2066)

80.4.20 UnicodeIsHighSurrogate

Synopsis: Check if a UTF16 character is the high character in a surrogate pair.

Declaration: `function UnicodeIsHighSurrogate(const AValue: UnicodeChar) : Boolean`

Visibility: default

Description: `UnicodeIsHighSurrogate` checks whether `AValue` is a valid high character of a surrogate pair, and returns `True` if this is the case. It does this by checking whether the values are within the bounds for high characters in surrogate pairs.

See also: `FromUCS4` (2061), `ToUCS4` (2065), `UnicodeIsHighSurrogate` (2065), `UnicodeIsLowSurrogate` (2065), `UnicodeIsSurrogatePair` (2066)

80.4.21 UnicodeIsLowSurrogate

Synopsis: Check if a UTF16 character is the low character in a surrogate pair.

Declaration: `function UnicodeIsLowSurrogate(const AValue: UnicodeChar) : Boolean`

Visibility: default

Description: `UnicodeIsLowSurrogate` checks whether `AValue` is a valid low character of a surrogate pair, and returns `True` if this is the case. It does this by checking whether the values are within the bounds for low characters in surrogate pairs.

See also: `FromUCS4` (2061), `ToUCS4` (2065), `UnicodeIsHighSurrogate` (2065), `UnicodeIsSurrogatePair` (2066)

80.4.22 `UnicodeIsSurrogatePair`

Synopsis: Check if a pair of UTF16 encoded characters is a valid surrogate pair.

Declaration:

```
function UnicodeIsSurrogatePair(const AHighSurrogate: UnicodeChar;
                                const ALowSurrogate: UnicodeChar)
                                : Boolean
```

Visibility: default

Description: `UnicodeIsSurrogatePair` checks whether `AHighSurrogate`, `ALowSurrogate` constitute a valid surrogate pair, and returns `True` if this is the case. It does this by checking whether the values are within the bounds for high and low surrogate pairs.

See also: `FromUCS4` ([2061](#)), `ToUCS4` ([2065](#)), `UnicodeIsHighSurrogate` ([2065](#)), `UnicodeIsLowSurrogate` ([2065](#))

80.4.23 `UnicodeToLower`

Synopsis: Transform unicode string to lowercase

Declaration:

```
function UnicodeToLower(const AString: UnicodeString;
                        const AIgnoreInvalidSequence: Boolean;
                        out AResultString: UnicodeString) : Integer
```

Visibility: default

Description: `UnicodeToLower` transforms a UTF16 unicode string `AString` to its lowercase equivalent and returns this in `AResultString`. If the transformation was successful, then the function returns 0. A nonzero return value means an error occurred. `AResultString` will remain untouched in that case.

If a character in `AString` cannot be found in the unicode data tables, an error will be reported, unless `AIgnoreInvalidSequence` is set to `True`, in which case the character will be copied as-is to the output.

Unicode collation data can be loaded using `RegisterCollation` ([2064](#)) or `LoadCollation` ([2063](#))

Errors: On error, a nonzero value will be returned.

See also: `UnicodeToUpper` ([2066](#)), `RegisterCollation` ([2064](#)), `LoadCollation` ([2063](#))

80.4.24 `UnicodeToUpper`

Synopsis: Transform unicode string to uppercase

Declaration:

```
function UnicodeToUpper(const AString: UnicodeString;
                        const AIgnoreInvalidSequence: Boolean;
                        out AResultString: UnicodeString) : Integer
```

Visibility: default

Description: `UnicodeToUpper` transforms a UTF16 unicode string `AString` to its uppercase equivalent and returns this in `AResultString`. If the transformation was successful, then the function returns 0. A nonzero return value means an error occurred. `AResultString` will remain untouched in that case.

If a character in `AString` cannot be found in the unicode data tables, an error will be reported, unless `AIgnoreInvalidSequence` is set to `True`, in which case the character will be copied as-is to the output.

Unicode collation data can be loaded using `RegisterCollation` ([2064](#)) or `LoadCollation` ([2063](#))

Errors: On error, a nonzero value will be returned.

See also: [UnicodeToLower \(2066\)](#), [RegisterCollation \(2064\)](#), [LoadCollation \(2063\)](#)

80.4.25 UnregisterCollation

Synopsis: Remove a collation from the list of known collections.

Declaration: `function UnregisterCollation(AName: UnicodeString) : Boolean`

Visibility: default

Description: `UnRegisterCollation` removes a collation `AName` from the list of known collations. It returns `True` if the collation was found and successfully removed.

Errors: If the collation was not found, `False` is returned.

See also: [RegisterCollation \(2064\)](#), [UnRegisterCollations \(2067\)](#), [LoadCollation \(2063\)](#)

80.4.26 UnregisterCollations

Synopsis: Unregister all collations.

Declaration: `procedure UnregisterCollations(const AFreeDynamicCollations: Boolean)`

Visibility: default

Description: `UnregisterCollations` unregisters all known collations. If `AFreeDynamicCollations` is `True`, then dynamic collations will be removed from memory using [FreeCollation \(2061\)](#). This must normally be set to `true`.

See also: [RegisterCollation \(2064\)](#), [UnRegisterCollation \(2067\)](#), [LoadCollation \(2063\)](#), [FreeCollation \(2061\)](#)

80.5 TCollationTable

```
TCollationTable = record
private
    FItems : TCollationTableItemArray
    ;
    FCount : Integer;
    function GetCapacity : Integer;
    function
    GetCount : Integer;
    function GetItem(const AIndex: Integer) : PCollationTableItem
    ;
    procedure Grow;
    procedure ClearItem(AItem: PCollationTableItem
    );
    AddAlias;
public
    class function NormalizeName(AName: UnicodeString
    ) : UnicodeString
    ; Static;

    procedure
    Clear;
```

```

    IndexOf;
    Find;
    function Add(ACollation: PUCA_DataBook
    ) : Integer;
    function Remove(AIndex: Integer) : PUCA_DataBook;
    property Item[AIndex: Integer]: PCollationTableItem; default;
    property Count : Integer;
    property Capacity : Integer;
end

```

80.5.1 Method overview

Page	Method	Description
2069	Add	
2068	Clear	
2068	Find	
2068	IndexOf	
2068	NormalizeName	
2069	Remove	

80.5.2 Property overview

Page	Properties	Access	Description
2069	Capacity	r	
2069	Count	r	
2069	Item	r	

80.5.3 TCollationTable.NormalizeName

Declaration: `class function NormalizeName(AName: UnicodeString) : UnicodeString; Static`

Visibility: public

80.5.4 TCollationTable.Clear

Declaration: `procedure Clear`

Visibility: public

80.5.5 TCollationTable.IndexOf

Declaration: `function IndexOf(AName: UnicodeString) : Integer; Overload`
`function IndexOf(ACollation: PUCA_DataBook) : Integer; Overload`

Visibility: public

80.5.6 TCollationTable.Find

Declaration: `function Find(AName: UnicodeString) : PCollationTableItem; Overload`
`function Find(ACollation: PUCA_DataBook) : PCollationTableItem`
`; Overload`

Visibility: public

80.5.7 TCollationTable.Add

Declaration: function Add(ACollation: PUCA_DataBook) : Integer

Visibility: public

80.5.8 TCollationTable.Remove

Declaration: function Remove(AIndex: Integer) : PUCA_DataBook

Visibility: public

80.5.9 TCollationTable.Item

Declaration: Property Item[AIndex: Integer]: PCollationTableItem; default

Visibility: public

Access: Read

80.5.10 TCollationTable.Count

Declaration: Property Count : Integer

Visibility: public

Access: Read

80.5.11 TCollationTable.Capacity

Declaration: Property Capacity : Integer

Visibility: public

Access: Read

80.6 TUCA_DataBook

```
TUCA_DataBook = record
public
  Base : PUCA_DataBook;
  Version :
    TCollationVersion;
  CollationName : TCollationName;
  VariableWeight
    : TUCA_VariableKind;
  Backwards : Array[0..3] of Boolean;
  BMP_Table1
    : PByte;
  BMP_Table2 : PUInt24;
```

```

OBMP_Table1 : PWord;
OBMP_Table2
: PUInt24;
PropCount : Integer;
Props : PUCA_PropItemRec;
VariableLowLimit
: Word;
VariableHighLimit : Word;
NoNormalization : Boolean;
ComparisonStrength : Byte;
Dynamic : Boolean;
function IsVariable
(const AWeight: PUCA_PropWeights) : Boolean;
end

```

TUCA_DataBook describes a Unicode Collation Algorithm data set. data sets can be registered using the RegisterCollation (2064) function or loaded from file using LoadCollation (2063). A collation data book must be specified when comparing unicode strings.

80.6.1 Method overview

Page	Method	Description
2070	IsVariable	Check if a weight is a variable weight

80.6.2 TUCA_DataBook.IsVariable

Synopsis: Check if a weight is a variable weight

Declaration: function IsVariable(const AWeight: PUCA_PropWeights) : Boolean

Visibility: public

Description: IsVariable checks whether AWeight is between the VariableLowLimit and VariableHighLimit limits.

80.7 TUCA_PropItemContextRec

```

TUCA_PropItemContextRec = packed record
public
  CodePointCount :
  Byte;
  WeightCount : Byte;
  function GetCodePoints : PUInt24;
  function GetWeights : PUCA_PropWeights;
end

```

This is an internal structure which should not be used directly, the actual structure is subject to change.

80.7.1 Method overview

Page	Method	Description
2071	GetCodePoints	get the address of actual code points.
2071	GetWeights	Get the Address of actual weights.

80.7.2 TUCA_PropltemContextRec.GetCodePoints

Synopsis: get the address of actual code points.

Declaration: `function GetCodePoints : PUInt24`

Visibility: public

80.7.3 TUCA_PropltemContextRec.GetWeights

Synopsis: Get the Address of actual weights.

Declaration: `function GetWeights : PUCA_PropWeights`

Visibility: public

80.8 TUCA_PropItemContextTreeNodeRec

```

TUCA_PropItemContextTreeNodeRec = packed record
public
    Left : Word
    ;
    Right : Word;
    Data : TUCA_PropItemContextRec;
    function GetLeftNode
    : PUCA_PropItemContextTreeNodeRec;
    function GetRightNode : PUCA_PropItemContextTreeNodeRec
    ;
end

```

This is an internal structure for the tree which should not be used directly, the actual structure is subject to change.

80.8.1 Method overview

Page	Method	Description
2071	GetLeftNode	Access to left tree node data
2072	GetRightNode	Access to right tree node data

80.8.2 TUCA_PropItemContextTreeNodeRec.GetLeftNode

Synopsis: Access to left tree node data

Declaration: `function GetLeftNode : PUCA_PropItemContextTreeNodeRec`

Visibility: public

80.8.3 TUCA_PropltemContextTreeNodeRec.GetRightNode

Synopsis: Access to right tree node data

Declaration: `function GetRightNode : PUCA_PropItemContextTreeNodeRec`

Visibility: public

80.9 TUCA_PropItemContextTreeRec

```
TUCA_PropItemContextTreeRec = packed record
public
  Size : UInt24
  ;
  function GetData : PUCA_PropItemContextTreeNodeRec;
  property
    Data : PUCA_PropItemContextTreeNodeRec;
  function Find(const AChars
    : PUInt24; const ACharCount: Integer;
    out ANode: PUCA_PropItemContextTreeNodeRec
  ) : Boolean;
end
```

This is an internal tree structure for storing unicode collation data which should not be used directly, the actual structure is subject to change.

80.9.1 Method overview

Page	Method	Description
2072	Find	Find data for encoded character
2072	GetData	Access to tree data (getter for Data property)

80.9.2 Property overview

Page	Properties	Access	Description
2073	Data	r	Read-only access to tree data

80.9.3 TUCA_PropltemContextTreeRec.GetData

Synopsis: Access to tree data (getter for Data property)

Declaration: `function GetData : PUCA_PropItemContextTreeNodeRec`

Visibility: public

80.9.4 TUCA_PropltemContextTreeRec.Find

Synopsis: Find data for encoded character

Declaration: `function Find(const AChars: PUInt24; const ACharCount: Integer;
 out ANode: PUCA_PropItemContextTreeNodeRec) : Boolean`

Visibility: public

Description: Find searches the tree for the collation data for the character encoded in AChars (ACharCount). It returns true if the data was found, false if not. A pointer to the collation data is returned in ANode.

80.9.5 TUCA_PropItemContextTreeRec.Data

Synopsis: Read-only access to tree data

Declaration: Property Data : PUCA_PropItemContextTreeNodeRec

Visibility: public

Access: Read

80.10 TUCA_PropItemRec

```
TUCA_PropItemRec = packed record
private
    FLAG_VALID = 0;
    FLAG_CODEPOINT
    = 1;
    FLAG_CONTEXTUAL = 2;
    FLAG_DELETION = 3;
    FLAG_COMPRESS_WEIGHT_1
    = 6;
    FLAG_COMPRESS_WEIGHT_2 = 7;
    function GetCodePoint : UInt24
    ;
public
    WeightLength : Byte;
    ChildCount : Byte;
    Size : Word
    ;
    Flags : Byte;
    function HasCodePoint : Boolean;
    property CodePoint
    : UInt24;
    function IsValid : Boolean;
    procedure GetWeightArray
    (ADest: PUCA_PropWeights);
    function GetSelfOnlySize : Cardinal;
    function GetContextual : Boolean;
    property Contextual : Boolean
    ;
    function GetContext : PUCA_PropItemContextTreeRec;
    function
    IsDeleted : Boolean;
    function IsWeightCompress_1 : Boolean;
    function
    IsWeightCompress_2 : Boolean;
end
```

TUCA_PropItemRec encodes 1 entry from the Unicode Collation data in an encoded form.

80.10.1 Method overview

Page	Method	Description
2075	GetContext	Access to context data
2075	GetContextual	Check if the contextual bit is set in the flags (getter for Contextual)
2074	GetSelfOnlySize	Size of this item data (in bytes).
2074	GetWeightArray	Return an array of weights
2074	HasCodePoint	Check flags whether a codepoint is present.
2075	IsDeleted	Check flags if deleted bit is set
2074	IsValid	Check flags for validity
2075	IsWeightCompress_1	Check whether weight compression flag 1 is set
2075	IsWeightCompress_2	Check whether weight compression flag 2 is set

80.10.2 Property overview

Page	Properties	Access	Description
2075	CodePoint	r	Get the codepoint
2076	Contextual	r	Check if the contextual bit is set in the flags

80.10.3 TUCA_ProplItemRec.HasCodePoint

Synopsis: Check flags whether a codepoint is present.

Declaration: `function HasCodePoint : Boolean`

Visibility: public

80.10.4 TUCA_ProplItemRec.IsValid

Synopsis: Check flags for validity

Declaration: `function IsValid : Boolean`

Visibility: public

80.10.5 TUCA_ProplItemRec.GetWeightArray

Synopsis: Return an array of weights

Declaration: `procedure GetWeightArray (ADest: PUCA_PropWeights)`

Visibility: public

Description: `GetWeightArray` returns an array with the weights in `ADest`. `ADest` must point to enough room for `WeightLength` weights.

80.10.6 TUCA_ProplItemRec.GetSelfOnlySize

Synopsis: Size of this item data (in bytes).

Declaration: `function GetSelfOnlySize : Cardinal`

Visibility: public

Description: Return the size of the item's data and properties.

80.10.7 TUCA_PropltemRec.GetContextual

Synopsis: Check if the contextual bit is set in the flags (getter for Contextual)

Declaration: `function GetContextual : Boolean`

Visibility: public

80.10.8 TUCA_PropltemRec.GetContext

Synopsis: Access to context data

Declaration: `function GetContext : PUCA_PropItemContextTreeRec`

Visibility: public

Description: `GetContext` returns a pointer to the context data. It is `Nil` if the context flag is not set.

80.10.9 TUCA_PropltemRec.IsDeleted

Synopsis: Check flags if deleted bit is set

Declaration: `function IsDeleted : Boolean`

Visibility: public

80.10.10 TUCA_PropltemRec.IsWeightCompress_1

Synopsis: Check whether weight compression flag 1 is set

Declaration: `function IsWeightCompress_1 : Boolean`

Visibility: public

80.10.11 TUCA_PropltemRec.IsWeightCompress_2

Synopsis: Check whether weight compression flag 2 is set

Declaration: `function IsWeightCompress_2 : Boolean`

Visibility: public

80.10.12 TUCA_PropltemRec.CodePoint

Synopsis: Get the codepoint

Declaration: `Property CodePoint : UInt24`

Visibility: public

Access: Read

Description: Access to codepoint if `HasCodePoint` returns true. If `HasCodePoint` returns false, an exception will be raised.

80.10.13 TUCA_PropltemRec.Contextual

Synopsis: Check if the contextual bit is set in the flags

Declaration: Property Contextual : Boolean

Visibility: public

Access: Read

80.11 TUC_Prop

```

TUC_Prop = packed record
private
    function GetCategory : Byte;
    procedure SetCategory(AValue: Byte);
    function GetWhiteSpace : Boolean
    ;
    procedure SetWhiteSpace(AValue: Boolean);
    function GetHangulSyllable
    : Boolean;
    procedure SetHangulSyllable(AValue: Boolean);
    function
    GetNumericValue : Double;
public
    CategoryData : Byte;
    CCC : Byte
    ;
    NumericIndex : Byte;
    SimpleUpperCase : UInt24;
    SimpleLowerCase
    : UInt24;
    DecompositionID : SmallInt;
    property Category : Byte
    ;
    property WhiteSpace : Boolean;
    property HangulSyllable : Boolean
    ;
    property NumericValue : Double;
end

```

TUC_Prop describes the collation characteristics of a unicode character. It is an internal structure which should not be used directly, the actual structure is subject to change.

80.11.1 Property overview

Page	Properties	Access	Description
2077	Category	rw	Get the category
2077	HangulSyllable	rw	Is the character a hangul syllable
2077	NumericValue	r	Numeric value
2077	WhiteSpace	rw	Is the character considered whitespace

80.11.2 TUC_Prop.Category

Synopsis: Get the category

Declaration: `Property Category : Byte`

Visibility: `public`

Access: `Read,Write`

Description: `CategoryData` provides access to the category part of `CategoryData` (encoded).

80.11.3 TUC_Prop.WhiteSpace

Synopsis: Is the character considered whitespace

Declaration: `Property WhiteSpace : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Whitespace` provides easy access to the `Whitespace` part of `CategoryData` (encoded).

80.11.4 TUC_Prop.HangulSyllable

Synopsis: Is the character a hangul syllable

Declaration: `Property HangulSyllable : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Whitespace` provides easy access to the `HangulSyllable` part of `CategoryData` (encoded).

80.11.5 TUC_Prop.NumericValue

Synopsis: Numeric value

Declaration: `Property NumericValue : Double`

Visibility: `public`

Access: `Read`

Description: `NumericValue` uses `numericalindex` to get the numerical value.

80.12 TUInt24Rec

```
TUInt24Rec = packed record
public
    byte2 : Byte;
    byte1 : Byte;
    byte0 : Byte;
    TUInt24Rec.class operator implicit(a: TUInt24Rec
    ) : Cardinal;
```

```

TUInt24Rec.class operator implicit(a: TUInt24Rec)
: LongInt;
TUInt24Rec.class operator implicit(a: TUInt24Rec) :
Word;
TUInt24Rec.class operator implicit(a: TUInt24Rec) : Byte
;
TUInt24Rec.class operator implicit(a: Cardinal) : TUInt24Rec;
TUInt24Rec.class operator equal(a: TUInt24Rec; b: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator equal(a: TUInt24Rec; b: Cardinal
) : Boolean;
TUInt24Rec.class operator equal(a: Cardinal; b: TUInt24Rec
) : Boolean;
TUInt24Rec.class operator equal(a: TUInt24Rec; b: LongInt
) : Boolean;
TUInt24Rec.class operator equal(a: LongInt; b: TUInt24Rec
) : Boolean;
TUInt24Rec.class operator equal(a: TUInt24Rec; b: Word
) : Boolean;
TUInt24Rec.class operator equal(a: Word; b: TUInt24Rec
) : Boolean;
TUInt24Rec.class operator equal(a: TUInt24Rec; b: Byte
) : Boolean;
TUInt24Rec.class operator equal(a: Byte; b: TUInt24Rec
) : Boolean;
TUInt24Rec.class operator notequal(a: TUInt24Rec; b
: TUInt24Rec)
: Boolean;

TUInt24Rec
.class operator notequal(a: TUInt24Rec; b: Cardinal) : Boolean;
TUInt24Rec.class operator notequal(a: Cardinal; b: TUInt24Rec) :
Boolean;
TUInt24Rec.class operator greaterthan(a: TUInt24Rec; b
: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator greaterthan(a: TUInt24Rec; b: Cardinal
)
: Boolean;

TUInt24Rec
.class operator greaterthan(a: Cardinal; b: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator
greaterthanorequal(a: TUInt24Rec;
b: TUInt24Rec) : Boolean;
TUInt24Rec.class operator
greaterthanorequal(a: TUInt24Rec; b: Cardinal)
: Boolean;
TUInt24Rec.class operator
greaterthanorequal(a: Cardinal; b: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator
lessthan(a: TUInt24Rec; b: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator lessthan(a: TUInt24Rec

```

```
; b: Cardinal) : Boolean;
TUInt24Rec.class operator lessthan(a:
Cardinal; b: TUInt24Rec) : Boolean;
TUInt24Rec.class operator lessthanorequal
(a: TUInt24Rec; b: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator lessthanorequal(a
: TUInt24Rec; b: Cardinal)
: Boolean;
TUInt24Rec.class operator lessthanorequal(a: Cardinal
; b: TUInt24Rec)
: Boolean
;
end
```

Unicode data exists mostly of 24-bit data (3 bytes). This type is meant to deal efficiently with this data. it has members to split out the data in bytes, and functions to query the various properties stored in the data.

80.12.1 Method overview

Page	Method	Description
2084	<code>equal(Byte,TUInt24Rec):Boolean</code>	Check whether a <code>TUInt24Rec</code> value equals a byte value.
2083	<code>equal(Cardinal,TUInt24Rec):Boolean</code>	Check whether a <code>TUInt24Rec</code> value equals a cardinal value.
2084	<code>equal(LongInt,TUInt24Rec):Boolean</code>	Check whether a <code>TUInt24Rec</code> value equals a longint value.
2084	<code>equal(TUInt24Rec,Byte):Boolean</code>	Check whether a <code>TUInt24Rec</code> value equals a byte value.
2083	<code>equal(TUInt24Rec,Cardinal):Boolean</code>	Check if cardinal and <code>TUInt24Rec</code> are equal
2083	<code>equal(TUInt24Rec,LongInt):Boolean</code>	Check whether a <code>TUInt24Rec</code> value equals a longint value.
2083	<code>equal(TUInt24Rec,TUInt24Rec):Boolean</code>	Determine equality of 2 <code>TUInt24Rec</code> records
2084	<code>equal(TUInt24Rec,Word):Boolean</code>	Check whether a <code>TUInt24Rec</code> value equals a word value.
2084	<code>equal(Word,TUInt24Rec):Boolean</code>	Check whether a <code>TUInt24Rec</code> value equals a word value.
2085	<code>greaterthan(Cardinal,TUInt24Rec):Boolean</code>	Check whether a cardinal value is greater than a <code>TUInt24Rec</code> value
2086	<code>greaterthanorequal(Cardinal,TUInt24Rec):Boolean</code>	Check whether a cardinal value is greater than or equal to a <code>TUInt24Rec</code> value
2086	<code>greaterthanorequal(TUInt24Rec,Cardinal):Boolean</code>	Check whether a <code>TUInt24Rec</code> value is greater than or equal to a cardinal value
2086	<code>greaterthanorequal(TUInt24Rec,TUInt24Rec):Boolean</code>	Check whether a <code>TUInt24Rec</code> value is greater than or equal to a cardinal value
2085	<code>greaterthan(TUInt24Rec,Cardinal):Boolean</code>	Check whether a <code>TUInt24Rec</code> value is greater than a cardinal value
2085	<code>greaterthan(TUInt24Rec,TUInt24Rec):Boolean</code>	Check whether a <code>TUInt24Rec</code> value is greater than another <code>TUInt24Rec</code> value
2083	<code>implicit(Cardinal):TUInt24Rec</code>	Assign <code>TUInt24Rec</code> from Cardinal
2082	<code>implicit(TUInt24Rec):Byte</code>	Assign <code>TUInt24Rec</code> to byte
2082	<code>implicit(TUInt24Rec):Cardinal</code>	Assign <code>TUInt24Rec</code> to cardinal
2082	<code>implicit(TUInt24Rec):LongInt</code>	Assign <code>TUInt24Rec</code> to longint
2082	<code>implicit(TUInt24Rec):Word</code>	Assign <code>TUInt24Rec</code> to word
2087	<code>lessthan(Cardinal,TUInt24Rec):Boolean</code>	Check whether a cardinal value is less than a <code>TUInt24Rec</code> value
2087	<code>lessthanorequal(Cardinal,TUInt24Rec):Boolean</code>	Check whether a cardinal value is less than or equal to a

80.12.2 TUInt24Rec.implicit(TUInt24Rec):Cardinal

Synopsis: Assign TUInt24Rec to cardinal

Declaration: `TUInt24Rec.class operator implicit(a: TUInt24Rec) : Cardinal`

Visibility: public

Description: Assign to cardinal, byte0 to MSB and so on.

See also: `TUInt24Rec.implicit(TUInt24Rec):LongInt` (2082), `TUInt24Rec.implicit(TUInt24Rec):Word` (2082), `TUInt24Rec.implicit(TUInt24Rec):Byte` (2082), `TUInt24Rec.implicit(Cardinal):TUInt24Rec` (2083), `TUInt24Rec.implicit(Longint):TUInt24Rec` (2079), `TUInt24Rec.implicit(Word):TUInt24Rec` (2079), `TUInt24Rec.implicit(Byte):TUInt24Rec` (2079)

80.12.3 TUInt24Rec.implicit(TUInt24Rec):LongInt

Synopsis: Assign TUInt24Rec to longint

Declaration: `TUInt24Rec.class operator implicit(a: TUInt24Rec) : LongInt`

Visibility: public

Description: Assign to cardinal, byte0 to MSB and so on.

See also: `TUInt24Rec.implicit(TUInt24Rec):Cardinal` (2082), `TUInt24Rec.implicit(TUInt24Rec):Word` (2082), `TUInt24Rec.implicit(TUInt24Rec):Byte` (2082)

80.12.4 TUInt24Rec.implicit(TUInt24Rec):Word

Synopsis: Assign TUInt24Rec to word

Declaration: `TUInt24Rec.class operator implicit(a: TUInt24Rec) : Word`

Visibility: public

Description: Assign to word, byte0 to MSB, byte1 to MSB.

Errors: If the value is too big (>\$FFFF) to be assigned, an overflow error occurs.

See also: `TUInt24Rec.implicit(TUInt24Rec):Cardinal` (2082), `TUInt24Rec.implicit(TUInt24Rec):Longint` (2082), `TUInt24Rec.implicit(TUInt24Rec):Byte` (2082), `TUInt24Rec.implicit(Cardinal):TUInt24Rec` (2083), `TUInt24Rec.implicit(Longint):TUInt24Rec` (2079), `TUInt24Rec.implicit(Word):TUInt24Rec` (2079), `TUInt24Rec.implicit(Byte):TUInt24Rec` (2079)

80.12.5 TUInt24Rec.implicit(TUInt24Rec):Byte

Synopsis: Assign TUInt24Rec to byte

Declaration: `TUInt24Rec.class operator implicit(a: TUInt24Rec) : Byte`

Visibility: public

Description: Assign to byte, byte0 is assigned.

Errors: If the value is too big (>\$FF) to be assigned, an overflow error occurs.

See also: `TUInt24Rec.implicit(TUInt24Rec):Cardinal` (2082), `TUInt24Rec.implicit(TUInt24Rec):Longint` (2082), `TUInt24Rec.implicit(TUInt24Rec):Word` (2082), `TUInt24Rec.implicit(Cardinal):TUInt24Rec` (2083), `TUInt24Rec.implicit(Longint):TUInt24Rec` (2079), `TUInt24Rec.implicit(Word):TUInt24Rec` (2079), `TUInt24Rec.implicit(Byte):TUInt24Rec` (2079)

80.12.6 TUInt24Rec.implicit(Cardinal):TUInt24Rec

Synopsis: Assign TUInt24Rec from Cardinal

Declaration: `TUInt24Rec.class operator implicit(a: Cardinal) : TUInt24Rec`

Visibility: public

Description: Assign from cardinal, byte0 to MSB.

Errors: If the value is too big (>\$FFFFFF) to be assigned, an overflow error occurs.

See also: `TUInt24Rec.implicit(TUInt24Rec):LongInt` (2082), `TUInt24Rec.implicit(TUInt24Rec):Word` (2082), `TUInt24Rec.implicit(TUInt24Rec):Byte` (2082), `TUInt24Rec.implicit(LongInt):TUInt24Rec` (2079), `TUInt24Rec.implicit(Word):TUInt24Rec` (2079), `TUInt24Rec.implicit(Byte):TUInt24Rec` (2079)

80.12.7 TUInt24Rec.equal(TUInt24Rec,TUInt24Rec):Boolean

Synopsis: Determine equality of 2 TUInt24Rec records

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The 2 records are considered equal if the 3 bytes are equal.

80.12.8 TUInt24Rec.equal(TUInt24Rec,Cardinal):Boolean

Synopsis: Check if cardinal and TUInt24Rec are equal

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: Cardinal) : Boolean`

Visibility: public

Description: The cardinal b is considered equal to a if the fourth byte (LSB) is zero, and the first three bytes equal byte0, byte1, and byte2.

80.12.9 TUInt24Rec.equal(Cardinal,TUInt24Rec):Boolean

Synopsis: Check whether a TUInt24Rec value equals a cardinal value.

Declaration: `TUInt24Rec.class operator equal(a: Cardinal; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The cardinal a is considered equal to b if the fourth byte (LSB) is zero, and the first three bytes equal byte0, byte1, and byte2.

80.12.10 TUInt24Rec.equal(TUInt24Rec,LongInt):Boolean

Synopsis: Check whether a TUInt24Rec value equals a longint value.

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: LongInt) : Boolean`

Visibility: public

Description: The longint b is considered equal to a if the fourth byte (LSB) is zero, and the first three bytes equal byte0, byte1, and byte2.

80.12.11 `TUInt24Rec.equal(LongInt,TUInt24Rec):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a longint value.

Declaration: `TUInt24Rec.class operator equal(a: LongInt; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The longint `a` is considered equal to `b` if the fourth byte (LSB) is zero, and the first three bytes equal `byte0`, `byte1`, and `byte2`.

80.12.12 `TUInt24Rec.equal(TUInt24Rec,Word):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a word value.

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: Word) : Boolean`

Visibility: public

Description: The word `b` is considered equal to `a` if its 2 bytes equal `byte0`, `byte1` and `byte2` is zero.

80.12.13 `TUInt24Rec.equal(Word,TUInt24Rec):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a word value.

Declaration: `TUInt24Rec.class operator equal(a: Word; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The word `a` is considered equal to `b` if its 2 bytes equal `byte0`, `byte1` and `byte2` is zero.

80.12.14 `TUInt24Rec.equal(TUInt24Rec,Byte):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a byte value.

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: Byte) : Boolean`

Visibility: public

Description: The byte `b` is considered equal to `a` if it equals `byte0` and `byte1` and `byte1` are zero.

80.12.15 `TUInt24Rec.equal(Byte,TUInt24Rec):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a byte value.

Declaration: `TUInt24Rec.class operator equal(a: Byte; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The byte `b` is considered equal to `a` if it equals `byte0` and `byte1` and `byte1` are zero.

80.12.16 `TUInt24Rec.notequal(TUInt24Rec,TUInt24Rec):Boolean`

Synopsis: Check whether 2 `TUInt24Rec` values differ.

Declaration: `TUInt24Rec.class operator notequal(a: TUInt24Rec; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing `byte0`, `byte1` and `byte2`.

80.12.17 `TUInt24Rec.notequal(TUInt24Rec, Cardinal): Boolean`

Synopsis: Check whether a `TUInt24Rec` value differs from a cardinal value.

Declaration: `TUInt24Rec.class operator notequal(a: TUInt24Rec; b: Cardinal) : Boolean`

Visibility: public

Description: The cardinal `a` is considered not equal to `b` if the fourth byte (LSB) is nonzero, or one of the first three bytes differ from `byte0`, `byte1`, and `byte2`.

80.12.18 `TUInt24Rec.notequal(Cardinal, TUInt24Rec): Boolean`

Synopsis: Check whether a `TUInt24Rec` value differs from a cardinal value.

Declaration: `TUInt24Rec.class operator notequal(a: Cardinal; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The cardinal `a` is considered not equal to `b` if the fourth byte (LSB) is nonzero, or one of the first three bytes differ from `byte0`, `byte1`, and `byte2`.

80.12.19 `TUInt24Rec.greaterthan(TUInt24Rec, TUInt24Rec): Boolean`

Synopsis: Check whether a `TUInt24Rec` value is greater than another `TUInt24Rec` value

Declaration: `TUInt24Rec.class operator greaterthan(a: TUInt24Rec; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 bytes `byte0`, `byte1` and `byte2`

80.12.20 `TUInt24Rec.greaterthan(TUInt24Rec, Cardinal): Boolean`

Synopsis: Check whether a `TUInt24Rec` value is greater than a cardinal value

Declaration: `TUInt24Rec.class operator greaterthan(a: TUInt24Rec; b: Cardinal)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

80.12.21 `TUInt24Rec.greaterthan(Cardinal, TUInt24Rec): Boolean`

Synopsis: Check whether a cardinal value is greater than a `TUInt24Rec` value

Declaration: `TUInt24Rec.class operator greaterthan(a: Cardinal; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

80.12.22 `TUInt24Rec.greaterthanorequal(TUInt24Rec,TUInt24Rec):Boolean`

Synopsis: Check whether a `TUInt24Rec` value is greater than or equal to a cardinal value

Declaration: `TUInt24Rec.class operator greaterthanorequal(a: TUInt24Rec;
b: TUInt24Rec) : Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

80.12.23 `TUInt24Rec.greaterthanorequal(TUInt24Rec,Cardinal):Boolean`

Synopsis: Check whether a `TUInt24Rec` value is greater than or equal to a cardinal value

Declaration: `TUInt24Rec.class operator greaterthanorequal(a: TUInt24Rec; b: Cardinal)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

80.12.24 `TUInt24Rec.greaterthanorequal(Cardinal,TUInt24Rec):Boolean`

Synopsis: Check whether a cardinal value is greater than or equal to a `TUInt24Rec` value

Declaration: `TUInt24Rec.class operator greaterthanorequal(a: Cardinal; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

80.12.25 `TUInt24Rec.less than(TUInt24Rec,TUInt24Rec):Boolean`

Synopsis: Check whether a `TUInt24Rec` value is less than another `TUInt24Rec` value

Declaration: `TUInt24Rec.class operator less than(a: TUInt24Rec; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing the bytes `byte0`, `byte1` and `byte2`.

80.12.26 `TUInt24Rec.less than(TUInt24Rec,Cardinal):Boolean`

Synopsis: Check whether a `TUInt24Rec` value is less than a cardinal value

Declaration: `TUInt24Rec.class operator less than(a: TUInt24Rec; b: Cardinal) : Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

80.12.27 **TUInt24Rec.less-than(Cardinal,TUInt24Rec):Boolean**

Synopsis: Check whether a cardinal value is less than a TUInt24Rec value

Declaration: `TUInt24Rec.class operator less-than(a: Cardinal; b: TUInt24Rec) : Boolean`

Visibility: public

Description: Check whether a cardinal value is less than a TUInt24Rec value

80.12.28 **TUInt24Rec.less-than-or-equal(TUInt24Rec,TUInt24Rec):Boolean**

Synopsis: Check whether a TUInt24Rec value is less than or equal to another TUInt24Rec value

Declaration: `TUInt24Rec.class operator less-than-or-equal(a: TUInt24Rec; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing the bytes `byte0`, `byte1` and `byte2`.

80.12.29 **TUInt24Rec.less-than-or-equal(TUInt24Rec,Cardinal):Boolean**

Synopsis: Check whether a TUInt24Rec value is less than or equal to a cardinal value

Declaration: `TUInt24Rec.class operator less-than-or-equal(a: TUInt24Rec; b: Cardinal)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

80.12.30 **TUInt24Rec.less-than-or-equal(Cardinal,TUInt24Rec):Boolean**

Synopsis: Check whether a cardinal value is less than or equal to a TUInt24Rec value

Declaration: `TUInt24Rec.class operator less-than-or-equal(a: Cardinal; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

Chapter 81

Reference for unit 'unicodeducet'

81.1 Used units

Table 81.1: Used units by unit 'unicodeducet'

Name	Page
System	1339

81.2 Overview

The `unicodeducet` unit registers the root Unicode collation (DUCET). This collation is needed by all other collations, so any collation unit will include this file.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 82

Reference for unit 'Unix'

82.1 Used units

Table 82.1: Used units by unit 'Unix'

Name	Page
BaseUnix	141
System	1339
unixtype	2127

82.2 Constants, types and variables

82.2.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`fs_ext = $137d`

File system type (TStatFS ([2104](#))): (ext) Extended

`fs_ext2 = $ef53`

File system type (TStatFS ([2104](#))): (ext2) Second extended

`fs_iso = $9660`

File system type (TStatFS ([2104](#))): ISO 9660

`fs_minix = $137f`

File system type (TStatFS ([2104](#))): Minix

`fs_minix_30 = $138f`

File system type (TStatFS (2104)): Minix 3.0

`fs_minix_V2 = $2468`

File system type (TStatFS (2104)): Minix V2

`fs_msdos = $4d44`

File system type (TStatFS (2104)): MSDOS (FAT)

`fs_nfs = $6969`

File system type (TStatFS (2104)): NFS

`fs_old_ext2 = $ef51`

File system type (TStatFS (2104)): (ext2) Old second extended

`fs_proc = $9fa0`

File system type (TStatFS (2104)): PROC fs

`fs_xia = $012FD16D`

File system type (TStatFS (2104)): XIA

`IOctl_TCGETS = $5401`

IOCTL call number: get Terminal Control settings

`LOCK_EX = 2`

FpFlock (2113) Exclusive lock

`LOCK_NB = 4`

FpFlock (2113) Non-blocking operation

`LOCK_SH = 1`

FpFlock (2113) Shared lock

`LOCK_UN = 8`

FpFlock (2113) unlock

`MAP_FAILED = baseunix.MAP_FAILED`

Error return value for mmap: mmap operation failed.

`MAP_FIXED = baseunix.MAP_FIXED`

#rtl.baseunix.FpMMap (202) map type: Interpret addr exactly

MAP_PRIVATE = baseunix.MAP_PRIVATE

#rtl.baseunix.FpMMap (202) map type: Changes are private

MAP_SHARED = baseunix.MAP_SHARED

#rtl.baseunix.FpMMap (202) map type: Share changes

MAP_TYPE = baseunix.MAP_TYPE

#rtl.baseunix.FpMMap (202) map type: Bitmask for type of mapping

NAME_MAX = UnixType.NAME_MAX

Maximum filename length.

Open_Accmode = 3

Bitmask to determine access mode in open flags.

Open_Append = 2 shl 9

File open mode: Append to file

Open_Creat = 1 shl 6

File open mode: Create if file does not yet exist.

Open_Direct = 4 shl 12

File open mode: Minimize caching effects

Open_Directory = 2 shl 15

File open mode: File must be directory.

Open_Excl = 2 shl 6

File open mode: Open exclusively

Open_LargeFile = 1 shl 15

File open mode: Open for 64-bit I/O

Open_NDelay = Open_NonBlock

File open mode: Alias for Open_NonBlock (2092)

Open_NoCtty = 4 shl 6

File open mode: No TTY control.

`Open_NoFollow = 4 shl 15`

File open mode: Fail if file is symbolic link.

`Open_NonBlock = 4 shl 9`

File open mode: Open in non-blocking mode

`Open_RdOnly = 0`

File open mode: Read only

`Open_RdWr = 2`

File open mode: Read/Write

`Open_Sync = 1 shl 12`

File open mode: Write to disc at once

`Open_Trunc = 1 shl 9`

File open mode: Truncate file to length 0

`Open_WrOnly = 1`

File open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`PRIO_PGRP = UnixType.PRIO_PGRP`

`#rtl.baseunix.fpGetPriority (196)` option: Get process group priority.

`PRIO_PROCESS = UnixType.PRIO_PROCESS`

`#rtl.baseunix.fpGetPriority (196)` option: Get process priority.

`PRIO_USER = UnixType.PRIO_USER`

`#rtl.baseunix.fpGetPriority (196)` option: Get user priority.

`PROT_EXEC = baseunix.PROT_EXEC`

`#rtl.baseunix.FpMMap (202)` memory access: page can be executed

`PROT_NONE = baseunix.PROT_NONE`

#rtl.baseunix.FpMMap (202) memory access: page can not be accessed

PROT_READ = baseunix.PROT_READ

#rtl.baseunix.FpMMap (202) memory access: page can be read

PROT_WRITE = baseunix.PROT_WRITE

#rtl.baseunix.FpMMap (202) memory access: page can be written

P_IN = 1

Input file descriptor of pipe pair.

P_OUT = 2

Output file descriptor of pipe pair.

SIG_MAXSIG = UnixType.SIG_MAXSIG

Maximum system signal number.

STAT_IFBLK = \$6000

File (#rtl.baseunix.stat (235) record) mode: Block device

STAT_IFCHR = \$2000

File (#rtl.baseunix.stat (235) record) mode: Character device

STAT_IFDIR = \$4000

File (#rtl.baseunix.stat (235) record) mode: Directory

STAT_IFIFO = \$1000

File (#rtl.baseunix.stat (235) record) mode: FIFO

STAT_IFLNK = \$a000

File (#rtl.baseunix.stat (235) record) mode: Link

STAT_IFMT = \$f000

File (#rtl.baseunix.stat (235) record) mode: File type bit mask

STAT_IFREG = \$8000

File (#rtl.baseunix.stat (235) record) mode: Regular file

STAT_IFSOCK = \$c000

File (#rtl.baseunix.stat (235) record) mode: Socket

STAT_IRGRP = STAT_IROTH shl 3

File (#rtl.baseunix.stat (235) record) mode: Group read permission

STAT_IROTH = \$4

File (#rtl.baseunix.stat (235) record) mode: Other read permission

STAT_IRUSR = STAT_IROTH shl 6

File (#rtl.baseunix.stat (235) record) mode: Owner read permission

STAT_IRWXG = STAT_IRWXO shl 3

File (#rtl.baseunix.stat (235) record) mode: Group permission bits mask

STAT_IRWXO = \$7

File (#rtl.baseunix.stat (235) record) mode: Other permission bits mask

STAT_IRWXU = STAT_IRWXO shl 6

File (#rtl.baseunix.stat (235) record) mode: Owner permission bits mask

STAT_ISGID = \$0400

File (#rtl.baseunix.stat (235) record) mode: GID bit set

STAT_ISUID = \$0800

File (#rtl.baseunix.stat (235) record) mode: UID bit set

STAT_ISVTX = \$0200

File (#rtl.baseunix.stat (235) record) mode: Sticky bit set

STAT_IWGRP = STAT_IWOTH shl 3

File (#rtl.baseunix.stat (235) record) mode: Group write permission

STAT_IWOTH = \$2

File (#rtl.baseunix.stat (235) record) mode: Other write permission

STAT_IWUSR = STAT_IWOTH shl 6

File (#rtl.baseunix.stat (235) record) mode: Owner write permission

STAT_IXGRP = STAT_IXOTH shl 3

File (#rtl.baseunix.stat (235) record) mode: Others execute permission

```
STAT_IXOTH = $1
```

File (#rtl.baseunix.stat (235) record) mode: Others execute permission

```
STAT_IXUSR = STAT_IXOTH shl 6
```

File (#rtl.baseunix.stat (235) record) mode: Others execute permission

```
SYS_NMLN = UnixType.SYS_NMLN
```

Max system name length.

```
Wait_Any = - 1
```

#rtl.baseunix.fpWaitPID (231): Wait on any process

```
Wait_Clone = $800000000
```

#rtl.baseunix.fpWaitPID (231): Wait on clone processes only.

```
Wait_MyPGRP = 0
```

#rtl.baseunix.fpWaitPID (231): Wait processes from current process group

```
Wait_NoHang = 1
```

#rtl.baseunix.fpWaitPID (231): Do not wait

```
Wait_UnTraced = 2
```

#rtl.baseunix.fpWaitPID (231): Also report stopped but untraced processes

82.2.2 Types

```
cbool = UnixType.cbool
```

Boolean type

```
cchar = UnixType.cchar
```

Alias for #rtl.UnixType.cchar (2129)

```
cdouble = UnixType.cdouble
```

Double precision real format.

```
cfloat = UnixType.cfloat
```


Floating-point real format

```
cint = UnixType.cint
```

C type: integer (natural size)

```
cint16 = UnixType.cint16
```

C type: 16 bits sized, signed integer.

```
cint32 = UnixType.cint32
```

C type: 32 bits sized, signed integer.

```
cint64 = UnixType.cint64
```

C type: 64 bits sized, signed integer.

```
cint8 = UnixType.cint8
```

C type: 8 bits sized, signed integer.

```
clock_t = UnixType.clock_t
```

Clock ticks type

```
clong = UnixType.clong
```

C type: long signed integer (double sized)

```
clonglong = UnixType.clonglong
```

C type: 64-bit (double long) signed integer.

```
coff_t = UnixType.TOff
```

character offset type.

```
cschar = UnixType.cschar
```

Signed character type

```
cshort = UnixType.cshort
```

C type: short signed integer (half sized)

```
csigned = UnixType.csigned
```

`csigned` is an alias for `cint` (2096).

```
csint = UnixType.csint
```

Signed integer

```
csize_t = UnixType.size_t
```

Character size type.

```
cslong = UnixType.cslong
```

The size is CPU dependent.

```
cslonglong = UnixType.cslonglong
```

cslonglong is an alias for clonglong ([2096](#)).

```
csshort = UnixType.csshort
```

Short signed integer type

```
cuchar = UnixType.cuchar
```

Alias for #rtl.UnixType.cuchar ([2130](#))

```
cuint = UnixType.cuint
```

C type: unsigned integer (natural size)

```
cuint16 = UnixType.cuint16
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = UnixType.cuint32
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = UnixType.cuint64
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = UnixType.cuint8
```

C type: 8 bits sized, unsigned integer.

```
culong = UnixType.culong
```

C type: long unsigned integer (double sized)

```
culonglong = UnixType.culonglong
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = UnixType.cunsigned
```

Alias for `#rtl.unixtype.cunsigned` ([2131](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
mode_t = UnixType.mode_t
```

Inode mode type.

```
nlink_t = UnixType.nlink_t
```

Number of links type.

```
off_t = UnixType.off_t
```

Offset type.

```
pcbool = UnixType.pcbool
```

Pointer to boolean type `cbool` ([2095](#))

```
pcchar = UnixType.pcchar
```

Alias for `#rtl.UnixType.pcchar` ([2132](#))

```
pcdouble = UnixType.pcdouble
```

Pointer to `cdouble` ([166](#)) type.

```
pcfloat = UnixType.pcfloating
```

Pointer to `cfloat` ([166](#)) type.

```
pcint = UnixType.pcint
```

Pointer to `cInt` ([2096](#)) type.

```
pcint16 = UnixType.pcint16
```

Pointer to 16-bit signed integer type

```
pcint32 = UnixType.pcint32
```

Pointer to signed 32-bit integer type

```
pcint64 = UnixType.pcint64
```

Pointer to signed 64-bit integer type

```
pcint8 = UnixType.pcint8
```

Pointer to 8-bits signed integer type

```
pClock = UnixType.pClock
```

Pointer to TClock (2102) type.

```
pclong = UnixType.pclong
```

Pointer to cLong (2096) type.

```
pclonglong = UnixType.pclonglong
```

Pointer to longlong type.

```
pcschar = UnixType.pcschar
```

Pointer to character type cschar (2096).

```
pcshort = UnixType.pcsshort
```

Pointer to cShort (2096) type.

```
pcsigned = UnixType.pcsigned
```

Pointer to signed integer type csigned (2096).

```
pcsint = UnixType.pcsint
```

Pointer to signed integer type csint (2097)

```
pctype_t = UnixType.pctype_t
```

Pointer to character size type pctype_t.

```
pcslong = UnixType.pcslong
```

Pointer to the signed long cslong (2097)

```
pcslonglong = UnixType.pcslonglong
```

Pointer to Signed longlong type cslonglong (2097)

```
pcssshort = UnixType.pcssshort
```

Pointer to short signed integer type csshort (2097)

```
pcuchar = UnixType.pcuchar
```

Alias for #rtl.UnixType.pcuchar (2133)

```
pcuint = UnixType.pcuint
```

Pointer to cUInt (2097) type.

```
pcuint16 = UnixType.pcuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = UnixType.pcuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = UnixType.pcuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = UnixType.pcuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = UnixType.pculong
```

Pointer to cuLong (2097) type.

```
pculonglong = UnixType.pculonglong
```

Unsigned longlong type

```
pcunsigned = UnixType.pcunsigned
```

Alias for #rtl.unixtype.pcunsigned (2134)

```
pcushort = UnixType.pcushort
```

Pointer to cuShort (2098) type.

```
pDev = UnixType.pDev
```

Pointer to TDev (2102) type.

```
pGid = UnixType.pGid
```

Pointer to TGid (2103) type.

```
pid_t = UnixType.pid_t
```

Process ID type.

```
pIno = UnixType.pIno
```

Pointer to TIno (2103) type.

```
pMode = UnixType.pMode
```

Pointer to TMode (2103) type.

```
pnLink = UnixType.pnLink
```

Pointer to TnLink (2103) type.

```
pOff = UnixType.pOff
```

Pointer to TOff (2103) type.

```
pPid = UnixType.pPid
```

Pointer to TPid (2103) type.

```
pSize = UnixType.pSize
```

Pointer to TSize (2104) type.

```
pSize_t = UnixType.pSize_t
```

Pointer to type Size_t.

```
pSocklen = UnixType.pSocklen
```

Pointer to TSockLen (2104) type.

```
psSize = UnixType.psSize
```

Pointer to TsSize (2104) type

```
pstatfs = UnixType.PStatFs
```

Pointer to statfs type

```
pthread_cond_t = UnixType.pthread_cond_t
```

Thread conditional variable type.

```
pthread_mutex_t = UnixType.pthread_mutex_t
```

Thread mutex type.

```
pthread_t = UnixType.pthread_t
```

POSIX thread type.

```
pTime = UnixType.pTime
```

Pointer to TTime (2104) type.

```
ptimespec = UnixType.ptimespec
```

Pointer to timespec (2103) type.

```
ptimeval = UnixType.ptimeval
```

Pointer to timeval (2103) type.

```
ptime_t = UnixType.ptime_t
```

Pointer to time_t (2103) type.

```
pUId = UnixType.pUId
```

Pointer to TUid (2104) type.

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

```
TClock = UnixType.TClock
```

Alias for clock_t (2096) type.

```
TDev = UnixType.TDev
```

Alias for dev_t (2098) type.

```
TFSearchOption = (NoCurrentDirectory, CurrentDirectoryFirst,  
    CurrentDirectoryLast)
```

Table 82.2: Enumeration values for type TFSearchOption

Value	Explanation
CurrentDirectoryFirst	Search the current directory first, before all directories in the search path.
CurrentDirectoryLast	Search the current directory last, after all directories in the search path
NoCurrentDirectory	Do not search the current directory unless it is specified in the search path.

Describes the search strategy used by FSearch ([2115](#))

TGid = UnixType.TGid

Alias for gid_t ([2098](#)) type.

timespec = UnixType.timespec

Short time specification type.

timeval = UnixType.timeval

Time specification type.

time_t = UnixType.time_t

Time span type

TIno = UnixType.TIno

Alias for ino_t ([2098](#)) type.

TIOctlRequest = UnixType.TIOctlRequest

Alias for the TIOctlRequest ([2137](#)) type in unixtypes

TMode = UnixType.TMode

Alias for mode_t ([2098](#)) type.

TnLink = UnixType.TnLink

Alias for nlink_t ([2098](#)) type.

TOff = UnixType.TOff

Alias for off_t ([2098](#)) type.

TPid = UnixType.TPid

Alias for pid_t ([2101](#)) type.

`TSize = UnixType.TSize`

Alias for `size_t` (2102) type

`TSocklen = UnixType.TSocklen`

Alias for `socklen_t` (2102) type.

`TsSize = UnixType.TsSize`

Alias for `ssize_t` (2102) type

`tstatfs = UnixType.TStatFs`

`StatFS` returns in `Info` information about the file system on which the file `Path` resides. `Info` is of type `TStatFS` (2141).

The function returns zero if the call was successful, a nonzero value is returned if the call failed.

`TTime = UnixType.TTime`

Alias for `TTime` (2104) type.

`Ttimespec = UnixType.Ttimespec`

Alias for `TimeSpec` (2103) type.

`TTimeVal = UnixType.TTimeVal`

Alias for `timeval` (2103) type.

`TUId = UnixType.TUId`

Alias for `uid_t` (2104) type.

`uid_t = UnixType.uid_t`

User ID type

82.2.3 Variables

`tzdaylight : Boolean`

Indicates whether daylight savings time is active.

`tzname : Array[Boolean] of PChar`

Timezone name.

82.3 Procedures and functions

82.3.1 AssignPipe

Synopsis: Create a set of pipe file handlers

Declaration: `function AssignPipe(var pipe_in: cint; var pipe_out: cint) : cint`
`function AssignPipe(var pipe_in: text; var pipe_out: text) : cint`
`function AssignPipe(var pipe_in: File; var pipe_out: File) : cint`

Visibility: default

Description: AssignPipe creates a pipe, i.e. two file objects, one for input, one for output. What is written to Pipe_out, can be read from Pipe_in.

This call is overloaded. The in and out pipe can take three forms: an typed or untyped file, a text file or a file descriptor.

If a text file is passed then reading and writing from/to the pipe can be done through the usual `Readln(Pipe_in, ...)` and `Writeln(Pipe_out, ...)` procedures.

The function returns `True` if everything went successfully, `False` otherwise.

Errors: In case the function fails and returns `False`, extended error information is returned by the `FpGetErrno (193)` function:

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

See also: `POpen (2118)`, `#rtl.baseunix.FpMkFifo (202)`

Listing: `./examples/unixex/ex36.pp`

Program Example36;

{ Program to demonstrate the AssignPipe function. }

Uses BaseUnix, Unix;

Var pipi, pipo : Text;
 s : **String**;

begin

```

  Writeln ('Assigning Pipes. ');
  If assignpipe(pipi, pipo) <> 0 then
    Writeln ('Error assigning pipes !', fpgeterrno);
  Writeln ('Writing to pipe, and flushing. ');
  Writeln (pipo, 'This is a textstring '); close(pipo);
  Writeln ('Reading from pipe. ');
  While not eof(pipi) do
    begin
      Readln (pipi, s);
      Writeln ('Read from pipe : ', s);
    end;
  close (pipi);
  writeln ('Closed pipes. ');
  writeln

```

end.

82.3.2 AssignStream

Synopsis: Assign stream for in and output to a program

Declaration:

```
function AssignStream(var StreamIn: text; var Streamout: text;
                    const Prog: ansiString;
                    const args: Array of ansistring) : cint
function AssignStream(var StreamIn: text; var Streamout: text;
                    var streamerr: text; const Prog: ansiString;
                    const args: Array of ansistring) : cint
```

Visibility: default

Description: AssignStream creates a 2 or 3 pipes, i.e. two (or three) file objects, one for input, one for output, (and one for standard error) the other ends of these pipes are connected to standard input and output (and standard error) of Prog. Prog is the path of a program (including path). The options for the program can be specified in Args.

What is written to StreamOut, will go to the standard input of Prog. Whatever is written by Prog to it's standard output can be read from StreamIn. Whatever is written by Prog to it's standard error read from StreamErr, if present.

Reading and writing happens through the usual Readln(StreamIn, ...) and Writeln(StreamOut, ...) procedures.

Remark You should *not* use Reset or Rewrite on a file opened with POpen. This will close the file before re-opening it again, thereby closing the connection with the program.

The function returns the process ID of the spawned process, or -1 in case of error.

Errors: Extended error information is returned by the FpGetErrno (193) function.

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

Other errors include the ones by the fork and exec programs

See also: AssignPipe (2105), POpen (2118)

Listing: ./examples/unixex/ex38.pp

Program Example38;

{ Program to demonstrate the AssignStream function. }

Uses BaseUnix, Unix;

Var Si, So : Text;
 S : String;
 i : longint;

begin
 if not (paramstr(1) = '-son') **then**
 begin
 Writeln ('Calling son');
 Assignstream (Si, So, paramstr(0), ['-son']);
 if fpgeterrno <> 0 **then**
 begin
 writeln ('AssignStream failed !');
 halt(1);
 end;

```

Writeln ('Speaking to son');
For i:=1 to 10 do
begin
  writeln (so,'Hello son !');
  if ioreult<>0 then writeln ('Can''t speak to son...');
end;
For i:=1 to 3 do writeln (so,'Hello chap !');
close (so);
while not eof(si) do
begin
  readln (si,s);
  writeln ('Father: Son said : ',S);
end;
Writeln ('Stopped conversation');
Close (Si);
Writeln ('Put down phone');
end
Else
begin
  Writeln ('This is the son ');
  While not eof (input) do
  begin
    readln (s);
    if pos ('Hello son !',S)<>0 then
      Writeln ('Hello Dad !')
    else
      writeln ('Who are you ?');
    end;
  close (output);
  end
end.

```

82.3.3 FpExecL

Synopsis: Execute process (using argument list, environment)

Declaration: `function FpExecL(const PathName: RawByteString;
const S: Array of RawByteString) : cint`

Visibility: default

Description: `FpExecL` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` must be an absolute pathname. The current process' environment is passed to the program. On success, `FpExecL` does not return.

Errors: Extended error information is returned by the `FpGetErrno` ([193](#)) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: [FpExecve \(187\)](#), [FpExecv \(2110\)](#), [FpExecvp \(2111\)](#), [FpExecl \(2108\)](#), [FpExeclp \(2109\)](#), [FpFork \(190\)](#)

Listing: ./examples/unixex/ex77.pp

Program Example77;

{ Program to demonstrate the FpExecl function. }

Uses Unix, strings;

begin

{ Execute 'ls -l', with current environment. }
{ 'ls' is NOT looked for in PATH environment variable. }
 FpExecl ('/bin/ls', ['-l']);

end.

82.3.4 FpExecLE

Synopsis: Execute process (using argument list, environment)

Declaration: `function FpExecLE(const PathName: RawByteString;
 const S: Array of RawByteString; MyEnv: PPChar) : cint`

Visibility: default

Description: FpExecLE replaces the currently running program with the program, specified in PathName. S is an array of command options. The executable in PathName must be an absolute pathname. The environment in MyEnv is passed to the program. On success, FpExecLE does not return.

Errors: Extended error information is returned by the [FpGetErrno \(193\)](#) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: [FpExecve \(187\)](#), [FpExecv \(2110\)](#), [FpExecvp \(2111\)](#), [FpExecl \(2107\)](#), [FpExeclp \(2109\)](#), [FpFork \(190\)](#)

Listing: ./examples/unixex/ex11.pp

Program Example11;

{ Program to demonstrate the Execl function. }

Uses Unix, strings;

```

begin
  { Execute 'ls -l', with current environment. }
  { 'ls' is NOT looked for in PATH environment variable. }
  { envp is defined in the system unit. }
  Execle ('/bin/ls -l',envp);
end.

```

82.3.5 FpExecLP

Synopsis: Execute process (using argument list, environment; search path)

Declaration: `function FpExecLP(const PathName: RawByteString;
const S: Array of RawByteString) : cint`

Visibility: default

Description: FpExecLP replaces the currently running program with the program, specified in PathName. S is an array of command options. The executable in PathName is searched in the path, if it isn't an absolute filename. The current environment is passed to the program. On success, FpExecLP does not return.

Errors: Extended error information is returned by the FpGetErrno ([193](#)) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: FpExecve ([187](#)), FpExecv ([2110](#)), FpExecvp ([2111](#)), FpExecle ([2108](#)), FpExecl ([2107](#)), FpFork ([190](#))

Listing: ./examples/unixex/ex76.pp

Program Example76;

```
{ Program to demonstrate the FpExeclp function. }
```

Uses Unix, strings;

```

begin
  { Execute 'ls -l', with current environment. }
  { 'ls' is looked for in PATH environment variable. }
  { envp is defined in the system unit. }
  FpExeclp ('ls',[ '-l' ]);
end.

```

82.3.6 FpExecLPE

Synopsis: Execute a program in the path, and pass it an environment

Declaration: `function FpExecLPE(const PathName: RawByteString;
const S: Array of RawByteString; env: PPChar) : cint`

Visibility: default

Description: `FpExecLPE` does the same as `FpExecLP` (2109), but additionally it specifies the environment for the new process in `env`, a pointer to a null-terminated array of null-terminated strings.

Errors: On success, this function does not return.

See also: `FpExecLP` (2109), `FpExecLE` (2108)

82.3.7 FpExecV

Synopsis: Execute process

Declaration: `function FpExecV(const PathName: RawByteString; args: PPChar) : cint`

Visibility: default

Description: `FpExecV` replaces the currently running program with the program, specified in `PathName`. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `FpExecV` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (193) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `FpExecve` (187), `FpExecvp` (2111), `FpExecle` (2108), `FpExecl` (2107), `FpExeclp` (2109), `FpFork` (190)

Listing: `./examples/unixex/ex8.pp`

Program Example8;

{ Program to demonstrate the Execv function. }

Uses Unix, strings;

Const Arg0 : PChar = '/bin/lis';
Arg1 : Pchar = '-l';

Var PP : PPchar;

```

begin
  GetMem (PP,3*SizeOf(Pchar));
  PP[0]:=Arg0;
  PP[1]:=Arg1;
  PP[3]:=Nil;
  { Execute '/bin/l$ -l', with current environment }
  fpExecv ('/bin/l$',pp);
end.

```

82.3.8 FpExecVP

Synopsis: Execute process, search path

Declaration: `function FpExecVP(const PathName: RawByteString; args: PPChar) : cint`

Visibility: default

Description: `FpExecVP` replaces the currently running program with the program, specified in `PathName`. The executable in `path` is searched in the path, if it isn't an absolute filename. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execvp` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (193) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `FpExecve` (187), `FpExecv` (2110), `FpExecl` (2108), `FpExecl` (2107), `FpExeclp` (2109), `FpFork` (190)

Listing: ./examples/unixex/ex79.pp

Program Example79;

{ Program to demonstrate the FpExecVP function. }

Uses Unix, strings;

Const Arg0 : PChar = 'ls';
 Arg1 : PChar = '-l';

Var PP : PPchar;

begin

```

GetMem (PP,3*SizeOf(Pchar));
PP[0]:=Arg0;
PP[1]:=Arg1;
PP[2]:=Nil;
{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
fpExecvp ('ls',pp);
end.

```

82.3.9 FpExecVPE

Synopsis: Execute process, search path using environment

Declaration: `function FpExecVPE(const PathName: RawByteString; args: PPChar;
env: PPChar) : cint`

Visibility: default

Description: FpExecVP replaces the currently running program with the program, specified in PathName. The executable in path is searched in the path, if it isn't an absolute filename. It gives the program the options in args. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The environment in Env is passed to the program. On success, execvp does not return.

Errors: Extended error information is returned by the FpGetErrno (193) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: FpExecve (187), FpExecv (2110), FpExecle (2108), FpExecl (2107), FpExeclp (2109), FpFork (190)

Listing: ./examples/unixex/ex79.pp

Program Example79;

{ Program to demonstrate the FpExecVP function. }

Uses Unix, strings;

Const Arg0 : PChar = 'ls';
Arg1 : PChar = '-l';

Var PP : PPchar;

begin
GetMem (PP,3*SizeOf(Pchar));

```

PP[0]:=Arg0;
PP[1]:=Arg1;
PP[2]:=Nil;
{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
fpExecvp ('ls',pp);
end.

```

82.3.10 fpFlock

Synopsis: Lock a file (advisory lock)

Declaration: `function fpFlock(var T: text; mode: cint) : cint`
`function fpFlock(var F: File; mode: cint) : cint`
`function fpFlock(fd: cint; mode: cint) : cint`

Visibility: default

Description: `FpFlock` implements file locking. it sets or removes a lock on the file `F`. `F` can be of type `Text` or `File`, or it can be a Linux file descriptor (a `longint`) `Mode` can be one of the following constants :

LOCK_SHsets a shared lock.

LOCK_EXsets an exclusive lock.

LOCK_UNunlocks the file.

LOCK_NBThis can be OR-ed together with the other. If this is done the application doesn't block when locking.

The function returns zero if successful, a nonzero return value indicates an error.

Errors: Extended error information is returned by the `FpGetErrno` ([193](#)) function:

See also: `#rtl.baseunix.FpFcntl` ([188](#)), `fpFSync` ([2113](#))

82.3.11 fpfStatFS

Synopsis: Retrieve file system information.

Declaration: `function fpfStatFS(Fd: cint; Info: pstatfs) : cint`

Visibility: default

Description: `fpStatFS` returns in `Info` information about the file system on which the open file descriptor `fd` resides. `Info` is of type `tstatfs`. The function returns 0 if the call was successful, or an error code if the call failed.

Errors: On error, a non-zero error code is returned

See also: `fpStatFS` ([2114](#)), `#rtl.baseunix.fpfStat` ([190](#))

82.3.12 **fpfsync**

Synopsis: Synchronize file's kernel data with disk.

Declaration: `function fpfsync(fd: cint) : cint`

Visibility: default

Description: `fpFSync` synchronizes the kernel data for file `fd` (the cache) with the disk. The call will not return till all file data was written to disk.

If the call was successful, 0 is returned. On failure, a nonzero value is returned.

Errors: Extended error information is returned by the `FpGetErrno` ([193](#)) function:

See also: `FpFLock` ([2113](#))

82.3.13 **fpgettimeofday**

Synopsis: Return kernel time of day in GMT

Declaration: `function fpgettimeofday(tp: ptimeval; tzp: ptimezone) : cint`

Visibility: default

Description: `FpGetTimeOfDay` returns the number of seconds since 00:00, January 1 1970, GMT in a `timeval` record. This time NOT corrected any way, not taking into account timezones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

Errors: None.

82.3.14 **fpStatFS**

Synopsis: Retrieve file system information.

Declaration: `function fpStatFS(Path: PChar; Info: pstatfs) : cint`
`function fpStatFS(Path: ansistring; Info: pstatfs) : cint`

Visibility: default

Description: `fpStatFS` returns in `Info` information about the file system on which the file or path `Path` resides. `Info` is of type `tstatfs`. The function returns 0 if the call was successful, or an error code if the call failed.

Errors: On error, a non-zero error code is returned

See also: `fpFStatFS` ([2113](#)), `#rtl.baseunix.fpStat` ([223](#))

82.3.15 **fpSystem**

Synopsis: Execute and feed command to system shell

Declaration: `function fpSystem(const Command: RawByteString) : cint`

Visibility: default

Description: `FpSystem` invokes the bash shell (`/bin/sh`), and feeds it the command `Command` (using the `-c` option). The function then waits for the command to complete, and then returns the exit status of the command in `wait(3)` format, or 127 if it could not complete the `FpFork` (190) or `FpExecve` (187) calls. To convert the return value of `fpsystem` to the real return value use `WEXITSTATUS()` (232).

Errors: Errors are reported in `(fpget)ErrNo` (193)

See also: `POpen` (2118), `FpFork` (190), `FpExecve` (187)

Listing: `./examples/unixex/ex80.pp`

```

program example56;

uses Unix;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  Writeln ('Output of ls -l *.pp');
  S:=fpSystem('ls -l *.pp');
  Writeln ('Command exited with status : ',S);
end.

```

82.3.16 FSearch

Synopsis: Search for file in search path.

Declaration:

```

function FSearch(const path: RawByteString; dirlist: RawByteString;
  CurrentDirStrategy: TFSearchOption) : RawByteString
function FSearch(const path: RawByteString; dirlist: RawByteString)
  : RawByteString
function FSearch(const path: UnicodeString; dirlist: UnicodeString;
  CurrentDirStrategy: TFSearchOption) : UnicodeString
function FSearch(const path: UnicodeString; dirlist: UnicodeString)
  : UnicodeString

```

Visibility: default

Description: `FSearch` searches in `DirList`, a colon separated list of directories, for a file named `Path`. It then returns a path to the found file.

The `CurrentDirStrategy` determines how the current directory is treated when searching:

NoCurrentDirectory Do not search the current directory unless it is specified in the search path.

CurrentDirectoryFirstSearch the current directory first, before all directories in the search path.

CurrentDirectoryLastSearch the current directory last, after all directories in the search path

It is mainly provided to mimic DOS search path behaviour. Default behaviour is to search the current directory first.

Errors: An empty string if no such file was found.

See also: `#rtl.unixutil.FNMatch` (2143)

Listing: `./examples/unixex/ex46.pp`

Program Example46;

{ Program to demonstrate the FSearch function. }

Uses BaseUnix, Unix, Strings;

begin

WriteLn ('Is is in : ', FSearch ('Is ', **strpas**(fpGetenv('PATH'))));
end.

82.3.17 GetDomainName

Synopsis: Return current domain name

Declaration: `function GetDomainName : string`

Visibility: default

Description: Get the domain name of the machine on which the process is running. An empty string is returned if the domain is not set.

Errors: None.

See also: `GetHostName` ([2116](#))

Listing: ./examples/unixex/ex39.pp

Program Example39;

{ Program to demonstrate the GetDomainName function. }

Uses Unix;

begin

WriteLn ('Domain name of this machine is : ', GetDomainName);
end.

82.3.18 GetHostName

Synopsis: Return host name

Declaration: `function GetHostName : string`

Visibility: default

Description: Get the hostname of the machine on which the process is running. An empty string is returned if hostname is not set.

Errors: None.

See also: `GetDomainName` ([2116](#))

Listing: ./examples/unixex/ex40.pp

Program Example40;

{ Program to demonstrate the GetHostName function. }

Uses unix;

begin

WriteLn ('Name of this machine is : ',GetHostName);
end.

82.3.19 GetLocalTimezone

Synopsis: Return local timezone information

Declaration: `procedure GetLocalTimezone(timer: cint; var leap_correct: cint;
 var leap_hit: cint)
 procedure GetLocalTimezone(timer: cint)`

Visibility: default

Description: `GetLocalTimezone` returns the local timezone information. It also initializes the `TZSeconds` variable, which is used to correct the epoch time to local time.

There should never be any need to call this function directly. It is called by the initialization routines of the Linux unit.

See also: `GetTimezoneFile` (2117), `ReadTimezoneFile` (2119)

82.3.20 GetTimezoneFile

Synopsis: Return name of timezone information file

Declaration: `function GetTimezoneFile : string`

Visibility: default

Description: `GetTimezoneFile` returns the location of the current timezone file. The location of file is determined as follows:

- 1.If `/etc/timezone` exists, it is read, and the contents of this file is returned. This should work on Debian systems.
- 2.If `/usr/lib/zoneinfo/localtime` exists, then it is returned. (this file is a symlink to the timezone file on SuSE systems)
- 3.If `/etc/localtime` exists, then it is returned. (this file is a symlink to the timezone file on RedHat systems)

Errors: If no file was found, an empty string is returned.

See also: `ReadTimezoneFile` (2119)

82.3.21 PClose

Synopsis: Close file opened with POpen (2118)

Declaration: `function PClose(var F: File) : cint`
`function PClose(var F: text) : cint`

Visibility: default

Description: PClose closes a file opened with POpen (2118). It waits for the command to complete, and then returns the exit status of the command.

For an example, see POpen (2118)

Errors: Extended error information is returned by the FpGetErrno (193) function.

See also: POpen (2118)

82.3.22 POpen

Synopsis: Pipe file to standard input/output of program

Declaration: `function POpen(var F: text; const Prog: RawByteString; rw: Char) : cint`
`function POpen(var F: File; const Prog: RawByteString; rw: Char) : cint`
`function POpen(var F: text; const Prog: UnicodeString; rw: Char) : cint`
`function POpen(var F: File; const Prog: UnicodeString; rw: Char) : cint`

Visibility: default

Description: POpen runs the command specified in Prog, and redirects the standard in or output of the command to the other end of the pipe F. The parameter rw indicates the direction of the pipe. If it is set to 'W', then F can be used to write data, which will then be read by the command from stdin. If it is set to 'R', then the standard output of the command can be read from F. F should be reset or rewritten prior to using it. F can be of type Text or File. A file opened with POpen can be closed with Close, but also with PClose (2117). The result is the same, but PClose returns the exit status of the command Prog.

Errors: Extended error information is returned by the FpGetErrno (193) function. Errors are essentially those of the Execve, Dup and AssignPipe commands.

See also: AssignPipe (2105), PClose (2117)

Listing: ./examples/unixex/ex37.pp

Program Example37;

{ Program to demonstrate the Popen function. }

uses BaseUnix, Unix;

var f : text;
i : longint;

begin

writeln ('Creating a shell script to which echoes its arguments');
 writeln ('and input back to stdout');
 assign (f, 'test21a');
 rewrite (f);
 writeln (f, '#!/bin/sh');

```

writeln (f, 'echo this is the child speaking.... ');
writeln (f, 'echo got arguments \*$*\ ');
writeln (f, 'cat');
writeln (f, 'exit 2');
writeln (f);
close (f);
fpchmod ('test21a', &755);
popen (f, './test21a arg1 arg2 ', 'W');
if fpgeterrno <> 0 then
    writeln ('error from POpen : errno : ', fpgeterrno);
for i:=1 to 10 do
    writeln (f, 'This is written to the pipe, and should appear on stdout. ');
Flush(f);
Writeln ('The script exited with status : ', PClose (f));
writeln;
writeln ('Press <return> to remove shell script. ');
readln;
assign (f, 'test21a ');
erase (f)
end.

```

82.3.23 ReadTimezoneFile

Synopsis: Read the timezone file and initialize time routines

Declaration: `procedure ReadTimezoneFile(fn: string)`

Visibility: default

Description: `ReadTimezoneFile` reads the timezone file `fn` and initializes the local time routines based on the information found there.

There should be no need to call this function. The initialization routines of the linux unit call this routine at unit startup.

Errors: None.

See also: `GetTimezoneFile` ([2117](#)), `GetLocalTimezone` ([2117](#))

82.3.24 ReReadLocalTime

Synopsis: Re-Read the local time files.

Declaration: `procedure ReReadLocalTime`

Visibility: default

Description: `ReReadLocalTime` can be used to re-initialize the local timezone information.

To speed up conversion of epoch (UTC) time to local time, the timezone information is loaded only once, at program startup. Calling this routine re-reads the timezone information using current timezone settings.

The `EpochToLocal` ([2144](#)) function uses timezone information to transform epoch time to local time. This timezone information does not change while the application is running: in particular, on DST transitions or when the timezone files change, the time returned by local time routines will be wrong.

See also: `Date` ([1673](#)), `Time` ([1777](#)), `Now` ([1742](#)), `EpochToLocal` ([2144](#))

82.3.25 SeekDir

Synopsis: Seek to position in directory

Declaration: `procedure SeekDir(p: pDir; loc: clong)`

Visibility: default

Description: `SeekDir` sets the directory pointer to the `loc`-th entry in the directory structure pointed to by `p`.

For an example, see `#rtl.baseunix.fpOpenDir` (207).

Errors: Extended error information is returned by the `FpGetErrno` (193) function:

See also: `#rtl.baseunix.fpCloseDir` (184), `#rtl.baseunix.fpReadDir` (211), `#rtl.baseunix.fpOpenDir` (207), `TellDir` (2120)

82.3.26 TellDir

Synopsis: Return current location in a directory

Declaration: `function TellDir(p: pDir) : TOff`

Visibility: default

Description: `TellDir` returns the current location in the directory structure pointed to by `p`. It returns -1 on failure.

For an example, see `#rtl.baseunix.fpOpenDir` (207).

See also: `#rtl.baseunix.fpCloseDir` (184), `#rtl.baseunix.fpReadDir` (211), `#rtl.baseunix.fpOpenDir` (207), `SeekDir` (2119)

82.3.27 WaitProcess

Synopsis: Wait for process to terminate.

Declaration: `function WaitProcess(Pid: cint) : cint`

Visibility: default

Description: `WaitProcess` waits for process `PID` to exit. `WaitProcess` is equivalent to the `#rtl.baseunix.FpWaitPID` (231) call:

```
FpWaitPid(PID, @result, 0)
```

Handles of Signal interrupts (`errno=EINTR`), and returns the Exitcode of Process `PID` (≥ 0) or - Status if it was terminated

Errors: None.

See also: `#rtl.baseunix.FpWaitPID` (231), `#rtl.baseunix.WTERMSIG` (233), `#rtl.baseunix.WSTOPSIG` (233), `#rtl.baseunix.WIFEXITED` (232), `WIFSTOPPED` (2120), `#rtl.baseunix.WIFSIGNALED` (233), `W_EXITCODE` (2121), `W_STOPCODE` (2121), `#rtl.baseunix.WEXITSTATUS` (232)

82.3.28 WIFSTOPPED

Synopsis: Check whether the process is currently stopped.

Declaration: `function WIFSTOPPED (Status: Integer) : Boolean`

Visibility: default

Description: `WIFSTOPPED` checks `Status` and returns `true` if the process is currently stopped. This is only possible if `WUNTRACED` was specified in the options of `FpWaitPID` (231).

See also: `#rtl.baseunix.FpWaitPID` (231), `WaitProcess` (2120), `#rtl.baseunix.WTERMSIG` (233), `#rtl.baseunix.WSTOPSIG` (233), `#rtl.baseunix.WIFEXITED` (232), `#rtl.baseunix.WIFSIGNALED` (233), `W_EXITCODE` (2121), `W_STOPCODE` (2121), `#rtl.baseunix.WEXITSTATUS` (232)

82.3.29 W_EXITCODE

Synopsis: Construct an exit status based on an return code and signal.

Declaration: `function W_EXITCODE (ReturnCode: Integer; Signal: Integer) : Integer`

Visibility: default

Description: `W_EXITCODE` combines `ReturnCode` and `Signal` to a status code fit for `WaitPid`.

See also: `#rtl.baseunix.FpWaitPID` (231), `WaitProcess` (2120), `#rtl.baseunix.WTERMSIG` (233), `#rtl.baseunix.WSTOPSIG` (233), `#rtl.baseunix.WIFEXITED` (232), `WIFSTOPPED` (2120), `#rtl.baseunix.WIFSIGNALED` (233), `W_EXITCODE` (2121), `W_STOPCODE` (2121), `#rtl.baseunix.WEXITSTATUS` (232)

82.3.30 W_STOPCODE

Synopsis: Construct an exit status based on a signal.

Declaration: `function W_STOPCODE (Signal: Integer) : Integer`

Visibility: default

Description: `W_STOPCODE` constructs an exit status based on `Signal`, which will cause `WIFSIGNALED` (233) to return `True`

See also: `#rtl.baseunix.FpWaitPID` (231), `WaitProcess` (2120), `#rtl.baseunix.WTERMSIG` (233), `#rtl.baseunix.WSTOPSIG` (233), `#rtl.baseunix.WIFEXITED` (232), `WIFSTOPPED` (2120), `#rtl.baseunix.WIFSIGNALED` (233), `W_EXITCODE` (2121), `#rtl.baseunix.WEXITSTATUS` (232)

Chapter 83

Reference for unit 'unixcp'

83.1 Used units

Table 83.1: Used units by unit 'unixcp'

Name	Page
BaseUnix	141
System	1339

83.2 Overview

The `unixcp` unit provides routines to handle mapping of code page names to numerical values as used in `libiconv`. The `GetCodepageByName` ([2125](#)) function is the main function for this. The `GetCodepageData` ([2126](#)) can be used to map a code page number to a name. These function can be used for instance to map code page information in environment variables to code page numbers used in string encodings. The supported code page names are the ones commonly in use in `libiconv`.

This unit is used for example in unit `cwstring` ([587](#)).

83.3 Constants, types and variables

83.3.1 Constants

```
UnixCpMap : Array[-1..UnixCpMapLimit] of TUnixCpData = ((cp: 0; name
: 'UTF-8'), (cp: 37; name: 'IBM037'), (cp: 37; name: 'IBM-037'),
(cp: 154; name: 'CP154'), (cp: 154; name: 'CYRILLIC-ASIAN'), (cp:
154; name: 'PT154'), (cp: 154; name: 'PTCP154'), (cp: 154; name:
'CSPTCP154'), (cp: 437; name: '437'), (cp: 437; name: 'CP437'),
(cp: 437; name: 'IBM-437'), (cp: 437; name: 'CSPC8CODEPAGE437'),
(cp: 437; name: 'IBM437'), (cp: 500; name: 'IBM500'), (cp: 500; name
: 'IBM-500'), (cp: 708; name: 'ASMO-708'), (cp: 720; name: 'DOS-720'
), (cp: 737; name: 'CP737'), (cp: 737; name: 'ibm737'), (cp: 775;
name: 'CP775'), (cp: 775; name: 'IBM775'), (cp: 775; name: 'CSPC775BALTIC'
), (cp: 775; name: 'ibm775'), (cp: 850; name: '850'), (cp: 850; name
: 'CP850'), (cp: 850; name: 'IBM850'), (cp: 850; name: 'CSPC850MULTILINGUAL'
```

```

), (cp: 850; name: 'ibm850'), (cp: 852; name: '852'), (cp: 852; name
: 'CP852'), (cp: 852; name: 'IBM852'), (cp: 852; name: 'CSPCP852'
), (cp: 852; name: 'ibm852'), (cp: 853; name: 'CP853'), (cp: 855;
name: '855'), (cp: 855; name: 'CP855'), (cp: 855; name: 'IBM855'
), (cp: 855; name: 'CSIBM855'), (cp: 855; name: 'IBM855'), (cp: 857
; name: '857'), (cp: 857; name: 'CP857'), (cp: 857; name: 'IBM857'
), (cp: 857; name: 'CSIBM857'), (cp: 857; name: 'ibm857'), (cp: 858
; name: 'CP858'), (cp: 858; name: 'IBM00858'), (cp: 860; name: '860'
), (cp: 860; name: 'CP860'), (cp: 860; name: 'IBM860'), (cp: 860;
name: 'CSIBM860'), (cp: 860; name: 'IBM860'), (cp: 861; name: '861'
), (cp: 861; name: 'CP-IS'), (cp: 861; name: 'CP861'), (cp: 861; name
: 'IBM861'), (cp: 861; name: 'CSIBM861'), (cp: 861; name: 'ibm861'
), (cp: 862; name: '862'), (cp: 862; name: 'CP862'), (cp: 862; name
: 'IBM862'), (cp: 862; name: 'CSPC862LATINHEBREW'), (cp: 862; name
: 'DOS-862'), (cp: 863; name: '863'), (cp: 863; name: 'CP863'), (cp
: 863; name: 'CSIBM863'), (cp: 863; name: 'IBM863'), (cp: 864; name
: 'CP864'), (cp: 864; name: 'CSIBM864'), (cp: 864; name: 'IBM864'
), (cp: 865; name: '865'), (cp: 865; name: 'IBM-865'), (cp: 865; name
: 'CP865'), (cp: 865; name: 'CSIBM865'), (cp: 865; name: 'IBM865'
), (cp: 866; name: '866'), (cp: 866; name: 'CP866'), (cp: 866; name
: 'IBM866'), (cp: 866; name: 'CSIBM866'), (cp: 866; name: 'cp866'
), (cp: 869; name: '869'), (cp: 869; name: 'IBM-869'), (cp: 869; name
: 'CP-GR'), (cp: 869; name: 'CP869'), (cp: 869; name: 'IBM869'),
(cp: 869; name: 'CSIBM869'), (cp: 869; name: 'ibm869'), (cp: 870;
name: 'IBM870'), (cp: 874; name: 'CP874'), (cp: 874; name: 'WINDOWS-874'
), (cp: 874; name: 'windows-874'), (cp: 875; name: 'cp875'), (cp:
932; name: 'CP932'), (cp: 932; name: 'IBM-943'), (cp: 932; name:
'MS932'), (cp: 932; name: 'SHIFFT_JIS'), (cp: 932; name: 'SHIFFT_JIS-MS'
), (cp: 932; name: 'SJIS'), (cp: 932; name: 'SJIS-MS'), (cp: 932;
name: 'SJIS-OPEN'), (cp: 932; name: 'SJIS-WIN'), (cp: 932; name:
'WINDOWS-31J'), (cp: 932; name: 'WINDOWS-932'), (cp: 932; name: 'CSWINDOWS31J'
), (cp: 932; name: 'shift_jis'), (cp: 932; name: 'shift-jis'), (cp
: 936; name: 'CP936'), (cp: 936; name: 'GBK'), (cp: 936; name: 'MS936'
), (cp: 936; name: 'WINDOWS-936'), (cp: 936; name: 'gb2312'), (cp
: 949; name: 'CP949'), (cp: 949; name: 'UHC'), (cp: 949; name: 'EUC-KR'
), (cp: 949; name: 'ks_c_5601-1987'), (cp: 950; name: 'CP950'), (cp
: 950; name: 'BIG5'), (cp: 950; name: 'big5'), (cp: 1026; name: 'IBM1026'
), (cp: 1047; name: 'IBM01047'), (cp: 1125; name: 'CP1125'), (cp:
1125; name: 'IBM-1125'), (cp: 1133; name: 'CP1133'), (cp: 1133; name
: 'IBM-1133'), (cp: 1133; name: 'IBM-CP1133'), (cp: 1140; name: 'IBM01140'
), (cp: 1141; name: 'IBM01141'), (cp: 1142; name: 'IBM01142'), (cp
: 1143; name: 'IBM01143'), (cp: 1144; name: 'IBM01144'), (cp: 1145
; name: 'IBM01145'), (cp: 1146; name: 'IBM01146'), (cp: 1147; name
: 'IBM01147'), (cp: 1148; name: 'IBM01148'), (cp: 1149; name: 'IBM01149'
), (cp: 1200; name: 'UTF-16LE'), (cp: 1200; name: 'UTF16LE'), (cp
: 1200; name: 'UCS-2LE'), (cp: 1200; name: 'CP1200'), (cp: 1200; name
: 'UTF16'), (cp: 1200; name: 'UTF-16'), (cp: 1200; name: 'UCS-2')
, (cp: 1201; name: 'UTF-16BE'), (cp: 1201; name: 'UTF16BE'), (cp:
1201; name: 'UCS-2BE'), (cp: 1201; name: 'unicodeFFFE'), (cp: 1201
; name: 'CP1201'), (cp: 1250; name: 'CP1250'), (cp: 1250; name: 'MS-EE'
), (cp: 1250; name: 'WINDOWS-1250'), (cp: 1250; name: 'windows-1250'
), (cp: 1251; name: 'CP1251'), (cp: 1251; name: 'MS-CYRL'), (cp: 1251
; name: 'WINDOWS-1251'), (cp: 1251; name: 'windows-1251'), (cp: 1252
; name: 'CP1252'), (cp: 1252; name: 'MS-ANSI'), (cp: 1252; name: 'WINDOWS-1252'

```

```

), (cp: 1252; name: 'windows-1252'), (cp: 1253; name: 'CP1253'),
(cp: 1253; name: 'MS-GREEK'), (cp: 1253; name: 'WINDOWS-1253'), (cp
: 1253; name: 'windows-1253'), (cp: 1254; name: 'CP1254'), (cp: 1254
; name: 'MS-TURK'), (cp: 1254; name: 'WINDOWS-1254'), (cp: 1254; name
: 'windows-1254'), (cp: 1255; name: 'CP1255'), (cp: 1255; name: 'MS-HEBR'
), (cp: 1255; name: 'WINDOWS-1255'), (cp: 1255; name: 'windows-1255'
), (cp: 1256; name: 'CP1256'), (cp: 1256; name: 'MS-ARAB'), (cp: 1256
; name: 'WINDOWS-1256'), (cp: 1256; name: 'windows-1256'), (cp: 1257
; name: 'CP1257'), (cp: 1257; name: 'WINBALTRIM'), (cp: 1257; name
: 'WINDOWS-1257'), (cp: 1257; name: 'windows-1257'), (cp: 1258; name
: 'CP1258'), (cp: 1258; name: 'WINDOWS-1258'), (cp: 1258; name: 'windows-1258'
), (cp: 1361; name: 'CP1361'), (cp: 1361; name: 'JOHAB'), (cp: 1361
; name: 'Johab'), (cp: 10000; name: 'macintosh'), (cp: 10001; name
: 'x-mac-japanese'), (cp: 10002; name: 'x-mac-chinesetrad'), (cp:
10003; name: 'x-mac-korean'), (cp: 10004; name: 'x-mac-arabic'),
(cp: 10005; name: 'x-mac-hebrew'), (cp: 10006; name: 'x-mac-greek'
), (cp: 10007; name: 'x-mac-cyrillic'), (cp: 10008; name: 'x-mac-chinesesimp'
), (cp: 10010; name: 'x-mac-romanian'), (cp: 10017; name: 'x-mac-ukrainian'
), (cp: 10021; name: 'x-mac-thai'), (cp: 10029; name: 'x-mac-ce')
, (cp: 10079; name: 'x-mac-icelandic'), (cp: 10081; name: 'x-mac-turkish'
), (cp: 10082; name: 'x-mac-croatian'), (cp: 12000; name: 'UTF-32LE'
), (cp: 12000; name: 'CP12000'), (cp: 12000; name: 'UTF32LE'), (cp
: 12000; name: 'UTF32'), (cp: 12000; name: 'UTF-32'), (cp: 12001;
name: 'UTF-32BE'), (cp: 12001; name: 'CP12001'), (cp: 12001; name
: 'UTF32BE'), (cp: 20000; name: 'x-Chinese_CNS'), (cp: 20001; name
: 'x-cp20001'), (cp: 20002; name: 'x_Chinese-Eten'), (cp: 20003; name
: 'x-cp20003'), (cp: 20004; name: 'x-cp20004'), (cp: 20005; name:
'x-cp20005'), (cp: 20105; name: 'x-IA5'), (cp: 20106; name: 'x-IA5-German'
), (cp: 20107; name: 'x-IA5-Swedish'), (cp: 20108; name: 'x-IA5-Norwegian'
), (cp: 20127; name: 'US-ASCII'), (cp: 20127; name: 'ASCII'), (cp
: 20127; name: 'ANSI_X3.4-1968'), (cp: 20127; name: 'ANSI_X3.4-1986'
), (cp: 20127; name: 'CP367'), (cp: 20127; name: 'IBM367'), (cp: 20127
; name: 'ISO-IR-6'), (cp: 20127; name: 'ISO646-US'), (cp: 20127; name
: 'ISO_646.IRV:1991'), (cp: 20127; name: 'US'), (cp: 20127; name:
'CSASCII'), (cp: 20127; name: 'us-ascii'), (cp: 20261; name: 'x-cp20261'
), (cp: 20269; name: 'x-cp20269'), (cp: 20273; name: 'IBM273'), (cp
: 20277; name: 'IBM277'), (cp: 20278; name: 'IBM278'), (cp: 20280
; name: 'IBM280'), (cp: 20284; name: 'IBM284'), (cp: 20285; name:
'IBM285'), (cp: 20290; name: 'IBM290'), (cp: 20297; name: 'IBM297'
), (cp: 20420; name: 'IBM420'), (cp: 20423; name: 'IBM423'), (cp:
20424; name: 'IBM424'), (cp: 20833; name: 'x-EBCDIC-KoreanExtended'
), (cp: 20838; name: 'IBM-Thai'), (cp: 20866; name: 'koi8-r'), (cp
: 20871; name: 'IBM871'), (cp: 20880; name: 'IBM880'), (cp: 20905
; name: 'IBM905'), (cp: 20924; name: 'IBM00924'), (cp: 20932; name
: 'EUC-JP'), (cp: 20936; name: 'x-cp20936'), (cp: 20949; name: 'x-cp20949'
), (cp: 21025; name: 'cp1025'), (cp: 21866; name: 'koi8-u'), (cp:
28591; name: 'CP819'), (cp: 28591; name: 'IBM819'), (cp: 28591; name
: 'ISO-8859-1'), (cp: 28591; name: 'ISO-IR-100'), (cp: 28591; name
: 'ISO8859-1'), (cp: 28591; name: 'ISO_8859-1'), (cp: 28591; name
: 'ISO_8859-1:1987'), (cp: 28591; name: 'L1'), (cp: 28591; name: 'LATIN1'
), (cp: 28591; name: 'CSISOLATIN1'), (cp: 28591; name: 'iso-8859-1'
), (cp: 28591; name: 'iso8859-1'), (cp: 28592; name: 'iso-8859-2'
), (cp: 28592; name: 'iso8859-2'), (cp: 28593; name: 'iso-8859-3'
), (cp: 28593; name: 'iso8859-3'), (cp: 28594; name: 'iso-8859-4'

```

```

), (cp: 28594; name: 'iso8859-4'), (cp: 28595; name: 'iso-8859-5'
), (cp: 28595; name: 'iso8859-5'), (cp: 28596; name: 'iso-8859-6'
), (cp: 28596; name: 'iso8859-6'), (cp: 28597; name: 'iso-8859-7'
), (cp: 28597; name: 'iso8859-7'), (cp: 28598; name: 'iso-8859-8'
), (cp: 28598; name: 'iso8859-8'), (cp: 28599; name: 'iso-8859-9'
), (cp: 28599; name: 'iso8859-9'), (cp: 28603; name: 'iso-8859-13'
), (cp: 28603; name: 'iso8859-13'), (cp: 28605; name: 'iso-8859-15'
), (cp: 28605; name: 'iso8859-15'), (cp: 29001; name: 'x-Europa')
, (cp: 38598; name: 'iso-8859-8-i'), (cp: 38598; name: 'iso8859-8-i'
), (cp: 50220; name: 'iso-2022-jp'), (cp: 50221; name: 'ISO-2022-JP'
), (cp: 50221; name: 'CP50221'), (cp: 50221; name: 'ISO-2022-JP-MS'
), (cp: 50221; name: 'ISO2022-JP'), (cp: 50221; name: 'ISO2022-JP-MS'
), (cp: 50221; name: 'MS50221'), (cp: 50221; name: 'WINDOWS-50221'
), (cp: 50221; name: 'csISO2022JP'), (cp: 50222; name: 'iso-2022-jp'
), (cp: 50225; name: 'iso-2022-kr'), (cp: 50225; name: 'iso2022-kr'
), (cp: 50227; name: 'x-cp50227'), (cp: 51932; name: 'EUC-JP'), (cp
: 51932; name: 'CP51932'), (cp: 51932; name: 'MS51932'), (cp: 51932
; name: 'WINDOWS-51932'), (cp: 51932; name: 'euc-jp'), (cp: 51936
; name: 'EUC-CN'), (cp: 51949; name: 'euc-kr'), (cp: 52936; name:
'hz-gb-2312'), (cp: 54936; name: 'GB18030'), (cp: 57002; name: 'x-iscii-de'
), (cp: 57003; name: 'x-iscii-be'), (cp: 57004; name: 'x-iscii-ta'
), (cp: 57005; name: 'x-iscii-te'), (cp: 57006; name: 'x-iscii-as'
), (cp: 57007; name: 'x-iscii-or'), (cp: 57008; name: 'x-iscii-ka'
), (cp: 57009; name: 'x-iscii-ma'), (cp: 57010; name: 'x-iscii-gu'
), (cp: 57011; name: 'x-iscii-pa'), (cp: 65001; name: 'UTF-8'), (cp
: 65001; name: 'CP65001'), (cp: 65001; name: 'UTF8'))

```

UnixCpMap is a fixed structure with codepage number/codepage name pairs. It is used in `GetCodepageData` (2126), `GetSystemCodepage` (2126) and `GetCodepageByName` (2125) to map code page names to numbers and vice versa.

The map is ordered on code page number, and for equal code page numbers, the names are ordered so the most common one is used first.

UnixCpMapLimit = 406 - 83

Number of code pages in map UnixCpMap.

83.3.2 Types

83.4 Procedures and functions

83.4.1 GetCodepageByName

Synopsis: Find code page by name

Declaration: `function GetCodepageByName(cpname: RawByteString) : TSystemCodePage`

Visibility: default

Description: `GetCodepageByName` returns the code page number matching `cpname`. The supported code page names are the ones commonly in use in `libiconv`. Names are searched case-sensitively, with the exception that `'cpN'` is converted to `'CPN'`, where N is a digit.

Errors: If no matching code page name is found, `CP_NONE` is returned.

See also: `UnixCpMap` (2125), `GetSystemCodepage` (2126), `GetCodepageData` (2126)

83.4.2 GetCodepageData

Synopsis: Return index of codepage.

Declaration: `function GetCodepageData(cp: TSystemCodePage) : LongInt`

Visibility: default

Description: `GetCodepageData` returns the index of the first entry in `UnixCpMap` (2125) which matches `cp`. Since the entries are ordered by code page number, this means the entries can be scanned for alternate code names starting at this index.

Errors: If no matching code page is found, -1 is returned.

See also: `UnixCpMap` (2125), `GetSystemCodepage` (2126), `GetCodepageByName` (2125)

83.4.3 GetSystemCodepage

Synopsis: Return the system code page based on the program environment.

Declaration: `function GetSystemCodepage : TSystemCodePage`

Visibility: default

Description: `GetSystemCodepage` returns the system code page, based on one of the environment variables `LC_ALL`, `LC_CTYPE` or `LANG`. The first non-empty variable (in the order mentioned here) is used.

Errors: If none is found, then a system default is used: Linux and Darwin use `CP_UTF8`, others use `CP_ASCII`.

See also: `UnixCpMap` (2125), `GetSystemCodepage` (2126), `GetCodepageByName` (2125)

83.5 TUnixCpData

```
TUnixCpData = record
  cp : Word;
  name : ansistring;
end
```

`TUnixCpData` contains 2 fields necessary to construct a map between code page number (`cp`) and name (`name`).

Chapter 84

Reference for unit 'unixtype'

84.1 Used units

Table 84.1: Used units by unit 'unixtype'

Name	Page
System	1339

84.2 Overview

The `unixtype` unit contains the definitions of basic UNIX types. It was initially implemented by Marco van de Voort.

When porting to a new UNIX platform, this unit should be adapted to the sizes and conventions of the platform to which the compiler is ported.

84.3 Constants, types and variables

84.3.1 Constants

`ARG_MAX` = 131072

Max number of command-line arguments.

`NAME_MAX` = 255

Max length (in bytes) of filename

`PATH_MAX` = 4095

Max length (in bytes) of pathname

`Prio_PGrp` = 1

#rtl.baseunix.fpGetPriority (196) option: Get process group priority.

Prio_Process = 0

#rtl.baseunix.fpGetPriority (196) option: Get process priority.

Prio_User = 2

#rtl.baseunix.fpGetPriority (196) option: Get user priority.

pthread_rwlocksize = 56

Size of pthread_rwlock_t _data structure

SIG_MAXSIG = 128

Maximum signal number.

SYS_NMLN = 65

Max system namelength

_PTHREAD_MUTEX_ADAPTIVE_NP = 3

Mutex options:

_PTHREAD_MUTEX_DEFAULT = _PTHREAD_MUTEX_NORMAL

Mutex options:

_PTHREAD_MUTEX_ERRORCHECK = _PTHREAD_MUTEX_ERRORCHECK_NP

Mutex options:

_PTHREAD_MUTEX_ERRORCHECK_NP = 2

Mutex options: double lock returns an error code.

_PTHREAD_MUTEX_FAST_NP = _PTHREAD_MUTEX_ADAPTIVE_NP

Mutex options: Fast mutex

_PTHREAD_MUTEX_NORMAL = _PTHREAD_MUTEX_TIMED_NP

Mutex options:

_PTHREAD_MUTEX_RECURSIVE = _PTHREAD_MUTEX_RECURSIVE_NP

Mutex options:

_PTHREAD_MUTEX_RECURSIVE_NP = 1

Mutex options: recursive mutex

_PTHREAD_MUTEX_TIMED_NP = 0

Mutex options: ?

84.3.2 Types

`cbool = longbool`

Boolean type

`cchar = cint8`

C type: 8-bit signed integer

`cdouble = Double`

Double precision real format.

`cfloat = single`

Floating-point real format

`cint = cint32`

C type: integer (natural size)

`cint16 = SmallInt`

C type: 16 bits sized, signed integer.

`cint32 = LongInt`

C type: 32 bits sized, signed integer.

`cint64 = Int64`

C type: 64 bits sized, signed integer.

`cint8 = ShortInt`

C type: 8 bits sized, signed integer.

`clock_t = cuint64`

Clock ticks type

`clong = Int64`

C type: long signed integer (double sized)

`clongdouble = extended`

Usually translates to an extended, but is CPU dependent.

`clonglong = cint64`

C type: 64-bit (double long) signed integer.

```
cschar = cint8
```

Signed character type

```
cshort = cint16
```

C type: short signed integer (half sized)

```
csigned = cint
```

csigned is an alias for cint ([2129](#)).

```
csint = cint32
```

Signed integer

```
cslong = Int64
```

The size is CPU dependent.

```
cslonglong = cint64
```

cslonglong is an alias for clonglong ([2130](#)).

```
csshort = cint16
```

Short signed integer type

```
cuchar = cuint8
```

C type: 8-bit unsigned integer

```
cuint = cuint32
```

C type: unsigned integer (natural size)

```
cuint16 = Word
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = LongWord
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = QWord
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = Byte
```

C type: 8 bits sized, unsigned integer.

```
culong = QWord
```

C type: long unsigned integer (double sized)

```
culonglong = uint64
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = uint
```

Alias for #rtl.unixtype.cuint ([2130](#))

```
cushort = uint16
```

C type: short unsigned integer (half sized)

```
dev_t = uint64
```

Device descriptor type.

```
gid_t = uint32
```

Group ID type.

```
ino64_t = uint64
```

ino64_t is an inode type capable of containing 64-bit inodes.

```
ino_t = clong
```

Inode type.

```
ipc_pid_t = cint
```

Process ID

```
kDev_t = ushort
```

Kernel device type

```
mbstate_value_t = record
case Byte of
0: (
  __wch : wint_t;
);
1
  : (
  __wchb : Array[0..3] of Char;
);
end
```

This type should never be used directly. It is part of the `mbstate_t` (2139) type.

`mode_t = cint`

Inode mode type.

`nlink_t = cuint32`

Number of links type.

`off64_t = cint64`

64-bit offset type.

`off_t = cint64`

Offset type.

`pbool = ^cbool`

Pointer to boolean type `cbool` (2129)

`pcchar = ^cchar`

Pointer to `#rtl.UnixType.cchar` (2129)

`pcdouble = ^cdouble`

Pointer to `cdouble` (2129) type.

`pcfloat = ^cfloat`

Pointer to `cfloat` (2129) type.

`pcint = ^cint`

Pointer to `cInt` (2129) type.

`pcint16 = ^cint16`

Pointer to 16-bit signed integer type

`pcint32 = ^cint32`

Pointer to signed 32-bit integer type

`pcint64 = ^cint64`

Pointer to signed 64-bit integer type

`pcint8 = ^cint8`

Pointer to 8-bits signed integer type

```
pClock = ^clock_t
```

Pointer to TClock (2137) type.

```
pclong = ^clong
```

Pointer to cLong (2129) type.

```
pclongdouble = ^clongdouble
```

Pointer to the long double type clongdouble (2129)

```
pclonglong = ^clonglong
```

Pointer to longlong type.

```
pcschar = ^cschar
```

Pointer to character type cschar (2130).

```
pcshort = ^cshort
```

Pointer to cShort (2130) type.

```
pcsigned = ^csigned
```

Pointer to signed integer type csigned (2130).

```
pcsint = ^csint
```

Pointer to signed integer type csint (2130)

```
pcslong = ^cslong
```

Pointer to the signed long cslong (2130)

```
pcslonglong = ^cslonglong
```

Pointer to Signed longlong type cslonglong (2130)

```
pcsshort = ^csshort
```

Pointer to short signed integer type csshort (2130)

```
pcuchar = ^cuchar
```

Pointer to #rtl.UnixType.cuchar (2130)

```
pcuint = ^cuint
```

Pointer to cUInt (2130) type.

```
pcuint16 = ^cuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = ^cuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = ^cuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = ^cuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = ^culong
```

Pointer to cuLong (2131) type.

```
pculonglong = ^culonglong
```

Unsigned longlong type

```
pcunsigned = ^cunsigned
```

Pointer to #rtl.unixtype.cunsigned (2131)

```
pcushort = ^cushort
```

Pointer to cuShort (2131) type.

```
pDev = ^dev_t
```

Pointer to TDev (2137) type.

```
pGid = ^gid_t
```

Pointer to TGid (2137) type.

```
pid_t = cint
```

Process ID type.

```
pIno = ^ino_t
```

Pointer to TIno (2137) type.

```
pIno64 = ^ino64_t
```

Pointer to `ino64_t` (2131)

```
pkDev = ^kDev_t
```

Pointer to `TkDev` (2138) type.

```
pmbstate_t = ^mbstate_t
```

Pointer to `mbstate_t` (2139) type

```
pMode = ^mode_t
```

Pointer to `TMode` (2138) type.

```
pnLink = ^nlink_t
```

Pointer to `TnLink` (2138) type.

```
pOff = ^off_t
```

Pointer to `TOff` (2138) type.

```
pOff64 = ^off64_t
```

Pointer to `off64_t` type

```
pPid = ^pid_t
```

Pointer to `TPid` (2138) type.

```
pSize = ^size_t
```

Pointer to `TSize` (2138) type.

```
psize_t = pSize
```

Pointer to `size_t` (2137) type.

```
pSockLen = ^socklen_t
```

Pointer to `TSockLen` (2138) type.

```
pSSize = ^ssize_t
```

Pointer to `TsSize` (2138) type

```
PStatFS = ^TStatfs
```

Pointer to `TStatFS` (2141) type.

```
pthread_key_t = cuint
```


Thread local storage key (opaque)

```
pthread_mutex_t = record
case Byte of
1: (
  __m_reserved : LongInt
  ;
  __m_count : LongInt;
  __m_owner : pointer;
  __m_kind : LongInt
  ;
  __m_lock : record
    __status : SizeInt;
    __spinlock : LongInt
  ;
  end;
);
end
```

`_pthread_mutex_t` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_rwlock_t = record
case Boolean of
False: (
  _data : Array
    [0..pthread_rwlocksize-1] of Char;
);
True: (
  align : clong;
);
end
```

`pthread_rwlock_t` describes a lock. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_t = culong
```

Thread description record

```
pTime = ^time_t
```

Pointer to TTime (2138) type.

```
ptimespec = ^timespec
```

Pointer to timespec (2141) record.

```
ptimeval = ^timeval
```

Pointer to timeval (2141) record.

`ptime_t = ^time_t`

Pointer to `time_t` (2137) type.

`pUId = ^uid_t`

Pointer to `TUId` (2138) type.

`pwchar_t = ^wchar_t`

Pointer to `wchar_t` (2139) type.

`size_t = uint64`

Size specification type.

`socklen_t = uint32`

Socket address length type.

`ssize_t = int64`

Small size type.

`TClock = clock_t`

Alias for `clock_t` (2129) type.

`TDev = dev_t`

Alias for `dev_t` (2131) type.

`TGid = gid_t`

Alias for `gid_t` (2131) type.

`time_t = int64`

Time span type

`TIno = ino_t`

Alias for `ino_t` (2131) type.

`TIno64 = ino64_t`

Alias for `ino64_t` (2131)

`TIOCtlRequest = culong`

Opaque type used in `FpIOCtl` (197)

TkDev = kDev_t

Alias for kDev_t (2131) type.

TMode = mode_t

Alias for mode_t (2132) type.

TnLink = nlink_t

Alias for nlink_t (2132) type.

TOff = off_t

Alias for off_t (2132) type.

TOff64 = off64_t

Alias for off64_t type.

TPid = pid_t

Alias for pid_t (2134) type.

TSize = size_t

Alias for size_t (2137) type

TSockLen = socklen_t

Alias for socklen_t (2137) type.

TSSize = ssize_t

Alias for ssize_t (2137) type

TTime = time_t

Alias for TTime (2138) type.

TTimeSpec = timespec

Alias for TimeSpec (2141) type.

TTimeVal = timeval

Alias for TimeVal (2141) record.

TUid = uid_t

Alias for uid_t (2139) type.

```
uid_t = cuint32
```

User ID type

```
wchar_t = cint32
```

Wide character type.

```
wint_t = cint32
```

Wide character size type.

84.4 mbstate_t

```
mbstate_t = record
  __count : cint;
  __value : mbstate_value_t;
end
```

This type should never be used directly.

84.5 pthread_attr_t

```
pthread_attr_t = record
  __detachstate : cint;
  __schedpolicy :
  cint;
  __schedparam : sched_param;
  __inheritsched : cint;
  __scope
  : cint;
  __guardsize : size_t;
  __stackaddr_set : cint;
  __stackaddr
  : pointer;
  __stacksize : size_t;
end
```

`pthread_attr_t` describes the thread attributes. It should be considered an opaque record, the names of the fields can change anytime. Use the appropriate functions to set the thread attributes.

84.6 pthread_condattr_t

```
pthread_condattr_t = record
  __dummy : cint;
end
```

`pthread_condattr_t` describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

84.7 pthread_cond_t

```
pthread_cond_t = record
  __c_lock : _pthread_fastlock;
  __c_waiting
  : pointer;
  __padding : Array[0..48-1-sizeof(_pthread_fastlock)
    -sizeof(pointer)-sizeof(clonglong)] of Byte;
  __align : clonglong
;
end
```

`pthread_cond_t` describes a thread conditional variable. It should be considered an opaque record, the names of the fields can change anytime.

84.8 pthread_mutexattr_t

```
pthread_mutexattr_t = record
  __mutexkind : cint;
end
```

`pthread_mutexattr_t` describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

84.9 pthread_rwlockattr_t

```
pthread_rwlockattr_t = record
  __lockkind : cint;
  __pshared : cint
;
end
```

`pthread_rwlockattr_t` describes the attributes of a lock. It should be considered an opaque record, the names of the fields can change anytime.

84.10 sched_param

```
sched_param = record
  __sched_priority : cint;
end
```

Scheduling parameter description record.

84.11 sem_t

```
sem_t = record
```

```

__sem_lock : _pthread_fastlock;
__sem_value : cint
;
__sem_waiting : pointer;
end

```

`sem_t` describes a thread semaphore. It should be considered an opaque record, the names of the fields can change anytime.

84.12 timespec

```

timespec = record
  tv_sec : time_t;
  tv_nsec : clong;
end

```

Record specifying time interval.

84.13 timeval

```

timeval = record
  tv_sec : time_t;
  tv_usec : clong;
end

```

Time specification type.

84.14 TStatfs

```

TStatfs = record
  fstype : clong;
  bsize : clong;
  blocks : culong
;
  bfree : culong;
  bavail : culong;
  files : culong;
  ffree
  : culong;
  fsid : Array[0..1] of cint;
  namelen : clong;
  frsize
  : clong;
  flags : clong;
  spare : Array[0..3] of clong;
end

```

Record describing a file system in the `unix.fpstatfs` ([2127](#)) call.

84.15 `_pthread_fastlock`

```
_pthread_fastlock = record
  __status : clong;
  __spinlock : cint
;
end
```

`_pthread_fastlock` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

Chapter 85

Reference for unit 'unixutil'

85.1 Used units

Table 85.1: Used units by unit 'unixutil'

Name	Page
System	1339

85.2 Overview

The UnixUtil unit contains some of the routines that were present in the old Linux unit, but which do not really belong in the UNIX ([2089](#)) or baseunix ([141](#)) units.

Most of the functions described here have cross-platform counterparts in the SysUtils ([1615](#)) unit. It is therefore recommended to use that unit.

85.3 Constants, types and variables

85.3.1 Variables

`Tzseconds : LongInt`

Seconds west of GMT

85.4 Procedures and functions

85.4.1 ArrayStringToPPchar

Synopsis: Concert an array of string to an array of null-terminated strings

Declaration: `function ArrayStringToPPchar(const S: Array of RawByteString;
reserveentries: LongInt) : PPChar`

Visibility: default

Description: `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array `S`. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

Errors: If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([2145](#))

85.4.2 EpochToLocal

Synopsis: Convert epoch time to local time

Declaration: `procedure EpochToLocal(epoch: LongInt; var year: Word; var month: Word; var day: Word; var hour: Word; var minute: Word; var second: Word)`

Visibility: default

Description: Converts the epoch time (=Number of seconds since 00:00:00, January 1, 1970, corrected for your time zone) to local date and time.

This function takes into account the timezone settings of your system.

Errors: None

See also: `LocalToEpoch` ([2145](#))

Listing: `./examples/unutilx/ex3.pp`

Program Example3;

{ Program to demonstrate the EpochToLocal function. }

Uses BaseUnix, Unix, UnixUtil;

Var Year, month, day, hour, minute, seconds : Word;

begin

EpochToLocal (FPTIME, Year, month, day, hour, minute, seconds);

Writeln ('Current date : ', Day:2, '/', Month:2, '/', Year:4);

Writeln ('Current time : ', Hour:2, ':', minute:2, ':', seconds:2);

end.

85.4.3 GregorianToJulian

Synopsis: Converts a Gregorian date to a Julian date

Declaration: `function GregorianToJulian(Year: LongInt; Month: LongInt; Day: LongInt) : LongInt`

Visibility: default

Description: `GregorianToJulian` takes a Gregorian date and converts it to a Julian day.

Errors: None.

See also: `JulianToGregorian` ([2145](#))

85.4.4 JulianToGregorian

Synopsis: Converts a Julian date to a Gregorian date

Declaration: `procedure JulianToGregorian(JulianDN: LongInt; var Year: Word;
var Month: Word; var Day: Word)`

Visibility: default

Description: `JulianToGregorian` takes a Julian day and converts it to a Gregorian date. (Start of the Julian Date count is from 0 at 12 noon 1 JAN -4712 (4713 BC),)

Errors: None.

See also: `GregorianToJulian` ([2144](#))

85.4.5 LocalToEpoch

Synopsis: Convert local time to epoch (UNIX) time

Declaration: `function LocalToEpoch(year: Word; month: Word; day: Word; hour: Word;
minute: Word; second: Word) : LongInt`

Visibility: default

Description: Converts the Local time to epoch time (=Number of seconds since 00:00:00, January 1, 1970).

Errors: None

See also: `EpochToLocal` ([2144](#))

Listing: `./examples/unutilx/ex4.pp`

Program `Example4;`

{ Program to demonstrate the LocalToEpoch function. }

Uses `UnixUtil;`

Var `year, month, day, hour, minute, second : Word;`

begin

`Write ('Year : '); readln (Year);`

`Write ('Month : '); readln (Month);`

`Write ('Day : '); readln (Day);`

`Write ('Hour : '); readln (Hour);`

`Write ('Minute : '); readln (Minute);`

`Write ('Seonds : '); readln (Second);`

`Write ('This is : ');`

`Write (LocalToEpoch (year, month, day, hour, minute, second));`

`Writeln (' seconds past 00:00 1/1/1980');`

end.

85.4.6 StringToPPChar

Synopsis: Split string in list of null-terminated strings

```
Declaration: function StringToPPChar(S: PChar; ReserveEntries: Integer) : PPChar
            function StringToPPChar(var S: RawByteString; ReserveEntries: Integer)
                : PPChar
```

Visibility: default

Description: `StringToPPChar` splits the string `S` in words, replacing any whitespace with zero characters. It returns a pointer to an array of `pchars` that point to the first letters of the words in `S`. This array is terminated by a `Nil` pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of `PChar`; The caller is responsible for freeing this memory.

This function can be called to create arguments for the various `Exec` calls.

Errors: None.

See also: [ArrayStringToPPchar \(2143\)](#), [#rtl.baseunix.FpExecve \(187\)](#)

Listing: ./examples/unutilex/ex70.pp

Program Example70 ;

```
{ Program to demonstrate the StringToPPchar function. }
```

Uses UnixUtil;

```
Var S : String;  
    P : PPChar;  
    I : longint;
```

```
begin
    // remark whitespace at end.
    S:='This is a string with words. ';
    P:=StringToPPChar(S,0);
    I:=0;
    While P[I]<>Nil do
        begin
            WriteLn( 'Word ',I, ' : ',P[I]);
            Inc(I);
        end;
    FreeMem(P, i * SizeOf(Pchar));
end.
```

Chapter 86

Reference for unit 'Variants'

86.1 Used units

Table 86.1: Used units by unit 'Variants'

Name	Page
rtlconsts	??
sysconst	??
System	1339
sysutils	1615
TypeInfo	1970

86.2 Overview

The compiler has built-in support for variants, and for many operations, variants can be used without thinking about it. The system unit has built-in support for some of the basic operations on a variant, as well as some compiler helper routines. However, some operations and definitions are implemented in the `Variants` unit so as not to burden the system unit with routines that may not always be needed.

There is a basic set of variants that are defined by the Windows OS, these are supported by the compiler and the routines in the `Variants` unit. Additional variant types can be registered using the `TCustomVariantType` ([2176](#)) type.

The variants unit also registers a handler for setting published properties (using RTTI) using variant-typed values. Nothing needs to be done for this except including the variants unit in your program.

86.3 Constants, types and variables

86.3.1 Constants

```
CFirstUserType = CMinVarType + CIncVarType
```

`CFirstUserType` is the first allocated value for `vType` when registering a variant type by the RTL, when instantiating a `TCustomVariantType` ([2176](#)) to register a variant type. It is better not to specify a custom variant type value, but let the system allocate a custom variant type.

```
CIncVarType = $000F
```

`CIncVarType` specifies the width of the gap after `CMinVarType` (2148). No user types are registered between `CMinVarType` and `CMinVarType+CIncVarType`.

```
CMaxNumberOfCustomVarTypes = $0EFF
```

`CMaxNumberOfCustomVarTypes` is the amount of custom variant types that can be registered. The range of the variant type indicator (`vType`) only allows a limited amount of variants. This constant is the maximum amount.

```
CMaxVarType = CMinVarType + CMaxNumberOfCustomVarTypes
```

`CMaxVarType` is the maximum allowed value for `vType` when registering a variant type, instantiating a `TCustomVariantType` (2176) to register a variant type. It is better not to specify a value, but let the system allocate a custom variant type.

```
CMinVarType = $0100
```

`CMinVarType` is the first allowed value for `vType` when registering a variant type by the OS, instantiating a `TCustomVariantType` (2176) to register a variant type. It is better not to specify a custom variant type value, but let the system allocate a custom variant type.

```
FloatVarTypes = [varSingle, varDouble, varCurrency, varDecimal]
```

`FloatlVarTypes` is used in `VarIsFloat` (2165) to decide which variant types are considered ordinals.

```
OrdinalVarTypes = [varSmallInt, varInteger, varBoolean, varShortInt,
    , varByte, varWord, varLongWord, varInt64, varQWord]
```

`OrdinalVarTypes` is used in `VarIsOrdinal` (2165) to decide which variant types are considered ordinals.

```
VarOpAsText : Array[TVarOp] of string = ('+', '-', '*', '/', 'div'
    , 'mod', 'shl', 'shr', 'and', 'or', 'xor', '', '-', 'not', '=', '<>'
    , '<', '<=', '>', '>=', '**')
```

`VarOpAsText` is an array with the names of the various variant operations.

86.3.2 Types

```
TAnyProc = procedure(var V: tvardata)
```

`TAnyProc` is the type for the `ClearAnyProc` (2150), `ChangeAnyProc` (2150) and `RefAnyProx` (2147) callbacks. It accepts a reference to a variant record. The operation to be performed depends on the callback.

```
TBooleanToStringRule = (bsrAsIs, bsrLower, bsrUpper)
```

Table 86.2: Enumeration values for type TBooleanToStringRule

Value	Explanation
bsrAsIs	Leave casing as is
bsrLower	Convert to lowercase
bsrUpper	Convert to uppercase

TBooleanToStringRule describes how boolean values are converted to string values. It is defined for Delphi compatibility, but is not used in the FPC runtime.

TCustomVariantTypeClass = class of TCustomVariantType

TCustomVariantTypeClass is the class type of TCustomVariantType.

TNullCompareRule = (ncrError, ncrStrict, ncrLoose)

Table 86.3: Enumeration values for type TNullCompareRule

Value	Explanation
ncrError	Raise an error when one of the values is Null.
ncrLoose	Attempt to compare anyway
ncrStrict	Act as if the comparison is false

TNullCompareRule is the type for the NullEqualityRule (2151) and NullMagnitudeRule (2151) variables. It can have the following values:

ncrError Raise an error when one of the values is Null.

ncrStrict Act as if the comparison is false

ncrLoose Attempt to compare anyway

TVarCompareResult = (crLessThan, crEqual, crGreaterThan)

Table 86.4: Enumeration values for type TVarCompareResult

Value	Explanation
crEqual	Both values are equal
crGreaterThan	The first value is greater than the second value
crLessThan	The first value is less than the second value

TVarCompareResult is used when comparing 2 custom variant values in TCustomVariantType.Compare (2180). The following values exist:

crLessThan The first value is less than the second value

crGreaterThan The first value is greater than the second value

crEqual Both values are equal

```
TVarDataArray = Array of tvardata
```

TVarDataArray is a helper type for instance used in IVarInvokeable.DoFunction (2175) to represent the arguments passed to a function.

```
TVarDispProc = procedure(Dest: PVariant; const Source: Variant;
    CallDesc: pcalldesc; Params: Pointer)
```

TVarDispProc is the type for the VarDispProc (2152) callback handler. It accepts a destination variant (Dest) for a result. Source is the variant on which the operation was invoked, CallDesc Describes the arguments to the call and Params points to the parameters provided in the call.

```
TVariantRelationship = (vrEqual, vrLessThan, vrGreaterThan, vrNotEqual
    )
```

Table 86.5: Enumeration values for type TVariantRelationship

Value	Explanation
vrEqual	Are the 2 variants equal
vrGreaterThan	Is the first variant (strictly) greater than the second
vrLessThan	Is the first variant (strictly) less than the second
vrNotEqual	Are the 2 variants unequal

TVariantRelationship is used by VarCompareValue (2161) to indicate the type of comparison operation it must perform. It has the following values:

vrEqual Are the 2 variants equal

vrLessThan Is the first variant (strictly) less than the second

vrGreaterThan Is the first variant (strictly) greater than the second

vrEqual Are the 2 variants equal

vrEqual Are the 2 variants equal

86.3.3 Variables

```
ChangeAnyProc : TAnyProc
```

ChangeAnyProc is currently not used in the Variants unit.

```
ClearAnyProc : TAnyProc
```

ClearAnyProc is called when the system needs to clear a variant of type varAny. it must clear the variant.

```
EmptyParam : OleVariant
```

`EmptyParam` is an initialized variant with type `varError` and error value `VAR_PARAMNOTFOUND`. In difference with `Null` (2154) and `UnAssigned` (2155) it is a variable. You should take care never to write to it.

```
InvalidCustomVariantType : TCustomVariantType
```

`InvalidCustomVariantType` can be set to a `TCustomVariantType` (2176) instance to indicate an unknown type. By default it is set to `Pointer(-1)`.

```
NullAsStringValue : string = ''
```

`NullAsStringValue` is the value used when converting a `Null` to a string. It is only used when `NullStrictConvert` (2151) is `False`, if `NullStrictConvert` (2151) is `True`, the value of `NullAsStringValue` is ignored.

```
NullEqualityRule : TNullCompareRule = ncrLoose
```

`NullEqualityRule` is checked when the system needs to compare the equality of variants with `Null` values (operations `opCmpEq`, `opCmpNe`). Check `TNullCompareRule` (2149) for a list of allowed values. The default is `ncrLoose`.

For determining the order (less than, greater than etc.) see `NullMagnitudeRule` (2151).

```
NullMagnitudeRule : TNullCompareRule = ncrLoose
```

`NullEqualityRule` is checked when the system needs to determine the ordering of variants with `Null` values (operations like `opCmpGe`, `opCmpLe`). Check `TNullCompareRule` (2149) for a list of allowed values. The default is `ncrLoose`.

For determining equality (`opCmpEq`, `opCmpNe`) of `Null` values, see `NullEqualityRule` (2151).

```
NullStrictConvert : Boolean = True
```

`NullStrictConvert` determines what to do when typecasting a `Null` value to another type: If it is `True` then an exception will be raised using `VarCastError` (2160). If it is `False` then a sensible default is used: 0 or some variation on 0 based on the type of the variant. For string values the `NullAsStringValue` (2151) is used.

```
OleVariantInt64AsDouble : Boolean = False
```

`OleVariantInt64AsDouble` describes what to do when a `Int64` value must be converted to a `OleVariant` value. When `True` the `Int64` variant is cast to a double. When `False`, it remains an `int64` value.

```
PackVarCreation : Boolean = True
```

`PackVarCreation` determines what to do when a variant array is created for elements with an integer type (`varSmallint`, `varByte` and the like). A value of `False` means the array will contain `varInteger` elements. This can result in better memory alignment. When `PackVarCreation` is `True` then the smallest possible size is selected for the elements.

```
RefAnyProc : TAnyProc
```


`RefAnyProc` is called when the system needs to obtain a reference to a variant of type `varAny`. it must replace the variant with a reference to the variant.

`VarDispProc : TVarDispProc`

`VarDispProc` is the handler invoked when a dispatch invoke is handled on a variant of type `varDispatch`, `varAny` or `varUnknown`.

86.4 Procedures and functions

86.4.1 DynArrayFromVariant

Synopsis: Convert a variant to a dynamic arrayt

Declaration: `procedure DynArrayFromVariant(var DynArray: Pointer; const V: Variant; TypeInfo: Pointer)`

Visibility: default

Description: `DynArrayFromVariant` transforms a variant array to a dynamic array. It uses `TypeInfo` to calculate the length, element type and dimension of the array.

The opposite transformation can be performed with `DynArrayToVariant` (2152).

See also: `VarArrayCreateError` (2156), `VarArrayCreate` (2155), `VarArrayOf` (2158), `DynArrayToVariant` (2152)

86.4.2 DynArrayToVariant

Synopsis: Convert a Dynamic Array To a Variant

Declaration: `procedure DynArrayToVariant(var V: Variant; const DynArray: Pointer; TypeInfo: Pointer)`

Visibility: default

Description: `DynArrayToVariant` converts the dynamic array `DynArray` to a variant array `V`. It uses the type information in `TypeInfo` to calculate the number of dimensions, array lengths and type of the element. The dynamic array can only contain basic types.

If there is no data, an empty variant will be returned.

The opposite transformation can be performed with `DynArrayFromVariant` (2152).

See also: `VarArrayCreateError` (2156), `VarArrayCreate` (2155), `VarArrayOf` (2158), `DynArrayFromVariant` (2152)

86.4.3 FindCustomVariantType

Synopsis: Find a custom variant class on vartype

Declaration: `function FindCustomVariantType(const aVarType: tvartype; out CustomVariantType: TCustomVariantType) : Boolean; Overload`
`function FindCustomVariantType(const TypeName: string; out CustomVariantType: TCustomVariantType) : Boolean; Overload`

Visibility: default

Description: `FindCustomVariantType` searches the registry of known `TCustomVariantType` (2176) classes and returns the instance registered for the variant type `aVarType` or the class name `TypeNames` in `CustomVariantType` if found.

It returns `True` if it found a matching definition, or `False` otherwise.

See also: `TCustomVariantType` (2176)

86.4.4 FindVarData

Synopsis: Return a pointer to variant data

Declaration: `function FindVarData(const V: Variant) : pvardata`

Visibility: default

Description: `FindVarData` returns a pointer to the argument `V` if it is not a reference. If it is a reference, then the reference pointer is returned.

86.4.5 GetPropValue

Synopsis: Return a property value as a variant

Declaration: `function GetPropValue(Instance: TObject; PropInfo: PPropInfo;
PreferStrings: Boolean) : Variant; Overload`

Visibility: default

Description: `GetPropValue` returns the value of the property described by `PropInfo` from the `Instance`. The property value is returned as a variant type.

when `PreferStrings` is true, the implementation will tend to cast to a string-valued variant when a conversion must be done.

This function is used as the value for the `TypeInfo` (2147) unit's `OnGetPropValue` (2147) callback. This callback is automatically initialized with the function when the variants unit is used.

See also: `TypeInfo` (2147), `TypeInfo.OnGetPropValue` (2147), `SetPropValue` (2154)

86.4.6 GetVariantProp

Synopsis: Get variant valued property

Declaration: `function GetVariantProp(Instance: TObject; PropInfo: PPropInfo)
: Variant
function GetVariantProp(Instance: TObject; const PropName: string)
: Variant`

Visibility: default

Description: `GetVariantProp` returns the value of the variant-types property described by `PropInfo` or `PropName` from the `Instance`.

This function is used as the value for the `TypeInfo` (2147) unit's `OnGetVariantProp` (2147) callback. This callback is automatically initialized with the function when the variants unit is used.

See also: `TypeInfo` (2147), `TypeInfo.OnGetVariantProp` (2147), `SetVariantProp` (2155), `GetPropValue` (2153)

86.4.7 HandleConversionException

Synopsis: Convert an exception to a variant exception

Declaration: `procedure HandleConversionException(const ASourceType: tvartype;
const ADestType: tvartype)`

Visibility: default

Description: `HandleConversionException` converts a RTL exception (`EConvertError` (2147) or `ERangeError` (2147) or `EOverflow` (2147)) to an appropriate variant error (`varCastError` (2160) and `varOverflowError` (2167)). Other exceptions are re-raised. If a source and destination type `ASourceType` and `ADestType` are specified they are included in the error message.

See also: `EConvertError` (2147), `ERangeError` (2147), `varCastError` (2160), `varOverflowError` (2167), `EOverflow` (2147)

86.4.8 Null

Synopsis: Return a null variant

Declaration: `function Null : Variant`

Visibility: default

Description: `UnAssigned` returns a Null variant (`type = varNull`). It can be used to test for equality with a Null variant.

See also: `UnAssigned` (2155), `EmptyParam` (2151)

86.4.9 SetClearVarToEmptyParam

Synopsis: Create an error variant with value `VAR_PARAMNOTFOUND`

Declaration: `procedure SetClearVarToEmptyParam(var V: tvardata)`

Visibility: default

Description: `SetClearVarToEmptyParam` clears the variant `Vvar` and sets its type to `varError` and value to `VAR_PARAMNOTFOUND`. `VarIsEmptyParam(SetClearVarToEmptyParam(V))` will return `True`.

Errors: None.

See also: `VarIsEmptyParam` (2164), `VarIsError` (2164)

86.4.10 SetPropValue

Synopsis: Set a property value as a variant

Declaration: `procedure SetPropValue(Instance: TObject; PropInfo: PPropInfo;
const Value: Variant); Overload`

Visibility: default

Description: `SetPropValue` sets the value of the property described by `PropInfo` from the `Instance`. The property value is set from the variant-typed value `Value`.

This function is used as the value for the `TypeInfo` (2147) unit's `OnSetPropValue` (2147) callback. This callback is automatically initialized with the function when the variants unit is used.

See also: `TypeInfo` (2147), `TypeInfo.OnSetPropValue` (2147), `GetPropValue` (2153)

86.4.11 SetVariantProp

Synopsis: Set variant valued property

Declaration:

```
procedure SetVariantProp(Instance: TObject; const PropName: string;
                        const Value: Variant)
procedure SetVariantProp(Instance: TObject; PropInfo: PPropInfo;
                        const Value: Variant)
```

Visibility: default

Description: `SetVariantProp` sets the value of the variant-types property described by `PropInfo` or `PropName` from the `Instance` to `Value`.

This function is used as the value for the `TypeInfo` (2147) unit's `OnSetVariantProp` (2147) callback. This callback is automatically initialized with the function when the variants unit is used.

See also: `TypeInfo` (2147), `TypeInfo.OnSetVariantProp` (2147), `GetVariantProp` (2153), `GetPropValue` (2153)

86.4.12 Unassigned

Synopsis: Return an unassigned variant

Declaration:

```
function Unassigned : Variant
```

Visibility: default

Description: `UnAssigned` returns an unassigned variant (`type = varEmpty`). It can be used to test for equality with an empty variant.

See also: `Null` (2154), `EmptyParam` (2151)

86.4.13 VarArrayAsPSafeArray

Synopsis: Return internal array of variant value

Declaration:

```
function VarArrayAsPSafeArray(const A: Variant) : pvararray
```

Visibility: default

Description: `VarArrayAsPSafeArray` returns the internal array of the variant `A` if it is a variant array. If not, an exception is raised.

Errors: if the variant `A` is not an array, an `EVariantInvalidArgError` (2172) exception is raised.

See also: `VarIsArray` (2163), `EVariantInvalidArgError` (2172)

86.4.14 VarArrayCreate

Synopsis: Create a variant array

Declaration:

```
function VarArrayCreate(const Bounds: Array of SizeInt;
                        aVarType: tvartype) : Variant
function VarArrayCreate(const Bounds: pvararrayboundarray;
                        Dims: SizeInt; aVarType: tvartype) : Variant
```

Visibility: default

Description: `VarArrayCreate` creates a (optionally multidimensional) array with upper,lower bounds specified in `Bounds`. The number of bounds (in case of a single array) must be even: 2 bounds for every dimension of the array are required. All elements of the array are of the same type. The following examples create a one-dimensional array with 10 elements

```
VarArrayCreate([0,9],varInteger);
VarArrayCreate([1,10],varInteger);
```

The first array is 0-based, the second is 1-based. The following creates a 2-dimensional array:

```
VarArrayCreate([0,9,0,1],varInteger);
VarArrayCreate([1,10,1,2],varInteger);
```

The first array is 0-based, the second is 1-based. Each array consists of an array of 2 elements.

The array can also be specified as a pointer to array of `system.tvararraybound` (2147) records, and a number of dimensions. The above 1-dimensional arrays can be specified as:

```
var
  B : tvararraybound;
begin
  b.elementcount:=10;
  B.lowbound:=0;
  VarArrayCreate(@B,1,varInteger);
  b.elementcount:=10;
  B.lowbound:=1;
  VarArrayCreate(@B,1,varInteger);
```

Errors: If an uneven amount of bounds is specified or the operating system failed to create the array, an exception is raised using `VarArrayCreateError` (2156)

See also: `VarArrayCreateError` (2156), `VarArrayOf` (2158)

86.4.15 VarArrayCreateError

Synopsis: Raise an `EVariantArrayCreateError` error

Declaration: `procedure VarArrayCreateError`

Visibility: default

Description: `VarArrayCreateError` raises an `EVariantArrayCreateError` (2171) exception with a standard error message.

See also: `EVariantArrayCreateError` (2171), `VarOverflowError` (2167), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162), `VarBadIndexError` (2159), `VarArrayLockedError` (2157)

86.4.16 VarArrayDimCount

Synopsis: Return the number of dimensions of the array.

Declaration: `function VarArrayDimCount(const A: Variant) : LongInt`

Visibility: default

Description: `VarArrayDimCount` returns the number of dimensions of the array `A`. If `A` is not an array, zero is returned.

Errors: None.

See also: `VarArrayCreate` (2155), `VarArrayLowBound` (2158), `VarArrayHighBound` (2157)

86.4.17 `VarArrayHighBound`

Synopsis: Return lower bound of an array

Declaration: `function VarArrayHighBound(const A: Variant; Dim: LongInt) : LongInt`

Visibility: default

Description: `VarArrayHighBound` returns the high bound (max index) of dimension `Dim` of array `A`. The dimension `Dim` is 1-based.

Errors: If the dimension is out of range, or `A` is not a variant array, an exception will be raised.

See also: `VarArrayCreate` (2155), `VarArrayDimCount` (2156), `VarArrayLowBound` (2158)

86.4.18 `VarArrayLock`

Synopsis: get a pointer to data of a variant array

Declaration: `function VarArrayLock(const A: Variant) : Pointer`

Visibility: default

Description: `VarArrayLock` returns a pointer to the data of an array-typed variant `A` and locks the variant. The pointer can then be used to manipulate the data of the array and be sure that the data is not modified by another process or thread. While the data is not released using `VarArrayUnlock` (2158) the variant cannot be changed or released, it is therefor imperative that the variant is again released. Memory leaks will be the result if this is not done.

See also: `VarArrayUnlock` (2158)

86.4.19 `VarArrayLockedError`

Synopsis: Raise an `EVariantArrayLockedError` error

Declaration: `procedure VarArrayLockedError`

Visibility: default

Description: `VarArrayLockedError` raises an `EVariantArrayLockedError` (2171) exception with a standard error message.

See also: `EVariantArrayLockedError` (2171), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162), `VarBadIndexError` (2159)

86.4.20 VarArrayLowBound

Synopsis: Return lower bound of an array

Declaration: `function VarArrayLowBound(const A: Variant; Dim: LongInt) : LongInt`

Visibility: default

Description: `VarArrayLowBound` returns the lower bound (min index) of dimension `Dim` of array `A`. The dimension `Dim` is 1-based.

Errors: If the dimension is out of range, or `A` is not a variant array, an exception will be raised.

See also: `VarArrayCreate` (2155), `VarArrayDimCount` (2156), `VarArrayHighBound` (2157)

86.4.21 VarArrayOf

Synopsis: Create a variants array of a series of values

Declaration: `function VarArrayOf(const Values: Array of Variant) : Variant`

Visibility: default

Description: `VarArrayOf` creates a variant array with elements of type `varVariant`. The array has as many values as there are elements in `Values` and the element values are copied from `Values`.

Errors: If the array cannot be created, an `EVariantError` exception may be raised.

See also: `VarArrayCreateError` (2156), `VarArrayCreate` (2155), `DynArrayToVariant` (2152)

86.4.22 VarArrayRef

Synopsis: Get a reference to a variant array

Declaration: `function VarArrayRef(const A: Variant) : Variant`

Visibility: default

Description: `VarArrayRef` returns a reference to the variant array `A`.

Errors: An exception will be raised if the variant `A` is not an array.

See also: `VarArrayLock` (2157), `VarArrayUnlock` (2158), `VarIsArray` (2163)

86.4.23 VarArrayUnlock

Synopsis: Release data captured by `VarArrayLock`

Declaration: `procedure VarArrayUnlock(const A: Variant)`

Visibility: default

Description: `VarArrayUnlock` unlocks the variant array `A` that was previously locked using `VarArrayLock` (2157).

See also: `VarArrayLock` (2157)

86.4.24 VarAsError

Synopsis: Create an error-typed variant

Declaration: `function VarAsError (AResult: HRESULT) : Variant`

Visibility: default

Description: `VarAsError` creates an error-typed variant with value `aResult`.

Errors: None.

See also: `SetClearVarToEmptyParam` (2154), `VarIsError` (2164)

86.4.25 VarAsType

Synopsis: Attempt to cast a variant to another type

Declaration: `function VarAsType (const V: Variant; aVarType: tvartype) : Variant`

Visibility: default

Description: `VarAsType` attempts to cast the variant `V` to a new variant of type `aVarType` and returns the new variant.

Errors: If the requested type cast is not supported or possible, an `EVariantTypeCastError` (2174) exception may be raised.

See also: `EVariantTypeCastError` (2174), `VarIsType` (2166), `VarAsType` (2159)

86.4.26 VarBadIndexError

Synopsis: Raise an `EVariantBadIndexError` error

Declaration: `procedure VarBadIndexError`

Visibility: default

Description: `VarBadIndexError` raises an `EVariantBadIndexError` (2172) exception with a standard error message.

See also: `EVariantBadIndexError` (2172), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162), `VarArrayLockedError` (2157)

86.4.27 VarBadTypeError

Synopsis: Raise an `EVariantBadVarTypeError` error

Declaration: `procedure VarBadTypeError`

Visibility: default

Description: `VarBadTypeError` raises an `EVariantBadVarTypeError` (2172) exception.

See also: `EVariantBadVarTypeError` (2172), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162)

86.4.28 VarCastError

Synopsis: Raise a variant type cast error `EVariantTypeCastError`

Declaration: `procedure VarCastError`
`procedure VarCastError(const ASourceType: tvartype;`
`const ADestType: tvartype)`

Visibility: default

Description: `VarCastError` raises an `EVariantTypeCastError` (2174) exception. If the source and destination types are specified, then a description of the types is included in the error message.

See also: `EVariantTypeCastError` (2174), `VarCastErrorOle` (2160)

86.4.29 VarCastErrorOle

Synopsis: Raise a variant type cast error `EVariantTypeCastError`

Declaration: `procedure VarCastErrorOle(const ASourceType: tvartype)`

Visibility: default

Description: `VarCastError` raises an `EVariantTypeCastError` (2174) exception. a description of the source type (`aSourceType`) is included in the error message.

See also: `EVariantTypeCastError` (2174), `VarCastError` (2160)

86.4.30 VarCheckEmpty

Synopsis: Raise exception if a variant is empty.

Declaration: `procedure VarCheckEmpty(const V: Variant)`

Visibility: default

Description: `VarCheckEmpty` will raise an `EVariantError` (2147) exception if the variant `V` is empty (it uses `VarIsEmpty` (2164) to check this.)

Errors: if the variant is empty an `EVariantError` (2147) exception is raised.

See also: `VarIsEmpty` (2164), `VarType` (2170), `VarIsNull` (2165)

86.4.31 VarClear

Synopsis: Clear the variant value

Declaration: `procedure VarClear(var V: Variant)`
`procedure VarClear(var V: OleVariant)`

Visibility: default

Description: `VarClear` clears the variant, possibly freeing any memory taken by the value

Errors: None.

See also: `SetClearVarToEmptyParam` (2154), `VarIsError` (2164), `VarIsClear` (2163)

86.4.32 VarCompareValue

Synopsis: Compare 2 variant values

Declaration: `function VarCompareValue(const A: Variant; const B: Variant)
: TVariantRelationship`

Visibility: default

Description: `VarCompareValue` compares 2 variants A and B. It returns one of the following values:

vrEqual if the 2 variant values are equal.

vrUnequal if one of the 2 variant is null or empty and the other is not.

vrGreaterThan if $A > B$

vrLessThan if $A < B$

See also: `VarSameValue` ([2167](#))

86.4.33 VarCopyNoInd

Synopsis: Not supported

Declaration: `procedure VarCopyNoInd(var Dest: Variant; const Source: Variant)`

Visibility: default

Description: `VarCopyNoInd` is currently not supported.

Errors: An `EVariantError` exception is always raised.

86.4.34 VarEnsureRange

Synopsis: Make sure the variant is within a specified range.

Declaration: `function VarEnsureRange(const AValue: Variant; const AMin: Variant;
const AMax: Variant) : Variant`

Visibility: default

Description: `VarEnsureRange` checks `AValue` and returns it if it is in the range specified by `AMin`, `AMax`. If it is less than `AMin`, then `AMin` is returned. If it is larger than `AMax`, then `AMax` is returned.

Errors: If the variants are of different types and they cannot be converted, an exception will be raised.

See also: `VarInRange` ([2162](#))

86.4.35 VarFromDateTime

Synopsis: Create variant from `TDateTime` value.

Declaration: `function VarFromDateTime(const DateTime: TDateTime) : Variant`

Visibility: default

Description: `VarFromDateTime` creates a variant with type `varDate` and value `DateTime`.

Errors: None.

See also: `varToDateTime` ([2168](#))

86.4.36 VarInRange

Synopsis: Check if a variant is in a range of values

Declaration: `function VarInRange(const AValue: Variant; const AMin: Variant;
const AMax: Variant) : Boolean`

Visibility: default

Description: `VarInRange` is an auxiliary function which checks whether `AValue` is in the range defined by `AMin` and `AMax`, borders included.

Errors: If the variants are of different types and they cannot be converted, an exception will be raised.

See also: `VarEnsureRange` ([2161](#))

86.4.37 VarInvalidArgError

Synopsis: Raise an `EVariantInvalidArgError` error

Declaration: `procedure VarInvalidArgError
procedure VarInvalidArgError(AType: tvartype)`

Visibility: default

Description: `VarInvalidArgError` raises an `EVariantInvalidArgError` ([2172](#)) exception with a standard error message. If the `AType` argument is specified, a description of the argument type is included in the error message.

See also: `EVariantInvalidArgError` ([2172](#)), `VarInvalidNullOp` ([2162](#)), `VarInvalidOp` ([2162](#)), `VarBadIndexError` ([2159](#)), `VarArrayLockedError` ([2157](#))

86.4.38 VarInvalidNullOp

Synopsis: Raise an `EVariantInvalidOpError` error

Declaration: `procedure VarInvalidNullOp`

Visibility: default

Description: `VarInvalidNullOp` raises an `EVariantInvalidOpError` ([2172](#)) exception including null type description.

See also: `EVariantInvalidOpError` ([2172](#)), `VarInvalidOp` ([2162](#))

86.4.39 VarInvalidOp

Synopsis: Raise a `EVariantInvalidOpError` error

Declaration: `procedure VarInvalidOp
procedure VarInvalidOp(const aLeft: tvartype; const aRight: tvartype;
aOpCode: tvarop)
procedure VarInvalidOp(const aRight: tvartype; aOpCode: tvarop)`

Visibility: default

Description: `VarInvalidOp` raises an `EVariantInvalidOpError` ([2172](#)) exception. when the left and/or right operand types (`aLeft`, `aRight`) and the operation are specified, a description of the operand types and operation is included in the error message.

See also: `EVariantInvalidOpError` ([2172](#)), `VarCastError` ([2160](#))

86.4.40 VarIsArray

Synopsis: Check whether a variant is an array

Declaration: `function VarIsArray(const A: Variant) : Boolean`
`function VarIsArray(const A: Variant; AResolveByRef: Boolean) : Boolean`

Visibility: default

Description: `VarIsArray` returns `True` if `A` is an array. If `AResolveByRef` is `True` (the default) then it will resolve all references first.

Errors: None.

See also: `VarTypeIsValidArrayType` (2170)

86.4.41 VarIsBool

Synopsis: Check if the variant is a boolean

Declaration: `function VarIsBool(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsCustom` returns `True` if the variant `V` is a boolean value.

See also: `VarIsEmpty` (2164), `VarIsNull` (2165), `VarIsCustom` (2164), `VarIsOrdinal` (2165), `VarIsFloat` (2165), `VarIsStr` (2166)

86.4.42 VarIsByRef

Synopsis: Check if the variant is a reference to a value.

Declaration: `function VarIsByRef(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsByRef` checks whether the variant `V` is a reference to a value instead of an actual value. It returns `True` if this is the case, `False` if not.

See also: `VarType` (2170), `VarAsType` (2159), `VarIsType` (2166), `VarIsEmpty` (2164), `VarIsNull` (2165)

86.4.43 VarIsClear

Synopsis: Check if a variant is clear

Declaration: `function VarIsClear(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsClear` returns `True` if the variant `V` is empty, or it is a dispatch type with value `Nil`. For custom types, the decision is left to the custom type.

See also: `VarIsEmpty` (2164), `VarIsNull` (2165), `VarIsNumeric` (2165), `VarIsStr` (2166)

86.4.44 VarIsCustom

Synopsis: Check if the variant is a custom value.

Declaration: `function VarIsCustom(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsCustom` returns `True` if the variant `V` is a custom variant (type is larger than `CFirstUserType` (2147)).

See also: `VarIsEmpty` (2164), `VarIsNull` (2165), `VarIsOrdinal` (2165), `VarIsNumeric` (2165), `VarIsStr` (2166)

86.4.45 VarIsEmpty

Synopsis: Check if the variant is empty

Declaration: `function VarIsEmpty(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsEmpty` checks whether the variant `V` is empty (i.e. the type is `varEmpty`).

See also: `VarType` (2170), `VarAsType` (2159), `VarIsType` (2166), `VarIsEmpty` (2164), `VarCheckEmpty` (2160), `VarIsNull` (2165)

86.4.46 VarIsEmptyParam

Synopsis: Check if the variant is an error value for `VAR_PARAMNOTFOUND`

Declaration: `function VarIsEmptyParam(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsEmptyParam` returns `True` if the variant `V` is an error typed variant with value `VAR_PARAMNOTFOUND`, or `False` otherwise.

See also: `VarIsError` (2164), `SetClearVarToEmptyParam` (2154)

86.4.47 VarIsError

Synopsis: Check if the variant has type `varError`

Declaration: `function VarIsError(const V: Variant; out AResult: HRESULT) : Boolean`
`function VarIsError(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsError` checks `V` and returns `True` if the type is `varError`.

See also: `VarIsNull` (2165), `VarIsEmpty` (2164), `VarIsOrdinal` (2165), `VarIsEmptyParam` (2164)

86.4.48 VarIsFloat

Synopsis: Check if the variant is a floating-point value.

Declaration: `function VarIsFloat(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsCustom` returns `True` if the variant `V` is of one of the ordinal types: `FloatVarTypes` (2148) (`varSingle`, `varDouble`, `varCurrency`).

See also: `VarIsEmpty` (2164), `VarIsNull` (2165), `VarIsCustom` (2164), `VarIsOrdinal` (2165), `VarIsNumeric` (2165), `VarIsStr` (2166)

86.4.49 VarIsNull

Synopsis: Check if a variant is null

Declaration: `function VarIsNull(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsNull` returns `True` if the type of the variant `V` is `varNull`. No dereferencing is done.

See also: `VarIsEmpty` (2164), `VarType` (2170), `VarIsNumeric` (2165), `VarIsStr` (2166)

86.4.50 VarIsNumeric

Synopsis: Check if the variant is a numerical value

Declaration: `function VarIsNumeric(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsCustom` returns `True` if the variant `V` is of one of the ordinal or floating point types: `FloatVarTypes` (2148), `OrdinalVarTypes` (2148)

See also: `VarIsEmpty` (2164), `VarIsNull` (2165), `VarIsCustom` (2164), `VarIsOrdinal` (2165), `VarIsFloat` (2165), `VarIsStr` (2166)

86.4.51 VarIsOrdinal

Synopsis: Check if the variant is an ordinal value.

Declaration: `function VarIsOrdinal(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsCustom` returns `True` if the variant `V` is of one of the ordinal types: `OrdinalVarTypes` (2148) (`varSmallInt`, `varInteger`, `varBoolean`, `varShortInt`, `varByte`, `varWord`, `varLongWord`, `varInt64`)

See also: `VarIsEmpty` (2164), `VarIsNull` (2165), `VarIsCustom` (2164), `VarIsFloat` (2165), `VarIsNumeric` (2165), `VarIsStr` (2166)

86.4.52 VarIsStr

Synopsis: Check if the variant is a string

Declaration: `function VarIsStr(const V: Variant) : Boolean`

Visibility: default

Description: `VarIsCustom` returns `True` if the variant `V` is of one of the string types: `varOleStr`, `varUString`, `varString`

See also: `VarIsEmpty` (2164), `VarIsNull` (2165), `VarIsCustom` (2164), `VarIsOrdinal` (2165), `VarIsFloat` (2165), `VarIsBool` (2163)

86.4.53 VarIsType

Synopsis: Check if a variant is of certain type

Declaration: `function VarIsType(const V: Variant; aVarType: tvartype) : Boolean`
`; Overload`
`function VarIsType(const V: Variant; const AVarTypes: Array of tvartype)`
`: Boolean; Overload`

Visibility: default

Description: `VarIsType` will return `True` if the variant `V` is of type `aVarType` or is in `aVarTypes`.

See also: `VarType` (2170), `VarAsType` (2159), `VarIsByRef` (2163), `VarIsNull` (2165), `VarIsEmpty` (2164)

86.4.54 VarNotImplError

Synopsis: Raise an `EVariantNotImplError` error

Declaration: `procedure VarNotImplError`

Visibility: default

Description: `VarNotImplError` raises an `EVariantNotImplError` (2173) exception with a standard error message.

See also: `EVariantNotImplError` (2173), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162), `VarBadIndexError` (2159), `VarArrayLockedError` (2157)

86.4.55 VarOutOfMemoryError

Synopsis: Raise an `EVariantOutOfMemoryError` error

Declaration: `procedure VarOutOfMemoryError`

Visibility: default

Description: `VarOutOfMemoryError` raises an `EVariantOutOfMemoryError` (2173) exception with a standard error message.

See also: `EVariantOutOfMemoryError` (2173), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162), `VarBadIndexError` (2159), `VarArrayLockedError` (2157)

86.4.56 VarOverflowError

Synopsis: Raise an `EVariantOverflowError` error.

Declaration: `procedure VarOverflowError`
`procedure VarOverflowError(const ASourceType: tvartype;`
`const ADestType: tvartype)`

Visibility: default

Description: `VarOverflowError` raises a `EVariantOverflowError` (2173) exception with a description of the `ASourceType` and `ADestType` types in the message.

See also: `EVariantOverflowError` (2173), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162)

86.4.57 VarRangeCheckError

Synopsis: Raise an `EVariantOverflowError` error

Declaration: `procedure VarRangeCheckError(const AType: tvartype)`
`procedure VarRangeCheckError(const ASourceType: tvartype;`
`const ADestType: tvartype)`

Visibility: default

Description: `VarRangeCheckError` raises an `EVariantOverflowError` (2173) exception with a standard error message. A description of the type `AType` is included in the error message, similarly if a `ASourceType` and `aDestType` source and destination types are provided.

See also: `EVariantOverflowError` (2173), `VarOverflowError` (2167), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162), `VarBadIndexError` (2159), `VarArrayLockedError` (2157)

86.4.58 VarResultCheck

Synopsis: Check the result of an operation and raise exception if not OK.

Declaration: `procedure VarResultCheck(AResult: HRESULT)`
`procedure VarResultCheck(AResult: HRESULT; ASourceType: tvartype;`
`ADestType: tvartype)`

Visibility: default

Description: `VarResultCheck` checks the result `aResult`. If it differs from `VAR_OK` then an appropriate exception is raised based on the error code. If a source and destination type `ASourceType` and `aDestType` are specified they are included in the error message.

See also: `VarOverflowError` (2167), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162), `VarBadIndexError` (2159), `VarArrayLockedError` (2157)

86.4.59 VarSameValue

Synopsis: Check if 2 variants are the same

Declaration: `function VarSameValue(const A: Variant; const B: Variant) : Boolean`

Visibility: default

Description: `varSameValue` checks whether A and B have the same value. Here empty variants equal empty variants, and null variants equal null variants. For all other cases, the actual values are compared.

Errors: If the variants are of different types and they cannot be converted, an exception will be raised.

86.4.60 VarSupports

Synopsis: Check if a variant supports an interface.

Declaration: `function VarSupports(const V: Variant; const IID: TGuid; out Intf) : Boolean`
`function VarSupports(const V: Variant; const IID: TGuid) : Boolean`

Visibility: default

Description: `VarSupports` checks if the variant `V` contains an interface (types `Unknown`, `varDispatch`) and the interface supports the specified interface `IID`. If it does, `True` is returned, `False` otherwise. If `Intf` is specified, and the variant supports the requested interface, the interface instance is returned in `Intf`.

See also: `#rtl.sysutils.Supports` ([1774](#))

86.4.61 VarToDateTime

Synopsis: Convert a variant to datetime value

Declaration: `function VarToDateTime(const V: Variant) : TDateTime`

Visibility: default

Description: `VarToDateTime` attempts to convert the variant `V` to a `TDateTime` value.

Errors: If the value is `Null`, an exception is raised.

See also: `VarToUnicodeStr` ([2169](#)), `VarToStrDef` ([2168](#)), `VarIsStr` ([2166](#)), `VarToWideStr` ([2169](#)), `VarToWideStrDef` ([2169](#)), `VarFromDateTime` ([2161](#))

86.4.62 VarToStr

Synopsis: Convert a variant to string value

Declaration: `function VarToStr(const V: Variant) : string`

Visibility: default

Description: `VarToStr` attempts to convert the variant `V` to a string. If the value is `Null`, the result is an empty string.

See also: `VarToStrDef` ([2168](#)), `VarIsStr` ([2166](#)), `VarToWideStr` ([2169](#))

86.4.63 VarToStrDef

Synopsis: Convert a variant to string value, specifying a default

Declaration: `function VarToStrDef(const V: Variant; const ADefault: string) : string`

Visibility: default

Description: `VarToStr` attempts to convert the variant `V` to a string. If the value is `Null`, the result is the specified `aDefault` string.

See also: `VarToStrDef` ([2168](#)), `VarIsStr` ([2166](#)), `VarToStr` ([2168](#))

86.4.64 VarToUnicodeStr

Synopsis: Convert a variant to string value

Declaration: `function VarToUnicodeStr(const V: Variant) : UnicodeString`

Visibility: default

Description: `VarToUnicodeStr` attempts to convert the variant `V` to a string. If the value is `Null`, the result is an empty string.

See also: `VarToWideStr` (2169), `VarToUnicodeStrDef` (2169), `VarIsStr` (2166), `VarToStr` (2168), `VarToUnicodeStr` (2169)

86.4.65 VarToUnicodeStrDef

Synopsis: Convert a variant to string value, specifying a default

Declaration: `function VarToUnicodeStrDef(const V: Variant;
const ADefault: UnicodeString)
: UnicodeString`

Visibility: default

Description: `VarToUnicodeStr` attempts to convert the variant `V` to a string. If the value is `Null`, the result is the specified `aDefault` string.

See also: `VarToUnicodeStr` (2169), `VarToStrDef` (2168), `VarIsStr` (2166), `VarToWideStr` (2169), `VarToWideStrDef` (2169)

86.4.66 VarToWideStr

Synopsis: Convert a variant to string value

Declaration: `function VarToWideStr(const V: Variant) : WideString`

Visibility: default

Description: `VarToWideStr` attempts to convert the variant `V` to a string. If the value is `Null`, the result is an empty string.

See also: `VarToWideStrDef` (2169), `VarIsStr` (2166), `VarToStr` (2168), `VarToUnicodeStr` (2169)

86.4.67 VarToWideStrDef

Synopsis: Convert a variant to string value, specifying a default

Declaration: `function VarToWideStrDef(const V: Variant; const ADefault: WideString)
: WideString`

Visibility: default

Description: `VarToWideStr` attempts to convert the variant `V` to a string. If the value is `Null`, the result is the specified `aDefault` string.

See also: `VarToWideStrDef` (2169), `VarIsStr` (2166), `VarToWideStr` (2169), `VarToUnicodeStrDef` (2169)

86.4.68 VarType

Synopsis: Return the type of a variant.

Declaration: `function VarType(const V: Variant) : tvartype`

Visibility: default

Description: `VarType` returns the type of the variant `V`. (it returns the internal type field of the variant structure)

See also: `VarTypeDeRef` (2170), `VarIsType` (2166), `VarAsType` (2159)

86.4.69 VarTypeAsText

Synopsis: Return a textual description of the variant type

Declaration: `function VarTypeAsText(const AType: tvartype) : string`

Visibility: default

Description: `VarTypeAsText` returns a textual description of the variant type `aType`. It is used in all exception raising routines to describe types, if a type is provided. For custom variant types, the name of the class is returned.

See also: `VarOpAsText` (2148)

86.4.70 VarTypeDeRef

Synopsis: Returns the resolved type of a variant.

Declaration: `function VarTypeDeRef(const V: Variant) : tvartype; Overload`
`function VarTypeDeRef(const V: tvardata) : tvartype; Overload`

Visibility: default

Description: `VarTypeDeRef` will resolve the final type of the variant `V`: if `V` is a reference to another variant, the function will return the type of the referenced variant, recursing as much as needed till a non-variant type is encountered.

See also: `VarType` (2170), `VarIsType` (2166), `VarAsType` (2159)

86.4.71 VarTypeIsValidArrayType

Synopsis: Check if a variant type can be used in an array

Declaration: `function VarTypeIsValidArrayType(const aVarType: tvartype) : Boolean`

Visibility: default

Description: `VarTypeIsValidArrayType` checks if the variant type `aVarType` can be used as the type of a variant array. It returns `True` if it is usable, false otherwise. Currently, the following types are valid: `SmallInt`, `Integer`, `Single`, `Double`, `Date`, `Currency`, `OleStr`, `Dispatch`, `Error`, `Boolean`, `Variant`, `Unknown` (interface `IUnknown`), `ShortInt`, `Byte`, `Word`, `LongWord`.

See also: `VarIsArray` (2163), `VarTypeIsValidElementType` (2171)

86.4.72 VarTypeIsValidElementType

Synopsis: Check if a variant type can be used in an array

Declaration: `function VarTypeIsValidElementType(const aVarType: tvartype) : Boolean`

Visibility: default

Description: `VarTypeIsValidElementType` checks if the variant type `aVarType` can be used as the type of a variant array, similar to `VarTypeIsValidArrayType` (2170). It returns `True` if it is usable, `False` otherwise. Currently, the following types are valid: `SmallInt`, `Integer`, `Single`, `Double`, `Date`, `Currency`, `OleStr`, `Dispatch`, `Error`, `Boolean`, `Variant`, `Unknown` (interface `IUnknown`), `ShortInt`, `Byte`, `Word`, `LongWord` `int64`. In addition, if the variant type is an known custom variant type, `True` is also returned.

Reference and array indicators are stripped before the test.

See also: `VarIsArray` (2163), `VarTypeIsValidArrayType` (2170)

86.4.73 VarUnexpectedError

Synopsis: Raise an `EVariantUnexpectedError` error

Declaration: `procedure VarUnexpectedError`

Visibility: default

Description: `VarUnexpectedError` raises an `EVariantUnexpectedError` (2174) exception with a standard error message.

See also: `EVariantUnexpectedError` (2174), `VarInvalidNullOp` (2162), `VarInvalidOp` (2162), `VarBadIndexError` (2159), `VarArrayLockedError` (2157)

86.5 EVariantArrayCreateError

86.5.1 Description

`EVariantArrayCreateError` is the exception raised when a problem is detected during creation of an array. It can be raised manually by calling `VarArrayCreateError` (2156).

See also: `VarArrayCreateError` (2156)

86.6 EVariantArrayLockedError

86.6.1 Description

`EVariantArrayLockedError` is the exception raised when the `VAR_ARRAYISLOCKED` error is encountered in `VarResultCheck` (2167)

See also: `VarResultCheck` (2167)

86.7 EVariantBadIndexError

86.7.1 Description

EVariantBadIndexError is the exception raised when the VAR_BADINDEX error is encountered in VarResultCheck (2167)

See also: VarResultCheck (2167)

86.8 EVariantBadVarTypeError

86.8.1 Description

EVariantBadVarTypeError is the exception raised when the VAR_BADVARTYPE error is encountered in VarResultCheck (2167)

See also: VarResultCheck (2167)

86.9 EVariantDispatchError

86.9.1 Description

EVariantDispatchError is the exception raised when a dispatch call fails.

See also: TCustomVariantType (2176)

86.10 EVariantInvalidArgError

86.10.1 Description

EVariantInvalidArgError is the exception raised when the VAR_INVALIDARG error is encountered in VarResultCheck (2167)

See also: VarResultCheck (2167)

86.11 EVariantInvalidNullOpError

86.11.1 Description

EVariantInvalidNullOpError is defined for Delphi compatibility, but is not used in the FPC run time.

86.12 EVariantInvalidOpError

86.12.1 Description

EVariantInvalidOpError is the exception raised when the VAR_EXCEPTION error is encountered in VarResultCheck (2167)

See also: VarResultCheck (2167)

86.13 EVariantNotAnArrayError

86.13.1 Description

`EVariantNotAnArrayError` is not used in FPC and is defined for Delphi compatibility.

See also: `VarResultCheck` ([2167](#))

86.14 EVariantNotImplError

86.14.1 Description

`EVariantNotImplError` is the exception raised when the `VAR_NOTIMPL` error is encountered in `VarResultCheck` ([2167](#))

See also: `VarResultCheck` ([2167](#))

86.15 EVariantOutOfMemoryError

86.15.1 Description

`EVariantOutOfMemoryError` is the exception raised when the `VAR_OUTOFMEMORY` error is encountered in `VarResultCheck` ([2167](#)) It can be raised manually by calling `VarOutOfMemoryError` ([2166](#)).

See also: `VarOutOfMemoryError` ([2166](#)), `VarResultCheck` ([2167](#))

86.16 EVariantOverflowError

86.16.1 Description

`EVariantOverflowError` is the exception raised when the `VAR_OVERFLOW` error is encountered in `VarResultCheck` ([2167](#))

See also: `VarResultCheck` ([2167](#))

86.17 EVariantParamNotFoundError

86.17.1 Description

`EVariantParamNotFoundError` is the exception raised when the `VAR_PARAMNOTFOUND` error is encountered in `VarResultCheck` ([2167](#))

See also: `VarResultCheck` ([2167](#))

86.18 EVariantRangeCheckError

86.18.1 Description

`EVariantRangeCheckError` is defined for Delphi compatibility, it is not used in FPC.

86.19 EVariantTypeCastError

86.19.1 Description

`EVariantTypeCastError` is the exception raised when the `VAR_TYPEMISMATCH` error is encountered in `VarResultCheck` (2167)

See also: `VarResultCheck` (2167)

86.20 EVariantUnexpectedError

86.20.1 Description

`EVariantUnexpectedError` is the exception raised when the `VAR_UNEXPECTED` error is encountered in `VarResultCheck` (2167). It can be raised manually by calling `VarUnexpectedError` (2171).

See also: `VarVarUnexpectedError` (2147), `VarResultCheck` (2167)

86.21 IVarInstanceReference

86.21.1 Description

`IVarInstanceReference` is used to get the instance of an object from a custom variant. It has only one method, `GetInstance` (2174) which is used to retrieve the instance of a variant that contains an object.

The `TPublishableVariantType` (2183) descendent of `TInvokeableVariantType` (2181) uses this interface to implement reading published properties from the instance.

See also: `IVarInstanceReference.GetInstance` (2174)

86.21.2 Method overview

Page	Method	Description
2174	<code>GetInstance</code>	Return the object instance referenced by the custom variant

86.21.3 IVarInstanceReference.GetInstance

Synopsis: Return the object instance referenced by the custom variant

Declaration: `function GetInstance(const V: tvardata) : TObject`

Visibility: default

Description: `GetInstance` must return the object instance referenced by the custom variant `V`.

See also: `TPublishableVariantType` (2183)

86.22 IVarInvokeable

86.22.1 Description

`IVarInvokeable` must be implemented by the `TCustomVariantType` (2176) descendent if the custom variant needs to implement dynamic properties and methods.

`IVarInvokeable` has four functions that must be implemented. Any of these functions can be called whenever a custom variant's method is invoked or a property of the variant is read or written using `DispInvoke`.

The `TCustomVariantType` descendent `TInvokeableVariantType` (2181) implements the needed `DispInvoke` to call the `IVarInvokeable` interface, so you can descend from that type instead when creating a new custom variant type and override the needed functions.

See also: `TInvokeableVariantType` (2181), `TCustomVariantType` (2176)

86.22.2 Method overview

Page	Method	Description
2175	<code>DoFunction</code>	Called for methods that return a result (functions)
2175	<code>DoProcedure</code>	Called for methods that do not return a result (procedures)
2176	<code>GetProperty</code>	Called when a property must be read
2176	<code>SetProperty</code>	Called when a property must be set

86.22.3 IVarInvokeable.DoFunction

Synopsis: Called for methods that return a result (functions)

Declaration:

```
function DoFunction(var Dest: tvardata; const V: tvardata;
                    const Name: string; const Arguments: TVarDataArray)
                    : Boolean
```

Visibility: default

Description: `DoFunction` is called whenever a variant method that returns a result needs to be invoked. The `Dest` parameter points to the location where the result of the function must be placed; the result must be a variant value.

`V` is the variant on which the method is being executed. The `Name` is the name of the function to execute, and `Arguments` is an array of variant arguments that were passed to the function.

The function must return `True` if the function was executed correctly, `False` otherwise.

See also: `IVarInvokeable.DoProcedure` (2175), `IVarInvokeable.GetProperty` (2176), `IVarInvokeable.SetProperty` (2176)

86.22.4 IVarInvokeable.DoProcedure

Synopsis: Called for methods that do not return a result (procedures)

Declaration:

```
function DoProcedure(const V: tvardata; const Name: string;
                    const Arguments: TVarDataArray) : Boolean
```

Visibility: default

Description: `DoProcedure` is called whenever a variant method that does not return a result needs to be invoked. `V` is the variant on which the method is being executed. The `Name` is the name of the method to execute, and `Arguments` is an array of variant arguments that were passed to the method.

The function must return `True` if the procedure was executed correctly, `False` otherwise.

See also: `IVarInvokeable.DoFunction` (2175), `IVarInvokeable.GetProperty` (2176), `IVarInvokeable.SetProperty` (2176)

86.22.5 IVarInvokeable.GetProperty

Synopsis: Called when a property must be read

Declaration: `function GetProperty(var Dest: tvardata; const V: tvardata;
const Name: string) : Boolean`

Visibility: default

Description: `DoFunction` is called whenever a variant property is read. `Dest` must be filled with the value of the property on success. `V` is the variant on which the property is read. The `Name` is the name of the property to read.

The function must return `True` if the property was read correctly, `False` otherwise.

See also: `IVarInvokeable.DoFunction` (2175), `IVarInvokeable.DoProcedure` (2175), `IVarInvokeable.SetProperty` (2176)

86.22.6 IVarInvokeable.SetProperty

Synopsis: Called when a property must be set

Declaration: `function SetProperty(var V: tvardata; const Name: string;
const Value: tvardata) : Boolean`

Visibility: default

Description: `DoFunction` is called whenever a variant property is written. `Value` is filled with the new value of the property. `V` is the variant on which the property is written. The `Name` is the name of the property to write.

The function must return `True` if the property was written correctly, `False` otherwise.

See also: `IVarInvokeable.DoFunction` (2175), `IVarInvokeable.DoProcedure` (2175), `IVarInvokeable.GetProperty` (2176)

86.23 TCustomVariantType

86.23.1 Description

`TCustomVariantType` is used as a base class to implement custom variants. To define a custom variant type, a descendent of `TCustomVariant` must be made, and the appropriate methods must be overridden and implemented according to the specifications of the new type. Typically this means defining how your new type maps to another variant or a basic type.

Note that the `TCustomVariantType` descendent does not hold the data of the variant: it just describes how a variant record (`TVarRec` (1415)) that contains the new type's data can be examined or manipulated.

See also: `#rtl.system.TVarRec` (1415)

86.23.2 Interfaces overview

Page	Interfaces	Description
1375	IInterface	Basic interface for all COM based interfaces

86.23.3 Method overview

Page	Method	Description
2179	BinaryOp	Perform a binary mathematical operation
2178	Cast	Cast a custom variant to another type
2178	CastTo	Cast a custom variant to another type
2178	CastToOle	Cast variant value to OLE value
2179	Clear	Clear a value
2180	Compare	Comparison 2 custom variant values
2180	CompareOp	Check result of a comparison between 2 custom variant values
2179	Copy	Copy a custom variant value
2177	Create	Instantiate a new custom variant type
2177	Destroy	Unregister variant type
2178	IsClear	Is the custom value unassigned ?
2180	UnaryOp	Perform a unary mathematical operation

86.23.4 Property overview

Page	Properties	Access	Description
2181	VarType	r	Registered type

86.23.5 TCustomVariantType.Create

Synopsis: Instantiate a new custom variant type

Declaration: `constructor Create; Overload`
`constructor Create(RequestedVarType: tvartype); Overload`

Visibility: `public`

Description: `Create` sets up the necessary reference counting mechanisms to act as an interface, and assigns the new variant type identifier. If specified, the `RequestedVarType` is the variant type that is registered. if it is zero, a new identifier is assigned.

See also: `TCustomVariantType.Destroy` ([2177](#))

86.23.6 TCustomVariantType.Destroy

Synopsis: Unregister variant type

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` unregisters the custom variant type and removes the instance from memory. After this is called, variants with the (now unregistered) type can no longer be used.

See also: `TCustomVariantType.Create` ([2177](#))

86.23.7 TCustomVariantType.IsClear

Synopsis: Is the custom value unassigned ?

Declaration: `function IsClear(const V: tvardata) : Boolean; Virtual`

Visibility: public

Description: `IsClear` must be overridden to decide whether the custom variant `V` is equivalent to `varClear` (unassigned) value. The `VarIsClear` (2163) function calls this method to decide whether a custom variant is unassigned.

The `TCustomVariantType` implementation of `IsClear` always returns `False`.

See also: `VarIsClear` (2163)

86.23.8 TCustomVariantType.Cast

Synopsis: Cast a custom variant to another type

Declaration: `procedure Cast(var Dest: tvardata; const Source: tvardata); Virtual`

Visibility: public

Description: `Cast` is called when a variant value `Source` is cast to a custom variant `Dest`. Descendents must override this method to provide the desired conversion behaviour.

The `TCustomVariantType` implementation of `Cast` calls `CastTo` on the source variant with as destination type the custom variant type.

Errors: If the variant type cannot be cast, an exception is raised.

See also: `TCustomVariantType.CastTo` (2178), `TCustomVariantType.CastToOle` (2178)

86.23.9 TCustomVariantType.CastTo

Synopsis: Cast a custom variant to another type

Declaration: `procedure CastTo(var Dest: tvardata; const Source: tvardata;
const aVarType: tvartype); Virtual`

Visibility: public

Description: `CastTo` is called when a custom variant value `Source` is cast to a variant type `aVarType` and stores the result in `Dest`. Descendents must override this method to provide the desired conversion behaviour.

See also: `TCustomVariantType.Cast` (2178), `TCustomVariantType.CastToOle` (2178)

86.23.10 TCustomVariantType.CastToOle

Synopsis: Cast variant value to OLE value

Declaration: `procedure CastToOle(var Dest: tvardata; const Source: tvardata)
; Virtual`

Visibility: public

Description: `CastToOle` is called when a variant must be cast to a value that can be used in OLE variants. Descendents must override this method to provide the desired conversion behaviour.

The `TCustomVariantType` implementation of `CastToOle` raises an 'unsupported' exception.

See also: `TCustomVariantType.Cast` (2178), `TCustomVariantType.CastTo` (2178)

86.23.11 TCustomVariantType.Clear

Synopsis: Clear a value

Declaration: `procedure Clear(var V: tvardata); Virtual; Abstract`

Visibility: public

Description: `Clear` is called when a variant value must be cleared, by `VarClear`. This is an abstract method that must be overridden and implemented in descendent classes. When the method returns, the type of the variant record must be `varClear`

If the custom variant value used some heap memory (for instance in an object) then this is the place to release that memory.

Errors: If this method is not overridden, an abstract error will be thrown.

See also: `TCustomVariantType.IsClear` (2178), `TCustomVariantType.Copy` (2179), `VarClear` (2160)

86.23.12 TCustomVariantType.Copy

Synopsis: Copy a custom variant value

Declaration: `procedure Copy(var Dest: tvardata; const Source: tvardata;
const Indirect: Boolean); Virtual; Abstract`

Visibility: public

Description: `Copy` is used when a custom variant value is assigned to another variant. This is an abstract method that must be overridden and implemented in descendent classes. When the method returns, the type of the `Dest` variant record must be equal to the `Source` type (the custom variant type value).

If `Indirect` is `True` source contains a reference to the custom variant. In that case, `dest` should also contain a reference.

Errors: If this method is not overridden, an abstract error will be thrown.

See also: `TCustomVariantType.Clear` (2179)

86.23.13 TCustomVariantType.BinaryOp

Synopsis: Perform a binary mathematical operation

Declaration: `procedure BinaryOp(var Left: tvardata; const Right: tvardata;
const Operation: tvarop); Virtual`

Visibility: public

Description: `BinaryOp` performs `Operation` on `Left` and `Right` and stores the result of the result in `Left`. The `TCustomVariantType` implementation of this method raises an invalid operation error. Descendent classes must override this.

Errors: If a descendent does not override this, an invalid operation error is raised.

See also: `=TCustomVariantType.UnaryOp` (2147), `=TCustomVariantType.CompareOp` (2147)

86.23.14 TCustomVariantType.UnaryOp

Synopsis: Perform a unary mathematical operation

Declaration: `procedure UnaryOp(var Right: tvardata; const Operation: tvarop)
; Virtual`

Visibility: public

Description: `UnaryOp` performs `Operation` on `Right` and stores the result of the result in `Right`. The `TCustomVariantType` implementation of this method raises an invalid operation error. Descendent classes must override this method.

Errors: If a descendent does not override this, an invalid operation error is raised.

See also: `=TCustomVariantType.BinaryOp` (2147), `=TCustomVariantType.CompareOp` (2147)

86.23.15 TCustomVariantType.CompareOp

Synopsis: Check result of a comparison between 2 custom variant values

Declaration: `function CompareOp(const Left: tvardata; const Right: tvardata;
const Operation: tvarop) : Boolean; Virtual`

Visibility: public

Description: `CompareOp` performs the comparison specified in `Operation` on `left` and `Right` and returns `True` if the values satisfy the requested operation. The `TCustomVariantType` implementation of this method raises an 'unsupported' error. Descendent classes must override this method.

Errors: If a descendent does not override this, an 'unsupported' error is raised.

See also: `TCustomVariantType.Compare` (2180), `TCustomVariantType.UnaryOp` (2180), `TCustomVariantType.binaryOp` (2179)

86.23.16 TCustomVariantType.Compare

Synopsis: Comparison 2 custom variant values

Declaration: `procedure Compare(const Left: tvardata; const Right: tvardata;
var Relationship: TVarCompareResult); Virtual`

Visibility: public

Description: `Compare` performs the comparison specified in `Operation` on `left` and `Right` and returns the result of the comparison. The `TCustomVariantType` implementation of this method raises an 'unsupported' error. Descendent classes must override this method.

Errors: If a descendent does not override this, an 'unsupported' error is raised.

See also: `TCustomVariantType.CompareOp` (2180), `TCustomVariantType.UnaryOp` (2180), `TCustomVariantType.binaryOp` (2179)

86.23.17 TCustomVariantType.VarType

Synopsis: Registered type

Declaration: `Property VarType : tvartype`

Visibility: public

Access: Read

Description: `VarType` is the custom variant type identifier for the custom variant values. It is assigned by the system in the constructor.

See also: `TCustomVariantType.Create` (2177)

86.24 TInvokeableVariantType

86.24.1 Description

`TInvokeableVariantType` is a `TCustomVariantType` (2176) descendent which implements the `TCustomVariantType.DispatchInvoke` (2176) method. It translates the `DispatchInvoke` method to calls to one or more of the four methods of `IVarInvokeable` (2175): `DoFunction` (2175) or `DoProcedure` (2175) for method calls (`DISPATCH_METHOD`) and `GetProperty` (2176) for property reading (`DISPATCH_PROPERTYGET`) or `SetProperty` (2176) for property writing (`DISPATCH_PROPERTYSET`). Other combinations are possible. It has empty stubs for these methods, which must be implemented in a descendent that is used to describe a custom variant.

See also: `IVarInvokeable.DoFunction` (2175), `IVarInvokeable.DoProcedure` (2175), `IVarInvokeable.GetProperty` (2176), `IVarInvokeable.SetProperty` (2176)

86.24.2 Interfaces overview

Page	Interfaces	Description
2175	<code>IVarInvokeable</code>	Interface needed for custom variants that need to implement dynamic properties and methods

86.24.3 Method overview

Page	Method	Description
2181	<code>DoFunction</code>	Empty stub for <code>IVarInvokeable.DoFunction</code> , to be implemented in descendents
2182	<code>DoProcedure</code>	Empty stub for <code>IVarInvokeable.DoProcedure</code> , to be implemented in descendents
2182	<code>GetProperty</code>	Empty stub for <code>IVarInvokeable.GetProperty</code> , to be implemented in descendents
2182	<code>SetProperty</code>	Empty stub for <code>IVarInvokeable.SetProperty</code> , to be implemented in descendents

86.24.4 TInvokeableVariantType.DoFunction

Synopsis: Empty stub for `IVarInvokeable.DoFunction`, to be implemented in descendents

Declaration: `function DoFunction(var Dest: tvardata; const V: tvardata;
const Name: string; const Arguments: TVarDataArray)
: Boolean; Virtual`

Visibility: public

Description: `DoFunction` is the default implementation of `IVarInvokeable.DoFunction` (2175), which always returns `False`. It must be overridden in descendent classes to implement actual calling of a function.

See also: `IVarInvokeable.DoFunction` (2175)

86.24.5 `TInvokeableVariantType.DoProcedure`

Synopsis: Empty stub for `IVarInvokeable.DoProcedure`, to be implemented in descendents

Declaration: `function DoProcedure(const V: tvardata; const Name: string;
const Arguments: TVarDataArray) : Boolean; Virtual`

Visibility: public

Description: `DoProcedure` is the default implementation of `IVarInvokeable.DoProcedure` (2175), which always returns `False`. It must be overridden in descendent classes to implement actual calling of a procedure.

See also: `IVarInvokeable.DoProcedure` (2175)

86.24.6 `TInvokeableVariantType.GetProperty`

Synopsis: Empty stub for `IVarInvokeable.GetProperty`, to be implemented in descendents

Declaration: `function GetProperty(var Dest: tvardata; const V: tvardata;
const Name: string) : Boolean; Virtual`

Visibility: public

Description: `GetProperty` is the default implementation of `IVarInvokeable.GetProperty` (2176), which always returns `False`. It must be overridden in descendent classes to implement actual reading of a property.

See also: `IVarInvokeable.GetProperty` (2176)

86.24.7 `TInvokeableVariantType.SetProperty`

Synopsis: Empty stub for `IVarInvokeable.SetProperty`, to be implemented in descendents

Declaration: `function SetProperty(var V: tvardata; const Name: string;
const Value: tvardata) : Boolean; Virtual`

Visibility: public

Description: `SetProperty` is the default implementation of `IVarInvokeable.SetProperty` (2176), which always returns `False`. It must be overridden in descendent classes to implement actual writing of a property.

See also: `IVarInvokeable.SetProperty` (2176)

86.25 TPublishableVariantType

86.25.1 Description

TPublishableVariantType implements the IVarInvokeable.GetProperty (2176) and IVarInvokeable.SetProperty (2176) methods by getting or setting the published properties of the class instance returned by the IVarInstanceReference interface it implements.

See also: TInvokeableVariantType (2181), IVarInvokeable.GetProperty (2176), IVarInvokeable.SetProperty (2176), IVarInstanceReference (2174)

86.25.2 Interfaces overview

Page	Interfaces	Description
2174	IVarInstanceReference	Interface for variants that refer to an object

86.25.3 Method overview

Page	Method	Description
2183	GetProperty	Read the property
2183	SetProperty	Write the property

86.25.4 TPublishableVariantType.GetProperty

Synopsis: Read the property

Declaration: `function GetProperty(var Dest: tvardata; const V: tvardata;
const Name: string) : Boolean; Override`

Visibility: public

Description: GetProperty implements reading the property by looking for the property in the published properties of the instance returned by the IVarInstanceReference (2174) interface, and returning the value as a variant.

See also: IVarInstanceReference (2174), IVarInvokeable.GetProperty (2176)

86.25.5 TPublishableVariantType.SetProperty

Synopsis: Write the property

Declaration: `function SetProperty(var V: tvardata; const Name: string;
const Value: tvardata) : Boolean; Override`

Visibility: public

Description: SetProperty implements writing the property by looking for the property in the published properties of the instance returned by the IVarInstanceReference (2174) interface, and setting the value as a variant.

See also: IVarInstanceReference (2174), IVarInvokeable.SetProperty (2176)

Chapter 87

Reference for unit 'video'

87.1 Used units

Table 87.1: Used units by unit 'video'

Name	Page
System	1339

87.2 Overview

The `Video` unit implements a screen access layer which is system independent. It can be used to write on the screen in a system-independent way, which should be optimal on all platforms for which the unit is implemented.

The working of the `Video` is simple: After calling `InitVideo` ([2201](#)), the array `VideoBuf` contains a representation of the video screen of size `ScreenWidth*ScreenHeight`, going from left to right and top to bottom when walking the array elements: `VideoBuf[0]` contains the character and color code of the top-left character on the screen. `VideoBuf[ScreenWidth]` contains the data for the character in the first column of the second row on the screen, and so on.

To write to the 'screen', the text to be written should be written to the `VideoBuf` array. Calling `UpdateScreen` ([2205](#)) will then copy the text to the screen in the most optimal way. (an example can be found further on).

The color attribute is a combination of the foreground and background color, plus the blink bit. The bits describe the various color combinations:

bits 0-3 The foreground color. Can be set using all color constants.

bits 4-6 The background color. Can be set using a subset of the color constants.

bit 7 The blinking bit. If this bit is set, the character will appear blinking.

Each possible color has a constant associated with it, see the constants section for a list of constants. The foreground and background color can be combined to a color attribute with the following code:

```
Attr:=ForeGroundColor + (BackGroundColor shl 4);
```

The color attribute can be logically or-ed with the blink attribute to produce a blinking character:

```
Attr:=Attr or blink;
```

But not all drivers may support this.

The contents of the `VideoBuf` array may be modified: This is 'writing' to the screen. As soon as everything that needs to be written in the array is in the `VideoBuf` array, calling `UpdateScreen` will copy the contents of the array screen to the screen, in a manner that is as efficient as possible.

The updating of the screen can be prohibited to optimize performance; To this end, the `LockScreenUpdate` (2202) function can be used: This will increment an internal counter. As long as the counter differs from zero, calling `UpdateScreen` (2205) will not do anything. The counter can be lowered with `UnlockScreenUpdate` (2204). When it reaches zero, the next call to `UpdateScreen` (2205) will actually update the screen. This is useful when having nested procedures that do a lot of screen writing.

The video unit also presents an interface for custom screen drivers, thus it is possible to override the default screen driver with a custom screen driver, see the `SetVideoDriver` (2204) call. The current video driver can be retrieved using the `GetVideoDriver` (2199) call.

Remark The video unit should *not* be used together with the CRT unit. Doing so will result in very strange behaviour, possibly program crashes.

87.3 Examples utility unit

The examples in this section make use of the unit `vidutil`, which contains the `TextOut` function. This function writes a text to the screen at a given location. It looks as follows:

Listing: ./examples/videoex/vidutil.pp

```
unit vidutil;

Interface

uses
  video;

Procedure TextOut(X,Y : Word;Const S : String);

Implementation

Procedure TextOut(X,Y : Word;Const S : String);

Var
  W,P,I,M : Word;

begin
  P:=((X-1)+(Y-1)*ScreenWidth);
  M:=Length(S);
  If P+M>ScreenWidth*ScreenHeight then
    M:=ScreenWidth*ScreenHeight-P;
  For I:=1 to M do
    VideoBuf^[P+I-1]:=Ord(S[I])+($07 shl 8);
  end;
end.
```

87.4 Writing a custom video driver

Writing a custom video driver is not difficult, and generally means implementing a couple of functions, which would be registered with the `SetVideoDriver` (2204) function. The various functions that can be implemented are located in the `TVideoDriver` (2206) record:

```
TVideoDriver = Record
  InitDriver      : Procedure;
  DoneDriver      : Procedure;
  UpdateScreen    : Procedure(Force : Boolean);
  ClearScreen     : Procedure;
  SetVideoMode    : Function (Const Mode : TVideoMode) : Boolean;
  GetVideoModeCount : Function : Word;
  GetVideoModeData : Function(Index : Word; Var Data : TVideoMode) : Boolean;
  SetCursorPos    : procedure (NewCursorX, NewCursorY: Word);
  GetCursorPos    : function : Word;
  SetCursorType   : procedure (NewType: Word);
  GetCursorType   : function : Word;
  GetCapabilities : Function : Word;
end;
```

Not all of these functions must be implemented. In fact, the only absolutely necessary function to write a functioning driver is the `UpdateScreen` function. The general calls in the `Video` unit will check which functionality is implemented by the driver.

The functionality of these calls is the same as the functionality of the calls in the `video` unit, so the expected behaviour can be found in the previous section. Some of the calls, however, need some additional remarks.

InitDriver Called by `InitVideo`, this function should initialize any data structures needed for the functionality of the driver, maybe do some screen initializations. The function is guaranteed to be called only once; It can only be called again after a call to `DoneVideo`. The variables `ScreenWidth` and `ScreenHeight` should be initialized correctly after a call to this function, as the `InitVideo` call will initialize the `VideoBuf` and `OldVideoBuf` arrays based on their values.

DoneDriver This should clean up any structures that have been initialized in the `InitDriver` function. It should possibly also restore the screen as it was before the driver was initialized. The `VideoBuf` and `OldVideoBuf` arrays will be disposed of by the general `DoneVideo` call.

UpdateScreen This is the only required function of the driver. It should update the screen based on the `VideoBuf` array's contents. It can optimize this process by comparing the values with values in the `OldVideoBuf` array. After updating the screen, the `UpdateScreen` procedure should update the `OldVideoBuf` by itself. If the `Force` parameter is `True`, the whole screen should be updated, not just the changed values.

ClearScreen If there is a faster way to clear the screen than to write spaces in all character cells, then it can be implemented here. If the driver does not implement this function, then the general routines will write spaces in all video cells, and will call `UpdateScreen(True)`.

SetVideoMode Should set the desired video mode, if available. It should return `True` if the mode was set, `False` if not.

GetVideoModeCount Should return the number of supported video modes. If no modes are supported, this function should not be implemented; the general routines will return 1. (for the current mode)

GetVideoModeData Should return the data for the `Index`-th mode; `Index` is zero based. The function should return true if the data was returned correctly, false if `Index` contains an invalid index. If this is not implemented, then the general routine will return the current video mode when `Index` equals 0.

GetCapabilities If this function is not implemented, zero (i.e. no capabilities) will be returned by the general function.

The following unit shows how to override a video driver, with a driver that writes debug information to a file. The unit can be used in any of the demonstration programs, by simply including it in the `uses` clause. Setting `DetailedVideoLogging` to `True` will create a more detailed log (but will also slow down functioning)

Listing: `./examples/videoex/viddbg.pp`

```
unit viddbg;
```

```
Interface
```

```
uses video;
```

```
Procedure StartVideoLogging;
```

```
Procedure StopVideoLogging;
```

```
Function IsVideoLogging : Boolean;
```

```
Procedure SetVideoLogFileName(FileName : String);
```

```
Const
```

```
    DetailedVideoLogging : Boolean = False;
```

```
Implementation
```

```
uses sysutils, keyboard;
```

```
var
```

```
    NewVideoDriver ,
    OldVideoDriver : TVideoDriver;
    Active, Logging : Boolean;
    LogFileName : String;
    VideoLog : Text;
```

```
Function TimeStamp : String;
```

```
begin
```

```
    TimeStamp := FormatDateTime( 'hh:nn:ss ', Time ());
```

```
end;
```

```
Procedure StartVideoLogging;
```

```
begin
```

```
    Logging := True;
    WriteLn(VideoLog, 'Start logging video operations at: ', TimeStamp);
```

```
end;
```

```
Procedure StopVideoLogging;
```

```
begin
```

```
    WriteLn(VideoLog, 'Stop logging video operations at: ', TimeStamp);
    Logging := False;
```

```

end;

Function IsVideoLogging : Boolean;

begin
  IsVideoLogging:=Logging;
end;

Var
  ColUpd,RowUpd : Array[0..1024] of Integer;

Procedure DumpScreenStatistics(Force : Boolean);

Var
  I,Count : Integer;

begin
  If Force then
    Write(VideoLog,'forced ');
    WriteLn(VideoLog,'video update at ',TimeStamp,' : ');
    FillChar(ColUpd,SizeOf(ColUpd),#0);
    FillChar(RowUpd,SizeOf(RowUpd),#0);
    Count:=0;
    For I:=0 to VideoBufSize div SizeOf(TVideoCell) do
      begin
        If VideoBuf^[i]<>OldVideoBuf^[i] then
          begin
            Inc(Count);
            Inc(ColUpd[I mod ScreenWidth]);
            Inc(RowUpd[I div ScreenHeight]);
          end;
        end;
      Write(VideoLog,Count,' videocells differed divided over ');
      Count:=0;
      For I:=0 to ScreenWidth-1 do
        If ColUpd[I]<>0 then
          Inc(Count);
      Write(VideoLog,Count,' columns and ');
      Count:=0;
      For I:=0 to ScreenHeight-1 do
        If RowUpd[I]<>0 then
          Inc(Count);
      WriteLn(VideoLog,Count,' rows. ');
      If DetailedVideoLogging Then
        begin
          For I:=0 to ScreenWidth-1 do
            If (ColUpd[I]<>0) then
              WriteLn(VideoLog,'Col ',i,' : ',ColUpd[I]:3,' rows changed');
          For I:=0 to ScreenHeight-1 do
            If (RowUpd[I]<>0) then
              WriteLn(VideoLog,'Row ',i,' : ',RowUpd[I]:3,' columns changed');
          end;
        end;
    end;

Procedure LogUpdateScreen(Force : Boolean);

begin
  If Logging then

```

```

        DumpScreenStatistics ( Force );
        OldVideoDriver . UpdateScreen ( Force );
    end;

Procedure LogInitVideo ;

begin
    OldVideoDriver . InitDriver ( );
    Assign ( VideoLog , logFileName );
    Rewrite ( VideoLog );
    Active := True ;
    StartVideoLogging ;
end;

Procedure LogDoneVideo ;

begin
    StopVideoLogging ;
    Close ( VideoLog );
    Active := False ;
    OldVideoDriver . DoneDriver ( );
end;

Procedure SetVideoLogFileName ( FileName : String );

begin
    If Not Active then
        LogFileName := FileName ;
    end;

Initialization
    GetVideoDriver ( OldVideoDriver );
    NewVideoDriver := OldVideoDriver ;
    NewVideoDriver . UpdateScreen := @LogUpdateScreen ;
    NewVideoDriver . InitDriver := @LogInitVideo ;
    NewVideoDriver . DoneDriver := @LogDoneVideo ;
    LogFileName := 'Video . log ' ;
    Logging := False ;
    SetVideoDriver ( NewVideoDriver );
end.

```

87.5 Constants, types and variables

87.5.1 Constants

Black = 0

Black color attribute

Blink = 128

Blink attribute

Blue = 1

Blue color attribute

`Brown = 6`

Brown color attribute

`cpBlink = $0002`

Video driver supports blink attribute

`cpChangeCursor = $0020`

Video driver supports changing cursor shape.

`cpChangeFont = $0008`

Video driver supports changing screen font.

`cpChangeMode = $0010`

Video driver supports changing mode

`cpColor = $0004`

Video driver supports color

`cpUnderLine = $0001`

Video driver supports underline attribute

`crBlock = 2`

Block cursor

`crHalfBlock = 3`

Half block cursor

`crHidden = 0`

Hide cursor

`crUnderLine = 1`

Underline cursor

`Cyan = 3`

Cyan color attribute

`DarkGray = 8`

Dark gray color attribute

```
errOk = 0
```

No error

```
ErrorCode : LongInt = ErrOK
```

Error code returned by the last operation.

```
ErrorHandler : TErrorHandler = @ DefaultErrorHandler
```

The `ErrorHandler` variable can be set to a custom-error handling function. It is set by default to the `DefaultErrorHandler` (2196) function.

```
ErrorInfo : Pointer = Nil
```

Pointer to extended error information.

```
errVioBase = 1000
```

Base value for video errors

```
errVioInit = errVioBase + 1
```

Video driver initialization error.

```
errVioNoSuchMode = errVioBase + 3
```

Invalid video mode

```
errVioNotSupported = errVioBase + 2
```

Unsupported video function

```
FVMaxWidth = 240
```

Maximum screen buffer width.

```
Green = 2
```

Green color attribute

```
iso_codepages = [iso01, iso02, iso03, iso04, iso05, iso06, iso07,  
  iso08, iso09, iso10, iso13, iso14, iso15]
```

`iso_codepages` is a set containing all code pages that use an ISO encoding.

```
LightBlue = 9
```

Light Blue color attribute

LightCyan = 11

Light cyan color attribute

LightGray = 7

Light gray color attribute

LightGreen = 10

Light green color attribute

LightMagenta = 13

Light magenta color attribute

LightRed = 12

Light red color attribute

LowAscii = True

On some systems, the low 32 values of the DOS code page are necessary for the ASCII control codes and cannot be displayed by programs. If LowAscii is true, you can use the low 32 ASCII values. If it is false, you must avoid using them.

LowAscii can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to LowAscii, or take its address.

Magenta = 5

Magenta color attribute

NoExtendedFrame = False

The VT100 character set only has line drawing characters consisting of a single line. If this value is true, the line drawing characters with two lines will be automatically converted to single lines.

NoExtendedFrame can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to NoExtendedFrame, or take its address.

Red = 4

Red color attribute

ScreenHeight : Word = 0

Current screen height

ScreenWidth : Word = 0

Current screen Width

```
vga_codepages = [cp437, cp850, cp852, cp866]
```

`vga_codepages` is a set containing all code pages that can be considered a normal vga font (as in use on early VGA cards) Note that KOI8-R has line drawing characters in wrong place.

```
vioOK = 0
```

No errors occurred

```
White = 15
```

White color attribute

```
Yellow = 14
```

Yellow color attribute

87.5.2 Types

```
PVideoBuf = ^TVideoBuf
```

Pointer type to TVideoBuf ([2194](#))

```
PVideoCell = ^TVideoCell
```

Pointer type to TVideoCell ([2194](#))

```
PVideoMode = ^TVideoMode
```

Pointer to TVideoMode ([2206](#)) record.

```
TErrorHandler = function(Code: LongInt; Info: Pointer)
    : TErrorHandlerReturnValue
```

The `TErrorHandler` function is used to register an own error handling function. It should be used when installing a custom error handling function, and must return one of the above values.

`Code` should contain the error code for the error condition, and the `Info` parameter may contain any data type specific to the error code passed to the function.

```
TErrorHandlerReturnValue = (errRetry, errAbort, errContinue)
```

Table 87.2: Enumeration values for type TErrorHandlerReturnValue

Value	Explanation
<code>errAbort</code>	abort and return error code
<code>errContinue</code>	abort without returning an errorcode.
<code>errRetry</code>	retry the operation

Type used to report and respond to error conditions

```
TVideoBuf = Array[0..32759] of TVideoCell
```

The TVideoBuf type represents the screen.

```
TVideoCell = Word
```

TVideoCell describes one character on the screen. One of the bytes contains the color attribute with which the character is drawn on the screen, and the other byte contains the ASCII code of the character to be drawn. The exact position of the different bytes in the record is operating system specific. On most little-endian systems, the high byte represents the color attribute, while the low-byte represents the ASCII code of the character to be drawn.

```
TVideoModeSelector = function(const VideoMode: TVideoMode;
    Params: LongInt) : Boolean
```

Video mode selection callback prototype.

87.5.3 Variables

```
CursorLines : Byte
```

CursorLines is a bitmask which determines which cursor lines are visible and which are not. Each set bit corresponds to a cursorline being shown.

This variable is not supported on all platforms, so it should be used sparingly.

```
CursorX : Word
```

Current horizontal position in the screen where items will be written.

```
CursorY : Word
```

Current vertical position in the screen where items will be written.

```
external_codepage : Tencoding
```

This variable is for internal use only and should not be used.

```
internal_codepage : Tencoding
```

This variable is for internal use only and should not be used.

```
OldVideoBuf : PVideoBuf
```

The OldVideoBuf contains the state of the video screen after the last screen update. The Update-Screen (2205) function uses this array to decide which characters on screen should be updated, and which not.

Note that the OldVideoBuf array may be ignored by some drivers, so it should not be used. The Array is in the interface section of the video unit mainly so drivers that need it can make use of it.

```
ScreenColor : Boolean
```

`ScreenColor` indicates whether the current screen supports colors.

`VideoBuf` : `PVideoBuf`

`VideoBuf` forms the heart of the `Video` unit: This variable represents the physical screen. Writing to this array and calling `UpdateScreen` (2205) will write the actual characters to the screen.

`VideoBufSize` : `LongInt`

Current size of the video buffer pointed to by `VideoBuf` (2195)

87.6 Procedures and functions

87.6.1 ClearScreen

Synopsis: Clear the video screen.

Declaration: `procedure ClearScreen`

Visibility: `default`

Description: `ClearScreen` clears the entire screen, and calls `UpdateScreen` (2205) after that. This is done by writing spaces to all character cells of the video buffer in the default color (lightgray on black, color attribute `\$07`).

Errors: None.

See also: `InitVideo` (2201), `UpdateScreen` (2205)

Listing: `./examples/videoex/ex3.pp`

```

program testvideo ;

uses video , keyboard , vidutil ;

Var
  i : longint ;
  k : TKeyEvent ;

begin
  InitVideo ;
  InitKeyboard ;
  For i:=1 to 10 do
    TextOut(i,i, 'Press any key to clear screen');
    UpdateScreen(false);
    K:=GetKeyEvent;
    ClearScreen;
    TextOut(1,1, 'Cleared screen. Press any key to end');
    UpdateScreen(true);
    K:=GetKeyEvent;
    DoneKeyBoard;
    DoneVideo;
end.

```

87.6.2 DefaultErrorHandler

Synopsis: Default error handling routine.

Declaration: `function DefaultErrorHandler (AErrorCode: LongInt; AErrorInfo: Pointer)
: TErrorHandlerReturnValue`

Visibility: default

Description: `DefaultErrorHandler` is the default error handler used by the video driver. It simply sets the error code `AErrorCode` and `AErrorInfo` in the global variables `ErrorCode` and `ErrorInfo` and returns `errContinue`.

Errors: None.

87.6.3 DoneVideo

Synopsis: Disable video driver.

Declaration: `procedure DoneVideo`

Visibility: default

Description: `DoneVideo` disables the Video driver if the video driver is active. If the videodriver was already disabled or not yet initialized, it does nothing. Disabling the driver means it will clean up any allocated resources, possibly restore the screen in the state it was before `InitVideo` was called. Particularly, the `VideoBuf` and `OldVideoBuf` arrays are no longer valid after a call to `DoneVideo`.

The `DoneVideo` should always be called if `InitVideo` was called. Failing to do so may leave the screen in an unusable state after the program exits.

For an example, see most other functions.

Errors: Normally none. If the driver reports an error, this is done through the `ErrorCode` variable.

See also: `InitVideo` ([2201](#))

87.6.4 GetCapabilities

Synopsis: Get current driver capabilities.

Declaration: `function GetCapabilities : Word`

Visibility: default

Description: `GetCapabilities` returns the capabilities of the current driver. It is an or-ed combination of the following constants:

cpUnderLine Video driver supports underline attribute

cpBlink Video driver supports blink attribute

cpColor Video driver supports color

cpChangeFont Video driver supports changing screen font.

cpChangeMode Video driver supports changing mode

cpChangeCursor Video driver supports changing cursor shape.

Note that the video driver should not yet be initialized to use this function. It is a property of the driver.

Errors: None.

See also: [GetCursorType \(2197\)](#), [GetVideoDriver \(2199\)](#)

Listing: ./examples/videoex/ex4.pp

Program Example4;

{ Program to demonstrate the GetCapabilities function. }

Uses video;

Var

W: Word;

Procedure TestCap(Cap: Word; Msg : **String**);

begin

Write(Msg, ' : ');

If (W **and** Cap=Cap) **then**

WriteLn('Yes')

else

WriteLn('No');

end;

begin

 W:= GetCapabilities;

WriteLn('Video driver supports following functionality');

 TestCap(cpUnderLine, 'Underlined characters');

 TestCap(cpBlink, 'Blinking characters');

 TestCap(cpColor, 'Color characters');

 TestCap(cpChangeFont, 'Changing font');

 TestCap(cpChangeMode, 'Changing video mode');

 TestCap(cpChangeCursor, 'Changing cursor shape');

end.

87.6.5 GetCursorType

Synopsis: Get screen cursor type

Declaration: `function GetCursorType : Word`

Visibility: default

Description: `GetCursorType` returns the current cursor type. It is one of the following values:

crHiddenHide cursor

crUnderLineUnderline cursor

crBlockBlock cursor

crHalfBlockHalf block cursor

Note that not all drivers support all types of cursors.

Errors: None.

See also: [SetCursorType \(2203\)](#), [GetCapabilities \(2196\)](#)

Listing: ./examples/videoex/ex5.pp

Program Example5;

{ Program to demonstrate the GetCursorType function. }

Uses video, keyboard, vidutil;

Const

CursorTypes : **Array**[crHidden..crHalfBlock] **of string** =
('Hidden', 'UnderLine', 'Block', 'HalfBlock');

begin

InitVideo;
InitKeyboard;
TextOut(1,1, 'Cursor type: '+CursorTypes[GetCursorType]);
TextOut(1,2, 'Press any key to exit.');

UpdateScreen(False);

GetKeyEvent;

DoneKeyboard;

DoneVideo;

end.

87.6.6 GetLockScreenCount

Synopsis: Get the screen lock update count.

Declaration: function GetLockScreenCount : Integer

Visibility: default

Description: GetLockScreenCount returns the current lock level. When the lock level is zero, a call to UpdateScreen (2205) will actually update the screen.

Errors: None.

See also: LockScreenUpdate (2202), UnlockScreenUpdate (2204), UpdateScreen (2205)

Listing: ./examples/videoex/ex6.pp

Program Example6;

{ Program to demonstrate the GetLockScreenCount function. }

Uses video, keyboard, vidutil;

Var

I : Longint;

S : **String**;

begin

InitVideo;

InitKeyboard;

TextOut(1,1, 'Press key till new text appears.');

UpdateScreen(False);

Randomize;

For I:=0 **to** Random(10)+1 **do**

LockScreenUpdate;

```

I:=0;
While GetLockScreenCount<>0 do
begin
  Inc(I);
  Str(I,S);
  UnlockScreenUpdate;
  GetKeyEvent;
  TextOut(1,1,'UnLockScreenUpdate had to be called '+S+' times');
  UpdateScreen(False);
end;
TextOut(1,2,'Press any key to end. ');
UpdateScreen(False);
GetKeyEvent;
DoneKeyboard;
DoneVideo;
end.

```

87.6.7 GetVideoDriver

Synopsis: Get a copy of the current video driver.

Declaration: `procedure GetVideoDriver(var Driver: TVideoDriver)`

Visibility: default

Description: `GetVideoDriver` returns the currently active video driver record in `Driver`. It can be used to clone the current video driver, or to override certain parts of it using the `SetVideoDriver` (2204) call.

Errors: None.

See also: `SetVideoDriver` (2204)

87.6.8 GetVideoMode

Synopsis: Return current video mode

Declaration: `procedure GetVideoMode(var Mode: TVideoMode)`

Visibility: default

Description: `GetVideoMode` returns the settings of the currently active video mode. The `row`, `col` fields indicate the dimensions of the current video mode, and `Color` is true if the current video supports colors.

See also: `SetVideoMode` (2204), `GetVideoModeData` (2201)

Listing: `./examples/videoex/ex7.pp`

Program Example7;

{ Program to demonstrate the GetVideoMode function. }

Uses video, keyboard, vidutil;

Var

 M : TVideoMode;
 S : **String**;

```

begin
  InitVideo;
  InitKeyboard;
  GetVideoMode(M);
  if M.Color then
    TextOut(1,1,'Current mode has color')
  else
    TextOut(1,1,'Current mode does not have color');
  Str(M.Row,S);
  TextOut(1,2,'Number of rows    : '+S);
  Str(M.Col,S);
  TextOut(1,3,'Number of columns : '+S);
  Textout(1,4,'Press any key to exit. ');
  UpdateScreen(False);
  GetKeyEvent;
  DoneKeyboard;
  DoneVideo;
end.

```

87.6.9 GetVideoModeCount

Synopsis: Get the number of video modes supported by the driver.

Declaration: `function GetVideoModeCount : Word`

Visibility: default

Description: `GetVideoModeCount` returns the number of video modes that the current driver supports. If the driver does not support switching of modes, then 1 is returned.

This function can be used in conjunction with the `GetVideoModeData` (2201) function to retrieve data for the supported video modes.

Errors: None.

See also: `GetVideoModeData` (2201), `GetVideoMode` (2199)

Listing: `./examples/videoex/ex8.pp`

Program Example8;

{ Program to demonstrate the GetVideoModeCount function. }

Uses video, keyboard, vidutil;

Procedure DumpMode (M : TVideoMode; Index : Integer);

Var

S : String;

begin

Str(Index:2,S);

inc(Index);

TextOut(1,Index,'Data for mode '+S+': ');

if M.Color then

TextOut(19,Index,' color,')

else

```

    TextOut(19,Index,'No color,');
    Str(M.Row:3,S);
    TextOut(28,Index,S+' rows');
    Str(M.Col:3,S);
    TextOut(36,index,S+' columns');
end;

Var
    i,Count : Integer;
    m : TVideoMode;

begin
    InitVideo;
    InitKeyboard;
    Count:=GetVideoModeCount;
    For I:=1 to Count do
        begin
            GetVideoModeData(I-1,M);
            DumpMode(M,I-1);
        end;
    TextOut(1,Count+1,'Press any key to exit');
    UpdateScreen(False);
    GetKeyEvent;
    DoneKeyboard;
    DoneVideo;
end.

```

87.6.10 GetVideoModeData

Synopsis: Get the specifications for a video mode

Declaration: `function GetVideoModeData(Index: Word; var Data: TVideoMode) : Boolean`

Visibility: default

Description: `GetVideoModeData` returns the characteristics of the `Index`-th video mode in `Data`. `Index` is zero based, and has a maximum value of `GetVideoModeCount-1`. If the current driver does not support setting of modes (`GetVideoModeCount=1`) and `Index` is zero, the current mode is returned.

The function returns `True` if the mode data was retrieved successfully, `False` otherwise.

For an example, see `GetVideoModeCount` ([2200](#)).

Errors: In case `Index` has a wrong value, `False` is returned.

See also: `GetVideoModeCount` ([2200](#)), `SetVideoMode` ([2204](#)), `GetVideoMode` ([2199](#))

87.6.11 InitVideo

Synopsis: Initialize video driver.

Declaration: `procedure InitVideo`

Visibility: default

Description: `InitVideo` initializes the video subsystem. If the video system was already initialized, it does nothing. After the driver has been initialized, the `VideoBuf` and `OldVideoBuf` pointers are

initialized, based on the `ScreenWidth` and `ScreenHeight` variables. When this is done, the screen is cleared.

For an example, see most other functions.

Errors: if the driver fails to initialize, the `ErrorCode` variable is set.

See also: `DoneVideo` (2196)

87.6.12 LockScreenUpdate

Synopsis: Prevent further screen updates.

Declaration: `procedure LockScreenUpdate`

Visibility: `default`

Description: `LockScreenUpdate` increments the screen update lock count with one. As long as the screen update lock count is not zero, `UpdateScreen` (2205) will not actually update the screen.

This function can be used to optimize screen updating: If a lot of writing on the screen needs to be done (by possibly unknown functions), calling `LockScreenUpdate` before the drawing, and `UnlockScreenUpdate` (2204) after the drawing, followed by a `UpdateScreen` (2205) call, all writing will be shown on screen at once.

For an example, see `GetLockScreenCount` (2198).

Errors: None.

See also: `UpdateScreen` (2205), `UnlockScreenUpdate` (2204), `GetLockScreenCount` (2198)

87.6.13 SetCursorPos

Synopsis: Set write cursor position.

Declaration: `procedure SetCursorPos (NewCursorX: Word; NewCursorY: Word)`

Visibility: `default`

Description: `SetCursorPos` positions the cursor on the given position: Column `NewCursorX` and row `NewCursorY`. The origin of the screen is the upper left corner, and has coordinates `(0, 0)`.

The current position is stored in the `CursorX` and `CursorY` variables.

Errors: None.

See also: `SetCursorType` (2203)

Listing: `./examples/videoex/ex2.pp`

```

program example2;

uses video , keyboard ;

Var
  P,PP,D : Integer;
  K: TKeyEvent;

  Procedure PutSquare (P : INteger; C : Char);

begin
```

```

    VideoBuf^[P]:=Ord(C)+($07 shl 8);
    VideoBuf^[P+ScreenWidth]:=Ord(c)+($07 shl 8);
    VideoBuf^[P+1]:=Ord(c)+($07 shl 8);
    VideoBuf^[P+ScreenWidth+1]:=Ord(c)+($07 shl 8);
end;

begin
    InitVideo;
    InitKeyBoard;
    P:=0;
    PP:=-1;
    Repeat
        If PP<>-1 then
            PutSquare(PP, ' ');
        PutSquare(P, '#');
        SetCursorPos(P Mod ScreenWidth,P div ScreenWidth);
        UpdateScreen(False);
        PP:=P;
        Repeat
            D:=0;
            K:=TranslateKeyEvent(GetKeyEvent);
            Case GetKeyEventCode(K) of
                kbdLeft : If (P Mod ScreenWidth)<>0 then
                    D:=-1;
                kbdUp : If P>=ScreenWidth then
                    D:=-ScreenWidth;
                kbdRight : If ((P+2) Mod ScreenWidth)<>0 then
                    D:=1;
                kbdDown : if (P<(VideoBufSize div 2)-(ScreenWidth*2)) then
                    D:=ScreenWidth;
            end;
            Until (D<>0) or (GetKeyEventChar(K)='q');
            P:=P+D;
        until GetKeyEventChar(K)='q';
        DoneKeyBoard;
        DoneVideo;
    end.

```

87.6.14 SetCursorType

Synopsis: Set cursor type

Declaration: `procedure SetCursorType(NewType: Word)`

Visibility: default

Description: `SetCursorType` sets the cursor to the type specified in `NewType`.

crHidden Hide cursor

crUnderLine Underline cursor

crBlock Block cursor

crHalfBlock Half block cursor

Errors: None.

See also: `SetCursorPos` ([2202](#))

87.6.15 SetVideoDriver

Synopsis: Install a new video driver.

Declaration: `function SetVideoDriver(const Driver: TVideoDriver) : Boolean`

Visibility: default

Description: `SetVideoDriver` sets the videodriver to be used to `Driver`. If the current videodriver is initialized (after a call to `InitVideo`) then it does nothing and returns `False`.

A new driver can only be installed if the previous driver was not yet activated (i.e. before a call to `InitVideo` (2201)) or after it was deactivated (i.e after a call to `DoneVideo`).

For more information about installing a videodriver, see `viddriver` (2186).

For an example, see the section on writing a custom video driver.

Errors: If the current driver is initialized, then `False` is returned.

See also: `viddriver` (2186)

87.6.16 SetVideoMode

Synopsis: Set current video mode.

Declaration: `function SetVideoMode(const Mode: TVideoMode) : Boolean`

Visibility: default

Description: `SetVideoMode` sets the video mode to the mode specified in `Mode`:

If the call was successful, then the screen will have `Col` columns and `Row` rows, and will be displaying in color if `Color` is `True`.

The function returns `True` if the mode was set successfully, `False` otherwise.

Note that the video mode may not always be set. E.g. a console on Linux or a telnet session cannot always set the mode. It is important to check the error value returned by this function if it was not successful.

The mode can be set when the video driver has not yet been initialized (i.e. before `InitVideo` (2201) was called) In that case, the video mode will be stored, and after the driver was initialized, an attempt will be made to set the requested mode. Changing the video driver before the call to `InitVideo` will clear the stored video mode.

To know which modes are valid, use the `GetVideoModeCount` (2200) and `GetVideoModeData` (2201) functions. To retrieve the current video mode, use the `GetVideoMode` (2199) procedure.

Errors: If the specified mode cannot be set, then `errVioNoSuchMode` may be set in `ErrorCode`

See also: `GetVideoModeCount` (2200), `GetVideoModeData` (2201), `GetVideoMode` (2199)

87.6.17 UnlockScreenUpdate

Synopsis: Unlock screen update.

Declaration: `procedure UnlockScreenUpdate`

Visibility: default

Description: `UnlockScreenUpdate` decrements the screen update lock count with one if it is larger than zero. When the lock count reaches zero, the `UpdateScreen` (2205) will actually update the screen. No screen update will be performed as long as the screen update lock count is nonzero. This mechanism can be used to increase screen performance in case a lot of writing is done.

It is important to make sure that each call to `LockScreenUpdate` (2202) is matched by exactly one call to `UnlockScreenUpdate`

For an example, see `GetLockScreenCount` (2198).

Errors: None.

See also: `LockScreenUpdate` (2202), `GetLockScreenCount` (2198), `UpdateScreen` (2205)

87.6.18 UpdateScreen

Synopsis: Update physical screen with internal screen image.

Declaration: `procedure UpdateScreen(Force: Boolean)`

Visibility: default

Description: `UpdateScreen` synchronizes the actual screen with the contents of the `VideoBuf` internal buffer. The parameter `Force` specifies whether the whole screen has to be redrawn (`Force=True`) or only parts that have changed since the last update of the screen.

The `Video` unit keeps an internal copy of the screen as it last wrote it to the screen (in the `OldVideoBuf` array). The current contents of `VideoBuf` are examined to see what locations on the screen need to be updated. On slow terminals (e.g. a Linux telnet session) this mechanism can speed up the screen redraw considerably.

On platforms where mouse cursor visibility is not guaranteed to be preserved during screen updates this routine has to restore the mouse cursor after the update (usually by calling `HideMouse` from unit `Mouse` before the real update and `ShowMouse` afterwards).

For an example, see most other functions.

Errors: None.

See also: `ClearScreen` (2195)

87.7 TVideoDriver

```
TVideoDriver = record
  InitDriver : procedure;
  DoneDriver : procedure
;
  UpdateScreen : procedure(Force: Boolean);
  ClearScreen : procedure
;
  SetVideoMode : function(const Mode: TVideoMode) : Boolean;
  GetVideoModeCount
  : function : Word;
  GetVideoModeData : function(Index: Word; var
  Data: TVideoMode) : Boolean;
  SetCursorPos : procedure(NewCursorX
  : Word; NewCursorY: Word);
  GetCursorType : function : Word;
```

```
SetCursorType
: procedure (NewType: Word);
GetCapabilities : function : Word;
end
```

`TVideoDriver` record can be used to install a custom video driver, with the `SetVideoDriver` [\(2204\)](#) call.

An explanation of all fields can be found there.

87.8 TVideoMode

```
TVideoMode = record
  Col : Word;
  Row : Word;
  Color : Boolean
;
end
```

The `TVideoMode` record describes a videomode. Its fields are self-explaining: `Col`, `Row` describe the number of columns and rows on the screen for this mode. `Color` is `True` if this mode supports colors, or `False` if not.

Chapter 88

Reference for unit 'WinCRT'

88.1 Used units

Table 88.1: Used units by unit 'WinCRT'

Name	Page
System	1339

88.2 Overview

The `wincrt` unit provides some auxiliary routines for use with the `graph` ([845](#)) unit, namely keyboard support. It has no connection with the `crt` ([562](#)) unit, nor with the Turbo-Pascal for Windows `WinCrt` unit. As such, it should not be used by end users. Refer to the `crt` ([562](#)) unit instead.

88.3 Constants, types and variables

88.3.1 Variables

`directvideo` : Boolean

On windows, this variable is ignored.

`lastmode` : Word

Is supposed to contain the last used video mode, but is actually unused.

88.4 Procedures and functions

88.4.1 `delay`

Synopsis: Pause program execution

Declaration: `procedure delay(ms: Word)`

Visibility: default

Description: Delay stops program execution for the indicated number ms of milliseconds.

See also: sound ([2208](#)), nosound ([2208](#))

88.4.2 keypressed

Synopsis: Check if a key was pressed.

Declaration: `function keypressed : Boolean`

Visibility: default

Description: KeyPressed returns True if the user pressed a key, or False if not. It does not wait for the user to press a key.

See also: readkey ([2208](#))

88.4.3 nosound

Synopsis: Stop the speaker

Declaration: `procedure nosound`

Visibility: default

Description: NoSound does nothing, windows does not support this.

See also: sound ([2208](#))

88.4.4 readkey

Synopsis: Read a key from the keyboard

Declaration: `function readkey : Char`

Visibility: default

Description: ReadKey reads a key from the keyboard, and returns the ASCII value of the key, or the scancode of the key in case it is a special key.

The function waits until a key is pressed.

See also: KeyPressed ([2208](#))

88.4.5 sound

Synopsis: Sound PC speaker

Declaration: `procedure sound(hz: Word)`

Visibility: default

Description: Sound sounds the PC speaker. It emits a tone with frequency Hz for 500 milliseconds. (the time argument is required by the windows API)

See also: nosound ([2208](#))

88.4.6 **textmode**

Synopsis: Set indicated text mode

Declaration: `procedure textmode(mode: Integer)`

Visibility: `default`

Description: `TextMode` does nothing.

Chapter 89

Reference for unit 'WinDirs'

89.1 Used units

Table 89.1: Used units by unit 'WinDirs'

Name	Page
System	1339

89.2 Overview

This unit contains only one function: `GetWindowsSpecialDir` ([2224](#)). It is a simple pascal wrapper around the `shfolder.dll` library, and is available under Windows only.

89.3 Constants, types and variables

89.3.1 Constants

`CSIDL_ADMINTOOLS` = `$0030`

ID for the personal "Start Menu\Programs\Administrative tools" folder (In the user's personal folder)

`CSIDL_APPDATA` = `$001A`

ID for the roaming "Application Data" folder (in the user's personal folder)

`CSIDL_CDBURN_AREA` = `$003B`

ID for the personal "Local Settings\Application Data\Microsoft\CD Burning" folder (Under "All users" folder)

`CSIDL_COMMON_ADMINTOOLS` = `$002F`

ID for the common "Start Menu\Programs\Administrative tools" folder (Under "All users" folder)

CSIDL_COMMON_APPDATA = \$0023

ID for the common "Application Data" folder (Under "All users" folder)

CSIDL_COMMON_DESKTOPDIRECTORY = \$0019

ID for the public "Desktop" folder (Under "All users" folder)

CSIDL_COMMON_DOCUMENTS = \$002E

ID for the common "Documents" folder (Under "All users" folder)

CSIDL_COMMON_FAVORITES = \$001F

ID for the public "Favorites" folder (Under "All users" folder)

CSIDL_COMMON_MUSIC = \$0035

ID for the common "Documents\My Music" folder (Under "All users" folder)

CSIDL_COMMON_PICTURES = \$0036

ID for the common "Documents\My Pictures" folder (Under "All users" folder)

CSIDL_COMMON_PROGRAMS = \$0017

ID for the public "Programs" folder (Under "All users" Start menu folder)

CSIDL_COMMON_STARTMENU = \$0016

ID for the public "Start Menu" folder (Under "All users")

CSIDL_COMMON_STARTUP = \$0018

ID for the public "Startup" folder (Under "All users\Start menu\Programs" folder)

CSIDL_COMMON_TEMPLATES = \$002D

ID for the common "Templates" folder (Under "All users" folder)

CSIDL_COMMON_VIDEO = \$0037

ID for the common "Documents\My Video" folder (Under "All users" folder)

CSIDL_COOKIES = \$0021

ID for the "Cookies" folder (in the user's personal folder)

CSIDL_DESKTOPDIRECTORY = \$0010

ID for the "Desktop" folder (in the user's personal folder)

CSIDL_FAVORITES = \$0006

ID for the "Favourites" folder (in the user's personal folder)

CSIDL_FLAG_CREATE = \$8000

Flag to specify if the requested folder must be created if it didn't exist yet.

CSIDL_FONTS = \$0014

CSIDL_HISTORY = \$0022

ID for the "History" folder (in the user's personal folder)

CSIDL_INTERNET_CACHE = \$0020

ID for the "Temporary Internet Files" folder (in the user's personal folder)

CSIDL_LOCAL_APPDATA = \$001C

ID for the local "Application Data" folder (in the user's personal folder)

CSIDL_MYMUSIC = \$000D

ID for the "My Music" folder (in the user's personal folder)

CSIDL_MYPICTURES = \$0027

ID for the "My Pictures" folder (in the user's personal folder)

CSIDL_MYVIDEO = \$000E

ID for the "My Videos" folder (in the user's personal folder)

CSIDL_NETHOOD = \$0013

ID for the "Nethood" folder (in the user's personal folder)

CSIDL_PERSONAL = \$0005

ID for the "My Documents" folder (in the user's personal folder)

CSIDL_PRINTHOOD = \$001B

ID for the "Printhood" folder (in the user's personal folder)

CSIDL_PROFILE = \$0028

ID for the user's personal folder

CSIDL_PROFILES = \$003E

ID for the parent folder for the user's folders

CSIDL_PROGRAMS = \$0002

ID for the "Program files" folder

CSIDL_PROGRAM_FILES = \$0026

ID for the "Program Files" folder (alias for CSIDL_PROGRAMS)

CSIDL_PROGRAM_FILES_COMMON = \$002B

ID for the Common folder under the "Program Files" folder.

CSIDL_RECENT = \$0008

ID for the "Recent" folder (in the user's personal folder)

CSIDL_SENDTO = \$0009

ID for the "Send to" folder (in the user's personal folder)

CSIDL_STARTMENU = \$000B

ID for the "Start menu" folder (in the user's personal folder)

CSIDL_STARTUP = \$0007

ID for the "Startup" menu folder (in the user's personal folder)

CSIDL_SYSTEM = \$0025

ID for the Windows System32 dir.

CSIDL_TEMPLATES = \$0015

ID for the "Templates" folder (in the user's personal folder)

CSIDL_WINDOWS = \$0024

ID for the Windows installation dir.

FOLDERID_AccountPictures : TGuid =
'{008CA0B1-55B4-4C56-B8A8-4DE4B299D3BE}'

FOLDERID_AddNewPrograms : TGuid =
'{DE61D971-5EBC-4F02-A3A9-6C82895E5C04}'

FOLDERID_AdminTools : TGuid =
'{724EF170-A42D-4FEF-9F26-B60E846FBA4F}'

FOLDERID_AllAppMods : TGuid =
'{7AD67899-66AF-43BA-9156-6AAD42E6C596}'

FOLDERID_AppCaptures : TGuid =
'{EDC0FE71-98D8-4F4A-B920-C8DC133CB165}'

FOLDERID_AppDataDesktop : TGuid =
'{B2C5E279-7ADD-439F-B28C-C41FE1BBF672}'

FOLDERID_AppDataDocuments : TGuid =
'{7BE16610-1F7F-44AC-BFF0-83E15F2FFCA1}'

FOLDERID_AppDataFavorites : TGuid =
'{7CFBEFBC-DE1F-45AA-B843-A542AC536CC9}'

FOLDERID_AppDataProgramData : TGuid =
'{559D40A3-A036-40FA-AF61-84CB430A4D34}'

FOLDERID_ApplicationShortcuts : TGuid =
'{A3918781-E5F2-4890-B3D9-A7E54332328C}'

FOLDERID_AppsFolder : TGuid =
'{1E87508D-89C2-42F0-8A7E-645A0F50CA58}'

FOLDERID_AppUpdates : TGuid =
'{A305CE99-F527-492B-8B1A-7E76FA98D6E4}'

FOLDERID_CameraRoll : TGuid =
'{AB5FB87B-7CE2-4F83-915D-550846C9537B}'

FOLDERID_CameraRollLibrary : TGuid =
'{2B20DF75-1EDA-4039-8097-38798227D5B7}'

FOLDERID_CDBurning : TGuid =
'{9E52AB10-F80D-49DF-ACB8-4330F5687855}'

FOLDERID_ChangeRemovePrograms : TGuid =
'{DF7266AC-9274-4867-8D55-3BD661DE872D}'

FOLDERID_CommonAdminTools : TGuid =
'{D0384E7D-BAC3-4797-8F14-CBA229B392B5}'

FOLDERID_CommonOEMLinks : TGuid =
'{C1BAE2D0-10DF-4334-BEDD-7AA20B227A9D}'

FOLDERID_CommonPrograms : TGuid =
'{0139D44E-6AFE-49F2-8690-3DAFCAE6FFB8}'

FOLDERID_CommonStartMenu : TGuid =
'{A4115719-D62E-491D-AA7C-E74B8BE3B067}'

FOLDERID_CommonStartMenuPlaces : TGuid =
'{A440879F-87A0-4F7D-B700-0207B966194A}'

FOLDERID_CommonStartup : TGuid =
'{82A5EA35-D9CD-47C5-9629-E15D2F714E6E}'

FOLDERID_CommonTemplates : TGuid =
'{B94237E7-57AC-4347-9151-B08C6C32D1F7}'

FOLDERID_ComputerFolder : TGuid =
'{0AC0837C-BBF8-452A-850D-79D08E667CA7}'

FOLDERID_ConflictFolder : TGuid =
'{4BFEFB45-347D-4006-A5BE-AC0CB0567192}'

FOLDERID_ConnectionsFolder : TGuid =
'{6F0CD92B-2E97-45D1-88FF-B0D186B8DEDD}'

FOLDERID_Contacts : TGuid =
'{56784854-C6CB-462B-8169-88E350ACB882}'

FOLDERID_ControlPanelFolder : TGuid =
'{82A74AEB-AEB4-465C-A014-D097EE346D63}'

FOLDERID_Cookies : TGuid =
'{2B0F765D-C0E9-4171-908E-08A611B84FF6}'

FOLDERID_CurrentAppMods : TGuid =
'{3DB40B20-2A30-4DBE-917E-771DD21DD099}'

FOLDERID_Desktop : TGuid =
'{B4BFCC3A-DB2C-424C-B029-7FE99A87C641}'

FOLDERID_DevelopmentFiles : TGuid =
'{DBE8E08E-3053-4BBC-B183-2A7B2B191E59}'

FOLDERID_Device : TGuid =
'{1C2AC1DC-4358-4B6C-9733-AF21156576F0}'

FOLDERID_DeviceMetadataStore : TGuid =
'{5CE4A5E9-E4EB-479D-B89F-130C02886155}'

FOLDERID_Documents : TGuid =
'{FDD39AD0-238F-46AF-ADB4-6C85480369C7}'

FOLDERID_DocumentsLibrary : TGuid =
'{7B0DB17D-9CD2-4A93-9733-46CC89022E7C}'

FOLDERID_Downloads : TGuid =
'{374DE290-123F-4565-9164-39C4925E467B}'

FOLDERID_Favorites : TGuid =
'{1777F761-68AD-4D8A-87BD-30B759FA33DD}'

FOLDERID_Fonts : TGuid = '{FD228CB7-AE11-4AE3-864C-16F3910AB8FE}'

FOLDERID_Games : TGuid = '{CAC52C1A-B53D-4EDC-92D7-6B2E8AC19434}'

FOLDERID_GameTasks : TGuid =
'{054FAE61-4DD8-4787-80B6-090220C4B700}'

FOLDERID_History : TGuid =
'{D9DC8A3B-B784-432E-A781-5A1130A75963}'

FOLDERID_HomeGroup : TGuid =
'{52528A6B-B9E3-4ADD-B60D-588C2DBA842D}'

FOLDERID_HomeGroupCurrentUser : TGuid =
'{9B74B6A3-0DFD-4F11-9E78-5F7800F2E772}'

```
FOLDERID_ImplicitAppShortcuts : TGuid =
    '{BCB5256F-79F6-4CEE-B725-DC34E402FD46}'

FOLDERID_InternetCache : TGuid =
    '{352481E8-33BE-4251-BA85-6007CAEDCF9D}'

FOLDERID_InternetFolder : TGuid =
    '{4D9F7874-4E0C-4904-967B-40B0D20C3E4B}'

FOLDERID_Libraries : TGuid =
    '{1B3EA5DC-B587-4786-B4EF-BD1DC332AEAE}'

FOLDERID_Links : TGuid = '{BFB9D5E0-C6A9-404C-B2B2-AE6DB6AF4968}'

FOLDERID_LocalAppData : TGuid =
    '{F1B32785-6FBA-4FCF-9D55-7B8E7F157091}'

FOLDERID_LocalAppDataLow : TGuid =
    '{A520A1A4-1780-4FF6-BD18-167343C5AF16}'

FOLDERID_LocalDocuments : TGuid =
    '{F42EE2D3-909F-4907-8871-4C22FC0BF756}'

FOLDERID_LocalDownloads : TGuid =
    '{7D83EE9B-2244-4E70-B1F5-5393042AF1E4}'

FOLDERID_LocalizedResourcesDir : TGuid =
    '{2A00375E-224C-49DE-B8D1-440DF7EF3DDC}'

FOLDERID_LocalMusic : TGuid =
    '{A0C69A99-21C8-4671-8703-7934162FCF1D}'

FOLDERID_LocalPictures : TGuid =
    '{0DDD015D-B06C-45D5-8C4C-F59713854639}'

FOLDERID_LocalVideos : TGuid =
    '{35286A68-3C57-41A1-BBB1-0EAE73D76C95}'

FOLDERID_Music : TGuid = '{4BD8D571-6D19-48D3-BE97-422220080E43}'
```

```

FOLDERID_MusicLibrary : TGuid =
    '{2112AB0A-C86A-4FFE-A368-0DE96E47012E}'

FOLDERID_NetHood : TGuid =
    '{C5ABBF53-E17F-4121-8900-86626FC2C973}'

FOLDERID_NetworkFolder : TGuid =
    '{D20BEEC4-5CA8-4905-AE3B-BF251EA09B53}'

FOLDERID_Objects3D : TGuid =
    '{31C0DD25-9439-4F12-BF41-7FF4EDA38722}'

FOLDERID_OneDrive : TGuid =
    '{A52BBA46-E9E1-435F-B3D9-28DAA648C0F6}'

FOLDERID_OriginalImages : TGuid =
    '{2C36C0AA-5812-4B87-BFD0-4CD0DFB19B39}'

FOLDERID_PhotoAlbums : TGuid =
    '{69D2CF90-FC33-4FB7-9A0C-EBB0F0FCB43C}'

FOLDERID_Pictures : TGuid =
    '{33E28130-4E1E-4676-835A-98395C3BC3BB}'

FOLDERID_PicturesLibrary : TGuid =
    '{A990AE9F-A03B-4E80-94BC-9912D7504104}'

FOLDERID_Playlists : TGuid =
    '{DE92C1C7-837F-4F69-A3BB-86E631204A23}'

FOLDERID_PrintersFolder : TGuid =
    '{76FC4E2D-D6AD-4519-A663-37BD56068185}'

FOLDERID_PrintHood : TGuid =
    '{9274BD8D-CFD1-41C3-B35E-B13F55A758F4}'

FOLDERID_Profile : TGuid =
    '{5E6C858F-0E22-4760-9AFE-EA3317B67173}'

FOLDERID_ProgramData : TGuid =
    '{62AB5D82-FDC1-4DC3-A9DD-070D1D495D97}'

```

FOLDERID_ProgramFiles : TGuid =
'{905E63B6-C1BF-494E-B29C-65B732D3D21A}'

FOLDERID_ProgramFilesCommon : TGuid =
'{F7F1ED05-9F6D-47A2-AAAE-29D317C6F066}'

FOLDERID_ProgramFilesCommonX64 : TGuid =
'{6365D5A7-0F0D-45E5-87F6-0DA56B6A4F7D}'

FOLDERID_ProgramFilesCommonX86 : TGuid =
'{DE974D24-D9C6-4D3E-BF91-F4455120B917}'

FOLDERID_ProgramFilesX64 : TGuid =
'{6D809377-6AF0-444B-8957-A3773F02200E}'

FOLDERID_ProgramFilesX86 : TGuid =
'{7C5A40EF-A0FB-4BFC-874A-C0F2E0B9FA8E}'

FOLDERID_Programs : TGuid =
'{A77F5D77-2E2B-44C3-A6A2-ABA601054A51}'

FOLDERID_Public : TGuid =
'{DFDF76A2-C82A-4D63-906A-5644AC457385}'

FOLDERID_PublicDesktop : TGuid =
'{C4AA340D-F20F-4863-AFEF-F87EF2E6BA25}'

FOLDERID_PublicDocuments : TGuid =
'{ED4824AF-DCE4-45A8-81E2-FC7965083634}'

FOLDERID_PublicDownloads : TGuid =
'{3D644C9B-1FB8-4F30-9B45-F670235F79C0}'

FOLDERID_PublicGameTasks : TGuid =
'{DEBF2536-E1A8-4C59-B6A2-414586476AEA}'

FOLDERID_PublicLibraries : TGuid =
'{48DAF80B-E6CF-4F4E-B800-0E69D84EE384}'

FOLDERID_PublicMusic : TGuid =
'{3214FAB5-9757-4298-BB61-92A9DEAA44FF}'

```
FOLDERID_PublicPictures : TGuid =  
    '{B6EBFB86-6907-413C-9AF7-4FC2ABF07CC5}'
```

```
FOLDERID_PublicRingtones : TGuid =  
    '{E555AB60-153B-4D17-9F04-A5FE99FC15EC}'
```

```
FOLDERID_PublicUserTiles : TGuid =  
    '{0482AF6C-08F1-4C34-8C90-E17EC98B1E17}'
```

```
FOLDERID_PublicVideos : TGuid =  
    '{2400183A-6185-49FB-A2D8-4A392A602BA3}'
```

```
FOLDERID_QuickLaunch : TGuid =  
    '{52A4F021-7B75-48A9-9F6B-4B87A210BC8F}'
```

```
FOLDERID_Recent : TGuid =  
    '{AE50C081-EBD2-438A-8655-8A092E34987A}'
```

```
FOLDERID_RecordedCalls : TGuid =  
    '{2F8B40C2-83ED-48EE-B383-A1F157EC6F9A}'
```

```
FOLDERID_RecordedTVLibrary : TGuid =  
    '{1A6FDBA2-F42D-4358-A798-B74D745926C5}'
```

```
FOLDERID_RecycleBinFolder : TGuid =  
    '{B7534046-3ECB-4C18-BE4E-64CD4CB7D6AC}'
```

```
FOLDERID_ResourceDir : TGuid =  
    '{8AD10C31-2ADB-4296-A8F7-E4701232C972}'
```

```
FOLDERID_RetailDemo : TGuid =  
    '{12D4C69E-24AD-4923-BE19-31321C43A767}'
```

```
FOLDERID_Ringtones : TGuid =  
    '{C870044B-F49E-4126-A9C3-B52A1FF411E8}'
```

```
FOLDERID_RoamedTileImages : TGuid =  
    '{AAA8D5A5-F1D6-4259-BAA8-78E7EF60835E}'
```

```
FOLDERID_RoamingAppData : TGuid =  
    '{3EB685DB-65F9-4CF6-A03A-E3EF65729F3D}'
```

```

FOLDERID_RoamingTiles : TGuid =
    '{00BCFC5A-ED94-4E48-96A1-3F6217F21990}'

FOLDERID_SampleMusic : TGuid =
    '{B250C668-F57D-4EE1-A63C-290EE7D1AA1F}'

FOLDERID_SamplePictures : TGuid =
    '{C4900540-2379-4C75-844B-64E6FAF8716B}'

FOLDERID_SamplePlaylists : TGuid =
    '{15CA69B3-30EE-49C1-ACE1-6B5EC372AFB5}'

FOLDERID_SampleVideos : TGuid =
    '{859EAD94-2E85-48AD-A71A-0969CB56A6CD}'

FOLDERID_SavedGames : TGuid =
    '{4C5C32FF-BB9D-43B0-B5B4-2D72E54EAAA4}'

FOLDERID_SavedPictures : TGuid =
    '{3B193882-D3AD-4EAB-965A-69829D1FB59F}'

FOLDERID_SavedPicturesLibrary : TGuid =
    '{E25B5812-BE88-4BD9-94B0-29233477B6C3}'

FOLDERID_SavedSearches : TGuid =
    '{7D1D3A04-DEBB-4115-95CF-2F29DA2920DA}'

FOLDERID_Screenshots : TGuid =
    '{B7BEDE81-DF94-4682-A7D8-57A52620B86F}'

FOLDERID_SearchHistory : TGuid =
    '{0D4C3DB6-03A3-462F-A0E6-08924C41B5D4}'

FOLDERID_SearchHome : TGuid =
    '{190337D1-B8CA-4121-A639-6D472D16972A}'

FOLDERID_SearchTemplates : TGuid =
    '{7E636BFE-DFA9-4D5E-B456-D7B39851D8A9}'

FOLDERID_SEARCH_CSC : TGuid =
    '{EE32E446-31CA-4ABA-814F-A5EBD2FD6D5E}'

```

FOLDERID_SEARCH_MAPI : TGuid =
'{98EC0E18-2098-4D44-8644-66979315A281}'

FOLDERID_SendTo : TGuid =
'{8983036C-27C0-404B-8F08-102D10DCFD74}'

FOLDERID_SidebarDefaultParts : TGuid =
'{7B396E54-9EC5-4300-BE0A-2482EBAE1A26}'

FOLDERID_SidebarParts : TGuid =
'{A75D362E-50FC-4FB7-AC2C-A8BEAA314493}'

FOLDERID_SkyDrive : TGuid =
'{A52BBA46-E9E1-435F-B3D9-28DAA648C0F6}'

FOLDERID_SkyDriveCameraRoll : TGuid =
'{767E6811-49CB-4273-87C2-20F355E1085B}'

FOLDERID_SkyDriveDocuments : TGuid =
'{24D89E24-2F19-4534-9DDE-6A6671FBB8FE}'

FOLDERID_SkyDriveMusic : TGuid =
'{C3F2459E-80D6-45DC-BFEF-1F769F2BE730}'

FOLDERID_SkyDrivePictures : TGuid =
'{339719B5-8C47-4894-94C2-D8F77ADD44A6}'

FOLDERID_StartMenu : TGuid =
'{625B53C3-AB48-4EC1-BA1F-A1EF4146FC19}'

FOLDERID_StartMenuAllPrograms : TGuid =
'{F26305EF-6948-40B9-B255-81453D09C785}'

FOLDERID_Startup : TGuid =
'{B97D20BB-F46A-4C97-BA10-5E3608430854}'

FOLDERID_SyncManagerFolder : TGuid =
'{43668BF8-C14E-49B2-97C9-747784D784B7}'

FOLDERID_SyncResultsFolder : TGuid =
'{289A9A43-BE44-4057-A41B-587A76D7E7F9}'

```
FOLDERID_SyncSetupFolder : TGuid =
    '{0F214138-B1D3-4A90-BBA9-27CBC0C5389A}'
```

```
FOLDERID_System : TGuid =
    '{1AC14E77-02E7-4E5D-B744-2EB1AE5198B7}'
```

```
FOLDERID_SystemX86 : TGuid =
    '{D65231B0-B2F1-4857-A4CE-A8E7C6EA7D27}'
```

```
FOLDERID_Templates : TGuid =
    '{A63293E8-664E-48DB-A079-DF759E0509F7}'
```

```
FOLDERID_UserPinned : TGuid =
    '{9E3995AB-1F9C-4F13-B827-48B24B6C7174}'
```

```
FOLDERID_UserProfiles : TGuid =
    '{0762D272-C50A-4BB0-A382-697DCD729B80}'
```

```
FOLDERID_UserProgramFiles : TGuid =
    '{5CD7AEE2-2219-4A67-B85D-6C9CE15660CB}'
```

```
FOLDERID_UserProgramFilesCommon : TGuid =
    '{BCBD3057-CA5C-4622-B42D-BC56DB0AE516}'
```

```
FOLDERID_UsersFiles : TGuid =
    '{F3CE0F7C-4901-4ACC-8648-D5D44B04EF8F}'
```

```
FOLDERID_UsersLibraries : TGuid =
    '{A302545D-DEFF-464B-ABE8-61C8648D939B}'
```

```
FOLDERID_Videos : TGuid =
    '{18989B1D-99B5-455B-841C-AB7C74E4DDFC}'
```

```
FOLDERID_VideosLibrary : TGuid =
    '{491E922F-5643-4AF4-A7EB-4E7A138D8174}'
```

```
FOLDERID_Windows : TGuid =
    '{F38BF404-1D43-42F2-9305-67DE0B28FC23}'
```

```
KF_FLAG_CREATE = DWORD($8000)
```

```
KF_FLAG_DEFAULT = DWORD(0)
```


89.4 Procedures and functions

89.4.1 ConvertCSIDLtoFOLDERID

Declaration: `function ConvertCSIDLtoFOLDERID(CSIDL: Integer; out FOLDERID: TGuid)
: Boolean`

Visibility: default

89.4.2 ConvertFOLDERIDtoCSIDL

Declaration: `function ConvertFOLDERIDtoCSIDL(const FOLDERID: TGuid;
out CSIDL: Integer) : Boolean`

Visibility: default

89.4.3 GetWindowsSpecialDir

Synopsis: Get the location of a special directory.

Declaration: `function GetWindowsSpecialDir(ID: Integer; CreateIfNotExists: Boolean)
: string
function GetWindowsSpecialDir(const GUID: TGuid;
CreateIfNotExists: Boolean) : string`

Visibility: default

Description: `GetWindowsSpecialDir` can be used to to get the path of special folders on the Windows system. The locations are identified using one of the `CSIDL_*` constants. If the ID of a location is or-ed with the `CSIDL_FLAG_CREATE` constant, then the directory will be created if it didn't exist yet (and the user has sufficient rights to do so).

Errors: On error, an empty string is returned.

89.4.4 GetWindowsSpecialDirUnicode

Declaration: `function GetWindowsSpecialDirUnicode(ID: Integer;
CreateIfNotExists: Boolean)
: UnicodeString
function GetWindowsSpecialDirUnicode(const GUID: TGuid;
CreateIfNotExists: Boolean)
: UnicodeString`

Visibility: default

89.4.5 GetWindowsSystemDirectory

Declaration: `function GetWindowsSystemDirectory : string`

Visibility: default

89.4.6 GetWindowsSystemDirectoryUnicode

Declaration: `function GetWindowsSystemDirectoryUnicode : UnicodeString`

Visibility: `default`

Chapter 90

Reference for unit 'x86'

90.1 Used units

Table 90.1: Used units by unit 'x86'

Name	Page
BaseUnix	141
System	1339

90.2 Overview

The x86 unit contains some of the routines that were present in the 1.0.X Linux unit, and which were Intel (PC) architecture specific.

These calls have been preserved for compatibility, but should be considered deprecated: they are not portable and may not even work on future Linux versions.

90.3 Procedures and functions

90.3.1 fpIOperm

Synopsis: Set permission on IO ports

Declaration: `function fpIOperm(From: Cardinal; Num: Cardinal; Value: cint) : cint`

Visibility: default

Description: `fpIOperm` sets permissions on `Num` ports starting with port `From` to `Value`. The function returns zero if the call was successful, a nonzero value otherwise.

Note:

- This works ONLY as root.
- Only the first `0x03ff` ports can be set.
- When doing a `FpFork` ([190](#)), the permissions are reset. When doing a `FpExecVE` ([187](#)) they are kept.

Errors: Extended error information can be retrieved with `FpGetErrno` ([193](#))

90.3.2 fpIoPL

Synopsis: Set I/O privilege level

Declaration: `function fpIoPL(Level: cint) : cint`

Visibility: default

Description: `FpIoPL` sets the I/O privilege level. It is intended for completeness only, one should normally not use it.

90.3.3 ReadPort

Synopsis: Read data from a PC port

Declaration: `procedure ReadPort(Port: LongInt; var Value: Byte)`
`procedure ReadPort(Port: LongInt; var Value: LongInt)`
`procedure ReadPort(Port: LongInt; var Value: Word)`

Visibility: default

Description: `ReadPort` reads one Byte, Word or Longint from port `Port` into `Value`.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (2226) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (2226), `ReadPortB` (2227), `ReadPortW` (2228), `ReadPortL` (2228), `WritePort` (2228), `WritePortB` (2229), `WritePortL` (2229), `WritePortW` (2229)

90.3.4 ReadPortB

Synopsis: Read bytes from a PC port

Declaration: `function ReadPortB(Port: LongInt) : Byte`
`procedure ReadPortB(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortB` reads `Count` bytes from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` bytes.

The functional form of `ReadPortB` reads 1 byte from port `B` and returns the byte that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (2226) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (2226), `ReadPort` (2227), `ReadPortW` (2228), `ReadPortL` (2228), `WritePort` (2228), `WritePortB` (2229), `WritePortL` (2229), `WritePortW` (2229)

90.3.5 ReadPortL

Synopsis: Read longints from a PC port

Declaration: `function ReadPortL(Port: LongInt) : LongInt`
`procedure ReadPortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortL` reads `Count` longints from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` Longints.

The functional form of `ReadPortL` reads 1 longint from port `B` and returns the longint that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (2226) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (2226), `ReadPort` (2227), `ReadPortW` (2228), `ReadPortB` (2227), `WritePort` (2228), `WritePortB` (2229), `WritePortL` (2229), `WritePortW` (2229)

90.3.6 ReadPortW

Synopsis: Read Words from a PC port

Declaration: `function ReadPortW(Port: LongInt) : Word`
`procedure ReadPortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortW` reads `Count` words from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` words.

The functional form of `ReadPortW` reads 1 word from port `B` and returns the word that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (2226) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (2226), `ReadPort` (2227), `ReadPortB` (2227), `ReadPortL` (2228), `WritePort` (2228), `WritePortB` (2229), `WritePortL` (2229), `WritePortW` (2229)

90.3.7 WritePort

Synopsis: Write data to PC port

Declaration: `procedure WritePort(Port: LongInt; Value: Byte)`
`procedure WritePort(Port: LongInt; Value: LongInt)`
`procedure WritePort(Port: LongInt; Value: Word)`

Visibility: default

Description: `WritePort` writes `Value` – 1 byte, `Word` or longint – to port `Port`.

Remark You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (2226) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(2226\)](#), [WritePortB \(2229\)](#), [WritePortL \(2229\)](#), [WritePortW \(2229\)](#), [ReadPortB \(2227\)](#), [ReadPortL \(2228\)](#), [ReadPortW \(2228\)](#)

90.3.8 WritePortB

Synopsis: Write byte to PC port

Declaration: `procedure WritePortB(Port: LongInt; Value: Byte)`
`procedure WritePortB(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(2226\)](#) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(2226\)](#), [WritePort \(2228\)](#), [WritePortL \(2229\)](#), [WritePortW \(2229\)](#), [ReadPortB \(2227\)](#), [ReadPortL \(2228\)](#), [ReadPortW \(2228\)](#)

90.3.9 WritePortL

Synopsis: Write longint to PC port.

Declaration: `procedure WritePortL(Port: LongInt; Value: LongInt)`
`procedure WritePortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(2226\)](#) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(2226\)](#), [WritePort \(2228\)](#), [WritePortB \(2229\)](#), [WritePortW \(2229\)](#), [ReadPortB \(2227\)](#), [ReadPortL \(2228\)](#), [ReadPortW \(2228\)](#)

90.3.10 WritePortW

Synopsis: Write Word to PC port

Declaration: `procedure WritePortW(Port: LongInt; Value: Word)`
`procedure WritePortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (2226) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (2226), `WritePort` (2228), `WritePortL` (2229), `WritePortB` (2229), `ReadPortB` (2227), `ReadPortL` (2228), `ReadPortW` (2228)